



## MediaPlug-inlibrary

Uàb^&câç^Á•^•c^ { •  
X^!•â [ }ÁX^!•â [ }Á€F  
ÌDJBG€€IÁGKFGÁÚT

# Table of Contents

Module Index	iv
Data Structure Index	v
File Index	vi
Module Documentation	2
Media API Internal Common Helper Functions	2
Media API Internal Linux Helper Functions	3
Media API	5
Media API Internal Socket Layer	9
Media API Internal Windows Helper Functions	17
Data Structure Documentation	25
BufferNode	25
ooWaveFile	26
WaveBuffer	27
File Documentation	28
ooCommon.h	28
oortp.h	29
ooSock.h	31
ooWave.h	34
Index	37

# MediaPlug-inlibrary Module Index

## MediaPlug-inlibrary Modules

Here is a list of all modules:

Media API Internal Common Helper Functions	2
Media API Internal Linux Helper Functions	3
Media API	5
Media API Internal Socket Layer	9
Media API Internal Windows Helper Functions	17

# MediaPlug-inlibrary Data Structure Index

## MediaPlug-inlibrary Data Structures

Here are the data structures with brief descriptions:

<b>BufferNode</b> (This holds the list of free buffers which can be used for sending data to waveout device )	
25	
<b>ooWaveFile</b> (Helper structure for reading wavefile )	26
<b>WaveBuffer</b> (This holds a list of buffers holding recorded data from MIC )	27

# MediaPlug-inlibrary File Index

## MediaPlug-inlibrary File List

Here is a list of all documented files with brief descriptions:

<b>g711.h</b>	<b>Error! Bookmark not defined.</b>
<b>ooCommon.h</b> (This file contains common helper functions )	28
<b>oomedialx.h</b>	<b>Error! Bookmark not defined.</b>
<b>oortp.h</b> (This file contains functions to create and use media channels )	29
<b>ooSock.h</b> (Common runtime constants, data structure definitions, and run-time functions to support the sockets' operations )	31
<b>ooWave.h</b> (This file contains low level wave functions )	34



# MediaPlug-inlibrary Module Documentation

## Media API Internal Common Helper Functions

Media API Internal Common Helper Functions

### Defines

- `#define OORTPPACKETDATASIZE 240 /* Send Receive Packet Data Size*/`
- `#define MAXLOGMSGLEN 1024`
- `#define OOLOG2(a, b) ooLog(a,b)`
- `#define OOLOG3(a, b, c) ooLog(a,b,c)`
- `#define OOLOG4(a, b, c, d) ooLog(a,b,c,d)`
- `#define OOLOG5(a, b, c, d, e) ooLog(a,b,c,d,e)`
- `#define OOLOG9(a, b, c, d, e, f, g, h, i) ooLog(a,b,c,d,e,f,g,h,i)`

### Functions

- `EXTERN void ooLog (int level, const char *fmtspec,...)`  
*This function logs a trace message into a log file.*
- `EXTERN void ooSleep (int milliseconds)`  
*Platform independent sleep function.*

### Variables

- `FILE * fpLog`
- 

### Function Documentation

**EXTERN void ooLog (int `level`, const char \* `fmtspec`, ...)**

This function logs a trace message into a log file.

#### Parameters:

*level* Log level(Currently not used)  
*fmtspec* Format specification for the log message.  
... Variable number of arguments representing the message.

**EXTERN void ooSleep (int `milliseconds`)**

Platform independent sleep function.

#### Parameters:

*milliseconds* Sleep time in milliseconds.

# Media API Internal Linux Helper Functions

Media API Internal Linux Helper Functions

## Functions

- **EXTERN int ooOpenWaveFileForRead** (char \*filename)  
*Opens a RAW audio data file for read.*
- **EXTERN int ooReadWaveFileData** (char \*databuf, int size)  
*Reads data from the opened raw audio file.*
- **EXTERN int ooCloseWaveFile** ()  
*Close the open raw audio data file.*
- **EXTERN int ooOpenAudioDevice** ()  
*Opens the audio device for read/write operation.*
- **EXTERN int ooPlayAudioBuffer** (unsigned char \*buff, long size)  
*Plays a buffer full of audio data onto the audio device.*
- **EXTERN int ooGetMicAudioBuffer** (unsigned char \*buff, long size)  
*Reads audio data from the microphone device.*

## Variables

- **int ghSoundDevice**  
*Global handle to open sound device.*
- **int ghSndFile**  
*Global handle to open raw audio data file.*

---

## Function Documentation

### **EXTERN int ooCloseWaveFile** ()

Close the open raw audio data file.



**Returns:**

Completion status - 0 on success, -1 on failure

**EXTERN int ooGetMicAudioBuffer (unsigned char \* *ViZ*, long *g/n*)**

Reads audio data from the microphone device.

**Parameters:**

*buff* Buffer in which data has to be captured.

*size* Size of the capture buffer

**Returns:**

Completion status - 0 on success, -1 on failure

**EXTERN int ooOpenAudioDevice ()**

Opens the audio device for read/write operation.

**Returns:**

Completion status - 0 on success, -1 on failure

**EXTERN int ooOpenWaveFileForRead (char \* *Z`YbUa* )**

Opens a RAW audio data file for read.

**Parameters:**

*filename* Name of the file to be opened.

**Returns:**

Completion status - 0 on success, -1 on failure

**EXTERN int ooPlayAudioBuffer (unsigned char \* *ViZ*, long *g/n*)**

Plays a buffer full of audio data onto the audio device.

**Parameters:**

*buff* Buffer containing the audio data to be played.

*size* Size of the audio data in the buffer

**Returns:**

Completion status - 0 on success, -1 on failure

**EXTERN int ooReadWaveFileData (char \* *XUUViZ*, int *gInY*)**

Reads data from the opened raw audio file.

The number of bytes to be read is specified by the size parameter.

**Parameters:**

*databuf* Pointer to a buffer in which data is returned.

*size* Number of bytes to be read.

**Returns:**

Number of bytes read on success, -1 on failure.

## Media API

Media API

**Data Structures**

- struct **OORTPChannel**

**Defines**

- #define **OO\_CHAN\_CLOSE** 0
- #define **OO\_CHAN\_OPEN** 1

**Functions**

- EXTERN int **ooInitializePlugin** ()  
*This function initializes the plugin library.*
- EXTERN int **ooCreateTransmitRTPChannel** (int \*channelId, char \*destip, int port)  
*This function is invoked to create Transmit RTP channel.*
- EXTERN int **ooCloseTransmitRTPChannel** (int channelId)  
*This function is invoked to close the Transmit RTP channel.*
- EXTERN int **ooCreateReceiveRTPChannel** (int \*channelId, char \*localip, int localport)  
*This function is invoked to create Receive RTP channel.*
- EXTERN int **ooCloseReceiveRTPChannel** (int channelId)

*This function is invoked to close the Receive RTP channel.*

- **EXTERN int ooStartTransmitWaveFile** (int channelId, char \*filename)  
*This function is used to transmit a wave file on already created transmit RTP channel.*
- **EXTERN int ooStopTransmitWaveFile** (int channelId)  
*This function is used to stop transmitting the wave file.*
- **EXTERN int ooStartTransmitMic** (int channelId)  
*This function is used to start capturing and transmitting the data from microphone.*
- **EXTERN int ooStopTransmitMic** (int channelId)  
*This function is used to stop transmitting the data from microphone.*
- **EXTERN int ooStartReceiveAudioAndPlayback** (int channelId)  
*This function is used to start receiving rtp stream and playing the received audio onto the speaker device.*
- **EXTERN int ooStopReceiveAudioAndPlayback** (int channelId)  
*This function is used to stop receiving rtp stream.*
- **EXTERN int ooStartReceiveAudioAndRecord** (int channelId)
- **EXTERN int ooStopReceiveAudioAndRecord** (int channelId)

## Variables

- OORTPChannel **gXmitChannel**
  - OORTPChannel **gRecvChannel**
  - pthread\_t **gXmitThrdHdl**
  - pthread\_t **gRecvThrdHdl**
- 

## Function Documentation

### **EXTERN int ooCloseReceiveRTPChannel (int channelId)**

This function is invoked to close the Receive RTP channel.

#### **Parameters:**

*channelId* An integer value indicating the RTP channel to be closed. Not used currently as only two channels are supported, 1 xmit channel and 1 recv channel.

#### **Returns:**

Completion status - 0 on success, -1 on failure

**EXTERN int ooCloseTransmitRTPChannel (int *W\UbbY=X*)**

This function is invoked to close the Transmit RTP channel.

**Parameters:**

*channelId* An integer value indicating the RTP channel to be closed. Not used currently as only two channels are supported, 1 xmit channel and 1 recv channel.

**Returns:**

Completion status - 0 on success, -1 on failure

**EXTERN int ooCreateReceiveRTPChannel (int \* *W\UbbY=X*, char \* *`cWU`jd*, int *`cWU`dcfn*)**

This function is invoked to create Receive RTP channel.

**Parameters:**

*channelId* Pointer to int for returning the newly created channel id. Not used currently as only two channels are supported, 1 xmit channel and 1 recv channel.

*localip* IP address of the local endpoint.

*localport* RTP receive port number at the local endpoint.

**Returns:**

Completion status - 0 on success, -1 on failure

**EXTERN int ooCreateTransmitRTPChannel (int \* *W\UbbY=X*, char \* *XYghjd*, int *dcfn*)**

This function is invoked to create Transmit RTP channel.

**Parameters:**

*channelId* Pointer to int for returning the newly created channel id. Not used currently as only two channels are supported, 1 xmit channel and 1 recv channel.

*destip* IP address of the destination endpoint.

*port* RTP receive port number at the destination endpoint.

**Returns:**

Completion status - 0 on success, -1 on failure

**EXTERN int oolInitializePlugin ()**

This function initializes the plugin library.

**Returns:**

0, on success. -ve on failure.

**EXTERN int ooStartReceiveAudioAndPlayback (int W\UbbY=X)**

This function is used to start receiving rtp stream and playing the received audio onto the speaker device.

**Parameters:**

*channelId* Indicates the receive channel on which data reception needs to be started. Not used currently as only one transmit channel is supported.

**Returns:**

Completion status - 0 on success, -1 on failure.

**EXTERN int ooStartTransmitMic (int W\UbbY=X)**

This function is used to start capturing and transmitting the data from microphone.

**Parameters:**

*channelId* Indicates the transmit channel on data transmission should begin. Not used currently as only one transmit channel is supported.

**Returns:**

Completion status - 0 on success, -1 on failure.

**EXTERN int ooStartTransmitWaveFile (int W\UbbY=X, char \* Z`YbU a Y)**

This function is used to transmit a wave file on already created transmit RTP channel.

This basically, creates a thread which will start reading from the wave file and transmit data as rtp packets on the transmit channel.

**Parameters:**

*channelId* Indicates the transmit channel to be used. Not used currently as only one transmit channel is supported.

*filename* Name of the wave file to be transmitted.

**Returns:**

Completion status - 0 on success, -1 on failure.

### **EXTERN int ooStopReceiveAudioAndPlayback (int W\UbbY=X)**

This function is used to stop receiving rtp stream.

#### **Parameters:**

*channelId* Indicates the receive channel on which data reception needs to be halted. Not used currently as only one transmit channel is supported.

#### **Returns:**

Completion status - 0 on success, -1 on failure.

### **EXTERN int ooStopTransmitMic (int W\UbbY=X)**

This function is used to stop transmitting the data from microphone.

#### **Parameters:**

*channelId* Indicates the transmit channel on which data transmission needs to be halted. Not used currently as only one transmit channel is supported.

#### **Returns:**

Completion status - 0 on success, -1 on failure.

### **EXTERN int ooStopTransmitWaveFile (int W\UbbY=X)**

This function is used to stop transmitting the wave file.

#### **Parameters:**

*channelId* Indicates the transmit channel on which wave file transmission needs to be halted. Not used currently as only one transmit channel is supported.

#### **Returns:**

Completion status - 0 on success, -1 on failure.

## **Media API Internal Socket Layer**

Media API Internal Socket Layer

#### **Defines**

- **#define OOSOCKET\_INVALID ((OOSOCKET)-1)**
- **#define ASN\_OK 0**

- `#define ASN_E_NOTINIT -1`
- `#define ASN_E_INVSOCKET -2`
- `#define ASN_E_INVPARAM -3`
- `#define ASN_E_BUFOVFLW -4`
- `#define OOIPADDR_ANY ((OOIPADDR)0)`
- `#define OOIPADDR_LOCAL ((OOIPADDR)0x7f000001UL) /* 127.0.0.1 */`

## Typedefs

- `typedef int OOSOCKET`  
*Socket's handle.*
- `typedef unsigned long OOIPADDR`  
*The IP address represented as unsigned long value.*
- `typedef char ASN1OCTET`
- `typedef unsigned int ASN1UINT`

## Functions

- `EXTERN int ooSocketAccept (OOSOCKET socket, OOSOCKET *pNewSocket, OOIPADDR *destAddr, int *destPort)`  
*This function permits an incoming connection attempt on a socket.*
- `EXTERN int ooSocketAddrToStr (OOIPADDR ipAddr, char *pbuf, int bufsize)`  
*This function converts an IP address to its string representation.*
- `EXTERN int ooSocketBind (OOSOCKET socket, OOIPADDR addr, int port)`  
*This function associates a local address with a socket.*
- `EXTERN int ooSocketClose (OOSOCKET socket)`  
*This function closes an existing socket.*
- `EXTERN int ooSocketConnect (OOSOCKET socket, const char *host, int port)`  
*This function establishes a connection to a specified socket.*
- `EXTERN int ooSocketCreate (OOSOCKET *psocket)`  
*This function creates a socket.*
- `EXTERN int ooSocketCreateUDP (OOSOCKET *psocket)`  
*This function creates a UDP datagram socket.*
- `EXTERN int ooSocketsInit (void)`  
*This function initiates use of sockets by an application.*
- `EXTERN int ooSocketsCleanup (void)`

*This function terminates use of sockets by an application.*

- **EXTERN int ooSocketListen (OOSOCKET socket, int maxConnection)**  
*This function places a socket a state where it is listening for an incoming connection.*
- **EXTERN int ooSocketRecv (OOSOCKET socket, ASNIOCTET \*pbuf, ASN1UINT bufsize)**  
*This function receives data from a connected socket.*
- **EXTERN int ooSocketRecvFrom (OOSOCKET socket, ASNIOCTET \*pbuf, ASN1UINT bufsize, char \*remotehost, int \*remoteport)**  
*This function receives data from a connected/unconnected socket.*
- **EXTERN int ooSocketSend (OOSOCKET socket, const ASNIOCTET \*pdata, ASN1UINT size)**  
*This function sends data on a connected socket.*
- **EXTERN int ooSocketSendTo (OOSOCKET socket, const ASNIOCTET \*pdata, ASN1UINT size, const char \*remotehost, int remoteport)**  
*This function sends data on a connected or unconnected socket.*
- **EXTERN int ooSocketSelect (int nfds, fd\_set \*readfds, fd\_set \*writefds, fd\_set \*exceptfds, struct timeval \*timeout)**  
*This function is used for synchronous monitoring of multiple sockets.*
- **EXTERN int ooSocketStrToAddr (const char \*pIPAddrStr, OOIPADDR \*pIPAddr)**  
*This function converts the string with IP address to a double word representation.*
- **EXTERN int ooGetLocalIPAddress (char \*pIPAddrs)**  
*This function retrives the IP address of the local host.*
- **EXTERN long ooHTONL (long val)**  
*This function converts a long value from host to network byte order.*
- **EXTERN short ooHTONS (short val)**  
*This function converts a short value from host to network byte order.*

---

## Typedef Documentation

### typedef unsigned long OOIPADDR

The IP address represented as unsigned long value.

The most significant 8 bits in this unsigned long value represent the first number of the IP address. The least significant 8 bits represent the last number of the IP address.

Definition at line 80 of file ooSock.h.



---

## Function Documentation

### **EXTERN int ooGetLocalIPAddress (char \* *dD5XXfg*)**

This function retrieves the IP address of the local host.

#### **Parameters:**

*pIPAddr* Pointer to a char buffer in which local IP address will be returned.

#### **Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

### **EXTERN long ooHTONL (long *jU*)**

This function converts a long value from host to network byte order.

#### **Parameters:**

*val* Value to be converted.

#### **Returns:**

Value converted to network byte order.

### **EXTERN short ooHTONS (short *jU*)**

This function converts a short value from host to network byte order.

#### **Parameters:**

*val* Value to be converted.

#### **Returns:**

Value converted to network byte order.

### **EXTERN int ooSocketAccept (OOSOCKET *gcW\_Yh*, OOSOCKET \* *dBYkGcW\_Yh*, OOIPADDR \* *XYgh5XXf*, int \* *XYghDcfh*)**

This function permits an incoming connection attempt on a socket.

It extracts the first connection on the queue of pending connections on socket. It then creates a new

socket and returns a handle to the new socket. The newly created socket is the socket that will handle the actual connection and has the same properties as original socket. See description of 'accept' socket function for further details.

**Parameters:**

*socket* The socket's handle created by call to `::rtSocketCreate` function.  
*pNewSocket* The pointer to variable to receive the new socket's handle.  
*destAddr* Optional pointer to a buffer that receives the IP address of the connecting entity. It may be NULL.  
*destPort* Optional pointer to a buffer that receives the port of the connecting entity. It may be NULL.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketAddrToStr (OOIPADDR *jd5XXf*, char \* *dViZ*, int *ViZgjnY*)**

This function converts an IP address to its string representation.

**Parameters:**

*ipAddr* The IP address to be converted.  
*pbuf* Pointer to the buffer to receive a string with the IP address.  
*bufsize* Size of the buffer.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketBind (OOSOCKET *gcW\_ Yh*, OOIPADDR *UXXf*, int *dcfh*)**

This function associates a local address with a socket.

It is used on an unconnected socket before subsequent calls to the `::rtSocketConnect` or `::rtSocketListen` functions. See description of 'bind' socket function for further details.

**Parameters:**

*socket* The socket's handle created by call to `::rtSocketCreate` function.  
*addr* The local IP address to assign to the socket.  
*port* The local port number to assign to the socket.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketClose (OOSOCKET *gcW\_ Yh*)**

This function closes an existing socket.

**Parameters:**

*socket* The socket's handle created by call to `::rtSocketCreate` or `::rtSocketAccept` function.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketConnect (OOSOCKET *gcW\_Yh*, const char \* *lcg*, int *dcfh*)**

This function establishes a connection to a specified socket.

It is used to create a connection to the specified destination. When the socket call completes successfully, the socket is ready to send and receive data. See description of 'connect' socket function for further details.

**Parameters:**

*socket* The socket's handle created by call to `::rtSocketCreate` function.

*host* The null-terminated string with the IP address in the following format: "NNN.NNN.NNN.NNN", where NNN is a number in the range (0..255).

*port* The destination port to connect.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketCreate (OOSOCKET \* *dgcW\_Yh*)**

This function creates a socket.

The only streaming TCP/IP sockets are supported at the moment.

**Parameters:**

*psocket* The pointer to the socket's handle variable to receive the handle of new socket.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketCreateUDP (OOSOCKET \* *dgcW\_Yh*)**

This function creates a UDP datagram socket.

**Parameters:**

*psocket* The pointer to the socket's handle variable to receive the handle of new socket.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketListen (OOSOCKET gcW\_Yh, int aUI7cbbYWhjcb)**

This function places a socket a state where it is listening for an incoming connection.

To accept connections, a socket is first created with the ::rtSocketCreate function and bound to a local address with the ::rtSocketBind function, a maxConnection for incoming connections is specified with ::rtSocketListen, and then the connections are accepted with the ::rtSocketAccept function. See description of 'listen' socket function for further details.

**Parameters:**

*socket* The socket's handle created by call to ::rtSocketCreate function.

*maxConnection* Maximum length of the queue of pending connections.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketRecv (OOSOCKET gcW\_Yh, ASN1OCTET \* dViZ, ASN1UINT ViZgjnY)**

This function receives data from a connected socket.

It is used to read incoming data on sockets. The socket must be connected before calling this function. See description of 'recv' socket function for further details.

**Parameters:**

*socket* The socket's handle created by call to ::rtSocketCreate or ::rtSocketAccept function.

*buf* Pointer to the buffer for the incoming data.

*bufsize* Length of the buffer.

**Returns:**

If no error occurs, returns the number of bytes received. Otherwise, the negative value is error code.

**EXTERN int ooSocketRecvFrom (OOSOCKET gcW\_Yh, ASN1OCTET \* dViZ, ASN1UINT ViZgjnY, char \* fYa chY\cgh, int \* fYa chYdcfh)**

This function receives data from a connected/unconnected socket.

It is used to read incoming data on sockets. It populates the remotehost and remoteport parameters with information of remote host. See description of 'recvfrom' socket function for further details.

**Parameters:**

*socket* The socket's handle created by call to ooSocketCreate  
*pbuf* Pointer to the buffer for the incoming data.  
*bufsize* Length of the buffer.  
*remotehost* Pointer to a buffer in which remote ip address will be returned.  
*remoteport* Pointer to an int in which remote port number will be returned.

**Returns:**

If no error occurs, returns the number of bytes received. Otherwise, the negative value is error code.

**EXTERN int ooSocketsCleanup (void)**

This function terminates use of sockets by an application.

This function must be called after done with sockets.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketSelect (int *bZXg*, fd\_set \* *fYUXZXg*, fd\_set \* *kfjhYZXg*, fd\_set \* *YIWYdhZXg*, struct timeval \* *hjaYc ih*)**

This function is used for synchronous monitoring of multiple sockets.

For more information refer to documnetation of "select" system call.

**Parameters:**

*nfds* The highest numbered descriptor to be monitored plus one.  
*readfds* The descriptors listed in readfds will be watched for whether read would block on them.  
*writefds* The descriptors listed in writefds will be watched for whether write would block on them.  
*exceptfds* The descriptors listed in exceptfds will be watched for exceptions.  
*timeout* Upper bound on amout of time elapsed before select returns.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketSend (OOSOCKET *gcWl\_Yh*, const ASN1OCTET \* *dXUhU*, ASN1UINT *glnY*)**

This function sends data on a connected socket.

It is used to write outgoing data on a connected socket. See description of 'send' socket function for further details.

**Parameters:**

*socket* The socket's handle created by call to :rtSocketCreate or :rtSocketAccept function.  
*pdata* Buffer containing the data to be transmitted.

*size* Length of the data in *pdata*.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketSendTo (OOSOCKET *gcWl\_Yh*, const ASN1OCTET \* *dXUhU*, ASN1UINT *gJnY*, const char \* *fYa chY\cgh*, int *fYa chYdcfh*)**

This function sends data on a connected or unconnected socket.

See description of 'sendto' socket function for further details.

**Parameters:**

*socket* The socket's handle created by call to ::rtSocketCreate or ::rtSocketAccept function.

*pdata* Buffer containing the data to be transmitted.

*size* Length of the data in *pdata*.

*remotehost* Remote host ip address to which data has to be sent.

*remoteport* Remote port ip address to which data has to be sent.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketsInit (void)**

This function initiates use of sockets by an application.

This function must be called first before use sockets.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

**EXTERN int ooSocketStrToAddr (const char \* *dD5XXfGhf*, OOIPADDR \* *dD5XXf*)**

This function converts the string with IP address to a double word representation.

The converted address may be used with the ::rtSocketBind function.

**Parameters:**

*pIPAddrStr* The null-terminated string with the IP address in the following format: "NNN.NNN.NNN.NNN", where NNN is a number in the range (0..255).

*pIPAddr* Pointer to the converted IP address.

**Returns:**

Completion status of operation: 0 (ASN\_OK) = success, negative return value is error.

## Media API Internal Windows Helper Functions

### Media API Internal Windows Helper Functions

#### Data Structures

- struct **ooWaveFile**  
*Helper structure for reading wavefile.*
- struct **WaveBuffer**  
*This holds a list of buffers holding recorded data from MIC.*
- struct **BufferNode**  
*This holds the list of free buffers which can be used for sending data to waveout device.*

#### Functions

- EXTERN int **ooOpenWaveFileForRead** (char \*filename)  
*Opens a WaveFile for read and traverses upto the data chunk, so that next mmioRead will return wavedata.*
- EXTERN int **ooCloseWaveFile** ()  
*Closes the open WaveFile.*
- EXTERN int **ooReadWaveFileData** (char \*buffer, int size)  
*Reads data from already opened wave file.*
- EXTERN int **ooOpenSpeaker** (HWAVEOUT \*phWaveOut, WAVEFORMATEX waveFormat)  
*Opens a waveOut device, i.e., speaker for playback.*
- EXTERN int **ooPlayWaveBuffer** (HWAVEOUT hWaveOut, unsigned char \*buff, long size)  
*Plays the number of bytes specified by the size parameter from the buff onto the speaker device.*
- EXTERN int **ooCloseSpeaker** (HWAVEOUT hWaveOut)  
*Release all the buffers queued into the waveOut device(speaker) for playback and close speaker.*
- EXTERN int **ooOpenMic** ()  
*Opens the WaveIn device, MIC, for recording and queues the buffers into the device which can be used for storing recorded data.*
- EXTERN int **ooStartMicDataCapture** (HWAVEIN hWaveIn)

*Start recording audio into the buffers.*

- **EXTERN int ooStopMicDataCapture (HWA VEIN hWaveIn)**  
*Stop recording audio.*
- **EXTERN int ooCloseMic (HWA VEIN hWaveIn)**  
*This releases all the buffers queued inside wave-in device, mic, and then closes the mic.*
- **EXTERN void CALLBACK ooMICCallback (HWA VEIN hwi, UINT uMsg, DWORD dwInstance, DWORD dwParam1, DWORD dwParam2)**  
*This is a callback function registered with the mic.*
- **EXTERN void CALLBACK ooSpeakerCallback (HWA VEOUT hwo, UINT uMsg, DWORD dwInstance, DWORD dwParam1, DWORD dwParam2)**  
*This is a callback function registered with the speaker.*
- **EXTERN int ooAddToWaveBufferList (WAVEHDR \*waveHdr)**  
*Helper function to maintain the list of buffers returned by mic, after recording.*
- **EXTERN int ooRemoveHeadOfWaveBufferList ()**  
*Helper function which removes the WAVEHDR at the front of the list.*
- **EXTERN int ooAddToFreeBufferList (char \*buffer)**  
*Helper function to put a buffer back into the free buffer list.*
- **EXTERN char \* ooGetFreeBuffer ()**  
*Get a free buffer from free buffer list.*

## **Variables**

- **ooWaveFile gWaveFile**  
*Global handle to open wave file.*
- **WaveBuffer \* gpWaveHead**  
*Global pointers to list of wave buffers.*
- **WaveBuffer \* gpWaveTail**  
*Global pointers to list of wave buffers.*
- **int gRecording**
- **int gQueuedBufCount**  
*Count of number of buffers queued inside the wave-in device.*
- **BufferNode \* gpFreeBufHead**



*Global pointers to the list holding free buffers.*

- **BufferNode \* gpFreeBufTail**

*Global pointers to the list holding free buffers.*

- **int gPlayQueueCount**
- **HWAVEIN ghWaveIn**

*Global handle to open wave-in device.*

- **HWAVEOUT ghWaveOut**

*Global handle to open wave-out device.*

- **CRITICAL\_SECTION gPlayMutex**

*As callback functions run in their own threads, we need mutex protection for data which is used by multiple threads.*

- **CRITICAL\_SECTION gReadMutex**

*As callback functions run in their own threads, we need mutex protection for data which is used by multiple threads.*

---

## Function Documentation

### **EXTERN int ooAddToFreeBufferList (char \* ViZYf)**

Helper function to put a buffer back into the free buffer list.

Once the buffer playback is done, it can be added to the free list

#### **Parameters:**

*buffer* Pointer to the buffer to be added to the free list.

#### **Returns:**

Completion status - 0 on success, -1 on failure

### **EXTERN int ooAddToWaveBufferList (WAVEHDR \* kUjY<Xf)**

Helper function to maintain the list of buffers returned by mic, after recording.

These buffers are kept in this list till there processing is done and then again queued back into the mic for further recording.

#### **Parameters:**

*waveHdr* Pointer to wave header structure which in turn contains the data buffer.

#### **Returns:**

Completion status - 0 on success, -1 on failure.

**EXTERN int ooCloseMic (HWAVEIN \KujYb)**

This releases all the buffers queued inside wave-in device, mic, and then closes the mic.

**Parameters:**

*hWaveIn* Handle to the wave-in device.

**Returns:**

Completion status - 0 on success, -1 on failure

**EXTERN int ooCloseSpeaker (HWAVEOUT \KujYCih)**

Release all the buffers queued into the waveOut device(speaker) for playback and close speaker.

**Parameters:**

*hWaveOut* Handle to the wave out device to be closed.

**Returns:**

Completion status - 0 on success, -1 on failure.

**EXTERN int ooCloseWaveFile ()**

Closes the open WaveFile.

**Returns:**

Completion status - 0 on success, -1 on failure.

**EXTERN char\* ooGetFreeBuffer ()**

Get a free buffer from free buffer list.

A free buffer is retrieved using this function for storing data which will then passed onto ooPlayWaveBuffer function for playback.

**Returns:**

Pointer to a character buffer

**EXTERN void CALLBACK ooMICCallback (HWAVEIN *hwi*, UINT *uMsg*, DWORD *dwInstance*,  
DWORD *dwParam1*, DWORD *dwParam2*)**

This is a callback function registered with the mic.

It will be called by mic device when a buffer full of data is recorded.

**Parameters:**

*hwi* Handle to the wave-in device.

*uMsg* Event message sent by the device.

*dwInstance* User data.

*dwParam1* Message parameter.

*dwParam2* Message parameter.

**Returns:**

None

**EXTERN int ooOpenMic ()**

Opens the WaveIn device, MIC, for recording and queues the buffers into the device which can be used for storing recorded data.

**Returns:**

Completion status - 0 on success, -1 on failure.

**EXTERN int ooOpenSpeaker (HWAVEOUT \* *phWaveOut*, WAVEFORMATEX \* *waveFormat*)**

Opens a waveOut device, i.e., speaker for playback.

*waveFormat* specifies the format to be used for playback.

**Parameters:**

*phWaveOut* Pointer to an empty HWAVEOUT handle which will contain the handle to the opened device on return.

*waveFormat* Wave format to be used for playback.

**Returns:**

Completion status - 0 on success, -1 on failure.

**EXTERN int ooOpenWaveFileForRead (char \* *filename*)**

Opens a WaveFile for read and traverses upto the data chunk, so that next mmioRead will return wavedata.

**Parameters:**

*filename* Name of the wave file to be opened.

**Returns:**

Completion status - 0 on success, -1 on failure.

**EXTERN int ooPlayWaveBuffer (HWAVEOUT *hWaveOut*, unsigned char \* *buff*, long *size*)**

Plays the number of bytes specified by the size parameter from the buff onto the speaker device.

**Parameters:**

*hWaveOut* Handle to the speaker device.

*buff* Pointer to the buffer containing the data to be played.

*size* Size of the buffer to be played out.

**Returns:**

Completion status - 0 on success, -1 on failure.

**EXTERN int ooReadWaveFileData (char \* *buffer*, int *size*)**

Reads data from already opened wave file.

Number of bytes to be read is specified by the "size" parameter. The data is returned in "buffer" parameter and the number of bytes read is returned as a return value.

**Parameters:**

*buffer* Buffer which will contain the data read.

*size* Size of the buffer passed.

**Returns:**

Number of bytes read on success, -1 on failure

**EXTERN int ooRemoveHeadOfWaveBufferList ()**

Helper function which removes the WAVEHDR at the front of the list.

Note this does not free up the mem used by WAVEHDR as it will be queued into the mic for further recording.

**Returns:**

Completion status - 0 on success, -1 on failure.

**EXTERN void CALLBACK ooSpeakerCallback (HWAVEOUT *hWaveOut*, UINT *nBytes*, DWORD *dwUser*, DWORD *dwFlags*)**

This is a callback function registered with the speaker.

It is called by the speaker, when a buffer full of data is played back.

**Parameters:**

*hwo* Handle to the wave out device.

*uMsg* Waveform audio output message.

*dwInstance* User instance data passed during waveOutOpen.

*dwParam1* Message parameter.

*dwParam2* Message parameter

**Returns:**

None

**EXTERN int ooStartMicDataCapture (HWAVEIN \KUjY-b)**

Start recording audio into the buffers.

**Parameters:**

*hWaveIn* Handle to wave-in device.

**Returns:**

Completion status - 0 on success, -1 on failure.

**EXTERN int ooStopMicDataCapture (HWAVEIN \KUjY-b)**

Stop recording audio.

Note that this marks current buffer as done and frees it by calling callback function. However, other queued buffers will stay there in wave-in device.

**Parameters:**

*hWaveIn* Handle to the wave-in device.

**Returns:**

Completion status - 0 on success, -1 on failure

# MediaPlug-inlibrary Data Structure Documentation

## BufferNode Struct Reference

BufferNodeThis holds the list of free buffers which can be used for sending data to waveout device.

```
#include <ooWave.h>
```

### Data Fields

- char \* **buf**
  - **BufferNode** \* **next**
- 

### Detailed Description

This holds the list of free buffers which can be used for sending data to waveout device.

Definition at line 83 of file ooWave.h.

---

The documentation for this struct was generated from the following file:

- **ooWave.h**

## ooWaveFile Struct Reference

ooWaveFileHelper structure for reading wavefile.

```
#include <ooWave.h>
```

### Data Fields

- char **filename** [1024]
  - HMMIO **hWaveFile**  
*Wave file name.*
  - WAVEFORMATEX **waveFormat**  
*Wave file handle.*
  - int **dataSize**  
*Wave file format.*
- 

### Detailed Description

Helper structure for reading wavefile.

Definition at line 54 of file ooWave.h.

---

The documentation for this struct was generated from the following file:

- **ooWave.h**

## WaveBuffer Struct Reference

WaveBufferThis holds a list of buffers holding recorded data from MIC.

```
#include <ooWave.h>
```

### Data Fields

- **WAVEHDR \* pWaveHdr**
  - **WaveBuffer \* next**
- 

### Detailed Description

This holds a list of buffers holding recorded data from MIC.

This data can then be sent on rtp channel or played back on speakers.

Definition at line 70 of file ooWave.h.

---

The documentation for this struct was generated from the following file:

- **ooWave.h**



# MediaPlug-inlibrary File Documentation

## ooCommon.h File Reference

ooCommon.h This file contains common helper functions.

```
#include <stdarg.h>
#include <stdlib.h>
#include <stdio.h>
#include "ooSock.h"
```

### Defines

- #define **OORTPPACKETDATASIZE** 240 /\* Send Receive Packet Data Size\*/
- #define **MAXLOGMSGLEN** 1024
- #define **OOLOG2**(a, b) ooLog(a,b)
- #define **OOLOG3**(a, b, c) ooLog(a,b,c)
- #define **OOLOG4**(a, b, c, d) ooLog(a,b,c,d)
- #define **OOLOG5**(a, b, c, d, e) ooLog(a,b,c,d,e)
- #define **OOLOG9**(a, b, c, d, e, f, g, h, i) ooLog(a,b,c,d,e,f,g,h,i)

### Functions

- EXTERN void **ooLog** (int level, const char \*fmtspec,...)  
*This function logs a trace message into a log file.*
- EXTERN void **ooSleep** (int milliseconds)  
*Platform independent sleep function.*

### Variables

- FILE \* **fpLog**
- 

### Detailed Description

This file contains common helper functions.

Definition in file **ooCommon.h**.

## oortp.h File Reference

oortp.h This file contains functions to create and use media channels.

```
#include <stdio.h>
#include "ooSock.h"
#include "ooCommon.h"
```

### Data Structures

- struct **OORTPChannel**

### Defines

- #define **OO\_CHAN\_CLOSE** 0
- #define **OO\_CHAN\_OPEN** 1

### Functions

- EXTERN int **ooInitializePlugin** ()  
*This function initializes the plugin library.*
- EXTERN int **ooCreateTransmitRTPChannel** (int \*channelId, char \*destip, int port)  
*This function is invoked to create Transmit RTP channel.*
- EXTERN int **ooCloseTransmitRTPChannel** (int channelId)  
*This function is invoked to close the Transmit RTP channel.*
- EXTERN int **ooCreateReceiveRTPChannel** (int \*channelId, char \*localip, int localport)  
*This function is invoked to create Receive RTP channel.*
- EXTERN int **ooCloseReceiveRTPChannel** (int channelId)  
*This function is invoked to close the Receive RTP channel.*
- EXTERN int **ooStartTransmitWaveFile** (int channelId, char \*filename)  
*This function is used to transmit a wave file on already created transmit RTP channel.*
- EXTERN int **ooStopTransmitWaveFile** (int channelId)  
*This function is used to stop transmitting the wave file.*
- EXTERN int **ooStartTransmitMic** (int channelId)  
*This function is used to start capturing and transmitting the data from microphone.*
- EXTERN int **ooStopTransmitMic** (int channelId)  
*This function is used to stop transmitting the data from microphone.*

- **EXTERN int ooStartReceiveAudioAndPlayback** (int channelId)  
*This function is used to start receiving rtp stream and playing the received audio onto the speaker device.*
- **EXTERN int ooStopReceiveAudioAndPlayback** (int channelId)  
*This function is used to stop receiving rtp stream.*
- **EXTERN int ooStartReceiveAudioAndRecord** (int channelId)
- **EXTERN int ooStopReceiveAudioAndRecord** (int channelId)

### Variables

- OORTPChannel **gXmitChannel**
  - OORTPChannel **gRecvChannel**
  - pthread\_t **gXmitThrdHdl**
  - pthread\_t **gRecvThrdHdl**
- 

### Detailed Description

This file contains functions to create and use media channels.

Definition in file **oortp.h**.

## ooSock.h File Reference

ooSock.h Common runtime constants, data structure definitions, and run-time functions to support the sockets' operations.

```
#include <sys/types.h>
#include "sys/time.h"
#include <sys/socket.h>
#include <netinet/in.h>
#include <netdb.h>
#include <unistd.h>
#include <arpa/inet.h>
```

### Defines

- `#define EXTERN`
- `#define OOSOCKET_INVALID ((OOSOCKET)-1)`
- `#define ASN_OK 0`
- `#define ASN_E_NOTINIT -1`
- `#define ASN_E_INVSOCKET -2`
- `#define ASN_E_INVPARAM -3`
- `#define ASN_E_BUFOVFLW -4`
- `#define OOIPADDR_ANY ((OOIPADDR)0)`
- `#define OOIPADDR_LOCAL ((OOIPADDR)0x7f000001UL) /* 127.0.0.1 */`

### Typedefs

- `typedef int OOSOCKET`  
*Socket's handle.*
- `typedef unsigned long OOIPADDR`  
*The IP address represented as unsigned long value.*
- `typedef char ASN1OCTET`
- `typedef unsigned int ASN1UINT`

### Functions

- `EXTERN int ooSocketAccept (OOSOCKET socket, OOSOCKET *pNewSocket, OOIPADDR *destAddr, int *destPort)`  
*This function permits an incoming connection attempt on a socket.*
- `EXTERN int ooSocketAddrToStr (OOIPADDR ipAddr, char *pbuf, int bufsize)`  
*This function converts an IP address to its string representation.*
- `EXTERN int ooSocketBind (OOSOCKET socket, OOIPADDR addr, int port)`  
*This function associates a local address with a socket.*

- **EXTERN int ooSocketClose (OOSOCKET socket)**  
*This function closes an existing socket.*
- **EXTERN int ooSocketConnect (OOSOCKET socket, const char \*host, int port)**  
*This function establishes a connection to a specified socket.*
- **EXTERN int ooSocketCreate (OOSOCKET \*psocket)**  
*This function creates a socket.*
- **EXTERN int ooSocketCreateUDP (OOSOCKET \*psocket)**  
*This function creates a UDP datagram socket.*
- **EXTERN int ooSocketsInit (void)**  
*This function initiates use of sockets by an application.*
- **EXTERN int ooSocketsCleanup (void)**  
*This function terminates use of sockets by an application.*
- **EXTERN int ooSocketListen (OOSOCKET socket, int maxConnection)**  
*This function places a socket a state where it is listening for an incoming connection.*
- **EXTERN int ooSocketRecv (OOSOCKET socket, ASNIOCTET \*pbuf, ASN1UINT bufsz)**  
*This function receives data from a connected socket.*
- **EXTERN int ooSocketRecvFrom (OOSOCKET socket, ASNIOCTET \*pbuf, ASN1UINT bufsz, char \*remotehost, int \*remoteport)**  
*This function receives data from a connected/unconnected socket.*
- **EXTERN int ooSocketSend (OOSOCKET socket, const ASNIOCTET \*pdata, ASN1UINT size)**  
*This function sends data on a connected socket.*
- **EXTERN int ooSocketSendTo (OOSOCKET socket, const ASNIOCTET \*pdata, ASN1UINT size, const char \*remotehost, int remoteport)**  
*This function sends data on a connected or unconnected socket.*
- **EXTERN int ooSocketSelect (int nfds, fd\_set \*readfds, fd\_set \*writefds, fd\_set \*exceptfds, struct timeval \*timeout)**  
*This function is used for synchronous monitoring of multiple sockets.*
- **EXTERN int ooSocketStrToAddr (const char \*pIPAddrStr, OOIPADDR \*pIPAddr)**  
*This function converts the string with IP address to a double word representation.*
- **EXTERN int ooGetLocalIPAddress (char \*pIPAddrs)**

*This function retrieves the IP address of the local host.*

- **EXTERN long ooHTONL (long val)**  
*This function converts a long value from host to network byte order.*
- **EXTERN short ooHTONS (short val)**  
*This function converts a short value from host to network byte order.*

---

### **Detailed Description**

Common runtime constants, data structure definitions, and run-time functions to support the sockets' operations.

Definition in file **ooSock.h**.

## ooWave.h File Reference

ooWave.h This file contains low level wave functions.

```
#include <stdio.h>
#include "ooCommon.h"
#include <Windows.h>
#include <Mmsystem.h>
#include <Basetsd.h>
```

### Data Structures

- struct **ooWaveFile**  
*Helper structure for reading wavefile.*
- struct **WaveBuffer**  
*This holds a list of buffers holding recorded data from MIC.*
- struct **BufferNode**  
*This holds the list of free buffers which can be used for sending data to waveout device.*

### Functions

- EXTERN int **ooOpenWaveFileForRead** (char \*filename)  
*Opens a WaveFile for read and traverses upto the data chunk, so that next mmioRead will return wavedata.*
- EXTERN int **ooCloseWaveFile** ()  
*Closes the open WaveFile.*
- EXTERN int **ooReadWaveFileData** (char \*buffer, int size)  
*Reads data from already opened wave file.*
- EXTERN int **ooOpenSpeaker** (HWAVEOUT \*phWaveOut, WAVEFORMATEX waveFormat)  
*Opens a waveOut device, i.e., speaker for playback.*
- EXTERN int **ooPlayWaveBuffer** (HWAVEOUT hWaveOut, unsigned char \*buff, long size)  
*Plays the number of bytes specified by the size parameter from the buff onto the speaker device.*
- EXTERN int **ooCloseSpeaker** (HWAVEOUT hWaveOut)  
*Release all the buffers queued into the waveOut device(speaker) for playback and close speaker.*
- EXTERN int **ooOpenMic** ()  
*Opens the WaveIn device, MIC, for recording and queues the buffers into the device which can be*

*used for storing recorded data.*

- **EXTERN int ooStartMicDataCapture (HWA VEIN hWaveIn)**  
*Start recording audio into the buffers.*
- **EXTERN int ooStopMicDataCapture (HWA VEIN hWaveIn)**  
*Stop recording audio.*
- **EXTERN int ooCloseMic (HWA VEIN hWaveIn)**  
*This releases all the buffers queued inside wave-in device, mic, and then closes the mic.*
- **EXTERN void CALLBACK ooMICCallback (HWA VEIN hwi, UINT uMsg, DWORD dwInstance, DWORD dwParam1, DWORD dwParam2)**  
*This is a callback function registered with the mic.*
- **EXTERN void CALLBACK ooSpeakerCallback (HWA VEOUT hwo, UINT uMsg, DWORD dwInstance, DWORD dwParam1, DWORD dwParam2)**  
*This is a callback function registered with the speaker.*
- **EXTERN int ooAddToWaveBufferList (WAVEHDR \*waveHdr)**  
*Helper function to maintain the list of buffers returned by mic, after recording.*
- **EXTERN int ooRemoveHeadOfWaveBufferList ()**  
*Helper function which removes the WAVEHDR at the front of the list.*
- **EXTERN int ooAddToFreeBufferList (char \*buffer)**  
*Helper function to put a buffer back into the free buffer list.*
- **EXTERN char \* ooGetFreeBuffer ()**  
*Get a free buffer from free buffer list.*

## **Variables**

- **ooWaveFile gWaveFile**  
*Global handle to open wave file.*
- **WaveBuffer \* gpWaveHead**  
*Global pointers to list of wave buffers.*
- **WaveBuffer \* gpWaveTail**  
*Global pointers to list of wave buffers.*
- **int gRecording**
- **int gQueuedBufCount**



*Count of number of buffers queued inside the wave-in device.*

- **BufferNode \* gpFreeBufHead**  
*Global pointers to the list holding free buffers.*
  - **BufferNode \* gpFreeBufTail**  
*Global pointers to the list holding free buffers.*
  - **int gPlayQueueCount**
  - **HWAVEIN ghWaveIn**  
*Global handle to open wave-in device.*
  - **HWAVEOUT ghWaveOut**  
*Global handle to open wave-out device.*
  - **CRITICAL\_SECTION gPlayMutex**  
*As callback functions run in their own threads, we need mutex protection for data which is used by multiple threads.*
  - **CRITICAL\_SECTION gReadMutex**  
*As callback functions run in their own threads, we need mutex protection for data which is used by multiple threads.*
- 

## **Detailed Description**

This file contains low level wave functions.

Definition in file **ooWave.h**.

# Index

- BufferNode, 25
- linuxhelpers
  - ooCloseWaveFile, 3
  - ooGetMicAudioBuffer, 4
  - ooOpenAudioDevice, 4
  - ooOpenWaveFileForRead, 4
  - ooPlayAudioBuffer, 4
  - ooReadWaveFileData, 5
- Media API, 5
- Media API Internal Common Helper Functions, 2
- Media API Internal Linux Helper Functions, 3
- Media API Internal Socket Layer, 9
- Media API Internal Windows Helper Functions, 17
- mediaapi
  - ooCloseReceiveRTPChannel, 6
  - ooCloseTransmitRTPChannel, 6
  - ooCreateReceiveRTPChannel, 7
  - ooCreateTransmitRTPChannel, 7
  - ooInitializePlugin, 7
  - ooStartReceiveAudioAndPlayback, 8
  - ooStartTransmitMic, 8
  - ooStartTransmitWaveFile, 8
  - ooStopReceiveAudioAndPlayback, 8
  - ooStopTransmitMic, 9
  - ooStopTransmitWaveFile, 9
- mediacommoin
  - ooLog, 2
  - ooSleep, 2
- ooAddToFreeBufferList
  - winhelpers, 20
- ooAddToWaveBufferList
  - winhelpers, 20
- ooCloseMic
  - winhelpers, 20
- ooCloseReceiveRTPChannel
  - mediaapi, 6
- ooCloseSpeaker
  - winhelpers, 21
- ooCloseTransmitRTPChannel
  - mediaapi, 6
- ooCloseWaveFile
  - linuxhelpers, 3
  - winhelpers, 21
- ooCommon.h, 28
- ooCreateReceiveRTPChannel
  - mediaapi, 7
- ooCreateTransmitRTPChannel
  - mediaapi, 7
- ooGetFreeBuffer
  - winhelpers, 21
- ooGetLocalIPAddress
  - sockets, 12

- ooGetMicAudioBuffer
  - linuxhelpers, 4
- ooHTONL
  - sockets, 12
- ooHTONS
  - sockets, 12
- ooInitializePlugin
  - mediaapi, 7
- OOIPADDR
  - sockets, 11
- ooLog
  - mediacommoin, 2
- ooMICCallback
  - winhelpers, 21
- ooOpenAudioDevice
  - linuxhelpers, 4
- ooOpenMic
  - winhelpers, 22
- ooOpenSpeaker
  - winhelpers, 22
- ooOpenWaveFileForRead
  - linuxhelpers, 4
  - winhelpers, 22
- ooPlayAudioBuffer
  - linuxhelpers, 4
- ooPlayWaveBuffer
  - winhelpers, 22
- ooReadWaveFileData
  - linuxhelpers, 5
  - winhelpers, 23
- ooRemoveHeadOfWaveBufferList
  - winhelpers, 23
- oortp.h, 29
- ooSleep
  - mediacommoin, 2
- ooSock.h, 31
- ooSocketAccept
  - sockets, 12
- ooSocketAddrToStr
  - sockets, 13
- ooSocketBind
  - sockets, 13
- ooSocketClose
  - sockets, 13
- ooSocketConnect
  - sockets, 14
- ooSocketCreate
  - sockets, 14
- ooSocketCreateUDP
  - sockets, 14
- ooSocketListen
  - sockets, 15
- ooSocketRecv
  - sockets, 15
- ooSocketRecvFrom

- sockets, 15
- ooSocketsCleanup
  - sockets, 16
- ooSocketSelect
  - sockets, 16
- ooSocketSend
  - sockets, 16
- ooSocketSendTo
  - sockets, 17
- ooSocketsInit
  - sockets, 17
- ooSocketStrToAddr
  - sockets, 17
- ooSpeakerCallback
  - winhelpers, 23
- ooStartMicDataCapture
  - winhelpers, 24
- ooStartReceiveAudioAndPlayback
  - mediaapi, 8
- ooStartTransmitMic
  - mediaapi, 8
- ooStartTransmitWaveFile
  - mediaapi, 8
- ooStopMicDataCapture
  - winhelpers, 24
- ooStopReceiveAudioAndPlayback
  - mediaapi, 8
- ooStopTransmitMic
  - mediaapi, 9
- ooStopTransmitWaveFile
  - mediaapi, 9
- ooWave.h, 34
- ooWaveFile, 26
- sockets
  - ooGetLocalIPAddress, 12
  - ooHTONL, 12
  - ooHTONS, 12
  - OOIPADDR, 11
  - ooSocketAccept, 12
  - ooSocketAddrToStr, 13
  - ooSocketBind, 13
  - ooSocketClose, 13
  - ooSocketConnect, 14
  - ooSocketCreate, 14
  - ooSocketCreateUDP, 14
  - ooSocketListen, 15
  - ooSocketRecv, 15
  - ooSocketRecvFrom, 15
  - ooSocketsCleanup, 16
  - ooSocketSelect, 16
  - ooSocketSend, 16
  - ooSocketSendTo, 17
  - ooSocketsInit, 17
  - ooSocketStrToAddr, 17
- WaveBuffer, 27

## winhelpers

- ooAddToFreeBufferList, 20
- ooAddToWaveBufferList, 20
- ooCloseMic, 20
- ooCloseSpeaker, 21
- ooCloseWaveFile, 21
- ooGetFreeBuffer, 21
- ooMICCallback, 21
- ooOpenMic, 22
- ooOpenSpeaker, 22
- ooOpenWaveFileForRead, 22
- ooPlayWaveBuffer, 22
- ooReadWaveFileData, 23
- ooRemoveHeadOfWaveBufferList, 23
- ooSpeakerCallback, 23
- ooStartMicDataCapture, 24
- ooStopMicDataCapture, 24

