

20 July 2015

Brocade vADC Device Driver for OpenStack Neutron LBaaS: Deployment Guide

BROCADE 

Copyright © 2015 Brocade Communications Systems, Inc. All Rights Reserved.

ADX, Brocade, Brocade Assurance, the B-wing symbol, DCX, Fabric OS, HyperEdge, ICX, MLX, MyBrocade, OpenScript, The Effortless Network, VCS, VDX, Vplane, and Vyatta are registered trademarks, and Fabric Vision and vADX are trademarks of Brocade Communications Systems, Inc., in the United States and/or in other countries. Other brands, products, or service names mentioned may be trademarks of others.

Notice: This document is for informational purposes only and does not set forth any warranty, expressed or implied, concerning any equipment, equipment feature, or service offered or to be offered by Brocade. Brocade reserves the right to make changes to this document at any time, without notice, and assumes no responsibility for its use. This informational document describes features that may not be currently available. Contact a Brocade sales office for information on feature and product availability. Export of technical data contained in this document may require an export license from the United States government.

The authors and Brocade Communications Systems, Inc. assume no liability or responsibility to any person or entity with respect to the accuracy of this document or any loss, cost, liability, or damages arising from the information contained herein or the computer programs that accompany it.

The product described by this document may contain “open source” software covered by the GNU General Public License or other open source license agreements. To find out which open source software is included in Brocade products, view the licensing terms applicable to the open source software, and obtain a copy of the programming source code, please visit

<http://www.brocade.com/en/support/support-tools/oscd.html>.

Brocade Communications Systems, Incorporated

Corporate and Latin American Headquarters
Brocade Communications Systems, Inc.
130 Holger Way
San Jose, CA 95134
Tel: 1-408-333-8000
Fax: 1-408-333-8101
E-mail: info@brocade.com

Asia-Pacific Headquarters
Brocade Communications Systems China HK, Ltd.
No. 1 Guanghua Road
Chao Yang District
Units 2718 and 2818
Beijing 100020, China
Tel: +8610 6588 8888
Fax: +8610 6588 9999
E-mail: china-info@brocade.com

European Headquarters
Brocade Communications Switzerland Sàrl
Centre Swissair
Tour B - 4ème étage
29, Route de l'Aéroport
Case Postale 105
CH-1215 Genève 15
Switzerland
Tel: +41 22 799 5640
Fax: +41 22 799 5641
E-mail: emea-info@brocade.com

Asia-Pacific Headquarters
Brocade Communications Systems Co., Ltd. (Shenzhen WFOE)
Citic Plaza
No. 233 Tian He Road North
Unit 1308 – 13th Floor
Guangzhou, China
Tel: +8620 3891 2000
Fax: +8620 3891 2111
E-mail: china-info@brocade.com

Contents

Preface.....	1
About This Guide	1
Document Conventions	1
Documentation and Release Notes	2
Traffic Manager and Services Director Documentation.....	2
Further Information Online	2
Getting Technical Help or Reporting Errors	2
Web Access	3
E-mail and Telephone Access	3
Chapter 1 - Prerequisites	4
Chapter 2 - Deployment Model.....	5
Using a Central Cluster of Traffic Managers	5
“Loadbalancer” Objects	5
“Listener” Objects.....	6
“Pool” Objects	6
“Member” Objects	6
“Healthmonitor” Objects.....	6
Chapter 3 - Installing and Configuring the Device Driver	7

Preface

Read this preface for an overview of the information provided in this guide. This preface includes the following sections:

- [“About This Guide,”](#) next
- [“Documentation and Release Notes”](#) on page 2
- [“Getting Technical Help or Reporting Errors”](#) on page 2

About This Guide

Brocade vADC Device Driver for OpenStack Neutron LBaaS: Deployment Guide describes how to deploy the Brocade vADC device driver for OpenStack Neutron LBaaS. It applies specifically to the OpenStack Kilo release and the Neutron LBaaS API version 2.

Document Conventions

This guide uses the following standard set of typographical conventions

Convention	Meaning
<i>italics</i>	Within text, new terms and emphasized words appear in <i>italic</i> typeface.
boldface	Within text, CLI commands, CLI parameters, and REST API properties appear in bold typeface.
Courier	Code examples appear in Courier font: <pre>amnesiac > enable amnesiac # configure terminal</pre>
< >	Values that you specify appear in angle brackets: interface <ip-address>
[]	Optional keywords or variables appear in brackets: ntp peer <ip-address> [version <number>]
{ }	Elements that are part of a required choice appear in braces: {<interface-name> ascii <string> hex <string>}
	The pipe symbol represents a choice to select one keyword or variable to the left or right of the symbol. The keyword or variable can be either optional or required: { delete <filename> upload <filename>}

Documentation and Release Notes

To obtain the most current version of all Brocade documentation, click through to the desired product page on the Brocade Web site at <http://www.brocade.com/en/products-services.html>.

If you need more information, see the Brocade Knowledge Base for any known issues, how-to documents, system requirements, and common error messages. You can browse titles or search for keywords and strings. To access the Brocade Knowledge Base, login to the MyBrocade Web site at <https://login.brocade.com>.

Each software release includes release notes. The release notes identify new features in the software as well as known and fixed problems. To obtain the most current version of the release notes, login to the MyBrocade Web site at <https://login.brocade.com>.

Examine the release notes before you begin the installation and configuration process.

Traffic Manager and Services Director Documentation

The Brocade Virtual Traffic Manager (Traffic Manager) and Brocade Services Director (Services Director) products includes comprehensive user's guides that describes their respective feature sets in depth.

There are also getting started guides for each variant of each product line, and a series of reference guides to cover additional functionality such as the TrafficScript rules language and product APIs.

You can download documentation for all supported editions from the relevant product pages on the Brocade Web site.

For the Traffic Manager, use:

<http://www.brocade.com/en/products-services/application-delivery-controllers/virtual-traffic-manager.html>.

For the Services Director, use:

<http://www.brocade.com/en/products-services/application-delivery-controllers/services-director.html>

Further Information Online

Visit the Brocade Community Web site for further documentation, examples, white papers, and other resources:

<http://community.brocade.com>

Getting Technical Help or Reporting Errors

Brocade is committed to ensuring that your investment in our products remains cost-effective. If you need assistance or find errors in the documentation, contact Brocade using one of the following options.

Web Access

The Brocade Web site contains the latest version of this guide and all other user guides for the Traffic Manager and Services Director. For more information, see <http://www.brocade.com/en/products-services/application-delivery-controllers.htm>

To report errors, log in to the MyBrocade Web site at <https://login.brocade.com> and click **Support Cases** to open a new support case. Make sure you specify the document title in the case description.

E-mail and Telephone Access

Go to <http://www.brocade.com/en/support.html> for the latest e-mail and telephone contact information.

CHAPTER 1 Prerequisites

Read this chapter for a description of the required prerequisites for this deployment guide.

You must first satisfy the following requirements:

- A configured OpenStack environment, consisting of at least the Keystone, Neutron, Nova and Glance services. For HTTPS decryption, the Barbican service is also required.
- A working understanding of the above OpenStack services, or the related documentation (available from <http://docs.openstack.org>) to work from.
- Suitable licenses for the Brocade products you are going to use. These could be:
 - None, if you are using the Developer Edition of the Traffic Manager in the “central cluster” deployment model for testing purposes.
 - One or more perpetual Traffic Manager licenses if you are using the “central cluster” deployment model in production.
- The necessary Brocade software packages, downloadable from the Brocade Web site:
 - A Traffic Manager Virtual Appliance image for the hypervisor you are using for OpenStack Nova. Must be version 10.1 or later.
- A working understanding of the above Brocade products, or the related documentation (available from the Brocade Web site) to work from.

The Brocade vADC driver currently supports one deployment model that is described in the second chapter of this guide. The steps for deploying the driver are included in the third chapter. Make sure you have planned your deployment and configured the necessary prerequisite services before creating your Brocade LBaaS configuration file (see [Chapter 4, “Installing and Configuring the Device Driver”](#)) to ensure you have all the required components and settings in place.

CHAPTER 2 Deployment Model


Using a Central Cluster of Traffic Managers

This configuration does not require the Services Director and is most suited to organizations that wish to use perpetual Traffic Manager license keys.

A central cluster of Traffic Managers (up to 64) is shared between all OpenStack tenants. A shared network on which all LBaaS “loadbalancer” IP addresses are raised is required, and there is no resource isolation between tenants’ services.

Although the load-balanced services use an IP address on a shared network, the back-end servers themselves remain within the tenants’ own subnets.

Figure 2-1. A central cluster of Traffic Managers (vTM Cluster) shared between all OpenStack tenants.



Note: All Traffic Manager configuration objects that are created on the cluster by the LBaaS driver will have the Neutron name of the object and the Keystone ID of the tenant included in the object’s “Note” field.

“Loadbalancer” Objects

LBaaS “loadbalancer” objects are implemented as Traffic Manager Traffic IP Groups.

Each group contains the “Loadbalancer” IP address, one primary Traffic Manager on which to host the IP during normal operation, and a configurable number of backup Traffic Managers to use in the event of a failure of the primary. The driver will automatically distribute Traffic IP Groups across the cluster to providing scalability and approximately even load distribution (assuming all “loadbalancers” process roughly the same amount of traffic). To facilitate Traffic IP failover, each Traffic IP address is added to the “allowed_address_pair” field of the Neutron port associated with each Traffic Manager.

“Listener” Objects

LBaaS “listener” objects are implemented as Virtual Servers in the Traffic Manager.

HTTP, HTTPS pass-through, HTTPS off-load, generic TCP (client-first) and UDP protocols are supported.

Certificates for HTTPS off-loading must be managed through the OpenStack Barbican tool.

The LBaaS “listener” “connection_limit” setting is implemented using a Traffic Manager Rate Class and a corresponding TrafficScript request rule to apply it. These are tied to the Virtual Server and will be deleted automatically along with it when the “listener” object is deleted.

“Pool” Objects

LBaaS “pool” objects are implemented as Pools in the Traffic Manager.

The LBaaS “pool” “session_persistence” setting is implemented using a Traffic Manager Session Persistence Class applied to the Pool. This is tied to the Pool and will be deleted automatically along with it when the “pool” object is deleted.

“Member” Objects

LBaaS “member” objects are implemented as nodes in the corresponding Traffic Manager Pool.

“Healthmonitor” Objects

LBaaS “healthmonitor” objects are implemented as Monitors in the Traffic Manager.

While there is a 1:1 relationship between “pools” and “healthmonitors”, the Traffic Manager Monitor object is not automatically deleted when the “pool” is deleted, allowing it to be reused by another “pool”.

CHAPTER 3 Installing and Configuring the Device Driver

This chapter contains instructions for installing and configuring the Brocade vADC Device Driver for OpenStack Neutron LBaaS.

The following instructions assume you have a fully configured OpenStack Kilo (or later) environment, including all of the required Neutron networks.

1. If you haven't already done so:
 - a. Create and configure the vTM cluster (for more information, see the *Brocade Virtual Traffic Manager: User's Guide* or *Brocade Virtual Traffic Manager: Virtual Appliance Installation and Getting Started Guide*) ensuring each cluster member has a vNIC on the shared data network, and on a management network if applicable. You can use either the applicable vTM Virtual Appliance for your hypervisor platform, or a vTM software installation.
 - b. Ensure that the REST API is enabled on all cluster members

2. On the NetworkNode, type the following command to clone the device driver GitHub repository:

```
# git clone https://github.com/brocade-vadc/neutron-lbaas-device-driver
```

3. Type the following commands to install the driver:

```
# cd neutron-lbaas-device-driver
# sudo python setup.py install
```

4. Type the following command to configure the driver:

```
# sudo brocade_lbass_config_generator > /etc/neutron/services/loadbalancer/brocade.conf
```

Answer the questions concerning the deployment settings you wish to use.

5. Use the following steps to configure Neutron to use the driver:

- In `/etc/neutron/neutron.conf`, under the `[DEFAULT]` section, ensure the `"service_providers="` line contains `"neutron_lbaas.services.loadbalancer.plugin.LoadBalancerPluginv2"`.
- In `/etc/neutron/neutron_lbaas.conf`, under the `[service_providers]` section, type the following:


```
service_provider = \
LOADBALANCERV2:brocade:neutron_lbaas.drivers.brocade.driver_v2.BrocadeLoadBalancerDriver:
default
```

9. Stop the Neutron server (system and installation-specific).

10. Start the Neutron server with the following additional CLI parameter:

```
--config-file /etc/neutron/services/loadbalancer/brocade.conf
```

At this point, you should be able to create, modify and delete LBaaS services through the Neutron command line tool, the Neutron REST API or the Horizon GUI. For more information, see <http://docs.openstack.org>.