

TMS, DMS and CMS Usage Guide for Falcon BMS 4.38.1

Carlos “Metal” Nader

Version C4-S1+202601120.2.4.0 | January 2026

Contents

1	DMS — Display Management Switch	3
1.1	Concept and Sensor of Interest (SOI)	3
1.1.1	SOI Definition and Scope Across Displays	4
1.1.2	Role of the DMS in SOI Selection	5

1 DMS — Display Management Switch

1.1 Concept and Sensor of Interest (SOI)

The Display Management Switch (DMS) is a four-direction spring-loaded hat located on the flight stick. Its primary role is to manage which display or sensor receives hands-on control inputs, known as the Sensor of Interest (SOI), and to cycle through the Multifunction Display Set (MFDS) format pages.

Unlike the Target Management Switch (TMS), which performs tactical functions such as target designation and data management (see Chapter 3), the DMS is a transversal SOI architecture manager. It does not designate targets or change radar modes directly; instead, it selects *which display or sensor* the pilot is currently controlling with other HOTAS inputs (such as CURSOR/ENABLE or TMS).

As presented in Chapter 3, condensed diagrams for throttle and flight stick switches functionalities can be found on Dash-34 § 2.1.5. Below is an image of the F-16 Flight Stick, with the DMS switch location.



Figure 1: F-16 Throttle and Flight Stick. Image by Falconpedia (falcon4.wikidot.com), via Wikimedia Commons (https://commons.wikimedia.org/wiki/File:F-16_Side_Stick_Controller.jpg), licensed under the Creative Commons Attribution-Share Alike 3.0 Unported (CC BY-SA 3.0) license.

DMS Across F-16 Blocks and Variants: The functionality of the DMS—SOI selection, MFD format cycling and all associated behaviors is identical across all F-16 blocks and variants available in Falcon BMS 4.38.1. Differences in aircraft avionics do not alter DMS switch usage. For this reason, all DMS procedures in this chapter apply universally to the entire F-16 family.

1.1.1 SOI Definition and Scope Across Displays

The Sensor of Interest (SOI) is the display or sensor that currently receives HOTAS cursor slew commands and, where applicable, TMS actions. At any moment, only one display can be the SOI. Valid SOI displays include:

- **Fire Control Radar (FCR)** — A-A and A-G modes.
- **Targeting Pod (TGP)** — A-G or A-A tracking.
- **Horizontal Situation Display (HSD)** — all master modes.
- **HARM Attack Display (HAD)** — A-G SEAD/EW context.
- **Weapon page (WPN)** — IAMs, Maverick, Harpoon and other weapon-specific pages.
- **Head-Up Display (HUD)** — Navigation and A-G master modes only (not A-A).

Displays that are *not* valid SOI include: SMS (Stores Management Set), DTE (Data Transfer Equipment), TEST, and blank/inactive MFDS formats. These pages provide information or control but do not accept sensor-like slew or targeting inputs.

The SOI is indicated visually:

- On the **HUD/HMCS**: an asterisk (*) appears in the upper left corner when HUD/HMCS is the SOI.
- On an **MFD**: a border outline appears around the edges of the display when it is the SOI. When an MFD format is *not* the SOI, the text “NOT SOI” may appear on the format (depending on the mode).

Valid SOI Displays by Master Mode: The availability of displays as valid SOI varies by master mode. Table 1 shows which displays can serve as SOI in the primary operational contexts. Note that in air-to-air modes (A-A, DGFT, MSL OVRD), the HUD is **never** available as SOI; A-A modes restrict the pilot to FCR, HSD, or TGP as the SOI. This constraint ensures that radar and tactical displays remain the primary source of truth in air-to-air engagements.

Table 1: Valid SOI Displays by Master Mode

Master Mode	Valid SOI Displays	Constraints & Notes
NAV (Navigation)	HUD/HMCS, FCR, TGP, HSD, WPN, HAD	All displays available. HUD is primary choice for situational awareness and NAV-specific tasks.
A-A (Air-to-Air)	FCR, HSD, TGP	HUD/HMCS cannot be SOI. SOI limited to radar and tactical displays.

Continues on next page

Master Mode	Valid SOI Displays	Constraints & Notes
A-G (PRE)	HUD/HMCS, FCR, TGP, WPN, HAD, HSD	All displays available. Common workflow: HUD for visual cueing, then TGP or WPN for weapon prep.
A-G (VIS)	HUD/HMCS, TGP, WPN	Restricted to visual-capable displays. FCR and HAD are not typically available in pure visual modes (e.g., AGM-65 VIS EO, DTOS, CCIP).
DGFT (Dogfight)	FCR, HSD, TGP	HUD/HMCS cannot be SOI. Dogfight context prioritizes radar and tactical displays.
MSL OVRD (Missile Override)	FCR, HSD, TGP	HUD/HMCS cannot be SOI. Missile management takes precedence; HUD displays cues only.

As shown in Table 1, the availability of SOI displays is strategically constrained by master mode to align pilot attention with the operational context. Navigation and pre-planned air-to-ground modes offer maximum display flexibility, allowing the pilot to transition between HUD, radar, targeting pod, and weapon pages as needed.

Conversely, air-to-air and associated override modes eliminate HUD as a selectable SOI. This design reflects the fundamental principle that air-to-air engagements must be driven by primary sensor information rather than derived or display-level cues, although HCMS is always an option.

For visual air-to-ground delivery (VIS modes), the SOI is restricted to visual-capable sensors: HUD/HMCS for target designation, TGP for optical tracking if available, and WPN for weapon-specific refinements. In these contexts, the radar falls out of the active SOI pool, and navigation accuracy defaults to system altitude and pre-entered steerpoint data rather than radar-derived range.

1.1.2 Role of the DMS in SOI Selection

The DMS manages SOI selection through two orthogonal axes of control:

- **Vertical (Up / Down):** Selects *which display* is the SOI.
 - **DMS Up:** Transfers SOI to the HUD (when permitted by master mode).
 - **DMS Down:** Cycles SOI between MFDs, or from HUD to an MFD.
- **Horizontal (Left / Right):** Steps through MFDS format pages on the left or right MFD, independently of which display is the SOI.
 - **DMS Left:** Cycles the left MFD format (FCR → SMS → HSD → TGP → ...).
 - **DMS Right:** Cycles the right MFD format.

In the following sections, this chapter details how the DMS interacts with MFD format selection (Section ?? and ??) and how DMS integrates with TMS in some weapon specific circumstances in Section ??.