

Multi-Processor Computing framework (MPC version 2.5.1)

General Installation guide

Please refer to the [GettingStarted.pdf](#) document for general installation.

Cross-compilation Installation guide

Prerequisites

- **For ARM architecture:** a cross-compiled gcc which generate code for ARM architecture
- **For MIC architecture:** the Intel Compiler suite and the Intel libraries ([Intel MPSS](#))
- **General:**
 - You need to install MPC for the architecture you will compile for *AND* the architecture you will launch on.
 - The prefix for both installations have to be on the *SAME* prefix.

MIC Compilation

1. Load Intel modules (*icc*, *libraries*, etc) in your environment.
2. Launch the **installmpc** script for the MIC:

```
$ ./installmpc --prefix=$HOME/install-mpc --target=mic --compiler=icc
--arch-library-path=(Path to Intel lib for mic architecture) --disable-mpc-gcc
--disable-mpc-gdb
```

--target=mic: specify the target architecture. You can either use **--target=mic** or **--target=k1om**.

--compiler=icc: specify the compiler to be used by MPC. Here *icc* has to be selected.

--arch-library-path=path: specify the path of libraries used for the target architecture.

Note: Do not forget to add **--disable-mpc-gcc** and **--disable-mpc-gdb** options to the **installmpc** script. You could have errors installing these two programs with *icc*.

3. Source the *mpcvars* script located in the root directory of your MPC installation prefix

```
$ . $HOME/install-mpc/mpcvars.sh for sh shells
$ source $HOME/install-mpc/mpcvars.csh for csh, tcsh or bash shells
```

This will load the MPC environment for the current architecture. You can force to load the environment for the MIC architecture by typing:

```
$ source $HOME/install-mpc/mpcvars.sh k1om
```

4. To compile your first MPC program for a MIC architecture, you may execute the **mpc_cc** compiler:

If you loaded the MIC environment:

```
$ mpc_cc main.c -o main.mic
```

If you loaded the host environment:

```
$ mpc_cc -target=k1om main.c -o main.mic
```

5. Execute your MPC program:

- **Homogeneous launch:**

- Compile your code for the MIC architecture (*main.mic*)
- Create *config.cfg* file:

```
-host mic0 -p 1 ./main.mic
```

- Launch the binary with **mpcrun** script:

```
$ mpcrun -p=1 -n=4 -net=tcp -l=mic_hybrid --mic-config=config.cfg
```

-l=mic_hybrid: load the mic launcher

--mic-config=*: load the config file for launch

Note that your process number have to be the same in *config.cfg* and launch command

- **Heterogeneous launch:**

- Compile your code for the MIC architecture (*main.mic*) as well as for the host architecture (*main.host*)
- Create *config.cfg* file:

```
-host knc02 -p 4 ./main.host
-host mic0 -p 3 ./main.mic
```

```
# Information
--help|-h|-?           : Display this help and exit
--version              : Report version number and exit

# Installation
--prefix=PREFIX        : Install architecture-independent files in PREFIX [/usr/local]
--disable-check-install : Override installation if it already exists in the prefix

# Build
--compiler              : Default compiler
clean                  : Delete directories inside build directory
distclean              : Delete directories and makefiles inside build directory

# Download missing deps
--download-missing-deps : Download dependencies
--mirror={1|2|3|4}      : Choose a mirror for downloading dependencies
```

```

# Disable sub packages
--disable-mpc-gdb           : Disable gdb
--disable-mpc-gcc           : Disable gcc
--disable-mpc-binutils      : Disable binutils
--disable-mpc-fortran       : Disable fortran

# Specify system subpackages
--with-mpc-gdb=*            : Specify gdb prefix on the system
--with-mpc-gcc=*            : Specify gcc prefix on the system
--with-sctk-arch=*          : Specify sctk_arch prefix on the system
--with-openpa=*             : Specify openpa prefix on the system
--with-mpfr=*               : Specify mpfr prefix on the system
--with-gmp=*                : Specify gmp prefix on the system
--with-mpc-binutils=*       : Specify binutils prefix on the system
--with-hwloc=*              : Specify hwloc prefix on the system
--with-libxml2=*            : Specify libxml2 prefix on the system

# Options to transmit to subpackages
--mpc-gcc-*                 : Add options to gcc configure
--mpc-gdb-*                 : Add options to gdb configure
--sctk-arch-*               : Add options to sctk-arch configure
--openpa-*                  : Add options to openpa configure
--gmp-*                     : Add options to gmp configure
--mpfr-*                    : Add options to mpfr configure
--mpc-*                     : Add options to mpc multiprecision library configure
--mpc-binutils-*            : Add options to binutils configure
--libxml2-*                 : Add options to libxml2 configure
--hwloc-*                   : Add options to hwloc configure
--mpc-option=*              : Add options to mpc framework configure

# Cross-compilation
--target=*                  : Specify architecture for target
--host=*                    : Specify architecture for host
--arch-library-path         : Specify path for architecture libraries

# Features
--disable-color             : Disable colors in display
--verbose=1|2|3            : Level of verbosity
-v|-vv|-vvv               : Level of verbosity
-jN                         : Allow N jobs at once (parallel install)

```