
Contents

1 Introduction to obsutil	3
2 Getting Started.....	5
2.1 Performing Initial Configuration	5
2.2 Quick Start.....	6
3 Bucket Commands	8
3.1 Creating a Bucket	8
3.2 Listing Buckets	10
3.3 Querying Bucket Properties	11
3.4 Setting Bucket Properties.....	12
3.5 Deleting a Bucket	14
4 Object Commands.....	16
4.1 Creating a Folder	16
4.2 Uploading an Object	17
4.3 Querying Object Properties	26
4.4 Setting Object Properties	27
4.5 Listing Objects.....	31
4.6 Copying an Object	33
4.7 Moving an Object	40
4.8 Downloading an Object	47
4.9 Generating the Download Link of an Object.....	53
4.10 Deleting an Object	56
4.11 Synchronously Uploading Incremental Objects.....	58
4.12 Synchronously Copying Incremental Objects.....	64
4.13 Synchronously Downloading Incremental Objects.....	70
4.14 Restoring Objects.....	75
4.15 Resuming a Failed Upload Task	78
4.16 Resuming a Failed Copy Task	82
4.17 Resuming a Failed Download Task	88
4.18 Listing Multipart Upload Tasks	93
4.19 Deleting a Multipart Upload Task.....	95
5 Auxiliary Commands	98

5.1 Updating a Configuration File	98
5.2 Deleting Part Records	99
5.3 Viewing Command Help Information.....	100
5.4 Querying the Version Number	101
5.5 Archiving Log Files	101
6 Common Examples	104
6.1 Upload Examples	104
6.2 Synchronous Upload Examples	105
6.3 Download Examples	106
6.4 Synchronous Download Examples	107
6.5 Copy Examples	108
6.6 Synchronous Copy Examples	109
6.7 List Examples	110
6.8 Examples of Listing Multipart Upload Tasks	111
7 Fault Locating.....	112
7.1 Overview	112
7.2 Log Files	112
7.3 Result Lists	113
7.4 Return Codes	113
8 Best Practices.....	116
8.1 Configuring Scheduled Tasks Using the Crontab Command.....	116
8.2 Fine-Tuning obsutil Performance	117
A Parameter Description.....	119

1 Introduction to obsutil

obsutil is a command line tool for accessing Object Storage Service (OBS). You can use this tool to perform common configurations in OBS, such as creating buckets, uploading and downloading files/folders, and deleting files/folders. If you are familiar with command line interface (CLI), obsutil is recommended as an optimal tool for batch processing and automated tasks.

Tool Advantages

obsutil features the following aspects:

1. Simple and easy to use
2. Lightweight and installation-free
3. Compatible with Windows, Linux, and macOS operating systems
4. Diversified configurations and excellent performance

Functions

Table 1-1 lists obsutil functions.

Table 1-1 obsutil functions

Function	Description
3 Bucket Commands	Create buckets of different storage classes in specific regions, delete buckets, and obtain the bucket list and configuration information.
4 Object Commands	Manage objects, including uploading, downloading, deleting, and listing objects. Supported operations are detailed as follows: <ul style="list-style-type: none">• Upload one or more files or folders.• Upload large files in multiple parts.• Synchronously upload, download, and copy incremental objects.• Copy a single object or copy multiple objects in batches by object name prefix.• Move a single object or move objects in batches by object name prefix.

Function	Description
	<ul style="list-style-type: none">Resume failed upload, download, or copy tasks.
7.2 Log Files	Allows you to configure logging on the client side to record operations on buckets and objects for statistics analysis later.

Command Line Structure

The obsutil command line structures are as follows:

- In Windows
obsutil *command* [*parameters...*] [*options...*]
- In Linux or macOS
.obsutil *command* [*parameters...*] [*options...*]



NOTE

- command** indicates the command to be executed, for example, **ls** or **cp**.
- parameters** indicates the basic parameters (mandatory) of the command, for example, bucket name when creating a bucket.
- options** indicates the additional parameters (optional) of the command. Additional parameters must be preceded with a hyphen (-) when you run the command.
- The square brackets ([]) are not part of the command. Do not enclose parameter values with them when entering a command.
- If the command contains special characters including ampersands (&), angle brackets (<) and (>), and spaces, they need to be escaped using quotation marks. Use single quotation marks for Linux or macOS and quotation marks for Windows.
- Additional parameters can be input in the **-key=value** or **-key value** format, for example, **-acl=private**, or **-acl private**. There is no difference between the two formats. Select either one as you like.
- In Windows, you can directly execute **obsutil.exe** to enter an interactive command mode. In this mode, you can input *command* [*parameters...*] [*options...*] without **obsutil** to run a command. An example is provided as follows:

```
Enter "exit" or "quit" to logout
Enter "help" or "help command" to show help docs
Input your command:
-->ls -limit=3 -s
obs://bucket-001
obs://bucket-002
obs://bucket-003
Bucket number is: 3

Input your command:
-->
```

- If you use SSH to remotely log in to the Linux or macOS for running obsutil commands, you are advised to set **TMOUT=0** to prevent the program from exiting due to the expiration of the SSH session.

2 Getting Started

2.1 Performing Initial Configuration

Before using obsutil, you need to configure the interconnection between obsutil and OBS, including the endpoint and access keys (AK and SK) of OBS. You can use obsutil to perform operations on OBS buckets and objects only after obtaining the OBS authentication.

Configuration Method

You can run the following commands to initialize obsutil:

- In Windows

```
obsutil config -i=ak -k=sk -e=endpoint
```

- In Linux or macOS

```
./obsutil config -i=ak -k=sk -e=endpoint
```



NOTE

- After running the preceding commands, a configuration file **.obsutilconfig** is automatically generated in the same home directory of the user who executes obsutil commands (the `~` directory in Linux or macOS, and the `C:\Users\<Username>` directory in Windows). **.obsutilconfig** contains all the configuration information of obsutil. For details about the parameters, see A Parameter Description.
- The **.obsutilconfig** file contains the AK and SK information of a user. Therefore, it is hidden by default to prevent key disclosure. To query the file, run the following command in the home directory of the user who executes obsutil commands.

- In Windows

```
dir
```

- In Linux or macOS

```
ls -a
```

or

```
ls -al
```

Checking the Connectivity

After the configuration is complete, you can check whether it is correct by running the following commands:

- In Windows

```
obsutil ls -s
```

- In Linux or macOS

```
./obsutil ls -s
```


Check the configuration result based on the command output:

- If the command output contains **Bucket number is:**, the configuration is correct.
- If the command output contains **Http status [403]**, the access keys are incorrectly configured.
- If the command output contains **A connection attempt failed**, then OBS cannot be accessed. In this case, check the network condition.

2.2 Quick Start

This section uses the Linux OS as an example to describe how to use obsutil to perform basic data access operations in OBS. For details, see Figure 2-1.

Figure 2-1 obsutil flow for a quick start



Prerequisites

- You have obtained obsutil and completed initial configuration.
- You have accessed to the directory where the tool is located.

Procedure

Step 1 Run the `./obsutil mb obs://bucket-test` command to create a new bucket named **bucket-test**.

```
./obsutil mb obs://bucket-test

Create bucket [bucket-test] successfully!
```

Step 2 Run the `./obsutil cp /temp/test.txt obs://bucket-test/test.txt` command to upload the **test.txt** file to bucket **bucket-test**.

```
./obsutil cp /temp/test.txt obs://bucket-test/test.txt

Parallel:      5              Jobs:      5
Threshold:    52428800        PartSize:   5242880
Exclude:      0              Include:    0
VerifyLength: false          VerifyMd5:   false
CheckpointDir: /temp/.obsutil_checkpoint

test.txt:[=====] 100.00% 48.47 KB/s 0s
Upload successfully, 4.44KB, /temp/test.txt --> obs://bucket-test1/test.txt
```

Step 3 Run the `./obsutil cp obs://bucket-test/test.txt /temp/test1.txt` command to download **test.txt** from bucket **bucket-test** to a local PC.

```
./obsutil cp obs://bucket-test/test.txt /temp/test1.txt

Parallel:      5              Jobs:      5
Threshold:    52428800        PartSize:   5242880
Exclude:      0              Include:    0
VerifyLength: false          VerifyMd5:   false
CheckpointDir: /temp/.obsutil_checkpoint

test.txt:[=====] 100.00% 775.52 KB/s 0s
Download successfully, 4.44KB, obs://bucket-test1/test.txt --> /temp/test1.txt
```

Step 4 Run the `./obsutil rm obs://bucket-test/test.txt -f` command to delete object **test.txt** from bucket **bucket-test**.

```
./obsutil rm obs://bucket-test/test.txt -f

Delete object [test.txt] in the bucket [bucket-test] successfully!
```

Step 5 Run the `./obsutil rm obs://bucket-test -f` command to delete bucket **bucket-test**.

```
./obsutil rm obs://bucket-test -f

Delete bucket [bucket-test] successfully!
```

----End

3 Bucket Commands

3.1 Creating a Bucket

Function

You can use this command to create a bucket. A bucket name must be unique in OBS. One account can create a maximum of 100 buckets.



NOTE

If you create a bucket and name it the same as an existing one in the same account and region, no error will be reported and status code 200 is returned. The bucket properties comply with those set in the first creation request. In other cases, creating a namesake bucket will receive the status code 409, indicating that the bucket already exists.

Command Line Structure

- In Windows

```
obsutil mb obs://bucket [-acl=xxx] [-sc=xxx] [-location=xxx] [-config=xxx]
```

- In Linux or macOS

```
./obsutil mb obs://bucket [-acl=xxx] [-sc=xxx] [-location=xxx] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
bucket	Mandatory	<p>Bucket name</p> <p>NOTE</p> <p>A bucket name must comply with the following rules:</p> <ul style="list-style-type: none">• Contains 3 to 63 characters, including lowercase letters, digits, hyphens (-), and periods (.), and starts with a digit or letter.• Cannot be an IP address.• Cannot start or end with a hyphen (-) or period (.).• Cannot contain two consecutive periods (.), for example, my..bucket.• Cannot contain periods (.) and hyphens (-) adjacent to each other, for example, my-.bucket or my.-bucket.

Parameter	Optional or Mandatory	Description
acl	Optional (additional parameter)	<p>Access control policies that can be specified when creating a bucket. Possible values are:</p> <ul style="list-style-type: none">• private• public-read• public-read-write <p>NOTE</p> <p>The preceding three values indicate private read and write, public read, and public read and write.</p>
sc	Optional (additional parameter)	<p>Default bucket storage class that can be specified when creating a bucket. Possible values are:</p> <ul style="list-style-type: none">• standard: Indicates the Standard storage class. It features low access latency and high throughput, and is applicable to storing frequently accessed data (multiple accesses per month averagely) or data that is smaller than 1 MB.• warm: It is applicable to storing semi-frequently accessed (less than 12 times a year averagely) data that requires quick response.• cold: It is secure, durable, and inexpensive, and applicable to archiving rarely-accessed (once a year averagely) data.
location	Mandatory unless the region where the OBS service resides is not the default region (additional parameter)	Region where the bucket resides.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Running Examples

- Take the Windows OS as an example. Run the **obsutil mb obs://bucket-test** command to create a bucket. The creation is successful.

```
obsutil mb obs://bucket-test
```

```
Create bucket [bucket-test] successfully, request id  
[0000016979E1D2EA860BB5E80A6B8FCC]
```

- Take the Windows OS as an example. Run the **obsutil mb obs://bucket001** command to create a namesake bucket. The creation fails.

```
obsutil mb obs://bucket001
```

```
Create bucket [bucket001] failed, http status [409], error code [BucketAlreadyExists],
```

```
error message [The requested bucket name is not available. The bucket namespace is shared by all users of the system. Please select a different name and try again.], request id [04030000016757F31A0333281A6B1E92]
```

3.2 Listing Buckets

Function

You can use this command to obtain the bucket list. In the list, bucket names are displayed in lexicographical order.

Command Line Structure

- In Windows

```
obsutil ls [-s] [-sc] [-j=1] [-limit=1] [-config=xxx]
```

- In Linux or macOS

```
./obsutil ls [-s] [-sc] [-j=1] [-limit=1] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
s	Optional (additional parameter)	Displays simplified query result. NOTE In the simplified format, the returned result contains only the bucket name.
sc	Optional (additional parameter)	Queries the storage classes of the buckets when listing buckets.
j	Optional (additional parameter). It must be used together with sc .	Indicates the maximum number of concurrent tasks for querying the bucket storage class. The default value is the value of defaultJobs in the configuration file. NOTE The value is ensured to be greater than or equal to 1.
limit	Optional (additional parameter)	Maximum number of buckets to be listed. The default value -1 indicates all buckets are listed.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Running Example

- Take the Windows OS as an example. Run the **obsutil ls -limit=5** command to obtain the bucket list.

```
obsutil ls -limit=5
```

Bucket	CreationDate	Location
obs://bucket001	2018-09-03T01:53:02Z	southchina
obs://bucket002	2018-11-01T01:40:01Z	southchina
obs://bucket003	2018-10-25T11:45:45Z	southchina
obs://bucket004	2018-10-26T02:33:09Z	southchina
obs://bucket005	2018-10-26T02:34:50Z	southchina

Bucket number is: 5

3.3 Querying Bucket Properties

Function

You can use this command to query the basic properties of a bucket, including its default storage class, region, version ID, storage usage, bucket quota, and the number of objects in the bucket.

Command Line Structure

- In Windows

```
obsutil stat obs://bucket [-acl] [-config=xxx]
```

- In Linux or macOS

```
./obsutil stat obs://bucket [-acl] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
acl	Optional	Queries the access control policies of the bucket while querying bucket properties.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Response

Field	Description
Bucket	Bucket name
StorageClass	Default storage class of the bucket

Field	Description
Location	Region where the bucket resides
ObsVersion	Version of the bucket
ObjectNumber	Number of objects in the bucket
Size	Storage usage of the bucket, in bytes
Quota	Bucket quota. Value 0 indicates that no upper limit is set for the bucket quota.
Acl	Access control policy of the bucket

Running Example

- Take the Windows OS as an example. Run the **obsutil stat obs://bucket-test** command to query the basic properties of bucket **bucket-test**.

```
obsutil stat obs://bucket-test
```

```
Bucket:
  obs://bucket-test
StorageClass:
  standard
Location:
  southchina
ObsVersion:
  3.0
ObjectNumber:
  8005
Size:
  320076506
Quota:
  0
```

3.4 Setting Bucket Properties

Function

You can use this command to set the properties of a bucket, including storage classes and access policies.

Command Line Structure

- In Windows

```
obsutil chattri obs://bucket [-sc=xxx] [-acl=xxx] [-aclXml=xxx] [-config=xxx]
```

- In Linux or macOS

```
./obsutil chattri obs://bucket [-sc=xxx] [-acl=xxx] [-aclXml=xxx] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
sc	Optional (additional parameter)	<p>Default storage class of the bucket. Possible values are:</p> <ul style="list-style-type: none">• standard: OBS Standard, which features low access latency and high throughput, and is applicable to storing frequently accessed data (multiple accesses per month averagely) or data that is smaller than 1 MB• warm: It is applicable to storing semi-frequently accessed (less than 12 times a year averagely) data that requires quick response.• cold: It is secure, durable, and inexpensive, and applicable to archiving rarely-accessed (once a year averagely) data.
acl	Optional (additional parameter)	<p>Access control policies that can be specified for buckets. Possible values are:</p> <ul style="list-style-type: none">• private• public-read• public-read-write <p>NOTE</p> <p>The preceding three values indicate private read and write, public read, and public read and write.</p>
aclXml	Optional (additional parameter)	<p>Access control policy of the bucket, in XML format.</p> <pre><AccessControlPolicy> <Owner> <ID>ownerid</ID> </Owner> <AccessControlList> <Grant> <Grantee> <ID>userid</ID> </Grantee> <Permission>[WRITE WRITE_ACP READ READ_ACP FULL_CONTROL]</Permission> </Grant> <Grant> <Grantee> <Canned>Everyone</Canned> </Grantee> <Permission>[WRITE WRITE_ACP READ READ_ACP FULL_CONTROL]</Permission> </Grant></pre>

Parameter	Optional or Mandatory	Description
		<pre></AccessControlList> </AccessControlPolicy></pre> <p>NOTE</p> <ul style="list-style-type: none">• Owner: Optional. Specify the bucket owner's ID.• In AccessControlList, the Grant field contains the authorized users. Grantee specifies the IDs of authorized users. Canned specifies the authorized user group (currently, only Everyone is supported).• The following permissions can be granted: WRITE (write), WRITE_ACP (write ACL), READ (read), READ_ACP (read ACL), and FULL_CONTROL (full control). <p>NOTICE</p> <p>Because angle brackets (<) and (>) are unavoidably included in the parameter value, you must use quotation marks to enclose them for escaping when running the command. Use single quotation marks for Linux or macOS and quotation marks for Windows.</p>
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

**NOTE**

Only one of **sc**, **acl**, and **aclXml** can be set for each command.

Running Example

- Take the Windows OS as an example. Run the **obsutil chattri obs://bucket-test -acl=private** command to change the access control policy of the bucket to private read and write.

```
obsutil chattri obs://bucket-test -acl=private
```

```
Set the acl of bucket [bucket-test] to [private] successfully, request id
[04050000016836C5DA6FB21F14A2A0C0]
```

3.5 Deleting a Bucket

Function

You can use this command to delete a bucket. The bucket to be deleted must be empty (containing no objects, historical versions, or fragments).

**NOTE**

To delete a non-empty bucket, run the commands in 4.19 Deleting a Multipart Upload Task and in 4.10 Deleting an Object to clear the bucket, and then run the following command to delete the bucket.

Command Line Structure

- In Windows

```
obsutil rm obs://bucket [-f] [-config=xxx]
```

- In Linux or macOS

```
./obsutil rm obs://bucket [-f] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
f	Optional (additional parameter)	Runs in force mode.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Running Example

- Take the Windows OS as an example. Run the **obsutil rm obs://bucket-test** command to delete bucket **bucket-test**.

```
obsutil rm obs://bucket-test
```

```
Do you want delete bucket [bucket-test] ? Please input (y/n) to confirm:
```

```
y
```

```
Delete bucket [bucket-test] successfully!
```

4 Object Commands

4.1 Creating a Folder

Function

You can use this command to create a folder in a specified bucket or local file system.

Command Line Structure

- In Windows

- Creating a folder in a specified bucket

```
obsutil mkdir obs://bucket/folder[/subfolder1/subfolder2] [-config=xxx]
```

- Creating a folder in the local file system

```
obsutil mkdir folder_url [-config=xxx]
```

- In Linux or macOS

- Creating a folder in a specified bucket

```
./obsutil mkdir obs://bucket/folder[/subfolder1/subfolder2] [-config=xxx]
```

- Creating a folder in the local file system

```
./obsutil mkdir folder_url [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
bucket	Mandatory when creating a folder in a specified bucket	Bucket name
folder	Mandatory when creating a folder in a specified bucket	Folder path in the bucket. This value can contain multi-level folders. Separate each level with a slash (/).

Parameter	Optional or Mandatory	Description
folder_url	Mandatory when creating a folder in the local file system	Folder path in the local file system. The value can be an absolute path or a relative path.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Running Example

- Take the Windows OS as an example. Run the **obsutil mkdir obs://bucket-test/folder1/folder2** command to create a folder in a bucket.

```
obsutil mkdir obs://bucket-test/folder1/folder2
```

```
Create folder [obs://bucket-test/folder1/] successfully, request id  
[0000016979E1D23C860BB3D8E4577C5E]  
Create folder [obs://bucket-test/folder1/folder2] successfully, request id  
[0000016979E1D2B2860BB5181229C72C]
```

4.2 Uploading an Object

Function

You can use this command to upload one or more local files or folders to a specified path in OBS. These files can be texts, images, videos, or any other type of files.

NOTICE

Do not change the local file or folder when uploading it. Otherwise, the upload may fail or data may be inconsistent.

Restrictions

obsutil has restrictions on the size of files or folders to be uploaded. You can upload an empty file or folder of 0 bytes. You can also upload a single file or folder with a maximum size of 5 GB in normal mode or a single file or folder with a maximum size of 48.8 TB in multipart mode.

Command Line Structure

- In Windows
 - Uploading a file

```
obsutil cp file_url obs://bucket[/key] [-arcDir=xxx] [-dryRun] [-link] [-u]
[-vlength] [-vmd5] [-p=1] [-threshold=5248800] [-acl=xxx] [-sc=xxx]
[-meta=aaa:bbb#ccc:ddd] [-ps=524880] [-o=xxx] [-cpd=xxx] [-fr] [-o=xxx]
[-config=xxx]
```

- Uploading a folder

```
obsutil cp folder_url obs://bucket[/key] -r [-arcDir=xxx] [-dryRun] [-link]
[-f] [-flat] [-u] [-vlength] [-vmd5] [-j=1] [-p=1] [-threshold=52428800]
[-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-include=*.xxx]
[-exclude=*.xxx] [-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

- Uploading multiple files/folders

```
obsutil cp file1 url, folder1 url|filelist url obs://bucket[/prefix] -msm=1
[-r] [-dryRun] [-link] [-f] [-u] [-vlength] [-vmd5] [-flat] [-j=1] [-p=1]
[-threshold=52428800] [-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd]
[-ps=5242880] [-include=*.xxx] [-exclude=*.xxx] [-arcDir=xxx]
[-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

• In Linux or macOS

- Uploading a file

```
./obsutil cp file_url obs://bucket[/key] [-arcDir=xxx] [-dryRun] [-link] [-u]
[-vlength] [-vmd5] [-p=1] [-threshold=5248800] [-acl=xxx] [-sc=xxx]
[-meta=aaa:bbb#ccc:ddd] [-ps=524880] [-o=xxx] [-cpd=xxx] [-fr] [-o=xxx]
[-config=xxx]
```

- Uploading a folder

```
./obsutil cp folder_url obs://bucket[/key] -r [-arcDir=xxx] [-dryRun] [-link]
[-f] [-flat] [-u] [-vlength] [-vmd5] [-j=1] [-p=1] [-threshold=52428800]
[-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-include=*.xxx]
[-exclude=*.xxx] [-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

- Uploading multiple files/folders

```
./obsutil cp file1 url, folder1 url|filelist url obs://bucket[/prefix] -msm=1
[-r] [-dryRun] [-link] [-f] [-u] [-vlength] [-vmd5] [-flat] [-j=1] [-p=1]
[-threshold=52428800] [-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd]
[-ps=5242880] [-include=*.xxx] [-exclude=*.xxx] [-arcDir=xxx]
[-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
file_url	Optional for uploading multiple files/folders Mandatory for uploading a file	Local file path NOTE <ul style="list-style-type: none">If this parameter is configured when uploading multiple files/folders, msm must be set to 1. In this case, use commas (,) to separate multiple file paths, for example, file_url1,file_url2.Files and folders can both be included when uploading multiple files/folders. For example, file_url1,folder_url1,file_url2,folder_url2.
folder_url	Optional for uploading multiple files/folders Mandatory for	Local folder path NOTE <ul style="list-style-type: none">If flat is not configured when uploading a folder, the entire folder is uploaded. If flat is configured, all files

Parameter	Optional or Mandatory	Description
	uploading a folder	<p>in the folder are uploaded.</p> <ul style="list-style-type: none">• If this parameter is configured when uploading multiple files/folders, msm must be set to 1. In this case, use commas (,) to separate multiple folder paths, for example, folder_url1, folder_url2.• Files and folders can be included when uploading multiple files/folders. For example, file_url1, folder_url1, file_url2, folder_url2.
filelist_url	Optional for uploading multiple files/folders	<p>Indicates the path of the file that contains the list of files/folders to be uploaded. If this parameter is configured, msm must be set to 2.</p> <p>NOTE</p> <p>The list file is in common text file formats, such as TXT and CSV. Each line in the file indicates a file or folder to be uploaded. For example:</p> <pre>file_url1 file_url2 folder_url1 folder_url2</pre>
bucket	Mandatory	Bucket name
key	Optional	<p>Indicates the object name or object name prefix specified when uploading a file, or the object name prefix specified when uploading a folder.</p> <p>The rules are as follows:</p> <ul style="list-style-type: none">• If this parameter is left blank when uploading a file, the file is uploaded to the root directory of the bucket and the object name is the file name. If the value ends with a slash (/), the value is used as the object name prefix when the file is uploaded, and the object name is the value plus the file name. If the value does not end with a slash (/), the file is uploaded with the value as the object name.• If this parameter is left blank when uploading a folder, the folder is uploaded to the root directory of the bucket. If the value ends with a slash (/), the value is used as the object name prefix of the folder to be uploaded. If the value does not end with a slash (/), the folder to be uploaded is prefixed with the value plus a slash (/). <p>NOTE</p> <p>For details about how to use this parameter, see 6.1 Upload Examples.</p>
fr	Optional for uploading a file (additional	Generates an operation result list when uploading a file.

Parameter	Optional or Mandatory	Description
	parameter)	
flat	Optional for uploading a folder or multiple files/folders (additional parameter)	Uploads all files in a folder but not the folder itself.
arcDir	Optional (additional parameter)	Path to which the uploaded files are archived
dryRun	Optional (additional parameter)	Conducts a dry run.
link	Optional (additional parameter)	Uploads the actual path of the symbolic-link file/folder NOTICE If this parameter is not set, and the file to be uploaded is a symbolic link, and the target file of the link does not exist, then files of 0 bytes can be normally uploaded in Windows but will fail in Linux or macOS.
u	Optional (additional parameter)	Indicates incremental upload. If this parameter is set, each file can be uploaded only when it does not exist in the bucket, its size is different from the namesake one in the bucket, or it has the latest modification time.
vlength	Optional (additional parameter)	After the upload is complete, check whether the sizes of the objects in the bucket are the same as those of the local files.
vmd5	Optional (additional parameter)	After the upload completes, check whether the MD5 values of the objects in the bucket are the same as those of the local files. NOTE <ul style="list-style-type: none">If the size of the file or folder to be uploaded is too large, using this parameter will degrade the overall performance due to MD5 calculation.After the MD5 value verification is successful, the parameter value is set to the object metadata x-obs-md5chksum, which is used for later MD5 verification during download or copy.
p	Optional (additional parameter)	Indicates the maximum number of concurrent multipart upload tasks when uploading a file. The default value is the value of defaultParallels in the configuration file.
threshold	Optional (additional parameter)	Indicates the threshold for enabling multipart upload, in bytes. The default value is the value of defaultBigfileThreshold in the configuration file. NOTE <ul style="list-style-type: none">If the size of the file or folder to be uploaded is smaller than the threshold, upload it directly. Otherwise, a

Parameter	Optional or Mandatory	Description
		<p>multipart upload is required.</p> <ul style="list-style-type: none">• If you upload a file or folder directly, no part record is generated, and resumable transmission is not supported.• This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.
acl	Optional (additional parameter)	<p>Access control policies that can be specified when uploading files. Possible values are:</p> <ul style="list-style-type: none">• private• public-read• public-read-write <p>NOTE</p> <p>The preceding three values indicate private read and write, public read, and public read and write.</p>
sc	Optional (additional parameter)	<p>Indicates the storage classes of objects that can be specified when uploading files. Possible values are:</p> <ul style="list-style-type: none">• standard: OBS Standard, which features low access latency and high throughput, and is applicable to storing frequently accessed data (multiple accesses per month averagely) or data that is smaller than 1 MB• warm: It is applicable to storing semi-frequently accessed (less than 12 times a year averagely) data that requires quick response.• cold: It is secure, durable, and inexpensive, and applicable to archiving rarely-accessed (once a year averagely) data.
meta	Optional (additional parameter)	<p>Indicates the customized metadata that can be specified when uploading files. The format is key1:value1#key2:value2#key3:value3.</p> <p>NOTE</p> <p>The preceding value indicates that the objects in the bucket contain three groups of customized metadata after the file is uploaded: key1:value1, key2:value2, and key3:value3.</p>
ps	Optional (additional parameter)	<p>Indicates the size of each part in a multipart upload task, in bytes. The value ranges from 100 KB to 5 GB. The default value is the value of defaultPartSize in the configuration file.</p> <p>NOTE</p> <p>This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.</p>
cpd	Optional (additional parameter)	<p>Indicates the folder where the part records reside. The default value is .obsutil_checkpoint, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p>

Parameter	Optional or Mandatory	Description
		A part record is generated during a multipart upload and saved to the upload subfolder. After the upload succeeds, its part record is deleted automatically. If the upload fails or is suspended, the system attempts to resume the task according to its part record when you perform the upload the next time.
r	Mandatory for uploading a folder (additional parameter) Optional for uploading multiple files/folders	Indicates files and subfolders within the folder when uploading a folder recursively. NOTE If this parameter is not set when you upload a folder, an empty folder is uploaded to an OBS bucket.
f	Optional for uploading a folder or multiple files/folders (additional parameter)	Runs in force mode.
j	Optional for uploading a folder or multiple files/folders (additional parameter)	Indicates the maximum number of concurrent tasks for uploading a folder. The default value is the value of defaultJobs in the configuration file. NOTE The value is ensured to be greater than or equal to 1.
msm	Mandatory for uploading multiple files/folders (additional parameter)	Enables the mode for uploading multiple files/folders. Possible values are 1 and 2 . NOTE <ul style="list-style-type: none">If msm is set to 1, the source URL indicates a list of file/folder names separated by commas.If msm is set to 2, the source URL indicates a file containing a list of file/folder names.If the file or folder name already contains commas (,), do not set msm to 1.If parameter r is not set, the folders in the list will not be uploaded.
exclude	Optional for uploading a folder or multiple files/folders (additional parameter)	Indicates the file matching patterns that are excluded, for example: *.txt . NOTE <ul style="list-style-type: none">The asterisk (*) represents any group of characters, and the question mark (?) represents any single character. For instance, abc*.txt indicates any file whose name starts with abc and ends with .txt.You can use * to represent * and \? to represent ?.If the name of the file to be uploaded matches the value of this parameter, the file is skipped. NOTICE <ul style="list-style-type: none">You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected

Parameter	Optional or Mandatory	Description
		<p>results. Use single quotation marks for Linux or macOS and quotation marks for Windows.</p> <ul style="list-style-type: none"> The matching pattern applies to the absolute file path (including the file name and file directory). The matching pattern takes effect only for files in the folder.
include	Optional for uploading a folder or multiple files/folders (additional parameter)	<p>Indicates the file matching patterns that are included, for example: *.jpg.</p> <p>NOTE</p> <ul style="list-style-type: none"> The asterisk (*) represents any group of characters, and the question mark (?) represents any single character. You can use * to represent * and \? to represent ?. Only after identifying that the name of the file to be uploaded does not match the value of exclude, the system checks whether the file name matches the value of this parameter. If yes, the file is uploaded. If not, the file is skipped. <p>NOTICE</p> <ul style="list-style-type: none"> You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows. The matching pattern applies to the absolute file path (including the file name and file directory). The matching pattern applies only to files in the folder.
timeRange	Optional for uploading a folder or multiple files/folders (additional parameter)	<p>Indicates the time range matching pattern when uploading files. Only files whose last modification time is within the configured time range are uploaded.</p> <p>This pattern has a lower priority than the file matching patterns (exclude/include). That is, the time range matching pattern is executed after the configured file matching patterns.</p> <p>NOTE</p> <ul style="list-style-type: none"> The matching time range is represented in <i>time1-time2</i>, where <i>time1</i> must be earlier than or the same as <i>time2</i>. The time format is <i>yyyyMMddHHmmss</i>. Automatic formatting is supported. For example, <i>yyyyMMdd</i> is equivalent to <i>yyyyMMdd000000</i>, and <i>yyyyMM</i> is equivalent to <i>yyyyMM01000000</i>. If this parameter is set to <i>*-time2</i>, all files whose last modification time is earlier than <i>time2</i> are matched. If it is set to <i>time1-*</i>, all files whose last modification time is later than <i>time1</i> are matched. <p>NOTICE</p> <p>Time in the matching pattern is the UTC time.</p>
o	Optional (additional parameter)	Indicates the folder where operation result lists reside. After the command is executed, result lists

Parameter	Optional or Mandatory	Description
		<p>(possibly including success, failure, and warning files) are generated in the folder. The default value is .obsutil_output, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <ul style="list-style-type: none">The naming rule for result lists is as follows: cp_{succeed failed warning}_report_time_TaskId.txtBy default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Response

Field	Description
Parallel	Parameter -p in the request
Jobs	Parameter -j in the request
Threshold	Parameter -threshold in the request
PartSize	Parameter -ps in the request
Exclude	Parameter -exclude in the request
Include	Parameter -include in the request
TimeRange	Parameter -timeRange in the request
VerifyLength	Parameter -vlength in the request
VerifyMd5	Parameter -vmd5 in the request
CheckpointDir	Parameter -cpd in the request
OutputDir	Parameter -o in the request
ArcDir	Parameter -arcDir in the request
Succeed count	Number of successful tasks
Failed count	Number of failed tasks
Skip count	Number of tasks that are skipped during incremental upload, download, or copy, and synchronous upload, download, or copy. NOTE

Field	Description
	Skipped tasks are recorded into successful tasks.
Warning count	Number of tasks that are executed successfully but contain warnings. NOTE <ul style="list-style-type: none">The task for which a warning is generated may be a failure or a success, which needs to be further determined according to the corresponding result list.The number of tasks that generate warnings is independent of the number of successful or failed tasks. The total number of tasks is the number of successful tasks plus the number of failed tasks.
Succeed bytes	Number of bytes that are successfully uploaded or downloaded.
max cost	Maximum duration of all tasks, in ms
min cost	Minimum duration of all tasks, in ms
average cost	Average duration of all tasks, in ms
average tps	The average number of tasks completed per second
Task id	Unique ID of an operation, which is used to search for the result list generated in a batch task

Running Examples

- Take the Windows OS as an example. Run the **obsutil cp d:\temp\test.txt obs://bucket-test/key** command to upload the **test.txt** file in the **temp** directory in the **D:** drive to bucket **bucket-test** and rename the file as **key**.

```
obsutil cp d:\temp\test.txt obs://bucket-test/key
```

```
Parallel:      3                Jobs:      3
Threshold:    524288000        PartSize:   5242880
Exclude:      Include:
VerifyLength: false          VerifyMd5:   false
CheckpointDir: d:\temp\.obsutil_checkpoint

[=====] 100.00% 1.68 MB/s 5s
Upload successfully, 8.46MB, d:\temp\test.txt --> obs://bucket-test/key
```

- Take the Windows OS as an example. Run the **obsutil cp d:\temp obs://bucket-test/temp -f -r** command to recursively upload all files and subfolders in the **temp** directory in the **D:** drive to the **temp** folder in bucket **bucket-test**.

```
obsutil cp d:\temp obs://bucket-test/temp -f -r
```

```
Parallel:      3                Jobs:      3
Threshold:    524288000        PartSize:   5242880
Exclude:      Include:
VerifyLength: false          VerifyMd5:   false
CheckpointDir: d:\temp\.obsutil_checkpoint
OutputDir:    d:\temp\.obsutil_output

[=====] 100.00% 2.02 KB/s 0s
Succeed count is: 5          Failed count is: 0
```

```
Metrics [max cost:90 ms, min cost:45 ms, average cost:63.80 ms, average tps:35.71]  
Task id is: 104786c8-27c2-48fc-bc6a-5886596fb0ed
```

- For more examples, see 6.1 Upload Examples.

4.3 Querying Object Properties

Function

You can use this command to query the basic properties of an object.

Command Line Structure

- In Windows

```
obsutil stat obs://bucket/key [-acl] [-config=xxx]
```

- In Linux or macOS

```
./obsutil stat obs://bucket/key [-acl] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
key	Mandatory	Object name
acl	Optional	Queries the access control policies of the object at the same time.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Response

Field	Description
Key	Object name
LastModified	Last modification time of the object
Size	Object size, in bytes
StorageClass	Storage class of the object
MD5	Real MD5 of the object NOTE You can query this value only after running the cp command and configuring the -vmd5 parameter.
ETag	ETag value of an object calculated on the server

Field	Description
ContentType	Content-Type of the object
Metadata	Customized metadata of the object
Acl	Access control policy of the object

Running Example

- Take the Windows OS as an example. Run the **obsutil stat obs://bucket-test/key** command to query the basic properties of an object.

```
obsutil stat obs://bucket-test/key

Key:
  obs://bucket-test/key
LastModified:
  2018-11-16T02:15:49Z
Size:
  7
ETag:
  43d93b553855b0e1fc67e31c28c07b65
ContentType:
  text/plain
```

4.4 Setting Object Properties

Function

You can use this command to set properties of an object or set properties of objects in batches by a specified object name prefix.



NOTE

You can set storage classes only for buckets whose version is 3.0.

Command Line Structure

- In Windows

- Setting properties of a single object

```
obsutil chattri obs://bucket/key [-sc=xxx] [-acl=xxx] [-aclXml=xxx]
[-versionId=xxx] [-fr] [-o=xxx] [-config=xxx]
```

- Setting properties of objects in batches

```
obsutil chattri obs://bucket[/key] -r [-f] [-v] [-sc=xxx] [-acl=xxx]
[-aclXml=xxx] [-o=xxx] [-j=1] [-config=xxx]
```

- In Linux or macOS

- Setting properties of a single object

```
./obsutil chattri obs://bucket/key [-sc=xxx] [-acl=xxx] [-aclXml=xxx]
[-versionId=xxx] [-fr] [-o=xxx] [-config=xxx]
```

- Setting properties of objects in batches

```
./obsutil chattri obs://bucket[/key] -r [-f] [-v] [-sc=xxx] [-acl=xxx]  
[-aclXml=xxx] [-o=xxx] [-j=1] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
key	Mandatory for setting properties of an object. Optional for setting properties of objects in batches.	Indicates the name of the object whose properties are to be set, or the name prefix of objects whose properties are to be set in batches. NOTE If this parameter is left blank during batch operation, properties of all objects in the bucket are set.
sc	Optional (additional parameter)	Storage classes of objects. Possible values are: <ul style="list-style-type: none">• standard: OBS Standard, which features low access latency and high throughput, and is applicable to storing frequently accessed data (multiple accesses per month averagely) or data that is smaller than 1 MB• warm: It is applicable to storing semi-frequently accessed (less than 12 times a year averagely) data that requires quick response.• cold: It is secure, durable, and inexpensive, and applicable to archiving rarely-accessed (once a year averagely) data. NOTE For an object whose storage class is cold , restore the object first and then set its storage class. To restore an object, see 4.14 Restoring Objects.
acl	Optional (additional parameter)	Access control policies that can be specified for objects. Possible values are: <ul style="list-style-type: none">• private• public-read• public-read-write NOTE The preceding three values indicate private read and write, public read, and public read and write.
aclXml	Optional (additional parameter)	Access control policy of the bucket, in XML format. <pre><AccessControlPolicy> <Owner> <ID>ownerid</ID> </Owner> <AccessControlList> <Grant> <Grantee> <ID>userid</ID> </Grantee></pre>

Parameter	Optional or Mandatory	Description
		<pre><Permission>[WRITE WRITE ACP READ READ ACP FULL CONTROL]</Permission> </Grant> <Grant> <Grantee> <Canned>Everyone</Canned> </Grantee> </Grant> <Permission>[WRITE WRITE ACP READ READ ACP FULL CONTROL]</Permission> </Grant> </AccessControlList> </AccessControlPolicy></pre> <p>NOTE</p> <ul style="list-style-type: none">• Owner: Optional. Specify the object owner's ID.• In AccessControlList, the Grant field contains the authorized users. Grantee specifies the IDs of authorized users. Canned specifies the authorized user group (currently, only Everyone is supported).• The following permissions can be granted: WRITE (write), WRITE_ACP (write ACL), READ (read), READ_ACP (read ACL), and FULL_CONTROL (full control). <p>NOTICE</p> <p>Because angle brackets (<) and (>) are unavoidably included in the parameter value, you must use quotation marks to enclose them for escaping when running the command. Use single quotation marks for Linux or macOS and quotation marks for Windows.</p>
versionId	Optional for setting properties of an object (additional parameter)	Version ID of the object whose properties are to be set
fr	Optional for setting properties of an object (additional parameter)	Generates an operation result list when setting properties of an object.
f	Optional when setting properties of objects in batches (additional parameter)	Runs in force mode.
r	Mandatory when setting properties of objects in batches (additional parameter)	Sets properties of objects in batches based on a specified object name prefix.
v	Optional when	Sets properties of versions of objects in batches based

Parameter	Optional or Mandatory	Description
	setting properties of objects in batches (additional parameter)	on a specified object name prefix.
o	Optional (additional parameter)	<p>Indicates the folder where operation result lists reside. After the command is executed, result lists (including success and failure files) are generated in the folder. The default value is .obsutil_output, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <ul style="list-style-type: none">The naming rule for result lists is as follows: chattri_{succeed failed}_report_time_TaskId.txt <p>By default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.</p>
j	Optional when setting properties of objects in batches (additional parameter)	<p>Indicates the maximum number of concurrent tasks for setting object properties in batches. The default value is the value of defaultJobs in the configuration file.</p> <p>NOTE</p> <p>The value is ensured to be greater than or equal to 1.</p>
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

**NOTE**

Only one of **sc**, **acl**, and **aclXml** can be set for each command.

Response

Refer to [Response](#) for uploading an object.

Running Examples

- Take the Windows OS as an example, run the **obsutil chattri obs://bucket-test/key -acl=public-read** command to set the access permission to an object to public read.

```
obsutil chattri obs://bucket-test/key -acl=public-read
```

Set the acl of object [key] in the bucket [bucket-test] to [public-read] successfully, request id [04050000016836DDFA73B2B5320E2651]

- Take the Windows OS as an example, run the **obsutil chattri obs://bucket-test -r -f -acl=public-read** command to set the access permission to all objects in the bucket to public read.

```
obsutil chattri obs://bucket-test -r -f -acl=public-read

[-----] 100.00% tps:155.15 5/5 233ms
Succeed count is: 5          Failed count is: 0
Metrics [max cost:177 ms, min cost:53 ms, average cost:102.40 ms, average tps:20.41]
Task id is: 9d7f73ff-f747-4fdd-9b2a-815ba2dc3b07
```

4.5 Listing Objects

Function

You can use this command to query objects or object versions in a bucket. All objects are listed in lexicographical order by object name and version ID.

Command Line Structure

- In Windows

```
obsutil ls obs://bucket[/prefix] [-s] [-d] [-v] [-marker=xxx] [-versionIdMarker=xxx]
[-limit=1] [-config=xxx]
```

- In Linux or macOS

```
./obsutil ls obs://bucket[/prefix] [-s] [-d] [-v] [-marker=xxx]
[-versionIdMarker=xxx] [-limit=1] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
prefix	Optional	Prefix of an object name for listing objects NOTE If this parameter is left blank, all objects in the bucket are listed.
s	Optional (additional parameter)	Displays simplified query result. NOTE In the simplified format, the returned result contains only the object name.
d	Optional (additional parameter)	Lists only objects and subdirectories in the current directory, instead of recursively listing all objects and subdirectories.
v	Optional (additional parameter)	Lists versions of an object in a bucket. The result contains the latest version and historical versions (if any) of the object.
marker	Optional (additional parameter)	Object name to start with when listing objects in a bucket. All objects are listed in lexicographical order by object name. NOTE

Parameter	Optional or Mandatory	Description
		For details about how to use this parameter, see 6.7 List Examples.
versionIdMarker	Optional (additional parameter). It must be used together with the v and marker parameters.	Version ID to start with when listing versions of objects in a bucket. All versions and objects are listed in lexicographical order by object name and version ID. NOTE If the value of versionIdMarker is not a version ID specified by marker , versionIdMarker is invalid.
limit	Optional (additional parameter)	Maximum number of objects that can be listed. If the value is less than or equal to 0, all objects are listed. If it is left blank, 1000 objects are listed by default. NOTE If there are a large number of objects in a bucket, you are advised to set this parameter to limit the number of objects to be listed each time. If not all objects are listed, marker and versionIdMarker of the next request will be returned in the result, which you can use to list the remaining objects.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Running Example

- Take the Windows OS as an example. Run the **obsutil ls obs://bucket-test -limit=10** command to list objects in the bucket.

```
obsutil ls obs://bucket-test -limit=10
```

```
Folder list:
```

```
obs://bucket-test/api/
```

```
Object list:
```

key	LastModified	Size
StorageClass	ETag	
obs://bucket-test/AUTHORS	2018-11-16T02:15:49Z	33243
standard	"796393c1eaf502ef56a85c2ceb640aea"	
obs://bucket-test/CONTRIBUTING.md	2018-11-16T02:15:49Z	1366
standard	"12d93325ba6131f852daecd18dd65edc"	
obs://bucket-test/CONTRIBUTORS	2018-11-16T02:15:49Z	45710
standard	"b486b5003e6215c9199e86ab3ccec9fa"	
obs://bucket-test/LICENSE	2018-11-16T02:15:49Z	1479
standard	"5d4950ecb7b26d2c5e4e7b4e0dd74707"	


```
obs://bucket-test/PATENTS                2018-11-16T02:15:49Z      1303
standard      "3a55d95595a6f9e37dee53826b4daff2"

obs://bucket-test/README.md              2018-11-16T02:15:49Z      1399
standard      "97351fd7946b9ea021a31a86ba2a10ab"

obs://bucket-test/VERSION                2018-11-16T02:15:49Z        7
standard      "43d93b553855b0e1fc67e31c28c07b65"

obs://bucket-test/api/README              2018-11-16T02:15:49Z      521
standard      "4e9e63a87075df60cdf65c8ce9e92117"

obs://bucket-test/api/except.txt          2018-11-16T02:15:49Z     20194
standard      "8eb96de3f60447e2f09a7531c99fb3ee"

Next marker is: api/except.txt
Folder number is: 1
Object number is: 9
```

- For more examples, see 6.7 List Examples.

4.6 Copying an Object

Function

You can use this command to copy a single object or copy objects in batches by a specified object name prefix.

NOTICE

- Do not change the source objects in the OBS bucket when copying a single object or objects in batches. Otherwise, the operation may fail or data may be inconsistent.
- If the storage class of the object to be copied is **cold**, you must restore the object to be copied first. Otherwise, the copy fails.
- To copy objects, you must have the read permission on the objects to be copied and the write permission on the destination bucket.
- If the client-side cross-region replication function is not enabled, ensure that the source bucket and destination bucket are in the same region.

Command Line Structure

- In Windows
 - Copying a single object

```
obsutil cp obs://srcbucket/key obs://dstbucket/[dest] [-dryRun] [-u] [-crr]
[-vlength] [-vmd5] [-p=1] [-threshold=52428800] [-versionId=xxx] [-acl=xxx]
[-sc=xxx] [-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-cpd=xxx] [-fr] [-o=xxx]
[-config=xxx]
```

- Copying objects in batches

```
obsutil cp obs://srcbucket[/key] obs://dstbucket[/dest] -r [-dryRun] [-f]
[-flat] [-u] [-crr] [-vlength] [-vmd5] [-j=1] [-p=1] [-threshold=52428800]
[-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-include=*.xxx]
[-exclude=*.xxx] [-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

- In Linux or macOS

- Copying a single object

```
./obsutil cp obs://srcbucket/key obs://dstbucket/[dest] [-dryRun] [-u] [-crr]
[-vlength] [-vmd5] [-p=1] [-threshold=52428800] [-versionId=xxx] [-acl=xxx]
[-sc=xxx] [-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-cpd=xxx] [-fr] [-o=xxx]
[-config=xxx]
```

- Copying objects in batches

```
./obsutil cp obs://srcbucket[/key] obs://dstbucket[/dest] -r [-dryRun] [-f]
[-flat] [-u] [-crr] [-vlength] [-vmd5] [-j=1] [-p=1] [-threshold=52428800]
[-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-include=*.xxx]
[-exclude=*.xxx] [-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

**NOTE**

- The source path and destination path cannot be the same.
- No overlapping between the source and destination paths is allowed when copying objects in batches.

Parameter Description

Parameter	Optional or Mandatory	Description
srcbucket	Mandatory	Source bucket name
dstbucket	Mandatory	Destination bucket name
dest	Optional	Indicates the destination object name when copying an object, or the name prefix of destination objects when copying objects in batches.
key	Mandatory for copying an object. Optional for copying objects in batches.	Indicates the source object name when copying an object, or the name prefix of source objects when copying objects in batches. The rules are as follows: <ul style="list-style-type: none">• This parameter cannot be left blank when copying an object. If dest is left blank, the source object is copied to the root directory of the destination bucket. If the value of dest ends with a slash (/), the destination object name is the value of dest plus the source object name. Otherwise, the destination object name is the value of dest.• If this parameter is left blank when copying objects in batches, all objects in the source bucket are copied. If not, objects whose name prefix is the set value in the source bucket are copied. The rules for confirming the name of the destination object are as follows:<ul style="list-style-type: none">– If the value of dest ends with a slash (/), the destination object name is the value of dest plus the source object name.

Parameter	Optional or Mandatory	Description
		<ul style="list-style-type: none">If the value of dest does not end with a slash (/), the destination object name is <i>the value of dest/source object name</i>. <p>NOTE</p> <ul style="list-style-type: none">If this parameter is configured but the flat parameter is not when copying objects in batches, the name of the source object contains the name prefix of the parent object. If flat is configured, then the name of the source object does not contain the name prefix of the parent object.For details about how to use this parameter, see 6.5 Copy Examples.
fr	Optional for copying an object (additional parameter)	Generates an operation result list when copying an object.
flat	Optional for copying objects in batches (additional parameter)	The name prefix of the parent object is excluded when copying objects in batches.
dryRun	Optional (additional parameter)	Conducts a dry run.
crr	Optional (additional parameter)	<p>Enables the client-side cross-region replication function. In this mode, data is directly copied to the destination bucket from the source bucket through data stream. The buckets can be any two OBS buckets.</p> <p>NOTE</p> <ul style="list-style-type: none">If this parameter is configured, ensure that the configuration of client-side cross-region replication is updated in the configuration file. For details, see 5.1 Updating a Configuration File.The configurations of the source bucket and destination bucket are respectively akCrr/skCrr/tokenCrr/endpointCrr and ak/sk/token/endpoint in the configuration file. <p>NOTICE</p> <p>After this function is enabled, both upload and download bandwidth are occupied.</p>
vlength	Optional (additional parameter)	<p>Verifies whether the object size in the destination bucket is the same as that in the source bucket after the copy task completes.</p> <p>NOTE</p> <p>This parameter must be used together with crr.</p>
vmd5	Optional (additional)	Verifies whether the MD5 value of the destination bucket is the same as that of the source bucket after the copy

Parameter	Optional or Mandatory	Description
	parameter)	task completes. NOTE <ul style="list-style-type: none">This parameter must be used together with crr.Objects in the source bucket must contain metadata x-obs-md5chksum. Otherwise, MD5 verification will be skipped. After the MD5 value verification is successful, the parameter value is set to the destination object metadata x-obs-md5chksum , which is used for later MD5 verification during download or copy.
u	Optional (additional parameter)	Indicates incremental copy. If this parameter is set, each object can be copied only when it does not exist in the destination bucket, its size is different from the namesake one in the destination bucket, or it has the latest modification time.
p	Optional (additional parameter)	Indicates the maximum number of concurrent multipart copy tasks when copying an object. The default value is the value of defaultParallels in the configuration file.
threshold	Optional (additional parameter)	Indicates the threshold for enabling multipart copy, in bytes. The default value is the value of defaultBigfileThreshold in the configuration file. NOTE <ul style="list-style-type: none">If the size of the object to be copied is smaller than the threshold, copy the object directly. If not, a multipart copy is required.If you copy an object directly, no part record is generated, and resumable transmission is not supported.This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.
versionId	Optional for copying an object (additional parameter)	Source object version ID that can be specified when copying an object
acl	Optional (additional parameter)	Access control policies for destination objects that can be specified when copying objects. Possible values are: <ul style="list-style-type: none">privatepublic-readpublic-read-write NOTE The preceding three values indicate private read and write, public read, and public read and write.
sc	Optional (additional parameter)	Storage classes of the destination objects that can be specified when copying objects. Possible values are: <ul style="list-style-type: none">standard: OBS Standard, which features low access latency and high throughput, and is applicable to

Parameter	Optional or Mandatory	Description
		<p>storing frequently accessed data (multiple accesses per month averagely) or data that is smaller than 1 MB</p> <ul style="list-style-type: none">• warm: It is applicable to storing semi-frequently accessed (less than 12 times a year averagely) data that requires quick response.• cold: It is secure, durable, and inexpensive, and applicable to archiving rarely-accessed (once a year averagely) data.
meta	Optional (additional parameter)	<p>Metadata of destination objects that can be specified when copying objects. The format is <i>key1:value1#key2:value2#key3:value3</i>.</p> <p>NOTE</p> <p>The preceding value indicates that the destination objects in the bucket contain three groups of customized metadata after objects are copied: key1:value1, key2:value2, and key3:value3.</p>
ps	Optional (additional parameter)	<p>Indicates the size of each part in a multipart copy task, in bytes. The value ranges from 100 KB to 5 GB. The default value is the value of defaultPartSize in the configuration file.</p> <p>NOTE</p> <p>This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.</p>
cpd	Optional (additional parameter)	<p>Indicates the folder where the part records reside. The default value is .obsutil_checkpoint, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <p>A part record is generated during a multipart copy and saved to the copy subfolder. After the copy succeeds, its part record is deleted automatically. If the copy fails or is suspended, the system attempts to resume the task according to its part record when you perform the copy the next time.</p>
r	Mandatory for copying objects in batches (additional parameter)	<p>Copies objects in batches based on a specified name prefix of objects in the source bucket.</p>
f	Optional for copying objects in batches (additional parameter)	<p>Runs in force mode.</p>
j	Optional for copying	<p>Indicates the maximum number of concurrent tasks for copying objects in batches. The default value is the value</p>

Parameter	Optional or Mandatory	Description
	objects in batches (additional parameter)	of defaultJobs in the configuration file. NOTE The value is ensured to be greater than or equal to 1.
exclude	Optional for copying objects in batches (additional parameter)	Indicates the matching patterns of source objects that are excluded, for example: *.txt . NOTE <ul style="list-style-type: none">The asterisk (*) represents any group of characters, and the question mark (?) represents any single character. For instance, abc*.txt indicates any file whose name starts with abc and ends with .txt.You can use * to represent * and \? to represent ?.If the name of the object to be copied matches the value of this parameter, the object is skipped. NOTICE <ul style="list-style-type: none">You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt.This matching pattern applies only to objects whose names do not end with a slash (/).
include	Optional for copying objects in batches (additional parameter)	Indicates the matching patterns of source objects that are included, for example: *.jpg . NOTE <ul style="list-style-type: none">The asterisk (*) represents any group of characters, and the question mark (?) represents any single character.You can use * to represent * and \? to represent ?.Only after identifying that the name of the file to be copied does not match the value of exclude, the system checks whether the file name matches the value of this parameter. If yes, the file is copied. If not, the file is skipped. NOTICE <ul style="list-style-type: none">You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt.This matching pattern applies only to objects whose names do not end with a slash (/).
timeRange	Optional for	Indicates the time range matching pattern when copying

Parameter	Optional or Mandatory	Description
	copying objects in batches (additional parameter)	<p>objects. Only objects whose last modification time is within the configured time range are copied.</p> <p>This pattern has a lower priority than the object matching patterns (exclude/include). That is, the time range matching pattern is executed after the configured object matching patterns.</p> <p>NOTE</p> <ul style="list-style-type: none">• The matching time range is represented in <i>time1-time2</i>, where <i>time1</i> must be earlier than or the same as <i>time2</i>. The time format is <i>yyyyMMddHHmmss</i>.• Automatic formatting is supported. For example, <i>yyyyMMdd</i> is equivalent to <i>yyyyMMdd000000</i>, and <i>yyyyMM</i> is equivalent to <i>yyyyMM01000000</i>.• If this parameter is set to <i>*-time2</i>, all files whose last modification time is earlier than <i>time2</i> are matched. If it is set to <i>time1-*</i>, all files whose last modification time is later than <i>time1</i> are matched. <p>NOTICE</p> <ul style="list-style-type: none">• The time in the matching mode is the UTC time.• This matching pattern applies only to objects whose names do not end with a slash (/).
o	Optional (additional parameter)	<p>Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success, failure, and warning files) are generated in the folder. The default value is .obsutil_output, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <ul style="list-style-type: none">• The naming rule for result lists is as follows: cp_{succeed failed warning}_report_time_TaskId.txt• By default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.
config	Optional (additional parameter)	<p>User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.</p>

Response

Refer to [Response](#) for uploading an object.

Running Examples

- Take the Windows OS as an example. Run the **obsutil cp obs://bucket-test/key obs://bucket-test2** command to copy a single object.

```
obsutil cp obs://bucket-test/key obs://bucket-test2

Parallel:      3                Jobs:      3
Threshold:    524288000        PartSize:   5242880
Exclude:      0                Include:    0
VerifyLength: false          VerifyMd5:   false
CheckpointDir: d:\temp\.obsutil_checkpoint

[=====] 100.00% 6/s 0s
Copy successfully, 19B, obs://bucket-test/key --> obs://bucket-test2/key
ext.txt
```

- Take the Windows OS as an example. Run the **obsutil cp obs://bucket-test/temp/ obs://bucket-test2 -f -r** command to copy objects in batches.

```
obsutil cp obs://bucket-test/temp/ obs://bucket-test2 -r -f

Parallel:      3                Jobs:      3
Threshold:    524288000        PartSize:   5242880
Exclude:      0                Include:    0
VerifyLength: false          VerifyMd5:   false
CheckpointDir: d:\temp\.obsutil_checkpoint
OutputDir:    d:\temp\.obsutil_output

[=====] 100.00% 10/s 0s
Succeed count is: 5           Failed count is: 0
Metrics [max cost:298 ms, min cost:192 ms, average cost:238.00 ms, average tps:9.71]
Task id is: 0476929d-9d23-4dc5-b2f8-0a0493f027c5
```

- For more examples, see 6.5 Copy Examples.

4.7 Moving an Object

Function

You can use this command to move a single object or move objects in batches by a specified object name prefix.

NOTICE

- Do not change the source objects in the OBS bucket when moving objects. Otherwise, the operation may fail or data may be inconsistent.
- The source objects are deleted after the move operation succeeds.

Command Line Structure

- In Windows
 - Moving a single object

```
obsutil mv obs://srcbucket/key obs://dstbucket/[dest] [-dryRun] [-u] [-p=1]
[-threshold=52428800] [-versionId=xxx] [-acl=xxx] [-sc=xxx]
[-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-cpd=xxx] [-fr] [-o=xxx] [-config=xxx]
```


- Moving objects in batches

```
obsutil mv obs://srcbucket[/key] obs://dstbucket[/dest] -r [-dryRun] [-f]
[-flat] [-u] [-j=1] [-p=1] [-threshold=52428800] [-acl=xxx] [-sc=xxx]
[-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-include=*.xxx] [-exclude=*.xxx]
[-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

- In Linux or macOS

- Moving a single object

```
./obsutil mv obs://srcbucket/key obs://dstbucket/[dest] [-dryRun] [-u] [-p=1]
[-threshold=52428800] [-versionId=xxx] [-acl=xxx] [-sc=xxx]
[-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-cpd=xxx] [-fr] [-o=xxx] [-config=xxx]
```

- Moving objects in batches

```
./obsutil mv obs://srcbucket[/key] obs://dstbucket[/dest] -r [-dryRun] [-f]
[-flat] [-u] [-j=1] [-p=1] [-threshold=52428800] [-acl=xxx] [-sc=xxx]
[-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-include=*.xxx] [-exclude=*.xxx]
[-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

**NOTE**

- The source path and destination path cannot be the same.
- No overlapping between the source and destination paths is allowed when moving objects in batches.

Parameter Description

Parameter	Optional or Mandatory	Description
srcbucket	Mandatory	Source bucket name
dstbucket	Mandatory	Destination bucket name
dest	Optional	Indicates the destination object name when moving a single object, or the name prefix of destination objects when moving objects in batches.
key	Mandatory for moving a single object Optional for moving objects in batches	<p>Indicates the source object name when moving a single object, or the name prefix of source objects when moving objects in batches.</p> <p>The rules are as follows:</p> <ul style="list-style-type: none">• This parameter cannot be left blank when moving a single object. If dest is left blank, the source object is moved to the root directory of the destination bucket. If the value of dest ends with a slash (/), the destination object name is the value of dest plus the source object name. Otherwise, the destination object name is the value of dest.• If this parameter is left blank when moving objects in batches, all objects in the source bucket are moved. If not, objects whose name prefix is the set value in the source bucket are moved. The rules for confirming the name of the destination object are as follows:<ul style="list-style-type: none">- If the value of dest ends with a slash (/), the destination object name is the value of dest plus the source object name.

Parameter	Optional or Mandatory	Description
		<ul style="list-style-type: none">– If the value of dest does not end with a slash (/), the destination object name is <i>the value of dest/source object name</i>. <p>NOTE</p> <ul style="list-style-type: none">• If this parameter is configured but parameter flat is not when moving objects in batches, the name of the source object contains the name prefix of the parent object. If flat is configured, then the name of the source object does not contain the name prefix of the parent object.• For details about how to use this parameter, see Command Line Structure.
fr	Optional for moving an object (additional parameter)	Generates an operation result list when moving an object.
flat	Optional for moving objects in batches (additional parameter)	The name prefix of the parent object is excluded when moving objects in batches.
dryRun	Optional (additional parameter)	Conducts a dry run.
u	Optional (additional parameter)	Indicates incremental move. If this parameter is set, each object can be moved only when it does not exist in the destination bucket, its size is different from the namesake one in the destination bucket, or it has the latest modification time. <p>NOTE</p> <p>If the size and modification time of the destination object are the same as those of the source object, the source object is directly deleted instead of being moved.</p>
p	Optional (additional parameter)	Indicates the maximum number of concurrent multipart move tasks when moving an object. The default value is the value of defaultParallels in the configuration file.
threshold	Optional (additional parameter)	Indicates the threshold for enabling multipart move, in bytes. The default value is the value of defaultBigfileThreshold in the configuration file. <p>NOTE</p> <ul style="list-style-type: none">• If the size of the object to be moved is smaller than the threshold, move the object directly. If not, a multipart move is required.• If you move an object directly, no part record is generated, and resumable transmission is not supported.• This value can contain a capacity unit. For example, 1 MB

Parameter	Optional or Mandatory	Description
		indicates 1048576 bytes.
versionId	Optional for moving an object (additional parameter)	Source object version ID that can be specified when moving a single object
acl	Optional (additional parameter)	<p>Access control policies for destination objects that can be specified when moving objects. Possible values are:</p> <ul style="list-style-type: none">• private• public-read• public-read-write <p>NOTE</p> <p>The preceding three values indicate private read and write, public read, and public read and write.</p>
sc	Optional (additional parameter)	<p>Storage classes of the destination objects that can be specified when moving objects. Possible values are:</p> <ul style="list-style-type: none">• standard: OBS Standard, which features low access latency and high throughput, and is applicable to storing frequently accessed data (multiple accesses per month averagely) or data that is smaller than 1 MB• warm: It is applicable to storing semi-frequently accessed (less than 12 times a year averagely) data that requires quick response.• cold: It is secure, durable, and inexpensive, and applicable to archiving rarely-accessed (once a year averagely) data.
meta	Optional (additional parameter)	<p>Metadata of destination objects that can be specified when copying objects. The format is <i>key1:value1#key2:value2#key3:value3</i>.</p> <p>NOTE</p> <p>The preceding value indicates that the destination objects in the bucket contain three groups of customized metadata after objects are copied: key1:value1, key2:value2, and key3:value3.</p>
ps	Optional (additional parameter)	<p>Indicates the size of each part in a multipart move task, in bytes. The value ranges from 100 KB to 5 GB. The default value is the value of defaultPartSize in the configuration file.</p> <p>NOTE</p> <p>This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.</p>
cpd	Optional (additional parameter)	Indicates the folder where the part records reside. The default value is .obsutil_checkpoint , the subfolder in the home directory of the user who executes obsutil commands.

Parameter	Optional or Mandatory	Description
		NOTE A part record is generated during a multipart move and saved to the copy subfolder. After the move succeeds, its part record is deleted automatically. If the move fails or is suspended, the system attempts to resume the task according to its part record when you perform the move the next time.
r	Mandatory for moving objects in batches (additional parameter)	Moves objects in batches based on a specified name prefix of objects in the source bucket.
f	Optional for moving objects in batches (additional parameter)	Runs in force mode.
j	Optional for moving objects in batches (additional parameter)	Indicates the maximum number of concurrent tasks for moving objects in batches. The default value is the value of defaultJobs in the configuration file. NOTE The value is ensured to be greater than or equal to 1.
exclude	Optional for moving objects in batches (additional parameter)	Indicates the matching patterns of source objects that are excluded, for example: *.txt . NOTE <ul style="list-style-type: none">The asterisk (*) represents any group of characters, and the question mark (?) represents any single character. For instance, abc*.txt indicates any file whose name starts with abc and ends with .txt.You can use * to represent * and \? to represent ?.If the name of the object to be moved matches the value of this parameter, the object is skipped. NOTICE <ul style="list-style-type: none">You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt.This matching pattern applies only to objects whose names do not end with a slash (/).
include	Optional for moving objects in	Indicates the matching patterns of source objects that are included, for example: *.jpg .

Parameter	Optional or Mandatory	Description
	batches (additional parameter)	<p>NOTE</p> <ul style="list-style-type: none">• The asterisk (*) represents any group of characters, and the question mark (?) represents any single character.• You can use * to represent * and \? to represent ?.• Only after identifying that the name of the file to be moved does not match the value of exclude, the system checks whether the file name matches the value of this parameter. If yes, the file is moved. If not, the file is skipped. <p>NOTICE</p> <ul style="list-style-type: none">• You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.• The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt.• This matching pattern applies only to objects whose names do not end with a slash (/).
timeRange	Optional for moving objects in batches (additional parameter)	<p>Indicates the time range matching pattern when moving objects. Only objects whose last modification time is within the configured time range are moved.</p> <p>This pattern has a lower priority than the object matching patterns (exclude/include). That is, the time range matching pattern is executed after the configured object matching patterns.</p> <p>NOTE</p> <ul style="list-style-type: none">• The matching time range is represented in <i>time1-time2</i>, where <i>time1</i> must be earlier than or the same as <i>time2</i>. The time format is <i>yyyyMMddHHmmss</i>.• Automatic formatting is supported. For example, <i>yyyyMMdd</i> is equivalent to <i>yyyyMMdd000000</i>, and <i>yyyyMM</i> is equivalent to <i>yyyyMM01000000</i>.• If this parameter is set to <i>*-time2</i>, all files whose last modification time is earlier than <i>time2</i> are matched. If it is set to <i>time1-*</i>, all files whose last modification time is later than <i>time1</i> are matched. <p>NOTICE</p> <ul style="list-style-type: none">• Time in the matching pattern is the UTC time.• This matching pattern applies only to objects whose names do not end with a slash (/).
o	Optional (additional parameter)	<p>Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success, failure, and warning files) are generated in the folder. The default value is .obsutil_output, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <ul style="list-style-type: none">• The naming rule for result lists is as follows: mv_{succeed

Parameter	Optional or Mandatory	Description
		 failed warning)_report_time_TaskId.txt <ul style="list-style-type: none">By default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Response

Refer to [Response](#) for uploading an object.

Running Examples

- Take the Windows OS as an example. Run the **obsutil mv obs://bucket-test/key obs://bucket-test2** command to move a single object.

```
obsutil mv obs://bucket-test/key obs://bucket-test2
```

```
Parallel:      3              Jobs:      3
Threshold:    524288000      PartSize:   5242880
Exclude:
VerifyLength: false        VerifyMd5:  false
CheckpointDir: d:\temp\.obsutil checkpoint
```

```
[=====] 100.00% 6/s 0s
Move successfully, 19B, obs://bucket-test/key --> obs://bucket-test2/key
ext.txt
```

- Take the Windows OS as an example. Run the **obsutil mv obs://bucket-test/temp/ obs://bucket-test2 -f -r** command to move objects in batches.

```
obsutil mv obs://bucket-test/temp/ obs://bucket-test2 -f -r
```

```
Parallel:      3              Jobs:      3
Threshold:    524288000      PartSize:   5242880
Exclude:
VerifyLength: false        VerifyMd5:  false
CheckpointDir: d:\temp\.obsutil checkpoint
OutputDir: d:\temp\.obsutil output
```

```
[=====] 100.00% 10/s 0s
Succeed count is:  5          Failed count is:  0
Metrics [max cost:298 ms, min cost:192 ms, average cost:238.00 ms, average tps:9.71]
Task id is: 0476929d-9d23-4dc5-b2f8-0a0493f027c5
```

4.8 Downloading an Object

Function

You can use this command to download an object or download objects in batches by object name prefix to your local PC.

NOTICE

- Do not change the source objects in the OBS bucket when downloading a single object or objects in batches. Otherwise, the download may fail or data may be inconsistent.
- If the storage class of the object to be copied is **cold**, you must restore the object to be downloaded first. Otherwise, the download fails.

Command Line Structure

- In Windows

- Downloading a single object

```
obsutil cp obs://bucket/key file or folder url [-tempFileDir=xxx] [-dryRun]
[-u] [-vlength] [-vmd5] [-p=1] [-threshold=52428800] [-versionId=xxx]
[-ps=5242880] [-cpd=xxx] [-fr] [-o=xxx] [-config=xxx]
```

- Downloading objects in batches

```
obsutil cp obs://bucket[/key] folder_url -r [-tempFileDir=xxx] [-dryRun] [-f]
[-flat] [-u] [-vlength] [-vmd5] [-j=1] [-p=1] [-threshold=52428800]
[-ps=5242880] [-include=*.xxx] [-exclude=*.xxx] [-timeRange=time1-time2]
[-o=xxx] [-cpd=xxx] [-config=xxx]
```

- In Linux or macOS

- Downloading a single object

```
./obsutil cp obs://bucket/key file or folder url [-tempFileDir=xxx] [-dryRun]
[-u] [-vlength] [-vmd5] [-p=1] [-threshold=52428800] [-versionId=xxx]
[-ps=5242880] [-cpd=xxx] [-fr] [-o=xxx] [-config=xxx]
```

- Downloading objects in batches

```
./obsutil cp obs://bucket[/key] folder url -r [-tempFileDir=xxx] [-dryRun] [-f]
[-flat] [-u] [-vlength] [-vmd5] [-j=1] [-p=1] [-threshold=52428800]
[-ps=5242880] [-include=*.xxx] [-exclude=*.xxx] [-timeRange=time1-time2]
[-o=xxx] [-cpd=xxx] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
file_or_folder_url	Mandatory for downloading an object	Local file/folder path
folder_url	Mandatory for downloading objects in batches	Local folder path

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
key	Mandatory for downloading an object Optional for downloading objects in batches	<p>Indicates the name of the object to be downloaded, or the name prefix of the objects to be downloaded in batches.</p> <p>This parameter cannot be left blank when downloading an object. The saving and naming rules are as follows:</p> <ul style="list-style-type: none">• If this parameter specifies a file or folder path that does not exist, the tool checks whether the value ends with a slash (/) or backslash (\). If yes, a folder is created based on the path, and the object is downloaded to this newly created directory.• If this parameter specifies a file or folder path that does not exist and the value does not end with a slash (/) or backslash (\), the object is downloaded to your local PC with the value of key as the file name.• If this parameter specifies an existing file, the object is downloaded to your local PC overwriting the existing file, with the value of key as the file name.• If this parameter specifies an existing folder, the object is downloaded to the directory specified by file_or_folder_url with the object name as the file name. <p>The saving rules when downloading objects in batches are as follows:</p> <ul style="list-style-type: none">• If this parameter is left blank, all objects in the bucket are downloaded to the directory specified by folder_url.• If this parameter is configured, objects whose name prefix is the configured value in the bucket are downloaded to the directory specified by folder_url. <p>NOTE</p> <ul style="list-style-type: none">• If this parameter is configured but the flat parameter is not configured when downloading objects in batches, the name of the downloaded file contains the name prefix of the parent object. If flat is configured, then the name of the downloaded file does not contain the name prefix of the parent object.• For details about how to use this parameter, see 6.3 Download Examples.
fr	Optional for downloading an object (additional	Generates an operation result list when downloading an object.

Parameter	Optional or Mandatory	Description
	parameter)	
flat	Optional for downloading objects in batches (additional parameter)	The name prefix of the parent object is excluded when downloading objects in batches.
tempFileDir	Optional (additional parameter)	<p>Indicates the directory for storing temporary files during multipart download. The default value is the value of defaultTempFileDir in the configuration file.</p> <p>NOTE</p> <ul style="list-style-type: none">• Temporary files generated during multipart download are stored in this directory. Therefore, ensure that the user who executes obsutil has the write permission on the path.• The available space of the partition where the path is located must be greater than the size of the objects to be downloaded.
dryRun	Optional (additional parameter)	Conducts a dry run.
u	Optional (additional parameter)	Indicates incremental download. If this parameter is set, each object can be downloaded only when it does not exist in the local path, its size is different from the namesake one in the local path, or it has the latest modification time.
vlength	Optional (additional parameter)	Checks whether the sizes of the local files are the same as those of the objects in the bucket after the download is complete.
vmd5	Optional (additional parameter)	<p>Checks whether MD5 values of the local files are the same as those of the objects in the bucket after the download is complete.</p> <p>NOTE</p> <p>Objects in the bucket must contain metadata x-obs-md5chksum. Otherwise, MD5 verification will be skipped.</p>
p	Optional (additional parameter)	Indicates the maximum number of concurrent multipart download tasks when downloading an object. The default value is the value of defaultParallels in the configuration file.
threshold	Optional (additional parameter)	<p>Indicates the threshold for enabling multipart download, in bytes. The default value is the value of defaultBigfileThreshold in the configuration file.</p> <p>NOTE</p> <ul style="list-style-type: none">• If the size of the object to be downloaded is smaller than the threshold, download the object directly. If not, a multipart download is required.

Parameter	Optional or Mandatory	Description
		<ul style="list-style-type: none">If you download an object directly, no part record is generated, and resumable transmission is not supported.This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.
versionId	Optional for downloading an object (additional parameter)	Source object version ID that can be specified when downloading an object
ps	Optional (additional parameter)	Indicates the size of each part in a multipart download task, in bytes. The default value is the value of defaultPartSize in the configuration file. NOTE This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.
cpd	Optional (additional parameter)	Indicates the folder where the part records reside. The default value is .obsutil_checkpoint , the subfolder in the home directory of the user who executes obsutil commands. NOTE A part record is generated during a multipart download and saved to the down subfolder. After the download succeeds, its part record is deleted automatically. If the download fails or is suspended, the system attempts to resume the task according to its part record when you perform the download the next time.
r	Mandatory for downloading objects in batches (additional parameter)	Copies objects in batches based on a specified object name prefix.
f	Optional for downloading objects in batches (additional parameter)	Runs in force mode.
j	Optional for downloading objects in batches (additional parameter)	Indicates the maximum number of concurrent tasks for downloading objects in batches. The default value is the value of defaultJobs in the configuration file. NOTE The value is ensured to be greater than or equal to 1.
exclude	Optional for downloading objects in batches (additional parameter)	Indicates the matching patterns of source objects that are excluded, for example: *.txt . NOTE <ul style="list-style-type: none">The asterisk (*) represents any group of characters, and the question mark (?) represents any single character. For instance, abc*.txt indicates any file whose name starts with abc and ends with .txt.

Parameter	Optional or Mandatory	Description
		<ul style="list-style-type: none"> You can use * to represent * and \? to represent ?. If the name of the object to be downloaded matches the value of this parameter, the object is skipped. <p>NOTICE</p> <ul style="list-style-type: none"> You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows. The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt. This matching pattern applies only to objects whose names do not end with a slash (/).
include	Optional for downloading objects in batches (additional parameter)	<p>Indicates the matching patterns of source objects that are included, for example: *.jpg.</p> <p>NOTE</p> <ul style="list-style-type: none"> The asterisk (*) represents any group of characters, and the question mark (?) represents any single character. You can use * to represent * and \? to represent ?. Only after identifying that the name of the file to be downloaded does not match the value of exclude, the system checks whether the file name matches the value of this parameter. If yes, the file is downloaded. If not, the file is skipped. <p>NOTICE</p> <ul style="list-style-type: none"> You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows. The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt. This matching pattern applies only to objects whose names do not end with a slash (/).
timeRange	Optional for downloading objects in batches (additional parameter)	<p>Indicates the time range matching pattern when downloading objects. Only objects whose last modification time is within the configured time range are downloaded.</p> <p>This pattern has a lower priority than the object matching patterns (exclude/include). That is, the time range matching pattern is executed after the configured object matching patterns.</p> <p>NOTE</p>

Parameter	Optional or Mandatory	Description
		<ul style="list-style-type: none">The matching time range is represented in <i>time1-time2</i>, where <i>time1</i> must be earlier than or the same as <i>time2</i>. The time format is <i>yyyyMMddHHmmss</i>.Automatic formatting is supported. For example, <i>yyyyMMdd</i> is equivalent to <i>yyyyMMdd000000</i>, and <i>yyyyMM</i> is equivalent to <i>yyyyMM01000000</i>.If this parameter is set to <i>*-time2</i>, all files whose last modification time is earlier than <i>time2</i> are matched. If it is set to <i>time1-*</i>, all files whose last modification time is later than <i>time1</i> are matched. NOTICE <ul style="list-style-type: none">Time in the matching pattern is the UTC time.This matching pattern applies only to objects whose names do not end with a slash (/).
o	Optional (additional parameter)	<p>Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success, failure, and warning files) are generated in the folder. The default value is .obsutil_output, the subfolder in the home directory of the user who executes obsutil commands.</p> NOTE <ul style="list-style-type: none">The naming rule for result lists is as follows: cp_{succeed failed warning}_report_time_TaskId.txtBy default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Response

Refer to [Response](#) for uploading an object.

Running Examples

- Take the Windows OS as an example. Run the **obsutil cp obs://bucket-test/key d:\temp\test.txt** command to download a single object.

```
obsutil cp obs://bucket-test/key d:\temp\test.txt
```

```
Parallel:      3                Jobs:      3
Threshold:    524288000         PartSize:   5242880
Exclude:      Include:
```

```
VerifyLength: false          VerifyMd5: false
CheckpointDir: d:\temp\.obsutil_checkpoint

[=====] 100.00% 4.86 KB/s 0s
Download successfully, 19B, obs://bucket-test/key --> d:\temp\test.txt
```

- Take the Windows OS as an example. Run the **obsutil cp obs://bucket-test/temp d:\ -f -r** command to download objects in batches.

```
obsutil cp obs://bucket-test/temp d:\ -f -r

Parallel:      3          Jobs:      3
Threshold:    524288000    PartSize:    5242880
Exclude:      Include:
VerifyLength: false      VerifyMd5: false
CheckpointDir: d:\temp\.obsutil_checkpoint
OutputDir: d:\temp\.obsutil_output

[=====] 100.00% 155.59 KB/s 0s
Succeed count is: 6      Failed count is: 0
Metrics [max cost:153 ms, min cost:129 ms, average cost:92.00 ms, average tps:17.86]
Task id is: 3066a4b0-4d21-4929-bb84-4829c32cbd0f
```

- For more examples, see 6.3 Download Examples.

4.9 Generating the Download Link of an Object

Function

You can use this command to generate the download link of a specified object in a bucket or generate the download links of objects in a bucket in batches by object name prefix.

Command Line Structure

- In Windows
 - Generating the download link of a single object

```
obsutil sign obs://bucket/key [-e=300] [-config=xxx]
```
 - Generating the download links of objects in batches by object name prefix

```
obsutil sign obs://bucket[/prefix] -r [-e=300] [-timeRange=time1-time2]
[-include=*.xxx] [-exclude=*.xxx] [-o=xxx] [-config=xxx]
```
- In Linux or macOS
 - Generating the download link of a single object

```
./obsutil sign obs://bucket/key [-e=300] [-config=xxx]
```
 - Generating the download links of objects in batches by object name prefix

```
./obsutil sign obs://bucket[/key] -r [-e=300] [-timeRange=time1-time2]
[-include=*.xxx] [-exclude=*.xxx] [-o=xxx] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
-----------	-----------------------	-------------

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
key	Optional	Object name used for generating the download link of a single object, or object name prefix used for generating download links of objects in batches
e	Optional (additional parameter)	Validity period of the generated download links of objects, in seconds. Minimum value: 60s. Default value: 300s
r	Mandatory when generating download links of objects in batches (additional parameter)	Generates the download links of objects in batches by a specified object name prefix.
exclude	Optional when generating download links of objects in batches (additional parameter)	<p>Indicates the matching patterns of objects that are excluded, for example: *.txt.</p> <p>NOTE</p> <ul style="list-style-type: none">• The asterisk (*) represents any group of characters, and the question mark (?) represents any single character. For instance, abc*.txt indicates any file whose name starts with abc and ends with .txt.• You can use * to represent * and \? to represent ?.• If the name of the object to be downloaded matches the value of this parameter, the object is skipped. <p>NOTICE</p> <ul style="list-style-type: none">• You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.• The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt.• This matching pattern applies only to objects whose names do not end with a slash (/).
include	Optional when generating download links of objects in batches (additional parameter)	<p>Indicates the matching patterns of objects that are included, for example: *.jpg.</p> <p>NOTE</p> <ul style="list-style-type: none">• The asterisk (*) represents any group of characters, and the question mark (?) represents any single character.• You can use * to represent * and \? to represent ?.• Only after identifying that the name of the file to be downloaded does not match the value of exclude, the system checks whether the file name matches the value of this parameter. If yes, the file is downloaded. If not, the file is skipped.

Parameter	Optional or Mandatory	Description
		NOTICE <ul style="list-style-type: none">You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt.This matching pattern applies only to objects whose names do not end with a slash (/).
timeRange	Optional (additional parameter)	<p>Indicates the time range matching pattern when generating download links of objects. Only the download links of objects whose last modification time is within the configured time range are generated.</p> <p>This pattern has a lower priority than the object matching patterns (exclude/include). That is, the time range matching pattern is executed after the configured object matching patterns.</p> NOTE <ul style="list-style-type: none">Time in the matching pattern is the UTC time.This matching pattern applies only to objects whose names do not end with a slash (/).The matching time range is represented in <i>time1-time2</i>, where <i>time1</i> must be earlier than or the same as <i>time2</i>. The time format is <i>yyyyMMddHHmmss</i>.Automatic formatting is supported. For example, <i>yyyyMMdd</i> is equivalent to <i>yyyyMMdd000000</i>, and <i>yyyyMM</i> is equivalent to <i>yyyyMM01000000</i>.If this parameter is set to <i>*-time2</i>, all files whose last modification time is earlier than <i>time2</i> are matched. If it is set to <i>time1-*</i>, all files whose last modification time is later than <i>time1</i> are matched.
o	Optional when generating download links of objects in batches (additional parameter)	<p>Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success and failure files) are generated in the folder. The default value is .obsutil_output, the subfolder in the home directory of the user who executes obsutil commands.</p> NOTE <ul style="list-style-type: none">The naming rule for result lists is as follows: sign_{succeed failed}_report_time_TaskId.txt <p>By default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.</p>
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Running Example

- Take the Windows OS as an example. Run the **obsutil sign obs://bucket-test/test.txt** command to generate the download link of a single object.

```
obsutil sign obs://bucket-test/test.txt
```

Download url of [obs://bucket-test/test.txt] is:

```
http://your-endpoint/bucket-test/test.txt?AccessKeyId=xxxx&Expires=1552548758&Signature=xxxx
```

4.10 Deleting an Object

Function

- You can use this command to delete a specified object.
- You can also use this command to delete objects in batches based on a specified object name prefix.

Command Line Structure

- In Windows

- Deleting a single object

```
obsutil rm obs://bucket/key [-f] [-versionId=xxx] [-fr] [-o=xxx] [-config=xxx]
```

- Deleting objects in batches

```
obsutil rm obs://bucket/[key] -r [-j=1] [-f] [-v] [-o=xxx] [-config=xxx]
```

- In Linux or macOS

- Deleting a single object

```
./obsutil rm obs://bucket/key [-f] [-versionId=xxx] [-fr] [-o=xxx]  
[-config=xxx]
```

- Deleting objects in batches

```
./obsutil rm obs://bucket/[key] -r [-j=1] [-f] [-v] [-o=xxx] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
key	Mandatory for deleting a single object. Optional for deleting objects in batches.	Indicates the name of the object to be deleted, or the name prefix of the objects to be deleted in batches. NOTE If this parameter is left blank when deleting objects in batches, all objects in the bucket are deleted.
fr	Optional for deleting a single object (additional	Generates an operation result list when deleting an object.

Parameter	Optional or Mandatory	Description
	parameter)	
f	Optional (additional parameter)	Runs in force mode.
versionId	Optional for deleting a single object (additional parameter)	Version ID of the object to be deleted.
r	Mandatory for deleting objects in batches (additional parameter)	Deletes objects in batches based on a specified object name prefix.
j	Optional for deleting objects in batches (additional parameter)	Indicates the maximum number of concurrent tasks for deleting objects in batches. The default value is the value of defaultJobs in the configuration file. NOTE The value is ensured to be greater than or equal to 1.
v	Optional for deleting objects in batches (additional parameter)	Deletes versions of an object and the delete markers in batches based on a specified object name prefix.
o	Optional (additional parameter)	Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success and failure files) are generated in the folder. The default value is .obsutil_output , the subfolder in the home directory of the user who executes obsutil commands. NOTE <ul style="list-style-type: none">The naming rule for result lists is as follows: rm_{succeed failed}_report_time_TaskId.txtBy default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Response

Refer to [Response](#) for uploading an object.

Running Examples

- Take the Windows OS as an example. Run the **obsutil rm obs://bucket-test/key -f** command to delete a single object named **key** in bucket **bucket-test**.

```
obsutil rm obs://bucket-test/key -f
```

```
Delete object [key] in the bucket [bucket-test] successfully!
```

- Take the Windows OS as an example. Run the **obsutil rm obs://bucket-test -r -f** command to delete all objects in bucket **bucket-test**.

```
obsutil rm obs://bucket-test -r -f
```

```
[=====] 100.00% 21s
```

```
Succeed count is: 1313 Failed count is: 0
```

```
Task id is: 95936984-f81a-441a-bba0-1fd8254d9241
```

4.11 Synchronously Uploading Incremental Objects

Function

You can use this command to synchronize all files in the local path with objects in the specified path in OBS to keep data consistency.

NOTICE

- Do not change the local file or folder during synchronization. Otherwise, the synchronization may fail or data may be inconsistent.
- Each file can be synchronously uploaded only when it does not exist in the bucket, its size is different from the namesake one in the bucket, or it has the latest modification time.

Command Line Structure

- In Windows

- Uploading a file synchronously

```
obsutil sync file url obs://bucket[/key] [-arcDir=xxx] [-dryRun] [-link] [-vlength] [-vmd5] [-p=1] [-threshold=5248800] [-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd] [-ps=524880] [-o=xxx] [-cpd=xxx] [-fr] [-config=xxx]
```

- Uploading a folder synchronously

```
obsutil sync folder url obs://bucket[/key] [-arcDir=xxx] [-dryRun] [-link] [-vlength] [-vmd5] [-j=1] [-p=1] [-threshold=5248800] [-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd] [-ps=524880] [-include=*.xxx] [-exclude=*.xxx] [-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

- In Linux or macOS

- Uploading a file synchronously

```
./obsutil sync file url obs://bucket[/key] [-arcDir=xxx] [-dryRun] [-link] [-vlength] [-vmd5] [-p=1] [-threshold=5248800] [-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd] [-ps=524880] [-o=xxx] [-cpd=xxx] [-fr] [-config=xxx]
```

- Uploading a folder synchronously

```
./obsutil sync folder_url obs://bucket[/key] [-arcDir=xxx] [-dryRun] [-link]
[-vlength] [-vmd5] [-j=1] [-p=1] [-threshold=52428800] [-acl=xxx] [-sc=xxx]
[-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-include=*.xxx] [-exclude=*.xxx]
[-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
file_url	Mandatory for uploading a file synchronously	Local file path
folder_url	Mandatory for uploading a folder synchronously	Local folder path
bucket	Mandatory	Bucket name
key	Optional	<p>Indicates the object name or object name prefix specified when uploading a file synchronously, or the object name prefix specified when uploading a folder synchronously.</p> <p>The rules are as follows:</p> <ul style="list-style-type: none">• If this parameter is left blank when synchronously uploading a file, the object is uploaded to the root directory of the bucket and the object name is the file name. If the value ends with a slash (/), the value is used as the object name prefix when the file is uploaded, and the object name is the value plus the file name. Otherwise, the file is uploaded with the value as the object name.• If this parameter is left blank when synchronously uploading a folder, all objects in the root directory of the bucket are the same as the files in the local folder. If this parameter is configured, objects whose name prefix is the configured value are the same as the files in the local folder. <p>NOTE</p> <ul style="list-style-type: none">• If the value of this parameter does not end with a slash (/) when synchronously uploading a folder, the obsutil tool automatically adds a slash (/) at the end of the configured value as the object name prefix.• For details about how to use this parameter, see 6.2 Synchronous Upload Examples.
fr	Optional for synchronously uploading a file (additional parameter)	Generates an operation result list when synchronously uploading a file.
arcDir	Optional (additional)	Path to which the synchronously uploaded files are archived

Parameter	Optional or Mandatory	Description
	parameter)	
dryRun	Optional (additional parameter)	Conducts a dry run.
link	Optional (additional parameter)	Uploads the actual path of the symbolic-link file/folder NOTICE If this parameter is not set, and the file to be uploaded is a symbolic link, and the target file of the link does not exist, then files containing 0 bytes are normally uploaded in Windows and the same upload fails in Linux or macOS.
vlength	Optional (additional parameter)	After the synchronous upload is complete, check whether the sizes of the objects in the bucket are the same as those of the local files.
vmd5	Optional (additional parameter)	After the synchronous upload is complete, check whether the MD5 values of the objects in the bucket are the same as those of the local files. NOTE <ul style="list-style-type: none">If the size of the file or folder to be uploaded is too large, using this parameter will degrade the overall performance due to MD5 calculation.After the MD5 value verification is successful, the parameter value is set to the object metadata x-obs-md5chksum, which is used for later MD5 verification during download or copy.
p	Optional (additional parameter)	Indicates the maximum number of concurrent multipart upload tasks when uploading a file. The default value is the value of defaultParallels in the configuration file.
threshold	Optional (additional parameter)	Indicates the threshold for enabling multipart upload, in bytes. The default value is the value of defaultBigfileThreshold in the configuration file. NOTE <ul style="list-style-type: none">If the size of the file or folder to be uploaded is smaller than the threshold, upload it directly. Otherwise, a multipart upload is required.If you upload a file or folder directly, no part record is generated, and resumable transmission is not supported.This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.
acl	Optional (additional parameter)	Access control policies that can be specified when synchronously uploading files. Possible values are: <ul style="list-style-type: none">privatepublic-readpublic-read-write NOTE The preceding three values indicate private read and write, public read, and public read and write.

Parameter	Optional or Mandatory	Description
sc	Optional (additional parameter)	<p>Indicates the storage classes of objects that can be specified when synchronously uploading files. Possible values are:</p> <ul style="list-style-type: none">• standard: OBS Standard, which features low access latency and high throughput, and is applicable to storing frequently accessed data (multiple accesses per month averagely) or data that is smaller than 1 MB• warm: It is applicable to storing semi-frequently accessed (less than 12 times a year averagely) data that requires quick response.• cold: It is secure, durable, and inexpensive, and applicable to archiving rarely-accessed (once a year averagely) data.
meta	Optional (additional parameter)	<p>Indicates the customized metadata that can be specified when uploading files. The format is key1:value1#key2:value2#key3:value3.</p> <p>NOTE</p> <p>The preceding value indicates that the object in the bucket contains three groups of customized metadata after the file is uploaded: key1:value1, key2:value2, and key3:value3.</p>
ps	Optional (additional parameter)	<p>Indicates the size of each part in a multipart upload task, in bytes. The value ranges from 100 KB to 5 GB. The default value is the value of defaultPartSize in the configuration file.</p> <p>NOTE</p> <p>This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.</p>
cpd	Optional (additional parameter)	<p>Indicates the folder where the part records reside. The default value is .obsutil_checkpoint, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <p>A part record is generated during a multipart upload and saved to the upload subfolder. After the upload succeeds, its part record is deleted automatically. If the upload fails or is suspended, the system attempts to resume the task according to its part record when you perform the upload the next time.</p>
j	Optional for synchronously uploading a folder (additional parameter)	<p>Indicates the maximum number of concurrent tasks for uploading a folder synchronously. The default value is the value of defaultJobs in the configuration file.</p> <p>NOTE</p> <p>The value is ensured to be greater than or equal to 1.</p>
exclude	Optional for synchronously uploading a folder	<p>Indicates the file matching patterns that are excluded, for example: *.txt.</p> <p>NOTE</p> <ul style="list-style-type: none">• The asterisk (*) represents any group of characters, and the

Parameter	Optional or Mandatory	Description
	(additional parameter)	<p>question mark (?) represents any single character. For instance, abc*.txt indicates any file whose name starts with abc and ends with .txt.</p> <ul style="list-style-type: none">• You can use * to represent * and \? to represent ?.• If the name of the file to be uploaded matches the value of this parameter, the file is skipped. <p>NOTICE</p> <ul style="list-style-type: none">• You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.• The matching pattern applies to the absolute file path (including the file name and file directory).• The matching pattern takes effect only for files in the folder.
include	Optional for synchronously uploading a folder (additional parameter)	<p>Indicates the file matching patterns that are included, for example: *.jpg.</p> <p>NOTE</p> <ul style="list-style-type: none">• The asterisk (*) represents any group of characters, and the question mark (?) represents any single character.• You can use * to represent * and \? to represent ?.• Only after identifying that the name of the file to be uploaded does not match the value of exclude, the system checks whether the file name matches the value of this parameter. If yes, the file is uploaded. If not, the file is skipped. <p>NOTICE</p> <ul style="list-style-type: none">• You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.• The matching pattern applies to the absolute file path (including the file name and file directory).• The matching pattern takes effect only for files in the folder.
timeRange	Optional for synchronously uploading a folder (additional parameter)	<p>Indicates the time range matching pattern when synchronously uploading files. Only files whose last modification time is within the configured time range are uploaded.</p> <p>This pattern has a lower priority than the file matching patterns (exclude/include). That is, the time range matching pattern is executed after the configured file matching patterns.</p> <p>NOTE</p> <ul style="list-style-type: none">• The matching time range is represented in <i>time1-time2</i>, where <i>time1</i> must be earlier than or the same as <i>time2</i>. The time format is <i>yyyyMMddHHmmss</i>.• Automatic formatting is supported. For example, <i>yyyyMMdd</i> is equivalent to <i>yyyyMMdd000000</i>, and <i>yyyyMM</i> is equivalent to <i>yyyyMM01000000</i>.• If this parameter is set to <i>*-time2</i>, all files whose last

Parameter	Optional or Mandatory	Description
		<p>modification time is earlier than <i>time2</i> are matched. If it is set to <i>time1</i>*, all files whose last modification time is later than <i>time1</i> are matched.</p> <p>NOTICE</p> <p>Time in the matching pattern is the UTC time.</p>
o	Optional (additional parameter)	<p>Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success, failure, and warning files) are generated in the folder. The default value is .obsutil_output, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <ul style="list-style-type: none">The naming rule for result lists is as follows: sync_{succeed failed warning}_report_time_TaskId.txtBy default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.
config	Optional (additional parameter)	<p>User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.</p>

Response

Refer to [Response](#) for uploading an object.

Running Examples

- Take the Windows OS as an example. Run the **obsutil sync d:\temp\test.txt obs://bucket-test/key** command to synchronously upload a file.

```
obsutil sync d:\temp\test.txt obs://bucket-test/key
```

```
Parallel:      3                Jobs:      3
Threshold:    524288000        PartSize:   5242880
Exclude:      Include:
VerifyLength: false          VerifyMd5:   false
CheckpointDir: d:\temp\.obsutil_checkpoint

[=====] 100.00% 1.68 MB/s 5s
Upload successfully, 8.46MB, d:\temp\test.txt --> obs://bucket-test/key
```

- Take the Windows OS as an example. Run the **obsutil sync d:\temp obs://bucket-test/temp** command to synchronously upload a folder.

```
obsutil sync d:\temp obs://bucket-test/temp
```

```
Parallel:      3                Jobs:      3
Threshold:    524288000        PartSize:   5242880
Exclude:      Include:
```

```
VerifyLength: false          VerifyMd5:    false
CheckpointDir: d:\temp\.obsutil_checkpoint
OutputDir: d:\temp\.obsutil_output

[=====] 100.00% 2.02 KB/s 0s
Succeed count is: 5          Failed count is: 0
Metrics [max cost:90 ms, min cost:45 ms, average cost:63.80 ms, average tps:35.71]
Task id is: 104786c8-27c2-48fc-bc6a-5886596fb0ed
```

- For more examples, see 6.2 Synchronous Upload Examples.

4.12 Synchronously Copying Incremental Objects

Function

You can use this command to synchronize all objects in the specified path in the source bucket with objects in the specified path in the destination bucket to keep data consistency.

NOTICE

- Do not change the source objects in the OBS bucket during synchronization. Otherwise, the synchronization may fail or data may be inconsistent.
- If the storage class of the object to be copied is **cold**, you must restore the object to be copied first. Otherwise, the copy fails.
- To copy objects, you must have the read permission on the objects to be copied and the write permission on the destination bucket.
- If the client-side cross-region replication function is not enabled, ensure that the source bucket and destination bucket are in the same region.
- Each object can be synchronously copied only when it does not exist in the destination bucket, its size is different from the namesake one in the destination bucket, or it has the latest modification time.

Command Line Structure

- In Windows

```
obsutil sync obs://srcbucket[/key] obs://dstbucket[/dest] [-dryRun] [-crr]
[-vlength] [-vmd5] [-j=1] [-p=1] [-threshold=52428800] [-acl=xxx] [-sc=xxx]
[-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-include=*.xxx] [-exclude=*.xxx]
[-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

- In Linux or macOS

```
./obsutil sync obs://srcbucket[/key] obs://dstbucket[/dest] [-dryRun] [-crr]
[-vlength] [-vmd5] [-j=1] [-p=1] [-threshold=52428800] [-acl=xxx] [-sc=xxx]
[-meta=aaa:bbb#ccc:ddd] [-ps=5242880] [-include=*.xxx] [-exclude=*.xxx]
[-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```



NOTE

The source path and destination path cannot be the same and no overlapping between the source and destination paths is allowed when synchronously copying objects.

Parameter Description

Parameter	Optional or Mandatory	Description
srcbucket	Mandatory	Source bucket name
dstbucket	Mandatory	Destination bucket name
dest	Optional	<p>Name prefix of destination objects.</p> <p>NOTE</p> <p>If the value of this parameter does not end with a slash (/), the obsutil tool automatically adds a slash (/) at the end of the configured value as the name prefix of destination objects.</p>
key	Optional	<p>Name prefix of source objects</p> <p>The rules are as follows:</p> <ul style="list-style-type: none">• If this parameter is left blank, objects whose name prefix is the value of dest in the destination bucket are the same as all objects in the source bucket.• If this parameter is configured, objects whose name prefix is the value of dest in the destination bucket are the same as objects whose name prefix is this configured value in the source bucket. <p>NOTE</p> <ul style="list-style-type: none">• If the value of this parameter does not end with a slash (/), the obsutil tool automatically adds a slash (/) at the end of the configured value as the name prefix of source objects.• For details about how to use this parameter, see 6.6 Synchronous Copy Examples.
dryRun	Optional (additional parameter)	Conducts a dry run.
crr	Optional (additional parameter)	<p>Enables the client-side cross-region replication function. In this mode, data is directly copied to the destination bucket from the source bucket through data stream. The buckets can be any two OBS buckets.</p> <p>NOTE</p> <ul style="list-style-type: none">• If this parameter is configured, ensure that the configuration of client-side cross-region replication is updated in the configuration file. For details, see 5.1 Updating a Configuration File.• The configurations of the source bucket and destination bucket are respectively akCrr/skCrr/tokenCrr/endpointCrr and ak/sk/token/endpoint in the configuration file. <p>NOTICE</p> <p>After this function is enabled, both upload and download bandwidth are occupied.</p>

Parameter	Optional or Mandatory	Description
vlength	Optional (additional parameter)	Verifies whether the object size in the destination bucket is the same as that in the source bucket after the copy task completes. NOTE This parameter must be used together with crr .
vmd5	Optional (additional parameter)	Verifies whether the MD5 value of the destination bucket is the same as that of the source bucket after the copy task completes. NOTE <ul style="list-style-type: none">This parameter must be used together with crr.Objects in the source bucket must contain metadata x-obs-md5chksum. Otherwise, MD5 verification will be skipped. After the MD5 value verification is successful, the parameter value is set to the destination object metadata x-obs-md5chksum , which is used for later MD5 verification during download or copy.
p	Optional (additional parameter)	Indicates the maximum number of concurrent multipart copy tasks when copying an object. The default value is the value of defaultParallels in the configuration file.
threshold	Optional (additional parameter)	Indicates the threshold for enabling multipart copy, in bytes. The default value is the value of defaultBigfileThreshold in the configuration file. NOTE <ul style="list-style-type: none">If the size of the object to be copied is smaller than the threshold, copy the object directly. If not, a multipart copy is required.If you copy an object directly, no part record is generated, and resumable transmission is not supported.This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.
acl	Optional (additional parameter)	Access control policies for destination objects that can be specified when copying objects. Possible values are: <ul style="list-style-type: none">privatepublic-readpublic-read-write NOTE The preceding three values indicate private read and write, public read, and public read and write.
sc	Optional (additional parameter)	Storage classes of the destination objects that can be specified when copying objects. Possible values are: <ul style="list-style-type: none">standard: OBS Standard, which features low

Parameter	Optional or Mandatory	Description
		<p>access latency and high throughput, and is applicable to storing frequently accessed data (multiple accesses per month averagely) or data that is smaller than 1 MB</p> <ul style="list-style-type: none">• warm: It is applicable to storing semi-frequently accessed (less than 12 times a year averagely) data that requires quick response.• cold: It is secure, durable, and inexpensive, and applicable to archiving rarely-accessed (once a year averagely) data.
meta	Optional (additional parameter)	<p>Metadata of destination objects that can be specified when copying objects. The format is <i>key1:value1#key2:value2#key3:value3</i>.</p> <p>NOTE</p> <p>The preceding value indicates that the destination objects in the bucket contain three groups of customized metadata after objects are copied: key1:value1, key2:value2, and key3:value3.</p>
ps	Optional (additional parameter)	<p>Indicates the size of each part in a multipart copy task, in bytes. The value ranges from 100 KB to 5 GB. The default value is the value of defaultPartSize in the configuration file.</p> <p>NOTE</p> <p>This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.</p>
cpd	Optional (additional parameter)	<p>Indicates the folder where the part records reside. The default value is .obsutil_checkpoint, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <p>A part record is generated during a multipart copy and saved to the copy subfolder. After the copy succeeds, its part record is deleted automatically. If the copy fails or is suspended, the system attempts to resume the task according to its part record when you perform the copy the next time.</p>
j	Optional for copying objects in batches (additional parameter)	<p>Indicates the maximum number of concurrent tasks for copying objects synchronously. The default value is the value of defaultJobs in the configuration file.</p> <p>NOTE</p> <p>The value is ensured to be greater than or equal to 1.</p>
exclude	Optional for copying objects in batches (additional parameter)	<p>Indicates the matching patterns of source objects that are excluded, for example: *.txt.</p> <p>NOTE</p> <ul style="list-style-type: none">• The asterisk (*) represents any group of characters, and the question mark (?) represents any single

Parameter	Optional or Mandatory	Description
		<p>character. For instance, abc*.txt indicates any file whose name starts with abc and ends with .txt.</p> <ul style="list-style-type: none">• You can use * to represent * and \? to represent ?.• If the name of the object to be copied matches the value of this parameter, the object is skipped. <p>NOTICE</p> <ul style="list-style-type: none">• You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.• The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt.• This matching pattern applies only to objects whose names do not end with a slash (/).
include	Optional for copying objects in batches (additional parameter)	<p>Indicates the matching patterns of source objects that are included, for example: *.jpg.</p> <p>NOTE</p> <ul style="list-style-type: none">• The asterisk (*) represents any group of characters, and the question mark (?) represents any single character.• You can use * to represent * and \? to represent ?.• Only after identifying that the name of the file to be copied does not match the value of exclude, the system checks whether the file name matches the value of this parameter. If yes, the file is copied. If not, the file is skipped. <p>NOTICE</p> <ul style="list-style-type: none">• You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.• The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt.• This matching pattern applies only to objects whose names do not end with a slash (/).
timeRange	Optional (additional parameter)	<p>Indicates the time range matching pattern when synchronously copying objects. Only objects whose last modification time is within the configured time range are copied.</p> <p>This pattern has a lower priority than the object matching patterns (exclude/include). That is, the time range matching pattern is executed after the</p>

Parameter	Optional or Mandatory	Description
		<p>configured object matching patterns.</p> <p>NOTE</p> <ul style="list-style-type: none">• The matching time range is represented in <i>time1-time2</i>, where <i>time1</i> must be earlier than or the same as <i>time2</i>. The time format is <i>yyyyMMddHHmmss</i>.• Automatic formatting is supported. For example, <i>yyyyMMdd</i> is equivalent to <i>yyyyMMdd000000</i>, and <i>yyyyMM</i> is equivalent to <i>yyyyMM01000000</i>.• If this parameter is set to <i>*-time2</i>, all files whose last modification time is earlier than <i>time2</i> are matched. If it is set to <i>time1-*</i>, all files whose last modification time is later than <i>time1</i> are matched. <p>NOTICE</p> <ul style="list-style-type: none">• Time in the matching pattern is the UTC time.• This matching pattern applies only to objects whose names do not end with a slash (/).
o	Optional (additional parameter)	<p>Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success, failure, and warning files) are generated in the folder. The default value is .obsutil_output, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <ul style="list-style-type: none">• The naming rule for result lists is as follows: sync_{succeed failed warning}_report_time_TaskId.txt <p>By default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.</p>
config	Optional (additional parameter)	<p>User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.</p>

Response

Refer to [Response](#) for uploading an object.

Running Example

- Take the Windows OS as an example. Run the **obsutil sync obs://bucket-test/temp/ obs://bucket-test2/temp/** command to synchronously copy objects.

```
obsutil sync obs://bucket-test/temp/ obs://bucket-test2/temp
```

```
Parallel:      3                      Jobs:      3
```

```
Threshold:      524288000          PartSize:      5242880
Exclude:        Include:
VerifyLength:  false          VerifyMd5:      false
CheckpointDir: d:\temp\.obsutil_checkpoint
OutputDir:     d:\temp\.obsutil_output

[=====] 100.00% 10/s 0s
Succeed count is: 5          Failed count is: 0
Metrics [max cost:298 ms, min cost:192 ms, average cost:238.00 ms, average tps:9.71]
Task id is: 0476929d-9d23-4dc5-b2f8-0a0493f027c5
```

- For more examples, see 6.6 Synchronous Copy Examples.

4.13 Synchronously Downloading Incremental Objects

Function

You can use this command to synchronize all objects in the specified path in OBS with files in the local path to keep data consistency.

NOTICE

- Do not change the source objects in the OBS bucket during synchronization. Otherwise, the synchronization may fail or data may be inconsistent.
- If the storage class of the object to be copied is **cold**, you must restore the object to be downloaded first. Otherwise, the download fails.
- Each object can be synchronously downloaded only when it does not exist in the local path, its size is different from the namesake one in the local path, or it has the latest modification time.

Command Line Structure

- In Windows

```
obsutil sync obs://bucket[/key] folder_url [-tempFileDir=xxx] [-dryRun] [-vlength]
[-vmd5] [-j=1] [-p=1] [-threshold=52428800] [-ps=5242880] [-include=*.xxx]
[-exclude=*.xxx] [-timeRange=time1-time2] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

- In Linux or macOS

```
./obsutil sync obs://bucket[/key] folder_url [-tempFileDir=xxx] [-dryRun]
[-vlength] [-vmd5] [-j=1] [-p=1] [-threshold=52428800] [-ps=5242880]
[-include=*.xxx] [-exclude=*.xxx] [-timeRange=time1-time2] [-o=xxx] [-cpd=xxx]
[-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
folder_url	Mandatory	Local folder path

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
key	Optional	<p>Indicates the name prefix of objects to be synchronously downloaded.</p> <p>The rules are as follows:</p> <ul style="list-style-type: none">• If this parameter is left blank, all files in the folder specified by folder_url are the same as all objects in the bucket.• If this parameter is configured, all files in the folder specified by folder_url are the same as the objects whose name prefix is the configured value in the bucket. <p>NOTE</p> <ul style="list-style-type: none">• If the value of this parameter does not end with a slash (/), the obsutil tool automatically adds a slash (/) at the end of the configured value as the object name prefix.• For details about how to use this parameter, see 6.4 Synchronous Download Examples.
tempFileDir	Optional (additional parameter)	<p>Indicates the directory for storing temporary files during synchronous download. The default value is the value of defaultTempFileDir in the configuration file.</p> <p>NOTE</p> <ul style="list-style-type: none">• Temporary files generated during multipart download are stored in this directory. Therefore, ensure that the user who executes obsutil has the write permission on the path.• The available space of the partition where the path is located must be greater than the size of the objects to be downloaded.
dryRun	Optional (additional parameter)	Conducts a dry run.
vlength	Optional (additional parameter)	Checks whether the sizes of the local files are the same as those of the objects in the bucket after the download is complete.
vmd5	Optional (additional parameter)	<p>Checks whether MD5 values of the local files are the same as those of the objects in the bucket after the download is complete.</p> <p>NOTE</p> <p>Objects in the bucket must contain metadata x-obs-md5chksum. Otherwise, MD5 verification will be skipped.</p>
p	Optional (additional parameter)	Indicates the maximum number of concurrent multipart download tasks when downloading an object. The default value is the value of defaultParallels in the configuration file.

Parameter	Optional or Mandatory	Description
threshold	Optional (additional parameter)	<p>Indicates the threshold for enabling multipart download, in bytes. The default value is the value of defaultBigfileThreshold in the configuration file.</p> <p>NOTE</p> <ul style="list-style-type: none"> • If the size of the object to be downloaded is smaller than the threshold, download the object directly. If not, a multipart download is required. • If you download an object directly, no part record is generated, and resumable transmission is not supported. • This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.
ps	Optional (additional parameter)	<p>Indicates the size of each part in a multipart download task, in bytes. The default value is the value of defaultPartSize in the configuration file.</p> <p>NOTE</p> <p>This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.</p>
cpd	Optional (additional parameter)	<p>Indicates the folder where the part records reside. The default value is .obsutil_checkpoint, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <p>A part record is generated during a multipart download and saved to the down subfolder. After the download succeeds, its part record is deleted automatically. If the download fails or is suspended, the system attempts to resume the task according to its part record when you perform the download the next time.</p>
j	Optional for downloading objects in batches (additional parameter)	<p>Indicates the maximum number of concurrent tasks for downloading objects synchronously. The default value is the value of defaultJobs in the configuration file.</p> <p>NOTE</p> <p>The value is ensured to be greater than or equal to 1.</p>
exclude	Optional for downloading objects in batches (additional parameter)	<p>Indicates the matching patterns of source objects that are excluded, for example: *.txt.</p> <p>NOTE</p> <ul style="list-style-type: none"> • The asterisk (*) represents any group of characters, and the question mark (?) represents any single character. For instance, abc*.txt indicates any file whose name starts with abc and ends with .txt. • You can use * to represent * and \? to represent ?. • If the name of the object to be downloaded matches the value of this parameter, the object is skipped.

Parameter	Optional or Mandatory	Description
		NOTICE <ul style="list-style-type: none">You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt.This matching pattern applies only to objects whose names do not end with a slash (/).
include	Optional for downloading objects in batches (additional parameter)	<p>Indicates the matching patterns of source objects that are included, for example: *.jpg.</p> NOTE <ul style="list-style-type: none">The asterisk (*) represents any group of characters, and the question mark (?) represents any single character.You can use * to represent * and \? to represent ?.Only after identifying that the name of the file to be downloaded does not match the value of exclude, the system checks whether the file name matches the value of this parameter. If yes, the file is downloaded. If not, the file is skipped. NOTICE <ul style="list-style-type: none">You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt.This matching pattern applies only to objects whose names do not end with a slash (/).
timeRange	Optional (additional parameter)	<p>Indicates the time range matching pattern when synchronously downloading objects. Only objects whose last modification time is within the configured time range are downloaded.</p> <p>This pattern has a lower priority than the object matching patterns (exclude/include). That is, the time range matching pattern is executed after the configured object matching patterns.</p> NOTE <ul style="list-style-type: none">The matching time range is represented in

Parameter	Optional or Mandatory	Description
		<p><i>time1-time2</i>, where <i>time1</i> must be earlier than or the same as <i>time2</i>. The time format is <i>yyyyMMddHHmmss</i>.</p> <ul style="list-style-type: none">Automatic formatting is supported. For example, <i>yyyyMMdd</i> is equivalent to <i>yyyyMMdd000000</i>, and <i>yyyyMM</i> is equivalent to <i>yyyyMM01000000</i>.If this parameter is set to <i>*-time2</i>, all files whose last modification time is earlier than <i>time2</i> are matched. If it is set to <i>time1-*</i>, all files whose last modification time is later than <i>time1</i> are matched. <p>NOTICE</p> <ul style="list-style-type: none">Time in the matching pattern is the UTC time.This matching pattern applies only to objects whose names do not end with a slash (/).
o	Optional (additional parameter)	<p>Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success, failure, and warning files) are generated in the folder. The default value is .obsutil_output, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <ul style="list-style-type: none">The naming rule for result lists is as follows: sync_{succeed failed warning}_report_time_TaskId.txtBy default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.
config	Optional (additional parameter)	<p>User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.</p>

Response

Refer to [Response](#) for uploading an object.

Running Example

- Take the Windows OS as an example. Run the **obsutil sync obs://bucket-test/temp d:\temp** command to download objects synchronously.

```
obsutil sync obs://bucket-test/temp d:\temp
```

```
Parallel:      3                Jobs:      3
Threshold:    524288000        PartSize:  5242880
Exclude:
VerifyLength: false          VerifyMd5:  false
```

```
CheckpointDir: d:\temp\.obsutil_checkpoint
OutputDir: d:\temp\.obsutil_output

[=====] 100.00% 155.59 KB/s 0s
Succeed count is: 6          Failed count is: 0
Metrics [max cost:153 ms, min cost:129 ms, average cost:92.00 ms, average tps:17.86]
Task id is: 3066a4b0-4d21-4929-bb84-4829c32cbd0f
```

- For more examples, see 6.4 Synchronous Download Examples.

4.14 Restoring Objects

Function

You can use this command to restore a specified object whose storage class is **cold** or restore objects in batches by object name prefix.



NOTE

- Object content cannot be read during restoration.
- After an object is restored, the time it requires before the object can be downloaded depends on the OBS server.

Command Line Structure

- In Windows

- Restoring an object

```
obsutil restore obs://bucket/key [-d=1] [-t=xxx] [-versionId=xxx] [-fr]
[-o=xxx] [-config=xxx]
```

- Restoring objects in batches

```
obsutil restore obs://bucket[/key] -r [-f] [-v] [-d=1] [-t=xxx] [-o=xxx] [-j=1]
[-config=xxx]
```

- In Linux or macOS

- Restoring an object

```
./obsutil restore obs://bucket/key [-d=1] [-t=xxx] [-versionId=xxx] [-fr]
[-o=xxx] [-config=xxx]
```

- Restoring objects in batches

```
./obsutil restore obs://bucket[/key] -r [-f] [-v] [-d=1] [-t=xxx] [-o=xxx]
[-j=1] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
key	Mandatory for restoring a single object whose storage class is cold Optional for batch	Indicates the name of the object to be restored or the name prefix of the objects to be restored in batches. NOTE If this parameter is left blank when batch restoring objects, all objects whose storage class is cold in the bucket are

Parameter	Optional or Mandatory	Description
	restoring objects whose storage class is cold	restored.
d	Optional (additional parameter)	
t	Optional (additional parameter)	Options for restoring objects. Possible values are: <ul style="list-style-type: none">• standard• expedited NOTE <ul style="list-style-type: none">• The preceding two values indicate standard restoration (3–5 hours) and quick restoration (1–5 minutes).• If this parameter is not set, expedited restoration is used by default.
versionId	Optional for restoring a single object whose storage class is cold (additional parameter)	Version ID of the to-be-restored object whose storage class is cold
fr	Optional for restoring a single object whose storage class is cold (additional parameter)	Generates an operation result list when restoring a single object whose storage class is cold .
f	Optional for batch restoring objects whose storage class is cold (additional parameter)	Runs in force mode.
r	Mandatory for batch restoring objects whose storage class is cold (additional parameter)	Restores objects whose storage class is cold in batches by object name prefix.
v	Optional for batch restoring objects whose storage class is cold (additional parameter)	Restores versions of objects whose storage class is cold in batches by object name prefix.
o	Optional (additional parameter)	Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success and failure files) are generated in the folder. The default value is .obsutil_output , the subfolder in the home

Parameter	Optional or Mandatory	Description
		directory of the user who executes obsutil commands. NOTE <ul style="list-style-type: none">The naming rule for result lists is as follows: restore_{succeed failed}_report_time_TaskId.txt By default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.
j	Optional for batch restoring objects whose storage class is cold (additional parameter)	Maximum number of concurrent tasks for batch restoring objects whose storage class is cold . The default value is the value of defaultJobs in the configuration file. NOTE The value is ensured to be greater than or equal to 1.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Response

Refer to [Response](#) for uploading an object.

Running Examples

- Take the Windows OS as an example. Run the **obsutil restore obs://bucket-test/key** command to restore a single object whose storage class is **cold**.

```
obsutil restore obs://bucket-test/key
```

```
Start to restore object [key] in the bucket [bucket-test] successfully!
```

- Take the Windows OS as an example. Run the **obsutil restore obs://bucket-test -r -f** command to restore objects whose storage class is **cold** in the bucket in batches.

```
obsutil restore obs://bucket-test -r -f
```

```
[=====] 100.00% 3s
```

```
Succeed count is: 12      Failed count is: 0
```

```
Metrics [max cost:264 ms, min cost:54 ms, average cost:119.33 ms, average tps:19.70]
```

```
Task id is: 96f104ee-d0bf-40ff-95dd-31dec0d8f4f4
```

4.15 Resuming a Failed Upload Task

Function

You can use this command to resume a failed upload task based on the task ID.

Command Line Structure

- In Windows

```
obsutil cp -recover=xxx [-arcDir=xxx] [-dryRun] [-f] [-u] [-vlength] [-vmd5] [-j=1]
[-p=1] [-threshold=52428800] [-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd]
[-ps=5242880] [-include=*.xxx] [-exclude=*.xxx] [-timeRange=time1-time2] [-o=xxx]
[-cpd=xxx] [-config=xxx]
```

- In Linux or macOS

```
./obsutil cp -recover=xxx [-arcDir=xxx] [-dryRun] [-f] [-u] [-vlength] [-vmd5] [-j=1]
[-p=1] [-threshold=52428800] [-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd]
[-ps=5242880] [-include=*.xxx] [-exclude=*.xxx] [-timeRange=time1-time2] [-o=xxx]
[-cpd=xxx] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
recover	Mandatory (additional parameter)	ID of the upload task to be resumed NOTE <ul style="list-style-type: none">You can obtain the task ID after an upload task is complete, or query it based on the file name of the operation result list, which is the 36 characters excluding the suffix .txt in the file name.You can locate the upload task to be resumed in the directory where the result lists reside. For details about the directory of the result lists, see additional parameter o.
arcDir	Optional (additional parameter)	Path to which the uploaded files are archived
dryRun	Optional (additional parameter)	Conducts a dry run.
u	Optional (additional parameter)	Indicates incremental upload. If this parameter is set, each file can be uploaded only when it does not exist in the bucket, its size is different from the namesake one in the bucket, or it has the latest modification time.
vlength	Optional (additional parameter)	After the upload is complete, check whether the sizes of the objects in the bucket are the same as those of the local files.
vmd5	Optional (additional parameter)	After the upload is complete, check whether the MD5 values of the objects in the bucket are the same as those of the local files.

Parameter	Optional or Mandatory	Description
		NOTE <ul style="list-style-type: none">• If the size of the file or folder to be uploaded is too large, using this parameter will degrade the overall performance due to MD5 calculation.• After the MD5 value verification is successful, the parameter value is set to the object metadata x-obs-md5chksum, which is used for later MD5 verification during download or copy.
p	Optional (additional parameter)	Indicates the maximum number of concurrent multipart upload tasks when uploading a file. The default value is the value of defaultParallels in the configuration file.
threshold	Optional (additional parameter)	Indicates the threshold for enabling multipart upload, in bytes. The default value is the value of defaultBigfileThreshold in the configuration file. NOTE <ul style="list-style-type: none">• If the size of the file or folder to be uploaded is smaller than the threshold, upload it directly. Otherwise, a multipart upload is required.• If you upload a file or folder directly, no part record is generated, and resumable transmission is not supported.• This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.
acl	Optional (additional parameter)	Access control policies that can be specified when uploading files. Possible values are: <ul style="list-style-type: none">• private• public-read• public-read-write NOTE The preceding three values indicate private read and write, public read, and public read and write.
sc	Optional (additional parameter)	Indicates the storage classes of objects that can be specified when uploading files. Possible values are: <ul style="list-style-type: none">• standard: OBS Standard, which features low access latency and high throughput, and is applicable to storing frequently accessed data (multiple accesses per month averagely) or data that is smaller than 1 MB• warm: It is applicable to storing semi-frequently accessed (less than 12 times a year averagely) data that requires quick response.• cold: It is secure, durable, and inexpensive, and applicable to archiving rarely-accessed (once a year averagely) data.
meta	Optional (additional parameter)	Indicates the customized metadata that can be specified when uploading files. The format is

Parameter	Optional or Mandatory	Description
		key1:value1#key2:value2#key3:value3. NOTE The preceding value indicates that the object in the bucket contains three groups of customized metadata after the file is uploaded: key1:value1 , key2:value2 , and key3:value3 .
ps	Optional (additional parameter)	Indicates the size of each part in a multipart upload task, in bytes. The value ranges from 100 KB to 5 GB. The default value is the value of defaultPartSize in the configuration file. NOTE This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.
cpd	Optional (additional parameter)	Indicates the folder where the part records reside. The default value is .obsutil_checkpoint , the subfolder in the home directory of the user who executes obsutil commands. NOTE A part record is generated during a multipart upload and saved to the upload subfolder. After the upload succeeds, its part record is deleted automatically. If the upload fails or is suspended, the system attempts to resume the task according to its part record when you perform the upload the next time.
f	Optional (additional parameter)	Runs in force mode.
j	Optional (additional parameter)	Maximum number of concurrent tasks for uploading a folder. The default value is the value of defaultJobs in the configuration file. NOTE The value is ensured to be greater than or equal to 1.
exclude	Optional (additional parameter)	Indicates the file matching patterns that are excluded, for example: *.txt . NOTE <ul style="list-style-type: none">The asterisk (*) represents any characters, and question mark (?) represents only one character. For instance, abc*.txt indicates any file whose name starts with abc and ends with .txt.You can use * to represent * and \? to represent ?.If the name of the file to be uploaded matches the value of this parameter, the file is skipped. NOTICE <ul style="list-style-type: none">You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.The matching pattern applies to the absolute file path (including the file name and file directory).

Parameter	Optional or Mandatory	Description
		<ul style="list-style-type: none">The matching pattern applies only to files in a folder.
include	Optional (additional parameter)	<p>Indicates the file matching patterns that are included, for example: *.jpg.</p> <p>NOTE</p> <ul style="list-style-type: none">The asterisk (*) represents any group of characters, and the question mark (?) represents any single character.You can use * to represent * and \? to represent ?.Only after identifying that the name of the file to be uploaded does not match the value of exclude, the system checks whether the file name matches the value of this parameter. If yes, the file is uploaded. If not, the file is skipped. <p>NOTICE</p> <ul style="list-style-type: none">You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.The matching pattern applies to the absolute file path (including the file name and file directory).The matching pattern applies only to files in a folder.
timeRange	Optional (additional parameter)	<p>Indicates the time range matching pattern when uploading files. Only files whose last modification time is within the configured time range are uploaded.</p> <p>This pattern has a lower priority than the file matching patterns (exclude/include). That is, the time range matching pattern is executed after the configured file matching patterns.</p> <p>NOTE</p> <ul style="list-style-type: none">The matching time range is represented in <i>time1-time2</i>, where <i>time1</i> must be earlier than or the same as <i>time2</i>. The time format is <i>yyyyMMddHHmmss</i>.Automatic formatting is supported. For example, <i>yyyyMMdd</i> is equivalent to <i>yyyyMMdd000000</i>, and <i>yyyyMM</i> is equivalent to <i>yyyyMM01000000</i>.If this parameter is set to <i>*-time2</i>, all files whose last modification time is earlier than <i>time2</i> are matched. If it is set to <i>time1-*</i>, all files whose last modification time is later than <i>time1</i> are matched. <p>NOTICE</p> <p>Time in the matching pattern is the UTC time.</p>
o	Optional (additional parameter)	<p>Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success, failure, and warning files) are generated in the folder. The default value is .obsutil_output, the subfolder in the home directory of the user who executes obsutil commands.</p>

Parameter	Optional or Mandatory	Description
		NOTE <ul style="list-style-type: none">The naming rule for result lists is as follows: cp_{succeed failed warning}_report_time_TaskId.txt By default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Response

Refer to [Response](#) for uploading an object.

Running Example

- Take the Windows OS as an example. Run the **obsutil cp -recover 104786c8-27c2-48fc-bc6a-5886596fb0ed -f** command to resume the failed upload task.

```
obsutil cp -recover 104786c8-27c2-48fc-bc6a-5886596fb0ed -f

Parallel:      3                Jobs:      3
Threshold:    524288000        PartSize:   5242880
Exclude:      524288000        Include:
VerifyLength: false          VerifyMd5:   false
CheckpointDir: d:\temp\obsutil_checkpoint
OutputDir:    d:\temp\obsutil_output

[=====] 100.00% 2.02 KB/s 0s
Succeed count is: 5          Failed count is: 0
Metrics [max cost:90 ms, min cost:45 ms, average cost:63.80 ms, average tps:35.71]
Task id is: a628d6da-c562-4a1f-b687-4fa125de0dc3
```

4.16 Resuming a Failed Copy Task

Function

You can use this command to resume a failed copy task based on the task ID.

Command Line Structure

- In Windows

```
obsutil cp -recover=xxx [-dryRun] [-f] [-u] [-crr] [-vlength] [-vmd5] [-j=1] [-p=1]
[-threshold=52428800] [-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd] [-ps=5242880]
```

```
[-include=*.xxx] [-exclude=*.xxx] [-timeRange=time1-time2] [-o=xxx] [-cpd=xxx]  
[-config=xxx]
```

- In Linux or macOS

```
./obsutil cp -recover=xxx [-dryRun] [-f] [-u] [-crr] [-vlength] [-vmd5] [-j=1] [-p=1]  
[-threshold=52428800] [-acl=xxx] [-sc=xxx] [-meta=aaa:bbb#ccc:ddd] [-ps=5242880]  
[-include=*.xxx] [-exclude=*.xxx] [-timeRange=time1-time2] [-o=xxx] [-cpd=xxx]  
[-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
recover	Mandatory (additional parameter)	<p>ID of the copy task to be resumed.</p> <p>NOTE</p> <ul style="list-style-type: none">• You can obtain the task ID after a copy task is complete, or query it based on the file name of the operation result list, which is the 36 characters excluding the suffix .txt in the file name.• You can locate the copy task to be resumed in the directory where the result lists reside. For details about the directory of the result lists, see additional parameter o.
dryRun	Optional (additional parameter)	Conducts a dry run.
crr	Optional (additional parameter)	<p>Enables the client-side cross-region replication function. In this mode, data is directly copied to the destination bucket from the source bucket through data stream. The buckets can be any two OBS buckets.</p> <p>NOTE</p> <ul style="list-style-type: none">• If this parameter is configured, ensure that the configuration of client-side cross-region replication is updated in the configuration file. For details, see 5.1 Updating a Configuration File.• The configurations of the source bucket and destination bucket are respectively akCrr/skCrr/tokenCrr/endpointCrr and ak/sk/token/endpoint in the configuration file. <p>NOTICE</p> <p>After this function is enabled, both upload and download bandwidth are occupied.</p>
vlength	Optional (additional parameter)	<p>Verifies whether the object size in the destination bucket is the same as that in the source bucket after the copy task completes.</p> <p>NOTE</p> <p>This parameter must be used together with crr.</p>
vmd5	Optional (additional parameter)	<p>Verifies whether the MD5 value of the destination bucket is the same as that of the source bucket after the copy task completes.</p> <p>NOTE</p>

Parameter	Optional or Mandatory	Description
		<ul style="list-style-type: none">• This parameter must be used together with crr.• Objects in the source bucket must contain metadata x-obs-md5chksum. Otherwise, MD5 verification will be skipped. <p>After the MD5 value verification is successful, the parameter value is set to the destination object metadata x-obs-md5chksum, which is used for later MD5 verification during download or copy.</p>
u	Optional (additional parameter)	Indicates incremental copy. If this parameter is set, each object can be copied only when it does not exist in the destination bucket, its size is different from the namesake one in the destination bucket, or it has the latest modification time.
p	Optional (additional parameter)	Indicates the maximum number of concurrent multipart copy tasks when copying an object. The default value is the value of defaultParallels in the configuration file.
threshold	Optional (additional parameter)	<p>Indicates the threshold for enabling multipart copy, in bytes. The default value is the value of defaultBigfileThreshold in the configuration file.</p> <p>NOTE</p> <ul style="list-style-type: none">• If the size of the object to be copied is smaller than the threshold, copy the object directly. If not, a multipart copy is required.• If you copy an object directly, no part record is generated, and resumable transmission is not supported.• This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.
acl	Optional (additional parameter)	<p>Access control policies for destination objects that can be specified when copying objects. Possible values are:</p> <ul style="list-style-type: none">• private• public-read• public-read-write <p>NOTE</p> <p>The preceding three values indicate private read and write, public read, and public read and write.</p>
sc	Optional (additional parameter)	<p>Storage classes of the destination objects that can be specified when copying objects. Possible values are:</p> <ul style="list-style-type: none">• standard: OBS Standard, which features low access latency and high throughput, and is applicable to storing frequently accessed data (multiple accesses per month averagely) or

Parameter	Optional or Mandatory	Description
		<p>data that is smaller than 1 MB</p> <ul style="list-style-type: none">• warm: It is applicable to storing semi-frequently accessed (less than 12 times a year averagely) data that requires quick response.• cold: It is secure, durable, and inexpensive, and applicable to archiving rarely-accessed (once a year averagely) data.
meta	Optional (additional parameter)	<p>Metadata of destination objects that can be specified when copying objects. The format is <i>key1:value1#key2:value2#key3:value3</i>.</p> <p>NOTE</p> <p>The preceding value indicates that the destination objects in the bucket contain three groups of customized metadata after objects are copied: key1:value1, key2:value2, and key3:value3.</p>
ps	Optional (additional parameter)	<p>Indicates the size of each part in a multipart copy task, in bytes. The value ranges from 100 KB to 5 GB. The default value is the value of defaultPartSize in the configuration file.</p> <p>NOTE</p> <p>This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.</p>
cpd	Optional (additional parameter)	<p>Indicates the folder where the part records reside. The default value is .obsutil_checkpoint, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <p>A part record is generated during a multipart copy and saved to the copy subfolder. After the copy succeeds, its part record is deleted automatically. If the copy fails or is suspended, the system attempts to resume the task according to its part record when you perform the copy the next time.</p>
f	Optional (additional parameter)	<p>Runs in force mode.</p>
j	Optional (additional parameter)	<p>Indicates the maximum number of concurrent tasks for copying objects in batches. The default value is the value of defaultJobs in the configuration file.</p> <p>NOTE</p> <p>The value is ensured to be greater than or equal to 1.</p>
exclude	Optional (additional parameter)	<p>Indicates the matching patterns of source objects that are excluded, for example: *.txt.</p> <p>NOTE</p> <ul style="list-style-type: none">• The asterisk (*) represents any group of characters, and the question mark (?) represents any single

Parameter	Optional or Mandatory	Description
		<p>character. For instance, abc*.txt indicates any file whose name starts with abc and ends with .txt.</p> <ul style="list-style-type: none"> You can use * to represent * and \? to represent ?. If the name of the object to be copied matches the value of this parameter, the object is skipped. <p>NOTICE</p> <ul style="list-style-type: none"> You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows. The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt. This matching pattern applies only to objects whose names do not end with a slash (/).
include	Optional (additional parameter)	<p>Indicates the matching patterns of source objects that are included, for example: *.jpg.</p> <p>NOTE</p> <ul style="list-style-type: none"> The asterisk (*) represents any group of characters, and the question mark (?) represents any single character. You can use * to represent * and \? to represent ?. Only after identifying that the name of the file to be copied does not match the value of exclude, the system checks whether the file name matches the value of this parameter. If yes, the file is copied. If not, the file is skipped. <p>NOTICE</p> <ul style="list-style-type: none"> You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows. The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt. This matching pattern applies only to objects whose names do not end with a slash (/).
timeRange	Optional (additional parameter)	<p>Indicates the time range matching pattern when copying objects. Only objects whose last modification time is within the configured time range are copied.</p> <p>This pattern has a lower priority than the object</p>

Parameter	Optional or Mandatory	Description
		<p>matching patterns (exclude/include). That is, the time range matching pattern is executed after the configured object matching patterns.</p> <p>NOTE</p> <ul style="list-style-type: none">• The matching time range is represented in <i>time1-time2</i>, where <i>time1</i> must be earlier than or the same as <i>time2</i>. The time format is <i>yyyyMMddHHmmss</i>.• Automatic formatting is supported. For example, <i>yyyyMMdd</i> is equivalent to <i>yyyyMMdd000000</i>, and <i>yyyyMM</i> is equivalent to <i>yyyyMM01000000</i>.• If this parameter is set to <i>*-time2</i>, all files whose last modification time is earlier than <i>time2</i> are matched. If it is set to <i>time1-*</i>, all files whose last modification time is later than <i>time1</i> are matched. <p>NOTICE</p> <ul style="list-style-type: none">• Time in the matching pattern is the UTC time.• This matching pattern applies only to objects whose names do not end with a slash (/).
o	Optional (additional parameter)	<p>Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success, failure, and warning files) are generated in the folder. The default value is .obsutil_output, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <ul style="list-style-type: none">• The naming rule for result lists is as follows: cp_{succeed failed warning}_report_time_TaskId.txt <p>By default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.</p>
config	Optional (additional parameter)	<p>User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.</p>

Response

Refer to [Response](#) for uploading an object.

Running Example

- Take the Windows OS as an example. Run the **obsutil cp -recover=0476929d-9d23-4dc5-b2f8-0a0493f027c5 -f** command to copy objects in batches.

```
obsutil cp -recover=0476929d-9d23-4dc5-b2f8-0a0493f027c5 -f

Parallel:      3                Jobs:      3
Threshold:    524288000         PartSize:   5242880
Exclude:      false            Include:    false
VerifyLength: false            VerifyMd5: false
CheckpointDir: d:\temp\.obsutil checkpoint
OutputDir:    d:\temp\.obsutil output

[=====] 100.00% 10/s 0s
Succeed count is: 1          Failed count is: 0
Metrics [max cost:298 ms, min cost:192 ms, average cost:238.00 ms, average tps:9.71]
Task id is: f4c4f2b6-6e54-4dff-96b8-52e8c8c9a4b0
```

4.17 Resuming a Failed Download Task

Function

You can use this command to resume a failed download task based on the task ID.

Command Line Structure

- In Windows

```
obsutil cp -recover=xxx [-dryRun] [-tempFileDir=xxx] [-f] [-u] [-vlength] [-vmd5]
[-j=1] [-p=1] [-threshold=52428800] [-ps=5242880] [-include=*.xxx]
[-exclude=*.xxx] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

- In Linux or macOS

```
./obsutil cp -recover=xxx [-dryRun] [-tempFileDir=xxx] [-f] [-u] [-vlength] [-vmd5]
[-j=1] [-p=1] [-threshold=52428800] [-ps=5242880] [-include=*.xxx]
[-exclude=*.xxx] [-o=xxx] [-cpd=xxx] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
recover	Mandatory (additional parameter)	<p>ID of the download task to be resumed</p> <p>NOTE</p> <ul style="list-style-type: none">You can obtain the task ID after a download task is complete, or query it based on the file name of the operation result list, which is the 36 characters excluding the suffix .txt in the file name.You can locate the download task to be resumed in the directory where the result lists reside. For details about the directory of the result lists, see additional parameter o.

Parameter	Optional or Mandatory	Description
tempFileDir	Optional (additional parameter)	Indicates the directory for storing temporary files during download. The default value is the value of defaultTempFileDir in the configuration file. NOTE <ul style="list-style-type: none">Temporary files generated during multipart download are stored in this directory. Therefore, ensure that the user who executes obsutil has the write permission on the path.The available space of the partition where the path is located must be greater than the size of the objects to be downloaded.
dryRun	Optional (additional parameter)	Conducts a dry run.
u	Optional (additional parameter)	Indicates incremental download. If this parameter is set, each object can be downloaded only when it does not exist in the local path, its size is different from the namesake one in the local path, or it has the latest modification time.
vlength	Optional (additional parameter)	Checks whether the sizes of the local files are the same as those of the objects in the bucket after the download is complete.
vmd5	Optional (additional parameter)	Checks whether MD5 values of the local files are the same as those of the objects in the bucket after the download is complete. NOTE Objects in the bucket must contain metadata x-obs-md5chksum . Otherwise, MD5 verification will be skipped.
p	Optional (additional parameter)	Indicates the maximum number of concurrent multipart download tasks when downloading an object. The default value is the value of defaultParallels in the configuration file.
threshold	Optional (additional parameter)	Indicates the threshold for enabling multipart download, in bytes. The default value is the value of defaultBigfileThreshold in the configuration file. NOTE <ul style="list-style-type: none">If the size of the object to be downloaded is smaller than the threshold, download the object directly. If not, a multipart download is required.If you download an object directly, no part record is generated, and resumable transmission is not supported.This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.
ps	Optional (additional parameter)	Indicates the size of each part in a multipart download task, in bytes. The default value is the

Parameter	Optional or Mandatory	Description
		value of defaultPartSize in the configuration file. NOTE This value can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.
cpd	Optional (additional parameter)	Indicates the folder where the part records reside. The default value is .obsutil_checkpoint , the subfolder in the home directory of the user who executes obsutil commands. NOTE A part record is generated during a multipart download and saved to the down subfolder. After the download succeeds, its part record is deleted automatically. If the download fails or is suspended, the system attempts to resume the task according to its part record when you perform the download the next time.
f	Optional (additional parameter)	Runs in force mode.
j	Optional (additional parameter)	Indicates the maximum number of concurrent tasks for downloading objects in batches. The default value is the value of defaultJobs in the configuration file. NOTE The value is ensured to be greater than or equal to 1.
exclude	Optional (additional parameter)	Indicates the matching patterns of source objects that are excluded, for example: *.txt . NOTE <ul style="list-style-type: none">The asterisk (*) represents any group of characters, and the question mark (?) represents any single character. For instance, abc*.txt indicates any file whose name starts with abc and ends with .txt.You can use * to represent * and \? to represent ?.If the name of the object to be downloaded matches the value of this parameter, the object is skipped. NOTICE <ul style="list-style-type: none">You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt.This matching pattern applies only to objects whose names do not end with a slash (/).

Parameter	Optional or Mandatory	Description
include	Optional (additional parameter)	<p>Indicates the matching patterns of source objects that are included, for example: *.jpg.</p> <p>NOTE</p> <ul style="list-style-type: none">• The asterisk (*) represents any group of characters, and the question mark (?) represents any single character.• You can use * to represent * and \? to represent ?.• Only after identifying that the name of the file to be downloaded does not match the value of exclude, the system checks whether the file name matches the value of this parameter. If yes, the file is downloaded. If not, the file is skipped. <p>NOTICE</p> <ul style="list-style-type: none">• You are advised to use quotation marks for the matching pattern to prevent special characters from being escaped by the OS and leading to unexpected results. Use single quotation marks for Linux or macOS and quotation marks for Windows.• The matching pattern applies to the absolute path of an object, including the object name prefix and object name starting from the root directory. For example, if the path of an object in the bucket is obs://bucket/src1/src2/test.txt, then the absolute path of the object is src1/src2/test.txt.• This matching pattern applies only to objects whose names do not end with a slash (/).
timeRange	Optional (additional parameter)	<p>Indicates the time range matching pattern when downloading objects. Only objects whose last modification time is within the configured time range are downloaded.</p> <p>This pattern has a lower priority than the object matching patterns (exclude/include). That is, the time range matching pattern is executed after the configured object matching patterns.</p> <p>NOTE</p> <ul style="list-style-type: none">• The matching time range is represented in <i>time1-time2</i>, where <i>time1</i> must be earlier than or the same as <i>time2</i>. The time format is <i>yyyyMMddHHmmss</i>.• Automatic formatting is supported. For example, <i>yyyyMMdd</i> is equivalent to <i>yyyyMMdd000000</i>, and <i>yyyyMM</i> is equivalent to <i>yyyyMM01000000</i>.• If this parameter is set to <i>*-time2</i>, all files whose last modification time is earlier than <i>time2</i> are matched. If it is set to <i>time1-*</i>, all files whose last modification time is later than <i>time1</i> are matched. <p>NOTICE</p> <ul style="list-style-type: none">• Time in the matching pattern is the UTC time.• This matching pattern applies only to objects whose names do not end with a slash (/).

Parameter	Optional or Mandatory	Description
o	Optional (additional parameter)	<p>Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success, failure, and warning files) are generated in the folder. The default value is .obsutil_output, the subfolder in the home directory of the user who executes obsutil commands.</p> <p>NOTE</p> <ul style="list-style-type: none">The naming rule for result lists is as follows: cp_{succeed failed warning}_report_time_TaskId.txt <p>By default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.</p>
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Response

Refer to [Response](#) for uploading an object.

Running Example

- Take the Windows OS as an example. Run the **obsutil cp -recover=3066a4b0-4d21-4929-bb84-4829c32cbd0f d:\ -f -r** command to download objects in batches.

```
obsutil cp -recover=3066a4b0-4d21-4929-bb84-4829c32cbd0f -f -r

Parallel:      3                Jobs:      3
Threshold:    524288000         PartSize:   5242880
Exclude:      0                Include:   0
VerifyLength: false            VerifyMd5:  false
CheckpointDir: d:\temp\.obsutil checkpoint
OutputDir:    d:\temp\.obsutil output

[=====] 100.00% 155.59 KB/s 0s
Succeed count is: 1          Failed count is: 0
Metrics [max cost:153 ms, min cost:129 ms, average cost:92.00 ms, average tps:17.86]
Task id is: 19ad99ce-434e-41b2-9c8d-3af5b42eb65a
```

4.18 Listing Multipart Upload Tasks

Function

You can use this command to query multipart upload tasks in a bucket.

Command Line Structure

- In Windows

```
obsutil ls obs://bucket[/prefix] [-s] [-d] -m [-a] [-uploadIdMarker=xxx]  
[-marker=xxx] [-limit=1] [-config=xxx]
```

- In Linux or macOS

```
./obsutil ls obs://bucket[/prefix] [-s] [-d] -m [-a] [-uploadIdMarker=xxx]  
[-marker=xxx] [-limit=1] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
prefix	Optional	Object name prefix for listing multipart uploads NOTE If this parameter is left blank, all multipart upload tasks in the bucket are listed.
s	Optional (additional parameter)	Displays simplified query result. NOTE In the simplified format, the returned result contains only the object name and upload ID of the multipart upload.
d	Optional (additional parameter)	Lists only the multipart upload tasks and sub-directories in the current directory are listed, instead of recursively listing all the multipart upload tasks and sub-directories.
m	Mandatory (additional parameter)	Lists multipart upload tasks in the bucket.
a	Optional (additional parameter)	Lists the objects and the multipart upload tasks in the bucket.
marker	Optional (additional parameter)	Indicates the upload ID after which the multipart upload listing begins. All returned multipart upload tasks are listed in lexicographical order by object name involved in the tasks. NOTE For details about how to use this parameter, see 6.8 Examples of Listing Multipart Upload Tasks.
uploadIdMark	Optional (additional parameter)	Indicates the upload ID after which the multipart upload listing begins. This parameter must be used

Parameter	Optional or Mandatory	Description
er	parameter)	together with marker . All returned multipart upload tasks are listed in lexicographical order by object name and upload ID involved in the tasks.
limit	Optional (additional parameter)	Maximum number of objects that can be listed. If the value is less than or equal to 0 , all objects are listed. NOTE If there are a large number of multipart upload tasks in a bucket, you are advised to set this parameter to limit the number of multipart upload tasks each time. If not all tasks are listed, marker and uploadIdMarker of the next request will be returned in the result, which you can use to list the remaining tasks.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Running Example

- Take the Windows OS as an example. Run the **obsutil ls obs://bucket-test -m -limit=10** command to query the multipart upload tasks in the bucket.

```
obsutil ls obs://bucket-test -m -limit=10

Listing multipart uploads.

Upload list:
Key                               Initiated
StorageClass      UploadId
obs://bucket-test/aaa                               2018-11-27T03:49:07Z
standard          000001675348ED21860C3F61EF955BD3

obs://bucket-test/dir1/10GB.txt                     2018-11-07T06:58:09Z
standard          00000166ECF6CF7C860D1DBAF3F76013

obs://bucket-test/dir1/1GB.txt                      2018-11-07T06:58:09Z
standard          00000166ECF6CF6F860B7FBE95D01B03

obs://bucket-test/dir1/50GB.txt                     2018-11-07T06:58:09Z
standard          00000166ECF6CF86860D1DC2C8E8F66B

obs://bucket-test/dir1/5GB.txt                      2018-11-07T06:58:09Z
standard          00000166ECF6CF75860CDA7780CB52C3

obs://bucket-test/test11/20GB.txt                   2018-11-27T08:21:26Z
standard          0000016754423D24860CA8A4D06C2054

Folder number is: 0
Upload number is: 6
```

- For more examples, see 6.8 Examples of Listing Multipart Upload Tasks.

4.19 Deleting a Multipart Upload Task

Function

- You can use this command to delete a multipart upload task in a specified bucket by using the multipart upload ID.
- You can also use this command to delete multipart upload tasks in batches based on a specified object name prefix.

Command Line Structure

- In Windows

- Deleting a single multipart upload task

```
obsutil abort obs://bucket/key -u=xxx [-f] [-fr] [-o=xxx] [-config=xxx]
```

- Deleting multipart upload tasks in batches

```
obsutil abort obs://bucket[/key] -r [-f] [-o=xxx] [-j=1] [-config=xxx]
```

- In Linux or macOS

- Deleting a single multipart upload task

```
./obsutil abort obs://bucket/key -u=xxx [-f] [-fr] [-o=xxx] [-config=xxx]
```

- Deleting multipart upload tasks in batches

```
./obsutil abort obs://bucket[/key] -r [-f] [-o=xxx] [-j=1] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
bucket	Mandatory	Bucket name
key	Mandatory for deleting a multipart upload task. Optional for deleting multipart upload tasks in batches.	Indicates the object name involved in a multipart upload task to be deleted, or the name prefix of the objects involved in multipart upload tasks to be deleted in batches. NOTE If this parameter is left blank when deleting multipart upload tasks in batches, all multipart upload tasks in the bucket are deleted.
u	Mandatory for deleting a single multipart upload task (additional parameter)	ID of the multipart upload task to be deleted NOTE You can obtain the value of this parameter from 4.18 Listing Multipart Upload Tasks.
fr	Optional for deleting a single multipart upload task (additional parameter)	Generates an operation result list when deleting a multipart upload task.
f	Optional (additional parameter)	Runs in force mode.
r	Mandatory for deleting	Deletes multipart upload tasks in batches based

Parameter	Optional or Mandatory	Description
	multipart upload tasks (additional parameter)	on a specified object name prefix.
j	Optional for deleting multipart upload tasks (additional parameter)	Indicates the maximum number of concurrent tasks for deleting multipart uploads in batches. The default value is the value of defaultJobs in the configuration file. NOTE The value is ensured to be greater than or equal to 1.
o	Optional (additional parameter)	Indicates the folder where operation result lists reside. After the command is executed, result lists (possibly including success and failure files) are generated in the folder. The default value is .obsutil_output , the subfolder in the home directory of the user who executes obsutil commands. NOTE <ul style="list-style-type: none">The naming rule for result lists is as follows: abort_{succeed failed}_report_time_TaskId.txtBy default, the maximum size of a single result list is 30 MB and the maximum number of result lists that can be retained is 1024. You can set the maximum size and number by configuring recordMaxLogSize and recordBackups in the configuration file.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Response

Refer to [Response](#) for uploading an object.

Running Examples

- Take the Windows OS as an example. Run the **obsutil abort obs://bucket-test/key -u=xxx -f** command to delete a single multipart upload task.

```
obsutil abort obs://bucket-test/key -u=xxx -f
```

```
Abort multipart upload [key] in the bucket [bucket-test] successfully!
```

- Take the Windows OS as an example. Run the **obsutil abort obs://bucket-test -r -f** command to delete all multipart upload tasks in the bucket in batches.

```
obsutil abort obs://bucket-test -r -f
```

```
Listing multipart uploads to abort...
```

```
Aborting progress:[=====] 100.00% 3s
```

```
Succeed count is: 12      Failed count is: 0
```



```
Metrics [max cost:264 ms, min cost:54 ms, average cost:119.33 ms, average tps:19.70]  
Task id is: 0b34b1fa-b015-4313-a216-0fd5b4fffa1c
```

5 Auxiliary Commands

5.1 Updating a Configuration File

Function

You can use this command to update some configurations in the **.obsutilconfig** configuration file.

Command Line Structure

- In Windows
 - Updating configurations in interactive mode
- In Linux or macOS
 - Updating configurations in interactive mode

```
obsutil config [-interactive] [-crr] [-config=xxx]
```

```
./obsutil config [-interactive] [-crr] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
interactive	Optional (additional parameter)	Updates configurations in interactive mode. NOTICE You are advised to configure AK and SK in interactive mode for security purpose.
crr	Optional (additional parameter)	Updates the configurations related to client-side cross-region replication in the configuration file. NOTE If this parameter is set, fields in the configuration file corresponding to parameters e , i , k , and t are respectively changed to endpointCrr , akCrr , skCrr , and tokenCrr .
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Running Example

- Take the Windows OS as an example. Run the **obsutil config -interactive** command to set the access keys and endpoint of OBS.

```
obsutil config -interactive

Please input your ak:
xxxxxxxxxxxxxxxxxxxxxxxxxxxx
Please input your sk:
xxxxxxxxxxxxxxxxxxxxxxxxxxxx
Please input your endpoint:
xxxxxxxxxxxxxxxxxxxxxxxxxxxx
Please input your token:

Config file url:
  C:\Users\tools\.obsutilconfig

Update config file successfully!
```

5.2 Deleting Part Records

Function

You can use this command to delete part records from a specified directory.

Command Line Structure

- In Windows

```
obsutil clear [checkpoint_dir] [-u] [-d] [-c] [-config=xxx]
```

- In Linux or macOS

```
./obsutil clear [checkpoint_dir] [-u] [-d] [-c] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
checkpoint_dir	Optional	Indicates the folder where the part records reside. The default value is .obsutil_checkpoint , the same subfolder where obsutil commands reside.
u	Optional (additional parameter)	Deletes the part records of all multipart upload tasks. NOTE At the same time, the system attempts to delete the multipart upload tasks in the part records.
d	Optional (additional parameter)	Deletes the part records of all multipart download tasks. NOTE At the same time, the system attempts to delete the fragments

Parameter	Optional or Mandatory	Description
		in the part records.
c	Optional (additional parameter)	Deletes the part records of all multipart copy tasks. NOTE At the same time, the system attempts to delete the multipart copy tasks in the part records.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

**NOTE**

You must configure at least one among the **u**, **d** and **c** parameters.

Running Example

- Take the Windows OS as an example. Run the **obsutil clear -u** command to delete the part records of multipart upload tasks in the default directory.

```
obsutil clear -u
```

```
Clear checkpoint files for uploading in folder [xxxxxx]
```

```
[=====] 100.00% 0s
```

```
Succeed files is: 1 Failed files is: 0
```

5.3 Viewing Command Help Information

Function

You can use this command to view the commands supported by obsutil or view the help information of a specific command.

Command Line Structure

- In Windows

```
obsutil help [command]
```

- In Linux or macOS

```
./obsutil help [command]
```

Parameter Description

Parameter	Optional or Mandatory	Description
command	Optional	Views the help information of a specific command.

Running Example

- Take the Windows OS as an example. Run the **obsutil help mb** command to view the help information about the command for creating a bucket.

```
obsutil help mb

Summary:
  create a bucket with the specified parameters

Syntax:
  obsutil mb obs://bucket [-acl=xxx] [-sc=xxx] [-location=xxx]

Options:
  -acl=xxx
    the acl of the bucket, possible values are [private|public-read|public-read-write]
  -sc=xxx
    the default storage class of the bucket, possible values are [standard|warm|cold]
  -location=xxx
    the location where the bucket to be created
```

5.4 Querying the Version Number

Function

You can use this command to query the current version of obsutil.

Command Line Structure

- In Windows

```
obsutil version
```

- In Linux or macOS

```
./obsutil version
```

Running Example

Take the Windows OS as an example.

```
obsutil version

obsutil version:5.1.4, obssdk version:2.2.9
operating system:windows, arch:amd64
```

5.5 Archiving Log Files

Function

You can use this command to archive log files to a local PC or to a specified bucket.

Command Line Structure

- In Windows

- Archiving to a local PC

```
obsutil archive [file_or_folder_url] [-config=xxx]
```

- Archiving to a specified bucket

```
obsutil archive obs://bucket[/key] [-config=xxx]
```

- In Linux or macOS

- Archiving to a local PC

```
obsutil archive [file_or_folder_url] [-config=xxx]
```

- Archiving to a specified bucket

```
obsutil archive obs://bucket[/key] [-config=xxx]
```

Parameter Description

Parameter	Optional or Mandatory	Description
file_or_folder_url	Optional	<p>Indicates the path to which log files are archived. The rules are as follows:</p> <ul style="list-style-type: none">• If this parameter is left blank, log files are archived to the same directory where obsutil commands reside with obsutil_log.zip as the archive file name.• If this parameter specifies a file or folder path that does not exist, the tool checks whether the value ends with a slash (/) or backslash (\). If yes, a folder is created based on the path, and log files are archived to the newly created directory with obsutil_log.zip as the archive file name.• If this parameter specifies a file or folder path that does not exist and the value does not end with a slash (/) or backslash (\), log files are archived to a local PC with the value as the archive file name.• If this parameter specifies an existing .zip file, then log files are archived to a local PC overwriting the existing file, with the value as the archive file name.• If this parameter specifies an existing folder, then log files are archived to the specified directory with obsutil_log.zip as the archive file name. <p>NOTE All archive files are .zip files.</p>
bucket	Mandatory for archiving log files to a specified bucket	Bucket name
key	Optional for archiving log files to	Indicates the object name or object name prefix when archiving log files to a specified bucket.

Parameter	Optional or Mandatory	Description
	a specified bucket	The rules are as follows: <ul style="list-style-type: none">• If this parameter is left blank, log files are archived to the root directory of the bucket with obsutil_log.zip as the object name.• If the value ends with a slash (/), the value is used as the object name prefix when archiving log files, and the object name is the value plus obsutil_log.zip. Otherwise, log files are archived with the value as the object name.
config	Optional (additional parameter)	User-defined configuration file for executing a command. For details about parameters that can be configured, see A Parameter Description.

Running Example

- Take the Windows OS as an example. Run the **obsutil archive** command to archive log files to the same directory where the tool is executed.

```
obsutil archive
```

```
[-----] 100.00% 15/15 35ms  
Succeed to archive log files to [D:\obsutil\obsutil_log.zip]
```

6 Common Examples

6.1 Upload Examples

Assume that a local folder is in the following structure:

```
└─ src1
   └─ src2
      ├── test1.txt
      └─ test2.txt
   └─ src3
      └─ test3.txt
```

Based on the preceding folder structure, different upload scenarios require different commands.

- To upload the **test3.txt** file in the local **src1** folder to the root directory of bucket **bucket-test**, the command is as follows:

```
obsutil cp /src1/test3.txt obs://bucket-test
```

After the upload is successful, the following object is generated in the bucket:

```
obs://bucket-test/test3.txt
```

- To upload the **test3.txt** file in the local **src1** folder to the root directory of bucket **bucket-test** and rename it to **aaa.txt**, the command is as follows:

```
obsutil cp /src1/test3.txt obs://bucket-test/aaa.txt
```

After the upload is successful, the following object is generated in the bucket:

```
obs://bucket-test/aaa.txt
```

- To upload the **test3.txt** file in the local **src1** folder to the **src** folder in bucket **bucket-test**, the command is as follows:

```
obsutil cp /src1/test3.txt obs://bucket-test/src/
```

After the upload is successful, the following object is generated in the bucket:

```
obs://bucket-test/src/test3.txt
```

- To recursively upload the entire local **src2** folder to the root directory of bucket **bucket-test** in force mode, the command is as follows:

```
obsutil cp /src1/src2 obs://bucket-test -r -f
```

After the upload is successful, the following objects are generated in the bucket:


```
obs://bucket-test/src2/  
obs://bucket-test/src2/test1.txt  
obs://bucket-test/src2/test2.txt
```

- To recursively upload the entire local **src1** folder to the **src** folder in bucket **bucket-test** in force mode, the command is as follows:

```
obsutil cp /src1 obs://bucket-test/src -r -f
```

After the upload is successful, the following objects are generated in the bucket:

```
obs://bucket-test/src/src1/  
obs://bucket-test/src/src1/src2/  
obs://bucket-test/src/src1/src2/test1.txt  
obs://bucket-test/src/src1/src2/test2.txt  
obs://bucket-test/src/src1/src3/  
obs://bucket-test/src/src1/test3.txt
```

- To recursively upload the all files and subfolders in the local **src1** folder to the **src** folder in bucket **bucket-test** in force mode, the command is as follows:

```
obsutil cp /src1 obs://bucket-test/src -r -f -flat
```

After the upload is successful, the following objects are generated in the bucket:

```
obs://bucket-test/src/  
obs://bucket-test/src/src2/  
obs://bucket-test/src/src2/test1.txt  
obs://bucket-test/src/src2/test2.txt  
obs://bucket-test/src/src3/  
obs://bucket-test/src/test3.txt
```

**NOTE**

All the commands in the preceding examples use the Windows OS as the running environment.

6.2 Synchronous Upload Examples

Assume that a local folder is in the following structure:

```
└─ src1  
  └─ src2  
    └─ test1.txt  
      └─ test2.txt  
  └─ src3  
    └─ test3.txt
```

Assume that bucket **bucket-test** contains the following objects:

```
obs://bucket-test/src1/  
obs://bucket-test/src1/src2/  
obs://bucket-test/src1/src2/test1.txt  
obs://bucket-test/src1/src3/
```

Based on the structure of the preceding local folder and objects in the bucket, different synchronous upload scenarios require different commands.

- To synchronize the **test3.txt** file in the local **src1** folder to the root directory of bucket **bucket-test**, the command is as follows:

```
obsutil sync /src1/test3.txt obs://bucket-test
```

After the synchronization is successful, the **test3.txt** file is directly uploaded to the bucket because there is no **test3.txt** in bucket **bucket-test**. Then, objects in the bucket are as follows:

```
obs://bucket-test/test3.txt
obs://bucket-test/src1/
obs://bucket-test/src1/src2/
obs://bucket-test/src1/src2/test1.txt
obs://bucket-test/src1/src3/
```

- To synchronize all files and subfolders in the local **src1** folder to the **src** folder in bucket **bucket-test**, the command is as follows:

```
obsutil sync /src1 obs://bucket-test/src1
```

After the synchronization, the objects in the bucket are as follows:

```
obs://bucket-test/src1/
obs://bucket-test/src1/test3.txt
obs://bucket-test/src1/src2/
obs://bucket-test/src1/src2/test1.txt
obs://bucket-test/src1/src2/test2.txt
obs://bucket-test/src1/src3/
```

**NOTE**

All the commands in the preceding examples use the Windows OS as the running environment.

6.3 Download Examples

Assume that bucket **bucket-test** contains the following objects:

```
obs://bucket-test/test1.txt
obs://bucket-test/test2.txt
obs://bucket-test/test3.txt
obs://bucket-test/test4.txt
obs://bucket-test/test5.txt
obs://bucket-test/test6.txt
obs://bucket-test/src1/
obs://bucket-test/src1/test7.txt
obs://bucket-test/src2/
obs://bucket-test/src2/test8.txt
obs://bucket-test/src2/src3/
obs://bucket-test/src2/src3/test9.txt
```

Based on the structure of objects in the bucket, different download scenarios require different commands.

- To download the **test1.txt** file from bucket **bucket-test** to the local **src1** folder, the command is as follows:

```
obsutil cp obs://bucket-test/test1.txt /src1
```

After the download is complete, the following file is generated on the local PC:

```
└─ src1
   └─ test1.txt
```

- Run the following command to download the **test1.txt** file to your local PC. If there is no **test.txt** on the local PC, the **test1.txt** file is directly downloaded and you can rename it to **test.txt**. If **test.txt** already exists, **test1.txt** is downloaded and overwrites the original local **test.txt** file after renaming.

```
obsutil cp obs://bucket-test/test1.txt /test.txt
```

After the download is complete, the following file generated on the local PC:

```
└─ test.txt
```

- To recursively download the entire **src2** folder from bucket **bucket-test** to the local **src1** folder in force mode, the command is as follows:

```
obsutil cp obs://bucket-test/src2 /src1 -r -f
```

After the download is complete, the following files are generated on the local PC:

```
└─ src1
  └─ src2
    ├── src3
    │   └─ test9.txt
    └─ test8.txt
```

- To recursively download all files and subfolders in the **src2** folder from bucket **bucket-test** to the local **src1** folder in force mode, the command is as follows:

```
obsutil cp obs://bucket-test/src2 /src1 -r -f -flat
```

After the download is complete, the following files are generated on the local PC:

```
└─ src1
  ├── src3
  │   └─ test9.txt
  └─ test8.txt
```

- To recursively download the all objects in bucket **bucket-test** to the local **src0** folder in force mode, the command is as follows:

```
obsutil cp obs://bucket-test /src0 -r -f
```

After the download is complete, the following files are generated on the local PC:

```
└─ src0
  ├── test1.txt
  ├── test2.txt
  ├── test3.txt
  ├── test4.txt
  ├── test5.txt
  ├── test6.txt
  ├── src1
  │   └─ test7.txt
  └─ src2
    ├── src3
    │   └─ test9.txt
    └─ test8.txt
```

**NOTE**

All the commands in the preceding examples use the Windows OS as the running environment.

6.4 Synchronous Download Examples

Assume that bucket **bucket-test** contains the following objects:

```
obs://bucket-test/src1/
obs://bucket-test/src1/test3.txt
obs://bucket-test/src1/src2/
obs://bucket-test/src1/src2/test1.txt
```

```
obs://bucket-test/src1/src2/test2.txt
obs://bucket-test/src1/src3/
```

Assume that a local folder is in the following format:

```
└─ src1
   └─ test3.txt
```

Based on the structure of the preceding local folder and objects in the bucket, different synchronous download scenarios require different commands.

- To synchronize all files and subfolders in the **src1** folder in bucket **bucket-test** to the local **src1** folder, the command is as follows:

```
obsutil sync obs://bucket-test/src1 /src1
```

After the synchronization is successful, the following files are generated in the local **src1** folder:

```
└─ src1
   └─ src2
      └─ test1.txt
         └─ test2.txt
   └─ src3
      └─ test3.txt
```

**NOTE**

All the commands in the preceding examples use the Windows OS as the running environment.

6.5 Copy Examples

Assume that bucket **bucket-src** contains the following objects:

```
obs://bucket-src/test1.txt
obs://bucket-src/test2.txt
obs://bucket-src/test3.txt
obs://bucket-src/test4.txt
obs://bucket-src/test5.txt
obs://bucket-src/test6.txt
obs://bucket-src/src1/
obs://bucket-src/src1/test7.txt
obs://bucket-src/src2/
obs://bucket-src/src2/test8.txt
obs://bucket-src/src2/src3/
obs://bucket-src/src2/src3/test9.txt
```

Based on the structure of objects in the bucket, different copy scenarios require different commands.

- To copy the **test1.txt** file from bucket **bucket-src** to bucket **bucket-dest**, the command is as follows:

```
obsutil cp obs://bucket-src/test1.txt obs://bucket-dest
```

After the copy is complete, the following object is generated in bucket **bucket-dest**:

```
obs://bucket-dest/test1.txt
```

- To copy the content of the **test1.txt** file in bucket **bucket-src** to the **test.txt** file in bucket **bucket-dest**, the command is as follows:

```
obsutil cp obs://bucket-src/test1.txt obs://bucket-dest/test.txt
```

After the copy is complete, the following object is generated in bucket **bucket-dest**:

```
obs://bucket-dest/test.txt
```

- To copy the **test1.txt** file in bucket **bucket-src** to the **test** folder in bucket **bucket-dest**, the command is as follows:

```
obsutil cp obs://bucket-src/test1.txt obs://bucket-dest/test/
```

After the copy is complete, the following object is generated in bucket **bucket-dest**:

```
obs://bucket-dest/test/test1.txt
```

- Run the following command to recursively copy the entire **src2** folder in bucket **bucket-src** to bucket **bucket-dest** in force mode:

```
obsutil cp obs://bucket-src/src2 obs://bucket-dest -r -f
```

After the copy is complete, the following objects are generated in bucket **bucket-dest**:

```
obs://bucket-dest/src2/  
obs://bucket-dest/src2/test8.txt  
obs://bucket-dest/src2/src3/  
obs://bucket-dest/src2/src3/test9.txt
```

- To recursively copy all files and subfolders in the **src2** folder in bucket **bucket-src** to bucket **bucket-dest** in force mode, the command is as follows:

```
obsutil cp obs://bucket-src/src2 obs://bucket-dest/prefix -r -f -flat
```

After the copy is complete, the following objects are generated in bucket **bucket-dest**:

```
obs://bucket-dest/test8.txt  
obs://bucket-dest/src3/  
obs://bucket-dest/src3/test9.txt
```

**NOTE**

All the commands in the preceding examples use the Windows OS as the running environment.

6.6 Synchronous Copy Examples

Assume that the source bucket **bucket-src** contains the following objects:

```
obs://bucket-src/src1/  
obs://bucket-src/src1/test3.txt  
obs://bucket-src/src1/src2/  
obs://bucket-src/src1/src2/test1.txt  
obs://bucket-src/src1/src2/test2.txt  
obs://bucket-src/src1/src3/
```

Assume that the destination bucket **bucket-dest** contains the following objects:

```
obs://bucket-dest/src1/  
obs://bucket-dest/src1/test3.txt
```

Based on the structure of objects in the bucket, different synchronous copy scenarios require different commands.

- To synchronize all files and subfolders in the **src1** folder in bucket **bucket-src** to the **src1** folder in bucket **bucket-dest**, the command is as follows:

```
obsutil sync obs://bucket-src/src1 obs://bucket-dest/src1
```

After the synchronous copy is complete, the objects in the destination bucket **bucket-dest** are as follows:

```
obs://bucket-dest/src1/  
obs://bucket-dest/src1/test3.txt  
obs://bucket-dest/src1/src2/  
obs://bucket-dest/src1/src2/test1.txt  
obs://bucket-dest/src1/src2/test2.txt  
obs://bucket-dest/src1/src3/
```

**NOTE**

All the commands in the preceding examples use the Windows OS as the running environment.

6.7 List Examples

Assume that bucket **bucket-test** contains the following objects:

```
obs://bucket-test/test1.txt  
obs://bucket-test/test2.txt  
obs://bucket-test/test3.txt  
obs://bucket-test/test4.txt  
obs://bucket-test/test5.txt  
obs://bucket-test/test6.txt  
obs://bucket-test/src1/  
obs://bucket-test/src1/test7.txt  
obs://bucket-test/src2/  
obs://bucket-test/src2/test8.txt
```

Based on the structure of objects in the bucket, different object listing scenarios require different commands.

- To list three objects in bucket **bucket-test**, the command is as follows:

```
obsutil ls obs://bucket-test -limit=3
```

The returned result is listed in lexicographical order by object name and version ID as follows:

```
obs://bucket-test/test1.txt  
obs://bucket-test/test2.txt  
obs://bucket-test/test3.txt
```

- To list three objects following **test3.txt** in bucket **bucket-test**, the command is as follows:

```
obsutil ls obs://bucket-test -limit=3 -marker=test3.txt
```

The returned result is listed in lexicographical order by object name and version ID as follows:

```
obs://bucket-test/test4.txt  
obs://bucket-test/test5.txt  
obs://bucket-test/test6.txt
```

- To list the files and subdirectories in the root directory of bucket **bucket-test** in non-recursive mode, that is, files in the subdirectories are not listed, the command is as follows:

```
obsutil ls obs://bucket-test -d
```

The returned result is listed in lexicographical order by object name and version ID as follows:

```
obs://bucket-test/test1.txt  
obs://bucket-test/test2.txt
```

```
obs://bucket-test/test3.txt
obs://bucket-test/test4.txt
obs://bucket-test/test5.txt
obs://bucket-test/test6.txt
obs://bucket-test/src1/
obs://bucket-test/src2/
```

**NOTE**

All the commands in the preceding examples use the Windows OS as the running environment.

6.8 Examples of Listing Multipart Upload Tasks

Assume that bucket **bucket-test** contains the following multipart upload tasks:

```
obs://bucket-test/task1.txt uploadid1
obs://bucket-test/task1.txt uploadid2
obs://bucket-test/task2.txt uploadid3
obs://bucket-test/task3.txt uploadid4
obs://bucket-test/src1/
obs://bucket-test/src1/task4.txt uploadid5
obs://bucket-test/src2/
obs://bucket-test/src2/task5.txt uploadid6
```

- Run the following command to list three multipart upload tasks in bucket **bucket-test**:

```
obsutil ls obs://bucket-test -m -limit=3
```

The returned result is listed in lexicographical order by object name as follows:

```
obs://bucket-test/task1.txt uploadid1
obs://bucket-test/task1.txt uploadid2
obs://bucket-test/task2.txt uploadid3
```

- To list the rest multipart upload tasks following **uploadid1**, the command is as follows:

```
obsutil ls obs://bucket-test -m -limit=3 -marker=task1.txt
-uploadIdMarker=uploadid1
```

The returned result is listed in lexicographical order by object name and upload ID as follows:

```
obs://bucket-test/task1.txt uploadid2
obs://bucket-test/task2.txt uploadid3
obs://bucket-test/task3.txt uploadid4
```

**NOTE**

All the commands in the preceding examples use the Windows OS as the running environment.

7 Fault Locating

7.1 Overview

obsutil provides multiple methods for users to locate and analyze faults. Table 7-1 details the methods. Generally, you need to combine these methods for a precise fault locating.

Table 7-1 Fault locating methods

Method	Description
7.2 Log Files	obsutil log files include tool logs and SDK logs. The tool logs record the success information and exceptions generated during obsutil running. The SDK logs record the success information and exceptions generated during requesting for OBS.
7.3 Result Lists	Result lists are generated after batch tasks complete and may include success, failure, and warning files.
7.4 Return Codes	obsutil yields different return codes based on different execution results. You can analyze and troubleshoot faults according to these return codes.

7.2 Log Files

Configuring Log Files

obsutil log files include tool logs and SDK logs. You can add the following parameters to the **.obsconfigutil** file to enable the two logging functions.

- Tool logging (records the log information generated during obsutil running): configure **utilLogPath**, **utilLogBackups**, **utilLogLevel**, and **utilMaxLogSize**.
- SDK logging (records the log information generated when using obsutil to call OBS server-side APIs): configure **sdkLogPath**, **sdkLogBackups**, **sdkLogLevel**, and **sdkMaxLogSize**.



NOTE

- For details about the parameter description, see A Parameter Description.

- **utilLogPath** and **sdkLogPath** indicate the absolute paths of the log files, not the folders that store the log files.
- If **utilLogPath** and **sdkLogPath** are not specified, tool logging and SDK logging are not enabled, and therefore no log file is generated during obsutil running.
- Log files that are rolled over are named as follows: *filename.log.number*

NOTICE

If multiple obsutil processes are running at the same time, log files may fail to be written concurrently or may be lost. In this case, add parameter **-config** when running commands to configure an independent configuration file for each process. Make sure that **utilLogPath** and **sdkLogPath** are set to different paths for each process.

Collecting Log Files

You can collect logs in either of the following methods:

Method 1: Use auxiliary commands by referring to 5.5 Archiving Log Files.

Method 2: Locate the paths specified by **utilLogPath** and **sdkLogPath** in the configuration file, and then search for the log files in the corresponding paths in the local file system.

7.3 Result Lists

Configuring Result Lists

Result lists are generated when batch tasks complete. By default, they are saved to the subfolder **.obsutil_output** in the home directory of the user who executes obsutil commands. You can specify another folder to save them by setting the additional parameter **-o** when executing a command.

Viewing Result Lists

Result lists are classified into success, failure, and warning lists. The naming rule is as follows: *Operation_{succeed | failed | warning}_report_Time_TaskId.txt*. For example, after a folder is successfully uploaded, the result list is named as follows: **cp_succeed_report_20190417021908_fbbc83e3-98ac-4d19-b23a-64023b1e0c34.txt**.

**NOTE**

- If the number of successes, failures, or warnings is zero, the corresponding result list is not generated.
- The task ID of a result list is unique for each operation.
- The maximum size of a result list is 30 MB and the maximum number of lists that can be retained is 1024.

7.4 Return Codes

If obsutil is invoked by processes, the command output cannot be viewed in real time. obsutil generates different return codes based on different execution results. Table 7-2 describes the

return codes. You can use either the following methods to obtain the return code of the latest execution result and then analyze and rectify the fault based on it:

- In the macOS or Linux OS, run the following command to obtain the return code of the latest execution result:

```
echo $?
```

- In the Windows OS, run the following command to obtain the return code of the latest execution result:

```
echo %errorlevel%
```

Table 7-2 Return codes

Return Code	Meaning	Example Scenario
0	Execution succeeded.	An object is successfully uploaded.
1	The file does not exist.	The entered file path does not exist for uploading a file by running the cp command.
2	The task does not exist.	The specified task ID does not exist for resuming a failed upload task by running the cp command.
3	Parameter error	<ul style="list-style-type: none">• At least one entered additional parameters is not supported for uploading a file by running the cp command.• The entered value of cloud_url is invalid for downloading a file by running the cp command. <p>NOTE</p> <p>cloud_url indicates the bucket path or object path. Set cloud_url in the format of obs://bucketname when downloading all objects in a bucket. Set cloud_url in the format of obs://bucketname/key when downloading a specified object in a bucket.</p>
4	Bucket status error	The specified destination bucket does not exist for uploading a folder by running the cp command.
5	Initialization error during command execution	<ul style="list-style-type: none">• An error occurs when loading the configuration file.• Parameter -o is configured when running the cp command to upload a folder, but the folder specified by -o for saving the result lists fails to be created.
6	Execution error.	When you run the ls command to query the bucket list, the query fails because the network times out.
7	The operation is not supported.	The version of the bucket is not 3.0 when you attempt to change the properties of an object in it by running the chattri command.
8	A batch task	Some objects fail to be downloaded during a

Return Code	Meaning	Example Scenario
	succeeded partially.	batch download by running the cp command.
9	Interruption error	Users press Ctrl + C to interrupt the command execution.
-1	Unknown error	-

8 Best Practices

8.1 Configuring Scheduled Tasks Using the Crontab Command

Scenario

Go to the **/root** directory at 21:30 every day and upload the **/src/src1** folder to bucket **obs://bucket-test** in the incremental mode.

Prerequisites

You have properly enabled the scheduled crond service in the Linux OS.



NOTE

Run the **service crond status** command to check whether the service is enabled.

Procedure

Step 1 Run the **crontab -e** command to open the configuration file for setting a scheduled task.

Step 2 Enter the Insert mode to edit the configuration file.

```
30 21 * * * cd /root && nohup ./obsutil cp /src/src1 obs://bucket-test -r -f -u
&>obsutil_crond.log &
```



NOTE

Assume that the obsutil tool is in the **/root** directory. The preceding configuration is described as follows:
Go to the **/root** directory at 21:30 every day, upload the **/src/src1** folder to bucket **obs://bucket-test** in incremental mode, and redirect the command output to the **obsutil_crond.log** file in the **/root** directory.

Step 3 Press **Esc** to exit the Insert mode. Then input **:wq** and press **Enter** to save the configuration and exit.

Step 4 Run the **crontab -l** command to check whether the scheduled task is configured successfully.

----End

FAQs

1. How do I determine whether a scheduled task is being executed?

- Run the **tail /var/log/cron** command to view the latest scheduled task execution records.
 - Run the **ps -ef | grep obsutil** command to check whether obsutil is being executed.
2. How do I forcibly stop an ongoing scheduled task?
- a. Run the **ps -ef | grep obsutil** command to check the process of obsutil.
 - b. Run the **kill -9 PID** command to forcibly stop the process, where *PID* indicates the queried process ID.

8.2 Fine-Tuning obsutil Performance

By default, obsutil uploads, downloads, and copies files or objects whose size is greater than 10 MB in multiple parts. Table 8-1 details related parameters in the **.obsutilconfig** file.

Table 8-1 Multipart-related parameters

Parameter	Description
defaultBigfileThreshold	Indicates the threshold for triggering multipart tasks, in bytes. If the size of a file to be uploaded, downloaded, or copied is greater than the threshold, the file is uploaded, downloaded, or copied in multiple parts. The default value is 10 MB.
defaultPartSize	Size of each part, in bytes. The default value is 5 MB. NOTE <ul style="list-style-type: none">• For multipart upload and copy, the value ranges from 100 KB to 5 GB.• For multipart download, the value is unrestricted.
defaultParallels	Maximum number of concurrent tasks in the multipart mode. The default value is 5.

Generally, multipart tasks not only speed up transmission but also allow you to resume failed tasks. obsutil has the multipart-related parameters all configured with default values. Modify them based on actual file size or network status as required to optimize transmission efficiency and to ensure successful transmission.

Adjust the number of concurrent tasks in the multipart mode according to the following formula:

Value of **defaultParallels** = (Destination object size/Value of **defaultPartSize**) x 1.5

In the upload, download, and copy commands, parameters **-p** and **-ps** are used to modify the number of concurrent tasks in the multipart mode and part size respectively, and then deliver the multipart task based on the parameter values configured in the command. The default values in the configuration file are used if you do not set them in a command.

Adjust the number of concurrent tasks in the multipart mode according to the following formula:

Value of **p** = (Destination object size/Value of **ps**) x 1.5



NOTE

- Resources of a running host are limited. Therefore, if the number of concurrent tasks in the multipart mode is set too large, the performance of obsutil upload, download, or copy may deteriorate due to resource switchover and preemption between threads. In this case, you need to adjust the values of **defaultParallels (-p)** and **defaultPartSize (-ps)** based on the actual file size and network status. To perform a pressure test, lower the two values at first, and then gradually increase them to determine the optimal values.
- If the values of **defaultParallels (-p)** and **defaultPartSize (-ps)** are too large, an EOF error may occur due to network instability. In this case, set the two parameters to smaller values.
- If a batch operation is performed, the destination object size can be set to the average size of the objects to be operated.

A

Parameter Description

You can use the **.obsutilconfig** file to configure the parameters of obsutil. The following table lists detailed information about the parameters.

Table A-1 obsutil parameters

Parameter	Optional or Mandatory	Description	Recommended Value
endpoint	Mandatory	Endpoint for accessing OBS, which can contain the protocol type, domain name, and port number. Example: http://your-endpoint:80 NOTE <ul style="list-style-type: none">If the configured endpoint does not contain any protocol, the HTTPS protocol is used by default.	N/A
ak	Mandatory	Access key ID	N/A
sk	Mandatory	Secret access key	N/A
endpointCrr	Optional	Endpoint for accessing OBS in the region where the source bucket resides when the client-side cross-region replication function is enabled, which can contain the protocol type, domain name, and port number. Example: http://your-endpoint:80 NOTE <ul style="list-style-type: none">If the configured endpoint does not contain any protocol, the HTTPS protocol is used by default.	N/A
akCrr	Optional	AK for the source bucket when the client-side cross-region replication function is enabled	N/A
skCrr	Optional	SK for the source bucket when the client-side cross-region replication function is enabled	N/A

Parameter	Optional or Mandatory	Description	Recommended Value
token	Optional	Security token. If this parameter is left blank, the security token is not set.	N/A
connectTimeout	Optional	Timeout interval for establishing an HTTP/HTTPS connection, in seconds. The default value is 30.	The recommended value ranges from 5 to 120.
socketTimeout	Optional	Timeout interval for reading and writing data, in seconds. The default value is 310.	The recommended value ranges from 5 to 600.
maxRetryCount	Optional	Maximum number of retry attempts. The default value is 1.	The recommended value ranges from 0 to 5.
maxConnections	Optional	Maximum number of HTTP connections that can be accessed. The default value is 1000.	N/A
defaultBigfileThreshold	Optional	Indicates the threshold for triggering multipart tasks, in bytes. If the size of a file to be uploaded, downloaded, or copied is greater than the threshold, the file is uploaded, downloaded, or copied in multiple parts. The default value is 10 MB.	It is recommended that the value be greater than 5 MB.
defaultPartSize	Optional	Size of each part, in bytes. The default value is 5 MB. NOTE <ul style="list-style-type: none">For multipart upload and copy, the value ranges from 100 KB to 5 GB.For multipart download, the value is unrestricted.	The recommended value ranges from 5 MB to 100 MB.
defaultParallelism	Optional	Maximum number of concurrent tasks in the multipart mode. The default value is 5.	Set this parameter according to 8.2 Fine-Tuning obsutil Performance.
defaultJobs	Optional	Maximum number of concurrent tasks in batches. The default value is 5. NOTE Batch tasks include uploading, downloading, and copying folders, as well as restoring and deleting objects in batches.	The recommended value ranges from 1 to 200.
defaultJobsCacheCount	Optional	Cache size of a batch task queue, indicating the maximum number of tasks that can be cached. The default	Default value

Parameter	Optional or Mandatory	Description	Recommended Value
		value is 1000000. NOTE More cached tasks consume more memory resources. Therefore, you are advised to adjust the value of this parameter based on site requirements.	
rateLimitThreshold	Optional	Indicates the traffic control threshold of an upload or download request, in bytes. The default value is 0, indicating that traffic is not limited. The minimum value is 10 KB.	It is recommended that the value be greater than 100 KB.
sdkLogBackups	Optional	Maximum number of SDK log files that can be retained. The default value is 10.	N/A
sdkLogLevel	Optional	SDK log level. Possible values are: <ul style="list-style-type: none">• DEBUG• INFO• WARN• ERROR The default value is WARN .	N/A
sdkLogPath	Optional	Indicates the absolute path of SDK logs. The value must be a file path. The default value is the path of the obs_sdk.log file in the subfolder obsutil_log of the user's home directory (HOME in Linux or macOS and C:\Users\<Username> in Windows). NOTE <ul style="list-style-type: none">• If this parameter is left blank, no SDK log is generated.• The path must be a file path and cannot be a folder path.• After the SDK log function is enabled, all logs of requests to OBS are saved in the SDK log file for problem analysis and location.• Ensure that the user who runs the command has the read and write permissions on the path. NOTICE If multiple obsutil processes are running at the same time, log files may fail to be written concurrently or may be lost. In this case, add parameter -config when running commands to configure an independent configuration file for each process.	N/A

Parameter	Optional or Mandatory	Description	Recommended Value
sdkMaxLogSize	Optional	Size of an SDK log file, in bytes. The default value is 30 MB.	The recommended value ranges from 10 MB to 100 MB.
utilLogBackups	Optional	Maximum number of obsutil log files that can be retained. The default value is 10.	N/A
utilLogLevel	Optional	obsutil log level. Possible values are: <ul style="list-style-type: none">• DEBUG• INFO• WARN• ERROR The default value is INFO .	N/A
utilLogPath	Optional	<p>Indicates the absolute path of obsutil logs. The value must be a file path. The default value is the path of the obsutil.log file in the subfolder .obsutil_log of the user's home directory (HOME in Linux or macOS and C:\Users\<Username> in Windows).</p> <p>NOTE</p> <ul style="list-style-type: none">• If this parameter is left blank, no obsutil log is generated.• The path must be a file path and cannot be a folder path.• After the obsutil log function is enabled, all logs generated during commands executing are saved in the obsutil log file for problem analysis and location.• Ensure that the user who runs the command has the read and write permissions on the path. <p>NOTICE</p> <p>If multiple obsutil processes are running at the same time, log files may fail to be written concurrently. In this case, add parameter -config when running commands to configure an independent configuration file for each process.</p>	N/A
utilMaxLogSize	Optional	Size of an obsutil log file, in bytes. The default value is 30 MB.	The recommended value ranges from 10 MB to 100 MB.
writeBufferIoSize	Optional	Size of the cache for downloading data, in bytes. The default value is 65536. NOTE	N/A

Parameter	Optional or Mandatory	Description	Recommended Value
		Set this parameter based on site requirements. If the size of the file to be downloaded is large, set this parameter to a large value.	
readBufferIoSize	Optional	Size of the cache for uploading data, in bytes. The default value is 8192. NOTE Set this parameter based on site requirements. If a large number of small files are uploaded, set this parameter to a small value. If large files are uploaded, set this parameter to a large value.	The recommended value ranges from 4096 to 65536.
recordMaxLogSize	Optional	Size of a result list containing success, failure, or warning lists in a batch task, in bytes. The default value is 30 MB.	The recommended value ranges from 5 MB to 100 MB.
recordBackups	Optional	Maximum number of result lists of successful or failed batch tasks that can be retained. The default value is 1024.	N/A
showProgressBar	Optional	Indicates whether to display the progress bar on the console. The value true indicates that the progress bar is displayed. The default value is true .	N/A
showStartTime	Optional	Indicates whether to display the start time on the console. The value true indicates that start time is displayed. The default value is true .	N/A
colorfulProgress	Optional	Indicates whether to enable the progress bar with colors. The value true indicates that the bar is enabled.	N/A
defaultTempFileDir	Optional	Indicates the directory for storing temporary files during download. The default value is the .obsutil_tempfile subfolder in the user directory (HOME in Linux or macOS and C:\Users\<Username> in Windows). NOTE <ul style="list-style-type: none">Temporary files generated during multipart download are stored in this directory. Therefore, ensure that the user who executes obsutil has the write permission on the path.The available space of the partition	N/A

Parameter	Optional or Mandatory	Description	Recommended Value
		where the path is located must be greater than the size of the objects to be downloaded.	
checkSourceChange	Optional	Indicates whether to check the change of source files or objects during upload/download/copy. The value true indicates that the function is enabled.	N/A
skipCheckEmptyFolder	Optional	Indicates whether to skip checking empty folders on the OBS server during download. true indicates to skip the check. The default value is false . NOTICE If this parameter is set to true , the directory structure downloaded to your local PC may be different from that in OBS.	N/A
fsyncForDownload	Optional	Indicates whether to forcibly synchronize memory data to disks during download. The value true indicates to enable forcible synchronization. The default value is false . NOTE <ul style="list-style-type: none">Set this parameter to true for scenarios that require high data reliability.If this parameter is set to true, the download performance will be deteriorated. Therefore, exercise caution when using this parameter.	N/A

**NOTE**

- Set parameters with **N/A** as the recommended value based on your needs.
- You are advised to specify **sdkLogPath** and **utilLogPath** to enable SDK logging and obsutil logging.
- The values of **defaultBigfileThreshold**, **defaultPartSize**, **rateLimitThreshold**, **sdkMaxLogSize**, **utilMaxLogSize**, **recordMaxLogSize**, **readBufferIoSize**, and **writeBufferIoSize** can contain a capacity unit. For example, 1 MB indicates 1048576 bytes.