

# Guide to using PintOS

Prof: Jorge Gonzalez  
jgonzalez@utec.edu.pe  
TA: Martin Carrasco  
martin.carrasco@utec.edu.pe

March 31, 2020

## 1 Making a docker container for PintOS

1. Pull the docker image from Docker Hub
2. Create a volume to have data be persistent e.g. *sudo docker volume create my\_volume PATH* (see additional info in item 5).
3. Create the Dockerfile (*Use the template Dockerfile included to guide you, notice that in our template we already pull the image*).
  - Install dependencies
  - Set environmental variables
4. Build the container e.g. *sudo docker build -t pintos .*
5. Run the container e.g. *sudo docker run -it -volume my\_volume:/pint-os -name pint-sim pintos*. For more details about using volumes, please refer to Docker Documentation.

## 2 Setting up and compiling PintOS

1. Make sure all the dependencies were installed correctly
2. Compile the following submodules

- `userprog`
  - `vm`
  - `filesystem`
3. Edit `src/utils/Makefile` to replace `LDFLAGS= -lm` to `LDLIBS = -lm` then compile `src/utils`
  4. Edit `src/thread/Make.vars` and change `SIMULATOR=` to `SIMULATOR=-qemu` then compile `src/threads`
  5. Change `src/utils/pintos $sim=bochsim` to `$sim=qemu`
  6. Change `src/utils/pintos`, check `$name = find_file('kernel.bin')` to point to `threads/build/kernel.bin`
  7. Change `src/utils/pintos my (@cmd) = ('qemu')` to `my (@cmd) =qemu-system-x86_64`
  8. Edit in `src/utils/Pintos.pm`, `$name = find_file('loader.bin')` and point it to `threads/build/loader.bin`
  9. See Pintos Documentation for compile and run. Notice that we are using Qemu.