

MidoNet Operations Guide

5.0-SNAPSHOT (2016-01-18 10:40 UTC)

DRAFT



MidoNet Operations Guide

5.0-SNAPSHOT (2016-01-18 10:40 UTC)

Copyright © 2016 Midokura SARL All rights reserved.

MidoNet is a network virtualization software for Infrastructure-as-a-Service (IaaS) clouds.

It decouples your IaaS cloud from your network hardware, creating an intelligent software abstraction layer between your end hosts and your physical network.

This guide includes instructions on creating routers, bridges, and ports. It also describes rule chains and several MidoNet features, including L4 load balancing, resource protection, NAT configuration, handling IP packet fragments, and L2 address matching.



Caution

This document is a DRAFT. It may be MISSING relevant information or contain UNTESTED information. Use it at your own risk.



Note

Please consult the [MidoNet Mailing Lists or Chat](#) if you need assistance.

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

Table of Contents

Preface	vii
Conventions	vii
1. Configuring uplinks	1
Edge Router Setup	1
BGP Setup	2
Static Setup	6
2. Authentication and authorization	8
Available authentication services in MidoNet	8
Using the Keystone authentication service	9
3. Admitting resources to MidoNet	11
What are tunnel zones?	11
Working with hosts	12
4. Device abstractions	15
Creating a router	15
Adding a port to a router	15
Adding a bridge	16
Adding a port to a bridge	16
Binding an exterior port to a host	16
Stateful port groups	17
5. Connecting devices	19
Connecting a bridge to a router	19
Connecting two routers	20
6. Routing	21
Routing process overview	21
Viewing routes	23
Adding routes	24
Deleting routes	25
7. Rule chains	26
A packet's flow within a router	26
A packet's flow within a rule chain	27
Rule types	28
Rule order	29
Rule conditions	30
MidoNet rule chain example	34
Listing the bridges for the tenant	36
Listing the OpenStack security group rule chain	37
8. Network Address Translation	39
Static NAT	39
Viewing NAT rule chain information	39
Configuring SNAT, DNAT, and REV_DNAT	41
DNAT/REV_DNAT example	41
SNAT example	42
9. Layer 4 Load Balancing	44
Load balancer configuration	45
Sticky Source IP	47
Health monitor	48
10. L2 address masking	51
L2 address mask rule chain example	51
11. Handling fragmented packets	52
Definitions and allowed values	52
Fragmented packets rule chain creation example	53
Non-Fragmented and Fragmented Packets	54

Fragmented and Non-Fragmented Packets with Different Destinations	55
12. MidoNet resource protection	57
Introduction	57
Expected Behavior	57
Configuration	58
Disabling Resource Protection	58
13. MidoNet monitoring	59
Metering	59
Monitoring Network State Database	61
Monitoring Midolman Agents	64
Monitoring events	66
Packet Tracing	75
Port mirroring	76
14. VXLAN configuration	80
VXLAN Gateway	80
VXLAN Coordinator	81
VXLAN Flooding Proxy	82
Connecting to the VTEP	82
Setting up a connection between a VTEP and a Neutron network	84
Enabling connection between VTEP and MidoNet hosts	85
Troubleshooting VTEP/VXGW configuration	86
CLI commands used for working with the VXGW	91
15. Setting up an L2 gateway	97
Configuring an L2 gateway	98
Fail-over/Fail-back	99
16. Working with the MidoNet CLI	100
Using the MidoNet CLI	100
17. Advanced configuration and concepts	102
MidoNet Configuration: mn-conf	102
Recommended configurations	107
MidoNet Agent (Midolman) configuration options	108
Advanced MidoNet REST API configuration options	110
Cassandra cache	112
18. MidoNet and OpenStack TCP/UDP service ports	114
Services on the Controller node	114
Services on the Network State Database nodes	115
Services on the Compute nodes	116
Services on the Gateway Nodes	116

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

List of Tables

2.1. Authentication Provider Classes	8
2.2. Keystone Protocol	9
7.1. CLI Rule Chain Attributes	30
7.2. CLI Rule Chain Attributes That Match Packets	31
13.1. Configuration Files/Locations	67
13.2. Event Message Files/Locations	67
17.1. Recommended Configuration Values	108
17.2. Admin Roles	110
17.3. System Properties for the HTTPS Key Store	111

Preface

Conventions

The MidoNet documentation uses several typesetting conventions.

Notices

Notices take these forms:



Note

A handy tip or reminder.



Important

Something you must be aware of before proceeding.



Warning

Critical information about the risk of data loss or security issues.

Command prompts

\$ prompt

Any user, including the root user, can run commands that are prefixed with the \$ prompt.

prompt

The root user must run commands that are prefixed with the # prompt. You can also prefix these commands with the **sudo** command, if available, to run them.

1. Configuring uplinks

Table of Contents

Edge Router Setup	1
BGP Setup	2
Static Setup	6

This section describes how to configure uplinks from a MidoNet-enabled cloud to an external network.

The basic steps for configuring uplinks are:

1. Connect a virtual port to an exterior port.
2. Set up a router. This includes configuring the routes for the traffic between networks.
3. Configure dynamic routing to allow for the exchange of routes between your local autonomous system (AS) and other autonomous systems. MidoNet supports BGP, which is an exterior routing protocol that allows MidoNet to advertize routes, such as the route to the network associated with floating IPs, and receive routes and reachability information from BGP peers.

Edge Router Setup

Prior to v5.0, with Neutron, you could set up the gateway in only one way, which was to have a special singleton gateway router called the Provider Router created implicitly when an external network was created in Neutron. The provider router sits at the edge of the cloud and interfaces with the uplink router. The Provider Router is where BGP was typically configured. The biggest limitation of this approach was that it took away the scenario in which you wanted to have an L2 network at the edge instead of a router. Another limitation was that only one such router could exist for the entire cloud.

These limitations are removed in v5.0, where you could design your gateway to be either L2 network or router with as many routers as you wish, all using the Neutron API.

There are two main changes:

Edge Router

The Provider Router is no longer implicitly created upon the external network creation. Instead, the edge gateway routers, called the Edge Routers, are created explicitly using standard Neutron API. With this approach, multiple Edge Routers can be created, and they are optional.

Gateway Virtual Topology

In the previous model, the Provider Router was connected directly to the tenant routers, with the external networks hanging off of the Provider Router.

In the new model, the external networks exist between the edge and the tenant routers.

To create the gateway topology issue the following Neutron commands.


```

midonet> router router0 add bgp-peer asn 64514 address 203.0.113.1
router0:peer1

midonet> router router0 list bgp-peer
peer peer0 asn 64513 address 198.51.100.1
peer peer1 asn 64514 address 203.0.113.1

```

4. If needed, configure MD5 authentication:

```

midonet> router router0 bgp-peer peer0 set password BGP_PASSWORD
midonet> router router0 bgp-peer peer1 set password BGP_PASSWORD

```

5. If needed, configure custom timers that will take precedence over the default ones defined in the MidoNet configuration:

```

midonet> router router0 bgp-peer peer0 set connect-retry 10
midonet> router router0 bgp-peer peer0 set hold-time 5
midonet> router router0 bgp-peer peer0 set keep-alive 5
midonet> router router0 bgp-peer peer1 set connect-retry 10
midonet> router router0 bgp-peer peer1 set hold-time 5
midonet> router router0 bgp-peer peer1 set keep-alive 5
midonet> router router0 list bgp-peer
peer peer0 asn 64513 address 198.51.100.1 keep-alive 5 hold-time 5
  connect-retry 10
peer peer1 asn 64514 address 203.0.113.1 keep-alive 5 hold-time 5
  connect-retry 10

```

6. Add routes to the remote BGP peers

In order to be able to establish connections to the remote BGP peers, corresponding routes have to be added.

```

midonet> router router0 route add src 0.0.0.0/0 dst 198.51.100.0/30
  port router0:port0 type normal
router0:route0

midonet> router router0 route add src 0.0.0.0/0 dst 203.0.113.0/30
  port router0:port1 type normal
router0:route1

```

7. Advertise BGP routes

In order to provide external connectivity for hosted virtual machines, the floating IP network has to be advertised to the BGP peers.

```

midonet> router router0 add bgp-network net 192.0.2.0/24
router0:net0

midonet> router router0 list bgp-network
net net0 net 192.0.2.0/24

```

Adding a second session on the same router port

It may be useful or a good idea to add a second BGP session to this router port if there is a second uplink router available. That has two upsides as the host that owns the port binding for this router port will be able to load balance among both upstream routers and it will not be disconnected if only one of them fails.

To add a second peer to the same router port, you use the same command as for the first peer, adjusting its AS number and IP address. The router port on which MidoNet establishes the BGP session is chosen automatically based on the peer's IP address.

You must make the change in `mn-conf(1)` on the MidoNet side, and the remote end BGP peer configuration.

The basic BGP timers are 'keepalive' and 'holdtime'. By default, keepalive timer is 60 seconds. The hold-down timer is, by convention, 3 times the keepalive interval, 180 seconds. You can go as low as 1 and 3 seconds for these values, but keep in mind that this may potentially result in the BGP session flapping.

Another important BGP timer that you can tweak is the BGP 'connect_retry' timer, also called the 'connect' timer. You can use this timer to set the amount of time between retries to establish a connection to configured peers which have gone down for some reason.

The example below shows how to reduce the default BGP values to 1, 1, and 3 seconds, for keep-alive, hold-time, and connect-retry, respectively, on the BGP peer's session end (e.g. Quagga or Cisco):

```
neighbor 192.0.2.1 timers 1 3
neighbor 192.0.2.1 timers connect 1
```

To match those settings you would have to set the following parameters on the MidoNet end of the BGP session:

```
agent {
  midolman {
    bgp_connect_retry : 1s
    bgp_holdtime : 3s
    bgp_keepalive : 1s
  }
}
```


Static Setup


If you are not connecting through a BGP link, or you just want to use static routing follow this section.

This creates a static up-link to connect VMs to the external network.

1. Create fake uplink

We are going to create the following topology to allow the VMs reach external networks:





2. Create a veth pair

```
# ip link add type veth
# ip link set dev veth0 up
# ip link set dev veth1 up
```

3. Create a bridge, set an IP address and attach veth0

```
# brctl addbr uplinkbridge
# brctl addif uplinkbridge veth0
# ip addr add 172.19.0.1/30 dev uplinkbridge
# ip link set dev uplinkbridge up
```

4. Enable IP forwarding

```
# sysctl -w net.ipv4.ip_forward=1
```

5. Route packets to 'external' network to the bridge

```
# ip route add 200.200.200.0/24 via 172.19.0.2
```

6. Create a port on the Edge Router and bind it to the veth:

```
$ midonet-cli
midonet> router list
router router0 name Edge Router state up
midonet> router router0 add port address 172.19.0.2 net 172.19.0.0/30
router0:port0
midonet> router router0 add route src 0.0.0.0/0 dst 0.0.0.0/0 type
normal port router router0 port port0 gw 172.19.0.1
midonet> host list
host host0 name controller alive true
midonet> host host0 add binding port router router0 port port0 interface
veth1
host host0 interface veth1 port router0:port
```

7. Add masquerading to your external interface so connections coming from the overlay with addresses that belong to the "fake" external network are NATed. Also make sure these packets can be forwarded:

```
# iptables -t nat -I POSTROUTING -o eth0 -s 200.200.200.0/24 -j
MASQUERADE
# iptables -I FORWARD -s 200.200.200.0/24 -j ACCEPT
```

Now we can reach VMs from the underlay host using their floating IPs, and VMs can reach external networks as well (as long as the host has external connectivity).



Important

You must restart all MidoNet Cluster instances after changing the authentication provider.

For additional Keystone configuration options, see [the section called “Enabling Keystone authentication” \[9\]](#)

Mock authentication

Mock authentication disables the authentication system by returning a fake tokens to authenticating clients, and ignoring the sent tokens during authorization. To enable the mock authentication configure the `MockAuthService` provider class.

```
echo "cluster.auth.provider_class : org.midonet.cluster.auth.  
MockAuthService" | mn-conf set -t default
```



Warning

Mock authentication is the default authentication provider for the MidoNet Cluster. However, this mode is used for testing purposes but should not be used in production.

Using the Keystone authentication service

This section explains how to use the Keystone authentication service with MidoNet.

Enabling Keystone authentication

In order to use the OpenStack Keystone authentication service with MidoNet, you must configure the following keys in the MidoNet configuration.

`cluster.auth.provider_class`

The fully qualified path of the Java class that provides the Keystone authentication service.

```
org.midonet.cluster.auth.keystone.v2_0.KeystoneService
```

`cluster.auth.admin_role`

Identifies the name of the admin role in MidoNet. The admin has read and write access to all the resources. We recommend re-using the OpenStack *admin* role. Optionally you can create a separate admin role for MidoNet.

`cluster.auth.keystone.protocol`

Identifies the protocol used for the Keystone service. The following values are allowed:

Table 2.2. Keystone Protocol

Class	Description
http	Uses plain text HTTP to communicate with the Keystone server.
https	Uses encrypted HTTPS to communicate with the Keystone service (recommended).

Deleting tunnel zones

Use this procedure to delete a tunnel zone.

1. Enter the `list tunnel-zone` command to list the tunnel zones. For example:

```
midonet> list tunnel-zone
tzone tzone0 name new-tz type gre
tzone tzone1 name gre type gre
```

2. Enter the `delete tunnel-zone tz-alias` command to delete the desired tunnel zone. For example:

```
midonet> delete tunnel-zone tzone0
```

Specify the dynamically assigned number of the alias for the tunnel zone to delete; in the above example, the assigned number is 0 (tzone0).

3. (Optional) Enter the command to list the tunnel zones to confirm the deletion:

```
midonet> list tunnel-zone
tzone tzone1 name gre type gre
```

Viewing tunnel zone information

Use this procedure to view tunnel zone information.

```
midonet> tunnel-zone tzone0 list member
zone tzone0 host host0 address 192.168.0.3
zone tzone0 host host1 address 192.168.0.5
zone tzone0 host host2 address 192.168.0.4
zone tzone0 host host3 address 192.168.0.6
```

The above output shows the:

- Aliases for the hosts in the tunnel zone (host0, host1, and so on)
- IP addresses assigned to the hosts

Working with hosts

This section shows how to view host information and admit new hosts to a tunnel zone.

Viewing host information

Use this procedure to view information about hosts.

- To list the hosts enter the command:

```
midonet> list host
host host0 name controller alive true
host host2 name compute1 alive true
host host3 name compute3 alive false
host host1 name compute2 alive false
```

- To list the interfaces on a certain host enter the command:

```
midonet> host host0 list interface
iface midonet host_id host0 status 0 addresses [] mac 12:6e:b7:d0:4f:f1
mtu 1500 type Virtual endpoint DATAPATH
```


In the above command example:

- tzone0 = the tunnel zone you want to add the member (host) to
- host0 = the alias of the host you want to add
- 10.1.2.200 = the IP address of the host you want to add

Removing a host from a tunnel zone

Use this procedure to remove a host from a tunnel zone.

1. Enter the `list tunnel-zone` command to list the tunnel zone. For example:

```
midonet> list tunnel-zone
tzone tzone0 name default_tz type gre
```

2. Enter the `tunnel-zone tunnel-zone list member` command to list the tunnel zone members (hosts). For example:

```
midonet> tunnel-zone tzone0 list member
zone tzone0 host host0 address 172.19.0.2
```

3. Enter the `tunnel-zone tunnel-zone member host host show` command to show information about a specific host. For example:

```
midonet> tunnel-zone tzone0 member host host0 show
tunnel-zone-host zone tzone0 host host0 address 172.19.0.2
```

4. Enter the `tunnel-zone tunnel-zone member host host delete` command to delete the desired host (identified by the host's alias). For example:

```
midonet> tunnel-zone tzone0 member host host0 delete
```

5. (Optional) You can add the host back to the tunnel zone, using the `tunnel-zone tunnel-zone member add host host address ip-address` command as shown below:

```
midonet> tunnel-zone tzone0 member add host host0 address 172.19.0.2
zone tzone0 host host0 address 172.19.0.2
```

Removing a host

Use this procedure to remove inactive hosts.

1. Enter the command to list the hosts:

```
midonet> list host
host host0 name precise64 alive true
```

2. Enter the command to delete the desired host (identified by its alias):

```
midonet> host host0 delete
```


2. Enter the command to list the bridges on the current tenant:

```
midonet> list bridge
bridge bridge0 name External state up
bridge bridge1 name Management state up
bridge bridge2 name Internal state up
```

3. Enter the command to list the ports on the desired bridge:

```
midonet> bridge bridge0 list port
port port0 device bridge0 state up
port port1 device bridge0 state up
port port2 device bridge0 state up
```

4. Enter the command to list the interfaces on a certain host:

```
midonet> host host0 list interface
iface lo host_id host0 status 3 addresses [u'127.0.0.1',
u'0:0:0:0:0:0:1'] mac 00:00:00:00:00:00 mtu 65536 type Virtual
endpoint LOCALHOST
iface midonet host_id host0 status 0 addresses [] mac 8e:4d:60:c1:70:d7
mtu 1500 type Virtual endpoint DATAPATH
iface eth1 host_id host0 status 3 addresses
[u'fe80:0:0:0:250:56ff:fe93:7c35'] mac 00:50:56:93:7c:35 mtu 1500 type
Physical endpoint PHYSICAL
iface eth0 host_id host0 status 3 addresses [u'10.1.2.200',
u'fe80:0:0:0:250:56ff:fe93:c9a4'] mac 00:50:56:93:c9:a4 mtu 1500 type
Physical endpoint PHYSICAL
```

5. Enter the command to bind a certain host to virtual port:

```
midonet> host host0 add binding
host interface port
```

6. Enter the command to bind a virtual port on the bridge with a physical interface on the host:

```
midonet> host host0 add binding port bridge0:port0 interface eth1
host host0 interface eth1 port bridge0:port0
```

Stateful port groups

MidoNet features stateful port groups, which are groups of virtual ports (typically two) that are logically associated, usually to perform load balancing or for link redundancy.

For such ports MidoNet keeps state local to the two endpoints of a connection. In most cases, connections that traverse MidoNet do so between a single pair of ports. Typical cases include a router with two uplink BGP ports, or an L2GW with two ports connected to a physical L2 network. In both cases, the pair of ports becomes a set of ports because packets may return through different paths. Those port pairs will share state.

You configure stateful port groups in the MidoNet CLI, using the `port-group` command.

Creating stateful port groups

Follow the steps of this procedure to create a stateful group of ports, using the MidoNet CLI.

Before you launch the MidoNet CLI you need to find out the OpenStack UUID of the tenant on which you want to create your port group. To this end, you can use keystone. Issue the following commands in the terminal on the MidoNet host:


```
# keystone tenant-list
+-----+-----+-----+
| id | name | enabled |
+-----+-----+-----+
| 7a4937fa604a425e867f085427cc351e | admin | True |
| 037b382a5706483a822d0f7b3b2a9555 | alt_demo | True |
| 0a1bf57198074c779894776a9d002146 | demo | True |
| 28c40ac757e746f08747cddb32a83c40b | services | True |
+-----+-----+-----+
```

The output of the command shows the full list of tenants. For this procedure we will use the 'admin' tenant, 7a4937fa604a425e867f085427cc351e.

1. In the MidoNet CLI determine the list of available routers.

```
midonet> list router
router router0 name Edge Router state up
router router1 name TenantRouter state up
```

Let's assume that the router whose ports you are going to add to the port group is Edge Router, router0.

2. Now list the ports on router0.

```
midonet> router router0 list port
port port0 device router0 state up mac 02:c2:0f:b0:f2:68 address 100.100.100.1 net 100.100.100.0/30
port port1 device router0 state up mac 02:cb:3d:85:89:2a address 172.168.0.1 net 172.168.0.0/16
port port2 device router0 state up mac 02:46:87:89:49:41 address 200.200.200.1 net 200.200.200.0/24 peer bridge0:port0
port port3 device router0 state up mac 02:6b:9f:0d:c4:a8 address 169.254.255.1 net 169.254.255.0/30
```

You want to add port0 and port1 on the router to load balance the BGP traffic on the Edge Router.

3. Load your tenant using the 'sett' command.

```
midonet-cli> sett 7a4937fa604a425e867f085427cc351e
tenant_id: 7a4937fa604a425e867f085427cc351e
```

4. Create a stateful port group using the 'port-group create' command.

```
midonet-cli> port-group create name SPG stateful true
pgroup0
```

5. Add the two ports on the Edge Router that you want to participate in load balancing, to the port group you just created.

```
midonet> port-group pgroup0 add member port router0:port0
port-group pgroup0 port router0:port0
midonet> port-group pgroup0 add member port router0:port1
port-group pgroup0 port router0:port1
```

You have successfully added both router ports to the stateful port group, which you can verify by issuing the following command:

```
midonet> port-group pgroup0 list member
port-group pgroup0 port router0:port1
port-group pgroup0 port router0:port0
```


Connecting two routers

You can easily connect two virtual routers via virtual ports on each router.

Make sure you create the router ports on the two routers and assign the ports to the same subnet. See [Chapter 4, “Device abstractions” \[15\]](#) for information about creating routers and adding router ports.

To connect two routers:

1. Enter the command to list the routers on the current tenant:

```
midonet> list router
router router3 name test-router2 state up
router router1 name test-router state up
```

2. Enter the command to list the ports on one of the routers you want to connect:

```
midonet> router router1 list port
port port0 device router1 state up mac 02:a6:81:08:ab:5d address 10.100.
1.1 net 10.0.0.0/24 peer bridge1:port0
port port1 device router1 state up mac 02:fa:5f:87:bb:d2 address 10.100.
1.2 net 10.0.0.0/24
```

3. Enter the command to list the ports on the router you want to connect it to:

```
midonet> router router3 list port
port port0 device router3 state up mac 02:df:24:5b:19:9b address 10.100.
1.128 net 10.0.0.0/24
```

4. Enter the command to bind the port on one router (for example, port 1 on router1) to the port on another router (for example, port0 on router3):

```
midonet> router router1 port port1 set peer router3:port0
```

5. Enter the command to list the ports on one of the routers:

```
midonet> router router1 list port
port port0 device router1 state up mac 02:a6:81:08:ab:5d address 10.100.
1.1 net 10.0.0.0/24 peer bridge1:port0
port port1 device router1 state up mac 02:fa:5f:87:bb:d2 address 10.100.
1.2 net 10.0.0.0/24 peer router3:port0
```

The above output shows that port1 on router1 is connected to port0 on router3.

Weight

Can be used for load balancing for destinations with multiple paths. Lower weight values identify preferred paths (for example, higher bandwidth). The default weight value is 100. For routes learned from BGP peers, the BGP administrative distance becomes the route's weight. See also "Source".

Viewing routes

You can view the routes defined on each virtual router in MidoNet. For example, you can view information about routes to virtual bridges and to other routers, including tenant routers and Edge Routers.

To display route information about the current tenant's routers:

1. Enter the command below to list the routers for the current tenant.

```
midonet> list router
router router0 name tenant-router state up infilter chain0 outfilter
chain1
```

2. Enter the command below to list the route list for the router, in this case, a tenant router (router0).

```
midonet> router router0 list route
route route0 type normal src 0.0.0.0/0 dst 169.254.255.2 port
router0:port0 weight 0
route route1 type normal src 0.0.0.0/0 dst 0.0.0.0/0 port router0:port0
weight 100
route route2 type normal src 0.0.0.0/0 dst 172.16.3.0/24 port
router0:port1 weight 100
route route3 type normal src 172.16.3.0/24 dst 169.254.169.254 gw 172.
16.3.2 port router0:port1 weight 100
route route4 type normal src 0.0.0.0/0 dst 172.16.3.1 port router0:port1
weight 0
```

The route list shows the following information:

- The source (src) for the traffic to match. route3 shows a specific source network to match; 0.0.0.0/0 means match traffic from every network.
- The destination (dst) for this traffic. This can be a network or a specific interface.
 - route0 shows an example of a route to a specific interface. This is the route to the link-local address, which, in this example, is peered with an Edge Router.
 - route2 shows a route to the 172.16.3.0/24 network, which is a private network.
 - route1 says: for traffic that matches every network (0.0.0.0/0) with a destination of any network (0.0.0.0/0), forward this traffic to port0, which is peered with an Edge Router. For traffic that matches the source IP address, MidoNet finds the route whose destination prefix matches the packet's destination and has the longest mask (a.k.a. longest-prefix matching). If the router cannot find a destination with a longer prefix than 0.0.0.0, the router sends the traffic to this default route.
- For destinations that are not directly connected to the router, the interface to the gateway to the destination is shown (next hop gateway).
 - route3 shows an example. This route says: traffic with a source that matches the 172.16.3.0/24 network (that is, traffic from the private network), with the destina-


```
route route1 type normal src 0.0.0.0/0 dst 10.100.1.2 port router2:port1
weight 0
route route2 type normal src 0.0.0.0/0 dst 169.254.255.3 port
router2:port2 weight 0
route route3 type normal src 0.0.0.0/0 dst 169.254.255.0/30 port
router2:port2 weight 0
```

Deleting routes

If you are using MidoNet as a standalone SDN controller, there are many situations where you might want to delete routes; all related to managing your physical network devices.

For example, if you want to reverse something you did that required manually adding routes, you can delete the routes.



Warning

It is not recommended to delete routes that were added automatically as a result of OpenStack Neutron operations.

To delete a route:

1. Enter the command to list the routes on a certain router:

```
midonet> router router2 list route
route route0 type normal src 0.0.0.0/0 dst 10.100.1.1 port router2:port0
weight 0
route route1 type normal src 0.0.0.0/0 dst 10.100.1.2 port router2:port1
weight 0
route route2 type normal src 0.0.0.0/0 dst 169.254.255.3 port
router2:port2 weight 0
route route3 type normal src 0.0.0.0/0 dst 169.254.255.0/30 port
router2:port2 weight 0
```

The above command lists the routes on router2.

2. Enter the command(s) to delete the desired route(s) from the desired router:

```
midonet> router router2 delete route route2
midonet> router router2 delete route route3
```

The above commands delete route2 and route3 from router2.

3. Enter the command to list the routes on the router to confirm the deletions:

```
midonet> router router2 list route
route route0 type normal src 0.0.0.0/0 dst 10.100.1.1 port router2:port0
weight 0
route route1 type normal src 0.0.0.0/0 dst 10.100.1.2 port router2:port1
weight 0
```


7. Rule chains

Table of Contents

A packet's flow within a router	26
A packet's flow within a rule chain	27
Rule types	28
Rule order	29
Rule conditions	30
MidoNet rule chain example	34
Listing the bridges for the tenant	36
Listing the OpenStack security group rule chain	37

The routing logic for a MidoNet virtual router includes the traversal of rule chains that may modify, record state, or reject a packet.

A newly created router has two chains: one named 'pre-routing' and the other named 'post-routing'. Below are a few important facts about rule chains:

- You can put chains not only on routers, but also on bridges and ports, too.
- Pre-routing chains have access to the ingress port ID, while post-routing chains have access to both the ingress and egress port. During post-routing, the router routes the packet and both the ingress port and the egress router port are known.

A packet's flow within a router

In order to understand rule chains, first consider how a router processes a packet:



Rule conditions

Every rule has a single Condition object that a packet must match in order for the rule to be applied.

Taking a jump rule as an example, if a packet matches the jump's Condition object, then rule processing for that packet will continue in the jump's target chain; if the packet doesn't match, then processing continues with the rule following the jump in the jump's own rule-chain.

Condition objects specify a set or combination of attributes. Attributes are simple statements about the contents of a packet's headers. Examples of attributes are:

- 'the packet's TCP/UDP port number is between 500 and 1000'
- 'the packet's source IP address is in 10.0.0.0/16'



Note

Conditions are checked against the packet in the state the packet is in when it reaches a rule. In other words, for example, if a previous rule modified the packet's port number, then the current rule's condition will be checked against the modified, not the original, port number.

In order to form a Condition, you specify a number of attributes (optionally, you can invert most attributes using the CLI). Enter an exclamation point (!) or "bang" symbol to invert it, as shown in the "CLI Rule Chain Attributes That Match Packets" table. For example, if you invert the src attribute, this matches packets whose source does not match the specified IP address or network.

Below is the list of Condition attributes (attributes, invert-flags, and arguments) and their descriptions.



Note

The ports identified in rules are virtual ports on virtual routers or bridges. A virtual port may be bound to a specific Ethernet interface (like a tap) on a physical host OR it may be peered with another virtual port (in which case it connects two virtual devices). In either case, think of the virtual port as virtual because the rules only exist in the virtual topology AND nothing is known during rule evaluation about possible bindings of the virtual port to physical Ethernet interfaces.

Table 7.1. CLI Rule Chain Attributes

Attributes	Description
pos <INTEGER>:	The rule's position in the chain
type <TYPE>:	The rule <TYPE>; this is mostly used to distinguish between regular filtering rules and different types of NAT rules. The recognized <TYPE> values are: accept, continue, drop, jump, reject, return, dnat, snat, rev_dnat, rev_snat.
action accept	continue
return:	The rule action, meaningful for NAT rules only.
jump-to <CHAIN>:	The chain to jump to (if this is a jump rule).
target <IP_ADDRESS[-IP_ADDRESS][:INTEGER[-INTEGER]]>:	The NAT target, if this is a dnat or snat rule. At least one IP address must be given, optionally the NAT target may

Attributes	Description
	also contain a second address to form an address range and L4 port number or range of ports.

Table 7.2. CLI Rule Chain Attributes That Match Packets

Attributes That Match Packets	Description
hw-src [!]<MAC_ADDRESS>:	The source hardware address
hw-dst [!]<MAC_ADDRESS>:	The destination hardware address
ethertype [!]<STRING>:	Sets the data link layer (EtherType) of packets matched by this rule.
in-ports [!]<PORT[,PORT...]>:	Matches the virtual port through which the packet ingresses the virtual device that is currently processing the packet.
out-ports [!]<PORT[,PORT...]>:	Matches the port through which the packet egresses the virtual device that is currently processing the packet.
tos [!]<INTEGER>:	The value of the packet's Type of Service (TOS) field to match. Use this field to match the differentiated services value. See TOS for information.
proto [!]<INTEGER>:	The IP protocol number to match. See Protocol Numbers for information. Examples: ICMP = 1, IGMP = 2, TCP = 6, UDP = 17
src [!]<CIDR>:	The source IP address or CIDR block
dst [!]<CIDR>:	The destination IP address or CIDR block
src-port [!]<INTEGER[-INTEGER]>:	The TCP or UDP source port or port range
dst-port [!]<INTEGER[-INTEGER]>:	The TCP or UDP destination port or port range
flow <fwd-flow return-flow>:	Matches the connection-tracking status of the packet. If the packet is starting a new connection, fwd-flow will match. Alternatively, if the packet belongs to a connection already known to MidoNet, return-flow will match.
port-group [!]<PORT_GROUP>:	Matches a port group. Port groups allow the grouping of virtual ports to ease the creation of chain rules. See the CLI commands help for information.
ip-address-group-src [!]<IP_ADDRESS_GROUP>:	Matches a source IP address group. IP address groups allow the grouping of IP addresses to ease the creation of chain rules. See the CLI commands help for information.
ip-address-group-dst [!]<IP_ADDRESS_GROUP>:	Matches a destination IP address group. IP address groups allow the grouping of IP addresses to ease the creation of chain rules. See the CLI commands help for information.
hw-src-mask	<p>Source MAC address mask - A 48-bit bitmask in the form xxxx.xxxx.xxxx, where x is any hexadecimal digit. Specifies which bits are to be considered when applying the rule's hw-src test.</p> <p>Default value = ffff.ffff.ffff: All bits are considered when applying the hw-src test, so a packet's source MAC address must match hw-src exactly.</p> <p>ffff.0000.0000: Only the first sixteen bits are considered when applying the hw-src test, the first sixteen bits of a packet's source MAC address must match the first sixteen bits of hw-src.</p> <p>0000.0000.0000: No bits are considered when applying the hw-src test, so any packet will match.</p>
hw-dst-mask	<p>Destination MAC address mask - A 48-bit bitmask in the form xxxx.xxxx.xxxx, where x is any hexadecimal digit. Specifies which bits are to be considered when applying the rule's hw-dst test.</p> <p>Default value = ffff.ffff.ffff: All bits are considered when applying the hw-dst test, so a packet's destination MAC address must match hw-dst exactly.</p>

Attributes That Match Packets	Description
	ffff.0000.0000: Only the first sixteen bits are considered when applying the hw-dst test, the first sixteen bits of a packet's destination MAC address must match the first sixteen bits of hw-dst. 0000.0000.0000: No bits are considered when applying the hw-dst test, so any packet will match.
fragment-policy header nonheader any unfragmented	fragment-policy - Specifies the fragment type to match. ANY: Matches any packet. HEADER: Matches any packet that has a full header, that is, a header fragment or unfragmented packet. NONHEADER: Matches only nonheader fragments. UNFRAGMENTED: Matches only unfragmented packets. In general, ANY is the default policy. However, if a rule has a value for the src or dst field, the NONHEADER and ANY policies are disallowed and the default is HEADER. Furthermore, if the rule's type is dn timer and its target is not a single IP address with no ports specified, then the policy will default to UNFRAGMENTED, which is the only policy permitted for such rules. Unlike other rule properties, fragment-policy may not be inverted.

Example condition 1

Only packets whose network source is in 10.0.0.0/16 are allowed through to network 10.0.5.0/24. You can accomplish this a few different ways.

One way is to construct a DROP or REJECT rule that has a Condition and an ACCEPT rule with these attributes specify:

1. DROP when (ethertype equal 2048) AND (src NOT equal (10.0.0.0, 16))
2. ACCEPT when (dst equal (10.0.5.0, 24))
3. DROP



Note

The unconditional drop is needed to make rule 2 meaningful.

To create a rule chain with the above attributes:

1. If necessary, use the sett command or some other means to access the desired tenant.

```
midonet> sett 10a83af63f9342118433c3a43a329528
tenant_id: 10a83af63f9342118433c3a43a329528
```

2. Enter the command to create a new rule chain and assign it a name:

```
midonet> chain create name "drop_not_src_mynetwork_INBOUND"
chain5
```

3. Enter the command to drop IPv4 traffic that does not have the source 10.0.0.0/16:

```
midonet> chain chain5 add rule ethertype 2048 src !10.0.0.0/16 type drop
chain5:rule0
```

4. Enter the command to accept IPv4 traffic with the destination 10.0.5.0/24:

```
midonet> chain chain5 add rule ethertype 2048 dst 10.0.5.0/24 pos 2 type
accept
chain5:rule2
```

5. Enter the command to list the rules added to the new rule chain:

```
midonet> chain chain5 list rule
rule rule3 ethertype 2048 src !10.0.0.0/16 proto 0 tos 0 pos 1 type drop
rule rule2 ethertype 2048 dst 10.0.5.0/24 proto 0 tos 0 pos 2 type
accept
```

Example condition 2

Same as Example Condition 1, except here assume that you're structuring your rules differently. You want to have one DROP rule at the end of the chain that matches all packets; earlier in the chain you place ACCEPT rules that match packets/flows that are specifically allowed through.

The ACCEPT rule for the traffic allowed by Example Condition 1 would have a Condition with these attributes:

In the rule language, the chain would have:

ACCEPT when src=(10.0.0.0, 16) OR dst=(10.0.5.0, 24)

Rule at the end:

DROP all other packets

To create a rule chain with the above attributes:

1. If necessary, use the sett command or some other means to access the desired tenant.

```
midonet> sett 10a83af63f9342118433c3a43a329528
tenant_id: 10a83af63f9342118433c3a43a329528
```

2. Enter the command to create a new rule chain and assign it a name:

```
midonet> chain create name "accept_src_dst_mynetwork_INBOUND"
chain11
```

3. Enter the command to accept IPv4 traffic from the source 10.0.0.0/16:

```
midonet> chain chain11 add rule ethertype 2048 src 10.0.0.0/16 type
accept
chain11:rule0
```

4. Enter the command to accept IPv4 traffic with the destination 10.0.5.0/24:

```
midonet> chain chain11 add rule ethertype 2048 dst 10.0.5.0/24 type
accept
chain11:rule1
```

5. Enter the command to drop all IPv4 traffic (that didn't match the attributes in the preceding rules):

```
midonet> chain chain11 add rule ethertype 2048 pos 3 type drop
chain11:rule2
```

6. Enter the command to list the rules added to the new rule chain:



Note

Ports with infiltrer (pre-routing) and outfilter (post-routing) chains are connected to VMs. port1 is connected to a VM.

Listing the Rules for the Inbound Chain on a Port

To list the pre-routing rule chain for port 1:

1. Enter the command:

```
midonet> chain chain2 list rule
rule rule0 ethertype 2048 src !172.16.3.3 proto 0 tos 0 pos 1 type drop
rule rule1 hw-src !fa:16:3e:fb:19:07 proto 0 tos 0 pos 2 type drop
rule rule2 proto 0 tos 0 flow return-flow pos 3 type accept
rule rule3 proto 0 tos 0 pos 4 type jump jump-to chain4
rule rule4 ethertype !2054 proto 0 tos 0 pos 5 type drop
```

The pre-routing rule chain contains the following instructions:

- rule0 says: for packets that match the ethertype 2048 (IPv4) that do not match the source IP address 172.16.3.3 (the private IP address of the VM), drop these packets. This prevents the port's VM from sending packets with a forged IP address.
- rule1 says: for packets with a hardware source that does not match the listed source MAC address (the VM's MAC address), drop these packets. This prevents the VM from sending packets with a forged MAC address.
- rule2 says: for packets that match a return flow (that is, a packet that belongs to a connection already known to MidoNet), accept these packets.
- rule3 says: for packets that were not dropped or accepted as a result of matching previous rules, allow these packets to jump to the indicated chain (chain4).
- rule4 says: for packets that do not match the ethertype 2054 (ARP packets), drop these packets.

Listing the OpenStack Security Group Rule Chain

You can list all the rule chains and then look at the rule chain for the OpenStack security group.

To list all the rule chains and examine specific rule chains:

1. Enter the command:

```
midonet> list chain
chain chain5 name OS_SG_050593ed-56ad-44ef-8489-4052d02d99ff_INGRESS
chain chain0 name OS_PRE_ROUTING_5a151b0b-dea7-4918-bd17-876c1f7f5c64
chain chain1 name OS_POST_ROUTING_5a151b0b-dea7-4918-bd17-876c1f7f5c64
chain chain6 name OS_SG_01fcelb8-c277-4a37-a8cc-86732eea186d_INGRESS
chain chain4 name OS_SG_050593ed-56ad-44ef-8489-4052d02d99ff_EGRESS
chain chain7 name OS_SG_01fcelb8-c277-4a37-a8cc-86732eea186d_EGRESS
chain chain2 name OS_PORT_6f72342b-4947-432f-8d01-0cf4e4b8d049_INBOUND
chain chain3 name OS_PORT_6f72342b-4947-432f-8d01-0cf4e4b8d049_OUTBOUND
```

Note chain5, identified as a chain for an OpenStack security group (OS_SG) for INGRESS traffic.

To look at rule chain5:

2. Enter the command:

```
midonet> chain chain5 list rule
rule rule0 ethertype 2048 src 0.0.0.0/0 proto 6 tos 0 dst-port 5900 pos
1 type accept
rule rule1 ethertype 2048 src 0.0.0.0/0 proto 1 tos 0 pos 2 type accept
rule rule2 ethertype 2048 src 0.0.0.0/0 proto 6 tos 0 dst-port 22 pos 3
type accept
rule rule3 ethertype 2048 src 0.0.0.0/0 proto 6 tos 0 dst-port 80 pos 4
type accept
```

The above output shows the rule chain used to implement the security group you configured in OpenStack. These rules contain the following instructions:

- All the rules match ethertype 2048 (IPv4) packets.
- All the rules match traffic from any source network (0.0.0.0/0).
- All the rules, except rule1, match packets of IP protocol 6 (TCP) and accept them. rule1 matches packets of the ICMP type and accepts them.
- In addition to the other matches already mentioned, the rules match and accept the packets according to the security group rules you defined in OpenStack, specifically, packets with the destinations:
 - TCP port 5900 (VNC)
 - TCP port 22 (SSH)
 - TCP port 80 (HTTP)

Listing the bridges for the tenant

Rule chains relating to OpenStack security groups are implemented on the network (bridge) ports.

To list the bridge(s) on the tenant and show the demo-private-net network (bridge) enter the command:

```
midonet> list bridgebridge bridge0 name demo-private-net state up
```

Listing the ports on the bridge

To list information about the rule chains configured on the bridge ports, enter the command:

```
midonet> bridge bridge0 list port
port port0 device bridge0 state up
port port1 device bridge0 state up infilter chain2 outfilter chain3
port port2 device bridge0 state up peer router1:port1
```



Note

ports with infilter (pre-routing) and outfilter (post-routing) chains are connected to VMs. port1 is connected to a VM.

Listing the rules for the pre-routing rule chain

To list the pre-routing rule chain for port 1 enter the command:

```
midonet> chain chain2 list rule
rule rule0 ethertype 2048 src !172.16.3.3 proto 0 tos 0 pos 1 type drop
rule rule1 hw-src !fa:16:3e:fb:19:07 proto 0 tos 0 pos 2 type drop
rule rule2 proto 0 tos 0 flow return-flow pos 3 type accept
rule rule3 proto 0 tos 0 pos 4 type jump jump-to chain4
rule rule4 ethertype !2054 proto 0 tos 0 pos 5 type drop
```

The pre-routing rule chain contains the following instructions:

- rule0 says: for packets that match the ethertype 2048 (IPv4) that do not match the source IP address 172.16.3.3 (the private IP address of the VM), drop these packets.
- rule1 says: for packets with a hardware source that does not match the listed source MAC address (the VM's MAC address), drop these packets.
- rule2 says: for packets that match a return flow (that is, a packet that belongs to a connection already known to MidoNet), accept these packets.
- rule3 says: for packets that were not dropped as a result of matching previous drop rules, allow these packets to jump to the indicated chain (chain4).
- rule4 says: for packets that do not match the ethertype 2054 (ARP packets), drop these packets.

Listing the OpenStack security group rule chain

You can list all the rule chains and then look at the rule chain for the OpenStack security group.

- To list all the rule chains and examine specific rule chains enter the command:

```
midonet> list chain
chain chain5 name OS_SG_050593ed-56ad-44ef-8489-4052d02d99ff_INGRESS
chain chain0 name OS_PRE_ROUTING_5a151b0b-dea7-4918-bd17-876c1f7f5c64
chain chain1 name OS_POST_ROUTING_5a151b0b-dea7-4918-bd17-876c1f7f5c64
chain chain6 name OS_SG_01fcelb8-c277-4a37-a8cc-86732eea186d_INGRESS
chain chain4 name OS_SG_050593ed-56ad-44ef-8489-4052d02d99ff_EGRESS
chain chain7 name OS_SG_01fcelb8-c277-4a37-a8cc-86732eea186d_EGRESS
chain chain2 name OS_PORT_6f72342b-4947-432f-8d01-0cf4e4b8d049_INBOUND
chain chain3 name OS_PORT_6f72342b-4947-432f-8d01-0cf4e4b8d049_OUTBOUND
```

Note chain5, identified as a chain for an OpenStack security group (OS_SG) for INGRESS traffic.

- To look at rule chain5 enter the command:

```
midonet> chain chain5 list rule
rule rule0 ethertype 2048 src 0.0.0.0/0 proto 6 tos 0 dst-port 5900 pos 1
type accept
rule rule1 ethertype 2048 src 0.0.0.0/0 proto 1 tos 0 pos 2 type accept
rule rule2 ethertype 2048 src 0.0.0.0/0 proto 6 tos 0 dst-port 22 pos 3
type accept
rule rule3 ethertype 2048 src 0.0.0.0/0 proto 6 tos 0 dst-port 80 pos 4
type accept
```

The above output shows the rule chain used to implement the security group you configured in OpenStack. These rules contain the following instructions:

- All the rules match ethertype 2048 (IPv4) packets.
- All the rules match traffic from any source network (0.0.0.0/0).

- All the rules, except rule1, match packets of IP protocol 6 (TCP) and accept them. rule1 matches packets of the ICMP type and accepts them.
- In addition to the other matches already mentioned, the rules match and accept the packets according to the security group rules you defined in OpenStack, specifically, packets with the destinations:
 - TCP port 5900 (VNC)
 - TCP port 22 (SSH)
 - TCP port 80 (HTTP)

- Display information about the infilter (pre-routing) and outfilter (post-routing) chains configured on a tenant router.
- List the rules for the rule chains.

Assumptions

For the example below, assume the following network conditions exist:

- A tenant router named "tenant-router"
- A private network with a 172.16.3.0/24 network address
- A public network with a 198.51.100.0/24 network address
- A VM with a 172.16.3.3 private IP address and a 198.51.100.3 public (floating) IP address

Viewing a Pre-Routing rule

To list routers on the current tenant and the router rule-chain information on the router(s), enter the command:

```
midonet> list router
router router0 name tenant-router state up infilter chain0 outfilter chain1
```

As shown in the above output, chain0 is the router's pre-routing (infilter) rule chain and chain1 is the post-routing (outfilter) rule chain.

To list information about the router's pre-routing rule chain, enter the command:

```
midonet> chain chain0 list rule
rule rule0 dst 198.51.100.3 proto 0 tos 0 in-ports router0:port0 pos 1 type
  dn timer action accept target 172.16.3.3
rule rule1 dst 198.51.100.2 proto 0 tos 0 in-ports router0:port0 pos 2 type
  rev_sn timer action accept
```

rule0 of the pre-routing rule chain on the tenant router contains the following instructions:

- For packets with the destination of 198.51.100.3 (the floating IP address associated with the VM):
 - Perform a destination NAT (DNAT) translation to change the destination IP address from the VM's floating IP address (198.51.100.3) to the VM's private IP address (172.16.3.3).

Viewing a Post-Routing rule

To list the post-routing rule on the tenant router, enter the command:

```
midonet> chain chain1 list rule
rule rule0 src 172.16.3.3 proto 0 tos 0 out-ports router1:port0 pos 1 type
  snat action accept target 198.51.100.3
rule rule1 proto 0 tos 0 out-ports router1:port0 pos 2 type snat action
  accept target 198.51.100.2:1--1
```

rule0 of the post-routing rule on tenant-router contains the following instructions:

2. Create a rule that accepts traffic on a router port with the source 10.100.1.150 and translates the destination to 198.51.100.4:

```
midonet> chain chain7 add rule src 10.100.1.150 out-ports router1:port0  
pos 1 type snat action accept target 198.51.100.4  
chain7:rule2
```

3. Create a rule that accepts traffic from the private network and performs SNAT to translate the source IP address to the IP address of the router's gateway to the public network.

```
midonet> chain chain7 add rule out-ports router1:port0 pos 2 type snat  
action accept target 198.51.100.2
```

Table of Contents

The load balancer service in MidoNet provides Layer 4 (L4) load balancing. A typical use case involves a tenant wishing to balance traffic (load) from floating IP addresses to private IP addresses.

Generally, the traffic comes in from external/publicly routable addresses (for example, from users of the service all over the world) to a virtual IP address (VIP) (often a public, floating IP address, but assigned to the load balancer instead of a VM), and is then load-balanced to numerous private IP addresses within the cloud. The load balancer sends the traffic to the private IP addresses of the back-end servers – in MidoNet’s case, these back-end servers are VMs. The load balancer does not terminate the connection, nor is it really transparent because it’s translating the destination IP.

Configuration overview

As part of the configuration, you define a pool of back-end servers (VMs) to which traffic is load-balanced. The pool members typically have private IP addresses. The placement of the VMs is flexible but must take into account where the load balancer is configured. A general rule is that the VM private addresses **must be** reachable from the router to which the load balancer is attached. Therefore, pool members may

- all belong to a single subnet of the router, or
- they may be placed in two or more subnets of the router

Finally, note that because the load balancer leaves the request source address unmodified, the load balancer must be placed in the path of the return traffic – otherwise return traffic will go directly to the request source without giving the load balancer a chance to reverse the VIP#back-end-IP translation that was applied on the forward packets.

Health monitoring

In addition, you can configure a health monitor to perform checks on the back-end servers. The health monitor automatically removes unhealthy nodes from the pool and adds them back when they return to health.

MidoNet load balancer limitations

MidoNet uses the Neutron API to set up load balancers (as documented in https://wiki.openstack.org/wiki/Neutron/LBaaS/API_1.0) but not all the Neutron LBaaS features are supported in MidoNet:

- L7 load balancing is not supported.
- There are no pool statistics.



```
midonet> router router1 set load-balancer lb0
```

The load balancer assigned to the router will act on traffic flowing through that router.

2. Create a pool to which target back-end servers will be assigned.

```
midonet> load-balancer lb0 create pool lb-method ROUND_ROBIN
lb0:pool0
midonet> load-balancer lb0 pool pool0 show
pool pool0 load-balancer lb0 lb-method ROUND_ROBIN state up
```

3. Next, add target back-end servers to the pool you just created.

```
midonet> load-balancer lb0 pool pool0 create member address 192.168.100.
100 protocol-port 80
lb0:pool0:pm0
midonet> load-balancer lb0 pool pool0 create member address 192.168.100.
101 protocol-port 80
lb0:pool0:pm1
midonet> load-balancer lb0 pool pool0 member pm0 show
pm pm0 address 192.168.100.1 protocol-port 80 weight 0 state up
```

For each back-end server you must add its IP address and port to the pool.

4. Create a virtual IP address (VIP) and port, then assign it to the pool against which load balancing will be performed (lb0:pool0). Typically, a VIP is an IP address from the public IP space.

```
midonet> load-balancer lb0 pool pool0 list vip
midonet> load-balancer lb0 pool pool0 create vip address 203.0.113.2
persistence SOURCE_IP protocol-port 8080
lb0:pool0:vip0
midonet> load-balancer lb0 pool pool0 vip vip0 show
vip vip0 load-balancer lb0 address 203.0.113.2 protocol-port 8080
persistence SOURCE_IP state up
```



Note

Above example uses sticky source IP address persistence, read more about it in [the section called "Sticky Source IP" \[47\]](#).

5. Lastly, you must add a routing rule on the Edge Router (router0) so that a packet sent to the VIP is able to find its way to the Tenant Router where the LB is defined.
 - a. First, identify the ports on the Edge Router, using the `router router0 list port` command, like so:

```
midonet> router router0 list port
port port0 device router0 state up mac 02:c2:0f:b0:f2:68 address 100.
100.100.1 net 100.100.100.0/30
port port1 device router0 state up mac 02:cb:3d:85:89:2a address 172.
168.0.1 net 172.168.0.0/16
port port2 device router0 state up mac 02:46:87:89:49:41 address 200.
200.200.1 net 200.200.200.0/24 peer bridge0:port0
port port3 device router0 state up mac 02:6b:9f:0d:c4:a8 address 169.
254.255.1 net 169.254.255.0/30 peer router1:port0
...
```

Identify the port on the Edge Router that is used to route traffic to the Tenant Router (router1). In this example, we see port3 on device router0 is peered to the Tenant Router port (router1:port0).



Health monitor

Health monitoring is the act of checking a set of pool members for "aliveness". This usually means HTTP, TCP, UDP, or ICMP connectivity is possible to the node.

In MidoNet's case, only TCP connectivity is checked. Health monitors work by sending packets to the pool members and checking whether or not they receive a reply. The node is considered ACTIVE if the pool member responds to the packet within a certain amount of time, and after a certain amount of retries. Therefore, health monitors act on the following three variables:

- **max_retries:** How many times the health monitor sends a packet to the pool member without receiving a response before the health monitor considers the node to be INACTIVE
- **delay:** Amount of time between each transmission of a packet from the health monitor to the pool member
- **timeout:** Additional timeout after a connection has been established

The health monitor keeps track of the current state of all pool members it is assigned to. Load balancing decisions can then be made based on the "aliveness" of a pool member.

HAProxy configuration

When using a Layer 4 load balancer, you can configure a health monitor to perform checks on the back-end servers.

Only a single host runs all health monitor instances at a given time. If that host goes down for any reason, a different host will be elected and spawn the HAProxy instances. These instances are managed by the MidoNet Agent and do not require any special set-up. However, hosts that can potentially hold the HAProxy instances have to be chosen.

To enable a MidoNet Agent host for health monitoring, its `health_monitor_enable` property has to be set to `true`.

Run the following command to check if a host is enabled for health monitoring:

```
$ mn-conf get agent.haproxy_health_monitor.health_monitor_enable
```

To toggle health monitoring for a certain host, use the following commands on that host:

```
$ echo "agent.haproxy_health_monitor.health_monitor_enable : true" | mn-conf set -h local
```

```
$ echo "agent.haproxy_health_monitor.health_monitor_enable : false" | mn-conf set -h local
```

Additionally, the hosts running the HAProxy instances must have a group called "nogroup" and a user called "nobody", otherwise HAProxy will not be able to start. While this is a default configuration on Ubuntu, on Red Hat you must create this user and group.

How the Health Monitor works in the MidoNet Agent

- The MidoNet Agent does not implement its own health monitor. Instead, it leverages the health checker that is a part of HAProxy.


```
midonet> health-monitor hm0 pool list
pool pool0 load-balancer lb0 health-monitor hm0 lb-method ROUND_ROBIN state
up
```

Disabling Health Monitoring

To disable health monitoring on a pool you can do perform one of the following:

- Set the `admin_state_up` on the health monitor to false. Note that all pools that are using this health monitor will have health monitoring disabled.
- Set the `health_monitor_id` on the pool to null.
- Delete the health monitor object.



A single L4 flow may generate up to two different flows: one to handle non-header fragments, another to handle all other packets.

Fragmented packets rule chain creation example

Create a chain (this creates a rule chain with an alias, "chain0" in the example, pointing to the chain created):

```
create chain name chain0
```

Add a rule to the chain that drops header fragments:

```
chain chain0 add rule fragment-policy header pos 2 header type drop
```

Example 1 Firewall, Does Not Account for Fragmented Packets

The example below only handles non-fragmented packets. These are the firewall rules you start with before you decide to handle fragmented packets.

Initially, you design your firewall to:

- Only allow incoming TCP port 80 (HTTP) traffic
- Drop all other packets

Without addressing fragmented packets, you create a rule chain with the following two rules:

- Rule at position 1
 - By default, this rule matches only non-fragmented packets and header fragments.
 - ACCEPTs packets with protocol=TCP and destination=80.

```
midonet> chain chain0 add rule ethertype 2048 src 0.0.0.0/0 proto 6 in-ports router2:port0 dst-port 80 pos 1 type accept
```

- Rule at position 2
 - DROPS all packets.

```
midonet> chain chain0 add rule ethertype 2048 src 0.0.0.0/0 dst 0.0.0.0/0 in-ports router2:port0 pos 2 type drop
```

```
midonet> chain chain0 list rule
rule rule0 ethertype 2048 src 0.0.0.0/0 proto 6 tos 0 dst-port 80 in-ports router2:port0 pos 1 type accept
rule rule1 ethertype 2048 src 0.0.0.0/0 dst 0.0.0.0/0 proto 0 tos 0 in-ports router2:port0 pos 2 type drop
```


With the above rule chain, MidoNet handles fragmented packet with the destination TCP port 80 as follows:

- The first half of the packet, which contains the TCP header, reaches the rule at position 1, and is accepted.

- However, the second half of the fragmented, which does not have the destination port, reaches the rule at position 1, does not match the rule's condition, and is dropped. This means the fragmented packets do not reach the Web server.

Example 2 Firewall, Addresses Fragmented Packets


To address this problem, MidoNet provides a mechanism to handle the fragmented packets. This mechanism allows the fragmented packets to reach their destination, as shown in the following example. The drawing below simply depicts a whole, non-fragmented packet and a fragmented packet that consists of two parts, a header and non-header.



Non-Fragmented and Fragmented Packets

For this example, consider the following packets:

- Non-fragmented packet with the destination, TCP port 80
- Fragmented packet with the destination, TCP port 80
- Non-fragmented packet with the destination, TCP port 72
- Fragmented packet with the destination, TCP port 72



Given the above packets and the rule in example 1, MidoNet processes the packets as follows:

- Packet 1 matches the rule in position 1 and is accepted.
- The header part of packet 2 matches the rule in position 1 and is accepted; the non-header fragment, which doesn't contain the destination, does not match the rule and is dropped.
- Packet 3's destination does not match the rule in position 1 and is dropped, same thing for the header part of packet 4. The non-header part of packet 4 does not contain destination information and is dropped.

- Rule at position 1
 - By default, this rule matches only non-fragmented packets and header fragments.
 - ACCEPTs packets from in-ports=router2:port0 with protocol=TCP and destination=80.

- Rule at position 2
 - Drop packets that contain TCP/UDP headers

- Rule at position 3
 - Accept all other packets

Look at the packets in the above figure, starting with the packets destined for port 72, and how they progress through this new rule chain:

- 55

- The non-header fragment of packet 4 does not contain a header (and therefore, has no destination information), does not match the rule at position 1, and continues to the rule at position 2.
- This non-header packet fragment does not contain a TCP/UDP header, does not match the rule at position 2, and continues to the rule at position 3.
- The rule at position 3 accepts all packets that reach it and accepts this packet fragment. Because this packet does not have any associated header information it will not be reassembled and sent to an application and will eventually be dropped.

Looking at packets 1 and 2:

- Packet 1 is destined for TCP port 80, matches the rule at position 1, and is accepted.
- For packet 2, the packet fragment with the header contains a destination of TCP port 80, matches the rule at position 1, and is accepted.
- The non-header packet fragment of packet number 2 does not contain a header, does not match the rule at position number 1, and continues to the rule at position number 2.
- This non-header packet fragment does not contain a TCP/UDP header, therefore does not match the rule at position number 2, is not dropped, and continues to the rule at position number 3.
- The rule at position number 3 accepts all packets, so this packet fragment is accepted.

This change allows non-header fragments to get past both the rules at positions 1 and 2, and exit the chain with an ACCEPT. With this change, the firewall now lets all non-header fragments through, but you decided that the level of risk is acceptable and are just trying to fix the broken HTTP flows. This is not a problem, as an unwanted non-header fragment will be discarded if the corresponding header fragment is never received.

Configuration

You can specify resource protection configuration parameters using `mn-conf(1)`, in the `agent.datapath` section. The available parameters are:

- `global_incoming_burst_capacity` - this sets the size of the top-level bucket and also defines the total number of tokens in the system (corresponding to in-flight packets) that will be divided among the different levels in the HTB; the rate at which tokens are placed back in the bucket is a function of the rate at which they are processed.
- `tunnel_incoming_burst_capacity` - this sets the capacity of the bucket associated with tunnel traffic, enforcing the rate at which a MidoNet Agent can communicate with the other Agents.
- `vm_incoming_burst_capacity` - this sets the capacity of each VM leaf bucket, which is below the shared VM bucket. This parameter enforces the rate at which individual VMs can send traffic.
- `vtep_incoming_burst_capacity` - this sets the capacity of the bucket associated with the VxLAN VTEP functionality, which enforces the rate at which the MidoNet Agent can communicate with the VxLAN domain.

See the `mn-conf(1)` schemas for more information about the above parameters.

Recommended values for these properties depend on the role of the MidoNet host (Gateway vs. Compute Node) and interaction with other resource-related properties, like JVM-memory and flow-table size. Midolman RPM and Debian packages include versions of each configuration tuned for Compute/Gateway hosts respectively. You can find these configurations in `/etc/midolman`, alongside the default configuration files. See "Recommended Values" for a table of recommended values.

Disabling Resource Protection

You can disable the resource protection feature.

To disable resource protection:

1. Specify a size value of "0" for all the parameters described in the Configuration section, except for the `global_incoming_burst_capacity` parameter.

This will cause all tokens to accumulate in the global bucket and all the traffic will be distributed from this single bucket.

13. MidoNet monitoring

Table of Contents

Metering	59
Monitoring Network State Database	61
Monitoring Midolman Agents	64
Monitoring events	66
Packet Tracing	75
Port mirroring	76

MidoNet is composed of various services; each service exposes a variety of metrics that can be fetched from typical monitoring services, such as Zabbix™, Munin, and so on.

This chapter describes the main available metrics for each service, as well as a procedure to configure a basic monitoring infrastructure based on Munin, based on scripts provided with the MidoNet deployment package.

Metering

Note: This feature is in **experimental** status.

Overview

The goal of metering is to provide packets and bytes traffic counters for arbitrary slices of the traffic that travels through MidoNet.

A meter is a counter of bytes and packets, associated with a name. In order to be incremented, the meter needs to have flows associated with it. MidoNet agents will automatically associate flows with certain meters, and users can create their own custom meters setting the `meterName` attribute in chain rules.

For example, all traffic going through bridge with uuid `FOO` in MidoNet be counted under meter `meters:device:FOO`. All traffic egressing port `BAR` will also be reflected in meter `meters:port:tx:BAR`.

MidoNet agents offer these counters for their partial view of overlay traffic. In other words, each agent will provide meters that only account for the traffic that agent has simulated. For a given meter, the MidoNet-wide real value is the sum of the value of this meter across all agents.

Note: Metering data is meant to be polled and stored by a monitoring layer onto a time series database. Thus agents don't persist the metering data they gather, and meter values will reset to zero when an agent reboots. **Any metering data collection layer should account for this effect and detect counter resets.**

Querying meters

Agents publish meters over JMX and a command line tool, `mm-meter`, uses their JMX interface to list, fetch and monitor meter values.

For example code on the JMX interface, the best source is [the code of mm-meter itself](#).

Querying meters with `mm-meter` is very simple:

```
$ mm-meter --help
-h, --host <arg>      Host (default = localhost)
-p, --port <arg>      JMX port (default = 7200)
--help                Show help message

Subcommand: list - list all active meters
--help                Show help message
Subcommand: get
-n, --meter-name <arg> name of the meter
--help                Show help message

trailing arguments:
delay (not required)  delay between updates, in seconds. If no delay is
                        specified, only one report is printed. (default = 0)
count (not required)  number of updates, defaults to infinity
                        (default = 2147483647)
```

The `list` command will print a list of all meters known to this agent:

```
$ mm-meter list
meters:user:port0-on-the-bridge
meters:port:rx:cf453c9d-94c4-4c27-ba32-529b7cbacf1d
meters:device:845a54bf-b702-4dc2-8958-bbe7156bc4ef
meters:port:tx:cf453c9d-94c4-4c27-ba32-529b7cbacf1d
meters:port:tx:9182485b-8f86-462d-a8be-62586060eeb9
meters:device:f0dlf093-2de7-49a1-a5ec-898f94769e34
meters:device:9182485b-8f86-462d-a8be-62586060eeb9
meters:port:rx:9182485b-8f86-462d-a8be-62586060eeb9
meters:device:cf453c9d-94c4-4c27-ba32-529b7cbacf1d
```

And the `get` command will print the *current, local* counters for a meter. It takes a delay, in which case it will poll the meter and print deltas periodically:

```
$ mm-meter get -n meters:port:rx:cf453c9d-94c4-4c27-ba32-529b7cbacf1d 10
  packets      bytes
    568935    4215888475
         0         0
         0         0
        23        5834
         0         0
```

Creating a custom meter

Operators may want to meter a custom slice of their virtual network traffic. This is possible by matching on that slice using one or several chain rules in the virtual topology. The `meterName` property in chain rules will assign matching flows to the meter referred to by its value, in addition to the meters that flow would naturally feed.

Besides using the REST API, operators can use `midonet-cli` to set up such rules. The following rule will assign to meter `my-meter` all traffic that hits the rule after having traversed device `9182485b-8f86-462d-a8be-62586060eeb9`:

```
midonet> chain chain0 list rule
rule rule0 proto 0 tos 0 traversed-device 9182485b-8f86-462d-
a8be-62586060eeb9 fragment-policy any pos 1 type accept meter my-meter
```

Note that, when inspecting meters `my-meter` will turn into `meters:user:my-meter`, to avoid naming conflicts with built-in meters.

Monitoring Network State Database

The Network State Database is deployed with Cassandra and ZooKeeper instances. Both offer JMX bindings.

The configuration provided with MidoNet uses only a subset of the most relevant for our use cases. Details in the sections below provide additional information about the metrics configured by MidoNet's deployment scripts, as well as an explanation about what to watch.

Cassandra

By default, Cassandra uses port 7199 for JMX service from all its nodes and you can connect using jconsole for a comprehensive view.

Additionally, Cassandra's own nodetool utility offers commands like cfstats and tpstats that allow access to valuable stats into keyspaces, tables, column families, and so on on a given node.

For a rich reference into Cassandra monitoring, visit the official documentation (go to <http://www.datastax.com/>, and search for "monitoring a Cassandra cluster").

Below are descriptions of the graphs resulting from the example Munin configurations provided in the MidoNet deployment repository. The graphs are built from a subset of the Cassandra JMX service. The available graphs are:

Cache Reqs vs. Hits

This is self-descriptive, ideally you want the cache hits to be as close to the requests as possible. Note that by default MidoNet Cassandra nodes only enable the Partition Key Cache, but not Row Cache, so it's normal that these stay at 0. For MidoNet the Partition Key Cache should effectively be very similar to the Row Key Cache because our column families (CF) have only one column and therefore rows are not spread across several SSTables.

Compactions

This indicates the number of bytes being compacted. Typical workloads will present regular small spikes when the minor compaction jobs are run, and infrequent large spikes when major compactions are run. A large number of compactions indicates the need to add capacity to the cluster.

Internal Tasks

These are internal Cassandra tasks. The most important are:

- Gossip: MidoNet's Cassandra nodes are expected to spend a fair amount of their time busy in Gossip (wherein state information transfers among peers).
- MemTable Post Flusher: memtable flushes that are waiting to be written to the commit log. These should be as low as possible, and definitely not sustained.
- Hinted Handoff tasks: the appearance of these tasks indicates cases where replicas are detected as unavailable, so non-replica nodes need to temporarily store data until the replicas become available. Frequent Hinted Handoff spikes may hint at nodes being partitioned from the cluster.

whether problems are related to a single CF or the entire storage. More importantly: it indicates what features may be impacted in Midolman agents.

In the aggregated view, an additional "clock" category configured in Munin shows the result of the time command in each of the nodes. Expect to see a straight line, as close as possible with the lines of all Cassandra nodes overlapping. Otherwise, this indicates divergences in the host's clocks that will almost certainly end up causing problems on conflict resolution. You should attend to this urgently and ensure that all hosts are using the Network Time Protocol (NTP).

The installation script also provides graphs to monitor the state of Cassandra's Java virtual machine (JVM):

- JVM garbage-collection (GC) times
- JVM Heap Summary
- JVM Non-Heap Summary

Descriptions of these graphs are beyond the scope of this guide, but high JVM GC times are the best indication that Cassandra may be consuming too much time on garbage collection. This will correlate with high latency accessing Midolman's column families, which will propagate to Midolman. The Midolman agent will increase simulation latency and also degrade the utilization of CPU resources (experiencing more idle time while waiting for responses from Cassandra).

ZooKeeper

The `install_plugins.sh` script also installs a set of Munin plugins and configuration files to generate graphs from ZooKeeper's exposed JMX metrics.

However, on each node, you need to indicate the ZooKeeper replica number; the script provides clear guidance on how to do this.

You can find ZooKeeper stats in the "zookeeper" category of the MidoStorage group. ZooKeeper classifies metrics in separate MBeans for leader/follower, so each node will report some values twice, one in the "Follower" role, another in the "Leader" role. Take into account that a given node may change roles (for example, if the leader shuts down, a follower node may be promoted to leader). You can easily spot these events. For example, the line in the "Connection Count as Follower" will suddenly blank out, and another will appear in the "Connection Count as Leader" graph.

Below are descriptions of the graphs resulting from the example Munin configurations provided in the MidoNet deployment repository. The graphs are built from a subset of the ZooKeeper JMX service. The available graphs are:

Connection Count (as Follower/Leader)

These two graphs display the number of live connections to this node in its role at a givenpoint in time.

In Memory Data Tree (as Follower/Leader)

Exposes the size of the in-memory znode database, both data nodes and watch count.

Latency (as Follower/Leader)

Exposes the average and maximum latency experienced in connections.

- The Old Generation is expected to contain a baseline of long-lived objects that get reused during simulations. An amount of short-lived objects may also be pushed from the young generation, eventually also filling the old generation and triggering a GC event that will collect them. This will show as a see-saw pattern in the "Old used". The see-saw should converge to oscillating between stable max./min. values on top of the long-lived objects baseline.
- Large spikes indicate higher CPU consumption in GC and are usually associated with a certain throughput degradation. You may slightly alleviate this by increasing the size of the Eden.
- JVM GC times: shows the duration of the last garbage collection performed by the ConcurrentMarkSweep's collector, (which runs only on the old generation). It is closely associated with the see-saw pattern described above.
- Note that these times do not stop the application completely, because part of the work is done concurrently. The main impact is in CPU "stolen" from Midolman.

Munin offers some generic metrics that are very relevant to understanding the performance of Midolman.

CPU Usage

Under high traffic, Midolman should tend to saturate all CPUs, reflecting in the graph as high "user" utilization and little or no "idle". Note that "user" may include other processes, so especially in Gateway Nodes, you should verify that only Midolman is consuming most of CPU time dedicated to user processes. High "system", "iowait" indicators are clear indication of high load, excessive context switching, and contention or other problems on the host.

Monitoring events

This section describes how MidoNet's event system works so you can monitor the system's day-to-day operations.

Overview

This section provides a high-level overview of the information covered regarding event monitoring.

Categories of Event Messages

Below are the following types of events defined in the MidoNet system:

- Changes in the virtual topology
- Events concerning the MidoNet API server, including:
 - Changes to the connection status to the Network State Database
- Events concerning MidoNet Agents, including:
 - Changes to the connection status to the Network State Database
 - Changes affecting the status of network interfaces (for example, physical network interfaces and taps)
 - Daemons starting and exiting

Configuration

Each event message is generated with logback (<http://logback.qos.ch/>).

The configuration files are located at the following locations, depending on the type of the node.

Table 13.1. Configuration Files/Locations

Type of Node	Location of the Configuration File
MidoNet Network Agent	/etc/midolman/logback.xml
MidoNet Cluster server	/etc/midonet-cluster/logback.xml

Below are the behaviors with the default configuration shipped with the MidoNet release, but you can configure the behaviors as you like. See <http://logback.qos.ch/manual/index.html> for instructions on how to configure the logback.xml file.

Event log files locations

Event messages are stored locally on the filesystem in a separate file, in addition to the ordinary log file.

Table 13.2. Event Message Files/Locations

Type of Node	Location
MidoNet Network Agent	/var/log/midolman/midolman.event.log
MidoNet API server	/var/log/tomcat6/midonet-api.event.log (on Red Hat) /var/log/tomcat7/midonet-api.event.log (on Ubuntu)



Tip

In addition to midolman.event.log, /var/log/midolman/midolman.log contains additional debug information. You do not normally need to use it, but it may contain useful troubleshooting information.

Message format

By default, event messages have the following format.

```
<pattern>%d{yyyy.MM.dd HH:mm:ss.SSS} ${HOSTNAME} %-5level %logger - %m%n
%rEx </pattern>
```

See <http://logback.qos.ch/manual/layouts.html> for details about the above placeholders.

List of event messages

This section lists the event messages.

The event messages are organized in the following major categories:

- Virtual topology events
- API server events
- MidoNet Agent events

Virtual topology events

This section describes the messages associated with virtual topology events.

Router

Logger	org.midonet.event.topology.Router.CREATE
Message	CREATE routerId={0}, data={1}.
Level	INFO
Explanation	Router with routerId={0} was created.
Corrective Action	N/A

Logger	org.midonet.event.topology.Router.UPDATE
Message	UPDATE routerId={0}, data={1}.
Level	INFO
Explanation	Router with routerId={0} was updated to {1}.
Corrective Action	N/A

Logger	org.midonet.event.topology.Router.DELETE
Message	DELETE routerId={0}.
Level	INFO
Explanation	Router with routerId={0} was deleted.
Corrective Action	N/A

Logger	org.midonet.event.topology.Router.ROUTE_CREATE
Message	ROUTE_CREATE routerId={0}, data={1}.
Level	INFO
Explanation	Route={1} was created in routerId={0}.
Corrective Action	N/A

Logger	org.midonet.event.topology.Router.ROUTE_DELETE
Message	ROUTE_DELETE routerId={0}, routeId={1}.
Level	INFO
Explanation	routeId={1} was deleted in routerId={0}.
Corrective Action	N/A

Bridge

Logger	org.midonet.event.topology.Bridge.CREATE
Message	CREATE bridgeId={0}, data={1}.
Level	INFO
Explanation	Bridge with bridgeId={0} was created.
Corrective Action	N/A

Logger	org.midonet.event.topology.Bridge.UPDATE
Message	UPDATE bridgeId={0}, data={1}.
Level	INFO
Explanation	Bridge with bridgeId={0} was updated to {1}.
Corrective Action	N/A

Logger	org.midonet.event.topology.Bridge.DELETE
Message	DELETE bridgeId={0}.

Port

Level	INFO
Explanation	Bridge with bridged={0} was deleted.
Corrective Action	N/A

Logger	org.midonet.event.topology.Port.CREATE
Message	CREATE portId={0}, data={1}.
Level	INFO
Explanation	Port with portId={0} was created.
Corrective Action	N/A

Logger	org.midonet.event.topology.Port.UPDATE
Message	UPDATE portId={0}, data={1}.
Level	INFO
Explanation	Port with portId={0} was updated to {1}.
Corrective Action	N/A

Logger	org.midonet.event.topology.Port.DELETE
Message	DELETE portId={0}.
Level	INFO
Explanation	Port with portId={0} was deleted.
Corrective Action	N/A

Logger	org.midonet.event.topology.Port.LINK
Message	LINK portId={0}, data={1}.
Level	INFO
Explanation	Port with portId={0} was linked.
Corrective Action	N/A

Logger	org.midonet.event.topology.Port.UNLINK
Message	UNLINK portId={0}, data={1}.
Level	INFO
Explanation	Port with portId={0} was unlinked.
Corrective Action	N/A

Logger	org.midonet.event.topology.Port.BIND
Message	BIND portId={0}, data={1}.
Level	INFO
Explanation	Port with portId={0} was bound.
Corrective Action	N/A

Logger	org.midonet.event.topology.Port.UNBIND
Message	UNBIND portId={0}.
Level	INFO
Explanation	Port with portId={0} was unbound.
Corrective Action	N/A

Chain

Logger	org.midonet.event.topology.Chain.CREATE
Message	CREATE chainId={0}, data={1}.

Level	INFO
Explanation	Chain with chainId={0} was created.
Corrective Action	N/A

Logger	org.midonet.event.topology.Chain.DELETE
Message	DELETE chainId={0}.
Level	INFO
Explanation	Chain with chainId={0} was deleted.
Corrective Action	N/A

Rule

Logger	org.midonet.event.topology.Rule.CREATE
Message	CREATE ruleId={0}, data={1}.
Level	INFO
Explanation	Rule with ruleId={0} was created.
Corrective Action	N/A

Logger	org.midonet.event.topology.Rule.DELETE
Message	DELETE ruleId={0}.
Level	INFO
Explanation	Rule with ruleId={0} was deleted.
Corrective Action	N/A

Tunnel Zone

Logger	org.midonet.event.topology.TunnelZone.CREATE
Message	CREATE tunnelZoneId={0}, data={1}.
Level	INFO
Explanation	TunnelZone with tunnelZoneId={0} was created.
Corrective Action	N/A

Logger	org.midonet.event.topology.TunnelZone.UPDATE
Message	UPDATE tunnelZoneId={0}, data={1}.
Level	INFO
Explanation	TunnelZone with tunnelZoneId={0} was updated to {1}.
Corrective Action	N/A

Logger	org.midonet.event.topology.TunnelZone.DELETE
Message	DELETE tunnelZoneId={0}.
Level	INFO
Explanation	TunnelZone with tunnelZoneId={0} was deleted.
Corrective Action	N/A

Logger	org.midonet.event.topology.TunnelZone.MEMBER_CREATE
Message	MEMBER_CREATE tunnelZoneId={0}, data={1}.
Level	INFO
Explanation	TunnelZone member={1} was added to tunnelZoneId={0}.
Corrective Action	N/A

Logger	org.midonet.event.topology.TunnelZone.MEMBER_DELETE
--------	---

Message	MEMBER_DELETE tunnelZoneId={0}, data={1}.
Level	INFO
Explanation	TunnelZone member={1} was deleted from tunnel-ZoneId={0}.
Corrective Action	N/A

BGP

Logger	org.midonet.event.topology.Bgp.CREATE
Message	CREATE bgpId={0}, data={1}.
Level	INFO
Explanation	Bgp with bgpId={0} was created.
Corrective Action	N/A

Logger	org.midonet.event.topology.Bgp.UPDATE
Message	UPDATE bgpId={0}, data={1}.
Level	INFO
Explanation	Bgp with bgpId={0} was updated to {1}.
Corrective Action	N/A

Logger	org.midonet.event.topology.Bgp.DELETE
Message	DELETE bgpId={0}.
Level	INFO
Explanation	Bgp with bgpId={0} was deleted.
Corrective Action	N/A

Logger	org.midonet.event.topology.Bgp.ROUTE_CREATE
Message	ROUTE_CREATE bgpId={0}, data={1}.
Level	INFO
Explanation	Route={1} was added to bgpId={0}.
Corrective Action	N/A

Logger	org.midonet.event.topology.Bgp.ROUTE_DELETE
Message	ROUTE_DELETE bgpId={0}, data={1}.
Level	INFO
Explanation	Route={1} was deleted from bgpId={0}.
Corrective Action	N/A

LoadBalancer

Logger	org.midonet.event.topology.LoadBalancer.CREATE
Message	CREATE loadBalancerId={0}, data={1}.
Level	INFO
Explanation	LoadBalancer with loadBalancerId={0} was created.
Corrective Action	N/A

Logger	org.midonet.event.topology.LoadBalancer.UPDATE
Message	UPDATE loadBalancerId={0}, data={1}.
Level	INFO
Explanation	LoadBalancer with loadBalancerId={0} was updated to {1}.
Corrective Action	N/A

Logger	org.midonet.event.topology.LoadBalancer.DELETE
Message	DELETE loadBalancerId={0}.
Level	INFO
Explanation	LoadBalancer with loadBalancerId={0} was deleted.
Corrective Action	N/A

VIP

Logger	org.midonet.event.topology.VIP.CREATE
Message	CREATE vipId={0}, data={1}.
Level	INFO
Explanation	VIP with vipId={0} was created.
Corrective Action	N/A

Logger	org.midonet.event.topology.VIP.UPDATE
Message	UPDATE vipId={0}, data={1}.
Level	INFO
Explanation	VIP with vipId={0} was updated to {1}.
Corrective Action	N/A

Logger	org.midonet.event.topology.VIP.DELETE
Message	DELETE vipId={0}.
Level	INFO
Explanation	VIP with vipId={0} was deleted.
Corrective Action	N/A

Pool

Logger	org.midonet.event.topology.Pool.CREATE
Message	CREATE poolId={0}, data={1}.
Level	INFO
Explanation	Pool with poolId={0} was created.
Corrective Action	N/A

Logger	org.midonet.event.topology.Pool.UPDATE
Message	UPDATE poolId={0}, data={1}.
Level	INFO
Explanation	Pool with poolId={0} was updated to {1}.
Corrective Action	N/A

Logger	org.midonet.event.topology.Pool.DELETE
Message	DELETE poolId={0}.
Level	INFO
Explanation	Pool with poolId={0} was deleted.
Corrective Action	N/A

PoolMember

Logger	org.midonet.event.topology.PoolMember.CREATE
Message	CREATE poolMemberId={0}, data={1}.
Level	INFO
Explanation	PoolMember with poolMemberId={0} was created.

Corrective Action	N/A
-------------------	-----

Logger	org.midonet.event.topology.PoolMember.UPDATE
Message	UPDATE poolMemberId={0}, data={1}.
Level	INFO
Explanation	PoolMember with poolMemberId={0} was updated to {1}.
Corrective Action	N/A

Logger	org.midonet.event.topology.PoolMember.DELETE
Message	DELETE poolMemberId={0}.
Level	INFO
Explanation	PoolMember with poolMemberId={0} was deleted.
Corrective Action	N/A

HealthMonitor

Logger	org.midonet.event.topology.HealthMonitor.CREATE
Message	CREATE healthMonitorId={0}, data={1}.
Level	INFO
Explanation	HealthMonitor with healthMonitorId={0} was created.
Corrective Action	N/A

Logger	org.midonet.event.topology.HealthMonitor.UPDATE
Message	UPDATE healthMonitorId={0}, data={1}.
Level	INFO
Explanation	HealthMonitor with healthMonitorId={0} was updated to {1}.
Corrective Action	N/A

Logger	org.midonet.event.topology.HealthMonitor.DELETE
Message	DELETE healthMonitorId={0}.
Level	INFO
Explanation	HealthMonitor with healthMonitorId={0} was deleted.
Corrective Action	N/A

API server events

This section describes the messages associated with API server events.

NSDB (Network State Database)

Logger	org.midonet.event.api.Nsdb.CONNECT
Message	CONNECT Connected to the NSDB cluster.
Level	INFO
Explanation	API server was connected to the NSDB cluster.
Corrective Action	N/A

Logger	org.midonet.event.api.Nsdb.DISCONNECT
Message	DISCONNECT Disconnected from the NSDB cluster.
Level	WARNING
Explanation	API server was disconnected from the NSDB cluster.

Corrective Action	If the connection is restored after this event, no corrective action is required. If this event continues, check the network connection between the API server and the NSDB cluster.
Logger	org.midonet.event.api.Nsdb.CONN_EXPIRE
Message	CONN_EXPIRE Connection to the NSDB cluster expired.
Level	ERROR
Explanation	The connection from the API server to the NSDB cluster expired.
Corrective Action	Check the network connection between the API server and the NSDB cluster and restart the MidoNet API server so it reconnects to the NSDB cluster.

MidoNet Agent events

This section describes the messages associated with MidoNet Agent events.

NSDB

Logger	org.midonet.event.agent.Nsdb.CONNECT
Message	CONNECT Connected to the NSDB cluster.
Level	INFO
Explanation	MidoNet Agent was connected to the NSDB cluster.
Corrective Action	N/A

Logger	org.midonet.event.agent.Nsdb.DISCONNECT
Message	DISCONNECT Disconnected from the NSDB cluster.
Level	WARNING
Explanation	MidoNet Agent was disconnected from the NSDB cluster.
Corrective Action	If the connection is restored after this event, no corrective action is required. If this event continues, check the network connection between the MidoNet Agent and the NSDB cluster.

Logger	org.midonet.event.agent.Nsdb.CONN_EXPIRE
Message	CONN_EXPIRE Connection to the NSDB cluster expired. Shutting down the MidoNet Agent.
Level	ERROR
Explanation	The connection from the MidoNet Agent to the NSDB cluster expired. Shutting down the MidoNet Agent.
Corrective Action	Check the network connection between the MidoNet Agent node and the NSDB cluster and restart the MidoNet Agent service on the node so it reconnects to the NSDB cluster.

Interface

Logger	org.midonet.event.agent.Interface.DETECT
Message	NEW interface={0}
Level	INFO
Explanation	MidoNet Agent detected a new interface={0}.
Corrective Action	N/A

Logger	org.midonet.event.agent.Interface.UPDATE
--------	--

Message	UPDATE interface={0} was updated.
Level	INFO
Explanation	MidoNet Agent detected an update in interface={0}.
Corrective Action	N/A

Logger	org.midonet.event.agent.Interface.DELETE
Message	DELETE interface={0} was deleted.
Level	INFO
Explanation	MidoNet Agent detected that interface={0} was deleted.
Corrective Action	N/A

Service

Logger	org.midonet.event.agent.Service.START
Message	START Service started.
Level	INFO
Explanation	Service started.
Corrective Action	N/A

Logger	org.midonet.event.agent.Service.EXIT
Message	EXIT Service exited.
Level	WARNING
Explanation	Service exited.
Corrective Action	Restart the MidoNet Agent service if this event happened unintentionally. If this event recurs, file a ticket in the bug tracker for further investigation by developers.

Packet Tracing

To configure packet tracing (via logging) in a MidoNet Agent (Midolman), the 'mm-trace' command can be used.

A MidoNet Agent can hold a set of filters that, when matching on an incoming packet, will cause it to log everything about its simulation to the agent's log file, regardless of the configured log level.

All trace messages have a "cookie:" prefix to identify its packet, and that can be used as a grep expression to filter out any non-tracing messages.



Important

The filters are not persistent, they are lost every time the agent is rebooted.

However, mm-trace prints the filters in exactly the same syntax that it will accept to re-add them again, allowing operators to easily replay the commands.

Usage

All available options can be displayed with the '-help' option:

```
$ mm-trace --help
-h, --host <arg>  Host (default = localhost)
```

```

-p, --port <arg>    JMX port (default = 7200)
--help              Show help message

Subcommand: add - add a packet tracing match
-d, --debug          logs at debug level
--dst-port <arg>     match on TCP/UDP destination port
--ethertype <arg>    match on ethertype
--ip-dst <arg>       match on ip destination address
--ip-protocol <arg>  match on ip protocol field
--ip-src <arg>       match on ip source address
-l, --limit <arg>    number of packets to match before disabling
this trace
--mac-dst <arg>      match on destination MAC address
--mac-src <arg>      match on source MAC address
--src-port <arg>     match on TCP/UDP source port
-t, --trace          logs at trace level
--help              Show help message

Subcommand: remove - remove a packet tracing match
-d, --debug          logs at debug level
--dst-port <arg>     match on TCP/UDP destination port
--ethertype <arg>    match on ethertype
--ip-dst <arg>       match on ip destination address
--ip-protocol <arg>  match on ip protocol field
--ip-src <arg>       match on ip source address
-l, --limit <arg>    number of packets to match before disabling
this trace
--mac-dst <arg>      match on destination MAC address
--mac-src <arg>      match on source MAC address
--src-port <arg>     match on TCP/UDP source port
-t, --trace          logs at trace level
--help              Show help message

Subcommand: flush - clear the list of tracing matches
-D, --dead-only      flush expired tracers only
--help              Show help message

Subcommand: list - list all active tracing matches
-L, --live-only      list active tracers only
--help              Show help message

```

Example

```

$ mm-trace list
$ mm-trace add --debug --ip-dst 192.0.2.1
$ mm-trace add --trace --ip-src 192.0.2.1 --dst-port 80
$ mm-trace list
tracer: --debug --ip-dst 192.0.2.1
tracer: --trace --ip-src 192.0.2.1 --dst-port 80
$ mm-trace remove --trace --ip-src 192.0.2.1 --dst-port 80
Removed 1 tracer(s)
$ mm-trace flush
Removed 1 tracer(s)

```

Port mirroring

Port mirroring lets operators monitor arbitrary subsets of traffic in the overlay in specified vports. This can be useful for passive monitoring or for active troubleshooting.

MidoNet v5.0 introduces port mirroring based on these concepts:

1. A new type of virtual device: **mirror**.
2. Each mirror is associated with a destination virtual port, through its **to-port** attribute. This is where mirror traffic will be copied to.

- AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

- AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

- AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

- AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

- Exposing VTEP state through the MidoNet REST API.
- Configuring the VTEP switch in order to implement the bindings configured through the MidoNet REST API.
- Acting as an L2 control plane for traffic flowing between MN and the VTEP.

VXLAN Flooding Proxy

Depending on the virtual topology, it may not always be possible to instruct the VTEP to tunnel to a specific physical location. This will typically happen on BUM (Broadcast, Unknown and Multicast) traffic. In these cases MidoNet will instruct the VTEP to tunnel the packet to a service node in order for it to be simulated and delivered to the right destination. This node is called the "Flooding Proxy", and it has the same properties:

- The weight assigned to a MidoNet Agent defaults to 1, and can be altered issuing the following command on the MidoNet CLI:

Higher weights will imply a higher probability of the host being chosen as Flooding Proxy.

Note that the Flooding Proxy may potentially process a large volume of traffic. In these circumstances it is recommended to assign a much higher weight to a dedicated host.

Connecting to the VTEP

1. Refer to the documentation of your switch to enable VXLAN on it, then configure it as a VTEP with all the required parameters.

82

```
vtep-ctl list Physical_switch
```

```
vtep-ctl list-ports <vtep-name>
```

- To test the connection to the management database, you can run:

```
$ telnet <management-ip> <management-port>
Trying <management-ip>...
Connected to <management-ip>
Escape character is '^['.
```

At this point, paste this on the console:

```
{"method":"list_dbs","id":"list_dbs","params":[]}
```

And you should see this reply:

```
{"id":"list_dbs","error":null,"result":["hardware_vtep"]}
```

This just verified that the OVSDB server that holds the configuration of this VTEP is active and handling connections. If you did not get a similar reply, please review the configuration of the VTEP.

3. The VXLAN service in Midonet is enabled by default. However, if the service has been previously disabled, you can enable it by typing the following command and restarting at least one cluster instance in order to become the VXLAN coordinator:

```
$ echo "cluster.vxgw.enabled=true" | mn-conf set -t default
```

4. Having ensured that the VTEP has been properly configured, now you're ready to add the VTEP to the MidoNet configuration.

For information, see [the section called “Adding a VTEP” \[92\]](#).



Important

Apart from the information on the VLAN-port assignment, and VTEP management interface IP and port, you will also need the identifier of a TunnelZone of type *vtep*. All the hosts running MidoNet Agent daemons that you want to create VXLAN tunnels with the VTEP should be members of this tunnel zone, using the local IP that each host uses as a VXLAN tunnel endpoint.

After you successfully add a VTEP to the MidoNet configuration, the API Server connects to its (VTEP's) management interface and collects all the required information for creating a Logical Bridge. For more information, see the "Logical Bridge" section.

Use this procedure to set up a connection between a VTEP and a Neutron network in MidoNet.

For this procedure you will need to know the VTEP's management IP and port, the physical port on the VTEP and the VLAN ID at this port to which you are connecting, the UUID of the Neutron network which you want to connect to the VTEP, and the IP addresses of all the hosts on the Neutron network that you want to communicate with the VTEP.

- All hosts that want to communicate with the VTEP using VXLAN tunnels are required to belong to a tunnel zone of type VTEP, using the IP that each of them will use as VXLAN tunnel endpoint.

```
midonet> tunnel-zone create name vtep_zone type vtep
tzone0
```

2. Add a VTEP to MidoNet and assign it to the `vtep` tunnel zone that you created, using the local IP that this host it meant to use in VXLAN tunnels to the VTEP. Note that this IP may be the same that the host uses to communicate with other MidoNet hosts.

You can determine the state of the VTEP connection by listing the current VTEPs. If your VTEP had been added successfully you should see a similar message, saying `connection-state connected`.

3. Create a binding between the VTEP and a Neutron network behind a MidoNet bridge. For that, you will need the UUID of the Neutron network behind that bridge. To find out the UUID use these commands:

The Neutron network you are binding the VTEP to is behind bridge0, and it has the UUID of 765cf657-3cf4-4d79-9621-7d71af38a298 as you can see in the output of the command.

- a. To find out their addresses, use these commands:

```
midonet> host list
host host0 name rhos5-allinone-jenkins.novalocal alive true
midonet> host host0 list interface
iface veth1 host_id host0 status 3 addresses [u'172.16.0.2',
u'fe80:0:0:0:fc2a:9eff:fef2:aa6c'] mac fe:2a:9e:f2:aa:6c mtu 1500
type Virtual endpoint DATAPATH
...
```

- b. Add the host's IP address to the same tunnel zone as the VTEP:

```
midonet> tunnel-zone tzone0 add member host host0 address 172.16.0.2
```

Repeat these steps for every host in the Neutron network that you want to communicate with the VTEP.



Important

Normally, a host may only be assigned to one tunnel zone, *gre* or *vxlan* type. A host connecting to a VTEP is an exception because you may assign it to two tunnel zones, a *gre/vxlan* one and a *vtep* one. Note that a host can still use the same IP for both tunnel zones.

5. Create a binding between the VTEP's VLAN 10 and the Neutron network behind the bridge0.

In this example you are connecting the hosts on VLAN 10 with the Neutron network 765cf657-3cf4-4d79-9621-7d71af38a298 behind the bridge0:

```
midonet> vtep vtep0 add binding network-id
765cf657-3cf4-4d79-9621-7d71af38a298 physical-port swp1 vlan 10
```

Congratulations, you have just created a binding between the network behind the VTEP's VLAN 10 physical port `swp1` and the Neutron network with the UUID `765cf657-3cf4-4d79-9621-7d71af38a298` in MidoNet.



Tip

To be able to test the connection between the VTEP and MidoNet (i.e. to *ping* MidoNet from a host on the VTEP) you have to modify the default ingress security rule, by adding to it the IP address of the host (pinging the host from MidoNet should work without any additional configuration). For more information, see [the section called “Enabling connection between VTEP and MidoNet hosts” \[85\]](#).

Enabling connection between VTEP and Mi-doNet hosts

By default Neutron includes a security rule on all networks that restricts forwarding only to traffic addressed to IP/MAC of VMs on that network.

By binding a network to physical ports in a VTEP, we're effectively adding hosts to the L2 segment of this Neutron network that Neutron itself does not know about, and thus traffic addressed to these physical hosts will be dropped.

The following procedure describes changes to the default ingress security rule in order to allow traffic to hosts on the VTEP.

- ```
midonet> list chain
chain chain0 name OS_SG_64d9f3df-9875-4896-ad0c-ffc5bba84c5e_INGRESS
chain chain1 name OS_SG_64d9f3df-9875-4896-ad0c-ffc5bba84c5e_EGRESS
...
```

2. List the rules that implement this security rule by issuing this command:

```
midonet> chain chain0 list rule
rule rule0 ethertype 2048 proto 0 tos 0 ip-address-group-src ip-address-
group0 fragment-policy unfragmented pos 1 type accept
rule rule1 ethertype -31011 proto 0 tos 0 ip-address-group-src ip-
address-group0 fragment-policy unfragmented pos 2 type accept
```

3. Now, go ahead and add the IP address of the host on the VTEP to the security group `ip-address-group0`.

```
midonet> ip-address-group ip-address-group0 add ip address 172.16.0.3
address 172.16.0.3
```

You should now be able to ping a host in MidoNet from host 172.16.0.3 on the VTEP (providing they are in the same tunnel zone).

## Troubleshooting VTEP/VXGW configuration

VTEP deployments have a relatively large number of moving pieces and potential failure points. This guide will focus on troubleshooting MidoNet and the integration with the VTEP. For specifics on the configuration of the logical switch please refer to your vendor's documentation.

## Is the MidoNet API able to connect to the VTEP

After following the procedure to add a VTEP as described in [the section called “Adding a VTEP” \[92\]](#), the expected output should be as follows:

```
midonet> vtep add management-ip 192.168.2.10 management-port 6633 tunnel-
zone tzone0
vtep0
midonet> vtep list
vtep vtep0 name VTEP-NAME management-ip 192.168.2.10 management-port 6633
tunnel-zone tzone0 connection-state connected
```

The same output should appear for VTEPs already added to MidoNet.

Note that the state is `connected`. An `error` state will indicate that the VTEP's management IP is unreachable from the MidoNet API.

## Is the VTEP well configured?











### The MidoNet agent is not emitting traffic

Verify the VXLAN-related options in `mn-conf(1)`. Examine the MidoNet Agent logs in debug mode and look for simulations on the Neutron network that might be dropping packets, or throwing errors on the simulation.

### The VTEP is not emitting traffic on the tunnel

Ensure that the VTEP configuration reflects the bindings configured through the MidoNet REST API. Use the following command to list the VTEPs present in the switch:

```
vtep-ctl list-ls
```

This will display all Logical Switches present in the switch. If you bound a Neutron network with UUID c68fa502-62e5-4b33-9f2f-d5d0257deb4f, then you should see the following item in the list:

mn-c68fa502-62e5-4b33-9f2f-d5d0257deb4f

Now list the bindings on the port that you used to create the port-vlan binding in the midonet-cli. Let's assume we have `swp1`, and created a binding with `swp1` and VLAN 93. The expected output would be:

```
vtep-ctl list-bindings <vtep-name> swp1
0093 mn-c68fa502-62e5-4b33-9f2f-d5d0257deb4f
```

You can find out the `<vtep-name>` using the `vtep-ctl list-ps` command.

If any of these outputs is not as expected, the MidoNet coordinator is most likely not being able to consolidate the configuration from the NSDB. Verify the MidoNet API logs and locate the relevant errors in order to correct them.

## Verify that MACs are being synchronized correctly to the VTEP

Finally, you can list the local and remote MACs present in the VTEP's database:

```
vtep-ctl list-local-macs mn-c68fa502-62e5-4b33-9f2f-d5d0257deb4f
```

This should show all the MACs learned by the VTEP from traffic observed on local ports. If the local server is correctly configured, you will typically see the server's MAC here.

The following command will display the remote MACs:

```
vtep-ctl list-remote-macs mn-c68fa502-62e5-4b33-9f2f-d5d0257deb4f
```

The list here will show MACs in MidoNet VMs or other VTEPs, which are injected by the MidoNet coordinator.

If any of these steps don't show an expected output, the synchronization processes may be failing. Inspect the MidoNet API logs for more details.

## CLI commands used for working with the VXGW

This section describes the CLI commands that you can use to work with the VXGW and VTEPs.

## Obtaining a list of VTEPs

Use this command to obtain the list of hardware VTEPs of which MidoNet is aware.









You can delete a single VTEP binding to a Neutron network. If that was the VTEP's last remaining port-VLAN pair bound to the network, then the Neutron network's VXLAN port is also deleted.

### Example

Examples of successfully run commands:

```
midonet> vtep vtep0 delete binding physical-port swp1
```

An example of a unsuccessful command:

```
midonet> vtep vtep0 delete binding
Syntax error at: ...binding
```

## Deleting a VTEP

Use this command to delete a VTEP.

### Syntax

```
vtep <vtep-alias> delete
```

### Result

Issuing this command completely deletes a VTEP from MidoNet's list of known VTEPs.

The command will fail if any of the VTEP's port-VLAN pairs are bound to any Neutron networks. For more information, see [the section called "Removing a VTEP binding" \[95\]](#)

### Example

```
midonet> vtep vtep0 delete
```







```
midonet> host host1 binding add interface eth1 port bridge0:port3
```

## Fail-over/Fail-back

In combination with the Spanning Tree Protocol (STP) enabled on the physical bridges, MidoNet VABs are able to provide fail-over capabilities by forwarding Bridge Protocol Data Unit (BPDU) frames across their trunk ports.

Assuming that both physical switches belong to the same bridged network, as a result of the STP, both devices detect a loop through MidoNet's VAB and one switch chooses to block its trunk. For example, let's assume the left switch blocks. The VAB only sees ingress traffic from the right trunk, and thus associates all source MAC addresses seen in those frames to the right trunk.

A variety of events, including failures in the network, may result in the switches deciding to invert the state of the trunks. An example could be MidoNet losing connection to the left switch, and thus stop forwarding BPDUs to/from the right bridge and undoing the loop.

In such a fail-over scenario, traffic would start flowing from the other switch. With this change, MidoNet now detects ingress traffic on a new port, and thus updates its internal MAC-port associations. If the former state of the topology is restored (that is, MidoNet recovers connectivity to the left switch), MidoNet will again react and update its MAC-port associations.

The fail-over/fail-back times depend on the STP configuration on the switches, mainly the "forward delay," and the nature of the traffic. With standard values, and continuous traffic ingressing from the trunks, fail-over and fail-back cycles should be completed in 50 seconds, plus MAC learning time.

## 16. Working with the MidoNet CLI

### Table of Contents

Using the MidoNet CLI ..... 100

You can explore and edit all of MidoNet's virtual topology through the CLI, however, you should use write operations with caution, as they are likely to create inconsistencies between MidoNet's idea of the virtual network and OpenStack's view of it.



#### Note

When using MidoNet with OpenStack, please be careful not to introduce inconsistencies between OpenStack and MidoNet virtual topologies.

With that warning in mind, there are certain tasks for which the CLI can be particularly useful:

- Creating an Edge Router
- Setting up the cloud's up-link using the Border Gateway Protocol (BGP)
- Upgrading MidoNet
- Registering MidoNet Agents
- Setting up an L2 gateway
- Troubleshooting problems with the MidoNet API. Because the CLI uses the MidoNet API directly, it's the easiest way to make requests to it to verify that it works.
- Viewing and exploring MidoNet's virtual topology and the status and network addresses of all hosts running the MidoNet agent

### Using the MidoNet CLI

To use the MidoNet CLI you need to connect to the MidoNet host running it.

1. Using SSH to connect to the host running the MidoNet CLI.

You must know the IP address of the machine you are connecting to as well as your login credentials, that is your username and password. Example of an SSH command:

```
$ ssh root@192.168.17.5
root@192.168.17.5's password:
```

You have already provided your username, 'root' as part of the command, and now the server is prompting you for a password. Type in your password to get in.

2. The CLI is documented in a set of man pages. To view the man pages, from the system command line, enter:

```
$ man midonet-cli
```

3. To start the midonet-cli, at the system prompt, enter:

```
$ midonet-cli
midonet>
```

The midonet> prompt that gets displayed indicates system readiness to accept MidoNet commands. Type in help and hit Enter to get a list of all available commands. You can also infer proper usage and syntax from context-aware auto-complete and by using the describe command.



AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

- AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

- AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

- AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -

AFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT - DRAFT -





```
import [-h HOST_ID | -t TEMPLATE_NAME`] [-a] -f` CONFIG_FILE
```

Imports values from a legacy configuration file into the centralized configuration repository. The default behavior is to import values that differ from the configuration schema only, but the `-a` option will make `mn-conf` import all values. `import` will automatically handle keys that have changed name, path or type. See above, in `dump`, the options for selecting the configuration source where `mn-conf` will write the imported values.

- `-a, --all`: Import all values, instead of just those that differ from the configuration schema.
- `-f CONFIG_FILE, --file CONFIG_FILE`: Path to the file where `mn-conf` will find the legacy configuration.

## MISCELLANEOUS OPTIONS

- `-h, --help`: Print a brief help message.

## EXAMPLES

Set a configuration key in the default agent template:

```
$ echo "a.config.key : 42" | mn-conf set -t default
```

Dump the runtime configuration (minus local configuration files) of a MidoNet agent:

```
$ mn-conf dump -h a5ff1460-d00c-11e4-8830-0800200c9a66
```

Create a configuration template and assign it to a particular agent:

```
$ echo "a.config.key : 42" | mn-conf set -t "new_template"
$ mn-conf template-set -h a5ff1460-d00c-11e4-8830-0800200c9a66 -t
new_template
```

Importing non-default values from a legacy configuration file:

```
$ mn-conf import -t default -f /etc/midolman/midolman.conf

Importing legacy configuration:
agent {
 midolman {
 "bgp_holdtime"="120s"
 }
}
zookeeper {
 "session_gracetime"="30000ms"
}
```

Notice how `mn-conf` will automatically handle keys that have been moved or renamed.

## FILES

While all configuration is stored in ZooKeeper and both `mn-conf` and MidoNet processes that will make use of it, they all need to bootstrap their connection to ZooKeeper before they can access configuration.

Both `mn-conf` and MidoNet nodes will read bootstrap configuration from these sources, in order of preference:

- Environment variables. See **ENVIRONMENT**, below.
- `~/.midonetr`
- `/etc/midonet/midonet.conf`
- `/etc/midolman/midolman.conf`

These files are expected to be in .ini format, and contain the following keys:

```
[zookeeper]
zookeeper_hosts = 127.0.0.1:2181
root_key = /midonet/v1
```

## ENVIRONMENT

- MIDO\_ZOOKEEPER\_HOSTS: The ZooKeeper connect string.
- MIDO\_ZOOKEEPER\_ROOT\_KEY: Root path in the ZooKeeper server where configuration is stored.

## Recommended configurations

This section contains information on recommended configurations that impact MidoNet performance.

## Overview of Performance-Impacting Configuration Options

**agent.midolman configuration section in mn-conf(1)**

simulation\_threads - Number of threads to dedicate to packet processing

output\_channels - Number of output channels to use for flow creation and packet execution. Each channel gets a dedicated thread.

**input\_channel\_threading** - The MidoNet Agent creates dedicated Netlink channels to receive packets from each datapath port. This option tunes the threading strategy for reading on those channels: `one_to_many` will make the Agent use a single thread for all input channels. `one_to_one` will make the Agent use one thread for each input channel.

### agent.datapath section in mn-conf(1)

**global\_incoming\_burst\_capacity** - Incoming packets are rate-limited by a Hierarchical Token Bucket (HTB) that gets refilled as packets are processed and exit the system. This setting controls the size in packets of the root bucket in the HTB. It is the number of packets that the daemon will accept in a burst (at a higher rate that it can handle) before it starts dropping packets. It's also the maximum number of in-flight packets in the system. Changes to this value affect latency at high-throughput rates.

`tunnel_incoming_burst_capacity` - Tunnel ports get their own bucket in the HTB, allowing them to accumulate burst capacity if they are not sending at the max. rate. This setting controls the size in packets of that bucket.

`vm_incoming_burst_capacity` - Each VM port gets its own bucket in the HTB, allowing the ports to accumulate burst capacity if they are not sending at the max. rate. This setting controls the size in packets of that bucket.





- the MidoNet cluster name

```
cassandra {
 servers = <comma separated IPs>
 replication_factor = 1
 cluster = midonet
}
```

## Datapath configuration

The agent uses a pool of reusable buffers to send requests to the datapath. You may use the options in the `agent.datapath` of `mn-conf(1)` to tune the pool's size and its buffers. One pool is created for each output channel, the settings defined here will apply to each of those pools.

If you notice decreased performance because packet sizes exceed the maximum buffer size, you can increase the value for the `buf_size_kb` setting. This setting controls the buffer size (in KB). Be aware that the buffer size puts a limit on the packet size that the MidoNet Agent can send. In a network that jumbo frames traverse, adjust the size so one buffer will accommodate a whole frame, plus enough room for the flow's actions.

## BGP failover configuration

The default BGP fail-over time is 2-3 minutes. However, you can reduce this time by changing some parameters on both ends of the session: in `mn-conf(1)` (the MidoNet side) and the remote end BGP peer configuration. The example below shows how to reduce the BGP fail-over time to one minute on the MidoNet side:

```
agent {
 midolman {
 bgp_connect_retry=1
 bgp_holdtime=3
 bgp_keepalive=1
 }
}
```

The settings in `mn-conf` must match those on the remote end BGP peer configuration. For more information about how to set them, see [the section called “BGP failover configuration on a BGP peer”](#) [5].

## Advanced MidoNet REST API configuration options

This section describes the configuration options for advanced users. The values for the following keys are modified using the MidoNet configuration tool, `mn-conf`. For more information on the MidoNet configuration, see [the section called “MidoNet Configuration: mn-conf” \[102\]](#).

## Configuration options

### Table 17.2. Admin Roles

| Configuration Key        | Default Value | Description                                                              |
|--------------------------|---------------|--------------------------------------------------------------------------|
| cluster.rest_api.enabled | true          | Specifies whether the REST API service is enabled at the MidoNet cluster |

| Configuration Key                        | Default Value | Description                                           |
|------------------------------------------|---------------|-------------------------------------------------------|
|                                          |               | instance where the configuration applies.             |
| <code>cluster.rest_api.http_port</code>  | 8181          | Specifies the listening port for the HTTP end-point.  |
| <code>cluster.rest_api.https_port</code> | 8443          | Specifies the listening port for the HTTPS end-point. |

## Specifying the private and public keys for HTTPS

To enable the HTTPS end-point of the MidoNet Cluster REST API service, you must configure a JKS key store containing the private and public key X.509 certificate used for encrypting such connections.

The location of the key store file and the password for the private key are specified as the following Java system properties.

**Table 17.3. System Properties for the HTTPS Key Store**

| Property Name                          | Default Value                                     | Description                                                                                                         |
|----------------------------------------|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------|
| <code>midonet.keystore_path</code>     | <code>/etc/midonet-cluster/ssl/midonet.jks</code> | The name of the key store file.                                                                                     |
| <code>midonet.keystore_password</code> | <i>none</i>                                       | The password for the private key entry. If not set, the HTTPS end-point of the REST API will be disabled (default). |

To change the previous properties, and enable HTTPS, you can add the corresponding property values to the environmental MidoNet Cluster script file found at `/etc/midonet-cluster/midonet-cluster-env.sh`:

```
JVM_OPTS="$JVM_OPTS -Dmidonet.keystore_path=<key-store-file>"
JVM_OPTS="$JVM_OPTS -Dmidonet.keystore_password=<key-entry-password>"
```

## Generating self-signed keys

To generate a self-signed key, you can use the following procedure. Note that you will be prompted for passwords during this process, and need to keep the keystore password for later use.

```
openssl genrsa -des3 -out midonet.key 2048
openssl rsa -in midonet.key -out midonet.key
openssl req -sha256 -new -key midonet.key -out midonet.csr -subj '/CN=localhost'
openssl x509 -req -days 365 -in midonet.csr -signkey midonet.key -out midonet.crt
```

Now we will combine the private key into the cert, because we generated them separately:

```
openssl pkcs12 -inkey midonet.key -in midonet.crt -export -out midonet.pkcs12
```

And load the certificate into the keystore:

```
keytool -importkeystore -srckeystore midonet.pkcs12 -srcstoretype PKCS12 -destkeystore midonet.jks
```

Now place the keystore in the default location:

```
mv midonet.jks /etc/midonet-cluster/ssl
```

For more advanced key management, including adding your own certificate to the key-store, please refer to the following documentation:

<https://www.eclipse.org/jetty/documentation/current/configuring-ssl.html>

# Cassandra cache

This section describes details relative to the Cassandra-based implementation of the Cassandra cache used for connection tracking and NAT mappings.

## Client library and normal operation

Cassandra operations are now asynchronous, so losing connectivity to Cassandra should not impact simulations.

The loss of connectivity to a majority of nodes creates a risk that connections will break on vport migration or MidoNet restart. But this is a low risk if the operator can avoid vport migrations and MidoNet Agent restarts until Cassandra is returned to normal operation.

To summarize, MidoNet can function with Cassandra down (but vport migrations and agent restarts may break connections) so it should only be tolerated for very brief periods.

## Agent behavior on node failure

The MidoNet Agent writes to Cassandra asynchronously after processing a packet that produced stateful connection data, such as NAT mappings or connection tracking keys.

The data written to Cassandra is purely a back up, as MidoNet agents share all stateful connection data directly amongst themselves. The back up is used upon agent reboot (to prevent lost connections across the reboot) and upon port migration. An agent binding a port will fetch the existing connection state from Cassandra for all connections traversing that port.

Should a Cassandra node fail, agents connected to it will fail over to other nodes in the Cassandra cluster. If the host tries to bind a port during that interval it may fail to fetch the state for the port, breaking pre-existing connections on that port. Additionally, state for flows processed during that interval may not be written to Cassandra, making it unavailable if it's needed later in the process of binding a port. State is refreshed every minute, thus a port migration would only break connections that were established in the minute prior to the port migration and only if the disconnection happened in that interval.

## Network State Database connectivity

In order to modify the MidoNet Network State Database, you must configure the following parameters in your `web.xml` file:

- zookeeper-zookeeper\_hosts
- zookeeper-session\_timeout
- cassandra-servers

Below are example web.xml snippets.



## Note

The rest of the configuration is cloud-controller dependent and is covered in the relevant sections of the documentation.

## zookeeper-zookeeper\_hosts

Lists the ZooKeeper hosts used to store the MidoNet configuration data. The entries are comma delimited:

```
<context-param>
 <param-name>zookeeper-zookeeper_hosts</param-name>
 <param-value>192.168.1.100:2181,192.168.1.101:2181,192.168.1.102:2181</param-value>
</context-param>
```

## zookeeper-session\_timeout

Sets the timeout value (in milliseconds) after which ZooKeeper considers clients to be disconnected from the ZooKeeper server:

```
<context-param>
 <param-name>zookeeper-session_timeout</param-name>
 <param-value>30000</param-value>
</context-param>
```



## 18. MidoNet and OpenStack TCP/UDP service ports

### Table of Contents

Services on the Controller node .....	114
Services on the Network State Database nodes .....	115
Services on the Compute nodes .....	116
Services on the Gateway Nodes .....	116

This section lists the TCP/UDP ports used by services in MidoNet and OpenStack.

### Services on the Controller node

This section lists the TCP/UDP ports used by the services on the Controller node.

Category	Service	Prot ocol	Port	Self	Controller	Compute	Mgmt. PC
OpenStack	glance-api	TCP	9292	x	x	x	x
OpenStack	httpd (Hori- zon)	TCP	80	x			x
MidoNet	midonet-api	TCP	8080	x	x		x
OpenStack	swift-ob- ject-server	TCP	6000	x	x	x	
OpenStack	swift-contain- er-server	TCP	6001	x	x	x	
OpenStack	swift-ac- count-server	TCP	6002	x	x	x	
OpenStack	keystone	TCP	35357	x	x	x	x
OpenStack	neutron-serv- er	TCP	9696	x	x	x	x
OpenStack	nova-novnc- proxy	TCP	6080	x	x		x
OpenStack	heat-api	TCP	8004	x	x		x
OpenStack	nova-api	TCP	8773	x	x		x
Tomcat	Tomcat shut- down control channel	TCP	8005	x	x		
OpenStack	nova-api	TCP	8774	x	x	x	x
OpenStack	nova-api	TCP	8775	x	x	x	x
OpenStack	glance-reg- istry	TCP	9191	x	x	x	
OpenStack	qpidd	TCP	5672	x	x	x	
OpenStack	keystone	TCP	5000	x	x	x	x
OpenStack	cinder-api	TCP	8776	x	x	x	x
Tomcat	Tomcat man- agement port (not used)	TCP	8009	x	x		
OpenStack	ceilome- ter-api	TCP	8777	x	x	x	x

Category	Service	Prot ocol	Port	Self	Controller	Compute	Mgmt. PC
OpenStack	mongod (ceilometer)	TCP	27017	x	x	x	
OpenStack	MySQL	TCP	3306	x	x	x	

## Services on the Network State Database nodes

This section lists the TCP/UDP ports used by the services on the Network State Database nodes.

Category	Service	Prot ocol	Port	Self	Controller	NSDB	Compute	Comment
MidoNet	ZooKeeper communication	TCP	3888	x		x		
MidoNet	ZooKeeper leader	TCP	2888	x		x		
MidoNet	ZooKeeper/Cassandra	TCP	random	x				ZooKeeper/Cassandra "LISTEN" to a TCP high number port. The port number is randomly selected on each ZooKeeper/Cassandra host.
MidoNet	Cassandra Query Language (CQL) native transport port	TCP	9042					
MidoNet	Cassandra cluster communication	TCP	7000	x		x		
MidoNet	Cassandra cluster communication (Transport Layer Security (TLS) support)	TCP	7001	x		x		
MidoNet	Cassandra JMX	TCP	7199	x				JMX monitoring port. If you're using this port to monitor Cassandra health, enable communication from the monitoring server.
MidoNet	ZooKeeper client	TCP	2181	x	x	x	x	
MidoNet	Cassandra clients	TCP	9160	x	x	x	x	

## Services on the Compute nodes

This section lists the TCP/UDP ports used by the services on the Compute nodes.

Category	Service	Protocol	Port	Self	Controller	Comment
OpenStack	qemu-kvm vnc	TCP	From 5900 to 5900 + # of VM		x	
MidoNet	midolman	TCP	random	x		midolman "LISTEN"s to a TCP high number port. The port number is randomly selected on each MN Agent host.
OpenStack	libvirtd	TCP	16509	x	x	
MidoNet	midolman	TCP	7200	x		JMX monitoring port If you're using this port to monitor health, enable communication from the monitoring server.
MidoNet	midolman	TCP	9697	x		If enabled, MidoNet Metadata Proxy listens on 169.254.169.254:9697 to accept metadata requests.

## Services on the Gateway Nodes

This section lists the TCP/UDP ports used by the services on the Gateway Nodes.

Category	Service	Protocol	Port	Self	Misc.	Comment
MidoNet	midolman	TCP	random	x		midolman LISTEN"s to a TCP high number port. The port number is randomly selected on each MN Agent host.
MidoNet	midolman	TCP	7200	x	x	JMX monitoring port If you're using this port to monitor health, enable communication from the monitoring server.
MidoNet	quagga bgpd control	TCP	2606	x		Network-NameSpace mbgp[Peer Number]_ns
MidoNet	quagga bgpd bgp	TCP	179		BGP neighbor	Network-NameSpace mbgp[Peer Number]_ns