

DBMS_DEBUG

`DBMS_DEBUG` is deprecated. Use `DBMS_DEBUG_JDWP` instead.

See [DBMS_DEBUG_JDWP](#) for more information.

`DBMS_DEBUG` is a PL/SQL interface to the PL/SQL debugger layer, Probe, in the Oracle server.

This package is primarily intended to implement server-side debuggers and it provides a way to debug server-side PL/SQL program units.

**Note:**

The term *program unit* refers to a PL/SQL program of any type (procedure, function, package, package body, trigger, anonymous block, object type, or object type body).

This chapter contains the following topics:

- [Overview](#)
- [Constants](#)
- [Variables](#)
- [Exceptions](#)
- [Operational Notes](#)
- [Data Structures](#)
- [Summary of DBMS_DEBUG Subprograms](#)

DBMS_DEBUG Overview

To debug server-side code, you must have two database sessions: one session to run the code in debug mode (the target session), and a second session to supervise the target session (the debug session).

The target session becomes available for debugging by making initializing calls with `DBMS_DEBUG`. This marks the session so that the PL/SQL interpreter runs in debug mode and generates debug events. As debug events are generated, they are posted from the session. In most cases, debug events require return notification: the interpreter pauses awaiting a reply.

Meanwhile, the debug session must also initialize itself using `DBMS_DEBUG`. This tells it which target session to supervise. The debug session may then call entry points in `DBMS_DEBUG` to read events that were posted from the target session and to communicate with the target session.

The following subprograms are run in the target session (the session that is to be debugged):

- [SYNCHRONIZE Function](#)
- [DEBUG_ON Procedure](#)

- [DEBUG_OFF Procedure](#)

DBMS_DEBUG does not provide an interface to the PL/SQL compiler, but it does depend on debug information optionally generated by the compiler. Without debug information, it is not possible to examine or modify the values of parameters or variables.

DBMS_DEBUG Constants

A breakpoint status may have the following value: `breakpoint_status_unused`—breakpoint is not in use.

Otherwise, the status is a mask of the following values:

- `breakpoint_status_active`—a line breakpoint
- `breakpoint_status_disabled`—breakpoint is currently disabled
- `breakpoint_status_remote`—a shadow breakpoint (a local representation of a remote breakpoint)

DBMS_DEBUG Variables

The DBMS_DEBUG uses the variables shown in the following table.

Table 72-1 DBMS_DEBUG Variables

Variable	Description
<code>default_timeout</code>	The timeout value (used by both sessions). The smallest possible timeout is 1 second. If this value is set to 0, then a large value (3600) is used.

DBMS_DEBUG Exceptions

These values are returned by the various functions called in the debug session (`SYNCHRONIZE`, `CONTINUE`, `SET_BREAKPOINT`, and so on). If PL/SQL exceptions worked across client/server and server/server boundaries, then these would all be exceptions rather than error codes.

Table 72-2 DBMS_DEBUG Exceptions

Status	Description
<code>success</code>	Normal termination

Statuses returned by `GET_VALUE` and `SET_VALUE`:

Table 72-3 DBMS_DEBUG Exceptions Returned by GET_VALUE and SET_VALUE

Status	Description
<code>error_bogus_frame</code>	No such entrypoint on the stack
<code>error_no_debug_info</code>	Program was compiled without debug symbols
<code>error_no_such_object</code>	No such variable or parameter
<code>error_unknown_type</code>	Debug information is unreadable

Table 72-3 (Cont.) DBMS_DEBUG Exceptions Returned by GET_VALUE and SET_VALUE

Status	Description
error_indexed_table	Returned by GET_VALUE if the object is a table, but no index was provided
error_illegal_index	No such element exists in the collection
error_nullcollection	Table is atomically NULL
error_nullvalue	Value is NULL

Statuses returned by SET_VALUE:

Table 72-4 DBMS_DEBUG Exceptions Returned by SET_VALUE

Status	Description
error_illegal_value	Constraint violation
error_illegal_null	Constraint violation
error_value_malformed	Unable to decipher the given value
error_other	Some other error
error_name_incomplete	Name did not resolve to a scalar

Statuses returned by the breakpoint functions:

Table 72-5 Statuses Returned by the Breakpoint Functions

Status	Description
error_no_such_breakpt	No such breakpoint
error_idle_breakpt	Cannot enable or disable an unused breakpoint
error_bad_handle	Unable to set breakpoint in given program (nonexistent or security violation)

General error codes (returned by many of the DBMS_DEBUG subprograms):

Table 72-6 DBMS_DEBUG Subprograms Error Codes

Status	Description
error_unimplemented	Functionality is not yet implemented
error_deferred	No program running; operation deferred
error_exception	An exception was raised in the DBMS_DEBUG or Probe packages on the server
error_communication	Some error other than a timeout occurred
error_timeout	Timeout occurred

Table 72-7 illegal_init Exceptions

Exception	Description
illegal_init	DEBUG_ON was called prior to INITIALIZE

The following exceptions are raised by procedure SELF_CHECK:

Table 72-8 SELF_CHECK Procedure Exceptions

Exception	Description
pipe_creation_failure	Could not create a pipe
pipe_send_failure	Could not write data to the pipe
pipe_receive_failure	Could not read data from the pipe
pipe_datatype_mismatch	Datatype in the pipe was wrong
pipe_data_error	Data got garbled in the pipe

DBMS_DEBUG Operational Notes

There are two ways to ensure that debug information is generated: through a session switch, or through individual recompilation.

To set the session switch, enter the following statement:

```
ALTER SESSION SET PLSQL_DEBUG = true;
```

This instructs the compiler to generate debug information for the remainder of the session. It does not recompile any existing PL/SQL.

To generate debug information for existing PL/SQL code, use one of the following statements (the second recompiles a package or type body):

```
ALTER [PROCEDURE | FUNCTION | PACKAGE | TRIGGER | TYPE] <name> COMPILE DEBUG;  
ALTER [PACKAGE | TYPE] <name> COMPILE DEBUG BODY;
```

[Figure 72-1](#) and [Figure 72-2](#) illustrate the flow of operations in the session to be debugged and in the debugging session.

Figure 72-1 Target Session




illustration: arpls001
release: 9
caption: Target Session
date: 1/29/01
platform: pc

Figure 72-2 Debug Session




illustration: arpls003
release: 9
caption: Target Session
 see arpls004
date: 1/30/01
platform: pc

Figure 72-3 Debug Session (Cont.)




illustration: arpls004
release: 9
caption: Target Session
 see arpls003
date: 1/30/01
platform: pc

Control of the Interpreter

The interpreter pauses execution at the following times:

1. At startup of the interpreter so any deferred breakpoints may be installed prior to execution.
2. At any line containing an enabled breakpoint.
3. At any line where an *interesting* event occurs. The set of interesting events is specified by the flags passed to `DBMS_DEBUG.CONTINUE` in the `breakflags` parameter.

Session Termination

There is no event for session termination. Therefore, it is the responsibility of the debug session to check and make sure that the target session has not ended. A call to `DBMS_DEBUG.SYNCHRONIZE` after the target session has ended causes the debug session to hang until it times out.

Deferred Operations

The diagram suggests that it is possible to set breakpoints prior to having a target session. This is true. In this case, Probe caches the breakpoint request and transmits it to the target session at first synchronization. However, if a breakpoint request is deferred in this fashion, then:

- `SET_BREAKPOINT` does not set the breakpoint number (it can be obtained later from `SHOW_BREAKPOINTS` if necessary).
- `SET_BREAKPOINT` does not validate the breakpoint request. If the requested source line does not exist, then an error silently occurs at synchronization, and no breakpoint is set.

Diagnostic Output

To debug Probe, there are *diagnostics* parameters to some of the calls in `DBMS_DEBUG`. These parameters specify whether to place diagnostic output in the RDBMS tracefile. If output to the RDBMS tracefile is disabled, these parameters have no effect.

Common Debug Session Sections

- Common Section
- Target Session
- Debug Session Section

Common Section

The following subprograms may be called in either the target or the debug session:

- [PROBE_VERSION Procedure](#)
- [SELF_CHECK Procedure](#)
- [SET_TIMEOUT Function](#)

Target Session

The following subprograms may be called only in the target session:

- [INITIALIZE Function](#)
- [DEBUG_ON Procedure](#)
- [SET_TIMEOUT_BEHAVIOUR Procedure](#)
- [GET_TIMEOUT_BEHAVIOUR Function](#)

Debug Session Section

The following subprograms should be run in the debug session only:

- [ATTACH_SESSION Procedure](#)
- [SYNCHRONIZE Function](#)
- [SHOW_FRAME_SOURCE Procedure](#)

- [SHOW_SOURCE Procedures](#)
- [GET_MORE_SOURCE Procedure](#)
- [PRINT_BACKTRACE Procedure](#)
- [CONTINUE Function](#)
- [SET_BREAKPOINT Function](#)
- [DELETE_BREAKPOINT Function](#)
- [SET_OER_BREAKPOINT Function](#)
- [DELETE_OER_BREAKPOINT Function](#)
- [ENABLE_BREAKPOINT Function](#)
- [DISABLE_BREAKPOINT Function](#)
- [SHOW_BREAKPOINTS Procedures](#)
- [SET_VALUE Function](#)
- [GET_VALUE Function](#)
- [TARGET_PROGRAM_RUNNING Procedure](#)
- [DETACH_SESSION Procedure](#)
- [GET_RUNTIME_INFO Function](#)
- [PRINT_INSTANTIATIONS Procedure](#)
- [PING Procedure](#)
- [GET_LINE_MAP Function](#)
- [GET_RUNTIME_INFO Function](#)
- [GET_INDEXES Function](#)
- [EXECUTE Procedure](#)

OER Breakpoints

Exceptions that are declared in PL/SQL programs are known as user-defined exceptions. In addition, there are Oracle Errors (OERs) that are returned from the Oracle kernel. To tie the two mechanisms together, PL/SQL provides the `exception_init` pragma that turns a user-defined exception into an OER, so that a PL/SQL handler may be used for it, and so that the PL/SQL engine can return OERs to the Oracle kernel. As of the current release, the only information available about an OER is its number. If two user-defined exceptions are `exception_init`'d to the same OER, they are indistinguishable.

Namespaces

Program units on the server reside in different namespaces. When setting a breakpoint, specify the desired namespace.

1. `Namespace_cursor` contains cursors (anonymous blocks).
2. `Namespace_pgkspec_or_toplevel` contains:
 - Package specifications.
 - Procedures and functions that are not nested inside other packages, procedures, or functions.
 - Object types.

3. `Namespace_pkg_body` contains package bodies and type bodies.
4. `Namespace_trigger` contains triggers.

Libunit Types

These values are used to disambiguate among objects in a given namespace. These constants are used in `PROGRAM_INFO` when Probe is giving a stack backtrace.

- `LibunitType_cursor`
- `LibunitType_procedure`
- `LibunitType_function`
- `LibunitType_package`
- `LibunitType_package_body`
- `LibunitType_trigger`
- `LibunitType_Unknown`

Breakflags

These are values to use for the `breakflags` parameter to `CONTINUE`, in order to tell Probe what events are of interest to the client. These flags may be combined.

Value	Description
<code>break_next_line</code>	Break at next source line (step over calls)
<code>break_any_call</code>	Break at next source line (step into calls)
<code>break_any_return</code>	Break after returning from current entrypoint (skip over any entrypoints called from the current routine)
<code>break_return</code>	Break the next time an entrypoint gets ready to return. (This includes entrypoints called from the current one. If interpreter is running <code>Proc1</code> , which calls <code>Proc2</code> , then <code>break_return</code> stops at the end of <code>Proc2</code> .)
<code>break_exception</code>	Break when an exception is raised
<code>break_handler</code>	Break when an exception handler is executed
<code>abort_execution</code>	Stop execution and force an 'exit' event as soon as <code>DBMS_DEBUG.CONTINUE</code> is called.

Information Flags

These are flags which may be passed as the `info_requested` parameter to `SYNCHRONIZE`, `CONTINUE`, and `GET_RUNTIME_INFO`.

Flag	Description
<code>info_getStackDepth</code>	Get the current depth of the stack
<code>info_getBreakpoint</code>	Get the breakpoint number
<code>info_getLineinfo</code>	Get program unit information

Reasons for Suspension

After `CONTINUE` is run, the program either runs to completion or breaks on some line.

Reason	Description
reason_none	-
reason_interpreter_starting	Interpreter is starting
reason_breakpoint	Hit a breakpoint
reason_enter	Procedure entry
reason_return	Procedure is about to return
reason_finish	Procedure is finished
reason_line	Reached a new line
reason_interrupt	An interrupt occurred
reason_exception	An exception was raised
reason_exit	Interpreter is exiting (old form)
reason_knl_exit	Kernel is exiting
reason_handler	Start exception-handler
reason_timeout	A timeout occurred
reason_instantiate	Instantiation block
reason_abort	Interpreter is aborting

DBMS_DEBUG Data Structures

The `DBMS_DEBUG` package defines `RECORD` types and `TABLE` types.

RECORD Types

- [BREAKPOINT_INFO Record Type](#)
- [PROGRAM_INFO Record Type](#)
- [RUNTIME_INFO Record Type](#)

TABLE Types

- [BACKTRACE_TABLE Table Type](#)
- [BREAKPOINT_TABLE Table Type](#)
- [INDEX_TABLE Table Type](#)
- [VC2_TABLE Table Type](#)

BREAKPOINT_INFO Record Type

This type gives information about a breakpoint, such as its current status and the program unit in which it was placed.

Syntax

```
TYPE breakpoint_info IS RECORD (  
    name          VARCHAR2(30),  
    owner         VARCHAR2(30),  
    dblink        VARCHAR2(30),
```

```

line#          BINARY_INTEGER,
libunitttype   BINARY_INTEGER,
status        BINARY_INTEGER);

```

Fields

Table 72-9 BREAKPOINT_INFO Fields

Field	Description
name	Name of the program unit
owner	Owner of the program unit
dblink	Database link, if remote
line#	Line number
libunitttype	NULL, unless this is a nested procedure or function
status	See Constants for values of breakpoint_status_*

PROGRAM_INFO Record Type

The `PROGRAM_INFO` record type of the `DBMS_DEBUG` package specifies a program location. It is a line number in a program unit.

This is used for stack backtraces and for setting and examining breakpoints. The read-only fields are currently ignored by Probe for breakpoint operations. They are set by Probe only for stack backtraces.

Syntax

```

TYPE program_info IS RECORD(
    -- The following fields are used when setting a breakpoint
    namespace   BINARY_INTEGER,
    name         VARCHAR2(30),
    owner       VARCHAR2(30),
    dblink      VARCHAR2(30),
    line#       BINARY_INTEGER,
    -- Read-only fields (set by Probe when doing a stack backtrace)
    libunitttype BINARY_INTEGER,
    entrypointname VARCHAR2(30));

```

Fields

Table 72-10 PROGRAM_INFO Fields

Field	Description
namespace	See DBMS_DEBUG Operational Notes for more information about namespaces.
name	Name of the program unit
owner	Owner of the program unit
dblink	Database link, if remote
line#	Line number
libunitttype	A read-only field, NULL, unless this is a nested procedure or function

Table 72-10 (Cont.) PROGRAM_INFO Fields

Field	Description
entrypointname	A read-only field, to disambiguate among objects that share the same namespace (for example, procedure and package specifications). See DBMS_DEBUG Operational Notes for more information about the libunit types.

RUNTIME_INFO Record Type

This type gives context information about the running program.

Syntax

```
TYPE runtime_info IS RECORD(  
    line#           BINARY_INTEGER,  
    terminated      binary_integer,  
    breakpoint      binary_integer,  
    stackdepth      BINARY_INTEGER,  
    interpreterdepth BINARY_INTEGER,  
    reason          BINARY_INTEGER,  
    program         program_info);
```

Fields

Table 72-11 RUNTIME_INFO Fields

Field	Description
line#	Duplicate of program.line#
terminated	Whether the program has terminated
breakpoint	Breakpoint number
stackdepth	Number of frames on the stack
interpreterdepth	[A reserved field]
reason	Reason for suspension
program	Source location

BACKTRACE_TABLE Table Type

This type is used by PRINT_BACKTRACE.

Syntax

```
TYPE backtrace_table IS TABLE OF program_info INDEX BY BINARY_INTEGER;
```

BREAKPOINT_TABLE Table Type

This type is used by SHOW_BREAKPOINTS.

Syntax

```
TYPE breakpoint_table IS TABLE OF breakpoint_info INDEX BY BINARY_INTEGER;
```

INDEX_TABLE Table Type

This type is used by `GET_INDEXES` to return the available indexes for an indexed table.

Syntax

```
TYPE index_table IS table of BINARY_INTEGER INDEX BY BINARY_INTEGER;
```

VC2_TABLE Table Type

This type is used by `SHOW_SOURCE`.

Syntax

```
TYPE vc2_table IS TABLE OF VARCHAR2(90) INDEX BY BINARY_INTEGER;
```

Summary of DBMS_DEBUG Subprograms

This table lists the `DBMS_DEBUG` subprograms in alphabetical order and briefly describes them.

Table 72-12 DBMS_DEBUG Package Subprograms

Subprogram	Description
ATTACH_SESSION Procedure	Notifies the debug session about the target debugID
CONTINUE Function	Continues execution of the target program
DEBUG_OFF Procedure	Turns debug-mode off
DEBUG_ON Procedure	Turns debug-mode on
DELETE_BREAKPOINT Function	Deletes a breakpoint
DELETE_OER_BREAKPOINT Function	Deletes an OER breakpoint
DETACH_SESSION Procedure	Stops debugging the target program
DISABLE_BREAKPOINT Function	Disables a breakpoint
ENABLE_BREAKPOINT Function	Activates an existing breakpoint
EXECUTE Procedure	Executes SQL or PL/SQL in the target session
GET_INDEXES Function	Returns the set of indexes for an indexed table
GET_MORE_SOURCE Procedure	Provides additional source in the event of buffer overflow when using <code>SHOW_SOURCE</code>
GET_LINE_MAP Function	Returns information about line numbers in a program unit
GET_RUNTIME_INFO Function	Returns information about the current program
GET_TIMEOUT_BEHAVIOUR Function	Returns the current timeout behavior
GET_VALUE Function	Gets a value from the currently-running program
INITIALIZE Function	Sets debugID in target session
PING Procedure	Pings the target session to prevent it from timing out

Table 72-12 (Cont.) DBMS_DEBUG Package Subprograms

Subprogram	Description
PRINT_BACKTRACE Procedure	Prints a stack backtrace
PRINT_INSTANTIATIONS Procedure	Prints a stack backtrace
PROBE_VERSION Procedure	Returns the version number of DBMS_DEBUG on the server
SELF_CHECK Procedure	Performs an internal consistency check
SET_BREAKPOINT Function	Sets a breakpoint in a program unit
SET_OER_BREAKPOINT Function	Sets an OER breakpoint
SET_TIMEOUT Function	Sets the timeout value
SET_TIMEOUT_BEHAVIOUR Procedure	Tells Probe what to do with the target session when a timeout occurs
SET_VALUE Function	Sets a value in the currently-running program
SHOW_BREAKPOINTS Procedures	Returns a listing of the current breakpoints
SHOW_FRAME_SOURCE Procedure	Fetches the frame source
SHOW_SOURCE Procedures	Fetches program source
SYNCHRONIZE Function	Waits for program to start running
TARGET_PROGRAM_RUNNING Procedure	Returns TRUE if the target session is currently executing a stored procedure, or FALSE if it is not

ATTACH_SESSION Procedure

This procedure notifies the debug session about the target program.

Syntax

```
DBMS_DEBUG.ATTACH_SESSION (  
    debug_session_id IN VARCHAR2,  
    diagnostics       IN BINARY_INTEGER := 0);
```

Parameters

Table 72-13 ATTACH_SESSION Procedure Parameters

Parameter	Description
debug_session_id	Debug ID from a call to INITIALIZE in target session
diagnostics	Generate diagnostic output if nonzero

CONTINUE Function

This function passes the given breakflags (a mask of the events that are of interest) to Probe in the target process. It tells Probe to continue execution of the target process, and it waits until the target process runs to completion or signals an event.

If `info_requested` is not `NULL`, then calls `GET_RUNTIME_INFO`.

Syntax

```
DBMS_DEBUG.CONTINUE (
    run_info      IN OUT runtime_info,
    breakflags    IN      BINARY_INTEGER,
    info_requested IN      BINARY_INTEGER := NULL)
RETURN BINARY_INTEGER;
```

Parameters

Table 72-14 CONTINUE Function Parameters

Parameter	Description
<code>run_info</code>	Information about the state of the program
<code>breakflags</code>	Mask of events that are of interest (see the discussion about break flags under DBMS_DEBUG Operational Notes)
<code>info_requested</code>	Which information should be returned in <code>run_info</code> when the program stops (see the discussion of information flags under DBMS_DEBUG Operational Notes)

Return Values

Table 72-15 CONTINUE Function Return Values

Return	Description
<code>success</code>	
<code>error_timeout</code>	Timed out before the program started running
<code>error_communication</code>	Other communication error

DEBUG_OFF Procedure

This procedure notifies the target session that debugging should no longer take place in that session. It is not necessary to call this function before ending the session.



WARNING:

There must be a debug session waiting if `immediate` is `TRUE`.

Syntax

```
DBMS_DEBUG.DEBUG_OFF;
```


Usage Notes

The server does not handle this entrypoint specially. Therefore, it attempts to debug this entrypoint.

DEBUG_ON Procedure

This procedure marks the target session so that all PL/SQL is run in debug mode. This must be done before any debugging can take place.

Syntax

```
DBMS_DEBUG.DEBUG_ON (
    no_client_side_plsql_engine BOOLEAN := TRUE,
    immediate                   BOOLEAN := FALSE);
```

Parameters

Table 72-16 DEBUG_ON Procedure Parameters

Parameter	Description
no_client_side_plsql_engine	Should be left to its default value unless the debugging session is taking place from a client-side PL/SQL engine
immediate	If this is TRUE, then the interpreter immediately switches itself into debug-mode, instead of continuing in regular mode for the duration of the call.

DELETE_BREAKPOINT Function

This function deletes a breakpoint.

Syntax

```
DBMS_DEBUG.DELETE_BREAKPOINT (
    breakpoint IN BINARY_INTEGER)
RETURN BINARY_INTEGER;
```

Parameters

Table 72-17 DELETE_BREAKPOINT Function Parameters

Parameter	Description
breakpoint	Breakpoint number from a previous call to SET_BREAKPOINT

Return Values

Table 72-18 DELETE_BREAKPOINT Function Return Values

Return	Description
success	

Table 72-18 (Cont.) DELETE_BREAKPOINT Function Return Values

Return	Description
error_no_such_break pt	No such breakpoint exists
error_idle_breakpt	Cannot delete an unused breakpoint
error_stale_breakpt	The program unit was redefined since the breakpoint was set

DELETE_OER_BREAKPOINT Function

This function deletes an OER breakpoint.

Syntax

```
DBMS_DEBUG.DELETE_OER_BREAKPOINT (  
    oer IN PLS_INTEGER)  
RETURN PLS_INTEGER;
```

Parameters

Table 72-19 DELETE_OER_BREAKPOINT Function Parameters

Parameter	Description
oer	The OER (positive 4-byte number) to delete

DETACH_SESSION Procedure

This procedure stops debugging the target program.

This procedure may be called at any time, but it does not notify the target session that the debug session is detaching itself, and it does not terminate execution of the target session. Therefore, care should be taken to ensure that the target session does not hang itself.

Syntax

```
DBMS_DEBUG.DETACH_SESSION;
```

DISABLE_BREAKPOINT Function

This function makes an existing breakpoint inactive but leaves it in place.

Syntax

```
DBMS_DEBUG.DISABLE_BREAKPOINT (  
    breakpoint IN BINARY_INTEGER)  
RETURN BINARY_INTEGER;
```

Parameters

Table 72-20 DISABLE_BREAKPOINT Function Parameters

Parameter	Description
breakpoint	Breakpoint number from a previous call to SET_BREAKPOINT

Return Values

Table 72-21 DISABLE_BREAKPOINT Function Return Values

Returns	Description
success	
error_no_such_breakpt	No such breakpoint exists
error_idle_breakpt	Cannot disable an unused breakpoint

ENABLE_BREAKPOINT Function

This function is the reverse of disabling. This enables a previously disabled breakpoint.

Syntax

```
DBMS_DEBUG.ENABLE_BREAKPOINT (  
    breakpoint IN BINARY_INTEGER)  
RETURN BINARY_INTEGER;
```

Parameters

Table 72-22 ENABLE_BREAKPOINT Function Parameters

Parameter	Description
breakpoint	Breakpoint number from a previous call to SET_BREAKPOINT

Return Values

Table 72-23 ENABLE_BREAKPOINT Function Return Values

Return	Description
success	Success
error_no_such_breakpt	No such breakpoint exists
error_idle_breakpt	Cannot enable an unused breakpoint

EXECUTE Procedure

This procedure executes SQL or PL/SQL code in the target session. The target session is assumed to be waiting at a breakpoint (or other event). The call to `DBMS_DEBUG.EXECUTE` occurs in the debug session, which then asks the target session to execute the code.

Syntax

```
DBMS_DEBUG.EXECUTE (
  what          IN VARCHAR2,
  frame#        IN BINARY_INTEGER,
  bind_results  IN BINARY_INTEGER,
  results       IN OUT NOCOPY dbms_debug_vc2coll,
  errm          IN OUT NOCOPY VARCHAR2);
```

Parameters

Table 72-24 EXECUTE Procedure Parameters

Parameter	Description
what	SQL or PL/SQL source to execute
frame#	The context in which to execute the code. Only -1 (global context) is supported at this time.
bind_results	Whether the source wants to bind to results in order to return values from the target session: 0 = No 1 = Yes
results	Collection in which to place results, if bind_results is not 0
errm	Error message, if an error occurred; otherwise, NULL

Examples

Example 1

This example executes a SQL statement. It returns no results.

```
DECLARE
  coll sys.dbms_debug_vc2coll; -- results (unused)
  errm VARCHAR2(100);
BEGIN
  dbms_debug.execute('insert into emp(ename,empno,deptno) ' ||
                    'values(''LJE'', 1, 1)',
                    -1, 0, coll, errm);
END;
```

Example 2

This example executes a PL/SQL block, and it returns no results. The block is an autonomous transaction, which means that the value inserted into the table becomes visible in the debug session.

```
DECLARE
  coll sys.dbms_debug_vc2coll;
  errm VARCHAR2(100);
BEGIN
  dbms_debug.execute(
```

```

        'DECLARE PRAGMA autonomous_transaction; ' ||
        'BEGIN ' ||
        '    insert into emp(ename, empno, deptno) ' ||
        '    values(''LJE'', 1, 1); ' ||
        ' COMMIT; ' ||
        'END;',
        -1, 0, coll, errm);
END;

```

Example 3

This example executes a PL/SQL block, and it returns some results.

```

DECLARE
    coll sys.dbms_debug_vc2coll;
    errm VARCHAR2(100);
BEGIN
    dbms_debug.execute(
        'DECLARE ' ||
        '    pp SYS.dbms_debug_vc2coll := SYS.dbms_debug_vc2coll(); ' ||
        '    x PLS_INTEGER; ' ||
        '    i PLS_INTEGER := 1; ' ||
        'BEGIN ' ||
        '    SELECT COUNT(*) INTO x FROM emp; ' ||
        '    pp.EXTEND(x * 6); ' ||
        '    FOR c IN (SELECT * FROM emp) LOOP ' ||
        '        pp(i) := ''Ename: '' || c.ename; i := i+1; ' ||
        '        pp(i) := ''Empno: '' || c.empno; i := i+1; ' ||
        '        pp(i) := ''Job: '' || c.job; i := i+1; ' ||
        '        pp(i) := ''Mgr: '' || c.mgr; i := i+1; ' ||
        '        pp(i) := ''Sal: '' || c.sal; i := i+1; ' ||
        '        pp(i) := null; i := i+1; ' ||
        '    END LOOP; ' ||
        '    :1 := pp; ' ||
        'END;',
        -1, 1, coll, errm);
    each := coll.FIRST;
    WHILE (each IS NOT NULL) LOOP
        dosomething(coll(each));
        each := coll.NEXT(each);
    END LOOP;
END;

```

GET_INDEXES Function

Given a name of a variable or parameter, this function returns the set of its indexes, if it is an indexed table. An error is returned if it is not an indexed table.

Syntax

```

DBMS_DEBUG.GET_INDEXES (
    varname    IN  VARCHAR2,
    frame#     IN  BINARY_INTEGER,
    handle     IN  program_info,
    entries    OUT index_table)
RETURN BINARY_INTEGER;

```

Parameters

Table 72-25 GET_INDEXES Function Parameters

Parameter	Description
varname	Name of the variable to get index information about
frame#	Number of frame in which the variable or parameter resides; NULL for a package variable
handle	Package description, if object is a package variable
entries	1-based table of the indexes: if non-NULL, then entries(1) contains the first index of the table, entries(2) contains the second index, and so on.

Return Values

Table 72-26 GET_INDEXES Function Return Values

Return	Description
error_no_such_object	One of the following: <ul style="list-style-type: none"> - The package does not exist - The package is not instantiated - The user does not have privileges to debug the package - The object does not exist in the package

GET_MORE_SOURCE Procedure

When the source does not fit in the buffer provided by the SHOW_SOURCE Procedure version which produced a formatted buffer, this procedure provides additional source.

Syntax

```
DBMS_DEBUG.GET_MORE_SOURCE (
    buffer      IN OUT VARCHAR2,
    buflen     IN BINARY_INTEGER,
    piece#     IN BINARY_INTEGER);
```

Parameters

Table 72-27 GET_MORE_SOURCE Procedure Parameters

Parameter	Description
buffer	The buffer
buflen	The length of the buffer
piece#	A value between 2 and the value returned in the parameter pieces from the call to the relevant version of the SHOW_SOURCE Procedures

Usage Notes

This procedure should be called only after the version of SHOW_SOURCE that returns a formatted buffer.

Related Topics

- [SHOW_SOURCE Procedures](#)
The procedure gets the source code. There are two overloaded `SHOW_SOURCE` procedures.

GET_LINE_MAP Function

This function finds line and entrypoint information about a program so that a debugger can determine the source lines at which it is possible to place breakpoints.

Syntax

```
DBMS_DEBUG.GET_LINE_MAP (  
    program          IN    program_info,  
    maxline          OUT   BINARY_INTEGER,  
    number_of_entry_points OUT BINARY_INTEGER,  
    linemap          OUT   RAW)  
RETURN BINARY_INTEGER;
```

Parameters

Table 72-28 GET_LINE_MAP Function Parameters

Parameter	Description
program	A top-level program unit (procedure / package / function / package body, and so on). Its <code>Namespace</code> , <code>Name</code> , and <code>Owner</code> fields must be initialized, the remaining fields are ignored.
maxline	The largest source code line number in 'program'
number_of_entry_points	The number of subprograms in 'program'
linemap	A bitmap representing the executable lines of 'program'. If line number <code>N</code> is executable, bit number <code>N MOD 8</code> will be set to 1 at <code>linemap</code> position <code>N / 8</code> . The length of returned <code>linemap</code> is either <code>maxline</code> divided by 8 (plus one if <code>maxline MOD 8</code> is not zero) or 32767 in the unlikely case of <code>maxline</code> being larger than <code>32767 * 8</code> .

Return Values

Table 72-29 GET_LINE_MAP Function Return Values

Return	Description
success	A successful completion
error_no_debug_info	The program unit exists, but has no debug info
error_bad_handle	No such program unit exists

GET_RUNTIME_INFO Function

This function returns information about the current program. It is only needed if the `info_requested` parameter to `SYNCHRONIZE` or `CONTINUE` was set to 0.



Note:

This is currently only used by client-side PL/SQL.

Syntax

```
DBMS_DEBUG.GET_RUNTIME_INFO (
    info_requested IN BINARY_INTEGER,
    run_info      OUT runtime_info)
RETURN BINARY_INTEGER;
```

Parameters

Table 72-30 GET_RUNTIME_INFO Function Parameters

Parameter	Description
<code>info_requested</code>	Which information should be returned in <code>run_info</code> when the program stops (see DBMS_DEBUG Operational Notes for information about information flags)
<code>run_info</code>	Information about the state of the program

GET_TIMEOUT_BEHAVIOUR Function

This procedure returns the current timeout behavior. This call is made in the target session.

Syntax

```
DBMS_DEBUG.GET_TIMEOUT_BEHAVIOUR
RETURN BINARY_INTEGER;
```

Parameters

Table 72-31 GET_TIMEOUT_BEHAVIOUR Function Parameters

Parameter	Description
<code>oer</code>	The OER (a 4-byte positive number)

Return Values

Table 72-32 GET_TIMEOUT_BEHAVIOUR Function Return Values

Return	Description
<code>success</code>	A successful completion

Information Flags

```
info_getOerInfo CONSTANT PLS_INTEGER:= 32;
```

Usage Notes

Less functionality is supported on OER breakpoints than on code breakpoints. In particular, note that:

- No "breakpoint number" is returned - the number of the OER is used instead. Thus it is impossible to set duplicate breakpoints on a given OER (it is a no-op).
- It is not possible to disable an OER breakpoint (although clients are free to simulate this by deleting it).
- OER breakpoints are deleted using `delete_oer_breakpoint`.

GET_VALUE Function

This function gets a value from the currently-running program. There are two overloaded `GET_VALUE` functions.

Syntax

```
DBMS_DEBUG.GET_VALUE (  
    variable_name IN VARCHAR2,  
    frame#        IN BINARY_INTEGER,  
    scalar_value  OUT VARCHAR2,  
    format        IN VARCHAR2 := NULL)  
RETURN BINARY_INTEGER;
```

Parameters

Table 72-33 GET_VALUE Function Parameters

Parameter	Description
variable_name	Name of the variable or parameter
frame#	Frame in which it lives; 0 means the current procedure
scalar_value	Value
format	Optional date format to use, if meaningful

Return Values

Table 72-34 GET_VALUE Function Return Values

Return	Description
success	A successful completion
error_bogus_frame	Frame does not exist
error_no_debug_info	Entrypoint has no debug information
error_no_such_object	variable_name does not exist in frame#
error_unknown_type	The type information in the debug information is illegible
error_nullvalue	Value is NULL

Table 72-34 (Cont.) GET_VALUE Function Return Values

Return	Description
error_indexed_table	The object is a table, but no index was provided

This form of `GET_VALUE` is for fetching package variables. Instead of a frame#, it takes a handle, which describes the package containing the variable.

Syntax

```
DBMS_DEBUG.GET_VALUE (  
    variable_name IN VARCHAR2,  
    handle        IN program_info,  
    scalar_value  OUT VARCHAR2,  
    format        IN VARCHAR2 := NULL)  
RETURN BINARY_INTEGER;
```

Parameters

Table 72-35 GET_VALUE Function Parameters

Parameter	Description
variable_name	Name of the variable or parameter
handle	Description of the package containing the variable
scalar_value	Value
format	Optional date format to use, if meaningful

Return Values

Table 72-36 GET_VALUE Function Return Values

Return	Description
error_no_such_object	One of the following: <ul style="list-style-type: none">- Package does not exist- Package is not instantiated- User does not have privileges to debug the package- Object does not exist in the package
error_indexed_table	The object is a table, but no index was provided

Examples

This example illustrates how to get the value with a given package `PACK` in schema `SCOTT`, containing variable `VAR`:

```
DECLARE  
    handle      dbms_debug.program_info;  
    resultbuf   VARCHAR2(500);  
    retval      BINARY_INTEGER;  
BEGIN  
    handle.Owner      := 'SCOTT';  
    handle.Name       := 'PACK';
```

```
handle.namespace := dbms_debug.namespace_pkgspec_or_toplevel;
retval           := dbms_debug.get_value('VAR', handle, resultbuf, NULL);
END;
```

INITIALIZE Function

This function initializes the target session for debugging.

Syntax

```
DBMS_DEBUG.INITIALIZE (
    debug_session_id IN VARCHAR2      := NULL,
    diagnostics       IN BINARY_INTEGER := 0)
RETURN VARCHAR2;
```

Parameters

Table 72-37 INITIALIZE Function Parameters

Parameter	Description
debug_session_id	Name of session ID. If NULL, then a unique ID is generated.
diagnostics	Indicates whether to dump diagnostic output to the tracefile: 0 = (default) no diagnostics 1 = print diagnostics

Return Values

The newly-registered debug session ID (debugID)

Usage Notes

You cannot use `DBMS_DEBUG` and the JDWP-based debugging interface simultaneously. This call will either fail with an ORA-30677 error if the session is currently being debugged with the JDWP-based debugging interface or, if the call succeeds, any further use of the JDWP-based interface to debug this session will be disallowed.

Calls to `DBMS_DEBUG` will succeed only if either the caller or the specified debug role carries the `DEBUG CONNECT SESSION` privilege. Failing that, an ORA-1031 error will be raised. Other exceptions are also possible if a debug role is specified but the password does not match, or if the calling user has not been granted the role, or the role is application-enabled and this call does not originate from within the role-enabling package.

The `CREATE ANY PROCEDURE` privilege does not affect the visibility of routines through the debugger. A privilege `DEBUG` for each object has been introduced with a corresponding `DEBUG ANY PROCEDURE` variant. These are required in order to see routines owned by users other than the session's login user.

Authentication of the debug role and the check for `DEBUG CONNECT SESSION` privilege will be done in the context of the caller to this routine. If the caller is a definer's rights routine or has been called from one, only privileges granted to the defining user, the debug role, or `PUBLIC` will be used to check for `DEBUG CONNECT SESSION`. If this call is from within a definer's rights routine, the debug role, if specified, must be one that has been granted to that definer, but it need not also have been granted to the session login user or be enabled in the calling session at the time the call is made.

The checks made by the debugger after this call is made looking for the `DEBUG` privilege on individual procedures will be done in the context of the session's login user, the roles that were enabled at session level at the moment this call was made (even if those roles were not available within a definer's rights environment of the call), and the debug role.

PING Procedure

This procedure pings the target session to prevent it from timing out. Use this procedure when execution is suspended in the target session, for example at a breakpoint.

If the `timeout_behaviour` is set to `retry_on_timeout` then this procedure is not necessary.

Syntax

```
DBMS_DEBUG.PING;
```

Exceptions

Oracle will display the `no_target_program` exception if there is no target program or if the target session is not currently waiting for input from the debug session.

Usage Notes

Timeout options for the target session are registered with the target session by calling `set_timeout_behaviour`:

- `retry_on_timeout` - Retry. Timeout has no effect. This is like setting the timeout to an infinitely large value.
- `continue_on_timeout` - Continue execution, using same event flags.
- `nodebug_on_timeout` - Turn debug-mode OFF (in other words, call `debug_off`) and then continue execution. No more events will be generated by this target session unless it is re-initialized by calling `debug_on`.
- `abort_on_timeout` - Continue execution, using the `abort_execution` flag, which should cause the program to terminate immediately. The session remains in debug-mode.

```
retry_on_timeout CONSTANT BINARY_INTEGER:= 0;
continue_on_timeout CONSTANT BINARY_INTEGER:= 1;
nodebug_on_timeout CONSTANT BINARY_INTEGER:= 2;
abort_on_timeout CONSTANT BINARY_INTEGER:= 3;
```

PRINT_BACKTRACE Procedure

This procedure prints a backtrace listing of the current execution stack. This should only be called if a program is currently running.

There are two overloaded `PRINT_BACKTRACE` procedures.

Syntax

```
DBMS_DEBUG.PRINT_BACKTRACE (
    listing IN OUT VARCHAR2);

DBMS_DEBUG.PRINT_BACKTRACE (
    backtrace OUT backtrace_table);
```

Parameters

Table 72-38 PRINT_BACKTRACE Procedure Parameters

Parameter	Description
listing	A formatted character buffer with embedded newlines
backtrace	1-based indexed table of backtrace entries. The currently-running procedure is the last entry in the table (that is, the frame numbering is the same as that used by <code>GET_VALUE</code>). Entry 1 is the oldest procedure on the stack.

PRINT_INSTANTIATIONS Procedure

This procedure returns a list of the packages that have been instantiated in the current session.

Syntax

```
DBMS_DEBUG.PRINT_INSTANTIATIONS (  
    pkgs    IN OUT NOCOPY backtrace_table,  
    flags   IN BINARY_INTEGER);
```

Parameters

Table 72-39 PRINT_INSTANTIATIONS Procedure Parameters

Parameter	Description
pkgs	The instantiated packages
flags	Bitmask of options: <ul style="list-style-type: none">• 1 - show specs• 2 - show bodies• 4 - show local instantiations• 8 - show remote instantiations (NYI)• 16 - do a fast job. The routine does not test whether debug information exists or whether the libunit is shrink-wrapped.

Exceptions

`no_target_program` - target session is not currently executing

Usage Notes

On return, `pkgs` contains a `program_info` for each instantiation. The valid fields are: Namespace, Name, Owner, and LibunitType.

In addition, `Line#` contains a bitmask of:

- 1 - the libunit contains debug info
- 2 - the libunit is shrink-wrapped

PROBE_VERSION Procedure

This procedure returns the version number of DBMS_DEBUG on the server.

Syntax

```
DBMS_DEBUG.PROBE_VERSION (  
    major out BINARY_INTEGER,  
    minor out BINARY_INTEGER);
```

Parameters

Table 72-40 PROBE_VERSION Procedure Parameters

Parameter	Description
major	Major version number
minor	Minor version number: increments as functionality is added

SELF_CHECK Procedure

This procedure performs an internal consistency check. SELF_CHECK also runs a communications test to ensure that the Probe processes are able to communicate.

If SELF_CHECK does not return successfully, then an incorrect version of DBMS_DEBUG was probably installed on this server. The solution is to install the correct version (pblog.sql loads DBMS_DEBUG and the other relevant packages).

Syntax

```
DBMS_DEBUG.SELF_CHECK (  
    timeout IN binary_integer := 60);
```

Parameters

Table 72-41 SELF_CHECK Procedure Parameters

Parameter	Description
timeout	The timeout to use for the communication test. Default is 60 seconds.

Exceptions

Table 72-42 SELF_CHECK Procedure Exceptions

Exception	Description
OER-6516	Probe version is inconsistent
pipe_creation_failure	Could not create a pipe
pipe_send_failure	Could not write data to the pipe
pipe_receive_failure	Could not read data from the pipe
pipe_datatype_mismatch	Datatype in the pipe was wrong

Table 72-42 (Cont.) SELF_CHECK Procedure Exceptions

Exception	Description
pipe_data_error	Data got garbled in the pipe

All of these exceptions are fatal. They indicate a serious problem with Probe that prevents it from working correctly.

SET_BREAKPOINT Function

This function sets a breakpoint in a program unit, which persists for the current session.

Execution pauses if the target program reaches the breakpoint.

Syntax

```
DBMS_DEBUG.SET_BREAKPOINT (
    program      IN  program_info,
    line#        IN  BINARY_INTEGER,
    breakpoint#  OUT BINARY_INTEGER,
    fuzzy        IN  BINARY_INTEGER := 0,
    iterations   IN  BINARY_INTEGER := 0)
RETURN BINARY_INTEGER;
```

Parameters

Table 72-43 SET_BREAKPOINT Function Parameters

Parameter	Description
program	Information about the program unit in which the breakpoint is to be set. (In version 2.1 and later, the namespace, name, owner, and dblink may be set to NULL, in which case the breakpoint is placed in the currently-running program unit.)
line#	Line at which the breakpoint is to be set
breakpoint#	On successful completion, contains the unique breakpoint number by which to refer to the breakpoint
fuzzy	Only applicable if there is no executable code at the specified line: 0 means return <code>error_illegal_line</code> 1 means search forward for an adjacent line at which to place the breakpoint -1 means search backward for an adjacent line at which to place the breakpoint
iterations	Number of times to wait before signalling this breakpoint

Return Values



Note:

The `fuzzy` and `iterations` parameters are not yet implemented

Table 72-44 SET_BREAKPOINT Function Return Values

Return	Description
success	A successful completion
error_illegal_line	Cannot set a breakpoint at that line
error_bad_handle	No such program unit exists

SET_OER_BREAKPOINT Function

This function sets an OER breakpoint.

Syntax

```
DBMS_DEBUG.SET_OER_BREAKPOINT (  
    oer IN PLS_INTEGER)  
RETURN PLS_INTEGER;
```

Parameters

Table 72-45 SET_OER_BREAKPOINT Function Parameters

Parameter	Description
oer	The OER (positive 4-byte number) to set

Return Values

Table 72-46 SET_OER_BREAKPOINT Function Return Values

Return	Description
success	A successful completion
error_no_such_breakpt	No such OER breakpoint exists

SET_TIMEOUT Function

This function sets the timeout value and returns the new timeout value.

Syntax

```
DBMS_DEBUG.SET_TIMEOUT (  
    timeout BINARY_INTEGER)  
RETURN BINARY_INTEGER;
```

Parameters

Table 72-47 SET_TIMEOUT Function Parameters

Parameter	Description
timeout	The timeout to use for communication between the target and debug sessions

SET_TIMEOUT_BEHAVIOUR Procedure

This procedure tells Probe what to do with the target session when a timeout occurs. This call is made in the target session.

Syntax

```
DBMS_DEBUG.SET_TIMEOUT_BEHAVIOUR (  
    behaviour IN PLS_INTEGER);
```

Parameters

Table 72-48 SET_TIMEOUT_BEHAVIOUR Procedure Parameters

Parameter	Description
behaviour - One of the following:	
retry_on_timeout	Retry. Timeout has no effect. This is like setting the timeout to an infinitely large value.
continue_on_timeout	Continue execution, using same event flags
nodebug_on_timeout	Turn debug-mode OFF (in other words, call <code>debug_off</code>) and continue execution. No more events will be generated by this target session unless it is re-initialized by calling <code>debug_on</code> .
abort_on_timeout	Continue execution, using the <code>abort_execution</code> flag, which should cause the program to terminate immediately. The session remains in debug-mode.

Exceptions

unimplemented - the requested behavior is not recognized

Usage Notes

The default behavior (if this procedure is not called) is `continue_on_timeout`, since it allows a debugger client to reestablish control (at the next event) but does not cause the target session to hang indefinitely.

SET_VALUE Function

This function sets a value in the currently-running program. There are two overloaded `SET_VALUE` functions.

Syntax

```
DBMS_DEBUG.SET_VALUE (  
    frame#                IN binary_integer,  
    assignment_statement IN varchar2)  
RETURN BINARY_INTEGER;
```

```
DBMS_DEBUG.SET_VALUE (  
    handle                IN program_info,  
    assignment_statement IN VARCHAR2)  
RETURN BINARY_INTEGER;
```

Parameters

Table 72-49 SET_VALUE Function Parameters

Parameter	Description
frame#	Frame in which the value is to be set; 0 means the currently executing frame.
handle	Description of the package containing the variable
assignment_statement	An assignment statement (which must be legal PL/SQL) to run in order to set the value. For example, 'x := 3;'. Only scalar values are supported in this release. The right side of the assignment statement must be a scalar.

Return Values

Table 72-50 SET_VALUE Function Return Values

Return	Description
success	-
error_illegal_value	Not possible to set it to that value
error_illegal_null	Cannot set to NULL because object type specifies it as 'not NULL'
error_value_malformed	Value is not a scalar
error_name_incomplete	The assignment statement does not resolve to a scalar. For example, 'x := 3;', if x is a record.
error_no_such_object	One of the following: - Package does not exist - Package is not instantiated - User does not have privileges to debug the package - Object does not exist in the package

Usage Notes

In some cases, the PL/SQL compiler uses temporaries to access package variables, and does not guarantee to update such temporaries. It is possible, although unlikely, that modification to a package variable using SET_VALUE might not take effect for a line or two.

Examples

To set the value of SCOTT.PACK.var to 6:

```
DECLARE
    handle  dbms_debug.program_info;
    retval  BINARY_INTEGER;
BEGIN
    handle.Owner      := 'SCOTT';
    handle.Name       := 'PACK';
    handle.namespace := dbms_debug.namespace_pkgspec_or_toplevel;
    retval           := dbms_debug.set_value(handle, 'var := 6;');
END;
```

SHOW_BREAKPOINTS Procedures

There are two overloaded procedures that return a listing of the current breakpoints. There are three overloaded SHOW_BREAKPOINTS procedures.

Syntax

```
DBMS_DEBUG.SHOW_BREAKPOINTS (  
    listing    IN OUT VARCHAR2);  
  
DBMS_DEBUG.SHOW_BREAKPOINTS (  
    listing    OUT breakpoint_table);  
  
DBMS_DEBUG.SHOW_BREAKPOINTS (  
    code_breakpoints OUT breakpoint_table,  
    oer_breakpoints  OUT oer_table);
```

Parameters

Table 72-51 SHOW_BREAKPOINTS Procedure Parameters

Parameter	Description
listing	A formatted buffer (including newlines) of the breakpoints. Indexed table of breakpoint entries. The breakpoint number is indicated by the index into the table. Breakpoint numbers start at 1 and are reused when deleted.
code_breakpoints	The indexed table of breakpoint entries, indexed by breakpoint number
oer_breakpoints	The indexed table of OER breakpoints, indexed by OER

SHOW_FRAME_SOURCE Procedure

The procedure gets the source code. There are two overloaded SHOW_SOURCE procedures.

Syntax

```
DBMS_DEBUG.SHOW_FRAME_SOURCE (  
    first_line IN BINARY_INTEGER,  
    last_line  IN BINARY_INTEGER,  
    source     IN OUT NOCOPY vc2_table,  
    frame_num  IN BINARY_INTEGER);
```

Parameters

Table 72-52 SHOW_FRAME_SOURCE Procedure Parameters

Parameter	Description
first_line	Line number of first line to fetch (PL/SQL programs always start at line 1 and have no holes)
last_line	Line number of last line to fetch. No lines are fetched past the end of the program.
source	The resulting table, which may be indexed by line#
frame_num	1-based frame number

Usage Notes

- You use this function only when backtrace shows an anonymous unit is executing at a given frame position and you need to view the source in order to set a breakpoint.
- If frame number is top of the stack and it's an anonymous block then `SHOW_SOURCE` can also be used.
- If it's a stored PL/SQL package/function/procedure then use SQL as described in the [Usage Notes](#) to [SHOW_SOURCE Procedures](#).

SHOW_SOURCE Procedures

The procedure gets the source code. There are two overloaded `SHOW_SOURCE` procedures.

Syntax

```
DBMS_DEBUG.SHOW_SOURCE (
    first_line IN BINARY_INTEGER,
    last_line  IN BINARY_INTEGER,
    source     OUT vc2_table);

DBMS_DEBUG.SHOW_SOURCE (
    first_line IN BINARY_INTEGER,
    last_line  IN BINARY_INTEGER,
    window     IN BINARY_INTEGER,
    print_arrow IN BINARY_INTEGER,
    buffer     IN OUT VARCHAR2,
    buflen     IN BINARY_INTEGER,
    pieces     OUT BINARY_INTEGER);
```

Parameters

Table 72-53 SHOW_SOURCE Procedure Parameters

Parameter	Description
first_line	Line number of first line to fetch (PL/SQL programs always start at line 1 and have no holes)
last_line	Line number of last line to fetch. No lines are fetched past the end of the program.
source	The resulting table, which may be indexed by line#
window	'Window' of lines (the number of lines around the current source line)
print_arrow	Nonzero means to print an arrow before the current line
buffer	Buffer in which to place the source listing
buflen	Length of buffer
pieces	Set to nonzero if not all the source could be placed into the given buffer

Return Values

An indexed table of source-lines. The source lines are stored starting at `first_line`. If any error occurs, then the table is empty.

Usage Notes

The best way to get the source code (for a program that is being run) is to use SQL. For example:

```
DECLARE
    info DBMS_DEBUG.runtime_info;
BEGIN
    -- call DBMS_DEBUG.SYNCHRONIZE, CONTINUE,
    -- or GET_RUNTIME_INFO to fill in 'info'
    SELECT text INTO <buffer> FROM all_source
    WHERE owner = info.Program.Owner
        AND name = info.Program.Name
        AND line = info.Line#;
END;
```

However, this does not work for nonpersistent programs (for example, anonymous blocks and trigger invocation blocks). For nonpersistent programs, call `SHOW_SOURCE`. There are two flavors: one returns an indexed table of source lines, and the other returns a packed (and formatted) buffer.

The second overloading of `SHOW_SOURCE` returns the source in a formatted buffer, complete with line-numbers. It is faster than the indexed table version, but it does not guarantee to fetch all the source.

If the source does not fit in `bufferlength` (`buflen`), then additional pieces can be retrieved using the `GET_MORE_SOURCE` procedure (`pieces` returns the number of additional pieces that need to be retrieved).

SYNCHRONIZE Function

This function waits until the target program signals an event. If `info_requested` is not `NULL`, then it calls `GET_RUNTIME_INFO`.

Syntax

```
DBMS_DEBUG.SYNCHRONIZE (
    run_info          OUT runtime_info,
    info_requested IN  BINARY_INTEGER := NULL)
RETURN BINARY_INTEGER;
```

Parameters

Table 72-54 SYNCHRONIZE Function Parameters

Parameter	Description
run_info	Structure in which to write information about the program. By default, this includes information about what program is running and at which line execution has paused.
info_requested	Optional bit-field in which to request information other than the default (which is <code>info_getStackDepth + info_getLineInfo</code>). 0 means that no information is requested at all (see DBMS_DEBUG Operational Notes for more about information flags).

Return Values

Table 72-55 SYNCHRONIZE Function Return Values

Return	Description
success	A successful completion
error_timeout	Timed out before the program started execution
error_communication	Other communication error

TARGET_PROGRAM_RUNNING Procedure

This procedure returns `TRUE` if the target session is currently executing a stored procedure, or `FALSE` if it is not.

Syntax

```
DBMS_DEBUG.TARGET_PROGRAM_RUNNING
RETURN BOOLEAN;
```