

The SMite Virtual Machine

Reuben Thomas

12th January 2019

Typographical conventions

Actions and registers are shown in Typewriter font; interface calls are shown in **Bold** type, and followed by empty parentheses.

Addresses are given in bytes and refer to the VM address space except where stated. Addresses are written in hexadecimal; hex numbers are prefixed with “0x”.

1 Introduction

SMite is a simple virtual machine for study and experiment. It is a stack machine, based on the more complex register machine [3]. This paper gives a full description of SMite, but certain implementation-dependent features, such as the size of the stacks, are purposely left unspecified, and the exact method of implementation is left to the implementor in many particulars.

SMite is self-contained. Machine code routines on the host computer may be accessed using the `CALL_NATIVE` action, which can also be used to implement I/O (see 3.10). SMite supports a simple object module format.

SMite is conceptually (and usually in fact) a library, embedded in other programs. A small interface is provided for other programs to control SMite.

2 Architecture

SMite’s address unit is the byte, which is eight bits. Words are `WORD_SIZE` bytes. The word is the size of the numbers and addresses on which SMite operates, and of the items placed on the stacks. The size of the byte and range of word sizes allowed have been chosen with a view to making efficient implementation possible on the vast majority of current machine architectures.

Words may have the bytes stored in big-endian or little-endian order. The address of a word is that of the byte in it with the lowest address.

2.1 Registers

The registers, each with its function, are set out in table 1.

The registers are word quantities.

To ease efficient implementation, the registers may only be accessed by actions (see section 3.7); not all registers are accessible, and only a few are writable.

2.2 Memory

SMite’s memory is a contiguous sequence of bytes with addresses in the range 0 to `MEMORY - 1`.

Register	Function
PC	The Program Counter. Points to the next byte from which an instruction may be loaded.
ITYPE	The type of an instruction to be executed: 0 for a number, and 1 for an action.
I	The Instruction. Holds the opcode of an instruction to be executed.
MEMORY	The size in bytes of SMite's memory, which must be a whole number of words.
SDEPTH	The data Stack DEPTH (number of items on the stack).
RDEPTH	The Return stack DEPTH (number of items on the return stack).
SSIZE	The number of words allocated for the data stack.
RSIZE	The number of words allocated for the return stack.
HANDLER	The address PC is set to when an exception is raised.
ENDISM	The endianness of SMite: 0 = Little-endian, 1 = Big-endian.
BADPC	The address of the instruction that raised the most recent exception.
INVALID	The last address which caused an address exception.
WORD_SIZE	The number of bytes in a word. Must be a power of 2, and in the range 2 to 32 inclusive.
NATIVE_POINTER_SIZE	The number of bytes in a host machine pointer (for CALL_NATIVE; see section 3.10).

Table 1: Registers

2.3 Stacks

The data and return stacks are LIFO stacks of words. To **push** an item on to a stack means to add a new item to the top of the stack, increasing the stack depth by 1; to **pop** an item means to reduce the stack depth by 1. Actions that change the number of items on a stack implicitly pop their arguments and push their results.

The data stack is used for passing values to actions and routines and the return stack for holding subroutine return addresses. The return stack may be used for other operations subject to the restrictions placed on it by its normal usage: it must be returned before a RET action to the state it was in directly after the corresponding CALL.

In what follows, for “the stack” read “the data stack”; the return stack is always mentioned explicitly.

2.4 Operation

Before SMite is started, ENDISM should be set to 0 or 1 according to the implementation, and WORD_SIZE and NATIVE_POINTER_SIZE to the appropriate values. The other registers should be initialised to 0.

ENDISM, WORD_SIZE and NATIVE_POINTER_SIZE must not change while SMite is executing.

SMite is started by a call to the interface calls **run()** or **single_step()** (see section 4.2). In the former case, the execution cycle is entered:

```

begin
    decode the next instruction into I from the bytes pointed to by PC
    set PC to point to the next byte after the end of the instruction
    execute the instruction in I
repeat

```

In the latter case, the contents of the execution cycle is executed once, and control returns to the calling program.

Note that the calls **run()** and **single_step()** do not perform the initialisation specified above.

2.5 Termination

When SMite encounters a **HALT** action (see section 3.9), it returns the top data stack item as the reason code, unless **SDEPTH** does not point to a valid word, in which case reason code -257 is returned (see section 2.6).

Reason codes which are also valid exception codes (either reserved (see section 2.6) or user exception codes) should not normally be used. This allows exception codes to be passed back by an exception handler to the calling program, so that the calling program can handle certain exceptions without confusing exception codes and reason codes.

2.6 Exceptions

Exceptional and error conditions may be dealt with by **raising an exception**. The type of exception is signalled by its **exception code**. Exception codes are signed numbers. -1 to -511 are reserved for SMite's own exception codes; the meanings of those that may be raised by SMite are shown in table 2.

Raising an exception proceeds as follows:

```

push the exception code on to the stack
set BADPC to PC - 1
set PC to the value of HANDLER

```

The instruction that caused the exception to be raised is then considered to have finished executing.

An exception can be raised explicitly by **THROW** (see section 3.9); exceptions are also raised by various errors, such as an attempt to access an invalid address, or divide by zero.

Code	Meaning
-9	Invalid address (see below).
-10	Division by zero attempted (see section 3.4).
-23	Address alignment exception (see below).
-256	Invalid opcode (see section 3.12).

Table 2: Exceptions raised by SMite

Exception -9 is raised whenever an attempt is made to access an invalid address, either by an instruction, or during an instruction fetch (because PC contains an invalid address). Exception -23 is raised when an action expecting an address of

type *a-addr* (word-aligned) is given a non-aligned address. When SMite raises an address exception (−9 or −23), *INVALID* is first set to the offending address.

If putting the code on the stack would cause *SDEPTH* to exceed *SSIZE*, the effect of a *HALT* with code −257 is performed (although the actual mechanics are not, as that too would involve putting a number on the stack).

3 Instruction set

The instruction set is listed in sections 3.1 to 3.10, with the instructions grouped according to function. The instructions are given in the following format:

NAME (*before* -- *after*)
R: (*before* -- *after*)

Description.

The first line consists of the name of the instruction. On the right are the stack effect or effects, which show the effect of the instruction on the data and return (R) stacks. Underneath is the description.

Stack effects are written

(*before* -- *after*)

where *before* and *after* are stack pictures showing the items on top of a stack before and after the instruction is executed. An instruction only affects the items shown in its stack effects. The brackets and dashes serve merely to delimit the stack effect and to separate *before* from *after*. **Stack pictures** are a representation of the top-most items on the stack, and are written

$i_1 \ i_2 \dots i_{n-1} \ i_n$

where the i_k are stack items, each of which occupies a whole number of words, with i_n being on top of the stack. The symbols denoting different types of stack item are shown in table 3.

Symbol	Data type
<i>flag</i>	a Boolean flag, 1 for true and 0 for false
<i>byte</i>	byte
<i>n</i>	signed number
<i>u</i>	unsigned number
<i>n u</i>	number (signed or unsigned)
<i>x</i>	unspecified word
<i>addr</i>	address
<i>a-addr</i>	word-aligned address
<i>n-addr</i>	native address

Table 3: Types used in stack effects

Types are only used to indicate how instructions treat their arguments and results; SMite does not distinguish between stack items of different types. In stack pictures the most general argument types with which each instruction can be supplied are given; subtypes may be substituted. Using the phrase “ $i \Rightarrow j$ ” to denote “ i is a subtype of j ”, table 4 shows the subtype relationships. The subtype relation is transitive.

Numbers are represented in twos complement form. *addr* consists of all valid virtual machine addresses. Numeric constants can be included in stack pictures, and are of type *n|u*. Native addresses may occupy more than one word, according

$u \Rightarrow x$
$n \Rightarrow x$
$flag \Rightarrow u$
$byte \Rightarrow u$
$a-addr \Rightarrow addr \Rightarrow u$

Table 4: The subtype relation

to the values of `WORD_SIZE` and `NATIVE_POINTER_SIZE`; the precise format of this address is implementation-dependent.

Each type may be suffixed by a number in stack pictures; if the same combination of type and suffix appears more than once in a stack effect, it refers to identical stack items. Alternative *after* pictures are separated by “|”, and the circumstances under which each occurs are detailed in the instruction description.

The symbols $i*x$, $j*x$ and $k*x$ are used to denote different collections of zero or more words of any data type. Ellipsis is used for indeterminate numbers of specified types of word.

If an instruction does not modify the return stack, the corresponding stack picture is omitted.

3.1 Numbers

number (-- n)

The number is pushed on to the stack.

3.2 Stack manipulation

These actions manage the data stack and move values between stacks.

POP ($x_u \dots x_1$ u --)

Remove u items from the stack.

DUP ($x_u \dots x_0$ u -- $x_u \dots x_0$ x_u)

Remove u . Copy x_u to the top of the stack.

SWAP ($x_u \dots x_0$ u -- $x_0 x_{u-1} \dots x_1$ x_u)

Exchange the top stack item with the u th. If u is zero, do nothing.

POP2R (x --)
R: (-- x)

Move x to the return stack.

RPOP (-- x)
R: (x --)

Move x from the return stack to the data stack.

RPUSH (u -- x_u)
R: (x_u $x_{u-1} \dots x_0$ -- x_u $x_{u-1} \dots x_0$)

Remove u . Copy x_u to the top of the data stack.

3.3 Comparison

These words compare two numbers (or, for equality tests, any two words) on the stack, returning a flag.

LT (n_1 n_2 -- $flag$)

$flag$ is true if and only if n_1 is less than n_2 .

EQ (x_1 x_2 -- $flag$)

$flag$ is true if and only if x_1 is bit-for-bit the same as x_2 .

ULT (u_1 u_2 -- $flag$)

$flag$ is true if and only if u_1 is less than u_2 .

3.4 Arithmetic

These actions consist of monadic and dyadic operators. All calculations are made without bounds or overflow checking, except as detailed for certain actions.

Addition and negation:

ADD ($n_1 | u_1$ $n_2 | u_2$ -- $n_3 | u_3$)

Add $n_2 | u_2$ to $n_1 | u_1$, giving the sum $n_3 | u_3$.

NEGATE (n_1 -- n_2)

Negate n_1 , giving its arithmetic inverse n_2 .

Multiplication and division (note that all division actions raise exception –10 if division by zero is attempted):

MUL ($n_1 | u_1$ $n_2 | u_2$ -- $n_3 | u_3$)

Multiply $n_1 | u_1$ by $n_2 | u_2$ giving the product $n_3 | u_3$.

UDIVMOD (u_1 u_2 -- u_3 u_4)

Divide u_1 by u_2 , giving the single-word quotient u_3 and the single-word remainder u_4 .

DIVMOD (n_1 n_2 -- n_3 n_4)

Divide n_1 by n_2 using symmetric division, giving the single-word quotient n_3 and the single-word remainder n_4 . The quotient is rounded towards zero.

3.5 Logic and shifts

These actions consist of bitwise logical operators and bitwise shifts.

Logic functions:

INVERT (x_1 -- x_2)

Invert all bits of x_1 , giving its logical inverse x_2 .

AND (x_1 x_2 -- x_3)

x_3 is the bit-by-bit logical “and” of x_1 with x_2 .

OR (x_1 x_2 -- x_3)

x_3 is the bit-by-bit inclusive-or of x_1 with x_2 .

XOR (x_1 x_2 -- x_3)

x_3 is the bit-by-bit exclusive-or of x_1 with x_2 .

Shifts:

LSHIFT (x_1 u -- x_2)

Perform a logical left shift of u bit-places on x_1 , giving x_2 . Put zero into the least significant bits vacated by the shift. If u is greater than or equal to the number of bits in a word, x_2 is zero.

RSHIFT (x_1 u -- x_2)
 Perform a logical right shift of u bit-places on x_1 , giving x_2 . Put zero into the most significant bits vacated by the shift. If u is greater than or equal to the number of bits in a word, x_2 is zero.

3.6 Memory

These actions fetch and store words and bytes to and from memory; there is also an action to add a number to another stored in memory.

LOAD ($a\text{-}addr$ -- x)
 x is the value stored at $a\text{-}addr$.
 STORE (x $a\text{-}addr$ --)
 Store x at $a\text{-}addr$.
 LOADB ($addr$ -- $byte$)
 Fetch the byte stored at $addr$. The unused high-order bits are all zeroes.
 STOREB ($byte$ $addr$ --)
 Store $byte$ at $addr$. Only one byte is transferred.

3.7 Registers

PUSH_SDEPTH (-- u)
 u is the value of SDEPTH, the number of items on the stack.
 STORE_SDEPTH (u --)
 Set SDEPTH to u .
 PUSH_RP (-- $a\text{-}addr$)
 $a\text{-}addr$ is the value of RP.
 STORE_RP ($a\text{-}addr$ --)
 Set RP to $a\text{-}addr$.
 PUSH_PC (-- $addr$)
 Push PC on to the stack.
 PUSH_SSIZE (-- u)
 Push SSIZE on to the stack.
 PUSH_RSIZE (-- u)
 Push RSIZE on to the stack.
 PUSH_HANDLER (-- $addr$)
 Push HANDLER on to the stack.
 STORE_HANDLER ($addr$ --)
 Set HANDLER to $addr$.
 PUSH_MEMORY (-- $a\text{-}addr$)
 Push MEMORY on to the stack.
 PUSH_BADPC (-- $addr$)
 Push BADPC on to the stack.
 PUSH_INVALID (-- $addr$)
 Push INVALID on to the stack.
 PUSH_WORD_SIZE (-- u)
 u is the value of WORD_SIZE.
 PUSH_NATIVE_POINTER_SIZE (-- u)
 u is the value of NATIVE_POINTER_SIZE.

3.8 Control structures

These actions implement unconditional and conditional branches, and subroutine call and return; there is also a no-op.

No-op:

NOP (--)

Do nothing.

Branches:

BRANCH (addr --)

Set PC to *addr*.

BRANCHZ (flag addr --)

If *flag* is false then set PC to *addr*.

Subroutine call and return:

CALL (a-addr₁ --)
R: (-- a-addr₂)

Push PC on to the return stack, put a-addr₁ into PC.

RET (--)
R: (addr --)

Put *addr* into PC.

3.9 Exceptions

These actions give access to SMite's exception mechanisms (see section 2.6).

THROW (n --)

Raise exception *n*.

HALT (x --)

Stop SMite, returning reason code *x* to the calling program (see section 4.2). If SDEPTH is greater than SSIZE, -257 is returned as the reason code.

3.10 External access

These actions allow access to SMite's libraries, the operating system and native machine code.

CALL_NATIVE (n-addr --)

Make a subroutine call to the routine at address *n-addr*, passing the current state as an argument.

EXTRA (i*x -- j*x)

Perform implementation-dependent actions; for example, this can be used to implement system-dependent functionality such as I/O.

3.11 Instruction encoding

Instructions are words encoded by one or more bytes, as follows: the significant bits of the number are split into groups of six bits, starting at the least significant end. The chunks are stored in consecutive bytes. All but the last byte have the seventh bit set and eighth bit clear. If the instruction is a number the final byte has the top two bits either both set or both clear, to match the number's most significant bit; otherwise, the top bit is set and the second bit clear, to indicate an action.

3.12 Action opcodes

Table 5 lists the action opcodes in numerical order. Other action opcodes are undefined. Undefined action opcodes raise exception -256 .

Opcode	Action	Opcode	Action	Opcode	Action
0x00	NOP	0x10	AND	0x20	EXTRA
0x01	POP	0x11	OR	0x21	PUSH_WORD_SIZE
0x02	DUP	0x12	XOR	0x22	PUSH_NATIVE_POINTER_SIZE
0x03	SWAP	0x13	LSHIFT	0x23	PUSH_SDEPTH
0x04	RPUSH	0x14	RSHIFT	0x24	STORE_SDEPTH
0x05	POP2R	0x15	LOAD	0x25	PUSH_RP
0x06	RPOP	0x16	STORE	0x26	STORE_RP
0x07	LT	0x17	LOADB	0x27	PUSH_PC
0x08	EQ	0x18	STOREB	0x28	PUSH_SSIZE
0x09	ULT	0x19	BRANCH	0x29	PUSH_RSIZE
0x0a	ADD	0x1a	BRANCHZ	0x2a	PUSH_HANDLER
0x0b	NEGATE	0x1b	CALL	0x2b	STORE_HANDLER
0x0c	MUL	0x1c	RET	0x2c	PUSH_MEMORY
0x0d	UDIVMOD	0x1d	THROW	0x2d	PUSH_BADPC
0x0e	DIVMOD	0x1e	HALT	0x2e	PUSH_INVALID
0x0f	INVERT	0x1f	CALL_NATIVE		

Table 5: Action opcodes

4 External interface

SMite’s external interface comes in three parts. The calling interface allows SMite to be controlled by other programs. The `CALL_NATIVE` action (see section 3.10) allows implementations to provide access to system facilities, previously written code, code written in other languages, and the speed of machine code in time-critical situations. The object module format allows compiled code to be saved, reloaded and shared between systems.

4.1 Object module format

The object module starts with the ASCII codes of the letters “smite” padded to eight bytes by ASCII NULs (0x00), then values of the `ENDISM` and `WORD_SIZE` registers of the system which saved the module, then the number of bytes the code occupies. These values are all encoded as in section 3.11. Then follows the code.

Object modules have a simple structure, as they are only intended for loading an initial memory image into SMite.

4.2 Calling interface

The calling interface is difficult to specify with the same precision as the rest of SMite, as it may be implemented in any language. However, since only basic types are used, and the semantics are simple, it is expected that implementations in different language producing the same result will be easy to program. A Modula-like syntax is used to give the definitions here. Implementation-defined error codes

must be documented, but are optional. All addresses passed as parameters must be word-aligned. An implementation of SMite must provide the following calls:

native_address (*integer, boolean*) : pointer

Return a native pointer corresponding to the given VM address. If the address is invalid, or the Boolean flag is true and the address is read-only, then a distinguished invalid pointer is returned.

run () : integer

Start SMite by entering the execution cycle as described in section 2.4. If SMite ever executes a HALT action (see section 3.9), the reason code is returned as the result.

single_step () : integer

Execute a single pass of the execution cycle, and return reason code -258 , unless a HALT action was obeyed (see section 3.9), in which case the reason code passed to it is returned.

load_object (*file, address*) : integer

Load the object module specified by *file*, which may be a filename or some other specifier, to the VM address *address*. First the module's header is checked; if the first seven bytes are not as specified above in section 4.1, or the endianness value is not 0 or 1, then return -2 . If the code will not fit into memory at the address given, or the address is out of range or unaligned, return -1 . Otherwise load the code into memory, converting it if the endianness value is different from the current value of `ENDISM`. The result is the length of the code in bytes if successful, and some other implementation-defined value if there is a filing system or other error.

SMite must also provide access to its registers and address space through appropriate data objects.

Acknowledgements

Martin Richards's demonstration of his BCPL-oriented Cintcode virtual machine [1] convinced me it was going to be fun working on virtual machines. He also supervised my BA dissertation project, Beetle [2], on which SMite is based.

References

- [1] Martin Richards. Cintcode distribution, 2000. <https://www.cl.cam.ac.uk/~mr/BCPL.html>.
- [2] Reuben Thomas. Beetle and pForth: a Forth virtual machine and compiler. BA dissertation, University of Cambridge, 1995. <https://rrt.sc3d.org/>.
- [3] Reuben Thomas. *Mite: a basis for ubiquitous virtual machines*. PhD thesis, University of Cambridge Computer Laboratory, November 2000. <https://rrt.sc3d.org/>.