
Virtel Audit, Administration, Operations and Performance Guide

Release 4.61

Syspertec Communications

Oct 23, 2022

CONTENTS

1	Operations	3
1.1	Commands	3
1.2	KILL Command	5
1.3	LINES Command	5
1.4	LINE Command	5
1.5	LOG command	7
1.6	LOG Status Switch Commands	8
1.7	MEMDISPLAY Command	9
1.8	MSG Command	11
1.9	NEW Command	11
1.10	RELAY TRACE Command	11
1.11	RELAYS Command	11
1.12	SILENCE Command	12
1.13	SNAP Command	12
1.14	SNAPMSG Command	12
1.15	SNAP80 Command	13
1.16	SNAPW Command	13
1.17	STAT Command	14
1.18	STOP Command	14
1.19	TCT Command	14
1.20	TERM Command	15
1.21	TRACE NOTRACE Command	16
1.22	UNLOAD Command	18
1.23	VIRSV Command	18
1.24	ZAP Command	19
2	Administration	21
2.1	Line Status Application	21
2.2	Memory Display Application	25
2.3	Maintenance	30
2.4	Correspondent Management	34
2.5	Web Entity Management	38
3	Performance	59
3.1	CONSOLE file	59
3.2	VIRLOG file	60
3.3	VIRTEL logger	62
3.4	Virtel trace	62
3.5	VIRTEL SNAP	66

4	Audit	69
4.1	VIRSTAT file	69
4.2	SMF Support	80
5	Appendix	83
5.1	Trademarks	83
5.2	Open Source Software	83



VIRTEL Audit, Administration, Operations and Performance

Warning: This is a draft version of the document.

Version : 4.61

Release Date : TBA. Publication Date : 23/10/2022

SysperTec Communication

196, Bureaux de la Colline 92213 Saint-Cloud Cedex Tél. : +33 (0) 1 46 02 60 42

www.syspertec.com

Note: Reproduction, transfer, distribution, or storage, in any form, of all or any part of the contents of this document, except by prior authorization of SysperTec Communication, is prohibited.

Every possible effort has been made by SysperTec Communication to ensure that this document is complete and relevant. In no case can SysperTec Communication be held responsible for any damages, direct or indirect, caused by errors or omissions in this document.

As SysperTec Communication uses a continuous development methodology; the information contained in this document may be subject to change without notice. Nothing in this document should be construed in any manner as conferring a right to use, in whole or in part, the products or trademarks quoted herein.

“SysperTec Communication” and “VIRTEL” are registered trademarks. Names of other products and companies mentioned in this document may be trademarks or registered trademarks of their respective owners.

OPERATIONS

1.1 Commands

VIRTEL allows certain functions to be controlled dynamically by console commands. Use one of the following methods to send a command to VIRTEL, according to the operating system:

1.1.1 z/OS Environment

The following modify command may be issued at the z/OS operator console, or from an SDSF session under TSO, in which case the command must be prefixed by the character “/”:

```
F stcvirte,virtel-command
```

stcvirte the name of the VIRTEL started task STC

virtel-cmd a VIRTEL command, as described in the following section.

1.1.2 z/VSE Environment

To send a command to VIRTEL, issue the following command at the VSE operator console:

```
MSG virtel,DATA=cirtel-command
```

virtel The VIRTEL jobname (usually VIRTEL), or the partition in which VIRTEL is executing (for example, F4)

virtel-cmd A VIRTEL command, as described in the following section. Alternatively, issue the following command at the VSE operator console:

```
MSG Fx
```

Fx Partition in which VIRTEL is executing

The system responds with:

```
AR 0015 1I40I READY  
Fx-nnnnAR 0015
```

Note: Note the reply number (nnnn) and issue the following command:

```
nnnn virtel-cmd
```

nnnn reply number

virtel-cmd A VIRTEL command, as described in the following section

1.2 KILL Command

The KILL command can be used to stop a scenario.

```
KILL,T=termid
```

termid terminal name

The KILL command requests VIRTEL to abnormally terminate the scenario currently active on the specified terminal.

1.3 LINES Command

The LINES command can be used to display a summary of the line status.

```
LINES | LINES,ACT | LINES,INACT
```

The LINES command displays the VIRTEL ACB name and a list of the lines defined in the VIRTEL configuration file. The optional keywords ACT or INACT may be used to restrict the display to lines that are in a “active” or “inactive” state respectively.

Example:

```
F VIRTEL,LINES
VIR0200I LINES
VIR0201I VIRTEL 4.61 APPLID=VIRTEL LINES
VIR0202I ALLOCATED IP ADDRESS = 192.168.170.047
VIR0202I INT.NAME EXT.NAME TYPE ACB OR IP
VIR0202I -----
VIR0202I C-HTTP HTTP-CLI TCP1 :41002
VIR0202I E-HTTP HTTP-EDS TCP1 :41003
VIR0202I F-HTTP HTTP-FOR TCP1 :41005
VIR0202I I-CONN IVP1 *TCP1
VIR0202I LM01TX1 LM01TX1 /FAST UMEHTX1
VIR0202I O-HTTP HTTP-OUT TCP1 £NONE£
VIR0202I P-PCLPDF PCL2PDF TCP1 £NONE£
VIR0202I V-HTTP HTTP-VSR TCP1 :41004
VIR0202I W-HTTP HTTP-W2H TCP1 :41001
VIR0202I 9-XMPASS VIRTELXM*XM2 XM44000
VIR0202I 9-XMVTA QLNKHOLT XM1 QLNKCICH
VIR0202I ---END OF LIST---
```

1.4 LINE Command

1.4.1 Display line detail

To display detail information about a Virtel line use the line detail command.

```
LINE=linename,DISPLAY (or L=linename,D)
```

linename Internal or external name of the line

The LINE DISPLAY command displays the status of a line and its associated terminals.

Example:

```
F VIRTEL,LINE=C-HTTP,D
VIR0200I LINE=C-HTTP,D
VIR0207I LINE C-HTTP  TCP1  HTTP STARTED
VIR0203I TERMINALS ASSOCIATED WITH LINE C-HTTP
VIR0203I TERMINAL RELAY  STATUS
VIR0203I -----
VIR0203I CLLOC000+                LINKED
VIR0203I CLLOC001                LINKED
VIR0203I CLLOC002                LINKED
VIR0203I CLLOC003                LINKED
VIR0203I CLLOC004                LINKED
VIR0203I CLLOC005                LINKED
VIR0203I CLLOC006                LINKED
VIR0203I CLLOC007                LINKED
VIR0203I CLLOC008                LINKED
VIR0203I CLLOC009                LINKED
VIR0203I CLVTA000 *W2HPOOL        LINKED
VIR0203I CLVTA001 *W2HPOOL        LINKED
VIR0203I CLVTA002 *W2HPOOL        LINKED
VIR0203I CLVTA003 *W2HPOOL        LINKED
VIR0203I CLVTA004 *W2HPOOL        LINKED
VIR0203I ---END OF LIST---
VIR0204I TERMINALS IN POOL *W2HPOOL
VIR0204I TERMINAL RELAY  PRINTER  USED BY
VIR0204I -----
VIR0204I W2HTP000 REHVT000 REHIP000
VIR0204I W2HTP001 REHVT001 REHIP001
VIR0204I W2HTP002 REHVT002 REHIP002
VIR0204I W2HTP003 REHVT003 REHIP003
VIR0204I W2HTP004 REHVT004 REHIP004
VIR0204I ---END OF LIST---
```

1.4.2 Tracing a line

To activate or deactivate a trace on the line the following command can be used:-

```
LINE=linename,NOTRACE | TRACE [ or L=linename,N | T ]
```

1.4.3 Starting and Stopping A Line

To STOP or START a line use the LINE command with the START or STOP function.

```
LINE=linename,START | STOP
```

OR

```
L=linename,P | S
```

linename Internal or external name of the line

The LINE START and LINE STOP commands perform the same function as the “S” and “P” commands on the “Status of lines”. These commands may only be issued for line types AntiGATE, AntiPCNE, AntiFASTC, and TCP/IP.

1.5 LOG command

The LOG command enables the VIRTEL log to be spun off to the console, a JES2 output dataset , a dataset [new in V4.58]. The LOG command has the following format:-

```
F VIRTEL,LOG=CONSOLE | SYSOUT | BOTH | SPIN | FILE
```

where

- CONSOLE means switch console messages back to the console.
- SYSOUT means switch to spooling consoles messages to SYSOUT.
- BOTH means write console messages to the console and SYSOUT.
- SPIN means spin off the current SYSOUT dataset.
- FILE means write messages to file.

1.5.1 LOG=SYSOUT TCT definition

Setting up VIRTEL to use the LOG=SYSOUT facility requires a change to the TCT definition to direct WTOs to a SYSOUT dataset. In the TCT code the following statement:-

```
LOG=(SYSOUT[,class[,destination]])
```

For example, LOG=(SYSOUT,A,EDSPRT)

This directs all WTOs to a SYSOUT dataset rather than the system console log (SYSLOG). If you want WTO messages going to both the system console and a SYSOUT dataset than issue the following VIRTEL command:-

```
F VIRTEL,LOG=BOTH
```

1.5.2 LOG=FILE [New in V4.58]

Setting up Virtel to use the LOG=FILE facility requires a change to the TCT definition. In the TCT code the following statement:-

```
LOG=FILE
```

This will trigger the log program VIR0021A to write messages to either the VIRLOGX DD statement or the VIRLOGY DD statement depending on the active LOG. These DDNAMES need to be added to the Virtel procedure to support LOG=FILE option. The following DCB attributes. Recommended space allocation could be 10 tracks for each dataset.

```
LOGFILEX and LOGFILEY  
DCB attributes : PS, LRECL=166, RECFM=VB, BLKSIZE=2000
```

If either LOGFILE becomes full (X37 Abend) an automatic switch will occur to to the inactive logfile.

1.6 LOG Status | Switch Commands

To determine the status of the LOG file, or to switch the log file manually issue one of the following commands:-

```
F VIRTEL,LOG,D      Display active logfile  
F VIRTEL,LOG,I      Switch logfiles
```

Note: If you issue the “SWITCH” or “DISPLAY” command and LOGFILES are not in use i.e. LOG=FILE is not coded in the TCT you will receive the message VIR0068E INVALID COMMAND.

1.7 MEMDISPLAY Command

To display Virtel Internal Memory Usage use the MEMDISPLAY command.

```
MEMDISPLAY
```

With the memory diagnostic tool active the MEMDISPLAY command summarize the VIRTEL subpool active allocated memory.

```
VIR0200I MEMDISPLAY
VIR0271I DISPLAY 978
SP1=00024478 SP2=00001044 SP3=0008E35F SP4=00002F61
    00910091 00040009 02380294 000B0011
SP5=000317DC SP6=0004DF73 SP7=00000000 SP8=00000220
    00C504C7 01370137 00000000 00000002
POOL CONTROL BLOCK. SUBPOOL=1
PAG=00109000 NFQ=00109008 #FQ=00000001 FRE=0000B2A0
PAG=000F9000 NFQ=000F9008 #FQ=00000001 FRE=00000080
PAG=000E9000 NFQ=000E9008 #FQ=00000001 FRE=00000078
POOL CONTROL BLOCK. SUBPOOL=2
PAG=1EC14000 NFQ=1EC14008 #FQ=00000005 FRE=0000EF68
POOL CONTROL BLOCK. SUBPOOL=3
PAG=1ECD4000 NFQ=1ECD4008 #FQ=00000002 FRE=00009DF8
PAG=1ED54000 NFQ=1ED54008 #FQ=00000002 FRE=00001750
PAG=1EC84000 NFQ=1EC84008 #FQ=00000001 FRE=00000878
PAG=1ED04000 NFQ=1ED04008 #FQ=00000001 FRE=00000878
PAG=1ED94000 NFQ=1ED94008 #FQ=00000002 FRE=00002768
PAG=1ECF4000 NFQ=1ECF4008 #FQ=00000001 FRE=00000878
PAG=1EE04000 NFQ=1EE04008 #FQ=00000001 FRE=00000878
PAG=1ED74000 NFQ=1ED74008 #FQ=00000001 FRE=00000878
PAG=1ECE4000 NFQ=1ECE4008 #FQ=00000001 FRE=00000878
PAG=1EC64000 NFQ=1EC64008 #FQ=00000001 FRE=00000878
POOL CONTROL BLOCK. SUBPOOL=4
PAG=1EC04000 NFQ=1EC04008 #FQ=00000004 FRE=0000CFA0
POOL CONTROL BLOCK. SUBPOOL=5
PAG=1ECA4000 NFQ=1ECA4008 #FQ=00000002 FRE=0000D870
PAG=1ED14000 NFQ=1ED14008 #FQ=00000001 FRE=000043B8
PAG=1ED24000 NFQ=1ED24008 #FQ=00000001 FRE=000043B8
PAG=1EC74000 NFQ=1EC74008 #FQ=00000001 FRE=0000A1D8
PAG=1EC54000 NFQ=1EC54008 #FQ=00000001 FRE=0000A1D8
PAG=1EBB4000 NFQ=1EBB4008 #FQ=00000001 FRE=000043B8
POOL CONTROL BLOCK. SUBPOOL=6
PAG=1EBF4000 NFQ=1EBF4008 #FQ=00000002 FRE=00000A50
PAG=1EBE4000 NFQ=1EBE4008 #FQ=00000001 FRE=00000088
PAG=1EBD4000 NFQ=1EBD4008 #FQ=00000001 FRE=000000B8
PAG=1EBC4000 NFQ=1EBC4008 #FQ=00000001 FRE=000000D0
PAG=1EBA4000 NFQ=1EBA4008 #FQ=00000001 FRE=00000108
POOL CONTROL BLOCK. SUBPOOL=7
PAG=00000000 NFQ=00000000 #FQ=00000000 FRE=00000000
POOL CONTROL BLOCK. SUBPOOL=8
```

The display response is split into a summary section for each subpool and a detailed allocated page block and free queue element display for each subpool. In the summary display, each subpool has two displayed values. The top value is the amount of storage currently allocated and the value below represents the current allocation in 1K chunks and a peak allocation in 1K chunks.

For example in the above display in SP5 we can see that there is an allocated value of 317DC bytes, represented by 00C5 in 1K chunks, and a peak value of 04C7 in 1K chunks. At the bottom of the display is

a line which provide allocated, free and total values.

1.7.1 Enabling the MEMDISPLAY function

Memory Display feature is activated by using the MEMHST subparameter in the MEMORY parameter present in the VIRTCT.(see the VIRTCT subparameter MEMHST in “VIRTEL461 Installation User Guide”).

1.7.2 Disabling the MEMDISPLAY function

It can be deactivated by using the command.

<code>F VIRTEL, MEMDISPLAY, DISABLE</code>
--

Note: This command should only be implemented when advised to do so by Technical Support. Performance degradation might occur due to the additional monitoring services. This will depend on VIRTEL demand.

1.8 MSG Command

To send a message to VIRTEL Multi-Session users use the MSG command:

```
MSG=message text
```

The specified message will be displayed on the VIRTEL multi-session screen.

1.9 NEW Command

The NEW command refreshes a VIRTEL program, VIRSV service or scenario.

```
NEW=programe
```

programe program name

The NEW command requests VIRTEL to load a fresh copy of a program (presentation module, exit, etc) into the VIRTEL address space. This is required after an update has been made to a program. The message VIR0060W PROGRAM programe IS A NEW COPY indicates a successful reload. The message VIR0061W PROGRAM programe NOT IN MEMORY indicates that the program has not yet been loaded into the VIRTEL address space. In this case, VIRTEL will load the program automatically when it is next needed.

1.10 RELAY TRACE Command

Use the RELAY command to trace the Virtel buffers between Virtel and the application.

```
RELAY=relayname,NOTRACE | TRACE
```

1.11 RELAYS Command

To display a list of Virtel LU relays use the RELAY command.

```
RELAYS
```

The RELAYS command displays the VIRTEL ACB name and a list of the relay LUs opened by VIRTEL. For example:

```
F VIRTEL,RELAYS
VIR0200I RELAYS
VIR0214I ACTIVE RELAY ACBS FOR VIRTEL 4.61 APPLID=APPLHOLT
VIR0214I TERMINAL RELAY      APPLID      CLIENT
VIR0214I -----
VIR0214I CLVTA004 REHVT000 SPCICST  192.168.92.58
VIR0214I W2HIP000 REHIP000
VIR0214I ---END OF LIST---
```

1.12 SILENCE Command

The SILENCE command manages message suppression. The format of the command is:

SILENCE	Toggle SILENCE mode ON or OFF
SILENCE=messageid	Add message to message table
SILENCE=messageid,D	Delete message from message table
SILENCE=RESET	Reset message table and remove all entries
SILENCE=LIST	List messages

The SILENCE command initially reverses the state of the SILENCE parameter as defined in the VIRTCT. A default static message table of connection and disconnection messages is built at initialization. This table includes the following messages - VIR0026W, VIR0028W, VIR0051I, VIR0052I, VIR0505I, VIR0507I, VIR1551I, VIRHT51I, VIRNA51I, VIRPF28I, VIRPF51I, VIRPF52I, VIRPF99I, VIRQ912W, VIRQ922W, VIRT912W, VIRT922W, VIR0002W, VIRU122I and VIR0914E. These messages ids are not effected by the RESET or LIST option of the SILENCE command.

1.13 SNAP Command

This command is used to take a dump of the Virtel SNAP internal trace table.

```
SNAP
```

The SNAP command prints the contents of the VIRTEL internal trace table to the SYSPRINT file . See “VIRTEL SNAP” for further information.

1.13.1 Terminal or Relay SNAP

```
SNAP,T=termid | R=relayname
```

termid terminal name

relayname name of VTAM relay LU currently associated with the terminal

1.14 SNAPMSG Command

```
SNAPMSG, [ALL, RESET, LIST]
```

```
ALL      - The SNAPMSG command requests VIRTEL to generate an automatic SNAP after
↳certain messages (VIRI902W VIR0026W VIR0052I VIR1552I VIR0526W VIR1952I) .
LIST     - List all messages and Actions
RESET    - Reset the dynamic table and clear out all messages.
```

```
SNAPMSG=message[,search string],action
```

The SNAPMSG command allows a SNAP or DUMP to be taken whenever a particular message number is issued by VIRTEL. The command has an additional search field which can be used to identify a message with a particular character string, for example a specific return code. This feature allows upto 10 messages to be held in a dynamic table, along with a static entry that can be defined in the TCT by using the SNAPMSG parameter in the TCT. See “SNAPMSG parameter” in the Virtel Installation Guide.

message Any message that can be issued by Virtel.

search Any search criteria issued within the message. The search file is restricted to a maximum of 10 characters. Anything beyond will be ignored. Default search is none.

action Possible values are S for SNAP, A for ABEND, and D to delete a message from the dynamic table. Virtel will abend with a U0999 abend code, reason code 15 if the ABEND action is used.

Default action is SNAP.

Examples:

```
F VIRTEL, SNAPMSG=VIRHT51I, CALL, S
```

Add message VIRHT51I to SNAPMSG table and take a SNAP if the message is issued and the string "CALL" is found in the message.

```
F SPVIREH1, SNAPMSG, LIST
```

List message subjected to SNAPMSG processing. Example output would look like: -

```
VIR0200I SNAPMSG, LIST
VIR0225I MESSAGE TABLE DISPLAY      459
VIR0230I TCT MSG=VIR0202I, ACTION=S, SEARCH=41001
VIR0227I MSG. 01=VIR0202I, ACTION=S, SEARCH=41002
VIR0225I MESSAGE TABLE END
```

Delete message number 1 from the dynamic SNAPMSG table: -

```
F SPVIREH1, SNAPMSG, D=1
```

1.15 SNAP80 Command

```
SNAP80
```

The SNAP80 command prints the contents of the VIRTEL internal trace table in 80 column format, whatever the current value of the SNAPW parameter.

1.16 SNAPW Command

The format of the SNAP output can be adjusted with the SNAPW command.

```
SNAPW=80 | 132
```

The SNAPW command sets the width for future SNAP commands (80 or 132 columns). The SNAPW parameter in the VIRTCT determines the default width at VIRTEL startup. Refer to the section "Parameters of the VIRTCT" in the VIRTEL Installation Guide for details of the SNAPW parameter.

1.17 STAT Command

1.17.1 Display statistics file information

To display information about the Virtel statistics file management use the STAT command.

```
STAT,D
```

This command displays the status of the VIRSTATx files (message VIR0601I). The STAT command is used to manage the VIRTEL statistics recording files (VIRSTATx). This command can be used only if STATS=MULTI is specified in the VIRTCT.

1.17.2 Switch the VIRSTAT file

To switch the STATISTIC file using the STAT switch command.

```
STAT,I
```

This command forces VIRTEL to free the current VIRSTATx file and to start recording onto the next file.

1.18 STOP Command

To stop Virtel issue the STOP command:

```
STOP
```

The STOP command allows to STOP the VIRTEL task. This command is intended to be mainly used in VSE environment even if it is also available in z/OS environment. On z/OS environment you can also use the following command :

```
P VIRTEL
```

1.19 TCT Command

The TCT command displays some of the TCT options that have been defined in the active TCT.

```
F VIRTEL,TCT
VIR0200I TCT
VIR0270I DISPLAY
VIRTEL TCT=VIRTCTEH:
SILENCE=N, MEMORY=(A,N), BFVSAM=32768, BUFDATA=016, BUFSIZE=32000, STR=03
COUNTRY=FR, GMT=SYSTZ, DEFUTF8=IBM1147, LANG=E, MAXSOCK=00240, VSAMTYP=N
APPLID=VIRTEL, SMF=N, PASSTCK=Y, VIRSECU=Y, SWA=N, NBTERM=0500, NTASK=04
MEMORY=(SYS(0001688K,0001688K), DATA(0002304K,0003200K)), LOG=CONSOLE
VIR0280I END
```

1.20 TERM Command

Use the TERM command to activate a Terminal trace. This will trace data between the browser and Virtel.

TERM=termid,NOTRACE | TRACE [or T=termid,N | T]

1.21 TRACE | NOTRACE Command

A trace can be activated or deactivated on a terminal, line or relay.

```
TRACE,T=termid
TRACE,L=linename
TRACE,R=relayname
NOTRACE,T=termid
NOTRACE,L=linename
NOTRACE,R=relayname
```

termid terminal name

linename Internal or external name of the line

relayname relay associated to the terminal

It is often easier to identify the relay used whose name appears at the bottom of the 3270 session screen as shown below.



Associated relay names

linename Internal or external name of the line

The following alternate forms of the TRACE/NOTRACE commands are also valid

```
TERM=termid,TRACE (or T=termid,T)
TERM=termid,NOTRACE (or T=termid,N)
LINE=linename,TRACE (or L=linename,T)
LINE=linename,NOTRACE (or L=linename,N)
RELAY=relayname,TRACE (or R=relayname,T)
RELAY=relayname,NOTRACE (or R=relayname,N)
```

termid terminal name

linename Internal or external name of the line

relayname Name of VTAM relay LU currently associated with the terminal

1.21.1 Display a list of active traces

```
TRACE,DISPLAY | D
```

An example of the response is:-

```
F VIRTEL,TRACE,DISPLAY or F VIRTEL,TRACE,D
VIR0200I TRACE,D
VIR0208I VIRTEL INTERNAL TRACE = YYY. EXT. BUFFERS = 0001/00FF.
VIR0213I NO ACTIVE TRACES
```

1.21.2 Setting trace options

To set the trace options issue the following command:

```
TRACE,VIT=Y|N Y|N Y|N
```

The default VIT trace parametr is YYN. The external archive trace setting should only be set when instructed to by Virtel support.

The VIT indicators apply the the level of tracing.

```
- Y|N          No tracing or minimal tracing
- Y|N          Data elements traced
- Y|N          External Archive active
```

1.21.3 Deactivate all traces

```
NOTRACE,ALL
```

This command does not affect any memory trace. To stop a memory trace, refer to “Memory trace management”

1.22 UNLOAD Command

Unload the ARBO configuration file.

```
UNLOAD
UNLOAD,DSN=*dsname*
```

The UNLOAD commands writes the contents of the ARBO file. Depending on the VIRTEL JCL, the output will be directed to the SYSPUNCH DD statement. If no SYSPUNCH DD statement is defined, one will be allocated through dynamic allocation. Output will then be written to JES class SYSOUT=B or, if the DSN= option is specified, to the dsname provided. The dataset must be pre-allocated with DCB attributes LRECL=80,RECFM=FB,BLKSIZE=3200. The SYSPUNCH DD statement will be dynamically allocated if not provided in the Virtel JCL.

1.23 VIRSV Command

Refreshing a VIRSV Service program

```
VIRSV,NEW=servname
```

servname service name

The VIRSV,NEW command requests VIRTEL to stop the requested VIRSV service. This has the effect of loading a fresh copy of the associated service program the next time the service is invoked by a scenario. The message VIR0260W SERVICE servname IS A NEW COPY indicates that the service was stopped successfully. The message VIR0261W

SERVICE servname NOT IN MEMORY indicates that the service is not yet started. In this case, VIRTEL will start the service and load the program automatically when it is next needed.

1.24 ZAP Command

The ZAP command allows dynamic patching of a Virtel Program

`ZAP=progrname+offset,verify,replace`

progrname program name

offset offset into program

verify verify value (2 to 8 hexadecimal digits)

replace replacement value (2 to 8 hexadecimal digits)

The ZAP command allows the dynamic application of a corrective patch to a program while VIRTEL is running. This command is intended to be used only under the advice of Syspertec technical support personnel.

ADMINISTRATION

2.1 Line Status Application

The Line Status sub-application allows the administrator to display the current status of lines and terminals or irtual circuits (CVC) managed by VIRTEL control, and optionally to modify the status of lines.

2.1.1 Displaying line status

The Line Status sub-application is invoked by pressing [PF9] in the Configuration Menu, by pressing [PF10] in the Sub- Application Menu, or via the Multi-Session Menu using a transaction which calls module VIR0027.

When the security subsystem is active, access to Line Status sub-application from the Configuration Menu or the Sub- Application Menu is controlled by the resource \$\$UTIL\$\$\$. When accessed by a transaction, normal transaction security rules will apply. Security management is described in chapter 5 of the VIRTEL Users Guide.

The sub-application begins by displaying the Line Status Display screen. Started lines are displayed in high-intensity or white text, stopped lines are displayed in low intensity or blue text.




Fig.1 - Line Status Display screen

STATUS OF-LINES Allows the administrator to display a subset of lines, by typing the first character of the name of each desired line into this field and pressing [Enter]. If the field is blank, all lines are displayed.

C Command input field.

Name The internal name of the line.

In The number of virtual circuits currently in use by incoming calls.

Out The number of virtual circuits currently in use by outgoing calls.

Links The number of terminals linked to the line.

Description Comments.

Seen User name.

2.1.2 Positioning the list

If the line status display occupies more than one screen, you can scroll through the list of lines by using [PF5], [PF7] and [PF8].

[PF5] return to the first page of the list.

[PF7] scroll back to previous page.

[PF8] scroll forward to next page.

2.1.3 Sending a command

To send a command to a line, place the cursor in the “C” field in front of the line name, type the command, then press [Enter]. The commands available are:

S

Starts a line. If the line is already started, VIRTEL attempts to start or restart any terminals associated with the line but not currently linked. This allows VIRTEL to recover LU's which have been deactivated and reactivated by VTAM, without stopping the line.

P

Stops a line. The LINE START and STOP commands can also be issued from the z/OS or VSE console. See “Starting and stopping a line”

To return to the configuration menu, press [PF3] or [Clear].

2.1.4 Displaying Line Usage

To display the status and line usage place the cursor on the desired line in the Line Status Display screen and press [PF12].

Security rules are the same as those which apply to the previous screen.

This sub-application begins by displaying the terminal usage for the selected line, as shown in the example below:

```
ACTIVE TERMINALS for LINE: C-HTTP ----- Applid: APPLHOLT 12:20:43
```

Prefix	: CL	Type	: TCP1	Defined	: 11	Linked	: 11
Number of occupied circuits	:	1	Number of connections	:	33		
Maximum simultaneously used	:	6	Total time connected	:	0 mn		

Terminal	User	Sends	Time	Node	Remote number	Call Data
CLVTA000	SPTHOLT	5	0 mn	REHVT000	192.168.092.047	W2H

P3=Return

P4=Next Line

P5=First Line

P7=Previous

P8=Next

Fig.2 - Line Usage Detail Display screen

ACTIVE TERMINALS for LINE Indicates the internal name of the line whose virtual circuits are being displayed.

Prefix The terminal name prefix associated with this line.

Type The line type, as defined in the line definition.

Defined The number of terminals defined for this line.

Linked The number of terminals currently linked to this line.

Number of occupied circuits The number of terminals or virtual circuits currently in use.

Number of connections The total number of calls received.

Maximum simultaneously used The maximum number of terminals or virtual circuits in use at any one time.

Total time connected The total connection time.

Terminal The terminal name (name of the virtual circuit).

User User name if signed on to VIRTEL.

Sends The number of messages sent to the terminal.

Time The connection time in minutes.

Node (for Minitel) The name of the node to which the terminal is currently connected.

Node (for HTTP lines) The relay name (3270 LU name) used to connect to the host application.

Remote number (for X25 lines) The X25 called number for an outgoing call, or the X25 calling number for an incoming call.

Remote number (for HTTP lines) The IP address of the client.

Call Data (for X25 lines) The call user data field of the call packet (for both incoming and outgoing calls).

Call Data (for HTTP lines) The external name of the transaction which represents the directory (path-name) in the URL.

If the Virtual Circuit Status Display occupies more than one screen, you can scroll through the list of terminals by using [PF7] and [PF8].

[PF7] scroll back to previous page.

[PF8] scroll forward to next page.

You can use the [PF4] and [PF5] keys to display information about the other lines under VIRTEL control. To view the terminal or Virtual Circuit Status Display screen for the following line, press [PF4]. To return to the Detail Usage Status Display screen for the first line defined in VIRTEL, press [PF5].

To return to the Lines Status Display, press [PF3]. To return to the Configuration Menu, press [Clear].

2.2 Memory Display Application

The VIRTEL memory management sub-application allows the system administrator to display VIRTEL memory utilisation in real time. The memory management sub-application is a pseudo-graphical display which shows the allocation of VIRTEL memory by function. VIRTEL manages its own memory, in order to avoid memory shortages as a result of fragmentation. The memory management display can be used by the administrator to help understand VIRTEL's memory requirements during normal operation.

To invoke the memory management sub-application, press [PA2] in the Configuration Menu to display the Sub- Application Menu, then press [PF4] in the Sub-Application Menu. The sub-application displays a screen similar to the example shown below. This screen represents the contents of the VIRTEL address space after deducting the space occupied by the VIRTEL kernel modules.

```

MEMORY BLOCKS USAGE ----- Applid: APPLHOLT 21:14:59

      System :      1609 K Data      :      1408 K Maximum :      3785 K
00000000 .....111.....
1E800000 .....6..5643257.3..53533353
1EC00000 ...6.3.....

.=Free block      1=Permanent      2=Temporary      3=Screen
4=EIB-Session     5=Tioa-Work      6=Sub-application

P3=Return         P6=1st Page      P7=Page-1      P8=Page+1

```

Fig 25. Memory display of VIRTEL address space

Each screen position represents a 2K memory block (if MEMORY=BELOW is specified in the VIRTCT), or a 64K memory block (if MEMORY=ABOVE). The address displayed at the start of each line is the virtual address represented by the first position in the line. Each free memory block is represented by a dot. Lines which consist entirely of dots are not displayed.

Permanently allocated memory blocks are represented by the following character types:

1. To avoid memory shortages as a result of fragmentation, these blocks are always allocated at the end of the VIRTEL address space.
2. Temporarily allocated memory blocks. Blocks of this type are allocated and freed by VIRTEL as required.
3. Memory blocks used by the VIRTEL Multi-Session feature to save screen images. Blocks of this type are allocated and freed by VIRTEL as required.

4. Memory blocks used for saving EIB and other session-related information. Blocks of this type are allocated and freed by VIRTEL as required.
5. Communication areas by VIRTEL sub-applications. Blocks of this type are allocated and freed by VIRTEL as required.
6. Sub-application modules loaded in the z/VSE SUBPOOL. Blocks of this type are allocated and freed by VIRTEL as required.

2.2.1 Memory display in Memory=Test mode.

If MEMORY=TEST is specified in the VIRTCT, the memory management sub-application displays its results in a different format. MEMORY=TEST mode allows support technicians to analyse memory occupation by module, as a debugging aid for possible memory shortage problems.

```

MEMORY BLOCKS USAGE ----- Applid: APPLHOLT 12:43:29

System :      1617 K  Data   :      1596 K  Maximum :      5715 K

000D48C0  VIR0009 +2860
00049040  VIR0000 +8084
00029293  VIR0009 +5318
0000B314  VIR0000 +8D30
00007538  VIR0P12 +2130
000040E8  VIR0B17 +4E3C
00003570  VIR0000 +7E16
00002300  VIR0000 +86E6
000013FF  VIR0017 +0626
00000F22  VIR0000 +3B9A
00000B98  VIR0T09 +4BF2
000009C0  VIR0000 +466C
00000820  VIR0T09 +3240
00000750  VIR0009 +550A
00000650  VIR0T09 +422A
000005C0  VIR0009 +54D8

.=Free block      1=Permanent      2=Temporary      3=Screen
4=EIB-Session     5=Tioa-Work      6=Sub-application

P3=Return        P6=1st Page      P7=Page-1      P8=Page+1

```

Fig. 26 - Memory display in MEMORY=TEST mode

Each line of the screen represents one VIRTEL module which has obtained one or more memory blocks. The first column represents the number of bytes of memory (in hexadecimal) currently allocated by the module. The first 16 modules are displayed, in descending order of memory utilisation.

Where the memory display occupies more than one screen, you can press [PF8] to view the following page, [PF7] to view the previous page, and [PF6] to go back to the first page.

To refresh the display with up-to-date information, press [Enter].

To return to the sub-application menu, press [PF3] or [Clear]

5.2 Virtual Memory Display

The Memory display feature is a memory diagnostic tool created to trap possible invalid Virtel memory free requests. Such request can lead to ABEND0C4s and other unwanted behaviour. Virtel memory requests (PRENDRE and RENDRE) are tracked in a diagnostic storage area located above the bar. The area is 1MB

in size and can contain 65536 active storage requests. An active storage request is a storage area that has been gotten (PRENDRE) and is pending a Virtel storage release (RENDRE).

Note: This diagnostic tool should only be used when recommended by Technical Support.

2.2.2 Memory trace management

Activating the memory trace

A memory trace can be activated using a command or from the VIRTCT. In both case, VIRTEL records an history of memory allocations that appears in a SNAP listing. A memory trace can be activated by using the following command

```
MEMTRACE
```

The will produce the following response:

```
VIR0200I MEMTRACE
VIR0214I MEMORY TRACE STARTED
VIR0218I MEMORY TRACE FOUND 00000000 BLOCKS USING 0000000000000000 BYTES (00000000
↔MEGS)
```

Resetting the memory trace

A memory trace can be reseted by using the following command:-

```
MEMTRACE,Clear
```

The trace is stopped, memory blocks used by the memory trace are released, the trace is restarted.

```
VIR0200I MEMTRACE,CLEAR
VIR0218I MEMORY TRACE FOUND 00000011 BLOCKS USING 0000000000053344 BYTES (00000000
↔MEGS)
VIR0216I CLEARING MEMORY TRACE
VIR0217I MEMORY TRACE CLEARED
VIR0214I MEMORY TRACE STARTED
VIR0218I MEMORY TRACE FOUND 00000000 BLOCKS USING 0000000000000000 BYTES (00000000
↔MEGS)
```

Stopping the memory trace

A memory trace can be stopped by using the following command:-

```
NOMEMTRACE
```

The trace is stopped, memory blocks used by the memory trace are released.

Setting Memory Trace in the VIRTCT

A memory trace can be activated from the VIRTCT by using MEMORY=TEST or MEMORY=(ABOVE,TRACE) parameter. In such case, there is no message VIR0218I display in the log, but only the benefit of recording the history of memory allocations is kept in the SNAP.

Since it is not possible to stop a trace initialized in this way, it is best to only use this method to perform an analysis of the memory allocation during the startup phase. Once a memory trace activated, issuing a SNAP command produce a report of the memory allocations history in the SNAP listing.

HTTP-CLI	041D	1EC57B68	9E987856	VIR0017	+0626	8040	STILL	HERE	0958379151	030013FF	1EA98300
CLLOC009	041A	1EAF4448	9E992E12	VIR0B17	+9962	8040	STILL	HERE	095837842	0400017F	1EA980E0
HTTP-CLI	041B	1EB1E708	9E9F41F0	VIR0T09	+3240	8040	STILL	HERE	095837286	02000208	1EA98280
HTTP-CLI	0416	1EB148B8	8002F470	VIR0009	+54D8	8040	STILL	HERE	0958377263	02000170	1EA98180
HTTP-CLI	0416	1EB4E1E0	8002F2B0	VIR0009	+5318	8040	STILL	HERE	0958377202	05005E15	1EA98340
HTTP-CLI	0418	1EB150A8	9E9F41F0	VIR0T09	+3240	8040	STILL	HERE	0958377098	02000208	1EA98240
CLVTA000	0419	1EC40F70	9E9A221C	VIR0V12	+2D34	8040	STILL	HERE	0958377089	06000024	1EA99FC0
CLVTA000	0419	1EC40FA0	9E9A221C	VIR0V12	+2D34	8040	STILL	HERE	0958377088	06000025	1EA99FE0
CLVTA000	0419	1EC40FD0	9E9A221C	VIR0V12	+2D34	8040	STILL	HERE	0958377088	0600001C	1EA98F20
CLVTA000	0419	1EB37520	9E9928B4	VIR0B17	+5404	8040	STILL	HERE	0958377078	07000078	1EA98F80
CLVTA000	0419	1EC40FF8	9E9A221C	VIR0V12	+2D34	8040	STILL	HERE	0958377077	06000022	1EA98FA0
CLVTA000	0419	1EB375A0	9E9928B4	VIR0B17	+5404	8040	STILL	HERE	0958377074	07000078	1EA98FC0
CLVTA000	0419	1EC41028	9E9A221C	VIR0V12	+2D34	8040	STILL	HERE	0958377073	06000022	1EA98FE0
CLVTA000	0419	1EB37620	9E9928B4	VIR0B17	+5404	8040	STILL	HERE	0958377069	07000078	1EA98E60
CLVTA000	0419	1EC41058	9E9A221C	VIR0V12	+2D34	8040	STILL	HERE	0958377069	06000022	1EA98E80
CLVTA000	0419	1EB376A0	9E9928B4	VIR0B17	+5404	8040	STILL	HERE	0958377066	07000078	1EA98EA0
CLVTA000	0419	1EC41088	9E9A221C	VIR0V12	+2D34	8040	STILL	HERE	0958377065	06000022	1EA98EC0
CLVTA000	0419	1EB37720	9E9928B4	VIR0B17	+5404	8040	STILL	HERE	0958377059	07000078	1EA98EE0
CLVTA000	0419	1EC410B8	9E9A221C	VIR0V12	+2D34	8040	STILL	HERE	0958377049	06000022	1EA98F00
CLVTA000	0419	1EC410E8	9E9A221C	VIR0V12	+2D34	8040	STILL	HERE	0958377018	06000038	1EA984A0
CLVTA000	0419	1EB377A0	9E9928B4	VIR0B17	+5404	8040	STILL	HERE	0958377016	07000040	1EA98520
HTTP-CLI	0417	1EB1EE28	8002F470	VIR0009	+54D8	8040	STILL	HERE	0958376950	02000170	1EA980A0
HTTP-CLI	0417	1EC0E1E0	8002F2B0	VIR0009	+5318	8040	STILL	HERE	0958376871	05005E15	1EA983C0
CLLOC009	0414	1EC41128	9E991F26	VIR0B17	+4A76	8040	STILL	HERE	0958375933	0600007C	1EA98320
CLLOC008	0409	1EC411B0	9E991F26	VIR0B17	+4A76	8040	STILL	HERE	0958372003	0600007C	1EA98400
CLLOC009	03FD	1EC41238	9E991F26	VIR0B17	+4A76	8040	STILL	HERE	0958371250	0600007C	1EA982A0
HTTP-CLI	0406	1EB14D20	9E9F41F0	VIR0T09	+3240	8040	STILL	HERE	0958371147	02000208	1EA98060
HTTP-CLI	0404	1EB1EFA0	9E9F41F0	VIR0T09	+3240	8040	STILL	HERE	0958371144	02000208	1EA98120
HTTP-CLI	0402	1EB1F1B0	9E9F41F0	VIR0T09	+3240	8040	STILL	HERE	0958371138	02000208	1EA98260
HTTP-CLI	0405	1EB14A30	8002F470	VIR0009	+54D8	8040	STILL	HERE	0958371123	02000170	1EA98080
HTTP-CLI	0405	1EB883C0	8002F2B0	VIR0009	+5318	8040	STILL	HERE	0958371068	05005E15	1EA98580
HTTP-CLI	0403	1EB14BA8	8002F470	VIR0009	+54D8	8040	STILL	HERE	0958370961	02000170	1EA98140
HTTP-CLI	0403	1EB783C0	8002F2B0	VIR0009	+5318	8040	STILL	HERE	0958370905	05005E15	1EA985A0
HTTP-CLI	03F8	1EB1FC00	8002F470	VIR0009	+54D8	8040	STILL	HERE	0958370840	02000170	1EA98020
HTTP-CLI	03F8	1EAD01E0	8002F2B0	VIR0009	+5318	8040	STILL	HERE	0958370791	05005E15	1EA985C0
CLLOC005	03F8	1EC412C0	9E991F26	VIR0B17	+4A76	8040	STILL	HERE	0958370790	0600007C	1EA985E0
CLVTA000	03EA	1EB377E8	9E9928B4	VIR0B17	+5404	8040	STILL	HERE	0958367657	07000040	1EA981E0
CLVTA000	03EB	1EAF42D0	8002B7F2	VIR0009	+185A	8040	STILL	HERE	0958367418	040000A8	1EA98160
CLVTA000	03EA	1EC413E0	9E96BE32	VIR0010	+0212	8040	STILL	HERE	0958366922	06000158	1EA981A0
CLVTA000	03EA	1EB87F50	9E9A98A8	VIR0S12	+0BC0	8040	STILL	HERE	0958366920	0500022A	1EA980C0
CLVTA000	03E9	1EAF4380	8002F4A2	VIR0009	+550A	8040	STILL	HERE	0958366920	04000270	1EA98080
CLVTA000	03E9	1EAF45E0	8002F4A2	VIR0017	+0626	8040	STILL	HERE	0958366913	0400017F	1EA98100

Example of a memory allocation history

Column Explanations

1. Line or terminal name for which memory allocation is performed. This information is omitted when the allocation relates VIRTEL itself.
2. Task number behind the allocation request.
3. Register 14 value.
4. Register 15 value.
5. Program name + offset of the origin request.
6. Memory allocation type. (8040 = GETMAIN).
7. Memory block state.
8. Time of the allocation.
9. Type and size of the allocation. The two first bytes represents the type of memory allocated (See “Memory display of VIRTEL address space” for a complete description of the memory block type.). The six last bytes represents the size of the memory block allocated.
10. Reserved for internal use.


Tracing memory activity can produce an important overhead estimated to 20-30% of the activity. When using MEMTRACE command, the memory previously allocated to records history is released.

2.3 Maintenance

Maintenance is normally delivered through email or by downloading a maintenance package from the Virtel ftp web server - <http://ftp-group.syspertec.com/login/>. Maintenance comes as either zaps to the Virtel mainframe modules or updates to the web elements. Application of the mainframe zaps is through the IBM Utility AMASPZAP. The updates to the web elements is through a Virtel GUI Drag and Drop interface or via a Virtel Batch process. This is found in the Administration Portal of Virtel. The Drag and Drop interface is described in section 1.6.2 in the Virtel User Guide.

2.3.1 Applying z/OS maintenance.

By default, maintenance to the z/OS components of Virtel is delivered as AMASPZAP control statements either delivered as an email attachment or downloaded from the Syspertec ftp web server. The mainframe zap packages come as an accumulation file called either *allptfs-mshpvr.txt* (z/VSE) or *allptfs-mvsvr.txt* (z/OS).




Syspertec ftp web server

Once downloaded and unzipped, the zap package will contain a sequential text file of AMASPZAP statements. These should be uploaded to the Virtel CNTL file as PTFvrrMV. The JOB ZAPJCL, also located in the CNTL file, should then be submitted to apply the zaps contained in the PTFvrrMV file. As the PTFvrrMV is an accumulation of PTFs some editing will have to be done to remove zaps that have already been applied. Virtel will report the zap maintenance level when it starts up.

```
VIR0018I VIRTEL 4.61 HAS THE FOLLOWING PTF(S) APPLIED
VIR0018I 5530,5540,5549,5557,5559,5567
VIR0089I VIRTEL RUNNING FROM AN AUTHORIZED LIBRARY
```


2.3.2 Applying maintenance to the TRSF files

The updates to the web entities are delivered as an accumulation update file called *virtelvrrupdtnnnn1.zip* where nnnn is the update number. These update files can be downloaded from the Syspertec ftp web server. Applying updates to the web elements is through a manual drap and drop GUI or via a batch process. Download the update package and unzip the contents. A directory structure representing the Virtel SAMPTRSF directories will be built. Note, not all of the directories are shipped with an update package, only those that have maintenance will be shipped. Normally, the W2H-DIR contains the majority of web element updates. The Administration portal is used to upload the updates to the Virtel directories. After applying the updates to the Virtel directories refresh the browsers cache to force an update of the client web elements.




Unzipped update file

In the above example, the update file contains updates to the W2H and DOC directories. The members in each directory should be selected (CTRL-A) and dragged over to the “Drag and Drop” upload option of the Virtel Administration portal, normally setup on port 41001.



Virtel Administration Portal

Open the “Drag and Drop” interface in Virtel, and then drag the files over on to the relevant directory in the upload interface. An upload window will open showing the results of the upload.



Virtel Drag and Drop Interface

2.3.3 Applying maintenance via batch.

A batch maintenance package called `virtelrvvVMPnnnn.zip` can also be used to apply maintenance to the `SAMPTRSF` file. Using the batch process doesn't require any manual process, it runs as a batch job on the mainframe. However, the target Virtel instance cannot be running at the same time. The process for applying a Virtel Maintenance Package is outlined in the Virtel Technical newsletter "TN201709 Virtel batch maintenance". This can be viewed online at <http://virtel.readthedocs.io/en/latest/manuals/newsletters/TN201709/TN201709.html>

2.4 Correspondent Management

One of the methods which VIRTEL may use to identify users is by means of a security code which the user presents to VIRTEL, either in an incoming e-mail, or by means of a “cookie” included in an HTTP request by the browser. A user which VIRTEL recognizes in this way is known as a “Correspondent”. VIRTEL stores the list of correspondents in a VSAM file known as the “Correspondent file”, also known as the “VIRHTML” file.

VIRTEL uses the correspondent file for the following purposes: - the rules of an HTTP line permit VIRTEL to distinguish between correspondents and non-correspondents when processing incoming HTTP requests. When the requesting user is identified as a correspondent, a special entry point may be assigned, or a set of rules specific to the user may be executed. Refer to “Rules” in the VIRTEL Connectivity Reference manual for further details. - the rules of an HTTP line may assign a specific LU name to a correspondent connecting to a host application via web access. This is known as “LU nailing” and is described in more detail in the VIRTEL LU Nailing HOWTO manual. - a correspondent may be authorized to upload HTML pages and other elements into an HTMLTRSF file. For further details, refer to *“Uploading pages by SMTP”* and *“Uploading pages by HTTP (secured by cookie)”*.

There are two types of correspondent: an e-mail correspondent and a local correspondent: - An **e-mail correspondent** is always defined by the VIRTEL administrator. When the administrator activates an email correspondent, VIRTEL sends an e-mail message to the correspondent containing the security code. The correspondent then either replies to the e-mail message or clicks on a link in the message to connect to VIRTEL. - A **local correspondent** is activated by the correspondent using a procedure known as “self-registration”. The self-registration procedure creates a clickable link which delivers the security code to the correspondent’s browser via a cookie. The VIRTEL administrator may optionally pre-define or change the characteristics of a correspondent by using the correspondent management sub-application. Self-registration is described in the VIRTEL LU Nailing HOWTO manual.

2.4.1 Access to the application

The correspondent management sub-application, which allows the VIRTEL administrator to define the parameters associated with a correspondent, is accessible by pressing [PF5] in the VIRTEL configuration menu, or [PF12] in the system services sub-application menu, or from the VIRTEL Multi-Session screen via an application referencing the module VIR0041A.

2.4.2 Security

When security is active, access to the correspondent management sub-application from the configuration menu or from the system services sub-application menu is controlled by the resource \$\$PCPC\$\$\$. When it is accessed by a transaction, the rules of security management of transactions will apply. Security management is described under the heading “Security” 282.

2.4.3 Objectives

This sub-application initially displays a summary screen of existing definitions presented in alphanumeric order. Access to the detail of a correspondent is achieved by positioning the cursor and pressing [PF12].

LIST of CORRESPONDENTS ----- Applid: APPLHOLT 23:42:54				
Id	Rules	VTAM name	Last connection	Contacts
holt@sypertec.com	TESTRULE	REHVT001		00000000
<div> <div>P1=Update</div> <div>P2=Delete</div> <div>P3=Return</div> <div>P6=Rules</div> <div>P7=Previous</div> <div>P8=Next</div> <div>P12=Edit/View</div> </div>				

Summary of correspondence

```

CORRESPONDENT DETAIL DEFINITION ----- Applid: APPLHOLT 23:41:49

Id            ===> holt@syspertec.com
                  email address with '@' sign
Type of Id    ===> 1                1:Email 2:Local+fixed 3:Local+changing
Activation message ===> To activate your Virtel connection, click:&Rhttp://192.
68.170.33:41001/web2host.htm++&C
                  Text of 'OK' message to user.
VTAM name     ===> REHVT001         &1 parameter to specify VTAM LU name
Rule Set      ===> TESTRULE        Rules to choose an entry point
Directory     ===>                 Where data is to be uploaded
Last contact  ===>
Contacts      ===> 00000000        Number of times cookie was updated
Date created  ===> 13 Mar 2017 23:41:49
Created by    ===> SPTHOLT
Date activated ===>
Activated by  ===>
Date disabled ===>
Disabled by   ===>

P1=Update          P3=Return          Enter=Add
P4=Activate        P5=Disable         P6=Rules
CREATION OK

```

Correspondent detail screen (e-mail correspondent)

```

CORRESPONDENT DETAIL DEFINITION ----- Applid: SPVIRE2 16:40:04
Id            ===> WKSTN-A2FE/SYSPERTEC
                  workstation/lan
Type of Id    ===> 2                1:Email 2:Local+fixed 3:Local+changing
Activation message ===>
                  Text of 'OK' message to user.
VTAM name     ===> RRVTC006         &1 parameter to specify VTAM LU name
Rule Set      ===>                 Rules to choose an entry point
Directory     ===>                 Where data is to be uploaded
Last contact  ===> 30 Jun 2009 11:24:49 192.168.002.082
Contacts      ===> 00000010        Number of times cookie was updated
Date created  ===> 30 Jun 2009 10:35:30
Created by    ===> VIRDBA
Date activated ===> 30 Jun 2009 10:35:30
Activated by  ===> VIRDBA
Date disabled ===>
Disabled by   ===>

P1=Update          P3=Return          Enter=Add
P4=Activate        P5=Disable         P6=Rules

```

Correspondent detail screen (local correspondent)

2.4.4 Field Contents

Id For an e-mail correspondent: the e-mail address of the correspondent. For a local correspondent: a unique identifier generated by the self-registration procedure, or assigned by the VIRTEL administrator.

Type of Id

1. this is an e-mail correspondent
2. this is a local correspondent whose security code is generated at activation time and subsequently remains constant
3. this is a local correspondent whose security code changes each time it is accessed.

Activation message Message received by the user at time of activation of his account. This message can contain a link allowing the user to connect to a host application or to open the upload.htm page with automatic installation of an authorization cookie.

The activation message may include the following variables: &R meaning “insert a blank line”.

&C meaning “insert security code”. The activation security code is inserted into the message in the form VirtelCookie=xxx.

Rule Set (optional) The name of the rule set associated with this user.

Directory (optional) Name of the directory into which this correspondent may upload files.

Last contact Date and time of the last transfer, and the IP address of the correspondent.

Contacts The number of contacts since the last activation.

2.4.5 Account activation

In order to be operational, a correspondent account must be activated. This is achieved by pressing [PF4] at the CORRESPONDENT DETAIL DEFINITION screen. In the case of an e-mail correspondent, VIRTEL will transmit an initial email to the correspondent containing the security code to be used for the transfers. The message ACTIVATION WAS REQUESTED indicates that the correspondent’s security code has been activated, and, in the case of an e-mail correspondent, that the e-mail was sent successfully. The number of contacts is reset to zero.

Note: To activate an e-mail correspondent, the administrator must be logged on to VIRTEL via an entry point containing a transaction with external name \$MAIL\$ (application type=3) which contains, in the application field, the name of the SMTP line used by VIRTEL. The message YOU ARE NOT AUTHORISED TO USE THIS APPLICATION indicates that the \$MAIL\$ transaction is not defined.

2.4.6 Account deactivation

A correspondent’s security code may be cancelled by deactivating with the [PF5] key. The message DISABLE WAS DONE indicates that the deactivation was successful.

2.4.7 Access to associated rule set

To display the list of rules associated with this correspondent, press the [PF6] key.

2.5 Web Entity Management

Web Entity Management is concerned with maintaining the Virtel Web entities, such as HTML template pages, CSS, JavaScript elements and images etc. These can all be uploaded to the VIRTEL directories by any of the following methods:

1. by web browser (HTTP) from a PC, with signon security. Provided by Administration Portal.
2. Via a batch process from a PC.
3. by e-mail (SMTP). (Correspondence Management only)
4. by web browser (HTTP), with cookie security. (Correspondence Management only)

2.5.1 Uploading by web browser (HTTP) (secured by signon)

The upload4.htm page allows the administrator to upload HTML pages and graphics to VIRTEL. When this page is first loaded, the web browser displays a signon dialog box requesting a userid and password. The userid allows the security product (RACF, ACF2, TSS, or VIRTEL) to determine which, if any, of the page upload transactions the user is authorized to use. Each VIRTEL directory has its own upload transaction, so that upload security can be applied individually to each directory, by authorizing users to the corresponding directory's upload transaction.

2.5.2 Definitions for upload (secured by signon)

All the elements needed for page upload by HTTP secured by signon are contained in the base configuration delivered with VIRTEL. Users who upgrade from a version prior to VIRTEL 4.27 while keeping their existing configuration need to add certain elements to their existing configuration to benefit from the new "page upload secured by signon" function.

The following steps show how to upgrade your configuration based on entry point WEB2HOST. You can also carry out these steps in batch by running the DEFUPLOD job in the SAMPLIB delivered with VIRTEL. Having updated the configuration, you then need to upload one new page (upload4.htm) to the W2H-DIR directory using the existing SMTP upload method.

1. In entry point WEB2HOST, define a new transaction W2H-68 with external name dirlist, application name VIR0041S and application type 2:

```

TRANSACTION DETAIL DEFINITION ----- Applid: SPVIRSSL 18:58:18

Internal name ==> W2H-68           To associate with an entry point name
External name ==> dirlist          Name displayed on user menu
Description   ==> List of directories for page upload
Application   ==> VIR0041S         Option ==>
PassTicket    ==> 0   Name ==>    0=no 1=yes 2=unsigned
Application type ==> 2             1=VTAM 2=VIRTEL 3=SERV 4=PAGE 5=LINE
Pseudo-terminals ==> DELOC        Prefix of name of partner terminals
Logmode       ==>                Specify when LOGMODE must be changed
How started   ==> 2               1=menu 2=sub-menu 3=auto
Security      ==> 0              0=none 1=basic 2=NTLM 3=TLS 4=HTML
H4W commands ? ==>              0=no 1=yes 2=if2VIRTEL 4=auto
Logon message ==>

TIOA at logon ==>

TIOA at logoff ==>

Initial Scenario ==>              Final Scenario ==>
Input Scenario   ==>              Output Scenario ==>

P1=Update                P3=Return                P12=Server

```

Page upload by HTTP with signon : Transaction dirlist

2. Still in entry point WEB2HOST, define three new transactions W2H-71, W2H-72, W2H-73 with external names uplbas, uplw2h, and upcli. Each of these transactions specifies VIR0041C as the application name and application type 2. The "Logon message" field contains the name of the target directory: HTMLBAS for transaction uplbas, W2HDIR for transaction uplw2h, and CLI-DIR for upcli :

```

TRANSACTION DETAIL DEFINITION ----- Applid: SPVIRSSL 19:01:00

Internal name ==> W2H-71           To associate with an entry point name
External name ==> uplbas           Name displayed on user menu
Description   ==> Chargement des pages HTML (r{pertoire HTMLBAS)
Application   ==> VIR0041C         Option ==>
PassTicket    ==> 0   Name ==>    0=no 1=yes 2=unsigned
Application type ==> 2             1=VTAM 2=VIRTEL 3=SERV 4=PAGE 5=LINE
Pseudo-terminals ==> DELOC        Prefix of name of partner terminals
Logmode       ==>                Specify when LOGMODE must be changed
How started   ==> 2               1=menu 2=sub-menu 3=auto
Security      ==> 1              0=none 1=basic 2=NTLM 3=TLS 4=HTML
H4W commands ? ==>              0=no 1=yes 2=if2VIRTEL 4=auto
Logon message ==> HTMLBAS

TIOA at logon ==>

TIOA at logoff ==>

Initial Scenario ==>              Final Scenario ==>
Input Scenario   ==>              Output Scenario ==>

P1=Update                P3=Return                P12=Server

```

Page upload by HTTP with signon : Directory HTMLBAS

```
TRANSACTION DETAIL DEFINITION ----- Applid: SPVIRSSL 19:06:42

Internal name ==> W2H-72                To associate with an entry point name
External name ==> uplw2h                Name displayed on user menu
Description   ==> Chargement des pages HTML (r{pertoire W2H-DIR)
Application   ==> VIR0041C              Option ==>
PassTicket    ==> 0 Name ==>            0=no 1=yes 2=unsigned
Application type ==> 2                  1=VTAM 2=VIRTEL 3=SERV 4=PAGE 5=LINE
Pseudo-terminals ==> DELOC              Prefix of name of partner terminals
Logmode       ==>                      Specify when LOGMODE must be changed
How started   ==> 2                    1=menu 2=sub-menu 3=auto
Security      ==> 1                    0=none 1=basic 2=NTLM 3=TLS 4=HTML
H4W commands ? ==>                    0=no 1=yes 2=if2VIRTEL 4=auto
Logon message ==> W2H-DIR

TIOA at logon ==>

TIOA at logoff ==>

Initial Scenario ==>                  Final Scenario ==>
Input Scenario  ==>                  Output Scenario ==>

P1=Update                      P3=Return                      P12=Server

3,21
```

Page upload by HTTP with signon : Directory W2HDIR

```
TRANSACTION DETAIL DEFINITION ----- Applid: SPVIRSSL 19:07:44

Internal name ==> W2H-73                To associate with an entry point name
External name ==> upcli                 Name displayed on user menu
Description   ==> Chargement des pages HTML (r{pertoire CLI-DIR)
Application   ==> VIR0041C              Option ==>
PassTicket    ==> 0 Name ==>            0=no 1=yes 2=unsigned
Application type ==> 2                  1=VTAM 2=VIRTEL 3=SERV 4=PAGE 5=LINE
Pseudo-terminals ==> DELOC              Prefix of name of partner terminals
Logmode       ==>                      Specify when LOGMODE must be changed
How started   ==> 2                    1=menu 2=sub-menu 3=auto
Security      ==> 1                    0=none 1=basic 2=NTLM 3=TLS 4=HTML
H4W commands ? ==>                    0=no 1=yes 2=if2VIRTEL 4=auto
Logon message ==> CLI-DIR

TIOA at logon ==>

TIOA at logoff ==>

Initial Scenario ==>                  Final Scenario ==>
Input Scenario  ==>                  Output Scenario ==>

P1=Update                      P3=Return                      P12=Server


3,21
```

Page upload by HTTP with signon : Directory CLIDIR

3. Use your security package (VIRTEL/SECURITE, RACF, TOP SECRET, ACF2) to grant access to resources W2H-71 and HTMLBAS (for users authorized to upload pages to the HTMLBAS directory) and/or to resources W2H-72 and W2HDIR (for users authorized to upload pages to the W2H-DIR directory) and/or to resources W2H-73 and CLI-DIR (for users authorized to upload pages to the CLI-DIR directory). For more details, refer to the “VIRTEL Security Guide” manual.

2.5.3 Procedure for upload (secured by signon)


1. Display the upload4.htm page by entering the URL <http://ipaddr:port/SECURE/upload4.htm+dirlist> in your browser, or by clicking the “Upload” link on the VIRTEL Web2Host welcome page. Because the directory named SECURE is defined as a secure transaction, VIRTEL first requests the browser to display the password dialog box shown below:



Page upload by HTTP with signon : Entering the userid and password


The user must have authority to access the resource represented by the internal name of the page upload transaction for the desired directory.

2. After entering the user name and password, the upload4.htm page will be displayed:




Page upload by HTTP with signon : Displaying the upload4.htm page

3. Press the “Browse” button to display the file selection dialog:




Page upload by HTTP with signon : File selection dialog

4. Select the file you want to upload, then press the “Open” button. The name of the selected file will be displayed in the input field:



Page upload by HTTP with signon : Sending the file

5. Press the button corresponding to the target directory (W2H-DIR in this example) to upload the file to VIRTEL. VIRTEL stores the file in the chosen directory, and displays the result:



Page upload by HTTP with signon : Confirmation of file upload


Depending on the values specified in the directory definition, VIRTEL may convert the filename to upper case, and truncate the filename to a maximum length, before storing it in the directory. The filename after conversion and truncation must not duplicate any other filename in the directory. For example, when uploading to a directory defined using the default parameters (not case sensitive, with maximum filename length 8), the file `links.gif` would be stored under the name `LINKS.GI`

2.5.4 Uploading by web browser (HTTP) by GUI drag and drop

The VIRTEL administrator can upload pages to a VIRTEL directory using the drag and drop upload interface with the Firefox or Chrome browser. This method has the advantage that multiple pages can be uploaded to a VIRTEL directory (for example, W2H-DIR) in a single operation.

Upload interface in the VIRTEL menu


After clicking on the Drag & Drop Upload link on the VIRTEL Web Access menu (URL <http://n.n.n.n:41001>), the VIRTEL administrator will be presented with a signon screen, followed by the drag and drop upload interface screen shown below:



Drag and drop upload interface

The administrator can then select one or more files using the workstation graphical user interface, drag them to the upload interface screen, and drop them on the button representing the VIRTEL directory (for example, CLI-DIR). Files in zipped archive may need to be extracted to a temporary directory first.

Displaying upload results



Displaying upload results

The results of the upload are displayed on the screen with a return code for each file uploaded. Each file should produce the message RETURN CODE IS: 00. In addition, by clicking on + or -, the administrator can open and close the detail display for each file uploaded.

Upload summary report

After multiple files have been uploaded, the drag and drop upload interface will display a summary showing the number of files processed with return code 00, and, in case of error, the number of files which failed to upload nonzero return codes.

The summary is not displayed when files are dragged and dropped one at a time.

In this example, one file has failed to upload because of an invalid VIRTEL tag, and the user has clicked on the + sign to the left of the file to expand the error messages:

+	W2H-DIR STYLBLUE.css	RETURN CODE IS: 00	Fri, 29 Mar 2013 11:28:03 GMT
+	W2H-DIR js01.js	RETURN CODE IS: 00	Fri, 29 Mar 2013 11:28:05 GMT
-	W2H-DIR WEB2AJAX.htm	RETURN CODE IS: 32	Fri, 29 Mar 2013 11:28:05 GMT
DIRECTORY : <W2H-DIR > RETURN CODE IS: 32 122805 LOADING FILE: WEB2AJAX.htm 122805 SIZE : 3083 BYTES (TEXT) 122805 MIME : text/html 122805 FIELD : SET-ENCODING-UTF-8 "" 122805 ERRM124 - INVALID FIELD			
+	W2H-DIR appmenu.htm	RETURN CODE IS: 00	Fri, 29 Mar 2013 11:28:07 GMT
+	W2H-DIR WEB2HOST.htm	RETURN CODE IS: 00	Fri, 29 Mar 2013 11:28:09 GMT
5 upload requests have been processed 4 with RETURN CODE IS: 00 1 with RETURN CODE IS: 32			
© SysperTec Communication Technical support			

Upload summary report

2.5.5 Extracting upload results as an Excel spreadsheet



The Excel button allows the administrator to export the results log as a .SLK file which can be opened as an Excel spreadsheet.

Directory	File name	Report	Time
CLI-DIR	custom.css	RETURN CODE IS: 00	Thu, 13 Sep 2012 08:13:16 GMT
CLI-DIR	custom.js	RETURN CODE IS: 00	Thu, 13 Sep 2012 08:13:16 GMT



The Delete button allows the administrator to clear the results log.

2.5.6 Uploading in batch with cURL

You can upload multiple pages (or other elements) at a time from a Windows workstation by using a command-line HTTP-client program, such as cURL from www.haxx.se. The following example shows a Windows command to upload all files of type .htm from the current directory to VIRTEL:

```
for %F in (*.htm) do curl -v -F "file=@%F;type=text/html" -u  
virdba:virdbapw http://192.168.235.30:41001/SECURE/virmsg.txt+uplbas
```

In this example:

***.htm** the files to be uploaded

virdba:virdbapw userid and password for VIRTEL

192.168.235.30:41001 identifies the VIRTEL HTTP line

virmsg.txt page template for displaying upload result messages

uplbas external name of the upload transaction in VIRTEL which specifies the target directory (HTML-BAS). See *“Uploading pages by HTTP (secured by signon)”* for a list of upload transactions.

Note:

%F appears twice in the command shown above. In conformance with the syntax requirements of the Windows command interpreter, you must use %F if you execute the command from the command prompt, but %%F if you execute the command from within a command (.cmd) file.

2.5.7 Uploading in batch using the upl2virt command

For users of Windows XP and above, the command procedure upl2virt.cmd may be used to upload elements to VIRTEL from the Windows command prompt, or from Windows Explorer. upl2virt automatically generates the required cURL commands as described in the previous section.

Pre-requisites

upl2virt requires as a pre-requisite the cURL package described in the previous section.

Optionally, Bill Stewart’s editvar freeware package from www.westmesatech.com may also be installed. This package allows upl2virt to securely prompt the administrator for a password. If the editvar package is not installed, then upl2virt can still prompt for a password but it will be unable to mask the password as the administrator types it into the command window.

Installation

upl2virt may be downloaded from VIRTEL to the workstation by entering the following URL in your browser:

```
http://n.n.n.n:41001/upl2virt.cmd
```

where n.n.n.n is the IP address of VIRTEL). When prompted, save the upl2virt.cmd file in a directory in your path (for example, C:WINDOWS).

Using upl2virt at the command prompt

To execute upl2virt as a command, open a Windows command prompt, navigate to the directory which contains the file(s) to be uploaded, and execute the command:

```
upl2virt [-u userid:password] -d directory -a n.n.n.n  
        [-p port] [-r] [-f ctlfile] [-k] [file1 file2 ...]
```

In the above command:

userid:password is your VIRTEL userid and password. If not specified, upl2virt will prompt for userid and password. If userid is specified without the password, then upl2virt will prompt for password.

directory is the name of the target VIRTEL directory (for example, CLI-DIR)

n.n.n.n is the IP address of VIRTEL

port is the VIRTEL administration port number (default 41001).

Note: This is the port number for the WEB2HOST entry point, not the port number associated with the directory you are uploading to.

ctlfile specifies the name of a control file containing a list of file names to be uploaded

file1 file2 ... are the names of files to be uploaded

-r specifies recursion into subdirectories

-k keeps the command window open after the last upload

If no file names are specified, and no control file is specified, the default is to upload all web elements from the current directory (and also from all subdirectories if the **-r** option is specified).

Using upl2virt from Windows Explorer

The upl2virt command may also be used to upload elements to VIRTEL from the Windows Explorer interface. Having selected one or more files in Windows Explorer, the administrator right-clicks on the selected files and chooses the “Send To” option, then chooses “Upload to VIRTEL” from the “Send To” menu. To activate the “Upload to VIRTEL” option in the “Send To” menu, use Windows Explorer to navigate to the “c:\Documents and Settings\username\SendTo” folder, where username is your Windows username. If you cannot see the SendTo folder, then click on “Tools” – “Folder options” – “View”, tick the option “Display hidden files and folders”, and click “OK”.

In the “SendTo” folder, right click and select “New” – “Shortcut”. Then click “Browse”, navigate to the place where you stored the upl2virt.cmd file, and click on it. Click “Next” and enter a descriptive title for the menu item, such as “Upload to VIRTEL”. Then click “Finish”. You now have an item in the “SendTo” folder named “Upload to VIRTEL”. Right-click on this item and choose “Properties”. In the “Target” field you will see the path to the upl2virt.cmd file which you specified. Update this field with parameters as shown in the example below:

```
C:\WINDOWS\upl2virt.cmd -u MYUSERID -d CLI-DIR -a 10.1.12.101 -k
```

where:

MYUSERID is your VIRTEL userid

CLI-DIR is the name of the VIRTEL directory that this shortcut will upload to

10.1.12.101 is the IP address of VIRTEL.

You may omit the **-u MYUSERID** parameter and upl2virt will prompt you for your userid.

2.5.8 Uploading template pages using SMTP

Upload by SMTP allows the administrator to load HTML pages into VIRTEL by e-mail. VIRTEL sends the administrator an e-mail, and the administrator replies to this e-mail with the pages to be uploaded included as attachments. VIRTEL sends another e-mail to inform the administrator that the upload was successful. The administrator saves this e-mail and replies to it the next time he has a set of pages to upload.

Definitions for page upload by SMTP

- Check the definition of your SMTP line (F1 then F12 from the Configuration Menu, see the VIRTEL Connectivity Reference documentation).
- Press F5 from the Configuration Menu and define an e-mail correspondent specifying W2H-DIR as the directory name:

```

CORRESPONDENT DETAIL DEFINITION ----- Applid: SPVIRE2 14:19:33
Id                               ===> upload2@saint.cloud.com
                                email address with '@' sign
Type of Id                       ===> 1 1:Email 2:Local+fixed 3:Local+changing
Activation message               ===> To upload file(s) to VIRTEL, reply to this message.
                                Text of 'OK' message to user.
VTAM name                       ===> &1 parameter to specify VTAM LU name
Rule Set                        ===> ADMRSET1 Rules to choose an entry point
Directory                       ===> W2H-DIR Where data is to be uploaded
Last contact                     ===> QUEUE ACTIVATION
Contacts                        ===> 00000000 Number of times cookie was updated
Date created                     ===> 11 May 2004 14:19:29
Created by                      ===> VIRDBA
Date activated                   ===> 11 May 2004 14:19:33
Activated by                     ===> VIRDBA
Date disabled                    ===>
Disabled by                      ===>
P1=Update                       P3=Return                               Enter=Add
P4=Activate                     P5=Disable                             P6=Rules
ACTIVATION WAS REQUESTED

```

Page upload by SMTP: Creating an e-mail correspondent

Procedure for page upload by SMTP

1. Activate the e-mail correspondent: see “Account activation” under the heading “*Correspondent Management*”. This triggers the sending of an e-mail containing the security code, as in the following example:-

```

Date: Tue, 27 Apr 2004 12:04:40 +0100
From: virtel@client.com
Organization: SYSPERTEC COMMUNICATION
To: upload2@saint.cloud.com
Message-id:
<20040427120439.07F5DA7C.5E416500Bgpamk4WZRKKBiZWjs4OTlqSES4OWlA==>
Subject: OK : < W2H-DIR >
SECURITY TOKEN:
20040427120439.07F5DA7C.5E416500Bgpamk4WZRKKBiZWjs4OTlqSES4OWlA==
To upload file(s) to VIRTEL, reply to this message.

```

Page upload by SMTP : activation e-mail

2. Reply to this e-mail, with the files to be uploaded (HTML pages, graphics, etc) included as attachments. VIRTEL recognizes the security code returned automatically by the e-mail client in the “Message-id” field, and loads the attached files into the directory defined in the definition of the correspondent.
3. VIRTEL replies by sending an e-mail containing the result of the upload. The following example shows the reply sent by VIRTEL to a request to upload two files: LOGOVERT.GIF and WEB2VIRT.HTM. The “Message-id” field in this e-mail contains the new security code. You can reply to this e-mail the next time you have files to upload.

```
Date: Tue, 27 Apr 2004 12:39:14 +0100
From: virtel@client.com
Organization: SYSPERTEC COMMUNICATION
To: upload2@saint.cloud.com
Message-id:
<20040427123911.07F5CDC4.F669FC80Bgpamk4WZRKKBiZWjs4OTlqSES4OWlA==>
Subject: OK : <W2H-DIR >
VirtelCookie=
20040427123911.07F5CDC4.F669FC80Bgpamk4WZRKKBiZWjs4OTlqSES4OWlA==
RETURN CODE IS: 00
123911 MESSAGE RECEIVED
123912 LOADING FILE: LOGOVERT
123912 SIZE : 14357 BYTES (BINARY)
123912 MIME : image/jpeg
123914 LOADING FILE: WEB2VIRT
123914 SIZE : 11477 BYTES (TEXT)
123914 MIME : text/html
123914 FIELD : SET-OUTPUT-ENCODING-UTF-8 ""
123914 FIELD : COPY-FROM (1,1,43)
123914 FIELD : FIELD-WITH-CURSOR
123914 FIELD : FIELD-WITH-CURSOR
```

Page upload by SMTP : upload response e-mail

Depending on the values specified in the directory definition, VIRTEL may convert the filename to upper case, and truncate the filename to a maximum length, before storing it in the directory. The filename after conversion and truncation must not duplicate any other filename in the directory. For example, when uploading to a directory defined using the default parameters (not case sensitive, with maximum filename length 8), the file links.gif would be stored under the name LINKS.GI

2.5.9 Uploading pages by HTTP (secured by cookie)

The upload.htm page allows HTML pages or graphics to be uploaded to VIRTEL. The user’s identity is guaranteed by a cookie named VirtelRef= whose value changes after each upload. The value of the cookie is the same as the security code used for uploading by SMTP.

To upload a page, a user must:

- have a valid cookie (obtained by activation of the VIRTEL e-mail correspondent)
- click on the link contained in the e-mail, which displays the upload.htm page and loads the cookie into the browser (first time only)
- click the “Browse” button and select a file
- click the “Send” button

The VIRTEL response is displayed in the page and is similar to the response received by e-mail when uploading via SMTP.

Definitions for page upload (secured by cookie)

All the elements needed for page upload by HTTP secured by cookie are contained in the base configuration delivered with VIRTEL 4.27. Users who upgrade to VIRTEL 4.27 while keeping their existing configuration need to add certain elements to their existing configuration to benefit from the new “page upload secured by cookie” function. The following steps show how to upgrade your configuration based on entry point WEB2HOST. You can also carry out these steps in batch by running the DEFUPLOD job in the SAMPLIB delivered with VIRTEL version 4.27. Having updated the configuration, you then need to upload three new elements (upload.htm, default.js, and logo_3.gif) to the W2HDIR directory using the existing SMTP upload method.

1. In entry point WEB2HOST, define a new transaction W2H-70, with external name upload. This transaction specifies VIR0041C as the application name and application type 2. The “Logon message” field is blank to indicate to VIRTEL that the name of the target directory is to be found in the definition of the e-mail correspondent:

```
TRANSACTION DETAIL DEFINITION ----- Applid: SPVIRSSL 16:44:31

Internal name ==> W2H-70                      To associate with an entry point name
External name ==> upload                      Name displayed on user menu
Description   ==> Upload HTML pages (secured by cookie)
Application   ==> VIR0041C                    Option ==>
PassTicket    ==> 0   Name ==>                0=no 1=yes 2=unsigned
Application type ==> 2                        1=VTAM 2=VIRTEL 3=SERV 4=PAGE 5=LINE
Pseudo-terminals ==> DELOC                   Prefix of name of partner terminals
Logmode       ==>                          Specify when LOGMODE must be changed
How started   ==> 2                          1=menu 2=sub-menu 3=auto
Security      ==> 0                          0=none 1=basic 2=NTLM 3=TLS 4=HTML
H4W commands ? ==>                          0=no 1=yes 2=if2VIRTEL 4=auto
Logon message ==>

TIOA at logon ==>

TIOA at logoff ==>

Initial Scenario ==>                        Final Scenario ==>
Input Scenario   ==>                        Output Scenario ==>

P1=Update                P3=Return                P12=Server
```

Page upload by HTTP with cookie : Creating the ‘upload’ transaction

2. Check the definition of your SMTP line (F1 then F12 from the Configuration Menu, see the VIRTEL Connectivity Reference documentation).
3. Press F5 from the Configuration Menu and define an e-mail correspondent specifying directory name W2H-DIR and ruleset name ADMRSET1 :

```
CORRESPONDENT DETAIL DEFINITION ----- Applid: SPVIRE2 14:39:04
e-mail address ==> upload2@saint.cloud.com
                  email address with '@' sign
Type of Id       ==> 1                      1:Email 2:Local+fixed 3:Local+changing
Activation message ==> To upload to VIRTEL, click:&Rhttp://192.168.229.20:4100
1/web2host/upload.htm+upload+&C
                  Text of 'OK' message to user.
```

(continues on next page)

(continued from previous page)

```

VTAM name      ===> &1 parameter to specify VTAM LU name
Rule Set       ===> ADMRSET1 Rules to choose an entry point
Directory      ===> W2H-DIR Where data is to be uploaded
Last contact   ===>
Contacts       ===> 00000000 Number of times cookie was updated
Date created   ===> 11 May 2004 14:19:29
Created by     ===> VIRDBA
Date activated ===> 11 May 2004 14:39:04
Activated by   ===> VIRDBA
Date disabled  ===>
Disabled by    ===>

P1=Update      P3=Return      Enter=Add
P4=Activate    P5=Disable     P6=Rules
ACTIVATION WAS REQUESTED

```

Page upload by HTTP with cookie : Creating the e-mail correspondent

4. Press F6 then F12 to create rule UPLOAD1B in ruleset ADMRSET1 :

```

DETAIL of RULE from RULE SET: ADMRSET1 ----- Applid: SPVIRE2 14:40:59

Name          ===> UPLOAD1B          Rule priority is per name
Status        ===> ACTIVE            Mon, 24 Sep 2001 14:19:14
Description    ===> Rule for WEB2HOST administrator
Entry point   ===> WEB2HOST          Target Entry Point
Parameter     ===>                  optional &1 value
Trace ===>                               1=commands 2=data 3=partner

C : 0=IGNORE 1=IS 2=IS NOT 3=STARTS WITH 4=DOES NOT 5=ENDS WITH 6=DOES NOT
0 IP Subnet   ===>                  Mask      ===>
5 HTTP Host   ===> :41001
0 eMail       ===>
0 Calling DTE ===>                  Calling DTE address
0 Called      ===>                  Called DTE address
0 CUD0 (Hex)  ===>                  First 4 bytes of CUD (X25 protocol)
0 User Data   ===>
0 Days        ===> M:      T:      W:      T:      F:      S:      S:
0 Start time  ===> H:      M:      S:      End time ===> H:      M:      S:

P1=Update      P3=Return      Enter=Add
P4=Activate    P5=Inactivate  P12=Entry P.

```

Page upload by HTTP with cookie : Creating rule UPLOAD1B

5. Define two new rules attached to the HTTP line. The first rule, which specifies \$COOKIE\$ as the entry point name, will be used for administrators; the second rule, which specifies entry point WEB2HOST, is for all other users:

```

LIST of RULES in RULE SET: W-HTTP ----- Applid: SPVIRE2      14:44:14

Name      Status   Description                                     Entry
Point
WHT00100 ACTIVE    HTTP access (users authorised by cookie)      $COOKIE$
WHT00200 ACTIVE    HTTP access (other users)                     WEB2HOST

```

(continues on next page)

(continued from previous page)

P1=Update	P2=Suppress	P3=Return	
P6=1st page	P7=Page-1	P8=Page+1	P12=Edit

List of rules associated with UPLOAD

```

DETAIL of RULE from RULE SET: W-HTTP ----- Applid: SPVIRE2 14:45:34
Name          ===> WHT00100                Rule priority is per name
Status        ===> ACTIVE                   Mon, 24 Sep 2001 14:19:14
Description    ===> HTTP access (users authorised by cookie)
Entry point    ===> $COOKIE$                Target Entry Point
Parameter      ===>                        optional &l value
Trace          ===>                        1=commands 2=data 3=partner
C : 0=IGNORE 1=IS 2=IS NOT 3=STARTS WITH 4=DOES NOT 5=ENDS WITH 6=DOES NOT
0 IP Subnet    ===>                        Mask ===>
0 HTTP Host    ===>
0 eMail        ===>
0 Calling DTE  ===>                        Calling DTE address
0 Called       ===>                        Called DTE address
0 CUD0 (Hex)   ===>                        First 4 bytes of CUD (X25 protocol)
0 User Data    ===>
0 Days         ===> M:          T:          W:          T:          F:          S:          S:
0 Start time   ===> H:          M:          S:          End time ===> H:          M:          S:

P1=Update          P3=Return          Enter=Add
P4=Activate        P5=Inactivate      P12=Entry P.

```

Page upload by HTTP with cookie : Rule \$COOKIE\$ of the HTTP line

DETAIL of RULE from RULE SET: W-HTTP ----- Applid: SPVIRE2 14:45:34									
Name	===>	WHT00200		Rule priority		is per name			
Status	===>	ACTIVE		Mon, 24 Sep 2001 14:19:14					
Description	===>	HTTP a							
ccess (users authorised by cookie)									
Entry point	===>	WEB2HOST		Target Entry Point					
Parameter	===>	optional &l value							
Trace	===>	1=commands 2=data 3=partner							
C : 0=IGNORE 1=IS 2=IS NOT 3=STARTS WITH 4=DOES NOT 5=ENDS WITH 6=DOES NOT									
0 IP Subnet	===>	Mask ===>							
0 HTTP Host	===>								
0 eMail	===>								
0 Calling DTE	===>	Calling DTE address							
0 Called	===>	Called DTE address							
0 CUD0 (Hex)	===>	First 4 bytes of CUD (X25 protocol)							
0 User Data	===>								
0 Days	===>	M:	T:	W:	T:	F:	S:	S:	
0 Start time	===>	H:	M:	S:	End time	===>	H:	M:	S:
P1=Update				P3=Return				Enter=Add	
P4=Activate				P5=Inactivate				P12=Entry P.	

*Page upload by HTTP with cookie : Rule WEB2HOST of the HTTP line***Procedure for page upload (secured by cookie)**

1. (First time only) Activate the e-mail correspondent: see "[Account activation](#)". This triggers the sending of an e-mail containing the security code, as in the following example:


```

Date: Tue, 27 Apr 2004 13:08:44 +0100
From: virtel@client.com
Organization: SYSPERTEC COMMUNICATION
To: upload2@saint.cloud.com
Message-id:
<20040427130843.07F5D1DC.56A85680Bgpamk4WZRKKBiZWjs4OTlqSES4OWlA==>
Subject: OK : < W2H-DIR >
SECURITY TOKEN:
20040427130843.07F5D1DC.56A85680Bgpamk4WZRKKBiZWjs4OTlqSES4OWlA==
To upload to VIRTEL, click:
http://192.168.229.20:41001/web2host/upload.htm+upload+VirtelCookie=20040
427130843.07F5D1DC.56A85680Bgpamk4WZRKKBiZWjs4OTlqSES4OWlA==

```


Page upload by HTTP with cookie : activation e-mail

2. Click the link in the e-mail to open the upload.htm page:




Page upload by HTTP with cookie : Displaying the upload.htm page

3. Click the “Browse” button and the file selection dialog will be displayed:




Page upload by HTTP with cookie : File selection dialog

4. Select the file you want to upload, then press the “Open” button. The name of the selected file will be displayed in the input field:



Page upload by HTTP with cookie : Sending the file

- Press the “Send File” button to upload the file to VIRTEL. VIRTEL stores the file in the directory (W2H-DIR in this example) specified in the definition of the correspondent associated with the cookie. VIRTEL then displays the result of the upload:



Page upload by HTTP with cookie : Confirmation of file upload

From now on, the cookies are managed automatically. After each upload, VIRTEL sends a new cookie to the browser, as indicated by the message “Upload code was set by the remote host”.

Depending on the values specified in the directory definition, VIRTEL may convert the file name to upper case, and truncate the filename to a maximum length, before storing it in the directory. The filename after conversion and truncation must not duplicate any other filename in the directory. For example, when uploading to a directory defined using the default parameters (not case sensitive, with maximum filename length 8), the file links.gif would be stored under the name LINKS.GI

PERFORMANCE

The VIRTEL started task offers the administrator 5 sources of information to verify the correct functioning and performance of VIRTEL, to monitor its activity, or to diagnose possible problems:

- the CONSOLE file
- the VIRLOG file
- the VIRTEL Logger
- the TRACE in the VIRTRACE file
- the SNAP in the SYSPRINT file

3.1 CONSOLE file

In **z/OS environment**, the CONSOLE file is written to the VIRTEL started task's JESMSG LG file.

In **VSE environment**, the CONSOLE file is written to the VIRTEL partition's POWER LST file (LIST-LOG)

The CONSOLE file allows the administrator to monitor the startup and subsequent activity of VIRTEL. Using the console file, the administrator can check that the VSAM files are correctly opened, verify that the customer key has been correctly recognized, check the initialization of the TCP/IP sockets interface using the correct IP address and port, and monitor connections and disconnections of terminals and applications.

Note: The SILENCE=YES parameter in the VIRTCT allows the suppression of certain console messages relating to the connection and disconnection of terminals.

```

JES2 JOB LOG -- SYSTEM MVS1 -- NODE N1
4.12.57 JOB04749 ---- SATURDAY, 03 JUN 2017 ----
4.12.57 JOB04749 IRR010I USERID SPTHOLT IS ASSIGNED TO THIS JOB.
4.12.57 JOB04749 ICH70001I SPTHOLT LAST ACCESS AT 14:11:09 ON SATURDAY, JUNE 3, 2017
4.12.57 JOB04749 £HASP373 SPTHOLTN STARTED - INIT 1 - CLASS A - SYS MVS1
4.12.57 JOB04749 IEF403I SPTHOLTN - STARTED - TIME=14.12.57
4.12.58 JOB04749 VIR6004I ATTACH VIRSV SUCCESSFUL TCB=008D6728 PROG=VSVTINIT
4.12.58 JOB04749 VSV0207I VIRSV V3R3 STARTED
4.12.59 JOB04749 VIR6006I INITIALIZE VIRSV SUCCESSFUL
4.12.59 JOB04749 VIR6012I ATTACH VIRTEL SUCCESSFUL TCB=008BB6E0 PROG=VIR6001
4.12.59 JOB04749 VIR0096I VIRTEL IS USING VIRTCT 'VIRTCTHP'
4.12.59 JOB04749 VIR0000I STARTING LICENCE CP00286465-VWA-L02052017 (2017 - 07 - 15)
4.12.59 JOB04749 VIR0018I VIRTEL 4.56 HAS THE FOLLOWING PTF(S) APPLIED
4.12.59 JOB04749 VIR0018I 5440,5470,5478,5499,5505,5505A
4.12.59 JOB04749 VIR0089I VIRTEL RUNNING FROM AN AUTHORIZED LIBRARY
4.12.59 JOB04749 VIR0860I VIRTEL IS USING RACROUTE SECURITY
4.12.59 JOB04749 VIR0861I MIXED-CASE PASSWORD SUPPORT IS ACTIVE
4.13.00 JOB04749 VIR0024I OPENING FILE VIRARBO
4.13.00 JOB04749 VIR0024I OPENING FILE VIRSWAP
4.13.01 JOB04749 VIR0024I OPENING FILE VIRHTML
4.13.01 JOB04749 VIR0024I OPENING FILE SAMPTRSF
4.13.01 JOB04749 VIR0024I OPENING FILE HTMLTRSF
4.13.02 JOB04749 VIR0024I ATTACHING SUBTASKS
4.13.02 JOB04749 VIR0235I VIRTEL LOG ROUTINE VIR0002A LOADED
4.13.03 JOB04749 VIR0024I READING VIRARBO
4.13.03 JOB04749 VIR0089W HOST IPADDR. OVERRIDDEN FROM PARM WITH IP=192.168.170.033
4.13.14 JOB04749 VIR0000I THIS COPY OF VIRTEL IS FOR THE EXCLUSIVE USE OF:

```

Fig. 4 Example of CONSOLE file

3.2 VIRLOG file

This is a printable file with record length 131 and record format FA which provides a record of IP connections to VIRTEL. The figure below shows an example of VIRLOG entries for incoming HTTP calls:

```

£Software: VIRTEL 4.32
£Date: 02/01/06
£Line Local Pseudo Started Ended Price Received Sent Remote Address User
W-HTTP WHT00200 DELOC003 I 15.34.53 15.34.53 00000007 00000381 00023135 192.168.000.
↳043 200 PUBLIC DATA.JS W2H-DIR
W-HTTP WHT00200 DELOC002 I 15.34.53 15.34.53 00000004 00000381 00010833 192.168.000.
↳043 200 PUBLIC JS01.JS W2H-DIR
W-HTTP WHT00200 DELOC003 I 15.34.53 15.34.53 00000007 00000386 00006976 192.168.000.
↳043 200 PUBLIC VIRTBBLUE W2H-DIR
W-HTTP WHT00200 DEVTA003 I 15.34.53 15.34.61 00000649 00001169 00010397 192.168.000.
↳043 PUBLIC WEB2VIRT W2H-10
W-HTTP WHT00200 DELOC002 I 15.35.02 15.35.02 00000005 00000402 00000049 192.168.000.
↳043 304 WEB2HOSTXHTML.JP W2H-DIR

```

Fig. 5 Example of VIRLOG file (HTTP)

The LINE column shows the internal name of the HTTP line. The LOCAL column shows the name of the rule selected for each call. The PSEUDO column shows the VIRTEL terminal name used.

The next column contains “I” to indicate this is an incoming call.

The STARTED and ENDED columns show the start and end time of each IP session.

The PRICE column represents the duration of the transaction in hundredths of a second. This value may be modified by exit 7.

The RECEIVED and SENT columns contain the number of bytes received from and sent to the browser. The REMOTE ADDRESS column contains the IP address of the browser.

The USER column contains the userid if the transaction is secured. The next column contains the HTTP status code (for static pages). The last three 8-byte columns represent:

- The external name of the VIRTEL transaction which represents the HTTP path name.

- The name of the HTML page.
- For static pages: The name of the VIRTEL directory containing the HTML page.
- For dynamic pages: The internal name of the HTTP transaction which was used to populate the page.

The figure below shows an example of VIRLOG entries for X25 calls:

```
£Software: VIRTEL 4.32
£Date: 11/21/07
£Line Local Pseudo Started Ended Price Received Sent Remote Address User
X001LINE 001880 X001T007 I 13.47.37 13.48.00 00002288 00000392 00000119 191334833
↳MINITEL
X001LINE G001T004 X001T000 O 13.48.30 13.48.50 00001966 00000001 00000001
↳191334833001870
X001LINE P001O001 X001T001 O 13.48.49 13.49.20 00003069 00000001 00000001 001870 PCNE1
X001LINE G001T003 X001T002 O 13.49.01 13.49.22 00002147 00000001 00000001 001870

*Fig. 6 Example of VIRLOG file (X25)*
```

The LINE column shows the internal name of the X25 line.

The LOCAL column shows the called subaddress for incoming calls, or the name of the associated AntiGATE or AntiPCNE terminal for outgoing calls.

The PSEUDO column shows the VIRTEL terminal name used.

In the next column “I” indicates an incoming call, “O” indicates an outgoing call. The STARTED and ENDED columns show the start and end time of each call.

The PRICE column represents the duration of the transaction in hundredths of a second, except for calls on Fast Connect lines, where the PRICE column contains the “X25 units sent” value supplied by NPSI. This value may also be modified by exit 7.

The RECEIVED and SENT columns contain the number of bytes received from and sent to the X25 line.

The REMOTE ADDRESS column contains the caller X25 number for incoming calls, or the called X25 number for outgoing calls.

The last column contains the PCNE call user data (if present), otherwise it contains the default entry point name for X25 calls specified by the DEFENTR parameter in the VIRTCT. For GATE calls this column is blank.

3.3 VIRTEL logger

The CONSOLE log can also be written to the system logger when LOG=LOGGER is specified in the TCT. VIR0002B is a batch program that can be run to extract the VIRTEL records from the System Logger.

The figure below shows an example of JCL to extract and format the VIRTEL LOG entries recorded in the System Logger:

```
//LOGGER PROC P=
//S01 EXEC PGM=VIR0002B, PARM='&P'
//STEPLIB DD DSN=VIRTEL.LOADLIB, DISP=SHR
//VIRLOG DD SYSOUT=*, DCB=BLKSIZE=25500
// PEND
//S01 EXEC LOGGERS, P='DELETE(>2)'
VIRLOG DCB LRECL=255, BLKSIZE=25500, RECFM=VB
```

Fig. 7 Example of JCL to extract the VIRTEL LOG from the System Logger

The available JCL parameters are:

```
                (>nnn)
COPY [-----]
        (fromdate[,todate])
                (>nnn)
DELETE [-----]
        (date)
```

The date format is yyyyddd.

3.3.1 Examples

```
COPY Copy all records
COPY(>2) Copy records older than 2 days
COPY(>0) Copy up to yesterday
DELETE(>2) Delete records older than 2 days
COPY(2015047) Copy records from 2015.047
COPY(2015047,2015048) Copy records from 2015.047 thru to 2015.048 DELETE(2015047)
→Delete records prior to 2015.047
COPY(>0),DELETE(>1) Will copy records from the previous and earlier,
and will then delete from 2 days ago leaving about 24 hours of data in the log stream.
```

Fig. 8 Example of VIRTEL LOGGERS extraction parameter

3.4 Virtel trace

All messages which pass between a terminal and a host application, or all messages received and sent on a line, can be traced to a print file.

Activation and deactivation of a trace on a terminal or a line is performed by means of the TRACE and NO-TRACE commands (see “VIRTEL commands” and “Activating and deactivating a terminal or line trace”).

Note: A terminal or line trace remains active until a corresponding NOTRACE command is issued or until the VIRTEL started task terminates.

It is also possible to trace specific incoming calls (“tracing by rule”). In this case, activation of the trace is specified in the definition of the rule which VIRTEL uses to route the incoming call. For example, a rule can be created to activate the trace for calls which originate from a specific terminal address (X25 or IP). The trace can be activated for commands and/or data packets.

Activation or deactivation of a “trace by rule” is performed via the VIRTEL on-line configuration menus, and consists of updating the “Trace” field in the rule definition, followed by pressing the F1 key. See “Rules” in the VIRTEL Connectivity Reference manual for more details.

Note: A “trace by rule” remains active as long as the “Trace” field in the rule definition is not empty. Message VIR0036W confirms the activation of the trace.

In **z/OS environment**, the trace data is written to the VIRTRACE file in the VIRTEL started task. In **VSE environment**, the trace data is written to the POWER LST file of the VIRTEL partition.

Activation and deactivation of a memory trace is performed by means of the MEMTRACE and NOMEMTRACE commands (see “Memory Trace Management”). The allocation memory is written in the SNAP file when a SNAP command is issued.

3.4.1 Contents of the trace

Line type	Contents of line trace	Contents of terminal trace or trace by rule
HTTP	All messages flowing between the VIRTEL HTTP server and client browsers	Terminal without relay: None Terminal with relay: Contents of the 3270 datastream between VIRTEL and the host application
SMTP	All messages flowing to and from the VIRTEL SMTP server	
XOT	All messages flowing between VIRTEL and the router, including the XOT headers	All X25 messages (excluding the XOT header) belonging to the specified virtual circuit.
/GATE /FASTC	Messages on the control session between the MCH LU and the CTCP (call packet and call acknowledgement)	Messages on the data session between the CVC LU and the CTCP (data packets, X25 RESET and CLEAR commands)
/PCNE	None	Data flowing between the terminal LU and the application.
APPC	N/A	Messages on the LU6.2 session
GATE FASTC	N/A	Messages on the data session between the NCP and VIRTEL.
3270	N/A	The 3270 datastream between the terminal and VIRTEL, and the 3270 datastream between the terminal and the host application.

Continued on next page

Table 3.1 – continued from previous page

Line type	Contents of line trace	Contents of terminal trace or trace by rule
PCNE (Minitel)	N/A	The Vidéotex datastream between the terminal and VIRTEL, and the 3270 datastream between VIRTEL and the host application.

3.4.2 Trace Examples

```

LCL712 11A: from application SPCICST 13:05:47.48
00000 F1C2 *1B * 099A95B4
LCL712 11A: from application SPCICST 13:05:47.49
00000 F5C2114B E9131140 5B290242 F1C0F8E2 89879596 9540A396 40C3C9C3 E24011C1 *5B..Z..
→$....lê8Signon to CICS .A* 099A95B4
00020 40290242 F4C0F0C1 D7D7D3C9 C4290242 F5C0F0E2 D7C3C9C3 E2E34011 C8F02902 * ...
→4ê0APPLID...5ê0SPCICST .H0..* 099A95D4
00040 42F4C0F0 E3A89785 40A896A4 9940A4A2 85998984 40819584 409781A2 A2A69699 *.
→4ê0Type your userid and passwor* 099A95F4
00060 846B40A3 88859540 979985A2 A240C5D5 E3C5D97A 114BD929 0242F4C0 F0E4A285 *d, then
→press ENTER:..R...4ê0Use* 099A9614
00080 99898440 4B404B40 4B404B29 0241F442 F5114BF1 1DF0114B F4290242 F4C0F0C7 *rid . .
→. ....4.5..1.0..4...4ê0G* 099A9634
000A0 9996A497 8984404B 404B404B 290241F4 42F5114C 4B1DF011 4CE92902 42F4C0F0 *roupid
→. . ....4.5.<..0.<Z...4ê0* 099A9654
000C0 D781A2A2 A6969984 404B404B 404B2903 41F442F5 C04C114D C11DF011 4DF92902
→*Password . . ....4.5ê<.(A.0.(9...* 099A9674
000E0 42F4C0F0 D3819587 A4818785 404B404B 404B2902 41F442F5 114E4C1D F01150D5 *.
→4ê0Language . . ....4.5.+<.0.&N* 099A9694
00100 290242F4 C0F0D585 A640D781 A2A2A696 9984404B 404B404B 290341F4 42F5C04C *...
→4ê0New Password . . ....4.5ê<* 099A96B4
00120 1150F11D F0115A50 1D7C115B 5B1DF011 5B602902 42F2C0F8 C4C6C8C3 C5F3F5F2 *.&1.0.&
→.to.$$.0.$-...2ê8DFHCE352* 099A96D4

```

Example of terminal trace (inbound 3270 terminal)

```

X001T007 XOT: RECEIVED FROM ROUTER 13:48:15.57
00000 00000003 100121 * ....
→ * 0989117C
X001T007 XOT: RECEIVED FROM ROUTER 13:48:15.72
00000 00000083 10013200 A0402000 D9030853 59535843 46544104 08535953 58434654 *.....
→.to ....SYSXCFTA..SYSXCFT* 0989117C
00020 42050653 59535041 53060102 07030024 02160102 17010163 6E434654 20593D4D *B..
→SYSPAS.....$......cnCFT Y=M* 0989119C
00040 2C443D32 30303530 31303531 33343831 3536302C 563D3233 302C5A3D 702D312D *,
→D=2005010513481560,V=230,Z=p-1-* 098911BC
00060 31352D2D 4D565332 3230432D 41323330 3033352D 32303031 2F31302F 32322C4B *15--
→MVS220C-A230035-2001/10/22,K* 098911DC
00080 3D514334 443248 *=QC4D2H
→ * 098911FC
X001T007 XOT: SENT TO ROUTER 13:48:15.72
00000 00000003 100141 * ....
→ * 0989117C

```

(continues on next page)

(continued from previous page)

```
X001T007 XOT: RECEIVED FROM ROUTER 13:48:15.72
00000 00000023 1001245A 56444850 37444C4E 39374A49 36513153 49594C2C 433D3830 *...£..
↳ $ZVDHP7DLN97JI6Q1SIYL,C=80* 0989117C
00020 33333430 333832 *3340382
↳ * 0989119C
X001T007 XOT: SENT TO ROUTER 13:48:15.73
00000 00000003 100161
```

Example of line trace (XOT line)

```
X001T007 005: INBOUND CALL PACKET 15:10:11.97
00000 0BF00806 0018800A 42070743 030302CC 0300C018 80105043 4E4531 *
↳ .....B..C.....PCNE1 * 09896176
X001T007 XOT: OUTBOUND X25 COMMAND 15:10:11.99
00000 0F *
↳ * 0989617E
X001T007 XOT: INBOUND DATA 15:10:12.08
00000 00C3C6E3 D7E2C9E3 E7C3D7C1 E7F14040 40D7D8D9 E2404040 400D25 *
↳ CFTPSITXCPAX1 PQRS .. * 09891182
P001I001 AP80LU51 I09: DATA TO CFTBACB1 15:10:12.21
00000 C3C6E3D7 E2C9E3E7 C3D7C1E7 F1404040 D7D8D9E2 40404040 0D25
↳ *CFTPSITXCPAX1 PQRS .. * 0989617D
P001I001 AP80LU51 I09: DATA FROM CFTBACB1 15:10:12.23
00000 C1C3D2F0 0D25
↳ *ACK0.. * 0989617C
X001T007 XOT: OUTBOUND DATA 15:10:12.23
00000 00C1C3D2 F00D25 *
↳ ACK0.. * 098A417C
X001T007 XOT: INBOUND DATA 15:10:12.46
00000 22003240 2000D903 0D4F5020 20202020 20435041 5831040D 4F502020 20202020 *
↳ ".to ....OP CPAX1..OP * 09891182
00020 43504258 31060101 07030024 02160100 170101
↳ *CPBX1.....$.***** * 098911A2
P001I001 AP80LU51 I09: DATA TO CFTBACB1 15:10:12.47
00000 00324020 00D9030D 4F502020 20202020 43504158 31040D4F 50202020 20202043 *
↳ to ....OP CPAX1..OP C * 098A417D
00020 50425831 06010107 03002402 16010017 0101
↳ *PBX1.....$.***** * 098A419D
P001I001 AP80LU51 I09: DATA FROM CFTBACB1 15:10:12.55
00000 00114021 D9E20601 01070300 24021701 01 *
↳ .RS..... * 0989617C
```

Example of “trace by rule” (XOT terminal to application on /PCNE line)

3.5 VIRTEL SNAP

VIRTEL maintains an internal trace table in which it records significant events which occur during VIRTEL processing. The SNAP command allows the administrator to obtain a snapshot listing of the contents of the trace table at a given point in time.

The SNAP listing is primarily intended for use by VIRTEL development personnel and will normally need to be forwarded to Syspertec for analysis. For customer diagnostics, the TRACE command (described above) may often be more useful.

Note: The format, the contents, and the size of the SNAP depend on the SNAPW, TRACBIG, TRACEB, TRACEON parameters in the VIRTCT.

The internal trace table is recorded in a circular fashion, so that each new event added to the table overlays and replaces the oldest event in the table. The table contains a fixed number of event slots (determined by the TRACBIG parameter in the VIRTCT), and additionally certain events may have a variable amount (up to 256 bytes) of data recorded. The variable data is stored in a separate area whose size is determined by the TRACEB parameter in the VIRTCT, and this area is also filled in a circular manner, with the oldest information being dropped from the table when new information is added. Thus, depending on the values of the TRACBIG and TRACB parameters, older entries in the trace table may no longer have data associated with them.

Clearly, the greater the level of activity in the VIRTEL system, the quicker the trace table will wrap and information will be pushed out to make way for new entries. Thus, in order for the SNAP listing to provide useful information, the size of the trace table and its associated buffer area must be adequate for the level of system activity, and the SNAP command must be issued as quickly as possible after the event under investigation occurs. In some cases it may be necessary to use an automation tool to issue the SNAP command immediately following the appearance of a certain console message.

As well as dumping the contents of the internal trace table, the SNAP command also dumps certain VIRTEL internal control blocks. A dump of the control blocks associated with a particular terminal may optionally be requested.

The SNAP command is described under the heading “VIRTEL commands”. VIRTEL may also produce a SNAP listing automatically if a program check or other abend occurs during VIRTEL processing.

In **z/OS environment**, the SNAP output is written to the SYSPRINT file in the VIRTEL started task. In **z/VSE environment**, the SNAP output is written to the POWER LST file of the VIRTEL partition.

Note: Several SNAP commands may be issued during a single run of VIRTEL. The output file may thus contain successive SNAP listings concatenated one after the other.

```

DATE=04 Jun 2017 TIME= 19:12:38 TASK= ABEND= TERM= APPLICATION=APPLHOLT VERSION=4.56 MVS
SYSPERTEC COMMUNICATION
196 BUREAUX DE LA COLLINE
92213 SAINT CLOUD CEDEX
P500 - PERMANENT
TASK R15 R14
TRACE BLOCK START=1306391013, END=1912383472
MODULE OFFS FUNCTION 1/10000 S.
DELOC003 02DD 00000004 9E98A852 VIR0017 +3922 000C WRITE END 1306391013
DELOC003 02DD 1EC1C7D8 9E9E5EC2 VIR0C12 +42AA 8042 £FREEMAIN 1306391013
DELOC003 02DD 1EC1CAC0 9E9E5EDA VIR0C12 +42C2 8042 £FREEMAIN 1306391013
DELOC003 02DD 1EAF7078 9E9E5EF0 VIR0C12 +42D8 8042 £FREEMAIN 1306391013
DELOC003 02DD 1EAF640 9E9E2962 VIR0C12 +0D4A 802E £DETACH 1306391013
DELOC003 02DD 1EAADEC0 8002CA62 VIR0009 +2ACA 806C £ENDING 1306391013
DELOC003 02DD 00480522 9E9C696A VIR00PE +0A02 400A ERRMSG 1306391013
DELOC003 EED0 1E93B4C7 9E9C69F8 VIR00PE +0B60 8088 £LOG FINI 1306391069
DELOC003 02DD 00026210 9E9C6A18 VIR00PE +0B80 808A £REQ STATS 1306391069
DELOC003 02DD 1EAF5F10 00000486 VIR0000 +5D66 804B £POST 1306391069
DELOC003 02DD 1EAF640 9E9C6084 VIR00PE +0D1C 802E £DETACH 1306391069
DELOC003 02DD 1EAAE0AC 8002CA80 VIR0009 +2AE8 806F £NO TIMER 1306391069
DELOC003 02DD 1EC06A68 8002C8CA VIR0009 +2C32 8042 £FREEMAIN 1306391069
DELOC003 02DD 00000000 8002CC96 VIR0009 +2CFE 3032 CONTINUE 1306391069
DELOC003 02DD 1EC06CA0 8002CD9A VIR0009 +2E02 8042 £FREEMAIN 1306391069
DELOC003 02DD 1EAF640 8002CD9A VIR0009 +2E02 8021 £RECANY 1306391069
DELOC003 02DD 1EAF638 8002DE86 VIR0009 +3EEE 8042 £FREEMAIN 1306391069
HTTP-W2H EED0 1E93B5CC 9E9E4B4A VIR0C12 +2F32 804E £CREATE 1306391069
HTTP-W2H 02DD 1EB14BA8 8002F470 VIR0009 +54D8 8040 £GETMAIN 1306391069
HTTP-W2H 02E0 00000008 8002F5BE VIR0009 +5626 804D TO LINE 1306391070
HTTP-W2H 02E0 1EAF5440 9EA88722 VIRHTTP +0B8A 8043 TO TCP 1306391070
HTTP-W2H 02E0 1EAF5440 9EA88F1C VIRHTTP +1384 0404 SEND 1306391070
HTTP-W2H EEE0 1E93B6D1 9EA92538 VIRHTTP +AA30 0022 /WRITE 1306391070
HTTP-W2H 02E0 1EB14998 9E9F4564 VIR0T09 +3584 8040 £GETMAIN 1306391070
J-HTTP EEE0 1E93B7D5 000E0F5A VIR0006 +1AFA 808E £VIRLOG 1306391083
J-HTTP 02E0 00000000 000DF688 VIR0006 +0228 8048 £WAIT 1306391084
HTTP-W2H 02E0 00000000 1EB14998 +0000 0804 /EXITAF 1306391084
HTTP-W2H 02DE 1EB150A8 9E9F46F4 VIR0T09 +3744 8042 £FREEMAIN 1306391090
DELOC006 02DE 1EAF4FC0 9EA8887A VIRHTTP +0D12 8085 £CVC FINI 1306391090
HTTP-W2H 02DE 1EAF4FC0 9EA87CE0 VIRHTTP +0178 081A /READ 1306391090
HTTP-W2H 02DE 1EB150A8 9E9F41F0 VIR0T09 +3240 8040 £GETMAIN 1306391090
HTTP-W2H 02DF 1EB14D20 9E9F46F4 VIR0T09 +3744 8042 £FREEMAIN 1306391095
DELOC004 02DF 1EAF4098 9EA8887A VIRHTTP +0D12 8085 £CVC FINI 1306391095
HTTP-W2H 02DF 1EAF4098 9EA87CE0 VIRHTTP +0178 081A /READ 1306391095
HTTP-W2H 02DF 1EB14D20 9E9F41F0 VIR0T09 +3240 8040 £GETMAIN 1306391095
HTTP-W2H 02E0 1EB14998 9E9F46F4 VIR0T09 +3744 8042 £FREEMAIN 1306391100
DELOC003 02E0 1EAF5440 9EA8887A VIRHTTP +0D12 8085 £CVC FINI 1306391100
HTTP-W2H 02E0 1EAF5440 9EA87CE0 VIRHTTP +0178 081A /READ 1306391100

```

Example of SNAP listing

3.5.1 Message-triggered SNAPMSG

The SNAPMSG command requests VIRTEL to generate an automatic SNAP after certain messages (VIRI902W, VIR0026W, VIR0052I, VIR1552I, VIR0526W or VIR1952I). Only one SNAP can also be obtained with user specific code provided by SYSPERTEC for messages VIRHT31E and VIRHT63E. See “VIRTEL commands”. See the SNAPMSG command for further details.

4.1 VIRSTAT file

The VIRSTAT file is a sequential file into which VIRTEL writes connection statistics.

Note: When the STATS=YES parameter is coded in the VIRTCT, the VIRSTAT file is reinitialised at each VIRTEL startup. With STATS=YES, VIRTEL must be stopped periodically in order to avoid filling the VIRSTAT file, and the file should be defined as a GDG in order not to lose the information from a previous run. The STATS=MULTI parameter may be coded in the z/OS environment to permit continuous operation.

Trying to browse the contents of the file from ISPF while it is in use by VIRTEL, can result to the obtain a system message indicating that the file is empty. In reality this is not true, because in fact the records are buffered in memory before being written in block.

The format of the statistics records depends on the value specified in the “Write Stats to” field of the VIRTEL terminal definition (refer to the VIRTEL Connectivity Reference manual for details of terminal definitions). Each terminal may request statistics in one or more of the possible formats:

Classic VIRSTAT classic format recording is intended for use with Minitel calls on terminals associated with NPSI lines (Gate or Fast Connect).

Alternate X25 VIRSTAT alternate format recording may be requested for terminals associated with any X25 line (GATE, FASTC, XOT).

Web VIRSTAT format suitable for terminals associated with an HTTP line.

For terminals associated with all other line types (including /GATE, /PCNE, and /FASTC) the statistics record may not contain meaningful information and the statistics field in the terminal definition should be left blank.

The statistics file may contain a mixture of classic, alternate X25, and web format records. The record type indicator at position 61 of each record identifies the format of the particular record.

4.1.1 VIRSTAT classic format

For terminals which specify classic format recording (STATS=1), the VIRSTAT record format is shown in the following table:

Position	Format	Type of information
1 to 8	Alphanumeric	Terminal name
9 to 12	Packed Decimal	Date (CCYYDDDF)
13 to 16	Packed Decimal	Time (HHMMSSTF)
17 to 28	Alphanumeric	User id
29 to 36	Alphanumeric	Originating terminal name (outbound calls)
37 to 40	Hexadecimal	No of bytes inbound (uncompressed)
41 to 44	Hexadecimal	No of bytes inbound (compressed)
45 to 48	Hexadecimal	No of bytes outbound (uncompressed)
49 to 52	Hexadecimal	No of bytes outbound (compressed)
53 to 56	Hexadecimal	No of sends
57 to 60	Hexadecimal	No of receives
61 to 61	Alphanumeric	Record type (C=cumulative,P=partial,E=end) [1]
62 to 62	Alphanumeric	Compression level (0,1,2)
63 to 70	Alphanumeric	Minitel: Server access node
71 to 74	Alphanumeric	Minitel: Call duration in minutes (ZZZ9)
75 to 82	Alphanumeric	Session start date (MM/DD/YY)
83 to 86	Alphanumeric	Session start date (.DDD)
87 to 94	Alphanumeric	Session start time (HH.MM.SS)
95 to 102	Alphanumeric	Session end date (MM/DD/YY)
103 to 106	Alphanumeric	Session end date (.DDD)
107 to 114	Alphanumeric	Session end time (HH.MM.SS)
115 to 115	Alphanumeric	Tarification level (External Servers)
116 to 116	Alphanumeric	Disconnection Type (T=by TIME-OUT)
117 to 120	Hexadecimal	X25 units received (Fast-Connect)
121 to 124	Hexadecimal	X25 units sent (Fast-Connect)

Format of VIRSTAT record (classic format)

For NPSI Fast Connect lines, the X25 accounting statistics are recorded in billing units provided by NPSI at virtual circuit disconnection time. Their interpretation depends on the TAXUNIT parameter in the NPSI X25.MCH macro. Similarly, the session start and end times (Fast Connect only) are provided by NPSI and depend on the clock settings in the NCP. For other types of lines, accounting statistics and times are generated by VIRTEL.

Type C (cumulative) Records are implemented at terminal disconnection.

Type P (partial) Records are implemented at regular intervals.

Type E (end of job) Records are implemented at VIRTEL shutdown.

4.1.2 VIRSTAT alternative X25 format

For terminals which specify alternate X25 format recording (STATS=4), the VIRSTAT record format is shown in the following table:

Position	Format	Type of information
1 to 8	Alphanumeric	Terminal name
9 to 12	Packed Decimal	Date (CCYYDDDF)
13 to 16	Packed Decimal	Time (HHMMSSTF)
17 to 36	Alphanumeric	Remote X25 number
37 to 40	Hexadecimal	Unused
41 to 44	Hexadecimal	Unused
45 to 48	Hexadecimal	Unused
49 to 52	Hexadecimal	Unused
53 to 56	Hexadecimal	Unused
57 to 60	Hexadecimal	Unused
61 to 61	Alphanumeric	Record type (I=inbound,O=outbound) [1]
62 to 62	Alphanumeric	Unused
63 to 70	Alphanumeric	Originating GATE/PCNE terminal name (outbound) Entry point name (inbound)
71 to 74	Alphanumeric	Unused
75 to 82	Alphanumeric	Session start date (MM/DD/YY)
83 to 86	Alphanumeric	Session start date (.DDD)
87 to 94	Alphanumeric	Session start time (HH.MM.SS)
95 to 102	Alphanumeric	Session end date (MM/DD/YY)
103 to 106	Alphanumeric	Session end date (.DDD)
107 to 114	Alphanumeric	Session end time (HH.MM.SS)
115 to 115	Alphanumeric	Unused
116 to 116	Alphanumeric	Disconnection Type (T=by TIME-OUT)
117 to 120	Hexadecimal	Unused
121 to 124	Hexadecimal	Call duration in 1/100 second

Format of VIRSTAT record (alternate X25 format)

For NPSI Fast Connect lines, the X25 session start and end times are provided by NPSI at virtual circuit disconnection time and depend on the clock settings in the NCP. For other types of lines, times are generated by VIRTEL.

Type I (inbound) Records relate to X25 incoming calls.

Type O (outbound) Records relate to X25 outgoing calls.

For terminals which specify web format recording (STATS=5 or STATS=6), the VIRSTAT record format is shown in the following tables:

Position	Format	Type of information
1 to 8	Alphanumeric	Terminal name
9 to 12	Packed Decimal	Date (CCYYDDDF)
13 to 16	Packed Decimal	Time (HHMMSSTF)
17 to 31	Alphanumeric	Caller's IP address
32 to 36	Alphanumeric	Alphanumeric
37 to 44	Alphanumeric	Entry point name
45 to 52	Alphanumeric	Transaction external name
53 to 60	Alphanumeric	Rule name
61 to 61	Alphanumeric	Record type (H=HTTP inbound)
62 to 64	Alphanumeric	Unused
65 to 68	Alphanumeric	Error code
69 to 76	Alphanumeric	Relay LU name
77 to 84	Alphanumeric	Call duration in 1/100 second

(continues on next page)

(continued from previous page)

85 to 92	Alphanumeric	No of bytes received
93 to 100	Alphanumeric	No of bytes sent
101 to 108	Alphanumeric	Session start date (MM/DD/YY)
109 to 116	Alphanumeric	Session start time (HH.MM.SS)
117 to 124	Alphanumeric	Session end time (HH.MM.SS)

Format of VIRSTAT record (type 5 for Web Access)

This record type is written when 5 is specified in the STATS field of the terminal definition used for the HTTP line. If the terminal is disconnected by TIMEOUT, the “Error Code” field contains the word “TIME”.

Position	Format	Type of information
1 to 8	Alphanumeric	Terminal name
9 to 12	Packed Decimal	Date (CCYYDDDF)
13 to 16	Packed Decimal	Time (HHMMSSSTF)
17 to 31	Alphanumeric	Caller's IP address
32 to 36	Alphanumeric	Caller's port number
37 to 44	Alphanumeric	Entry point name
45 to 52	Alphanumeric	Transaction external name
53 to 60	Alphanumeric	Rule name
61 to 61	Alphanumeric	Record type (B=binary HTTP inbound)
62 to 64	Alphanumeric	Unused
65 to 68	Alphanumeric	Error code
69 to 76	Alphanumeric	Relay LU name
77 to 80	Hexadecimal	Call duration in 1/100 second
81 to 84	Hexadecimal	No of bytes received
85 to 88	Hexadecimal	No of bytes sent
89 to 108	Alphanumeric	User name
109 to 124	Alphanumeric	URL parameter

Format of VIRSTAT record (type 6 for Web Access)

For this record type, the counters are in binary, and the Session Date and Time fields are replaced by User name (20 bytes) and URL parameter (first 16 bytes).

This record type is written when 6 is specified in the STATS field of the terminal definition used for the HTTP line.

4.1.3 Printing the contents of the VIRSTAT file (X25)

The VIR0070 program allows the contents of the VIRSTAT file to be printed. The source for this program is supplied in the SSL (VSE) or in the SAMPLIB (z/OS) and you can use this as the basis of a user-written program to print statistics.

Examples of the JCL required to execute this program are shown below:

```
* $$ JOB JNM=VIRSTAT,CLASS=0,DISP=D
* $$ LST DISP=D,CLASS=V,DEST=(,SPTUSER)
// JOB VIRPRNT
// LIBDEF *,SEARCH=VIRT442.SUBLIB
// DLBL STAT,'VIRTEL.VIRSTAT.ESDS',,VSAM,CAT=VSESPUC
// EXEC VIR0070,SIZE=AUTO
/*
/&
* $$ EOJ
```

Fig. 17 VIR0070 JCL to print VIRSTAT file (VSE)

```
//VIRSTAT JOB 1,USER,CLASS=A,MSGCLASS=X,NOTIFY=&SYSUID
//TRI EXEC PGM=SORT
//SYSPRINT DD SYSOUT=*
//SYSOUT DD SYSOUT=*
//SORTWK01 DD UNIT=3380,SPACE=(TRK,(100,20),RLSE)
//SORTWK02 DD UNIT=3380,SPACE=(TRK,(100,20),RLSE)
//SORTIN DD DISP=SHR,DSN=VIRTEL.STAT
//SORTOUT DD DSN=&&STAT,UNIT=SYSDA,DISP=(,PASS),
// DCB=(LRECL=124,BLKSIZE=620,RECFM=FB),
// SPACE=(TRK,(100,20),RLSE)
//SYSIN DD *
SORT FIELDS=(1,16,A),FORMAT=CH
END
//STAT EXEC PGM=VIR0070
//STEPLIB DD DISP=SHR,DSN=VIRT442.LOADLIB
//SYSUDUMP DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//VIRSTAT DD DISP=(OLD,DELETE),DSN=&&STAT
//
```

VIR0070 JCL to print VIRSTAT file (z/OS)

4.1.4 Printing the contents of the VIRSTAT file (HTTP)

The PRTSTATW program supplied with the system allows printing of type 6 records from the VIRSTAT file. This program is delivered as a load module in the VIRTEL LOADLIB (from version 4.45 onwards) and the execution JCL is provided as member JCLPRTST in the VIRTEL SAMPLIB.

Examples of the execution JCL for this program are shown below.

z/VSE JCL

In the VSE environment the VIRPRTST job, loaded into the POWER reader queue during VIRTEL installation, contains an example of JCL for printing the VIRSTAT file. This job is an example only and must be modified before execution:

```
* $$ JOB JNM=VIRPRTST,CLASS=0,DISP=D
* $$ LST DA
// JOB VIRPRTST
* *****
* * VIRTEL: EXAMPLE JCL TO EXECUTE STAT VIRTEL PRINT *
* *****
// LIBDEF *,SEARCH=(VIRT452.SUBLIB,PRD2.CONFIG,PRD1.BASE)
// DLBL SORTIN1,'VIRTEL.STAT',,VSAM,CAT=VSESPUC
// DLBL SORTOUT,'%VIRTEL.SORTFILE',0,VSAM,CAT=VSESPUC,DISP=(NEW,KEEP), C
RECORDS=(10,100),RECSIZE=124
* // DLBL SORTOUT,'VIRTEL.SORTFILE',0,SD
* // EXTENT SYS001,SYSWK2,1,0,NNNN,15
* // ASSGN SYS001,DISK,VOL=SYSWK2,SHR
// EXEC SORT,SIZE=100K
SORT FIELDS=(01,08,A),FORMAT=CH
RECORD TYPE=F,LENGTH=124
END
/*
* OPTIONS FOR PRINT OR COUNT
```

(continues on next page)

(continued from previous page)

```

* // DLBL SYSPRINT DD SYSOUT=*
* // DLBL SYSABEND DD SYSOUT=*
* // DLBL IJSYSLS DD SYSOUT=*
*
// DLBL VIRSTAT, '%VIRTEL.SORTFILE', 0, VSAM, CAT=VSESPUC, DISP=(,DELETE)
// ASSGN SYS007, SYSLST
// ASSGN SYS006, SYSRDR
// EXEC PGM=PRTSTATW, SIZE=AUTO
PRTSTATW PRINT NNN 0250
SELDATE 01012011 31122012
SELTERM DEVTA* CLVTA*
/*
* * MAIN CARD (REQUIRED)
* * -----
* * 1 2 3 4 5 6
* * 1...!...0...!...0...!...0...!...0...!...0...!...0...
* *PRTSTATW PRINT BREAK USER NNN PPPP
* * SPECIFIC REQUEST TO PRINT THE STATISTICS
* *PRTSTATW COUNT $ALL$ NNN PPPP
* * SPECIFIC REQUEST TO COUNT THE NUMBERS OF DIFFERENT
* * USERS
* *SELECT CARD (OPTIONAL)
* * -----
* * 1 2 3 4 5 6
* * 1...5...0...5...0...5...0...5...0...5...0...5...0
* *SELDATE DDMMYYYY DDMMYYYY
* * DATE SELECTION BEGIN,
* * END DATE
* *SELTERM TTTTTTTT XXXXXXXX YYYYYYYY ZZZZZZZZ (UP TO 8 BYTES)
* *SELUSER USER4571890123457789 (UP TO 20 BYTES)
* *SELPARM PARM457189012345 (UP TO 16 BYTES)
* * 1...!...0...!...0...!...0...!...0...!...0...!...0...
* * THE '*' CHARACTER ALLOWS A GENERIC EVALUATION.
/&
* $$ EOJ

```

PRTSTATW JCL to print VIRSTAT file in VSE (type=6)

z/OS JCL

In the z/OS environment the JCL for executing the PRTSTATW program is supplied as member JCLPRTST in the VIRTEL SAMPLIB:

```

//VIRPRTST JOB 1,USER,CLASS=A,MSGCLASS=X,NOTIFY=&SYSUID
/*JOBPARM LINES=9999
/*-----*
/* * VIRSTAT FILE PRINTING JOB *
/* * VIRSTAT RECORD TYPE 6 (VSTA-RECORD-TYPE='B') *
/*-----*
// SET LOAD=yourqual.VIRTnnn.LOADLIB
// SET STAT=yourqual.VIRTnnn.STAT
/*-----*
//JOB LIB DD DISP=SHR,DSN=&LOAD
/*-----*
/*

```

(continues on next page)

(continued from previous page)

```

//STEP0 EXEC PGM=SORT
//SYSOUT DD SYSOUT=*
//SORTIN DD DISP=SHR,DSN=&STAT
//SORTOUT DD DSN=&&SORTSTAT,DISP=(NEW,PASS),UNIT=SYSDA,
// DCB=(BLKSIZE=1240,LRECL=124,RECFM=FB),
// SPACE=(TRK,(1,1))
//SYSIN DD *
SORT FIELDS=(1,8,A),FORMAT=CH
/*
//STEP1 EXEC PGM=PRTSTATW
//SYSPRINT DD SYSOUT=*
//SYSABEND DD SYSOUT=*
//IJSYSL S DD SYSOUT=*
/*
//VIRSTAT DD DSN=&&SORTSTAT,DISP=OLD
//SYSIN DD *
PRTSTATW PRINT NNN 0250
SELDATE 01012011 31122012
SELTERM DEVTA* CLVTA*
* ..!....0....!....0....!....0....!....0....!....0....!....0...
/* MAIN CARD (required)
/* -----
/* 1 2 3 4 5 6
/* 1...!....0....!....0....!....0....!....0....!....0....!....0...
/* PRTSTATW PRINT BREAK USER NNN PPPP
/* specific request to print the statistics
/* PRTSTATW COUNT $ALL$ NNN PPPP
/* specific request to count the numbers of different
/* users
/* SELECT CARD (optional)
/* -----
/* 1 2 3 4 5 6
/* 1...5....0....5....0....5....0....5....0....5....0
/* SELDATE DDMMYYYY DDMMYYYY
/* DATE selection begin,
/* end date
/* SELTERM TTTTTTTT XXXXXXXX YYYYYYYY ZZZZZZZZ (up to 8 bytes)
/* SELUSER USER4571890123457789 (up to 20 bytes)
/* SELPARM PARM457189012345 (up to 16 bytes)
/* 1...!....0....!....0....!....0....!....0....!....0....!....0...
/* The '*' character allows a generic evaluation.
/*

```

PRTSTATW JCL to print VIRSTAT file in z/OS (type=6)

This JCL consists of two main steps:

- a first step to sort the file
- a second step to PRINT or COUNT the records

4.1.5 Sorting the VIRSTAT file

The sort requirements are determined by the type of report desired. Since the PRTSTATW program offers the option of selecting records and also offers up to two levels of report break to allow printing of subtotals, it is important to specify the appropriate sort criteria to obtain the correct result.

The sort operates on one or more criteria, in ascending (A) or descending (D) mode. You should adapt the SORT SYSIN according to the syntax of the specific SORT program being used.

Several examples of sort criteria are shown below for various fields: terminal (TERM), date (DATE), user name (USER), URL parameter (PARM)

```
SORT FIELDS=(1,8,A) --> TERM A: ascending D: descending
SORT FIELDS=(9,4,A) --> DATE
SORT FIELDS=(89,20,A) --> USER
SORT FIELDS=(109,16,A) --> PARM
SORT FIELDS=(1,8,A),FORMAT=CH sort by TERM
SORT FIELDS=(1,8,A,89,20,A),FORMAT=CH sort by TERM first then USER
SORT FIELDS=(17,15,A) --> IP Address (for $ALL$ request)
SORT FIELDS=(89,20,A,17,15,A),FORMAT=CH sort for $ALL$ request
```

PRTSTATW JCL sort criteria

For example, to obtain a report in ascending order of session start date, specify the following statements in the SORT SYSIN:

```
//SYSIN DD *
SORT FIELDS=(9,4,A),FORMAT=CH
/*
```

4.1.6 PRTSTATW program

The PRTSTATW program executed in the second step reads the sorted output file from the first step. It contains required and optional SYSIN cards.

```
First card (Required)
      1      2      3      4      5      6
1...!...0...!...0...!...0...!...0...!...0...
PRTSTATW PRINT                BREAK USER                NNN PPPP
```

PRTSTATW first SYSIN card

Columns 1 to 8 Program name: must be PRTSTATW

Columns 11 to 16 Report type: specify PRINT (print report) or COUNT (calculate number of distinct users)

Columns 31 to 35 Optionally specify BREAK if report break is desired (up to 2 levels) for printing (PRINT) or \$ALL\$ if counting (COUNT)

Columns 37 to 40 Optionally indicates the type of report break: TERM (break on change of terminal name), USER (break on change of user name), DATE (break on change of date) or PARM (break on change of URL parameter)

Columns 43 to 46 Optionally indicates the second level report break (TERM, USER, DATE, or PARM)

Columns 51 to 53 Optionally specify N (no) or O (yes) to print additional trace information (program trace, input/output trace, and miscellaneous trace respectively). The default is N for each trace.

Columns 56 to 59 Maximum number of pages to be printed (default 50 pages)

```
Second card (Optional)
      1      2      3      4      5      6
1...5...0...5...0...5...0...5...0...5...0...
SELDATE   DDMMYYYY DDMMYYYY
           DATE selection begin,
           end date
SELTERM    TTTTTTTT XXXXXXXX YYYYYYYY ZZZZZZZZ (up to 8 bytes)
SELUSER    USER4571890123457789 (up to 20 bytes)
SELPARM    PARM457189012345 (up to 16 bytes)
```

PRTSTATW second SYSIN card

This card allows records to be selected according to 4 fields: DATE (selection by date range), TERM (selection of up to 4 different terminal names, otherwise 4 different HTTP lines), USER (selection by user name), PARM (selection by URL parameter).

It is possible to make a **generic** selection by coding a '*' character at the end of a field. For example, specifying a terminal selection value of DEVT* allows the program to select all records whose terminal name begins with DEVT.

Columns 1 to 7 Optional, indicates the selection type: SELDATE (for DATE), SELTERM (for terminal), SELUSER (for user), or SELPARM (for URL parameter).

Columns 11 to 19 Indicates up to 8 characters for the chosen value (SELDATE and SELTERM). The value may end in '*' for a generic search.

Columns 21 to 29 For SELDATE: second date in the range, for SELTERM: second terminal name (optional)

Columns 31 to 39 For SELTERM: third terminal name (optional)

Columns 41 to 49 For SELTERM: fourth terminal name (optional)

Columns 21 to 40 For SELUSER: up to 20 characters for the user name. The value may end in '*' for a generic search.

Columns 21 to 36 For SELPARM: up to 16 characters for the URL parameter. The value may end in '*' for a generic search.

Counter Report

Clients who wish to obtain the total number of unique users can execute the PRTSTATW program with the SYSIN shown below.

For the SORT: the first sort field is the user name, and the second sort field is the IP address:

```
//SYSIN DD *
SORT  FIELDS=(89,20,A,17,15,A),FORMAT=CH
//
```

For the PRTSTATW program:

```
//SYSIN DD *
PRTSTATW COUNT $ALL$ NNN 0465
SELDATE 01012011 30122011
SELTERM DEVTA* CLVTA*
```

COUNT and \$ALL\$ are required. The selection cards are optional. They allow for example to report for a given period the number of different users connected to the system in HTTP mode and/or to filter on an HTTP line defined with transaction security active, which requires the user to sign on.

For z/OS, sample JCL for the user counter report is supplied in the JCLCOUST member of the VIRTEL SAMPLIB. For VSE, a sample job named VIRCOUST is loaded into the POWER Reader Queue at installation time.

```
1== VIRTEL == Statistics file COUNT job ==
Submit on: 18-01-2011 at: 14:23:12          PAGE : 000
Parameters CARDS list read by PRTSTATW

PRTSTATW COUNT          $ALL$   PARM          NNN 0469
SELDATE 01012010 30122011
* ..!....0.....!....0.....!....0.....!....0.....!....0.....!....0....

18-01-2011      14:23:12          * S U M M A R Y *
18-01-2011      14:23:12          With criterias put for selection at top of
→listing:
18-01-2011      14:23:12          Total Records read           : 00207
18-01-2011      14:23:12          Total Calls selected         : 00017
18-01-2011      14:23:12          Total Calls duration         : 001hr04mn35s
18-01-2011      14:23:12          Total Calls ended by "Timeout" : 00007
18-01-2011      14:23:12          Total Defined different Users  : 00004
```

(continues on next page)

(continued from previous page)

18-01-2011	14:23:12	Total Calls without signature	: 00001
18-01-2011	14:23:12	End of execution	

PRTSTATW user counter report

4.2 SMF Support

Using VIRTEL 4.53+ and onwards allows VIRTEL SMF support writing VIRSTATS records into SMF. The VIRTCT must be reassembled and link-edited with a new value SMF or (SMF,nnn) for the STATS parameter to have this feature active. The SMF record format is the same as the current STATS record but prefixed by the standard SMF header. The default SMF record number is 223, but it can be modified using the (SMF,nnn) syntax.

4.2.1 Printing the VIRSTAT SMF record

The SMFPRINT/SMFPRINTL jobs in VIRTEL.SAMPLIB can be used to print the Virtel SMF records. The SMFPRINT job is an example of printing SYS1.MANx datasets and calls a REXX procedure called SMFREXX. SMFPRINT can be used to process Virtel SMF stats records written by Virtel V4.59. The SMFPRNTL job in VIRTEL.SAMPLIB can be used to print Virtel SMF records that have been written to a z/OS LOGSTREAM. This job calls the SMFREXXL REXX procedure to format and print the SMF records extracted from the LOGSTREAM. Virtel V4.60 onwards has a different SMF record format to older versions of Virtel. SMFREXXL must be used to format the records from V4.60 onwards.

Messages “VIR0612E VIRSTAT SMFWTM FAILED. RC=rc” and “VIR0611I VIRSTAT NOW RECORDING TO SMF” are in relation with SMF support. See “Virtel Messages and Operations” manual for more details.

4.2.2 Structure of the Binary STATS record.

The segment within the SMF record starts at offset X'0E'. For Virtel V4.59 or less the following structure is used: -

-----				42310349
* DESCRIPTION DU FICHIER DES STATISTIQUES (MCVFALT2)				42310349
-----				42310349
*				42310349
H\$STATS	DSECT			42310349
H\$LUNAME	DS	CL8	NOM DU TERMINAL	42310349
H\$DATE	DS	PL4	DATE STATISTIQUES	42310349
H\$TIME	DS	PL4	HEURE STATISTIQUES	42310349
H\$IPADDR	DS	CL15	CALLER IP ADDRESS	42310349
H\$IPPORT	DS	CL5	CALLER IP PORT	42310349
H\$ENTRY	DS	CL8	ENTRY POINT	42310349
H\$TRANS	DS	CL8	TRANSACTION	42310349
H\$RULE	DS	CL8	RULE (default to LINE)	42310349
H\$CUMPAR	DS	CL1	H HTTP entrant	42310349
	DS	CL3	filler	42310349
H\$STATUS	DS	CL4	HTTP STATUS	42310349
H\$RELAY	DS	CL8	NOM DU RELAY	42310349
H\$SPENT	DS	CL8	Durée d'appel en 1/100s	42310349
*H\$NBIN1	DS	XL4	INPUT COUNT	42310349
*H\$NBOUT2	DS	XL4	OUTPUT COUNT	42310349
H\$BYTRD	DS	CL8	BYTES RECEIVED	42310349
H\$BYTST	DS	CL8	BYTES SENT	42310349
H\$START1	DS	CL8	SESSION START DATE GREGORIENNE	42310349
H\$START3	DS	CL8	SESSION START TIME	42310349
H\$END3	DS	CL8	SESSION END TIME	42310349
LHSTATS	EQU	*-HSTATS	LONGUEUR ENREGISTREMENT	42310349

Example of output :-

Date	Time	SMF	IP Address	Port	Entry	Rule	Trans.	User	Code	Duration	Send	Recv
2022.277	00:57:35	SPT1	192.168.092.035	63757	WEB2HOST	HTTP-W2H	W2H-DIR		200	3	6181	522
2022.277	00:57:35	SPT1	192.168.092.035	63757	WEB2HOST	HTTP-W2H	W2H-DIR		200	11	1072	501
2022.277	00:57:35	SPT1	192.168.092.035	63767	WEB2HOST	HTTP-W2H	W2H-DIR		200	5	3542	499
2022.277	00:57:35	SPT1	192.168.092.035	63765	WEB2HOST	HTTP-W2H	W2H-DIR		200	10	1917	506
2022.277	00:57:35	SPT1	192.168.092.035	63764	WEB2HOST	HTTP-W2H	W2H-DIR		200	16	4834	522
2022.277	00:57:35	SPT1	192.168.092.035	63766	WEB2HOST	HTTP-W2H	W2H-DIR		200	15	7322	506
2022.277	00:57:35	SPT1	192.168.092.035	63768	WEB2HOST	HTTP-W2H	W2H-DIR		200	14	58240	507
2022.277	00:57:35	SPT1	192.168.092.035	63765	WEB2HOST	HTTP-W2H	W2H-DIR		200	9	31678	502
2022.277	00:57:35	SPT1	192.168.092.035	63757	WEB2HOST	HTTP-W2H	W2H-DIR		200	16	11065	509
2022.277	00:57:35	SPT1	192.168.092.035	63767	WEB2HOST	HTTP-W2H	W2H-DIR		200	15	613	506
2022.277	00:57:35	SPT1	192.168.092.035	63766	WEB2HOST	HTTP-W2H	W2H-DIR		200	9	3853	504
2022.277	00:57:35	SPT1	192.168.092.035	63764	WEB2HOST	HTTP-W2H	W2H-DIR		200	7	75514	504
2022.277	00:57:36	SPT1	192.168.092.035	63770	CLIWHOST	HTTP-CLI	CLI-DIR		200	2	1370	500
2022.277	00:57:39	SPT1	192.168.092.035	63770	CLIWHOST	HTTP-CLI	CLI-90	SPTHOLT	200	8	10638	636
2022.277	00:57:39	SPT1	192.168.092.035	63773	CLIWHOST	HTTP-CLI	W2H-DIR		200	7	3619	529
2022.277	00:57:39	SPT1	192.168.092.035	63774	CLIWHOST	HTTP-CLI	W2H-DIR		200	7	1072	511
2022.277	00:57:39	SPT1	192.168.092.035	63772	CLIWHOST	HTTP-CLI	W2H-DIR		200	13	1917	512
2022.277	00:57:39	SPT1	192.168.092.035	63770	CLIWHOST	HTTP-CLI	W2H-DIR		200	19	58240	508
2022.277	00:57:39	SPT1	192.168.092.035	63776	CLIWHOST	HTTP-CLI	W2H-DIR		200	13	4834	528
2022.277	00:57:39	SPT1	192.168.092.035	63775	CLIWHOST	HTTP-CLI	W2H-DIR		200	14	11065	515
2022.277	00:57:39	SPT1	192.168.092.035	63774	CLIWHOST	HTTP-CLI	W2H-DIR		200	9	3542	509
2022.277	00:57:39	SPT1	192.168.092.035	63770	CLIWHOST	HTTP-CLI	W2H-DIR		200	5	2366	509
2022.277	00:57:39	SPT1	192.168.092.035	63773	CLIWHOST	HTTP-CLI	W2H-DIR		200	16	7322	512
2022.277	00:57:39	SPT1	192.168.092.035	63772	CLIWHOST	HTTP-CLI	W2H-DIR		200	14	115416	459
2022.277	00:57:39	SPT1	192.168.092.035	63773	CLIWHOST	HTTP-CLI	W2H-DIR		200	4	2161	529
2022.277	00:57:39	SPT1	192.168.092.035	63772	CLIWHOST	HTTP-CLI	W2H-DIR		200	4	81464	569
2022.277	00:57:42	SPT1	192.168.092.035	63770	CLIWHOST	HTTP-CLI	W2H-DIR		200	5	1224	473
2022.277	00:57:42	SPT1	192.168.092.035	63773	CLIWHOST	HTTP-CLI	W2H-DIR		200	7	1253	473
2022.277	00:57:42	SPT1	192.168.092.035	63774	CLIWHOST	HTTP-CLI	W2H-DIR		200	7	12324	521
2022.277	00:57:42	SPT1	192.168.092.035	63772	CLIWHOST	HTTP-CLI	W2H-DIR		200	15	308256	511
2022.277	00:57:42	SPT1	192.168.092.035	63772	CLIWHOST	HTTP-CLI	W2H-DIR		200	2	852	470
2022.277	00:57:42	SPT1	192.168.092.035	63773	CLIWHOST	HTTP-CLI	W2H-DIR		200	2	3106	539
2022.277	00:57:42	SPT1	192.168.092.035	63774	CLIWHOST	HTTP-CLI	W2H-DIR		200	4	20998	521
2022.277	00:57:42	SPT1	192.168.092.035	63773	CLIWHOST	HTTP-CLI	W2H-DIR		200	1	6498	525
2022.277	00:57:42	SPT1	192.168.092.035	63772	CLIWHOST	HTTP-CLI	W2H-DIR		200	2	650	516
2022.277	00:57:42	SPT1	192.168.092.035	63773	CLIWHOST	HTTP-CLI	W2H-DIR		200	4	8241	496
2022.277	00:57:43	SPT1	192.168.092.035	63773	CLIWHOST	HTTP-CLI	W2H-DIR		200	3	78528	494

For Virtel V4.60 onwards, the record structure is as follows: -

-----										42310349
* DESCRIPTION DU FICHIER DES STATISTIQUES (MCVFALT2)										42310349
-----										42310349
*										42310349
H\$STATS	DSECT									42310349
H\$LUNAME	DS	CL8				NOM DU TERMINAL				42310349
H\$DATE	DS	PL4				DATE STATISTIQUES				42310349
H\$TIME	DS	PL4				HEURE STATISTIQUES				42310349
H\$CUMPAR	DS	CL1				H HTTP entrant				58530289
	DS	CL3				filler				58530289
H\$IPADDR	DS	CL40	(was 15}			CALLER IP ADDRESS				58530289
* H\$IPPORT	DS	CL5				CALLER IP PORT				58530289
H\$ENTRY	DS	CL8				ENTRY POINT				42310349
H\$TRANS	DS	CL8				TRANSACTION				42310349
H\$RULE	DS	CL8				RULE (default to LINE)				42310349
* H\$CUMPAR	DS	CL1				H HTTP entrant				58530289
*	DS	CL3				filler				58530289
H\$STATUS	DS	CL4				HTTP STATUS				42310349
H\$RELAY	DS	CL8				NOM DU RELAY				42310349
H\$SPENT	DS	CL8				Durée d'appel en 1/100s				42310349
*H\$NBIN1	DS	XL4				INPUT COUNT				42310349
*H\$NBOUT2	DS	XL4				OUTPUT COUNT				42310349
H\$BYTRD	DS	CL8				BYTES RECEIVED				42310349
H\$BYTST	DS	CL8				BYTES SENT				42310349
H\$START1	DS	CL8				SESSION START DATE GREGORIENNE				42310349
H\$START3	DS	CL8				SESSION START TIME				42310349
H\$END3	DS	CL8				SESSION END TIME				42310349
* H\$SRCADR	DS	CL15				SOURCE IP ADDRESS				58530289
* H\$HSTADR	DS	CL15				HOST IP ADDRESS				58530289
H\$PXADDR	DS	CL40				PROXY IP ADDRESS				58530289
	ORG	H\$STATS+255								58360198
LH\$STATS	EQU	*-H\$STATS				LONGUEUR ENREGISTREMENT				42310349

Example of output : -

NUMBER OF RECORDS IN ERROR												
0												
Date	Time	SMF	-- IP Addressee	Callers/Proxy	--> Entry	Rule	Trans.	Userid	CDE	Duration	Send	Recei
2022.296	10:48:00	SPT1	192.168.92.35:56501		CLIWHOST	HTTP-CLI	CLI-DIR		304	5	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56500		CLIWHOST	HTTP-CLI	CLI-90	SPTHOLT	200	55	10841	6
2022.296	10:48:01	SPT1	192.168.92.35:56500		CLIWHOST	HTTP-CLI	W2H-DIR		304	7	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56501		CLIWHOST	HTTP-CLI	W2H-DIR		304	10	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56502		CLIWHOST	HTTP-CLI	W2H-DIR		304	8	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56500		CLIWHOST	HTTP-CLI	W2H-DIR		304	8	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56501		CLIWHOST	HTTP-CLI	W2H-DIR		304	6	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56502		CLIWHOST	HTTP-CLI	W2H-DIR		304	7	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56501		CLIWHOST	HTTP-CLI	W2H-DIR		304	3	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56500		CLIWHOST	HTTP-CLI	W2H-DIR		304	9	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56501		CLIWHOST	HTTP-CLI	W2H-DIR		304	3	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56502		CLIWHOST	HTTP-CLI	W2H-DIR		304	8	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56501		CLIWHOST	HTTP-CLI	W2H-DIR		304	1	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56501		CLIWHOST	HTTP-CLI	W2H-DIR		304	3	195	5
2022.296	10:48:01	SPT1	192.168.92.35:56501		CLIWHOST	HTTP-CLI	W2H-DIR		304	2	195	5
2022.296	10:48:34	SPT1	192.168.92.35:56501		CLIWHOST	HTTP-CLI	W2H-DIR		304	7	195	5
2022.296	10:48:34	SPT1	192.168.92.35:56506		CLIWHOST	HTTP-CLI	W2H-DIR		304	5	195	5
2022.296	10:48:34	SPT1	192.168.92.35:56500		CLIWHOST	HTTP-CLI	W2H-DIR		304	7	195	5
2022.296	10:48:34	SPT1	192.168.92.35:56502		CLIWHOST	HTTP-CLI	W2H-DIR		304	11	195	5
2022.296	10:48:34	SPT1	192.168.92.35:56502		CLIWHOST	HTTP-CLI	CLI-DIR		304	4	195	5
2022.296	10:48:34	SPT1	192.168.92.35:56506		CLIWHOST	HTTP-CLI	W2H-DIR		304	4	195	5
2022.296	10:48:34	SPT1	192.168.92.35:56500		CLIWHOST	HTTP-CLI	W2H-DIR		304	8	195	5
2022.296	10:48:34	SPT1	192.168.92.35:56502		CLIWHOST	HTTP-CLI	W2H-DIR		304	4	195	5
2022.296	10:48:35	SPT1	192.168.92.35:56506		CLIWHOST	HTTP-CLI	W2H-DIR		304	2	195	5
2022.296	10:48:35	SPT1	192.168.92.35:56502		CLIWHOST	HTTP-CLI	W2H-DIR		304	5	195	5
2022.296	10:48:35	SPT1	192.168.92.35:56502		CLIWHOST	HTTP-CLI	W2H-DIR		304	3	195	5
2022.296	13:36:54	SPT1	192.168.92.35:57542		CLIWHOST	HTTP-CLI	W2H-DIR		404	8	268	5
2022.296	13:42:21	SPT1	192.168.92.35:57569		CLIWHOST	HTTP-CLI	CLI-DIR		304	10	128	4
2022.296	13:42:33	SPT1	192.168.92.35:57569		CLIWHOST	HTTP-CLI	CLI-90	SPTHOLT	200	140	10638	6
2022.296	13:42:33	SPT1	192.168.92.35:57575		CLIWHOST	HTTP-CLI	W2H-DIR		304	22	128	4
2022.296	13:42:34	SPT1	192.168.92.35:57569		CLIWHOST	HTTP-CLI	W2H-DIR		304	43	128	4
2022.296	13:42:34	SPT1	192.168.92.35:57574		CLIWHOST	HTTP-CLI	W2H-DIR		304	32	128	4
2022.296	13:42:34	SPT1	192.168.92.35:57573		CLIWHOST	HTTP-CLI	W2H-DIR		304	48	128	4
2022.296	13:42:34	SPT1	192.168.92.35:57576		CLIWHOST	HTTP-CLI	W2H-DIR		304	49	128	4
2022.296	13:42:34	SPT1	192.168.92.35:57577		CLIWHOST	HTTP-CLI	W2H-DIR		304	45	128	4
2022.296	13:42:34	SPT1	192.168.92.35:57569		CLIWHOST	HTTP-CLI	W2H-DIR		304	25	128	4
2022.296	13:42:34	SPT1	192.168.92.35:57573		CLIWHOST	HTTP-CLI	W2H-DIR		304	16	128	4
2022.296	13:42:34	SPT1	192.168.92.35:57574		CLIWHOST	HTTP-CLI	W2H-DIR		304	26	128	4
2022.296	13:42:34	SPT1	192.168.92.35:57575		CLIWHOST	HTTP-CLI	W2H-DIR		304	41	128	4
2022.296	13:42:34	SPT1	192.168.92.35:57575		CLIWHOST	HTTP-CLI	W2H-DIR		304	12	128	4
2022.296	13:42:34	SPT1	192.168.92.35:57574		CLIWHOST	HTTP-CLI	W2H-DIR		304	10	128	5
2022.296	13:42:34	SPT1	192.168.92.35:57574		CLIWHOST	HTTP-CLI	W2H-DIR		304	6	128	5
2022.296	14:02:47	SPT1	192.168.92.35		CLIWHOST	HTTP-CLI	W2H-DIR		200	9	243	7
2022.296	14:02:47	SPT1	192.168.40.111		CLIWHOST	HTTP-CLI	W2H-DIR		200	3	243	13
2022.296	14:02:47	SPT1	192.168.40.111		CLIWHOST	HTTP-CLI	W2H-DIR		200	3	243	13
F1=HELP F2=SPLIT F3=END F4=RETURN F5=IFIND F6=B00K F7=UP F8=DOWN F9=SWAP F10=LEFT F11=RIGHT F12=RETRIEVE												

5.1 Trademarks

SysperTec, the SysperTec logo, syspertec.com and VIRTEL are trademarks or registered trademarks of SysperTec Communication Group, registered in France and other countries.

IBM, VTAM, CICS, IMS, RACF, DB2, MVS, WebSphere, MQSeries, System z are trademarks or registered trademarks of International Business Machines Corp., registered in United States and other countries.

Adobe, Acrobat, PostScript and all Adobe-based trademarks are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States and other countries.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States and other countries.

UNIX is a registered trademark of The Open Group in the United States and other countries. Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Other company, product, or service names may be trademarks or service names of others.

5.2 Open Source Software

The current VIRTEL Web Access product uses the following open source software:

- **jQuery** Under MIT license - <https://jquery.org/license/>
- **jQuery__UI** Under MIT license - http://en.wikipedia.org/wiki/JQuery_UI