

## אינהאלטס-טאבעלע

<a href="#">RAAS Client1</a>	
<a href="#">1.1 אינסטאלאציע</a>	
<a href="#">1.1.1 אוואַנסירטע סעטינגס</a>	
<a href="#">RAAS Server Configuration1.2</a>	
<a href="#">1.2.1 אלגעמיין</a>	
<a href="#">1.2.2 ווייט-שאַרטקאָץ</a>	
<a href="#">1.2.3 וויזואליזאציעס</a>	
<a href="#">1.2.4 טעקע עקספלאַרער עקסטענשאַן</a>	
<a href="#">RAAS Client1.3</a>	
<a href="#">RAAS Client1.4 טעקע עקספלאַרער עקסטענשאַן</a>	
<a href="#">RAAS Client Remote Desktop1.5</a>	
<a href="#">Search &amp; Run1.6</a>	
<a href="#">RAAS Server2</a>	
<a href="#">2.1 אינסטאלאציע</a>	
<a href="#">2.1.1 פארגעשריטענע סעטינגס</a>	
<a href="#">2.2 רעקאָמענדירטע ווינדאָוס קאָנפֿיגוראציע</a>	
<a href="#">Search &amp; Run2.3</a>	
<a href="#">3 ווערסיעס</a>	
<a href="#">4 שטיצע</a>	
<a href="#">4.1 געוויינטלעכע פראבלעמען</a>	

## RAAS Client1

איז געבויט אויף צוויי קאמפאָנענטן RAAS Client און RAAS Server. כדי צו קאנטראָלירן סערווערס, אדער האָסט קאמפיוטערס, RAAS Server דאַרף אינסטאַלירט ווערן אויף די האָסט קאמפיוטערס איידער מען קאנפֿיגורירט די האָסט קאמפיוטערס אויף דער קליענט זייט ניצנדיק RAAS Client אפליקאציעס. די סעקציע כולל אינסטרוקציעס פֿאַר אינסטאַלירן, קאנפֿיגורירן און נוצן RAAS Client.

### 1.1 אינסטאלאציע

RAAS Client קען אינסטאַלירט ווערן דורך אראפלאדן די RAASClient\_ [ווערסיע] x64.msi טעקע און עס אויספירן אויפן ציל קאמפיוטער. אויב די דיפאלט אינסטאלאציע איז גענוג, די איינציגסטע זאך וואס מען דארף נעמען איז אננעמען די לייסענס אפמאך און דריקן אינסטאל.

סיסטעם רעקווייערמענטן: שטיצט 64 ביט ווערסיעס פון Windows 10 און 11 Pro און .NET Framework 4.8 Enterprise. איז נויטיק.

#### 1.1.1 אוואַנסירטע סעטינגס

אויב די דיפאלט אינסטאלאציע איז נישט גענוג, קען מען עס צופאסן דורך קליקן דעם "אָוואַנסירט" קנעפל ביים אינסטאלירן. דער ערשטער אָפּטייל כולל אָפּציעס פֿאַר אינסטאַלירן עס אויף מאַשין לעווּעל, וואָס וועט זיין צוטריטלעך פֿאַר אַלע באַניצער, אָדער באַניצער לעווּעל, וואָס וועט זיין צוטריטלעך בלויז פֿאַר דעם איצטיקן באַניצער. קליקן "ווייטער" וועט ברענגען דעם באַניצער צו די פֿעלטשערז מעניו. אין דעם אָפּטייל איז מעגלעך צו קלייבן וועלכע פֿעלטשערז צו אינסטאַלירן דורך אַקטיווירן אָדער דיאַקטיווירן פֿעלטשערז אין דער צובינד. פרטים וועגן אַ פֿעלטשער ווערן פרעזענטירט אונטער דער קעסטל וואָס כולל די קאָנטראָלס ביים אויסקלייבן עס.

עצה: RAAS Client קען ווערן אפערירט דורך רעכט-קליקן אויף זיין מעלדונג אייקאן. כדי שטענדיק צו ווייזן דעם מעלדונג אייקאן אין דער טאָסקבאַר, קליקט אויף ווייזן באַהאַלטענע אייקאָנען אין טאָסקבאַר און שלעפט RAAS Client ייקאָן צו קענטיק ייקאָנז געגנט.

## RAAS Server Configuration1.2

RAAS Server Configuration קען ווערן אנגעהויבן פון די סטארט מעניו, דורך רעכט-קליקן א סערווער אין פייל עקספלארער און אויסקלויבן "RAAS Server Configuration" אדער דורך רעכט-קליקן דעם RAAS Client בילדל אין סיסטעם טאָץ און אָדער אויסקלייבן "RAAS Server Configuration" אין די וואָרצל מעניו אָדער אין איינעם פון די סערווער מעניוז. עס ווערט גענוצט צו קאָנפּיגורירן די סעטטינגס וואָס זאָלן ווערן געווענדט פֿאַר יעדן סערווער.

- סערווערס קענען אויסגעקליבן ווערן דורך די סערווער ליסטבאָקס, צו ענדערן קאָנפּיגוראַציע פֿאַר אַ באַזונדער סערווער.
- כדי צו לייגן צו א סערווער, דריקט דעם "לייג צו..." קנעפל, דערנאָך אריינלייגן דעם סערווער נאמען אדער סערווער IP אדרעס און דריקט דעם "לייג צו" קנעפל.
- כדי צו אַראָפּנעמען אַ סערווער, סעלעקטירט דעם סערווער צו אַראָפּנעמען און דריקט דעם "אַראָפּנעמען" קנעפל.

די קאָנפּיגוראַציע איז אַרגאַניזירט אין טאַבס, און סעטטינגס בנימצא אונטער יעדער טאַב ווערן פרעזענטירט אין די פאלגענדע סעקשאַנז.

### 1.2.1 אַלגעמײן

- **סערווער אַקטיווירן** : מאַכט דעם סערווער אַקטיוו און אַפּליקירט אַלע סערווער סעטטינגס. דער סערווער זאָל נישט זיין אַקטיוו ביז אַלע סעטטינגס זענען קאָנפּיגורירט.

סעטטינגס:

- **אַליאַס** : באַשטימט וועלכע אַליאַס דער סערווער זאָל האָבן אין אַלע RAAS Client אינטערפּייסיז.

- **קאנטע :** באשטימט דעם ווינדאוס קאנטע צו ניצן פאר קאמוניקאציע מיטן סערווער.
- **Password:** Determines the password to the windows account .to use for communication with the server
- **Domain:** Determines the domain for the windows account to .use for communication with the server
- **RDP authentication:** Determines which authentication rules to use when connecting though RemoteApp to the server, using .the RDP protocol
- **Auto reconnect:** Determines if RemoteApp should be reconnected to automatically if it was connected to before .lock, sleep or hibernate etc
- **Autostart startup programs:** Determines if applications which are configured to start automatically during startup on the server should start automatically through RemoteApp .when first connecting
- **Keep alive agent:** Determines if a keep alive agent should be started through RemoteApp on the server when first connecting, to prevent the connection from automatically .disconnecting when no applications are opened
- **Redirect clipboard:** Determines if clipboard redirection should .be on or off
- **Redirect devices:** Determines if devices should be redirected. This option requires additional settings to be active, which are .documented by Microsoft
- **Redirect printers:** Determines if printer redirection should be .on or off
- **Show notifications:** Determines if the user should receive a balloon tip notification when connecting or disconnecting RemoteApp. Notifications need to be activated in Windows .settings for notification to work

:Connection RAAS Server

- **Status:** Displays information about the servers current communication status. "No contact" indicates that no communication is present, "Contact" indicates that the server is reachable, "Available" indicates that communication with the RAAS Server service on the server is present and "Connected", which indicates that the server is connected to .through RemoteApp
- **version:** This information is only present if **RAAS Server** communication with the RAAS Server service on the server is

present, and indicates the installed version of RAAS Server on  
.the server

**Connect/Reconnect**-button: Used to connect or reconnect to •  
.the server through RemoteApp

**Disconnect**-button: Used to disconnect the server from •  
.RemoteApp

## Remote Shortcuts 1.2.2

**Enable remote shortcuts:** Makes remote shortcuts active and •  
.applies all remote shortcuts settings

:Remote Shortcuts Settings

**Create start-menu shortcuts:** Determines if start-menu •  
shortcuts on the server should be transferred to the current  
user of the local computer, to be started through RemoteApp.

Shortcuts will be placed in a dedicated folder in the start-  
.menu with the name format [Server alias]

**Create Windows Apps shortcuts:** Determines if Windows •

Apps shortcuts on the server should be transferred to the  
current user of the local computer, to be started through  
RemoteApp. Shortcuts will be placed in a dedicated folder in  
the start-menu with the name format [Server alias]. For  
Windows Apps shortcuts to be transferred after an installation  
Update Shortcuts need to be chosen for the server from  
.the RAAS Client notification area

**Create desktop shortcuts:** Determines if desktop shortcuts on •  
the server should be transferred to the current user of the local  
.computer, to be started through RemoteApp

**Place desktop shortcuts on desktop root:** Determines if •  
transferred desktop shortcuts from the server should be  
placed on desktop root of the current user. The alternative is  
to place them in a dedicated folder on the desktop with the  
.name format [Server alias]

**Append server alias to shortcut names:** Determines if •  
shortcuts that are transferred from the server should be given  
.names that are appended by the server alias

**Server language for shortcut names:** Determines if shortcuts •  
that are transferred from the server should be given names  
.according to the installed language on the server

## Visualizations 1.2.3

**Enable visualizations:** Makes visualizations active and applies •  
.all visualizations settings

:Visualizations Settings

**Main color:** Determines the main color to use for all •  
.visualizations

**Text color:** Determines the color of text used for all •  
.visualizations

**Line color:** Determines the color of lines used for all •  
.visualizations

**Frames:** Determines if RemoteApp windows for applications •  
on the server should have a frame decorization. The frames  
can be used to indicate to the user which applications belong  
.to the server

**Connection bar:** Determines if a connection bar should be •  
present when a RemoteApp window for an application on the  
server is active. The connection bar can be used to indicate  
.that an application on the server is receiving input

**Connection bar opacity:** If "Connection bar" is set, this setting •  
.determines the opacity of the connection bar

## File Explorer Extension 1.2.4

**Enable in File explorer extension:** Makes the server visible in •  
the RAAS Client File explorer extension and applies all  
.effective RAAS Client File explorer extension settings

Visible Folders: Use these options to determine which user folders that  
.should be visible for the server in the File explorer extension

Visible Devices and Drives: Use these options to determine which types  
of devices and drives that should be visible for the server in the File  
.explorer extension

## RAAS Client 1.3

The RAAS Client application is reached through its system tray icon.  
When right-clicking the icon in system tray a context menu will appear.  
.The menu items of this context menu will be described in this section

**Remote Desktop:** Opens the RAAS Client Remote" •  
."Desktop application, with no server selected

Opens the RAAS Server" :**RAAS Server Configuration** •  
."Configuration application, with no server selected

**Help (pdf):** Opens a pdf with help concerning RAAS •

- **About:** Opens a window with information about the .RAAS Client installed
- **Exit:** Closes .RAAS Client

The context menu contains one sub menu for each enabled server. A red circle before the server name indicates that the server is offline, a yellow circle before the server name indicates that the server is available and a green circle before the server name indicates that a connection through .RemoteApp to the server exist

:Server sub context menu

- **Connect:** Creates a connection to the server through .RemoteApp
- **.Disconnect:** Disconnects the server from RemoteApp
- **Reconnect:** Reconnects the RemoteApp connection to the .server
- **.Loggoff:** Logs out all logged in users from the server
- **.Reboot:** Reboots the server
- **Update Shortcuts:** Updates all remote shortcuts from server. This action is required when installing Windows Apps .shortcuts
- **Remote Desktop:** Opens the "RAAS Client Remote Desktop" .application with the server selected
- **RAAS Server Configuration** Opens the "RAAS Server :Configuration" application with the server selected

## File Explorer Extension RAAS Client 1.4

If shell namespace extension is installed for ,RAAS Client there will be a section in File explorer called "RAAS Client" in the treeview of File explorer root level. This section can be used to handle files and folders for each server which has File explorer extension active in settings. It is designed to function just as normal handling of files and folders in File Explorer, with some additional options which are described in this .section

:Right-clicking a server

- **Remote Desktop:** Opens the RAAS Client Remote "Desktop application with the server selected
- **RAAS Server Configuration** Opens the "RAAS Server :Configuration" application with the server selected

:Right-clicking a file

**Open on remote host:** Opens the file on the remote host •  
.through RemoteApp

**Create remote shortcut:** Creates a shortcut which starts the •  
file on the server through RemoteApp when activated. The file  
.is created in the current folder

:Right-clicking a file and dragging it to another location before release

**Create remote shortcut here:** Creates a shortcut which starts •  
the file on the server through RemoteApp when activated. The  
.file is created in the location which the file was dragged to

## RAAS Client Remote Desktop 1.5

can be started by right-clicking a server "RAAS Client Remote Desktop"  
in the File explorer extension and choosing "Remote Desktop" or by  
right-clicking the RAAS Client icon in system tray and either choosing  
"Remote Desktop" in the root menu or in one of the server menus. It is  
used to connect to a server with remote desktop using the stored  
.RAAS Server Configuration credentials, which can be configured using

**Server:** Choose the server to connect to using remote •  
.desktop

:Settings

**RDP authentication:** Determines which authentication rules to •  
use when connecting through remote desktop to the server,  
.using the RDP protocol

**Redirect clipboard:** Determines if clipboard redirection should •  
.be on or off

**Redirect devices:** Determines if devices should be redirected. •  
This option requires additional settings to be active, which are  
.documented by Microsoft

**Redirect printers:** Determines if printer redirection should be •  
.on or off

**Fullscreen:** Determines if remote desktop should be started in •  
.fullscreen mode

**Connection bar:** Determines if a connection bar should be •  
.present in fullscreen mode

**Pin connection bar:** Determines if the connection bar should •  
.be pinned initially

**Desktop width:** Determines the desktop width for the remote •  
.desktop session

- **Desktop height:** Determines the desktop height for the .remote desktop session

## Search & Run 1.6

provides an easy way to search for installed applications Search & Run on the server and then run the applications. It is installed on the server but is intended to be used as a RemoteApp application through RAAS Client on the client computer. It functions as a replacement for Windows search, which is not accessible through RAAS Client. Searching for files is performed by looking for files which begin with the provided string in the search field. "\*" in the string matches any string and "?" in the string matches any character

## RAAS Server 2

In order to control servers, or host computers, through RAAS Client, RAAS Server needs to be installed on the host computers

### Installation 2.1

is installed by downloading RAASServer\_[version]\_x64.msi RAAS Server to a server, or host computer, and opening the file. If default installation is sufficient the only actions which need to be taken is accepting the licence agreement and hitting install

In order use RAAS Server from a RAAS Client computer, you need to login once through the desktop interface once the program is installed with the user you wish to control the server with through RemoteApp

System requirements: Supports 64 bit versions of Windows 10 & 11 Pro and Enterprise as well as Windows Server RDS. .NET Framework 4.8 and ..NET 8 are both needed

### Advanced settings 2.1.1

If default installation is inadequate, it can be customized by clicking the "Advanced" button when installing. In this section it is possible to choose which features to install by enabling or disabling features in the interface.

Details of a feature is presented underneath the box containing the controls when selecting it

- If installed on Windows Server for RDS access it is recommended to disable the ability to reboot the server from the RDS clients. This can be configured by clicking the "Advanced" button on the installation and selecting "Entire



feature will be unavailable" for the feature named "Can  
."Reboot

## Recommended Windows 2.2 configuration

- It is recommended to allow password protected authentication to the computer shares on the server to allow access through the RAAS Client File explorer extension on the client computer. Documentation to provide password protected authentication to the computer shares on the server is documented by .Microsoft
- It is recommended to disable User Account Control, UAC, on the server to be able to install programs on the server through RAAS Client RemoteApp. User Account Control and privilege escalation are not supported by RAAS Client RemoteApp. Documentation to disable User Account Control is provided by Microsoft
- Remote desktop connections need to be allowed on the server .RAAS Client for Microsoft RemoteApp to work with communicates with RAAS Server through port RAAS Client 43000, this port need to be allowed through firewalls. An entry in Windows firewall is automatically created on installation .RAAS Server of
- An initial connect to the server with the user you wish to control the server with through RemoteApp is required for .shortcuts to be created
- If used with connection bar from RAAS Client, it is recommended to disable the Multi-tasking setting "Show snap layouts when I drag a window to the top of my screen", which is accessible in Windows system settings. That function comes in conflict with the RAAS Client connection bar when used simultaneously. Changing this will make the remote applications run more smoothly

## Search & Run 2.3

provides an easy way to search for installed applications Search & Run on the server and then run the applications. It is installed on the server but is intended to be used as a RemoteApp application through RAAS Client on the client computer. It functions as a replacement for Windows search, which is not accessible RAAS Client. Searching for files is performed by looking for files which begin with the provided string in

the search field. "\*" in the string matches any string and "?" in the string  
.matches any character

## Versioning 3

New versions of RAAS Client and RAAS Server should be published at the same time with the same version number corresponding to the version tag in GitHub. RAAS Client and RAAS Server should be compatible as long as the major version number is the same i.e. the first of the numbers  
.in the file names

## Support 4

### Common issues 4.1

File explorer may take longer time to start due to network locations being automatically added to quick access by Windows. In that case the  
.problem will occur if the network location is unreachable

To resolve: Change open location for File explorer setting from •  
."Home" to "This PC"