



Red Hat Enterprise Linux 7

Networking Guide

Configuration and Administration of Networking for Red Hat Enterprise Linux

Red Hat Enterprise Linux 7 Networking Guide

Configuration and Administration of Networking for Red Hat Enterprise Linux

Ioanna Gkioka
Red Hat Customer Content Services
igkioka@redhat.com

Mirek Jahoda
Red Hat Customer Content Services
mjahoda@redhat.com

Jana Heves
Red Hat Customer Content Services

Stephen Wadeley
Red Hat Customer Content Services

Christian Huffman
Red Hat Customer Content Services

Legal Notice

Copyright © 2010–2017 Red Hat, Inc.

This document is licensed by Red Hat under the [Creative Commons Attribution-ShareAlike 3.0 Unported License](#). If you distribute this document, or a modified version of it, you must provide attribution to Red Hat, Inc. and provide a link to the original. If the document is modified, all Red Hat trademarks must be removed.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java ® is a registered trademark of Oracle and/or its affiliates.

XFS ® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack ® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

The Red Hat Enterprise Linux 7 Networking Guide documents relevant information regarding the configuration and administration of network interfaces, networks and network services in Red Hat Enterprise Linux. It is oriented towards system administrators with a basic understanding of Linux and networking. This book is based on the Red Hat Enterprise Linux 6 Deployment Guide. The chapters related to networking were taken from the Deployment Guide to form the foundation for this book.

Table of Contents

PART I. IP NETWORKING	5
CHAPTER 1. INTRODUCTION TO RED HAT ENTERPRISE LINUX NETWORKING	6
1.1. HOW THIS BOOK IS STRUCTURED	6
1.2. IP NETWORKS VERSUS NON-IP NETWORKS	6
1.3. INTRODUCTION TO NETWORKMANAGER	7
1.4. INSTALLING NETWORKMANAGER	7
1.5. NETWORK CONFIGURATION USING A TEXT USER INTERFACE (NMTUI)	8
1.6. NETWORK CONFIGURATION USING NETWORKMANAGER'S CLI (NMCLI)	9
1.7. NETWORK CONFIGURATION USING THE COMMAND-LINE INTERFACE (CLI)	9
1.8. NETWORKMANAGER AND THE NETWORK SCRIPTS	10
1.9. NETWORK CONFIGURATION USING SYSCONFIG FILES	11
1.10. SETTING THE WIRELESS REGULATORY DOMAIN	13
1.11. CONFIGURING NETCONSOLE	13
1.12. ADDITIONAL RESOURCES	14
CHAPTER 2. CONFIGURE IP NETWORKING	16
2.1. STATIC AND DYNAMIC INTERFACE SETTINGS	16
2.2. EDITING NETWORK CONFIGURATION FILES	33
2.3. USING NETWORKMANAGER WITH THE GNOME GRAPHICAL USER INTERFACE	40
2.4. ESTABLISHING A VPN CONNECTION	51
2.5. ESTABLISHING A MOBILE BROADBAND CONNECTION	56
2.6. ESTABLISHING A DSL CONNECTION	59
2.7. CONFIGURING CONNECTION SETTINGS	60
2.8. ADDITIONAL RESOURCES	72
CHAPTER 3. CONFIGURE HOST NAMES	74
3.1. UNDERSTANDING HOST NAMES	74
3.2. CONFIGURING HOST NAMES USING TEXT USER INTERFACE, NMTUI	74
3.3. CONFIGURING HOST NAMES USING HOSTNAMECTL	75
3.4. CONFIGURING HOST NAMES USING NMCLI	76
3.5. ADDITIONAL RESOURCES	77
CHAPTER 4. CONFIGURE NETWORK BONDING	78
4.1. UNDERSTANDING THE DEFAULT BEHAVIOR OF MASTER AND SLAVE INTERFACES	78
4.2. CONFIGURE BONDING USING THE TEXT USER INTERFACE, NMTUI	78
4.3. NETWORK BONDING USING THE NETWORKMANAGER COMMAND LINE TOOL, NMCLI	83
4.4. USING THE COMMAND LINE INTERFACE (CLI)	85
4.5. USING CHANNEL BONDING	88
4.6. CREATING A BOND CONNECTION USING A GUI	95
4.7. ADDITIONAL RESOURCES	101
CHAPTER 5. CONFIGURE NETWORK TEAMING	102
5.1. UNDERSTANDING NETWORK TEAMING	102
5.2. UNDERSTANDING THE DEFAULT BEHAVIOR OF MASTER AND SLAVE INTERFACES	103
5.3. COMPARISON OF NETWORK TEAMING TO BONDING	103
5.4. UNDERSTANDING THE NETWORK TEAMING DAEMON AND THE "RUNNERS"	105
5.5. INSTALL THE NETWORK TEAMING DAEMON	105
5.6. CONVERTING A BOND TO A TEAM	105
5.7. SELECTING INTERFACES TO USE AS PORTS FOR A NETWORK TEAM	107
5.8. SELECTING NETWORK TEAM CONFIGURATION METHODS	107
5.9. CONFIGURE A NETWORK TEAM USING THE TEXT USER INTERFACE, NMTUI	107
5.10. CONFIGURE A NETWORK TEAM USING THE COMMAND LINE	112

5.11. CONTROLLING TEAMD WITH TEAMDCTL	120
5.12. CONFIGURE TEAMD RUNNERS	121
5.13. CREATING A NETWORK TEAM USING A GUI	128
5.14. ADDITIONAL RESOURCES	132
CHAPTER 6. CONFIGURE NETWORK BRIDGING	133
6.1. CONFIGURE BRIDGING USING THE TEXT USER INTERFACE, NMTUI	133
6.2. USING THE NETWORKMANAGER COMMAND LINE TOOL, NMCLI	136
6.3. USING THE COMMAND LINE INTERFACE (CLI)	138
6.4. CONFIGURE NETWORK BRIDGING USING A GUI	141
6.5. ETHERNET BRIDGE CONFIGURATION USING IPROUTE	146
6.6. ADDITIONAL RESOURCES	147
CHAPTER 7. CONFIGURE 802.1Q VLAN TAGGING	148
7.1. SELECTING VLAN INTERFACE CONFIGURATION METHODS	149
7.2. CONFIGURE 802.1Q VLAN TAGGING USING THE TEXT USER INTERFACE, NMTUI	149
7.3. CONFIGURE 802.1Q VLAN TAGGING USING THE COMMAND LINE TOOL, NMCLI	151
7.4. CONFIGURE 802.1Q VLAN TAGGING USING THE COMMAND LINE	154
7.5. CONFIGURE 802.1Q VLAN TAGGING USING A GUI	155
7.6. VLAN ON BOND AND BRIDGE USING IP COMMANDS	158
7.7. VLAN ON BOND AND BRIDGE USING THE NETWORKMANAGER COMMAND LINE TOOL, NMCLI	158
7.8. CONFIGURING VLAN SWITCHPORT MODE	159
7.9. ADDITIONAL RESOURCES	159
CHAPTER 8. CONSISTENT NETWORK DEVICE NAMING	160
8.1. NAMING SCHEMES HIERARCHY	160
8.2. UNDERSTANDING THE DEVICE RENAMING PROCEDURE	161
8.3. UNDERSTANDING THE PREDICTABLE NETWORK INTERFACE DEVICE NAMES	161
8.4. NAMING SCHEME FOR NETWORK DEVICES AVAILABLE FOR LINUX ON SYSTEM Z	162
8.5. NAMING SCHEME FOR VLAN INTERFACES	162
8.6. CONSISTENT NETWORK DEVICE NAMING USING BIOSDEVNAME	163
8.7. NOTES FOR ADMINISTRATORS	164
8.8. CONTROLLING THE SELECTION OF NETWORK DEVICE NAMES	164
8.9. DISABLING CONSISTENT NETWORK DEVICE NAMING	165
8.10. TROUBLESHOOTING NETWORK DEVICE NAMING	166
8.11. ADDITIONAL RESOURCES	168
PART II. INFINIBAND AND RDMA NETWORKING	169
CHAPTER 9. CONFIGURE INFINIBAND AND RDMA NETWORKS	170
9.1. UNDERSTANDING INFINIBAND AND RDMA TECHNOLOGIES	170
9.2. INFINIBAND AND RDMA RELATED SOFTWARE PACKAGES	171
9.3. CONFIGURING THE BASE RDMA SUBSYSTEM	172
9.4. CONFIGURING THE SUBNET MANAGER	179
9.5. TESTING EARLY INFINIBAND RDMA OPERATION	181
9.6. CONFIGURING IPOIB	184
9.7. CONFIGURE INFINIBAND USING THE TEXT USER INTERFACE, NMTUI	186
9.8. CONFIGURE IPOIB USING THE COMMAND-LINE TOOL, NMCLI	187
9.9. CONFIGURE IPOIB USING THE COMMAND LINE	189
9.10. TESTING AN RDMA NETWORK AFTER IPOIB IS CONFIGURED	190
9.11. CONFIGURE IPOIB USING A GUI	191
9.12. ADDITIONAL RESOURCES	192
PART III. SERVERS	194

CHAPTER 10. DHCP SERVERS	195
10.1. WHY USE DHCP?	195
10.2. CONFIGURING A DHCP SERVER	195
10.3. DHCP RELAY AGENT	201
10.4. CONFIGURING A MULTIHOMED DHCP SERVER	203
10.5. DHCP FOR IPV6 (DHCPV6)	206
10.6. CONFIGURING THE RADVD DAEMON FOR IPV6 ROUTERS	206
10.7. COMPARISON OF DHCPV6 TO RADVD	208
10.8. ADDITIONAL RESOURCES	209
CHAPTER 11. DNS SERVERS	210
11.1. INTRODUCTION TO DNS	210
11.2. BIND	211
CHAPTER 12. SQUID	239
12.1. INTRODUCTION TO SQUID	239
12.2. INSTALLING AND RUNNING SQUID	239
12.3. SQUID CONFIGURATION	240
12.4. SQUID AUTHENTICATION	245
12.5. USING SQUID FOR RESTRICTING ACCESS	249
12.6. ADDITIONAL RESOURCES	251
APPENDIX A. RED HAT CUSTOMER PORTAL LABS RELEVANT TO NETWORKING	252
BRIDGE CONFIGURATION	252
NETWORK BONDING HELPER	252
PACKET CAPTURE SYNTAX GENERATOR	252
APPENDIX B. REVISION HISTORY	253
B.1. ACKNOWLEDGMENTS	253
INDEX	254

PART I. IP NETWORKING

This part describes how to configure the network on Red Hat Enterprise Linux.

CHAPTER 1. INTRODUCTION TO RED HAT ENTERPRISE LINUX NETWORKING

1.1. HOW THIS BOOK IS STRUCTURED

All new material in this book has been written and arranged in such a way as to clearly separate introductory material, such as explanations of concepts and use cases, from configuration tasks. Red Hat Engineering Content Services hope that you can quickly find configuration instructions you need, while still providing some relevant explanations and conceptual material to help you understand and decide on the appropriate tasks relevant to your needs. Where material has been reused from the *Red Hat Enterprise Linux 6 Deployment Guide*, it has been reviewed and changed, where possible, to fit this idea of separating concepts from tasks.

The material is grouped according to the goal rather than the method. Instructions on how to achieve a specific task using different methods are grouped together. This is intended to make it easier for you to find the information on how to achieve a particular task or goal, and at the same time allow you to quickly see the different methods available.

In each chapter, the configuration methods will be presented in the following order:


- the text user interface tool, **nmtui**,
- **NetworkManager**'s command-line tool **nmcli**,
- other command-line methods and the use of configuration files,
- a graphical user interface (GUI) method, such as the use of **nm-connection-editor** or **control-network** to direct **NetworkManager**.

The command line can be used to issue commands, hence the term *command-line interface* (CLI) however the command line can also start an editor, to compose or edit configuration files. Therefore the use of **ip** commands and configuration files, such as **ifcfg** files, will be documented together.

1.2. IP NETWORKS VERSUS NON-IP NETWORKS

Most modern networks fall into one of two very broad categories: IP based networks. These are all networks that communicate through Internet Protocol addresses, which is the standard for the Internet and for most internal networks today. This generally includes Ethernet, Cable Modems, DSL Modems, dial up modems, wireless networks, VPN connections and more.

Then there are non-IP based networks. These are usually very specific niche networks, but one in particular has grown in usage enough to warrant mention here and that is InfiniBand. Because InfiniBand is not an IP network, many features and configurations normally used on IP networks are not applicable to InfiniBand. [Chapter 9, *Configure InfiniBand and RDMA Networks*](#) in this guide covers the specific requirements of configuring and administrating an InfiniBand network and also the broader class of RDMA capable devices.



IMPORTANT

Red Hat Enterprise Linux does not provide consistent naming when attempting to use the **ethX** naming convention. For more information, see [Section 8.10, “Troubleshooting Network Device Naming”](#)

1.3. INTRODUCTION TO NETWORKMANAGER

In Red Hat Enterprise Linux 7, the default networking service is provided by **NetworkManager**, which is a dynamic network control and configuration daemon that attempts to keep network devices and connections up and active when they are available. The traditional `ifcfg` type configuration files are still supported. See [Section 1.8, “NetworkManager and the Network Scripts”](#) for more information.

Table 1.1. A Summary of Networking Tools and Applications

Application or Tool	Description
NetworkManager	The default networking daemon
nmtui	A simple curses-based text user interface (TUI) for NetworkManager
nmcli	A command-line tool provided to allow users and scripts to interact with NetworkManager
control-center	A graphical user interface tool provided by the GNOME Shell
nm-connection-editor	A GTK+ 3 application available for certain tasks not yet handled by control-center

NetworkManager can configure network aliases, **IP** addresses, static routes, **DNS** information, and VPN connections, as well as many connection-specific parameters. **NetworkManager** provides an API through D-Bus which allows applications to query and control network configuration and state.

Finally, **NetworkManager** now maintains the state of devices after the reboot process and takes over interfaces which are set into managed mode during restart. In addition, **NetworkManager** can handle devices which are not explicitly set as unmanaged but controlled manually by the user or another network service.

1.4. INSTALLING NETWORKMANAGER

NetworkManager is installed by default on Red Hat Enterprise Linux. If necessary, to ensure that it is, enter the following command as the **root** user:

```
~]# yum install NetworkManager
```

For information on user privileges and gaining privileges, see the [Red Hat Enterprise Linux System Administrator's Guide](#).

1.4.1. The NetworkManager Daemon

The **NetworkManager** daemon runs with root privileges and is, by default, configured to start up at boot time. You can determine whether the **NetworkManager** daemon is running by entering this command:

```
~]$ systemctl status NetworkManager
NetworkManager.service - Network Manager
   Loaded: loaded (/lib/systemd/system/NetworkManager.service; enabled)
   Active: active (running) since Fri, 08 Mar 2013 12:50:04 +0100; 3 days
```

ago

The `systemctl status` command will report **NetworkManager** as **Active: inactive (dead)** if the **NetworkManager** service is not running. To start it for the current session enter the following command as the root user:

```
~]# systemctl start NetworkManager
```

Run the `systemctl enable` command to ensure that **NetworkManager** starts up every time the system boots:

```
~]# systemctl enable NetworkManager
```

For more information on starting, stopping and managing services, see the [Red Hat Enterprise Linux System Administrator's Guide](#).

1.4.2. Interacting with NetworkManager

Users do not interact with the **NetworkManager** system service directly. Instead, users perform network configuration tasks using graphical and command-line user interface tools. The following tools are available in Red Hat Enterprise Linux 7:

1. A simple curses-based text user interface (TUI) for **NetworkManager**, **nmtui**, is available.
2. A command-line tool, **nmcli**, is provided to allow users and scripts to interact with **NetworkManager**. Note that **nmcli** can be used on systems without a GUI such as servers to control all aspects of **NetworkManager**. It is on an equal footing with the GUI tools.
3. The GNOME Shell also provides a network icon in its Notification Area representing network connection states as reported by **NetworkManager**. The icon has multiple states that serve as visual indicators for the type of connection you are currently using.
4. A graphical user interface tool called **control-center**, provided by the GNOME Shell, is available for desktop users. It incorporates a **Network** settings tool. To start it, press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Super** key appears in a variety of guises, depending on the keyboard and other hardware, but often as either the Windows or Command key, and typically to the left of the Space key.
5. A graphical user interface tool, **nm-connection-editor**, is available for certain tasks not yet handled by **control-center**. To start it, press the **Super** key to enter the Activities Overview, type **network connections** or **nm-connection-editor** and then press **Enter**.




Figure 1.1. Network connection icon states

1.5. NETWORK CONFIGURATION USING A TEXT USER INTERFACE (NMTUI)

The **NetworkManager** text user interface (TUI) tool, **nmtui**, provides a text interface to configure networking by controlling **NetworkManager**. The tool is contained in the **NetworkManager-tui**

package. At time of writing, it is not installed along with **NetworkManager** by default. To install **NetworkManager-tui**, issue the following command as **root**:

```
~]# yum install NetworkManager-tui
```

If required, for details on how to verify that **NetworkManager** is running, see [Section 1.4.1, “The NetworkManager Daemon”](#).

To start **nmtui**, issue a command as follows:

```
~]$ nmtui
```

The text user interface appears. To navigate, use the arrow keys or press **Tab** to step forwards and press **Shift+Tab** to step back through the options. Press **Enter** to select an option. The **Space** bar toggles the status of a check box.

The following commands are available:

- **nmtui edit *connection-name***

If no connection name is supplied, the selection menu appears. If the connection name is supplied and correctly identified, the relevant **Edit connection** screen appears.

- **nmtui connect *connection-name***

If no connection name is supplied, the selection menu appears. If the connection name is supplied and correctly identified, the relevant connection is activated. Any invalid command prints a usage message.

At time of writing, **nmtui** does not support all types of connections. In particular, you cannot edit VPNs, wireless network connections using WPA Enterprise, or Ethernet connections using **802.1X**.

1.6. NETWORK CONFIGURATION USING NETWORKMANAGER'S CLI (NMCLI)

The **NetworkManager** command-line tool, **nmcli**, provides a command line way to configure networking by controlling **NetworkManager**. It is installed, along with **NetworkManager**, by default. If required, for details on how to verify that **NetworkManager** is running, see [Section 1.4.1, “The NetworkManager Daemon”](#).

Examples of using the **nmcli** tool for each task will be included where possible, before explaining the use of other command-line methods and graphical user interfaces. See [Section 2.1.5, “Using the NetworkManager Command Line Tool, nmcli”](#) for an introduction to **nmcli**, and check the **man nmcli-examples(7)** page for useful examples. To find out which properties are available for the **nmcli c add** and **nmcli c modify** commands, use the **man nm-settings(5)** page.

1.7. NETWORK CONFIGURATION USING THE COMMAND-LINE INTERFACE (CLI)

The commands for the **ip** utility, sometimes referred to as **iproute2** after the upstream package name, are documented in the **man ip(8)** page. The package name in Red Hat Enterprise Linux 7 is **iproute**. If necessary, you can check that the **ip** utility is installed by checking its version number as follows:

```
~]$ ip -V
ip utility, iproute2-ss130716
```

The **ip** commands can be used to add and remove addresses and routes to interfaces in parallel with **NetworkManager**, which will preserve them and recognize them in **nmcli**, **nmtui**, **control-center**, and the D-Bus API.

Note that the **ip** utility replaces the **ifconfig** utility because the **net-tools** package (which provides **ifconfig**) does not support InfiniBand addresses. The command **ip help** prints a usage message. Specific help is available for OBJECTS, for example: **ip link help** and **ip addr help**.



NOTE

ip commands given on the command line will not persist after a system restart. Where persistence is required, make use of configuration files (**ifcfg** files) or add the commands to a script.

Examples of using the command line and configuration files for each task are included after **nmtui** and **nmcli** examples but before explaining the use of one of the graphical user interfaces to **NetworkManager**, namely, **control-center** and **nm-connection-editor**.

1.8. NETWORKMANAGER AND THE NETWORK SCRIPTS

In previous Red Hat Enterprise Linux releases, the default way to configure networking was using *network scripts*. The term *network scripts* is commonly used for the script `/etc/init.d/network/` and any other installed scripts it calls. The user supplied files are typically viewed as configuration, but can also be interpreted as an amendment to the scripts.

Although **NetworkManager** provides the default networking service, Red Hat developers have worked hard to ensure that scripts and **NetworkManager** cooperate with each other. Administrators who are used to the scripts can certainly continue to use them. We expect both systems to be able to run in parallel and work well together. It is expected that most user shell scripts from previous releases will still work. Red Hat recommends that you test them first.

Running Network Script

Run the script **only** with the **systemctl** utility which will clear any existing environment variables and ensure clean execution. The command takes the following form:

```
systemctl start|stop|restart|status network
```

Note that in Red Hat Enterprise Linux 7, **NetworkManager** is started first, and `/etc/init.d/network` checks with **NetworkManager** to avoid tampering with **NetworkManager**'s connections. **NetworkManager** is intended to be the primary application using **sysconfig** configuration files and `/etc/init.d/network` is intended to be secondary, playing a fallback role.

The `/etc/init.d/network` script is not event-driven, it runs either:

1. manually (by one of the **systemctl** commands **start|stop|restart network**),
2. on boot and shutdown if the network service is enabled (as a result of the command **systemctl enable network**).

It is a manual process and does not react to events that happen after boot. Users can also call the scripts **ifup** and **ifdown** manually.

Custom Commands and the Network Scripts

Custom commands in the scripts `/sbin/ifup-local`, `ifdown-pre-local`, and `ifdown-local` are only executed when those devices are controlled by the `/etc/init.d/network` service. The `ifup-local` file does not exist by default. If required, create it under the `/sbin/` directory.

The `ifup-local` script is readable only by the `initscripts` and not by **NetworkManager**. To run a custom script using **NetworkManager**, create it under the `dispatcher.d/` directory. See [the section called “Running Dispatcher scripts”](#) for an explanation of the dispatcher scripts.



NOTE

Red Hat does not provide support if a user modifies any files included with the `initscripts` package or related rpms.

There are ways to perform custom tasks when network connections go up and down, both with the old network scripts and with **NetworkManager**. When **NetworkManager** is enabled, the `ifup` and `ifdown` script will ask **NetworkManager** whether **NetworkManager** manages the interface in question, which is found from the “DEVICE=” line in the `ifcfg` file. If **NetworkManager** does manage that device, and the device is not already connected, then `ifup` will ask **NetworkManager** to start the connection.

- If the device is managed by **NetworkManager** and it is already connected, nothing is done.
- If the device is not managed by **NetworkManager**, then the scripts will start the connection using the older, non-**NetworkManager** mechanisms that they have used since the time before **NetworkManager** existed.

If you are calling `ifdown` and the device is managed by **NetworkManager**, then `ifdown` will ask **NetworkManager** to terminate the connection.

The scripts dynamically check **NetworkManager**, so if **NetworkManager** is not running, the scripts will fall back to the old, pre-**NetworkManager** script-based mechanisms.

Running Dispatcher scripts

NetworkManager provides a way to run additional custom scripts to start or stop services based on the connection status. By default, the `/etc/NetworkManager/dispatcher.d/` directory exists and **NetworkManager** runs scripts there, in alphabetical order. Each script must be an executable file owned by `root` and must have `write` permission only for the file owner. For more information about running **NetworkManager** dispatcher scripts, see the Red Hat Knowledgebase solution [How to write a NetworkManager dispatcher script to apply ethtool commands](#).

1.9. NETWORK CONFIGURATION USING SYSCONFIG FILES

The `/etc/sysconfig/` directory is a location for configuration files and scripts. Most network configuration information is stored there, with the exception of VPN, mobile broadband and PPPoE configuration, which are stored in `/etc/NetworkManager/` subdirectories. Interface specific information for example, is stored in `ifcfg` files in the `/etc/sysconfig/network-scripts/` directory.

The file `/etc/sysconfig/network` is for global settings. Information for VPNs, mobile broadband and PPPoE connections is stored in `/etc/NetworkManager/system-connections/`.

In Red Hat Enterprise Linux 7 when you edit an `ifcfg` file, **NetworkManager** is not automatically aware of the change and has to be prompted to notice the change. If you use one of the tools to update

NetworkManager profile settings, then **NetworkManager** does not implement those changes until you reconnect using that profile. For example, if configuration files have been changed using an editor, **NetworkManager** must be told to read the configuration files again. To do that, issue the following command as **root**:

```
~]# nmcli connection reload
```

The above command reads all connection profiles. Alternatively, to reload only one changed file, **ifcfg-*ifname***, issue a command as follows:

```
~]# nmcli con load /etc/sysconfig/network-scripts/ifcfg-ifname
```

The command accepts multiple file names. These commands require **root** privileges. For more information on user privileges and gaining privileges, see the [Red Hat Enterprise Linux System Administrator's Guide](#) and the **su(1)** and **sudo(8)** man pages.

Changes made using tools such as **nmcli** do not require a reload but do require the associated interface to be put down and then up again. That can be done by using commands in the following format:

```
nmcli dev disconnect interface-name
```

Followed by:

```
nmcli con up interface-name
```

NetworkManager does not trigger any of the network scripts, though the network scripts will try to trigger **NetworkManager** if it is running when **ifup** commands are used. See [Section 1.8, “NetworkManager and the Network Scripts”](#) for an explanation of the network scripts.

The **ifup** script is a generic script which does a few things and then calls interface-specific scripts like **ifup-ethX**, **ifup-wireless**, **ifup-ppp**, and so on. When a user runs **ifup eth0** manually, the following occurs:

1. **ifup** looks for a file called **/etc/sysconfig/network-scripts/ifcfg-eth0**;
2. if the **ifcfg** file exists, **ifup** looks for the **TYPE** key in that file to determine which type-specific script to call;
3. **ifup** calls **ifup-wireless** or **ifup-eth** or **ifup-XXX** based on **TYPE**;
4. the type-specific scripts do type-specific setup;
5. and then the type-specific scripts let common functions perform **IP**-related tasks like **DHCP** or static setup.

On bootup, **/etc/init.d/network** reads through all the **ifcfg** files and for each one that has **ONBOOT=yes**, it checks whether **NetworkManager** is already starting the **DEVICE** from that **ifcfg** file. If **NetworkManager** is starting that device or has already started it, nothing more is done for that file, and the next **ONBOOT=yes** file is checked. If **NetworkManager** is not yet starting that device, the initscripts will continue with their traditional behavior and call **ifup** for that **ifcfg** file.

The end result is that any **ifcfg** file that has **ONBOOT=yes** is expected to be started on system bootup, either by **NetworkManager** or by the initscripts. This ensures that some legacy network types which **NetworkManager** does not handle (such as ISDN or analog dial-up modems) as well as any new

application not yet supported by **NetworkManager** are still correctly started by the initscripts even though **NetworkManager** is unable to handle them.



NOTE

It is recommended not to store backup **ifcfg** files in the same location as the live ones. The script literally does **ifcfg-*** with an exclude only for these extensions: **.old**, **.orig**, **.rpmnew**, **.rpmorig**, and **.rpmsave**. The best way is not to store backup files anywhere within the **/etc** directory.

1.10. SETTING THE WIRELESS REGULATORY DOMAIN

In Red Hat Enterprise Linux, the **crda** package contains the Central Regulatory Domain Agent that provides the kernel with the wireless regulatory rules for a given jurisdiction. It is used by certain udev scripts and should not be run manually unless debugging udev scripts. The kernel triggers to run **crda** by sending a udev event upon a new regulatory domain change. Regulatory domain changes are triggered by the Linux wireless subsystem (IEEE-802.11). This subsystem uses the **regulatory.bin** file to keep its regulatory database information.

The **setregdomain** utility sets the regulatory domain for your system; it takes no arguments and is normally called through system script such as udev rather than manually by the administrator. If a country code look-up fails, the system administrator can define the **COUNTRY** environment variable in the **/etc/sysconfig/regdomain** file.

See the following man pages for more detailed information about the regulatory domain:

- **setregdomain(1)** man page – set regulatory domain based on country code
- **crda(8)** man page – send to the kernel a wireless regulatory domain for a given ISO or IEC 3166 alpha2
- **regulatory.bin(5)** man page – The Linux wireless regulatory database
- **iw(8)** man page – show or manipulate wireless devices and their configuration

1.11. CONFIGURING NETCONSOLE

The **netconsole** kernel module enables logging of kernel messages over the network to another computer. It allows kernel debugging in the cases where disk logging fails or using the serial console is not possible.

It is necessary to have a **rsyslog** server on the network with the **rsyslogd** daemon listening on the 514/udp port. To configure **rsyslogd** to listen on the 514/udp port and receive messages from the network, uncomment the following lines in the **MODULES** section of **/etc/rsyslog.conf**:

```
$ModLoad imudp
$UDPServerRun 514
```

Restart the **rsyslogd** service for the changes to take effect:

```
]# systemctl restart rsyslog
```

To verify that **rsyslogd** is listening on the 514/udp port, use the following command:

```
]# netstat -l | grep syslog
udp        0      0 0.0.0.0:syslog      0.0.0.0:*
udp6       0      0 [::]:syslog        [::]:*
```

The `0.0.0.0:syslog` and `[::]:syslog` values in the `netstat -l` output mean that `rsyslogd` is listening on default `netconsole` port, which is defined in the `/etc/services` file:

```
]$ cat /etc/services | grep syslog
syslog      514/udp
syslog-conn 601/tcp      # Reliable Syslog Service
syslog-conn 601/udp      # Reliable Syslog Service
syslog-tls  6514/tcp     # Syslog over TLS
syslog-tls  6514/udp     # Syslog over TLS
syslog-tls  6514/dccp    # Syslog over TLS
```

Configuring a Sending Machine

In Red Hat Enterprise Linux, `netconsole` is configured using the file `/etc/sysconfig/netconsole`, which is part of the `initscripts` package. This package is installed by default and it also provides the `netconsole` service.

To configure a sending machine, set the value of the `SYSLOGADDR` variable in the `/etc/sysconfig/netconsole` file to match the IP address of the `syslogd` server, for example:

```
SYSLOGADDR=192.168.0.1
```

Restart the `netconsole` service so the changes take effect. Then, enable `netconsole.service` so it is running again after next reboot:

```
]# systemctl restart netconsole.service
[# systemctl enable netconsole.service
```

By default, the `rsyslogd` server writes the `netconsole` messages from the client in `/var/log/messages` or in the file specified in `rsyslog.conf`.

NOTE

To set `rsyslogd` and `netconsole.service` to use a different port, change the following line in `/etc/rsyslog.conf` to the desired port number:

```
$UDPServerRun <PORT>
```

On the sending machine, uncomment and edit the following line in the `/etc/sysconfig/netconsole` file:

```
SYSLOGPORT=514
```

For more information about `netconsole` configuration and troubleshooting tips, see [Netconsole Kernel Documentation](#).

1.12. ADDITIONAL RESOURCES

- **man(1)** man page – Describes man pages and how to find them.
- **NetworkManager(8)** man page – Describes the network management daemon.
- **NetworkManager.conf(5)** man page – Describes the **NetworkManager** configuration file.
- **/usr/share/doc/initscripts-*version*/sysconfig.txt** – Describes **ifcfg** configuration files and their directives as understood by the legacy network service.
- **/usr/share/doc/initscripts-*version*/examples/networking/** – A directory containing example configuration files.

CHAPTER 2. CONFIGURE IP NETWORKING

2.1. STATIC AND DYNAMIC INTERFACE SETTINGS

When to use static addressing and when to use dynamic addressing? These decisions are subjective, they depend on your accessed needs, your specific requirements. Having a policy, documenting it, and applying it consistently are usually more important than the specific decisions you make. In a traditional company LAN, this is an easier decision to make as you typically have fewer servers than other hosts. Provisioning and installation tools make providing static configurations to new hosts easy and using such tools will change your work flow and requirements. The following two sections are intended to provide just basic guidance to those who have not already been through this decision-making process. Experienced system administrators will likely have their own set of rules and requirements that may differ from what is discussed here. For more information on automated configuration and management, see the **OpenLMI** section in the [Red Hat Enterprise Linux 7 System Administrators Guide](#). The [Red Hat Enterprise Linux 7 Installation Guide](#) documents the use of **kickstart** which can also be used for automating the assignment of network settings.

2.1.1. When to Use Static Network Interface Settings

Use static **IP** addressing on those servers and devices whose network availability you want to ensure when automatic assignment methods, such as **DHCP**, fail. **DHCP**, **DNS**, and authentication servers are typical examples. Interfaces for out-of-band management devices are also worth configuring with static settings as these devices are supposed to work, as far as is possible, independently of other network infrastructure.

For hosts which are not considered vital, but for which static **IP** addressing is still considered desirable, use an automated provisioning method when possible. For example, **DHCP** servers can be configured to provide the same **IP** address to the same host every time. This method could be used for communal printers for example.

All the configuration tools listed in [Section 2.1.3, “Selecting Network Configuration Methods”](#) allow assigning static **IP** addresses manually. The **nmcli** tool is also suitable for use with scripted assignment of network configuration.

2.1.2. When to Use Dynamic Interface Settings

Enable and use dynamic assignment of **IP** addresses and other network information whenever there is no compelling reason not to. The time saved in planning and documenting manual settings can be better spent elsewhere. The *dynamic host control protocol* (**DHCP**) is a traditional method of dynamically assigning network configurations to hosts. See [Section 10.1, “Why Use DHCP?”](#) for more information on this subject.

By default, **NetworkManager** calls the **DHCP** client, **dhclient**, when a profile has been set to obtain addresses automatically, by setting **BOOTPROTO** to **dhcp** in an interface configuration file. If **DHCP** is required, an instance of **dhclient** is started for every Internet protocol, **IPv4** and **IPv6**, on an interface. If **NetworkManager** is not running, or not managing an interface, then the legacy network service will call instances of **dhclient** as required.

2.1.3. Selecting Network Configuration Methods

- To configure an interface using **NetworkManager**'s text user interface tool, **nmtui**, proceed to [Section 2.1.4, “Using the Text User Interface, nmtui”](#)

- To configure an interface using NetworkManager's command-line tool, `nmcli`, proceed to [Section 2.1.5, “Using the NetworkManager Command Line Tool, `nmcli`”](#)
- To configure a network interface manually, see [Section 2.2, “Editing Network Configuration Files”](#).
- To configure a network using graphical user interface tools, proceed to [Section 2.3, “Using NetworkManager with the GNOME Graphical User Interface”](#)

2.1.4. Using the Text User Interface, `nmtui`

The text user interface tool `nmtui` can be used to configure an interface in a terminal window. Issue the following command to start the tool:

```
~]$ nmtui
```

The text user interface appears. Any invalid command prints a usage message.




Figure 2.1. The NetworkManager Text User Interface starting menu

To navigate, use the arrow keys or press `Tab` to step forwards and press `Shift+Tab` to step back through the options. Press `Enter` to select an option. The `Space` bar toggles the status of a check box.

To apply changes after a modified connection which is already active requires a reactivation of the connection. In this case, follow the procedure below:

1. Select the `Activate a connection` menu entry.




Figure 2.2. Activate a Connection

2. Select the modified connection. On the right, click the **Deactivate** button.




Figure 2.3. Deactivate the Modified Connection

3. Choose the connection again and click the **Activate** button.




Figure 2.4. Reactivate the Modified Connection

See [Section 1.5, “Network Configuration Using a Text User Interface \(nmtui\)”](#) for information on installing **nmtui**.

2.1.5. Using the NetworkManager Command Line Tool, **nmcli**

The **nmcli** (NetworkManager Command Line Interface) command-line utility is used for controlling NetworkManager and reporting network status. It can be utilized as a replacement for **nm-applet** or other graphical clients. **nmcli** is used to create, display, edit, delete, activate, and deactivate network connections, as well as control and display network device status.

The **nmcli** utility can be used by both users and scripts for controlling **NetworkManager**:

- For servers, headless machines, and terminals, **nmcli** can be used to control **NetworkManager** directly, without GUI, including creating, editing, starting and stopping network connections and viewing network status.
- For scripts, **nmcli** supports a terse output format which is better suited for script processing. It is a way to integrate network configuration instead of managing network connections manually.

The basic format of a **nmcli** command is as follows:


```
nmcli OPTIONS OBJECT { COMMAND | help }
```

where OBJECT can be one of the following options: **general**, **networking**, **radio**, **connection**, **device**, **agent**, and **monitor**. You can use any prefix of these options in your commands. For example: **nmcli con help**.

Some of useful OPTIONS to get started are:

-t, terse

This mode is designed and suitable for computer (script) processing.

-p, pretty

This causes **nmcli** to produce human-readable output. For example, values are aligned and headers are printed.

-h, help

Prints help information.

The **nmcli** tool has some built-in context-sensitive help:

nmcli help

This command lists the available options and object names to be used in subsequent commands.

nmcli object help

This command displays the list of available actions related to a specified object. For example,

```
nmcli c help
```

Brief Selection of nmcli Examples

The *nmcli-examples(5)* man page has many useful examples. Some of them show:

the overall status of NetworkManager:

```
nmcli general status
```

the current NetworkManager logging status:

```
nmcli general logging
```

all connections:

```
nmcli connection show
```

only currently active connections, add the **--active** or **(-a)** option as follows:

```
nmcli connection show --active
```

devices recognized by NetworkManager and their state:

```
nmcli device status
```

Starting and Stopping an Interface Using nmcli

The **nmcli** tool can be used to start and stop any network interface, including masters. For example:

```
nmcli con up id bond0
nmcli con up id port0
nmcli dev disconnect bond0
nmcli dev disconnect ens3
```



NOTE

The **nmcli connection down** command, deactivates a connection from a device without preventing the device from further auto-activation. The **nmcli device disconnect** command, disconnects a device and prevent the device from automatically activating further connections without manual intervention.

The nmcli Interactive Connection Editor

The **nmcli** tool has an interactive connection editor. To use it, enter the following command:

```
~]$ nmcli con edit
```

You will be prompted to enter a valid connection type from the list displayed. After entering a connection type you will be placed at the **nmcli** prompt. If you are familiar with the connection types you can add a valid connection type option to the **nmcli con edit** command and be taken straight to the **nmcli** prompt. The format is as follows for editing an existing connection profile:

```
nmcli con edit [id | uuid | path] ID
```

For editing a new connection profile, the following format applies:

```
nmcli con edit [type new-connection-type] [con-name new-connection-name]
```

Type **help** at the **nmcli** prompt to see a list of valid commands. Use the **describe** command to get a description of settings and their properties. The format is as follows:

```
describe setting.property
```

For example:

```
nmcli> describe team.config
```

Creating and Modifying a Connection Profile

A connection profile contains the connection property information needed to connect to a data source. To **create** a new profile for NetworkManager, use the following command:

```
nmcli c add {ARGUMENTS}
```

The **nmcli c add** accepts two different types of parameters:

Property names

the names which NetworkManager uses to describe the connection internally. The most important are:

- `connection.type`

```
nmcli c add connection.type bond
```

- `connection.interface-name`

```
nmcli c add connection.interface-name eth0
```

- `connection.id`

```
nmcli c add connection.id "My Connection"
```

See the `nm-settings(5)` man page for more information on properties and their settings.

Aliases names

the human-readable names which are translated to properties internally. The most common are:

- `type` (the `connection.type` property)

```
nmcli c add type bond
```

- `ifname` (the `connection.interface-name` property)

```
nmcli c add ifname eth0
```

- `con-name` (the `connection.id` property)

```
nmcli c add con-name "My Connection"
```

In previous versions of `nmcli`, to create a connection required using the **aliases**. For example, **ifname** `eth0` and **con-name** `My Connection`. A command in the following format could be used:

```
nmcli c add type ethernet ifname eth0 con-name "My Connection"
```

In more recent versions, both the **property** names and the **aliases** can be used interchangeably. The following examples are all valid and equivalent:

```
nmcli c add type ethernet ifname eth0 con-name "My Connection"  
ethernet.mtu 1600
```

```
nmcli c add connection.type ethernet ifname eth0 con-name "My Connection"  
ethernet.mtu 1600
```

```
nmcli c add connection.type ethernet connection.interface-name eth0  
connection.id "My Connection" ethernet.mtu 1600
```

The arguments differ according to the connection types. Only the **type** argument is mandatory for all connection types and **ifname** is mandatory for all types except **bond**, **team**, **bridge** and **vlan**.

type *type_name*

connection type. For example:

```
nmcli c add type bond
```

ifname *interface_name*

interface to bind the connection to. For example:


```
nmcli c add ifname interface_name type ethernet
```

To **modify** one or more properties of a connection profile, use the following command:

```
nmcli c modify
```

For example, to change the **connection.id** from **My Connection** to **My favorite connection** and the **connection.interface-name** to **eth1**, issue the command as follows:

```
nmcli c modify "My Connection" connection.id "My favorite connection"
connection.interface-name eth1
```



NOTE

It is preferable to use the **property names**. The **aliases** are used only for compatibility reasons.

In addition, to set the ethernet MTU to 1600, modify the size as follows:

```
nmcli c modify "My favorite connection" ethernet.mtu 1600
```

To apply changes after a modified connection using nmcli, activate again the connection by entering this command:

```
nmcli con up con-name
```

For example:

```
nmcli con up My-favorite-connection
Connection successfully activated (D-Bus active path:
/org/freedesktop/NetworkManager/ActiveConnection/16)
```

2.1.6. Understanding the nmcli Options

Following are some of the important nmcli property options. See the comprehensive list in the *nmcli(1)* man page :

connection.type

A connection type. Allowed values are: `adsl`, `bond`, `bond-slave`, `bridge`, `bridge-slave`, `bluetooth`, `cdma`, `ethernet`, `gsm`, `infiniband`, `olpc-mesh`, `team`, `team-slave`, `vlan`, `wifi`, `wimax`. Each connection type has type-specific command options. You can see the **TYPE_SPECIFIC_OPTIONS** list in the `nmcli(1)` man page. For example:

- A **gsm** connection requires the access point name specified in an **apn**.

```
nmcli c add connection.type gsm apn access_point_name
```

- A **wifi** device requires the service set identifier specified in a **ssid**.

```
nmcli c add connection.type wifi ssid My identifier
```

connection.interface-name

A device name relevant for the connection.

```
nmcli con add connection.interface-name eth0 type ethernet
```

connection.id

A name uses the connection profile. If you do not specify a connection name, one will be generated as follows:

```
connection.type -connection.interface-name
```

The **connection.id** is the name of a *connection profile* and should not be confused with the interface name which denotes a device (`wlan0`, `ens3`, `em1`). However, users can name the connections after interfaces, but they are not the same thing. There can be multiple connection profiles available for a device. This is particularly useful for mobile devices or when switching a network cable back and forth between different devices. Rather than edit the configuration, create different profiles and apply them to the interface as needed. The **id** option also refers to the connection profile name.

The most important options for `nmcli` commands such as **show**, **up**, **down** are:

id

An identification string assigned by the user to a connection profile. **id** can be used in `nmcli` connection commands to identify a connection. The **NAME** field in the command output always denotes the connection id. It refers to the same connection profile name that the **con-name** does.

uuid

A unique identification string assigned by the system to a connection profile. The **uuid** can be used in `nmcli` connection commands to identify a connection.

2.1.7. Connecting to a Network Using nmcli

To list the currently available network connections, issue a command as follows:

```
~]$ nmcli con show
NAME                                UUID                                TYPE
```

```

DEVICE
Auto Ethernet      9b7f2511-5432-40ae-b091-af2457dfd988  802-3-ethernet  --
ens3               fb157a65-ad32-47ed-858c-102a48e064a2  802-3-ethernet
ens3
MyWiFi             91451385-4eb8-4080-8b82-720aab8328dd  802-11-wireless
wlan0

```

Note that the NAME field in the output always denotes the connection ID (name). It is not the interface name even though it might look the same. In the second connection shown above, `ens3` in the NAME field is the connection ID given by the user to the profile applied to the interface `ens3`. In the last connection shown, the user has assigned the connection ID `MyWiFi` to the interface `wlan0`.

Adding an Ethernet connection means creating a configuration profile which is then assigned to a device. Before creating a new profile, review the available devices as follows:

```

~]$ nmcli device status
DEVICE  TYPE      STATE      CONNECTION
ens3    ethernet  disconnected --
ens9    ethernet  disconnected --
lo      loopback  unmanaged  --

```

To set the device unmanaged by the **NetworkManager**:

```
$ nmcli device set ifname managed no
```

For example, to set `eth2` unmanaged:

```

$ nmcli device status
DEVICE      TYPE      STATE      CONNECTION
bond0       bond      connected  bond0
virbr0      bridge   connected  virbr0
eth1        ethernet  connected  bond-slave-eth1
eth2        ethernet  connected  bond-slave-eth2
eth0        ethernet  unmanaged  --

```

```
$ nmcli device set eth2 managed no
```

```

$ nmcli device status
DEVICE      TYPE      STATE      CONNECTION
bond0       bond      connected  bond0
virbr0      bridge   connected  virbr0
eth1        ethernet  connected  bond-slave-eth1
eth2        ethernet  unmanaged  --
eth0        ethernet  unmanaged  --

```



NOTE

When you set the device unmanaged, **NetworkManager** does not control it. However, the device is still connected.

Adding a Dynamic Ethernet Connection

To add an Ethernet configuration profile with dynamic IP configuration, allowing **DHCP** to assign the network configuration, a command in the following format can be used:

```
nmcli connection add type ethernet con-name connection-name ifname
interface-name
```

For example, to create a dynamic connection profile named *my-office*, issue a command as follows:

```
~]$ nmcli con add type ethernet con-name my-office ifname ens3
Connection 'my-office' (fb157a65-ad32-47ed-858c-102a48e064a2) successfully
added.
```

NetworkManager will set its internal parameter `connection.autoconnect` to `yes`.

NetworkManager will also write out settings to `/etc/sysconfig/network-scripts/ifcfg-my-office` where the `ONBOOT` directive will be set to `yes`.

Note that manual changes to the `ifcfg` file will not be noticed by **NetworkManager** until the interface is next brought up. See [Section 1.9, “Network Configuration Using sysconfig Files”](#) for more information on using configuration files.

To open the Ethernet connection, issue a command as follows:

```
~]$ nmcli con up my-office
Connection successfully activated (D-Bus active path:
/org/freedesktop/NetworkManager/ActiveConnection/5)
```

Review the status of the devices and connections:

```
~]$ nmcli device status
DEVICE  TYPE      STATE      CONNECTION
ens3    ethernet  connected  my-office
ens9    ethernet  disconnected --
lo      loopback  unmanaged  --
```

To change the host name sent by a host to a **DHCP** server, modify the `dhcp-hostname` property as follows:

```
~]$ nmcli con modify my-office my-office ipv4.dhcp-hostname host-name
ipv6.dhcp-hostname host-name
```

To change the **IPv4** client ID sent by a host to a **DHCP** server, modify the `dhcp-client-id` property as follows:

```
~]$ nmcli con modify my-office my-office ipv4.dhcp-client-id client-ID-
string
```

There is no `dhcp-client-id` property for **IPv6**, `dhclient` creates an identifier for **IPv6**. See the `dhclient(8)` man page for details.

To ignore the **DNS** servers sent to a host by a **DHCP** server, modify the `ignore-auto-dns` property as follows:

```
~]$ nmcli con modify my-office my-office ipv4.ignore-auto-dns yes
ipv6.ignore-auto-dns yes
```

See the `nm-settings(5)` man page for more information on properties and their settings.

Example 2.1. Configuring a Dynamic Ethernet Connection Using the Interactive Editor

To configure a dynamic Ethernet connection using the interactive editor, issue commands as follows:

```
~]$ nmcli con edit type ethernet con-name ens3

===| nmcli interactive connection editor |===

Adding a new '802-3-ethernet' connection

Type 'help' or '?' for available commands.
Type 'describe [<setting>.<prop>]' for detailed property description.

You may edit the following settings: connection, 802-3-ethernet
(ethernet), 802-1x, ipv4, ipv6, dcb
nmcli> describe ipv4.method

=== [method] ===
[NM property description]
IPv4 configuration method. If 'auto' is specified then the appropriate
automatic method (DHCP, PPP, etc) is used for the interface and most
other properties can be left unset. If 'link-local' is specified, then
a link-local address in the 169.254/16 range will be assigned to the
interface. If 'manual' is specified, static IP addressing is used and
at least one IP address must be given in the 'addresses' property. If
'shared' is specified (indicating that this connection will provide
network access to other computers) then the interface is assigned an
address in the 10.42.x.1/24 range and a DHCP and forwarding DNS server
are started, and the interface is NAT-ed to the current default network
connection. 'disabled' means IPv4 will not be used on this connection.
This property must be set.

nmcli> set ipv4.method auto
nmcli> save
Saving the connection with 'autoconnect=yes'. That might result in an
immediate activation of the connection.
Do you still want to save? [yes] yes
Connection 'ens3' (090b61f7-540f-4dd6-bf1f-a905831fc287) successfully
saved.
nmcli> quit
~]$
```

The default action is to save the connection profile as persistent. If required, the profile can be held in memory only, until the next restart, by means of the **save temporary** command.

Adding a Static Ethernet Connection

To add an Ethernet connection with static IPv4 configuration, a command in the following format can be used:

```
nmcli connection add type ethernet con-name connection-name ifname
interface-name ip4 address gw4 address
```

IPv6 address and gateway information can be added using the **ip6** and **gw6** options.

For example, a command to create a static Ethernet connection with only **IPv4** address and gateway is as follows:

```
~]$ nmcli con add type ethernet con-name test-lab ifname ens9 ip4
10.10.10.10/24 \
gw4 10.10.10.254
```

Optionally, at the same time specify **IPv6** address and gateway for the device as follows:

```
~]$ nmcli con add type ethernet con-name test-lab ifname ens9 ip4
10.10.10.10/24 \
gw4 10.10.10.254 ip6 abbe::cafe gw6 2001:db8::1
Connection 'test-lab' (05abfd5e-324e-4461-844e-8501ba704773) successfully
added.
```

NetworkManager will set its internal parameter `ipv4.method` to `manual` and `connection.autoconnect` to `yes`. **NetworkManager** will also write out settings to `/etc/sysconfig/network-scripts/ifcfg-my-office` where the corresponding `BOOTPROTO` will be set to `none` and `ONBOOT` will be set to `yes`.

Note that manual changes to the `ifcfg` file will not be noticed by **NetworkManager** until the interface is next brought up. See [Section 1.9, “Network Configuration Using sysconfig Files”](#) for more information on using configuration files.

To set two **IPv4 DNS** server addresses:

```
~]$ nmcli con mod test-lab ipv4.dns "8.8.8.8 8.8.4.4"
```

Note that this will replace any previously set **DNS** servers. To set two **IPv6 DNS** server addresses:

```
~]$ nmcli con mod test-lab ipv6.dns "2001:4860:4860::8888
2001:4860:4860::8844"
```

Note that this will replace any previously set **DNS** servers. Alternatively, to add additional **DNS** servers to any previously set, use the `+` prefix as follows:

```
~]$ nmcli con mod test-lab +ipv4.dns "8.8.8.8 8.8.4.4"
```

```
~]$ nmcli con mod test-lab +ipv6.dns "2001:4860:4860::8888
2001:4860:4860::8844"
```

To open the new Ethernet connection, issue a command as follows:

```
~]$ nmcli con up test-lab ifname ens9
Connection successfully activated (D-Bus active path:
/org/freedesktop/NetworkManager/ActiveConnection/6)
```

Review the status of the devices and connections:

```
~]$ nmcli device status
DEVICE  TYPE      STATE      CONNECTION
ens3    ethernet  connected  my-office
```

```
ens9    ethernet    connected    test-lab
lo      loopback    unmanaged    --
```

To view detailed information about the newly configured connection, issue a command as follows:

```
~]$ nmcli -p con show test-lab
=====
=====
                                Connection profile details (test-lab)
=====
=====
connection.id:                    test-lab
connection.uuid:                  05abfd5e-324e-4461-844e-
8501ba704773
connection.interface-name:       ens9
connection.type:                 802-3-ethernet
connection.autoconnect:         yes
connection.timestamp:            1410428968
connection.read-only:           no
connection.permissions:
connection.zone:                 --
connection.master:              --
connection.slave-type:          --
connection.secondaries:
connection.gateway-ping-timeout: 0
[output truncated]
```

The use of the `-p`, `--pretty` option adds a title banner and section breaks to the output.

Example 2.2. Configuring a Static Ethernet Connection Using the Interactive Editor

To configure a static Ethernet connection using the interactive editor, issue commands as follows:

```
~]$ nmcli con edit type ethernet con-name ens3

===| nmcli interactive connection editor |===

Adding a new '802-3-ethernet' connection

Type 'help' or '?' for available commands.
Type 'describe [>setting<.>prop<|>' for detailed property description.

You may edit the following settings: connection, 802-3-ethernet
(ethernet), 802-1x, ipv4, ipv6, dcb
nmcli> set ipv4.addresses 192.168.122.88/24
Do you also want to set 'ipv4.method' to 'manual'? [yes]: yes
nmcli>
nmcli> save temporary
Saving the connection with 'autoconnect=yes'. That might result in an
immediate activation of the connection.
Do you still want to save? [yes] no
nmcli> save
Saving the connection with 'autoconnect=yes'. That might result in an
immediate activation of the connection.
Do you still want to save? [yes] yes
Connection 'ens3' (704a5666-8cbd-4d89-b5f9-fa65a3dbc916) successfully
```

```

saved.
nmcli> quit
~]$

```

The default action is to save the connection profile as persistent. If required, the profile can be held in memory only, until the next restart, by means of the `save temporary` command.

Locking a Profile to a Specific Device

To lock a profile to a specific interface device, the commands used in the examples above include the interface name. For example:

```

nmcli connection add type ethernet con-name connection-name ifname
interface-name

```

To make a profile usable for all compatible Ethernet interfaces, issue a command as follows:

```

nmcli connection add type ethernet con-name connection-name ifname "*"

```

Note that you have to use the `ifname` argument even if you do not want to set a specific interface. Use the wildcard character `*` to specify that the profile can be used with any compatible device.

To lock a profile to a specific MAC address, use a command in the following format:

```

nmcli connection add type ethernet con-name "connection-name" ifname "*"
mac 00:00:5E:00:53:00

```







Adding a Wi-Fi Connection

To view the available Wi-Fi access points, issue a command as follows:

```

~]$ nmcli dev wifi list

```

	SSID	MODE	CHAN	RATE	SIGNAL	BARS	SECURITY
	FedoraTest	Infra	11	54 MB/s	98		WPA1
	Red Hat Guest	Infra	6	54 MB/s	97		WPA2
	Red Hat	Infra	6	54 MB/s	77		WPA2 802.1X
*	Red Hat	Infra	40	54 MB/s	66		WPA2 802.1X
	VoIP	Infra	1	54 MB/s	32		WEP
	MyCafe	Infra	11	54 MB/s	39		WPA2

To create a Wi-Fi connection profile with static **IP** configuration, but allowing automatic **DNS** address assignment, issue a command as follows:

```

~]$ nmcli con add con-name MyCafe ifname wlan0 type wifi ssid MyCafe \
ip4 192.168.100.101/24 gw4 192.168.100.1

```

To set a WPA2 password, for example “caffeine”, issue commands as follows:

```

~]$ nmcli con modify MyCafe wifi-sec.key-mgmt wpa-psk
~]$ nmcli con modify MyCafe wifi-sec.psk caffeine

```

See the [Red Hat Enterprise Linux 7 Security Guide](#) for information on password security.

To change Wi-Fi state, issue a command in the following format:

■

```
~]$ nmcli radio wifi [on | off ]
```

Changing a Specific Property

To check a specific property, for example `mtu`, issue a command as follows:

```
~]$ nmcli connection show id 'MyCafe' | grep mtu
802-11-wireless.mtu:                auto
```

To change the property of a setting, issue a command as follows:

```
~]$ nmcli connection modify id 'MyCafe' 802-11-wireless.mtu 1350
```

To verify the change, issue a command as follows:

```
~]$ nmcli connection show id 'MyCafe' | grep mtu
802-11-wireless.mtu:                1350
```

Note that **NetworkManager** refers to parameters such as **802-3-ethernet** and **802-11-wireless** as the setting, and `mtu` as a property of the setting. See the `nm-settings(5)` man page for more information on properties and their settings.

2.1.8. Configuring Static Routes Using nmcli

To configure static routes using the `nmcli` tool, the command line or the interactive editor mode can be used.

Example 2.3. Configuring Static Routes Using nmcli

To configure a static route for an existing Ethernet connection using the command line, enter a command as follows:

```
~]# nmcli connection modify eth0 +ipv4.routes "192.168.122.0/24
10.10.10.1"
```

This will direct traffic for the **192.168.122.0/24** subnet to the gateway at **10.10.10.1**

Example 2.4. Configuring Static Routes Using nmcli Editor

To configure a static route for an Ethernet connection using the interactive editor, issue commands as follows:

```
~]$ nmcli con edit type ethernet con-name ens3

===| nmcli interactive connection editor |===

Adding a new '802-3-ethernet' connection

Type 'help' or '?' for available commands.
Type 'describe [>setting<.>prop<'] for detailed property description.

You may edit the following settings: connection, 802-3-ethernet
(ethernet), 802-1x, ipv4, ipv6, dcb
```

```
nmcli> set ipv4.routes 192.168.122.0/24 10.10.10.1
nmcli>
nmcli> save persistent
Saving the connection with 'autoconnect=yes'. That might result in an
immediate activation of the connection.
Do you still want to save? [yes] yes
Connection 'ens3' (704a5666-8cbd-4d89-b5f9-fa65a3dbc916) successfully
saved.
nmcli> quit
~]$
```

2.2. EDITING NETWORK CONFIGURATION FILES

2.2.1. Configuring a Network Interface Using ifcfg Files

Interface configuration files control the software interfaces for individual network devices. As the system boots, it uses these files to determine what interfaces to bring up and how to configure them. These files are usually named `ifcfg-name`, where the suffix *name* refers to the name of the device that the configuration file controls. By convention, the `ifcfg` file's suffix is the same as the string given by the **DEVICE** directive in the configuration file itself.

Static Network Settings

For example, to configure an interface with static network settings using `ifcfg` files, for an interface with the name `eth0`, create a file with the name `ifcfg-eth0` in the `/etc/sysconfig/network-scripts/` directory, that contains:

- For **IPv4** configuration

```
DEVICE=eth0
BOOTPROTO=none
ONBOOT=yes
PREFIX=24
IPADDR=10.0.1.27
```

- For **IPv6** configuration

```
DEVICE=eth0
BOOTPROTO=none
ONBOOT=yes
IPV6INIT=yes
IPV6ADDR=2001:db8::2/48
```

You do not need to specify the network or broadcast address as this is calculated automatically by **ipcalc**.

For more **IPv6** `ifcfg` configuration options, see `nm-settings-ifcfg-rh(5)` man page.



IMPORTANT

In Red Hat Enterprise Linux 7, the naming convention for network interfaces has been changed, as explained in [Chapter 8, Consistent Network Device Naming](#). Specifying the hardware or MAC address using **HWADDR** directive can influence the device naming procedure.

Dynamic Network Settings

For example, to configure an interface with dynamic network settings using **ifcfg** files, for an interface with the name **em1**, create a file with the name **ifcfg-em1** in the **/etc/sysconfig/network-scripts/** directory, that contains:

```
DEVICE=em1
BOOTPROTO=dhcp
ONBOOT=yes
```

To configure an interface to send a different host name to the **DHCP** server, add the following line to the **ifcfg** file:

```
DHCP_HOSTNAME=hostname
```

To configure an interface to send a different fully qualified domain name (FQDN) to the **DHCP** server, add the following line to the **ifcfg** file:

```
DHCP_FQDN=fully.qualified.domain.name
```



NOTE

Only one directive, either **DHCP_HOSTNAME** or **DHCP_FQDN**, should be used in a given **ifcfg** file. In case both **DHCP_HOSTNAME** and **DHCP_FQDN** are specified, only the latter is used.

To configure an interface to use particular **DNS** servers, add the following lines to the **ifcfg** file:

```
PEERDNS=no
DNS1=ip-address
DNS2=ip-address
```

where *ip-address* is the address of a **DNS** server. This will cause the network service to update **/etc/resolv.conf** with the specified **DNS** servers specified. Only one **DNS** server address is necessary, the other is optional.

By default, **NetworkManager** calls the **DHCP** client, **dhclient**, when a profile has been set to obtain addresses automatically by setting **BOOTPROTO** to **dhcp** in an interface configuration file. If **DHCP** is required, an instance of **dhclient** is started for every Internet protocol, **IPv4** and **IPv6**, on an interface. If **NetworkManager** is not running, or is not managing an interface, then the legacy network service will call instances of **dhclient** as required. For more details, see [Section 2.1.2, “When to Use Dynamic Interface Settings”](#).



IMPORTANT

In order to apply the configuration, you need to enter the `nmcli c reload` command.

2.2.2. Configuring the Network Settings from the Kernel Command-line

When connecting to the root file system on an iSCSI target from an interface, the network settings are not configured on the installed system. To work around this problem:

1. Install the **dracut** utility. For information on using **dracut**, see [Red Hat Enterprise Linux System Administrator's Guide](#)
2. Set the configuration using the **ip** option on the kernel command-line:

```
ip<client-IP-number>:[<server-id>]:<gateway-IP-number>:<netmask>:
<client-hostname>:<interface>:{dhcp|dhcp6|auto6|on|any|none|off}
```

- **dhcp** - DHCP configuration
- **dhcp6** - DHCP IPv6 configuration
- **auto6** - automatic IPv6 configuration
- **on, any** - any protocol available in the kernel (default)
- **none, off** - no autoconfiguration, static network configuration

For example:

```
ip=192.168.180.120:192.168.180.100:192.168.180.1:255.255.255.0::eth0:off
```

3. Set the name server configuration:

```
nameserver=srv1 [nameserver=srv2 [nameserver=srv3 [...]]]
```

The **dracut** utility sets up a network connection and generates new **ifcfg** files that can be copied to the `/etc/sysconfig/network-scripts/` file.

2.2.3. Configuring a Network Interface Using ip Commands

The **ip** utility can be used to assign IP addresses to an interface. The command takes the following form:

```
ip addr [ add | del ] address dev ifname
```

Assigning a Static Address Using ip Commands

To assign an IP address to an interface, issue a command as **root** as follows:

```
~]# ip address add 10.0.0.3/24 dev eth0
The address assignment of a specific device can be viewed as follows:
~]# ip addr show dev eth0
2: eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state
```

```
UP qlen 1000
    link/ether f0:de:f1:7b:6e:5f brd ff:ff:ff:ff:ff:ff
    inet 10.0.0.3/24 brd 10.0.0.255 scope global global eth0
        valid_lft 58682sec preferred_lft 58682sec
    inet6 fe80::f2de:f1ff:fe7b:6e5f/64 scope link
        valid_lft forever preferred_lft forever
```

Further examples and command options can be found in the **ip-address(8)** manual page.

Configuring Multiple Addresses Using ip Commands

As the **ip** utility supports assigning multiple addresses to the same interface it is no longer necessary to use the alias interface method of binding multiple addresses to the same interface. The **ip** command to assign an address can be repeated multiple times in order to assign multiple address. For example:

```
~]# ip address add 192.168.2.223/24 dev eth1
~]# ip address add 192.168.4.223/24 dev eth1
~]# ip addr
3: eth1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state
UP qlen 1000
    link/ether 52:54:00:fb:77:9e brd ff:ff:ff:ff:ff:ff
    inet 192.168.2.223/24 scope global eth1
    inet 192.168.4.223/24 scope global eth1
```

The commands for the **ip** utility are documented in the **ip(8)** manual page.



NOTE

ip commands given on the command line will not persist after a system restart.

2.2.4. Static Routes and the Default Gateway

Static routes are for traffic that must not, or should not, go through the default gateway. Routing is often handled by devices on the network dedicated to routing (although any device can be configured to perform routing). Therefore, it is often not necessary to configure static routes on Red Hat Enterprise Linux servers or clients. Exceptions include traffic that must pass through an encrypted VPN tunnel or traffic that should take a specific route for reasons of cost or security. The default gateway is for any and all traffic which is not destined for the local network and for which no preferred route is specified in the routing table. The default gateway is traditionally a dedicated network router.



NOTE

To expand your expertise, you might also be interested in the [Red Hat System Administration I \(RH124\)](#) training course.

If static routes are required, they can be added to the routing table by means of the **ip route add** command and removed using the **ip route del** command. The more frequently used **ip route** commands take the following form:

```
ip route [ add | del | change | append | replace ] destination-address
```

See the **ip-route(8)** man page for more details on the options and formats.

Use the **ip route** command without options to display the **IP** routing table. For example:


```
~]$ ip route
default via 192.168.122.1 dev ens9 proto static metric 1024
192.168.122.0/24 dev ens9 proto kernel scope link src 192.168.122.107
192.168.122.0/24 dev eth0 proto kernel scope link src 192.168.122.126
```

To add a static route to a host address, in other words to a single **IP** address, issue a command as **root**:

```
ip route add 192.0.2.1 via 10.0.0.1 [dev ifname]
```

Where *192.0.2.1* is the **IP** address of the host in dotted decimal notation, *10.0.0.1* is the next hop address and *ifname* is the exit interface leading to the next hop.

To add a static route to a network, in other words to an **IP** address representing a range of **IP** addresses, issue the following command as **root**:

```
ip route add 192.0.2.0/24 through 10.0.0.1 [dev ifname]
```

where *192.0.2.0* is the **IP** address of the destination network in dotted decimal notation and */24* is the network prefix. The network prefix is the number of enabled bits in the subnet mask. This format of network address slash network prefix length is sometimes referred to as *classless inter-domain routing* (CIDR) notation.

Static route configuration can be stored per-interface in a `/etc/sysconfig/network-scripts/route-interface` file. For example, static routes for the `eth0` interface would be stored in the `/etc/sysconfig/network-scripts/route-eth0` file. The `route-interface` file has two formats: `ip` command arguments and `network/netmask` directives. These are described below.

See the `ip-route(8)` man page for more information on the `ip route` command.

Configuring The Default Gateway

The default gateway is determined by the network scripts which parse the `/etc/sysconfig/network` file first and then the network interface `ifcfg` files for interfaces that are “up”. The `ifcfg` files are parsed in numerically ascending order, and the last `GATEWAY` directive to be read is used to compose a default route in the routing table.

The default route can thus be indicated by means of the `GATEWAY` directive, either globally or in interface-specific configuration files. However, in Red Hat Enterprise Linux the use of the global `/etc/sysconfig/network` file is deprecated, and specifying the gateway should now only be done in per-interface configuration files.

In dynamic network environments, where mobile hosts are managed by **NetworkManager**, gateway information is likely to be interface specific and is best left to be assigned by **DHCP**. In special cases where it is necessary to influence **NetworkManager**'s selection of the exit interface to be used to reach a gateway, make use of the `DEFROUTE=no` command in the `ifcfg` files for those interfaces which do not lead to the default gateway.

2.2.5. Configuring Static Routes in ifcfg files

Static routes set using `ip` commands at the command prompt will be lost if the system is shutdown or restarted. To configure static routes to be persistent after a system restart, they must be placed in per-interface configuration files in the `/etc/sysconfig/network-scripts/` directory. The file name should be of the format `route-ifname`. There are two types of commands to use in the configuration

files; **ip** commands as explained in [Section 2.2.5.1, “Static Routes Using the IP Command Arguments Format”](#) and the *Network/Netmask* format as explained in [Section 2.2.5.2, “Network/Netmask Directives Format”](#).

2.2.5.1. Static Routes Using the IP Command Arguments Format

If required in a per-interface configuration file, for example `/etc/sysconfig/network-scripts/route-eth0`, define a route to a default gateway on the first line. This is only required if the gateway is not set through **DHCP** and is not set globally in the `/etc/sysconfig/network` file:

```
default via 192.168.1.1 dev interface
```

where *192.168.1.1* is the **IP** address of the default gateway. The *interface* is the interface that is connected to, or can reach, the default gateway. The **dev** option can be omitted, it is optional. Note that this setting takes precedence over a setting in the `/etc/sysconfig/network` file.

If a route to a remote network is required, a static route can be specified as follows. Each line is parsed as an individual route:

```
10.10.10.0/24 via 192.168.1.1 [dev interface]
```

where *10.10.10.0/24* is the network address and prefix length of the remote or destination network. The address *192.168.1.1* is the **IP** address leading to the remote network. It is preferably the *next hop address* but the address of the exit interface will work. The “next hop” means the remote end of a link, for example a gateway or router. The **dev** option can be used to specify the exit interface *interface* but it is not required. Add as many static routes as required.

The following is an example of a *route-interface* file using the **ip** command arguments format. The default gateway is **192.168.0.1**, interface `eth0` and a leased line or WAN connection is available at **192.168.0.10**. The two static routes are for reaching the **10.10.10.0/24** network and the **172.16.1.10/32** host:

```
default via 192.168.0.1 dev eth0
10.10.10.0/24 via 192.168.0.10 dev eth0
172.16.1.10/32 via 192.168.0.10 dev eth0
```

In the above example, packets going to the local **192.168.0.0/24** network will be directed out the interface attached to that network. Packets going to the **10.10.10.0/24** network and **172.16.1.10/32** host will be directed to **192.168.0.10**. Packets to unknown, remote, networks will use the default gateway therefore static routes should only be configured for remote networks or hosts if the default route is not suitable. Remote in this context means any networks or hosts that are not directly attached to the system.

For **IPv6** configuration, an example of a *route6-interface* file in **ip route** format:

```
2001:db8:1::/48 via 2001:db8::1 metric 2048
2001:db8:2::/48
```


Specifying an exit interface is optional. It can be useful if you want to force traffic out of a specific interface. For example, in the case of a VPN, you can force traffic to a remote network to pass through a `tun0` interface even when the interface is in a different subnet to the destination network.

The **ip route** format can be used to specify a source address. For example:

```
10.10.10.0/24 via 192.168.0.10 src 192.168.0.2
```

or to define an existing policy-based routing configuration, which specifies multiple routing tables. For example:

```
10.10.10.0/24 via 192.168.0.10 table 1
10.10.10.0/24 via 192.168.0.10 table 2
```



IMPORTANT

If the default gateway is already assigned by **DHCP** and if the same gateway with the same metric is specified in a configuration file, an error during start-up, or when bringing up an interface, will occur. The following error message may be shown: "RTNETLINK answers: File exists". This error may be ignored.

2.2.5.2. Network/Netmask Directives Format

You can also use the network/netmask directives format for **route-*interface*** files. The following is a template for the network/netmask format, with instructions following afterwards:

```
ADDRESS0=10.10.10.0
NETMASK0=255.255.255.0
GATEWAY0=192.168.1.1
```

- **ADDRESS0=10.10.10.0** is the network address of the remote network or host to be reached.
- **NETMASK0=255.255.255.0** is the netmask for the network address defined with **ADDRESS0=10.10.10.0**.
- **GATEWAY0=192.168.1.1** is the default gateway, or an **IP** address that can be used to reach **ADDRESS0=10.10.10.0**

The following is an example of a **route-*interface*** file using the network/netmask directives format. The default gateway is **192.168.0.1** but a leased line or WAN connection is available at **192.168.0.10**. The two static routes are for reaching the **10.10.10.0/24** and **172.16.1.0/24** networks:

```
ADDRESS0=10.10.10.0
NETMASK0=255.255.255.0
GATEWAY0=192.168.0.10
ADDRESS1=172.16.1.10
NETMASK1=255.255.255.0
GATEWAY1=192.168.0.10
```

Subsequent static routes must be numbered sequentially, and must not skip any values. For example, **ADDRESS0**, **ADDRESS1**, **ADDRESS2**, and so on.

By default, forwarding packets from one interface to another, or out of the same interface, is disabled for security reasons. This prevents the system acting as a router for external traffic. If you need the system to route external traffic, such as when sharing a connection or configuring a VPN server, you will need to enable IP forwarding. See the [Red Hat Enterprise Linux 7 Security Guide](#) for more details.

2.2.6. Configuring a VPN

IPsec, provided by **Libreswan**, is the preferred method for creating a VPN in Red Hat Enterprise Linux 7. **Libreswan** is an open-source, user-space **IPsec** implementation for VPN. Configuring an **IPsec** VPN using the command line is documented in the [Red Hat Enterprise Linux 7 Security Guide](#).

2.3. USING NETWORKMANAGER WITH THE GNOME GRAPHICAL USER INTERFACE

In Red Hat Enterprise Linux 7, **NetworkManager** does not have its own graphical user interface (GUI). The network connection icon on the top right of the desktop is provided as part of the GNOME Shell and the **Network** settings configuration tool is provided as part of the new GNOME **control-center** GUI. The **nm-connection-editor** GUI applies the functionality which is not provided the GNOME **control-center** such as configuring bonds and teaming connections.

2.3.1. Connecting to a Network Using a GUI

There are two ways to access the **Network** settings window of the **control-center** application:

- Press the **Super** key to enter the Activities Overview, type **control network**, and then press **Enter**. The **Network** settings tool appears. Proceed to [Section 2.3.2, “Configuring New and Editing Existing Connections”](#).
- Click on the GNOME Shell network connection icon in the top right-hand corner of the screen to open its menu.




Figure 2.5. The Network utility being selected in GNOME

When you click on the GNOME Shell network connection icon, you are presented with:

- a list of categorized networks you are currently connected to (such as **Wired** and **Wi-Fi**);
- a list of all **Available Networks** that **NetworkManager** has detected;
- options for connecting to any configured Virtual Private Networks (VPNs); and,
- an option for selecting the **Network Settings** menu entry.

If you are connected to a network, this is indicated by a **black bullet** on the left of the connection name.

Click **Network Settings**. The **Network** settings tool appears. Proceed to [Section 2.3.2, “Configuring New and Editing Existing Connections”](#).

2.3.2. Configuring New and Editing Existing Connections

The **Network** settings window shows the connection status, its type and interface, its **IP** address and routing details, and so on.



Figure 2.6. Configure Networks Using the Network Settings Window

The **Network** settings window has a menu on the left-hand side showing the available network devices or interfaces. This includes software interfaces such as for VLANs, bridges, bonds, and teams. On the right-hand side, the *connection profiles* are shown for the selected network device or interface. A profile is a named collection of settings that can be applied to an interface. Below that is a plus and a minus button for adding and deleting new network connections, and on the right a gear wheel icon will appear for editing the connection details of the selected network device or VPN connection. To add a new connection, click the plus symbol to open the **Add Network Connection** window and proceed to [Section 2.3.2.1, “Configuring a New Connection”](#).

Editing an Existing Connection

Clicking on the gear wheel icon of an existing connection profile in the **Network** settings window opens the **Network** details window, from where you can perform most network configuration tasks such as **IP** addressing, **DNS**, and routing configuration.



Figure 2.7. Configure Networks Using the Network Connection Details Window

To apply changes after a connection modification, you can click the button from ON to OFF to deactivate and set it to ON again to reactivate the device. See [Section 2.3.2, “Configuring New and Editing Existing Connections”](#) for more details.

2.3.2.1. Configuring a New Connection

In the **Network** settings window, click the plus sign below the menu to open the **Add Network Connection** window. This displays a list of connection types that can be added.

Then, to configure:

- **VPN connections**, click the **VPN** entry and proceed to [Section 2.4, “Establishing a VPN Connection”](#);
- **Bond connections**, click the **Bond** entry and proceed to [Section 4.6.1, “Establishing a Bond Connection”](#);
- **Bridge connections**, click the **Bridge** entry and proceed to [Section 6.4.1, “Establishing a Bridge Connection”](#);
- **VLAN connections**, click the **VLAN** entry and proceed to [Section 7.5.1, “Establishing a VLAN Connection”](#); or,
- **Team connections**, click the **Team** entry and proceed to [Section 5.13, “Creating a Network Team Using a GUI”](#).

2.3.3. Connecting to a Network Automatically

For any connection type you add or configure, you can choose whether you want **NetworkManager** to try to connect to that network automatically when it is available.

Procedure 2.1. Configuring NetworkManager to Connect to a Network Automatically When Detected

1. Press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears.
2. Select the network interface from the left-hand-side menu.
3. Click on the gear wheel icon of a connection profile on the right-hand side menu. If you have only one profile associated with the selected interface the gear wheel icon will be in the lower right-hand-side corner. The **Network** details window appears.
4. Select the **Identity** menu entry on the left. The **Network** window changes to the identity view.
5. Select **Connect automatically** to cause **NetworkManager** to auto-connect to the connection whenever **NetworkManager** detects that it is available. Clear the check box if you do not want **NetworkManager** to connect automatically. If the check box is clear, you will have to select that connection manually in the network connection icon's menu to cause it to connect.

2.3.4. Common Configuration Options in nm-connection-editor

If you are using the `nm-connection-editor` utility, there are five configuration options which are common to the most connection types (ethernet, wifi, mobile broadband, DSL):

1. Run the `nm-connection-editor`. Then, click the **Add** button to choose a connection type:




Figure 2.8. Add a connection type



Figure 2.9. Choose a connection type

Alternatively for an existing connection type, click the **Edit** button from the **Network Connections** dialog.

2. Select the **General** tab in the **Editing** dialog:

Figure 2.10. Configuration options in nm-connection-editor

- **Connection name** – Enter a descriptive name for your network connection. This name will be used to list this connection in the menu of the **Network** window.
- **Automatically connect to this network when it is available** – Select this box if you want **NetworkManager** to auto-connect to this connection when it is available. See [Section 2.3.3, “Connecting to a Network Automatically”](#) for more information.
- **All users may connect to this network** – Select this box to create a connection available to all users on the system. Changing this setting may require root privileges. See [Section 2.3.5, “System-wide and Private Connection Profiles”](#) for details.
- **Automatically connect to VPN when using this connection** – Select this box if you want **NetworkManager** to auto-connect to a VPN connection when it is available. Select the VPN from the drop-down menu.
- **Firewall Zone** – Select the firewall zone from the drop-down menu. See the [Red Hat Enterprise Linux 7 Security Guide](#) for more information on firewall zones.



NOTE

For the VPN connection type, only three of the above configuration options are available: **Connection name**, **All users may connect to this network** and **Firewall Zone**.

2.3.5. System-wide and Private Connection Profiles

NetworkManager stores all *connection profiles*. A profile is a named collection of settings that can be applied to an interface. **NetworkManager** stores these connection profiles for system-wide use

(*system connections*), as well as all *user connection* profiles. Access to the connection profiles is controlled by permissions which are stored by **NetworkManager**. See the **nm-settings(5)** man page for more information on the **connection settings permissions** property. The permissions correspond to the **USERS** directive in the **ifcfg** files. If the **USERS** directive is not present, the network profile will be available to all users. As an example, the following command in an **ifcfg** file will make the connection available only to the users listed:

```
USERS="joe bob alice"
```

This can also be set using graphical user interface tools. In **nm-connection-editor**, there is the corresponding **All users may connect to this network** check box on the **General** tab, and in the GNOME **control-center** Network settings Identity window, there is the **Make available to other users** check box.

NetworkManager's default policy is to allow all users to create and modify system-wide connections. Profiles that should be available at boot time cannot be private because they will not be visible until the user logs in. For example, if user **user** creates a connection profile **user-em2** with the **Connect Automatically** check box selected but with the **Make available to other users** not selected, then the connection will not be available at boot time.

To restrict connections and networking, there are two options which can be used alone or in combination:

- Clear the **Make available to other users** check box, which changes the connection to be modifiable and usable only by the user doing the changing.
- Use the **polkit** framework to restrict permissions of general network operations on a per-user basis.

The combination of these two options provides fine-grained security and control over networking. See the **polkit(8)** man page for more information on **polkit**.

Note that VPN connections are **always** created as private-per-user, since they are assumed to be more private than a Wi-Fi or Ethernet connection.

Procedure 2.2. Changing a Connection to Be User-specific Instead of System-Wide, or Vice Versa

Depending on the system's policy, you may need root privileges on the system in order to change whether a connection is user-specific or system-wide.

1. Press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears.
2. Select the network interface from the left-hand-side menu.
3. Click on the gear wheel icon of a connection profile on the right-hand side menu. If you have only one profile associated with the selected interface the gear wheel icon will be in the lower right-hand-side corner. The **Network** details window appears.
4. Select the **Identity** menu entry on the left. The **Network** window changes to the identity view.
5. Select the **Make available to other users** check box to cause **NetworkManager** to make the connection available system-wide.

Conversely, clear the **Make available to other users** check box to make the

connection user-specific.

2.3.6. Configuring a Wired (Ethernet) Connection

To configure a wired network connection, press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears.

Select the **Wired** network interface from the left-hand-side menu if it is not already highlighted.

The system creates and configures a single wired *connection profile* called **Wired** by default. A profile is a named collection of settings that can be applied to an interface. More than one profile can be created for an interface and applied as needed. The default profile cannot be deleted but its settings can be changed. You can edit the default **Wired** profile by clicking the gear wheel icon. You can create a new wired connection profile by clicking the **Add Profile** button. Connection profiles associated with a selected interface are shown on the right-hand side menu.

When you add a new connection by clicking the **Add Profile** button, **NetworkManager** creates a new configuration file for that connection and then opens the same dialog that is used for editing an existing connection. The difference between these dialogs is that an existing connection profile has a **Details** and **Reset** menu entry. In effect, you are always editing a connection profile; the difference only lies in whether that connection previously existed or was just created by **NetworkManager** when you clicked **Add Profile**.

Basic Configuration Options

You can see the following configuration settings in the **Wired** dialog, by selecting the **Identity** menu entry on the left:

The screenshot shows the 'Wired' network configuration window with the 'Identity' tab selected in the left-hand menu. The main area contains the following settings:

- Name:** A text input field.
- MAC Address:** A text input field with a dropdown arrow on the right.
- Cloned Address:** A text input field.
- MTU:** A text input field showing 'automatic', with minus and plus buttons on the right.
- Firewall Zone:** A dropdown menu showing 'Default'.
- Connect automatically:** A checked checkbox.
- Make available to other users:** A checked checkbox.
- Buttons:** 'Cancel' and 'Apply' buttons at the bottom right.

Figure 2.11. Basic Configuration options of a Wired Connection

- **Name** – Enter a descriptive name for your network connection. This name will be used to list this connection in the menu of the **Network** window.
- **MAC Address** – Select the MAC address of the interface this profile must be applied to.
- **Cloned Address** – If required, enter a different MAC address to use.
- **MTU** – If required, enter a specific *maximum transmission unit* (MTU) to use. The MTU value represents the size in bytes of the largest packet that the link layer will transmit. This value defaults to **1500** and does not generally need to be specified or changed.
- **Firewall Zone** – If required, select a different firewall zone to apply. See the [Red Hat Enterprise Linux 7 Security Guide](#) for more information on firewall zones.
- **Connect automatically** – Select this box if you want **NetworkManager** to auto-connect to this connection when it is available. See [Section 2.3.3, “Connecting to a Network Automatically”](#) for more information.
- **Make available to other users** – Select this box to create a connection available to all users on the system. Changing this setting may require root privileges. See [Section 2.3.5, “System-wide and Private Connection Profiles”](#) for details.

Saving Your New (or Modified) Connection and Making Further Configurations

Once you have finished editing your wired connection, click the **Apply** button to save your customized configuration. If the profile was in use while being edited, restart the connection to make **NetworkManager** apply the changes. If the profile is OFF, set it to ON or select it in the network connection icon's menu. See [Section 2.3.1, “Connecting to a Network Using a GUI”](#) for information on using your new or altered connection.

You can further configure an existing connection by selecting it in the **Network** window and clicking the gear wheel icon to return to the editing dialog.

Then, to configure:

- **port-based Network Access Control (PNAC)**, click the **802.1X Security** tab and proceed to [Section 2.7.2, “Configuring 802.1X Security”](#);
- **IPv4** settings for the connection, click the **IPv4 Settings** tab and proceed to [Section 2.7.6, “Configuring IPv4 Settings”](#); or,
- **IPv6** settings for the connection, click the **IPv6 Settings** tab and proceed to [Section 2.7.7, “Configuring IPv6 Settings”](#).

2.3.7. Configuring a Wi-Fi Connection

This section explains how to use **NetworkManager** to configure a Wi-Fi (also known as wireless or 802.11a/b/g/n) connection to an Access Point.

To configure a mobile broadband (such as 3G) connection, see [Section 2.5, “Establishing a Mobile Broadband Connection”](#).

Quickly Connecting to an Available Access Point

The easiest way to connect to an available access point is to click on the network connection icon to activate the network connection icon's menu, locate the *Service Set Identifier* (SSID) of the access point in the list of **Wi-Fi** networks, and click on it. A padlock symbol indicates the access point requires

authentication. If the access point is secured, a dialog prompts you for an authentication key or password.

NetworkManager tries to auto-detect the type of security used by the access point. If there are multiple possibilities, **NetworkManager** guesses the security type and presents it in the **Wi-Fi security** drop-down menu. For WPA-PSK security (WPA with a passphrase) no choice is necessary. For WPA Enterprise (802.1X) you have to specifically select the security, because that cannot be auto-detected. If you are unsure, try connecting to each type in turn. Finally, enter the key or passphrase in the **Password** field. Certain password types, such as a 40-bit WEP or 128-bit WPA key, are invalid unless they are of a requisite length. The **Connect** button will remain inactive until you enter a key of the length required for the selected security type. To learn more about wireless security, see [Section 2.7.3, “Configuring Wi-Fi Security”](#).

If **NetworkManager** connects to the access point successfully, the network connection icon will change into a graphical indicator of the wireless connection's signal strength.

You can also edit the settings for one of these auto-created access point connections just as if you had added it yourself. The **Wi-Fi** page of the **Network** window has a **History** button. Clicking it reveals a list of all the connections you have ever tried to connect to. See [the section called “Editing a Connection or Creating a New One”](#)

Connecting to a Hidden Wi-Fi Network

All access points have a *Service Set Identifier* (SSID) to identify them. However, an access point may be configured not to broadcast its SSID, in which case it is *hidden*, and will not show up in **NetworkManager**'s list of **Available** networks. You can still connect to a wireless access point that is hiding its SSID as long as you know its SSID, authentication method, and secrets.

To connect to a hidden wireless network, press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** window appears. Select **Wi-Fi** from the menu and then select **Connect to Hidden Network** to cause a dialog to appear. If you have connected to the hidden network before, use the **Connection** drop-down to select it, and click **Connect**. If you have not, leave the **Connection** drop-down as **New**, enter the SSID of the hidden network, select its **Wi-Fi security** method, enter the correct authentication secrets, and click **Connect**.

For more information on wireless security settings, see [Section 2.7.3, “Configuring Wi-Fi Security”](#).

Editing a Connection or Creating a New One

You can edit an existing connection that you have tried or succeeded in connecting to in the past by opening the **Wi-Fi** page of the **Network** dialog and selecting the gear wheel icon to the right of the Wi-Fi connection name. If the network is not currently in range, click **History** to display past connections. When you click the gear wheel icon the editing connection dialog appears. The **Details** window shows the connection details.

To configure a new connection whose SSID is in range, first attempt to connect to it by opening the **Network** window, selecting the **Wi-Fi** menu entry, and clicking the connection name (by default, the same as the SSID). If the SSID is not in range, see [the section called “Connecting to a Hidden Wi-Fi Network”](#) for more information. If the SSID is in range, the procedure is as follows:

1. Press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears.
2. Select the **Wi-Fi** interface from the left-hand-side menu entry.

3. Click the Wi-Fi connection profile on the right-hand side menu you want to connect to. A padlock symbol indicates a key or password is required.
4. If requested, enter the authentication details.

Basic Configuration Options for a Wi-Fi Connection

To edit a Wi-Fi connection's settings, select **Wi-Fi** in the **Network** page and then select the gear wheel icon to the right of the Wi-Fi connection name. Select **Identity**. The following settings are available:

The screenshot shows a window titled "my wifi" with a close button (X) in the top right corner. On the left is a vertical sidebar with a menu containing "Details", "Security", "Identity" (highlighted in blue), "IPv4", "IPv6", and "Reset". The main area of the window displays the "Identity" settings for the "my wifi" connection. It includes four input fields: "SSID" with the value "my wifi", "BSSID" which is empty, "MAC Address" with the value "F0:D5:BF:65:C6:89", and "Cloned Address" which is empty. Below these fields are two checked checkboxes: "Connect automatically" and "Make available to other users". At the bottom right are "Cancel" and "Apply" buttons.

Figure 2.12. Basic Configuration Options for a Wi-Fi Connection

SSID

The *Service Set Identifier* (SSID) of the access point (AP).

BSSID

The *Basic Service Set Identifier* (BSSID) is the MAC address, also known as a *hardware address*, of the specific wireless access point you are connecting to when in **Infrastructure** mode. This field is blank by default, and you are able to connect to a wireless access point by **SSID** without having to specify its **BSSID**. If the BSSID is specified, it will force the system to associate to a specific access point only.

For ad-hoc networks, the **BSSID** is generated randomly by the **mac80211** subsystem when the ad-hoc network is created. It is not displayed by **NetworkManager**

MAC address

Select the MAC address, also known as a *hardware address*, of the Wi-Fi interface to use.

A single system could have one or more wireless network adapters connected to it. The **MAC address** field therefore allows you to associate a specific wireless adapter with a specific connection (or connections).

Cloned Address

A cloned MAC address to use in place of the real hardware address. Leave blank unless required.

The following settings are common to the most connection types:

- **Connect automatically** – Select this box if you want **NetworkManager** to auto-connect to this connection when it is available. See [Section 2.3.3, “Connecting to a Network Automatically”](#) for more information.
- **Make available to other users** – Select this box to create a connection available to all users on the system. Changing this setting may require root privileges. See [Section 2.3.5, “System-wide and Private Connection Profiles”](#) for details.

Saving Your New (or Modified) Connection and Making Further Configurations

Once you have finished editing the wireless connection, click the **Apply** button to save your configuration. Given a correct configuration, you can connect to your modified connection by selecting it from the network connection icon's menu. See [Section 2.3.1, “Connecting to a Network Using a GUI”](#) for details on selecting and connecting to a network.

You can further configure an existing connection by selecting it in the **Network** window and clicking the gear wheel icon to reveal the connection details.

Then, to configure:

- **security authentication** for the wireless connection, click **Security** and proceed to [Section 2.7.3, “Configuring Wi-Fi Security”](#);
- **IPv4 settings** for the connection, click **IPv4** and proceed to [Section 2.7.6, “Configuring IPv4 Settings”](#); or,
- **IPv6 settings** for the connection, click **IPv6** and proceed to [Section 2.7.7, “Configuring IPv6 Settings”](#).

2.4. ESTABLISHING A VPN CONNECTION

IPsec, provided by **Libreswan**, is the preferred method for creating a VPN in Red Hat Enterprise Linux 7. For more information, see [Section 2.2.6, “Configuring a VPN”](#).

The GNOME graphical user interface tool described below requires the **NetworkManager-libreswan-gnome** package. To install the package, run the following command as **root**:

```
~]# yum install NetworkManager-libreswan-gnome
```

See [Red Hat Enterprise Linux System Administrator's Guide](#) for more information on how to install new packages in Red Hat Enterprise Linux.

Establishing a Virtual Private Network (VPN) enables communication between your Local Area Network (LAN), and another, remote LAN. This is done by setting up a tunnel across an intermediate network such as the Internet. The VPN tunnel that is set up typically uses authentication and encryption. After successfully establishing a VPN connection using a secure tunnel, a VPN router or gateway performs the following actions upon the packets you transmit:

1. it adds an *Authentication Header* for routing and authentication purposes;
2. it encrypts the packet data; and,
3. it encloses the data in packets according to the Encapsulating Security Payload (ESP) protocol, which constitutes the decryption and handling instructions.

The receiving VPN router strips the header information, decrypts the data, and routes it to its intended destination (either a workstation or other node on a network). Using a network-to-network connection, the receiving node on the local network receives the packets already decrypted and ready for processing. The encryption and decryption process in a network-to-network VPN connection is therefore transparent to clients.

Because they employ several layers of authentication and encryption, VPNs are a secure and effective means of connecting multiple remote nodes to act as a unified intranet.

Procedure 2.3. Adding a New IPsec VPN Connection

You can configure a new IPsec VPN connection using **NetworkManager** by opening the **Network** window and selecting the plus button below the menu.

1. Press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears.
2. Click the plus button at the bottom of the window.




Figure 2.13. Adding a connection

3. The **Add Network Connection** window appears. Select the **VPN** menu entry.




Figure 2.14. Selecting the VPN menu

4. For manually configuration, select **IPsec based VPN**.




Figure 2.15. Configuring VPN on IPsec mode

5. In the **Identity** configuration form, you can specify the fields in the **General** and **Advanced** sections:

The screenshot shows a window titled "Add Network Connection". On the left is a sidebar with a blue header "Identity" and two options: "IPv4" and "IPv6". The main area contains the following fields and controls:

- Name:** A text field containing "VPN 2".
- Firewall Zone:** A dropdown menu showing "Default".
- ☐ **Make available to other users**
- General section:**
 - Gateway:** An empty text field.
 - User name:** An empty text field.
 - User password:** An empty text field with a question mark icon on the right.
 - Group name:** An empty text field.
 - Secret:** An empty text field with a question mark icon on the right.
 - ☐ **Show passwords**
- Advanced section:** (indicated by a downward arrow)
 - Phase1 Algorithms:** An empty text field.
 - Phase2 Algorithms:** An empty text field.
 - Domain:** An empty text field.

At the bottom right are two buttons: "Cancel" and "Add".

Figure 2.16. General and Advanced sections

- In **General** section, you can specify:

Gateway

The name or **IP** address of the remote VPN gateway.

User name

If required, enter the user name used to authenticate with the VPN for the user's identity.

User password

If required, enter the password used to authenticate with the VPN for the user's identity.

Group name

The name of a VPN group configured on the remote gateway. In case it is blank, the IKEv1 Main mode is used instead of the default Aggressive mode.

Secret

It is a pre-shared key which is used to initialize the encryption before the user's authentication. If required, enter the password associated with the group name.

- The following configuration settings are available under the **Advanced** section:

Phase1 Algorithms

If required, enter the algorithms to be used to authenticate and set up an encrypted channel.

Phase2 Algorithms

If required, enter the algorithms to be used for the **IPsec** negotiations.

Domain

If required, enter the Domain Name.

**NOTE**

Configuring an **IPsec** VPN without using **NetworkManager**, see [Section 2.2.6](#), “Configuring a VPN”.

Procedure 2.4. Editing an Existing VPN Connection

You can configure an existing VPN connection by opening the **Network** window and selecting the name of the connection from the list.

1. Press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears.
2. Select the **VPN** connection you want to edit from the left hand menu.
3. Click the **Configure** button.




Figure 2.17. Editing an existing VPN connection

4. Select the **Identity** menu entry on the left, and specify the fields in the **General** section:

VPN 1 VPN

Name

Firewall Zone

☐ Make available to other users

General

Gateway

User name

User password

Group name

Secret

☐ Show passwords

► Advanced

Figure 2.18. Configuring an existing VPN connection

Saving Your New (or Modified) Connection and Making Further Configurations

Once you have finished editing your new VPN connection, click the **Save** button to save your customized configuration. If the profile was in use while being edited, power cycle the connection to make **NetworkManager** apply the changes. If the profile is OFF, set it to ON or select it in the network connection icon's menu. See [Section 2.3.1, “Connecting to a Network Using a GUI”](#) for information on using your new or altered connection.

You can further configure an existing connection by selecting it in the **Network** window and clicking **Configure** to return to the **Editing** dialog.

Then, to configure:

- **IPv4** settings for the connection, click the **IPv4 Settings** tab and proceed to [Section 2.7.6, “Configuring IPv4 Settings”](#).

2.5. ESTABLISHING A MOBILE BROADBAND CONNECTION

You can use **NetworkManager**'s mobile broadband connection abilities to connect to the following 2G and 3G services:

- 2G – *GPRS (General Packet Radio Service), EDGE (Enhanced Data Rates for GSM Evolution), or CDMA (Code Division Multiple Access).*
- 3G – *UMTS (Universal Mobile Telecommunications System), HSPA (High Speed Packet Access), or EVDO (EVolution Data-Only).*

Your computer must have a mobile broadband device (modem), which the system has discovered and recognized, in order to create the connection. Such a device may be built into your computer (as is the case on many notebooks and netbooks), or may be provided separately as internal or external hardware. Examples include PC card, USB Modem or Dongle, mobile or cellular telephone capable of acting as a modem.

Procedure 2.5. Adding a New Mobile Broadband Connection

You can configure a mobile broadband connection by opening the **Network Connections** tool and selecting the **Mobile Broadband** tab.

1. Press the **Super** key to enter the Activities Overview, type **nm-connection-editor** and then press **Enter**. The **Network Connections** tool appears.
2. Click the **Add** button. The **Choose a Connection Type** menu opens.
3. Select the **Mobile Broadband** menu entry.
4. Click **Create** to open the **Set up a Mobile Broadband Connection** assistant.
5. Under **Create a connection for this mobile broadband device**, choose the 2G- or 3G-capable device you want to use with the connection. If the drop-down menu is inactive, this indicates that the system was unable to detect a device capable of mobile broadband. In this case, click **Cancel**, ensure that you do have a mobile broadband-capable device attached and recognized by the computer and then retry this procedure. Click the **Continue** button.
6. Select the country where your service provider is located from the list and click the **Continue** button.
7. Select your provider from the list or enter it manually. Click the **Continue** button.
8. Select your payment plan from the drop-down menu and confirm the *Access Point Name* (APN) is correct. Click the **Continue** button.
9. Review and confirm the settings and then click the **Apply** button.
10. Edit the mobile broadband-specific settings by referring to [the section called “Configuring the Mobile Broadband Tab”](#)

Procedure 2.6. Editing an Existing Mobile Broadband Connection

Follow these steps to edit an existing mobile broadband connection.

1. Press the **Super** key to enter the Activities Overview, type **nm-connection-editor** and then press **Enter**. The **Network Connections** tool appears.
2. Select the **Mobile Broadband** tab.

3. Select the connection you want to edit and click the **Edit** button. See [Section 2.3.4, “Common Configuration Options in nm-connection-editor”](#) for more information.
4. Edit the mobile broadband-specific settings by referring to [the section called “Configuring the Mobile Broadband Tab”](#)

Saving Your New (or Modified) Connection and Making Further Configurations

Once you have finished editing your mobile broadband connection, click the **Apply** button to save your customized configuration. If the profile was in use while being edited, power cycle the connection to make **NetworkManager** apply the changes. If the profile is OFF, set it to ON or select it in the network connection icon's menu. See [Section 2.3.1, “Connecting to a Network Using a GUI”](#) for information on using your new or altered connection.

You can further configure an existing connection by selecting it in the **Network Connections** window and clicking **Edit** to return to the **Editing** dialog.

Then, to configure:

- **Point-to-point** settings for the connection, click the **PPP Settings** tab and proceed to [Section 2.7.5, “Configuring PPP \(Point-to-Point\) Settings”](#);
- **IPv4** settings for the connection, click the **IPv4 Settings** tab and proceed to [Section 2.7.6, “Configuring IPv4 Settings”](#); or,
- **IPv6** settings for the connection, click the **IPv6 Settings** tab and proceed to [Section 2.7.7, “Configuring IPv6 Settings”](#).

Configuring the Mobile Broadband Tab

If you have already added a new mobile broadband connection using the assistant (see [Procedure 2.5, “Adding a New Mobile Broadband Connection”](#) for instructions), you can edit the **Mobile Broadband** tab to disable roaming if home network is not available, assign a network ID, or instruct **NetworkManager** to prefer a certain technology (such as 3G or 2G) when using the connection.

Number

The number that is dialed to establish a PPP connection with the GSM-based mobile broadband network. This field may be automatically populated during the initial installation of the broadband device. You can usually leave this field blank and enter the **APN** instead.

Username

Enter the user name used to authenticate with the network. Some providers do not provide a user name, or accept any user name when connecting to the network.

Password

Enter the password used to authenticate with the network. Some providers do not provide a password, or accept any password.

APN

Enter the *Access Point Name* (APN) used to establish a connection with the GSM-based network. Entering the correct APN for a connection is important because it often determines:

- how the user is billed for their network usage;
- whether the user has access to the Internet, an intranet, or a subnetwork.

Network ID

Entering a **Network ID** causes **NetworkManager** to force the device to register only to a specific network. This can be used to ensure the connection does not roam when it is not possible to control roaming directly.

Type

Any – The default value of **Any** leaves the modem to select the fastest network.

3G (UMTS/HSPA) – Force the connection to use only 3G network technologies.

2G (GPRS/EDGE) – Force the connection to use only 2G network technologies.

Prefer 3G (UMTS/HSPA) – First attempt to connect using a 3G technology such as HSPA or UMTS, and fall back to GPRS or EDGE only upon failure.

Prefer 2G (GPRS/EDGE) – First attempt to connect using a 2G technology such as GPRS or EDGE, and fall back to HSPA or UMTS only upon failure.

Allow roaming if home network is not available

Uncheck this box if you want **NetworkManager** to terminate the connection rather than transition from the home network to a roaming one, thereby avoiding possible roaming charges. If the box is checked, **NetworkManager** will attempt to maintain a good connection by transitioning from the home network to a roaming one, and vice versa.

PIN

If your device's *SIM (Subscriber Identity Module)* is locked with a *PIN (Personal Identification Number)*, enter the PIN so that **NetworkManager** can unlock the device. **NetworkManager** must unlock the SIM if a PIN is required in order to use the device for any purpose.

CDMA and EVDO have fewer options. They do not have the **APN**, **Network ID**, or **Type** options.

2.6. ESTABLISHING A DSL CONNECTION

This section is intended for those installations which have a DSL card fitted within a host rather than the external combined DSL modem router combinations typical of private consumer or SOHO installations.

Procedure 2.7. Adding a New DSL Connection

You can configure a new DSL connection by opening the **Network Connections** window, clicking the **Add** button and selecting **DSL** from the **Hardware** section of the new connection list.

1. Press the **Super** key to enter the Activities Overview, type **nm-connection-editor** and then press **Enter**. The **Network Connections** tool appears.
2. Click the **Add** button.
3. The **Choose a Connection Type** list appears.
4. Select **DSL** and press the **Create** button.
5. The **Editing DSL Connection 1** window appears.

Procedure 2.8. Editing an Existing DSL Connection

You can configure an existing DSL connection by opening the **Network Connections** window and selecting the name of the connection from the list. Then click the **Edit** button.

1. Press the **Super** key to enter the Activities Overview, type **nm-connection-editor** and then press **Enter**. The **Network Connections** tool appears.
2. Select the connection you want to edit and click the **Edit** button. See [Section 2.3.4, “Common Configuration Options in nm-connection-editor”](#) for more information.

Configuring the DSL Tab

Username

Enter the user name used to authenticate with the service provider.

Service

Leave blank unless otherwise directed by your service provider.

Password

Enter the password supplied by the service provider.

Saving Your New (or Modified) Connection and Making Further Configurations

Once you have finished editing your DSL connection, click the **Apply** button to save your customized configuration. If the profile was in use while being edited, power cycle the connection to make **NetworkManager** apply the changes. If the profile is OFF, set it to ON or select it in the network connection icon's menu. See [Section 2.3.1, “Connecting to a Network Using a GUI”](#) for information on using your new or altered connection.

You can further configure an existing connection by selecting it in the **Network Connections** window and clicking **Edit** to return to the **Editing** dialog.

Then, to configure:

- **The MAC address and MTU** settings, click the **Wired** tab and proceed to [the section called “Basic Configuration Options ”](#)
- **Point-to-point** settings for the connection, click the **PPP Settings** tab and proceed to [Section 2.7.5, “Configuring PPP \(Point-to-Point\) Settings”](#);
- **IPv4** settings for the connection, click the **IPv4 Settings** tab and proceed to [Section 2.7.6, “Configuring IPv4 Settings”](#).

2.7. CONFIGURING CONNECTION SETTINGS

This section describes various configurations of the 802.3 link settings and shows how to configure them by using **NetworkManager**.

2.7.1. Configuring 802.3 Link Settings

You can configure the 802.3 link settings of an Ethernet connection by modifying the following configuration parameters:

- `802-3-ethernet.auto-negotiate`
- `802-3-ethernet.speed`
- `802-3-ethernet.duplex`

You can configure the 802.3 link settings to three main modes:


- Ignore link negotiation
- Enforce auto-negotiation activation
- Manually set the **speed** and **duplex** link settings

Ignoring link negotiation

In this case, **NetworkManager** ignores link configuration for an ethernet connection, keeping the already configuration on the device.

To ignore link negotiation, set the following parameters:

```
802-3-ethernet.auto-negotiate = no
802-3-ethernet.speed = 0
802-3-ethernet.duplex = NULL
```



IMPORTANT

If the **auto-negotiate** parameter is set to **no**, but the **speed** and **duplex** values are not set, that does not mean that auto-negotiation is disabled.

Enforcing auto-negotiation activation

In this case, **NetworkManager** enforces auto-negotiation on a device.

To enforce auto-negotiation activation, set the following options:


```
802-3-ethernet.auto-negotiate = yes
802-3-ethernet.speed = 0
802-3-ethernet.duplex = NULL
```

Manually setting the link speed and duplex

In this case, you can manually configure the **speed** and **duplex** settings on the link.

To manually set the **speed** and **duplex** link settings, set the aforementioned parameters as follows:

```
802-3-ethernet.auto-negotiate = no
802-3-ethernet.speed = [speed in Mbit/s]
802-3-ethernet.duplex = [half |full]
```



IMPORTANT

Make sure to set both the **speed** and the **duplex** values, otherwise **NetworkManager** does not update the link configuration.

To configure 802.3 link settings, you can use:

- The **nmcli** tool
- The **nm-connection-editor** utility

Procedure 2.9. Configuring 802.3 Link Settings by Using the nmcli Tool

1. Create a new ethernet connection for the *eth0* device.
2. Set the 802.3 link setting to a configuration of your choice. For details, see [Section 2.7.1, “Configuring 802.3 Link Settings”](#)

For example, to manually set the **speed** option *100 Mbit/s* and **duplex** to *full*:

```
nmcli connection add con-name MyEthernet type ethernet ifname
eth0 \
  802-3-ethernet.auto-negotiate no \
  802-3-ethernet.speed 100 \
  802-3-ethernet.duplex full
```

Procedure 2.10. Configuring 802.3 Link Settings by Using the nm-connection-editor Utility

1. Run the **nm-connection-editor** utility.
2. Select the ethernet connection you want to edit and click **Edit**. See [Section 2.3.4, “Common Configuration Options in nm-connection-editor”](#) for more information.
3. Select the link negotiation of your choice.
 - **Ignore**: link configuration is skipped (default).
 - **Automatic**: link auto-negotiation is enforced on the device.
 - **Manual**: the **Speed** and **Duplex** options can be specified to enforce the link negotiation.




Figure 2.19. Configure 802.3 link settings using nm-connection-editor

2.7.2. Configuring 802.1X Security

802.1X security is the name of the IEEE standard for *port-based Network Access Control* (PNAC). It is also called *WPA Enterprise*. Simply put, 802.1X security is a way of controlling access to a *logical network* from a physical one. All clients who want to join the logical network must authenticate with the server (a router, for example) using the correct 802.1X authentication method.

802.1X security is most often associated with securing wireless networks (WLANs), but can also be used to prevent intruders with physical access to the network (LAN) from gaining entry. In the past, **DHCP** servers were configured not to lease **IP** addresses to unauthorized users, but for various reasons this practice is both impractical and insecure, and thus is no longer recommended. Instead, 802.1X security is used to ensure a logically-secure network through port-based authentication.

802.1X provides a framework for WLAN and LAN access control and serves as an envelope for carrying one of the Extensible Authentication Protocol (EAP) types. An EAP type is a protocol that defines how security is achieved on the network.

Configuring Connection Settings 802.1X Security Using a GUI

You can configure 802.1X security for a wired or wireless connection type by opening the **Network** window (see [Section 2.3.1, “Connecting to a Network Using a GUI”](#)) and following the applicable procedure below. Press the **Super** key to enter the Activities Overview, type **control network** and

then press **Enter**. The **Network** settings tool appears. Proceed to [Procedure 2.11, “For a Wired Connection”](#) or [Procedure 2.12, “For a Wireless Connection”](#) :

Procedure 2.11. For a Wired Connection

1. Select a **Wired** network interface from the left-hand-side menu.
2. Either click on **Add Profile** to add a new network connection profile for which you want to configure 802.1X security, or select an existing connection profile and click the gear wheel icon.
3. Then select **Security** and set the symbolic power button to **ON** to enable settings configuration.
4. Proceed to [Section 2.7.2.1, “Configuring Transport Layer Security \(TLS\) Settings”](#)

Procedure 2.12. For a Wireless Connection

1. Select a **Wireless** network interface from the left-hand-side menu. If necessary, set the symbolic power button to **ON** and check that your hardware switch is on.
2. Either select the connection name of a new connection, or click the gear wheel icon of an existing connection profile, for which you want to configure 802.1X security. In the case of a new connection, complete any authentication steps to complete the connection and then click the gear wheel icon.
3. Select **Security**.
4. From the drop-down menu select one of the following security methods: **LEAP**, **Dynamic WEP (802.1X)**, or **WPA & WPA2 Enterprise**.
5. See [Section 2.7.2.1, “Configuring Transport Layer Security \(TLS\) Settings”](#) for descriptions of which *extensible authentication protocol* (EAP) types correspond to your selection in the **Security** drop-down menu.

Configuring Connection Settings 802.1X Security Using the nmcli tool

To configure a wireless connection using the **nmcli** tool, follow the procedure below:

1. Set the accepted authenticated **key-mgmt** (key management) protocol. It configures the keying mechanism for a secure **wifi** connection. See the *nm-settings(5)* man page for more details on properties.
2. Configure the 802-1x authentication settings. For the Transport Layer Security (TLS) authentication, see [Section 2.7.2.1, “Configuring Transport Layer Security \(TLS\) Settings”](#) and [Section 2.7.2.2, “Configuring TLS Settings”](#) for descriptions of relevant properties:

Table 2.1. The 802-1x authentication settings

802-1x authentication setting	Name
802-1x.identity	Identity
802-1x.ca-cert	CA certificate

802-1x authentication setting	Name
802-1x.client-cert	User certificate
802-1x.private-key	Private key
802-1x.private-key-password	Private key password

For example, to configure WPA2 Enterprise using the EAP-TLS authentication method, apply the following settings:

```
nmcli c add type wifi ifname wlan0 con-name 'My Wifi Network' \
      802-11-wireless.ssid 'My Wifi' \
      802-11-wireless-security.key-mgmt wpa-eap \
      802-1x.eap tls \
      802-1x.identity identity@example.com \
      802-1x.ca-cert /etc/pki/my-wifi/ca.crt \
      802-1x.client-cert /etc/pki/my-wifi/client.crt \
      802-1x.private-key /etc/pki/my-wifi/client.key \
      802-1x.private-key-password s3cr3t
```



NOTE

To configure a wired connection using the `nmcli` tool, follow the same procedure as for a wireless connection, except the `802-11-wireless.ssid` and `802-11-wireless-security.key-mgmt` settings.

2.7.2.1. Configuring Transport Layer Security (TLS) Settings

With Transport Layer Security, the client and server mutually authenticate using the TLS protocol. The server demonstrates that it holds a digital certificate, the client proves its own identity using its client-side certificate, and key information is exchanged. Once authentication is complete, the TLS tunnel is no longer used. Instead, the client and server use the exchanged keys to encrypt data using AES, TKIP or WEP.

The fact that certificates must be distributed to all clients who want to authenticate means that the EAP-TLS authentication method is very strong, but also more complicated to set up. Using TLS security requires the overhead of a public key infrastructure (PKI) to manage certificates. The benefit of using TLS security is that a compromised password does not allow access to the (W)LAN: an intruder must also have access to the authenticating client's private key.

NetworkManager does not determine the version of TLS supported. **NetworkManager** gathers the parameters entered by the user and passes them to the daemon, `wpa_supplicant`, that handles the procedure. It in turn uses OpenSSL to establish the TLS tunnel. OpenSSL itself negotiates the SSL/TLS protocol version. It uses the highest version both ends support.

Selecting an Authentication Method

Select from one of following authentication methods:

- Select **TLS** for *Transport Layer Security* and proceed to [Section 2.7.2.2, “Configuring TLS Settings”](#);

- Select **FAST** for *Flexible Authentication through Secure Tunneling* and proceed to [Section 2.7.2.4, “Configuring Tunneled TLS Settings”](#);
- Select **Tunneled TLS** for *Tunneled Transport Layer Security*, otherwise known as TTLS, or EAP-TTLS and proceed to [Section 2.7.2.4, “Configuring Tunneled TLS Settings”](#);
- Select **Protected EAP (PEAP)** for *Protected Extensible Authentication Protocol* and proceed to [Section 2.7.2.5, “Configuring Protected EAP \(PEAP\) Settings”](#).

2.7.2.2. Configuring TLS Settings

Identity

Provide the identity of this server.

User certificate

Click to browse for, and select, a personal X.509 certificate file encoded with *Distinguished Encoding Rules* (DER) or *Privacy Enhanced Mail* (PEM).

CA certificate

Click to browse for, and select, an X.509 *certificate authority* certificate file encoded with *Distinguished Encoding Rules* (DER) or *Privacy Enhanced Mail* (PEM).

Private key

Click to browse for, and select, a *private key* file encoded with *Distinguished Encoding Rules* (DER), *Privacy Enhanced Mail* (PEM), or the *Personal Information Exchange Syntax Standard* (PKCS #12).

Private key password

Enter the password for the private key in the **Private key** field. Select **Show password** to make the password visible as you type it.

2.7.2.3. Configuring FAST Settings

Anonymous Identity

Provide the identity of this server.

PAC provisioning

Select the check box to enable and then select from **Anonymous**, **Authenticated**, and **Both**.

PAC file

Click to browse for, and select, a *protected access credential* (PAC) file.

Inner authentication

GTC – Generic Token Card.

MSCHAPv2 – Microsoft Challenge Handshake Authentication Protocol version 2.

Username

Enter the user name to be used in the authentication process.

Password

Enter the password to be used in the authentication process.

2.7.2.4. Configuring Tunneled TLS Settings**Anonymous identity**

This value is used as the unencrypted identity.

CA certificate

Click to browse for, and select, a Certificate Authority's certificate.

Inner authentication

PAP – Password Authentication Protocol.

MSCHAP – Challenge Handshake Authentication Protocol.

MSCHAPv2 – Microsoft Challenge Handshake Authentication Protocol version 2.

CHAP – Challenge Handshake Authentication Protocol.

Username

Enter the user name to be used in the authentication process.

Password

Enter the password to be used in the authentication process.

2.7.2.5. Configuring Protected EAP (PEAP) Settings**Anonymous Identity**

This value is used as the unencrypted identity.

CA certificate

Click to browse for, and select, a Certificate Authority's certificate.

PEAP version

The version of Protected EAP to use. Automatic, 0 or 1.

Inner authentication

MSCHAPv2 – Microsoft Challenge Handshake Authentication Protocol version 2.

MD5 – Message Digest 5, a cryptographic hash function.

GTC – Generic Token Card.

Username

Enter the user name to be used in the authentication process.

Password

Enter the password to be used in the authentication process.

2.7.3. Configuring Wi-Fi Security

Security

None – Do not encrypt the Wi-Fi connection.

WEP 40/128-bit Key – Wired Equivalent Privacy (WEP), from the IEEE 802.11 standard. Uses a single pre-shared key (PSK).

WEP 128-bit Passphrase – An MD5 hash of the passphrase will be used to derive a WEP key.

LEAP – Lightweight Extensible Authentication Protocol, from Cisco Systems.

Dynamic WEP (802.1X) – WEP keys are changed dynamically. Use with [Section 2.7.2.1, “Configuring Transport Layer Security \(TLS\) Settings”](#)

WPA & WPA2 Personal – Wi-Fi Protected Access (WPA), from the draft IEEE 802.11i standard. A replacement for WEP. Wi-Fi Protected Access II (WPA2), from the 802.11i-2004 standard. Personal mode uses a pre-shared key (WPA-PSK).

WPA & WPA2 Enterprise – WPA for use with a RADIUS authentication server to provide IEEE 802.1X network access control. Use with [Section 2.7.2.1, “Configuring Transport Layer Security \(TLS\) Settings”](#)

Password

Enter the password to be used in the authentication process.

2.7.4. Using MACsec with wpa_supplicant and NetworkManager

Media Access Control Security (MACsec, IEEE 802.1AE) encrypts and authenticates all traffic in LANs with the GCM-AES-128 algorithm. **MACsec** can protect not only **IP** but also Address Resolution Protocol (ARP), Neighbor Discovery (ND), or **DHCP**. While **IPsec** operates on the network layer (layer 3) and **SSL** or **TLS** on the transport layer (layer 4), **MACsec** operates in the data link layer (layer 2). Combine **MACsec** with security protocols for other networking layers to take advantage of different security features that these standards provide.

To enable **MACsec** with a switch that performs authentication using a pre-shared Connectivity Association Key/CAK Name (CAK/CKN) pair, perform the following steps:

1. Create a CAK/CKN pair. For example, the following command generates a 16-byte key in hexadecimal notation:

```
~]$ dd if=/dev/urandom count=16 bs=1 2> /dev/null | hexdump -e '1/2
"%02x" '
```

2. Create the `wpa_supplicant.conf` configuration file and add the following lines to it:

```
ctrl_interface=/var/run/wpa_supplicant
eapol_version=3
```



```

ap_scan=0
fast_reauth=1

network={
    key_mgmt=NONE
    eapol_flags=0
    macsec_policy=1

    mka_cak=0011... # 16 bytes hexadecimal
    mka_ckn=2233... # 32 bytes hexadecimal
}

```

Use the values from the previous step to complete the `mka_cak` and `mka_ckn` lines in the `wpa_supplicant.conf` configuration file.

See the `wpa_supplicant.conf(5)` man page for more information.

3. Assuming you are using `eth0` to connect to your network, start `wpa_supplicant` using the following command:

```
~]# wpa_supplicant -i eth0 -Dmacsec_linux -c wpa_supplicant.conf
```

Instead of creating and editing the `wpa_supplicant.conf` file, Red Hat recommends using the `nmcli` command to configure `wpa_supplicant` equivalently as in the previous steps. The following example assumes that you already have a 16-byte hexadecimal CAK (`$MKA_CAK`) and a 32-byte hexadecimal CKN (`$MKA_CKN`):

```

~]# nmcli connection add type macsec \
    con-name test-macsec+ ifname macsec0 \
    connection.autoconnect no \
    macsec.parent eth0 macsec.mode psk \
    macsec.mka-cak $MKA_CAK \
    macsec.mka-cak-flags 0 \
    macsec.mka-ckn $MKA_CKN

~]# nmcli connection up test-macsec+

```

After this step, the `macsec0` device should be configured and used for networking.

For more details, see the [What's new in MACsec: setting up MACsec using wpa_supplicant and \(optionally\) NetworkManager](#) article. In addition, see the [MACsec: a different solution to encrypt network traffic](#) article for more information about the architecture of a MACsec network, use case scenarios, and configuration examples.

2.7.5. Configuring PPP (Point-to-Point) Settings

Authentication Methods

In most cases, the provider's PPP servers supports all the allowed authentication methods. If a connection fails, the user should disable support for some methods, depending on the PPP server configuration.

Use point-to-point encryption (MPPE)

Microsoft Point-To-Point Encryption protocol ([RFC 3078](#)).

Allow BSD data compression

PPP BSD Compression Protocol ([RFC 1977](#)).

Allow Deflate data compression


PPP Deflate Protocol ([RFC 1979](#)).

Use TCP header compression

Compressing TCP/IP Headers for Low-Speed Serial Links ([RFC 1144](#)).

Send PPP echo packets

LCP Echo-Request and Echo-Reply Codes for loopback tests ([RFC 1661](#)).

**NOTE**

Since the PPP support in **NetworkManager** is optional, to configure PPP settings, make sure that the NetworkManager-ppp package is already installed.

2.7.6. Configuring IPv4 Settings

The **IPv4 Settings** tab allows you to configure the method used to connect to a network, to enter **IP** address, route, and **DNS** information as required. The **IPv4 Settings** tab is available when you create and modify one of the following connection types: wired, wireless, mobile broadband, VPN or DSL. If you need to configure **IPv6** addresses, see [Section 2.7.7, “Configuring IPv6 Settings”](#). If you need to configure static routes, click the **Routes** button and proceed to [Section 2.7.8, “Configuring Routes”](#).

If you are using **DHCP** to obtain a dynamic **IP** address from a **DHCP** server, you can simply set **Method** to **Automatic (DHCP)**.

Setting the Method

Available IPv4 Methods by Connection Type

When you click the **Method** drop-down menu, depending on the type of connection you are configuring, you are able to select one of the following **IPv4** connection methods. All of the methods are listed here according to which connection type, or types, they are associated with:

Method

Automatic (DHCP) – Choose this option if the network you are connecting to uses a **DHCP** server to assign **IP** addresses. You do not need to fill in the **DHCP client ID** field.

Automatic (DHCP) addresses only – Choose this option if the network you are connecting to uses a **DHCP** server to assign **IP** addresses but you want to assign **DNS** servers manually.

Link-Local Only – Choose this option if the network you are connecting to does not have a **DHCP** server and you do not want to assign **IP** addresses manually. Random addresses will be assigned as per [RFC 3927](#) with prefix **169.254/16**.

Shared to other computers – Choose this option if the interface you are configuring is for sharing an Internet or WAN connection. The interface is assigned an address in the **10.42.x.1/24** range, a **DHCP** server and **DNS** server are started, and the interface is connected to the default network

connection on the system with *network address translation* (NAT).

Disabled – IPv4 is disabled for this connection.

Wired, Wireless and DSL Connection Methods

Manual – Choose this option if you want to assign IP addresses manually.

Mobile Broadband Connection Methods

Automatic (PPP) – Choose this option if the network you are connecting to assigns your IP address and DNS servers automatically.

Automatic (PPP) addresses only – Choose this option if the network you are connecting to assigns your IP address automatically, but you want to manually specify DNS servers.

VPN Connection Methods

Automatic (VPN) – Choose this option if the network you are connecting to assigns your IP address and DNS servers automatically.

Automatic (VPN) addresses only – Choose this option if the network you are connecting to assigns your IP address automatically, but you want to manually specify DNS servers.

DSL Connection Methods

Automatic (PPPoE) – Choose this option if the network you are connecting to assigns your IP address and DNS servers automatically.

Automatic (PPPoE) addresses only – Choose this option if the network you are connecting to assigns your IP address automatically, but you want to manually specify DNS servers.

For information on configuring static routes for the network connection, go to [Section 2.7.8, “Configuring Routes”](#).

2.7.7. Configuring IPv6 Settings

Method

Ignore – Choose this option if you want to ignore IPv6 settings for this connection.

Automatic – Choose this option to use SLAAC to create an automatic, stateless configuration based on the hardware address and *router advertisements* (RA).

Automatic, addresses only – Choose this option if the network you are connecting to uses *router advertisements* (RA) to create an automatic, stateless configuration, but you want to assign DNS servers manually.

Automatic, DHCP only – Choose this option to not use RA, but request information from DHCPv6 directly to create a stateful configuration.

Manual – Choose this option if you want to assign IP addresses manually.

Link-Local Only – Choose this option if the network you are connecting to does not have a DHCP server and you do not want to assign IP addresses manually. Random addresses will be assigned as per [RFC 4862](#) with prefix FE80::0.

Addresses

DNS servers – Enter a comma separated list of **DNS** servers.

Search domains – Enter a comma separated list of domain controllers.

For information on configuring static routes for the network connection, go to [Section 2.7.8, “Configuring Routes”](#).

2.7.8. Configuring Routes

A host's routing table will be automatically populated with routes to directly connected networks. The routes are learned by examining the network interfaces when they are “up”. This section describes entering static routes to networks or hosts which can be reached by traversing an intermediate network or connection, such as a VPN tunnel or leased line. In order to reach a remote network or host, the system is given the address of a gateway to which traffic should be sent.

When a host's interface is configured by **DHCP**, an address of a gateway that leads to an upstream network or the Internet is usually assigned. This gateway is usually referred to as the default gateway as it is the gateway to use if no better route is known to the system (and present in the routing table). Network administrators often use the first or last host **IP** address in the network as the gateway address; for example, **192 . 168 . 10 . 1** or **192 . 168 . 10 . 254**. Not to be confused by the address which represents the network itself; in this example, **192 . 168 . 10 . 0**, or the subnet's broadcast address; in this example **192 . 168 . 10 . 255**.

Configuring Static Routes

To set a static route, open the **IPv4** or **IPv6** settings window for the connection you want to configure. See [Section 2.3.1, “Connecting to a Network Using a GUI”](#) for instructions on how to do that.

Routes

Address – Enter the **IP** address of a remote network, sub-net, or host.

Netmask – The netmask or prefix length of the **IP** address entered above.

Gateway – The **IP** address of the gateway leading to the remote network, sub-net, or host entered above.

Metric – A network cost, a preference value to give to this route. Lower values will be preferred over higher values.

Automatic

When Automatic is **ON**, routes from **RA** or **DHCP** are used, but you can also add additional static routes. When **OFF**, only static routes you define are used.

Use this connection only for resources on its network

Select this check box to prevent the connection from becoming the default route. Typical examples are where a connection is a VPN tunnel or a leased line to a head office and you do not want any Internet-bound traffic to pass over the connection. Selecting this option means that only traffic specifically destined for routes learned automatically over the connection or entered here manually will be routed over the connection.

2.8. ADDITIONAL RESOURCES

Installed Documentation

- *ip(8)* man page – Describes the **ip** utility's command syntax.
- *nmcli(1)* man page – Describes **NetworkManager**'s command-line tool.
- *nmcli-examples(5)* man page – Gives examples of **nmcli** commands.
- *nm-settings(5)* man page – Describes **NetworkManager** properties and their settings.
- *nm-settings-ifcfg-rh(5)* man page – Describes **ifcfg-rh** settings plug-in.

Online Documentation

[Red Hat Enterprise Linux 7 Security Guide](#)

Describes **IPsec** based VPN and its configuration. Describes the use of authenticated **DNS** queries using **DNSSEC**.

[RFC 1518](#) – Classless Inter-Domain Routing (CIDR)

Describes the CIDR Address Assignment and Aggregation Strategy, including variable-length subnetting.

[RFC 1918](#) – Address Allocation for Private Internets

Describes the range of **IPv4** addresses reserved for private use.

[RFC 3330](#) – Special-Use IPv4 Addresses

Describes the global and other specialized **IPv4** address blocks that have been assigned by the Internet Assigned Numbers Authority (IANA).

CHAPTER 3. CONFIGURE HOST NAMES

3.1. UNDERSTANDING HOST NAMES

There are three classes of `hostname`: static, pretty, and transient.

The “static” host name is the traditional `hostname`, which can be chosen by the user, and is stored in the `/etc/hostname` file. The “transient” `hostname` is a dynamic host name maintained by the kernel. It is initialized to the static host name by default, whose value defaults to “localhost”. It can be changed by `DHCP` or `mDNS` at runtime. The “pretty” `hostname` is a free-form UTF8 host name for presentation to the user.



NOTE

A host name can be a free-form string up to 64 characters in length. However, Red Hat recommends that both static and transient names match the *fully-qualified domain name* (FQDN) used for the machine in `DNS`, such as `host.example.com`. It is also recommended that the static and transient names consists only of 7 bit ASCII lower-case characters, no spaces or dots, and limits itself to the format allowed for `DNS` domain name labels, even though this is not a strict requirement. Older specifications do not permit the underscore, and so their use is not recommended.

The `hostnamectl` tool will enforce the following: Static and transient host names to consist of `a-z`, `A-Z`, `0-9`, “-”, “_” and “.” only, to not begin or end in a dot, and to not have two dots immediately following each other. The size limit of 64 characters is enforced.

3.1.1. Recommended Naming Practices

The Internet Corporation for Assigned Names and Numbers (ICANN) sometimes adds previously unregistered Top-Level Domains (such as `.yourcompany`) to the public register. Therefore, Red Hat strongly recommends that you do not use a domain name that is not delegated to you, even on a private network, as this can result in a domain name that resolves differently depending on network configuration. As a result, network resources can become unavailable. Using domain names that are not delegated to you also makes DNSSEC more difficult to deploy and maintain, as domain name collisions require manual configuration to enable DNSSEC validation. See the [ICANN FAQ on domain name collision](#) for more information on this issue.

3.2. CONFIGURING HOST NAMES USING TEXT USER INTERFACE, NMTUI

The text user interface tool `nmtui` can be used to configure a host name in a terminal window. Issue the following command to start the tool:

```
~]$ nmtui
```

The text user interface appears. Any invalid command prints a usage message.





Figure 3.1. The NetworkManager Text User Interface starting menu

To navigate, use the arrow keys or press **Tab** to step forwards and press **Shift+Tab** to step back through the options. Press **Enter** to select an option. The **Space** bar toggles the status of a check box.

See [Section 1.5, “Network Configuration Using a Text User Interface \(nmtui\)”](#) for information on installing **nmtui**.

The **NetworkManager** text user interface tool **nmtui** can be used to query and set the static host name in the `/etc/hostname` file.



IMPORTANT

In Red Hat Enterprise Linux, **NetworkManager** uses the `systemd-hostnamed` service to read and write the static host name, which is stored in the `/etc/hostname` file. Due to this, manual modifications done to the `/etc/hostname` file are no longer picked up automatically by **NetworkManager**; you should change the system host name through the `hostnamectl` utility. Also, the use of the `HOSTNAME` variable in the `/etc/sysconfig/network` file is now deprecated.

3.3. CONFIGURING HOST NAMES USING HOSTNAMECTL

The `hostnamectl` tool is provided for administering the three separate classes of host names in use on a given system.

3.3.1. View All the Host Names

To view all the current host names, enter the following command:

```
~]$ hostnamectl status
```

The `status` option is implied by default if no option is given.

3.3.2. Set All the Host Names

To set all the host names on a system, enter the following command as **root**:

```
~]# hostnamectl set-hostname name
```

This will alter the pretty, static, and transient host names alike. The static and transient host names will be simplified forms of the pretty host name. Spaces will be replaced with “-” and special characters will be removed.

3.3.3. Set a Particular Host Name

To set a particular host name, enter the following command as **root** with the relevant option:

```
~]# hostnamectl set-hostname name [option...]
```

Where *option* is one or more of: **--pretty**, **--static**, and **--transient**.

If the **--static** or **--transient** options are used together with the **--pretty** option, the static and transient host names will be simplified forms of the pretty host name. Spaces will be replaced with “-” and special characters will be removed. If the **--pretty** option is not given, no simplification takes place.

When setting a pretty host name, remember to use the appropriate quotation marks if the host name contains spaces or a single quotation mark. For example:

```
~]# hostnamectl set-hostname "Stephen's notebook" --pretty
```

3.3.4. Clear a Particular Host Name

To clear a particular host name and allow it to revert to the default, enter the following command as **root** with the relevant option:

```
~]# hostnamectl set-hostname "" [option...]
```

Where "" is a quoted empty string and where *option* is one or more of: **--pretty**, **--static**, and **--transient**.

3.3.5. Changing Host Names Remotely

To execute a **hostnamectl** command on a remote system, use the **-H**, **--host** option as follows:

```
~]# hostnamectl set-hostname -H [username]@hostname
```

Where *hostname* is the remote host you want to configure. The *username* is optional. The **hostnamectl** tool will use **SSH** to connect to the remote system.

3.4. CONFIGURING HOST NAMES USING NMCLI

The **NetworkManager** tool **nmcli** can be used to query and set the static host name in the **/etc/hostname** file.

To query the static host name, issue the following command:

```
~]$ nmcli general hostname
```


To set the static host name to *my-server*, issue the following command as **root**:

```
~]# nmcli general hostname my-server
```

3.5. ADDITIONAL RESOURCES

- **hostnamectl(1)** man page – Describes **hostnamectl** including the commands and command options.
- **hostname(1)** man page – Contains an explanation of the **hostname** and **domainname** commands.
- **hostname(5)** man page – Contains an explanation of the host name file, its contents, and use.
- **hostname(7)** man page – Contains an explanation of host name resolution.
- **machine-info(5)** man page – Describes the local machine information file and the environment variables it contains.
- **machine-id(5)** man page – Describes the local machine ID configuration file.
- **systemd-hostnamed.service(8)** man page – Describes the **systemd-hostnamed** system service used by **hostnamectl**.


CHAPTER 4. CONFIGURE NETWORK BONDING

Red Hat Enterprise Linux 7 allows administrators to bind multiple network interfaces together into a single, bonded, channel. Channel bonding enables two or more network interfaces to act as one, simultaneously increasing the bandwidth and providing redundancy.



WARNING

The use of direct cable connections without network switches is not supported for bonding. The failover mechanisms described here will not work as expected without the presence of network switches. See the Red Hat Knowledgebase article [Why is bonding in not supported with direct connection using crossover cables?](#) for more information.



NOTE

The active-backup, balance-tlb and balance-alb modes do not require any specific configuration of the switch. Other bonding modes require configuring the switch to aggregate the links. For example, a Cisco switch requires EtherChannel for Modes 0, 2, and 3, but for Mode 4 LACP and EtherChannel are required. See the documentation supplied with your switch and see <https://www.kernel.org/doc/Documentation/networking/bonding.txt>

4.1. UNDERSTANDING THE DEFAULT BEHAVIOR OF MASTER AND SLAVE INTERFACES

When controlling bonded slave interfaces using the **NetworkManager** daemon, and especially when fault finding, keep the following in mind:

1. Starting the master interface does not automatically start the slave interfaces.
2. Starting a slave interface always starts the master interface.
3. Stopping the master interface also stops the slave interfaces.
4. A master without slaves can start static **IP** connections.
5. A master without slaves waits for slaves when starting **DHCP** connections.
6. A master with a **DHCP** connection waiting for slaves completes when a slave with a carrier is added.
7. A master with a **DHCP** connection waiting for slaves continues waiting when a slave without a carrier is added.

4.2. CONFIGURE BONDING USING THE TEXT USER INTERFACE, NMTUI

The text user interface tool **nmtui** can be used to configure bonding in a terminal window. Issue the following command to start the tool:

```
~]$ nmtui
```

The text user interface appears. Any invalid command prints a usage message.

To navigate, use the arrow keys or press **Tab** to step forwards and press **Shift+Tab** to step back through the options. Press **Enter** to select an option. The **Space** bar toggles the status of a check box.

1. From the starting menu, select **Edit a connection**. Select **Add**, the **New Connection** screen opens.




Figure 4.1. The NetworkManager Text User Interface Add a Bond Connection menu

2. Select **Bond** and then **Create**; the **Edit connection** screen for the bond will open.

Edit connection

Profile name Bond connection 1
 Device bond0

BOND
Slaves

<Hide>

↑

↓

<Add>
 <Edit...>
 <Delete>

Mode <Round-robin>
 Link monitoring <MII (recommended)>
 Monitoring frequency 100 ms
 Link up delay 0 ms
 Link down delay 0 ms

= IPv4 CONFIGURATION <Automatic> <Show>
 = IPv6 CONFIGURATION <Automatic> <Show>

[X] Automatically connect
 [X] Available to all users

<Cancel> <OK>

Figure 4.2. The NetworkManager Text User Interface Configuring a Bond Connection menu

3. At this point slave interfaces will need to be added to the bond; to add these select **Add**, the **New Connection** screen opens. Once the type of Connection has been chosen select the **Create** button.




Figure 4.3. The NetworkManager Text User Interface Configuring a New Bond Slave Connection menu

4. The slave's **Edit Connection** display appears; enter the desired slave's device name or MAC address in the **Device** section. If required, enter a clone MAC address to be used as the bond's MAC address by selecting **Show** to the right of the **Ethernet** label. Select the **OK** button to save the slave.



NOTE

If the device is specified without a MAC address the **Device** section will be automatically populated once the **Edit Connection** window is reloaded, but only if it successfully finds the device.

The screenshot displays the 'Edit connection' window in the NetworkManager Text User Interface. The window has a title bar with 'Edit connection' in red. Inside, the 'Profile name' is 'Ethernet connection 1' and the 'Device' is 'ens3 (52:54:00:D3:1C:FF)'. Below these, there is a section for 'ETHERNET' settings, which includes 'Cloned MAC address' and 'MTU (default)'. To the right of the 'ETHERNET' section is a '<Hide>' button. At the bottom left, there are two checked options: '[X] Automatically connect' and '[X] Available to all users'. At the bottom right, there are two buttons: '<Cancel>' and '<OK>' (the latter is highlighted in red). On the left side of the window, there is a vertical menu with several icons, including a network icon, a plus sign, and a minus sign.

Figure 4.4. The NetworkManager Text User Interface Configuring a Bond Slave Connection menu

5. The name of the bond slave appears in the **Slaves** section. Repeat the above steps to add further slave connections.
6. Review and confirm the settings before selecting the **OK** button.




Figure 4.5. The NetworkManager Text User Interface Completed Bond

See [Section 4.6.1.1, “Configuring the Bond Tab”](#) for definitions of the bond terms.

See [Section 1.5, “Network Configuration Using a Text User Interface \(nmtui\)”](#) for information on installing **nmtui**.

4.3. NETWORK BONDING USING THE NETWORKMANAGER COMMAND LINE TOOL, NMCLI



NOTE

See [Section 2.1.5, “Using the NetworkManager Command Line Tool, nmcli”](#) for an introduction to **nmcli**.

To create a **bond** connection with the **nmcli** tool, issue the following command:

```
~]$ nmcli con add type bond ifname mybond0
Connection 'bond-mybond0' (5f739690-47e8-444b-9620-1895316a28ba)
successfully added.
```

Note that as no **con-name** was given for the bond, the connection name was derived from the interface name by prepending the type.

NetworkManager supports most of the bonding options provided by the kernel. For example:

```
~]$ nmcli con add type bond ifname mybond0 bond.options "mode=balance-rr,miimon=100"  
Connection 'bond-mybond0' (5f739690-47e8-444b-9620-1895316a28ba)  
successfully added.
```

To add a **slave** interface:

1. Create a new connection, see [the section called “Creating and Modifying a Connection Profile”](#) for details.
2. Set the master property to the **bond** interface name, or to the name of the master connection:

```
~]$ nmcli con add type ethernet ifname ens3 master mybond0  
Connection 'bond-slave-ens3' (220f99c6-ee0a-42a1-820e-454cbabc2618)  
successfully added.
```

To add a new **slave** interface, repeat the previous command with the new interface. For example:

```
~]$ nmcli con add type ethernet ifname ens7 master mybond0  
Connection 'bond-slave-ens7' (ecc24c75-1c89-401f-90c8-9706531e0231)  
successfully added.
```

To activate the slaves, issue a command as follows:

```
~]$ nmcli con up bond-slave-ens7  
Connection successfully activated (D-Bus active path:  
/org/freedesktop/NetworkManager/ActiveConnection/14)
```

```
~]$ nmcli con up bond-slave-ens3  
Connection successfully activated (D-Bus active path:  
/org/freedesktop/NetworkManager/ActiveConnection/15)
```

When you activate a slave, the master connection also starts. You can see [Section 4.1, “Understanding the Default Behavior of Master and Slave Interfaces”](#) for more information. In this case, it is not necessary to manually activate the master connection.

It is possible to change the **active_slave** option and the **primary** option of the bond at runtime, without deactivating the connection. For example to change the **active_slave** option, issue the following command:

```
~]$ nmcli dev mod bond0 +bond.options "active_slave=ens7"  
Connection successfully reapplied to device 'bond0'.
```

or to change the **primary** option:

```
~]$ nmcli dev mod bond0 +bond.options "primary=ens3"  
Connection successfully reapplied to device 'bond0'.
```




NOTE

The `active_slave` option sets the currently active slave whereas the `primary` option of the bond specifies the active slave to be automatically selected by kernel when a new slave is added or a failure of the active slave occurs.

4.4. USING THE COMMAND LINE INTERFACE (CLI)

A bond is created using the `bonding` kernel module and a special network interface called a *channel bonding interface*.

4.4.1. Check if Bonding Kernel Module is Installed

In Red Hat Enterprise Linux 7, the `bonding` module is not loaded by default. You can load the module by issuing the following command as `root`:

```
~]# modprobe --first-time bonding
```

This activation will not persist across system restarts. See the [Red Hat Enterprise Linux System Administrator's Guide](#) for an explanation of persistent module loading. Note that given a correct configuration file using the `BONDING_OPTS` directive, the `bonding` module will be loaded as required and therefore does not need to be loaded separately.

To display information about the module, issue the following command:

```
~]$ modinfo bonding
```

See the `modprobe(8)` man page for more command options.

4.4.2. Create a Channel Bonding Interface

To create a channel bonding interface, create a file in the `/etc/sysconfig/network-scripts/` directory called `ifcfg-bondN`, replacing `N` with the number for the interface, such as `0`.

The contents of the file can be based on a configuration file for whatever type of interface is getting bonded, such as an Ethernet interface. The essential differences are that the `DEVICE` directive is `bondN`, replacing `N` with the number for the interface, and `TYPE=Bond`. In addition, set `BONDING_MASTER=yes`.

Example 4.1. Example `ifcfg-bond0` Interface Configuration File

An example of a channel bonding interface.

```
DEVICE=bond0
NAME=bond0
TYPE=Bond
BONDING_MASTER=yes
IPADDR=192.168.1.1
PREFIX=24
ONBOOT=yes
BOOTPROTO=none
BONDING_OPTS="bonding parameters separated by spaces"
```

The **NAME** directive is useful for naming the connection profile in **NetworkManager**. **ONBOOT** says whether the profile should be started when booting (or more generally, when auto-connecting a device).

IMPORTANT

Parameters for the bonding kernel module must be specified as a space-separated list in the **BONDING_OPTS="bonding parameters"** directive in the **ifcfg-bondN** interface file. Do *not* specify options for the bonding device in **/etc/modprobe.d/bonding.conf**, or in the deprecated **/etc/modprobe.conf** file.

The **max_bonds** parameter is not interface specific and should not be set when using **ifcfg-bondN** files with the **BONDING_OPTS** directive as this directive will cause the network scripts to create the bond interfaces as required.

For further instructions and advice on configuring the bonding module and to view the list of bonding parameters, see [Section 4.5, “Using Channel Bonding”](#).

4.4.3. Creating SLAVE Interfaces

The channel bonding interface is the “master” and the interfaces to be bonded are referred to as the “slaves”. After the channel bonding interface is created, the network interfaces to be bound together must be configured by adding the **MASTER** and **SLAVE** directives to the configuration files of the slaves. The configuration files for each of the slave interfaces can be nearly identical.

Example 4.2. Example Slave Interface Configuration File

For example, if two Ethernet interfaces are being channel bonded, **eth0** and **eth1**, they can both look like the following example:

```
DEVICE=ethN
NAME=bond0-slave
TYPE=Ethernet
BOOTPROTO=none
ONBOOT=yes
MASTER=bond0
SLAVE=yes
```

In this example, replace *N* with the numerical value for the interface. Note that if more than one profile or configuration file exists with **ONBOOT=yes** for an interface, they may race with each other and a plain **TYPE=Ethernet** profile may be activated instead of a bond slave.

4.4.4. Activating a Channel Bond

To activate a bond, open all the slaves. As **root**, issue the following commands:

```
~]# ifup ifcfg-eth0
Connection successfully activated (D-Bus active path:
/org/freedesktop/NetworkManager/ActiveConnection/7)
```

```
~]# ifup ifcfg-eth1
Connection successfully activated (D-Bus active path:
/org/freedesktop/NetworkManager/ActiveConnection/8)
```

Note that if editing interface files for interfaces which are currently “up”, set them down first as follows:

```
ifdown ethN
```

Then when complete, open all the slaves, which will open the bond (provided it was not set “down”).

To make **NetworkManager** aware of the changes, issue a command for every changed interface as **root**:

```
~]# nmcli con load /etc/sysconfig/network-scripts/ifcfg-device
```

Alternatively, to reload all interfaces:

```
~]# nmcli con reload
```

The default behavior is for **NetworkManager** not to be aware of the changes and to continue using the old configuration data. This is set by the **monitor-connection-files** option in the **NetworkManager.conf** file. See the **NetworkManager.conf(5)** manual page for more information.

To view the status of the bond interface, issue the following command:

```
~]# ip link show
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN mode
DEFAULT
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
2: eth0: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast
master bond0 state UP mode DEFAULT qlen 1000
    link/ether 52:54:00:e9:ce:d2 brd ff:ff:ff:ff:ff:ff
3: eth1: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast
master bond0 state UP mode DEFAULT qlen 1000
    link/ether 52:54:00:38:a6:4c brd ff:ff:ff:ff:ff:ff
4: bond0: <BROADCAST,MULTICAST,MASTER,UP,LOWER_UP> mtu 1500 qdisc noqueue
state UP mode DEFAULT
    link/ether 52:54:00:38:a6:4c brd ff:ff:ff:ff:ff:ff
```

4.4.5. Creating Multiple Bonds

In Red Hat Enterprise Linux, for each bond a channel bonding interface is created including the **BONDING_OPTS** directive. This configuration method is used so that multiple bonding devices can have different configurations. To create multiple channel bonding interfaces, proceed as follows:

- Create multiple **ifcfg-bondN** files with the **BONDING_OPTS** directive; this directive will cause the network scripts to create the bond interfaces as required.
- Create, or edit existing, interface configuration files to be bonded and include the **SLAVE** directive.
- Assign the interfaces to be bonded, the slave interfaces, to the channel bonding interfaces by means of the **MASTER** directive.

Example 4.3. Example multiple ifcfg-bondN interface configuration files

The following is an example of a channel bonding interface configuration file:

```
DEVICE=bondN
NAME=bondN
TYPE=Bond
BONDING_MASTER=yes
IPADDR=192.168.1.1
PREFIX=24
ONBOOT=yes
BOOTPROTO=none
BONDING_OPTS="bonding parameters separated by spaces"
```

In this example, replace *N* with the number for the bond interface. For example, to create two bonds create two configuration files, `ifcfg-bond0` and `ifcfg-bond1`, with appropriate IP addresses.

Create the interfaces to be bonded as per [Example 4.2, “Example Slave Interface Configuration File”](#) and assign them to the bond interfaces as required using the `MASTER=bondN` directive. For example, continuing on from the example above, if two interfaces per bond are required, then for two bonds create four interface configuration files and assign the first two using `MASTER=bond0` and the next two using `MASTER=bond1`.

4.5. USING CHANNEL BONDING

To enhance performance, adjust available module options to ascertain what combination works best. Pay particular attention to the `miimon` or `arp_interval` and the `arp_ip_target` parameters. See [Section 4.5.1, “Bonding Module Directives”](#) for a list of available options and how to quickly determine the best ones for your bonded interface.

4.5.1. Bonding Module Directives

It is a good idea to test which channel bonding module parameters work best for your bonded interfaces before adding them to the `BONDING_OPTS="bonding parameters"` directive in your bonding interface configuration file (`ifcfg-bond0` for example). Parameters to bonded interfaces can be configured without unloading (and reloading) the bonding module by manipulating files in the `sysfs` file system.

`sysfs` is a virtual file system that represents kernel objects as directories, files and symbolic links. `sysfs` can be used to query for information about kernel objects, and can also manipulate those objects through the use of normal file system commands. The `sysfs` virtual file system is mounted under the `/sys/` directory. All bonding interfaces can be configured dynamically by interacting with and manipulating files under the `/sys/class/net/` directory.

In order to determine the best parameters for your bonding interface, create a channel bonding interface file such as `ifcfg-bond0` by following the instructions in [Section 4.4.2, “Create a Channel Bonding Interface”](#). Insert the `SLAVE=yes` and `MASTER=bond0` directives in the configuration files for each interface bonded to `bond0`. Once this is completed, you can proceed to testing the parameters.

First, open the bond you created by running `ifup bondN` as root:

```
~]# ifup bond0
```

If you have correctly created the `ifcfg-bond0` bonding interface file, you will be able to see `bond0` listed in the output of running `ip link show as root`:

```
~]# ip link show
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN mode
  DEFAULT
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
2: eth0: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast
  master bond0 state UP mode DEFAULT qlen 1000
    link/ether 52:54:00:e9:ce:d2 brd ff:ff:ff:ff:ff:ff
3: eth1: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast
  master bond0 state UP mode DEFAULT qlen 1000
    link/ether 52:54:00:38:a6:4c brd ff:ff:ff:ff:ff:ff
4: bond0: <BROADCAST,MULTICAST,MASTER,UP,LOWER_UP> mtu 1500 qdisc noqueue
  state UP mode DEFAULT
    link/ether 52:54:00:38:a6:4c brd ff:ff:ff:ff:ff:ff
```

To view all existing bonds, even if they are not up, run:

```
~]$ cat /sys/class/net/bonding_masters
bond0
```

You can configure each bond individually by manipulating the files located in the `/sys/class/net/bondN/bonding/` directory. First, the bond you are configuring must be taken down:

```
~]# ifdown bond0
```

As an example, to enable MII monitoring on `bond0` with a 1 second interval, run as `root`:

```
~]# echo 1000 > /sys/class/net/bond0/bonding/miimon
```

To configure `bond0` for ***balance-alb*** mode, run either:

```
~]# echo 6 > /sys/class/net/bond0/bonding/mode
```

...or, using the name of the mode:

```
~]# echo balance-alb > /sys/class/net/bond0/bonding/mode
```

After configuring options for the bond in question, you can bring it up and test it by running `ifup bondN`. If you decide to change the options, take the interface down, modify its parameters using `sysfs`, bring it back up, and re-test.

Once you have determined the best set of parameters for your bond, add those parameters as a space-separated list to the ***BONDING_OPTS***= directive of the `/etc/sysconfig/network-scripts/ifcfg-bondN` file for the bonding interface you are configuring. Whenever that bond is brought up (for example, by the system during the boot sequence if the ***ONBOOT=yes*** directive is set), the bonding options specified in the ***BONDING_OPTS*** will take effect for that bond.

The following list provides the names of many of the more common channel bonding parameters, along with a description of what they do. For more information, see the brief descriptions for each `parm` in `modinfo bonding` output, or for more detailed information, see

<https://www.kernel.org/doc/Documentation/networking/bonding.txt>.

Bonding Interface Parameters

ad_select=value

Specifies the 802.3ad aggregation selection logic to use. Possible values are:

- **stable** or **0** – Default setting. The active aggregator is chosen by largest aggregate bandwidth. Reselection of the active aggregator occurs only when all slaves of the active aggregator are down or if the active aggregator has no slaves.
- **bandwidth** or **1** – The active aggregator is chosen by largest aggregate bandwidth. Reselection occurs if:
 - A slave is added to or removed from the bond;
 - Any slave's link state changes;
 - Any slave's 802.3ad association state changes;
 - The bond's administrative state changes to up.
- **count** or **2** – The active aggregator is chosen by the largest number of slaves. Reselection occurs as described for the **bandwidth** setting above.

The **bandwidth** and **count** selection policies permit failover of 802.3ad aggregations when partial failure of the active aggregator occurs. This keeps the aggregator with the highest availability, either in bandwidth or in number of slaves, active at all times.

arp_interval=time_in_milliseconds

Specifies, in milliseconds, how often **ARP** monitoring occurs.



IMPORTANT

It is essential that both **arp_interval** and **arp_ip_target** parameters are specified, or, alternatively, the **miimon** parameter is specified. Failure to do so can cause degradation of network performance in the event that a link fails.

If using this setting while in **mode=0** or **mode=2** (the two load-balancing modes), the network switch must be configured to distribute packets evenly across the NICs. For more information on how to accomplish this, see <https://www.kernel.org/doc/Documentation/networking/bonding.txt>.

The value is set to **0** by default, which disables it.

arp_ip_target=ip_address[, ip_address_2,...ip_address_16]

Specifies the target **IP** address of **ARP** requests when the **arp_interval** parameter is enabled. Up to 16 **IP** addresses can be specified in a comma separated list.

arp_validate=value

Validate source/distribution of **ARP** probes; default is **none**. Other valid values are **active**, **backup**, and **all**.

`downdelay=time_in_milliseconds`

Specifies (in milliseconds) how long to wait after link failure before disabling the link. The value must be a multiple of the value specified in the `miimon` parameter. The value is set to `0` by default, which disables it.

`fail_over_mac=value`

Specifies whether active-backup mode should set all slaves to the same MAC address at enslavement (the traditional behavior), or, when enabled, perform special handling of the bond's MAC address in accordance with the selected policy. Possible values are:

- **none** or **0** – Default setting. This setting disables `fail_over_mac`, and causes bonding to set all slaves of an active-backup bond to the same MAC address at enslavement time.
- **active** or **1** – The “active” `fail_over_mac` policy indicates that the MAC address of the bond should always be the MAC address of the currently active slave. The MAC address of the slaves is not changed; instead, the MAC address of the bond changes during a failover.

This policy is useful for devices that cannot ever alter their MAC address, or for devices that refuse incoming broadcasts with their own source MAC (which interferes with the ARP monitor). The disadvantage of this policy is that every device on the network must be updated by gratuitous ARP, as opposed to the normal method of switches snooping incoming traffic to update their ARP tables. If the gratuitous ARP is lost, communication may be disrupted.

When this policy is used in conjunction with the MII monitor, devices which assert link up prior to being able to actually transmit and receive are particularly susceptible to loss of the gratuitous ARP, and an appropriate updelay setting may be required.

- **follow** or **2** – The “follow” `fail_over_mac` policy causes the MAC address of the bond to be selected normally (normally the MAC address of the first slave added to the bond). However, the second and subsequent slaves are not set to this MAC address while they are in a backup role; a slave is programmed with the bond's MAC address at failover time (and the formerly active slave receives the newly active slave's MAC address).

This policy is useful for multiport devices that either become confused or incur a performance penalty when multiple ports are programmed with the same MAC address.

`lacp_rate=value`

Specifies the rate at which link partners should transmit LACPDU packets in 802.3ad mode. Possible values are:

- **slow** or **0** – Default setting. This specifies that partners should transmit LACPDUs every 30 seconds.
- **fast** or **1** – Specifies that partners should transmit LACPDUs every 1 second.

`miimon=time_in_milliseconds`

Specifies (in milliseconds) how often MII link monitoring occurs. This is useful if high availability is required because MII is used to verify that the NIC is active. To verify that the driver for a particular NIC supports the MII tool, type the following command as root:

```
~]# ethtool interface_name | grep "Link detected:"
```

In this command, replace `interface_name` with the name of the device interface, such as `eth0`, not

the bond interface. If MII is supported, the command returns:

```
Link detected: yes
```

If using a bonded interface for high availability, the module for each NIC must support MII. Setting the value to **0** (the default), turns this feature off. When configuring this setting, a good starting point for this parameter is **100**.



IMPORTANT

It is essential that both **arp_interval** and **arp_ip_target** parameters are specified, or, alternatively, the **miimon** parameter is specified. Failure to do so can cause degradation of network performance in the event that a link fails.

mode=*value*

Allows you to specify the bonding policy. The *value* can be one of:

- **balance-rr** or **0** – Sets a round-robin policy for fault tolerance and load balancing. Transmissions are received and sent out sequentially on each bonded slave interface beginning with the first one available.
- **active-backup** or **1** – Sets an active-backup policy for fault tolerance. Transmissions are received and sent out through the first available bonded slave interface. Another bonded slave interface is only used if the active bonded slave interface fails.
- **balance-xor** or **2** – Transmissions are based on the selected hash policy. The default is to derive a hash by XOR of the source and destination MAC addresses multiplied by the modulo of the number of slave interfaces. In this mode traffic destined for specific peers will always be sent over the same interface. As the destination is determined by the MAC addresses this method works best for traffic to peers on the same link or local network. If traffic has to pass through a single router then this mode of traffic balancing will be suboptimal.
- **broadcast** or **3** – Sets a broadcast policy for fault tolerance. All transmissions are sent on all slave interfaces.
- **802.3ad** or **4** – Sets an IEEE 802.3ad dynamic link aggregation policy. Creates aggregation groups that share the same speed and duplex settings. Transmits and receives on all slaves in the active aggregator. Requires a switch that is 802.3ad compliant.
- **balance-tlb** or **5** – Sets a Transmit Load Balancing (TLB) policy for fault tolerance and load balancing. The outgoing traffic is distributed according to the current load on each slave interface. Incoming traffic is received by the current slave. If the receiving slave fails, another slave takes over the MAC address of the failed slave. This mode is only suitable for local addresses known to the kernel bonding module and therefore cannot be used behind a bridge with virtual machines.
- **balance-alb** or **6** – Sets an Adaptive Load Balancing (ALB) policy for fault tolerance and load balancing. Includes transmit and receive load balancing for **IPv4** traffic. Receive load balancing is achieved through **ARP** negotiation. This mode is only suitable for local addresses known to the kernel bonding module and therefore cannot be used behind a bridge with virtual machines.

primary=interface_name

Specifies the interface name, such as **eth0**, of the primary device. The **primary** device is the first of the bonding interfaces to be used and is not abandoned unless it fails. This setting is particularly useful when one NIC in the bonding interface is faster and, therefore, able to handle a bigger load.

This setting is only valid when the bonding interface is in **active-backup** mode. See <https://www.kernel.org/doc/Documentation/networking/bonding.txt> for more information.

primary_reselect=value

Specifies the reselection policy for the primary slave. This affects how the primary slave is chosen to become the active slave when failure of the active slave or recovery of the primary slave occurs. This parameter is designed to prevent flip-flopping between the primary slave and other slaves. Possible values are:

- **always** or **0** (default) – The primary slave becomes the active slave whenever it comes back up.
- **better** or **1** – The primary slave becomes the active slave when it comes back up, if the speed and duplex of the primary slave is better than the speed and duplex of the current active slave.
- **failure** or **2** – The primary slave becomes the active slave only if the current active slave fails and the primary slave is up.

The **primary_reselect** setting is ignored in two cases:

- If no slaves are active, the first slave to recover is made the active slave.
- When initially enslaved, the primary slave is always made the active slave.

Changing the **primary_reselect** policy through **sysfs** will cause an immediate selection of the best active slave according to the new policy. This may or may not result in a change of the active slave, depending upon the circumstances

resend_igmp=range

Specifies the number of IGMP membership reports to be issued after a failover event. One membership report is issued immediately after the failover, subsequent packets are sent in each 200ms interval.

The valid range is **0** to **255**; the default value is **1**. A value of **0** prevents the IGMP membership report from being issued in response to the failover event.

This option is useful for bonding modes **balance-rr** (mode 0), **active-backup** (mode 1), **balance-tlb** (mode 5) and **balance-alb** (mode 6), in which a failover can switch the IGMP traffic from one slave to another. Therefore a fresh IGMP report must be issued to cause the switch to forward the incoming IGMP traffic over the newly selected slave.

updelay=time_in_milliseconds

Specifies (in milliseconds) how long to wait before enabling a link. The value must be a multiple of the value specified in the **miimon** parameter. The value is set to **0** by default, which disables it.

use_carrier=number

Specifies whether or not `miimon` should use MII/ETHTOOL ioctls or `netif_carrier_ok()` to determine the link state. The `netif_carrier_ok()` function relies on the device driver to maintain its state with `netif_carrier_on/off`; most device drivers support this function.

The MII/ETHTOOL ioctls tools utilize a deprecated calling sequence within the kernel. However, this is still configurable in case your device driver does not support `netif_carrier_on/off`.

Valid values are:

- **1** – Default setting. Enables the use of `netif_carrier_ok()`.
- **0** – Enables the use of MII/ETHTOOL ioctls.



NOTE

If the bonding interface insists that the link is up when it should not be, it is possible that your network device driver does not support `netif_carrier_on/off`.

`xmit_hash_policy=value`

Selects the transmit hash policy used for slave selection in **balance-xor** and **802.3ad** modes. Possible values are:

- **0** or **layer2** – Default setting. This parameter uses the XOR of hardware MAC addresses to generate the hash. The formula used is:

```
(source_MAC_address XOR destination_MAC) MODULO slave_count
```

This algorithm will place all traffic to a particular network peer on the same slave, and is 802.3ad compliant.

- **1** or **layer3+4** – Uses upper layer protocol information (when available) to generate the hash. This allows for traffic to a particular network peer to span multiple slaves, although a single connection will not span multiple slaves.

The formula for unfragmented TCP and UDP packets used is:

```
((source_port XOR dest_port) XOR
 ((source_IP XOR dest_IP) AND 0xffff)
 MODULO slave_count
```

For fragmented TCP or UDP packets and all other IP protocol traffic, the source and destination port information is omitted. For non-IP traffic, the formula is the same as the **layer2** transmit hash policy.

This policy intends to mimic the behavior of certain switches; particularly, Cisco switches with PFC2 as well as some Foundry and IBM products.

The algorithm used by this policy is not 802.3ad compliant.

- **2** or **layer2+3** – Uses a combination of layer2 and layer3 protocol information to generate the hash.

Uses XOR of hardware MAC addresses and **IP** addresses to generate the hash. The formula is:

```
(( (source_IP XOR dest_IP) AND 0xffff) XOR
 ( source_MAC XOR destination_MAC ))
MODULO slave_count
```

This algorithm will place all traffic to a particular network peer on the same slave. For non-**IP** traffic, the formula is the same as for the layer2 transmit hash policy.

This policy is intended to provide a more balanced distribution of traffic than layer2 alone, especially in environments where a layer3 gateway device is required to reach most destinations.

This algorithm is 802.3ad compliant.

4.6. CREATING A BOND CONNECTION USING A GUI

You can use the GNOME **control-center** utility to direct **NetworkManager** to create a Bond from two or more Wired or InfiniBand connections. It is not necessary to create the connections to be bonded first. They can be configured as part of the process to configure the bond. You must have the MAC addresses of the interfaces available in order to complete the configuration process.

4.6.1. Establishing a Bond Connection

Procedure 4.1. Adding a New Bond Connection

Follow the below steps to create a new bond connection.

1. Press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears. This step is fully covered in [Section 2.3, “Using NetworkManager with the GNOME Graphical User Interface”](#).
2. Click the plus symbol to open the selection list. Select **Bond**. The **Editing Bond connection 1** window appears.

Editing Bond connection 1

Connection name:

General **Bond** IPv4 Settings IPv6 Settings

Interface name:

Bonded connections:

Mode: ▾

Link Monitoring: ▾

Monitoring frequency: ms

Link up delay: ms

Link down delay: ms

Figure 4.6. The NetworkManager Graphical User Interface Add a Bond menu

- On the **Bond** tab, click **Add** and select the type of interface you want to use with the bond connection. Click the **Create** button. Note that the dialog to select the slave type only comes up when you create the first slave; after that, it will automatically use that same type for all further slaves.
- The **Editing bond0 slave 1** window appears. Use the **Device MAC address** drop-down menu to select the MAC address of the interface to be bonded. The first slave's MAC address will be used as the MAC address for the bond interface. If required, enter a clone MAC address to be used as the bond's MAC address. Click the **Save** button.




Figure 4.7. The NetworkManager Graphical User Interface Add a Bond Connection menu

5. The name of the bonded slave appears in the **Bonded connections** window. Click the **Add** button to add further slave connections.
6. Review and confirm the settings and then click the **Save** button.
7. Edit the bond-specific settings by referring to [Section 4.6.1.1, “Configuring the Bond Tab”](#) below.

Procedure 4.2. Editing an Existing Bond Connection

Follow these steps to edit an existing bond connection.

1. Press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears.
2. Select the connection you want to edit and click the **Options** button.
3. Select the **General** tab.
4. Configure the connection name, auto-connect behavior, and availability settings.

Five settings in the **Editing** dialog are common to all connection types, see the **General** tab:

- **Connection name** – Enter a descriptive name for your network connection. This name will be used to list this connection in the menu of the **Network** window.
- **Automatically connect to this network when it is available** – Select this

box if you want **NetworkManager** to auto-connect to this connection when it is available. See [Section 2.3.3, “Connecting to a Network Automatically”](#) for more information.

- **All users may connect to this network** – Select this box to create a connection available to all users on the system. Changing this setting may require root privileges. See [Section 2.3.5, “System-wide and Private Connection Profiles”](#) for details.
 - **Automatically connect to VPN when using this connection** – Select this box if you want **NetworkManager** to auto-connect to a VPN connection when it is available. Select the VPN from the drop-down menu.
 - **Firewall Zone** – Select the firewall zone from the drop-down menu. See the [Red Hat Enterprise Linux 7 Security Guide](#) for more information on firewall zones.
5. Edit the bond-specific settings by referring to [Section 4.6.1.1, “Configuring the Bond Tab”](#) below.

Saving Your New (or Modified) Connection and Making Further Configurations

Once you have finished editing your bond connection, click the **Save** button to save your customized configuration. If the profile was in use while being edited, power cycle the connection to make **NetworkManager** apply the changes. If the profile is OFF, set it to ON or select it in the network connection icon's menu. See [Section 2.3.1, “Connecting to a Network Using a GUI”](#) for information on using your new or altered connection.

You can further configure an existing connection by selecting it in the **Network** window and clicking **Options** to return to the **Editing** dialog.

Then, to configure:

- **IPv4** settings for the connection, click the **IPv4 Settings** tab and proceed to [Section 2.7.6, “Configuring IPv4 Settings”](#); or,
- **IPv6** settings for the connection, click the **IPv6 Settings** tab and proceed to [Section 2.7.7, “Configuring IPv6 Settings”](#).

Once saved the Bond will appear in the Network settings tool with each slave showing in the display.




Figure 4.8. The NetworkManager Graphical User Interface with Bond

4.6.1.1. Configuring the Bond Tab

If you have already added a new bond connection (see [Procedure 4.1, “Adding a New Bond Connection”](#) for instructions), you can edit the **Bond** tab to set the load sharing mode and the type of link monitoring to use to detect failures of a slave connection.

Mode

The mode that is used to share traffic over the slave connections which make up the bond. The default is **Round-robin**. Other load sharing modes, such as **802.3ad**, can be selected by means of the drop-down list.

Link Monitoring

The method of monitoring the slaves ability to carry network traffic.

The following modes of load sharing are selectable from the **Mode** drop-down list:

Round-robin

Sets a round-robin policy for fault tolerance and load balancing. Transmissions are received and sent out sequentially on each bonded slave interface beginning with the first one available. This mode might not work behind a bridge with virtual machines without additional switch configuration.

Active backup

Sets an active-backup policy for fault tolerance. Transmissions are received and sent out through the first available bonded slave interface. Another bonded slave interface is only used if the active bonded slave interface fails. Note that this is the only mode available for bonds of InfiniBand devices.

XOR

Sets an XOR (exclusive-or) policy. Transmissions are based on the selected hash policy. The default is to derive a hash by XOR of the source and destination MAC addresses multiplied by the modulo of the number of slave interfaces. In this mode traffic destined for specific peers will always be sent over the same interface. As the destination is determined by the MAC addresses this method works best for traffic to peers on the same link or local network. If traffic has to pass through a single router then this mode of traffic balancing will be suboptimal.

Broadcast

Sets a broadcast policy for fault tolerance. All transmissions are sent on all slave interfaces. This mode might not work behind a bridge with virtual machines without additional switch configuration.

802.3ad

Sets an IEEE **802.3ad** dynamic link aggregation policy. Creates aggregation groups that share the same speed and duplex settings. Transmits and receives on all slaves in the active aggregator. Requires a network switch that is **802.3ad** compliant.

Adaptive transmit load balancing

Sets an adaptive Transmit Load Balancing (TLB) policy for fault tolerance and load balancing. The outgoing traffic is distributed according to the current load on each slave interface. Incoming traffic is received by the current slave. If the receiving slave fails, another slave takes over the MAC address of the failed slave. This mode is only suitable for local addresses known to the kernel bonding module and therefore cannot be used behind a bridge with virtual machines.

Adaptive load balancing

Sets an Adaptive Load Balancing (ALB) policy for fault tolerance and load balancing. Includes transmit and receive load balancing for **IPv4** traffic. Receive load balancing is achieved through **ARP** negotiation. This mode is only suitable for local addresses known to the kernel bonding module and therefore cannot be used behind a bridge with virtual machines.

The following types of link monitoring can be selected from the **Link Monitoring** drop-down list. It is a good idea to test which channel bonding module parameters work best for your bonded interfaces.

MII (Media Independent Interface)

The state of the carrier wave of the interface is monitored. This can be done by querying the driver, by querying MII registers directly, or by using **ethtool** to query the device. Three options are available:

Monitoring Frequency

The time interval, in milliseconds, between querying the driver or MII registers.

Link up delay

The time in milliseconds to wait before attempting to use a link that has been reported as up. This delay can be used if some gratuitous **ARP** requests are lost in the period immediately following the link being reported as “up”. This can happen during switch initialization for example.

Link down delay

The time in milliseconds to wait before changing to another link when a previously active link has been reported as “down”. This delay can be used if an attached switch takes a relatively long time to change to backup mode.

ARP

The address resolution protocol (**ARP**) is used to probe one or more peers to determine how well the link-layer connections are working. It is dependent on the device driver providing the transmit start time and the last receive time.

Two options are available:

Monitoring Frequency

The time interval, in milliseconds, between sending **ARP** requests.

ARP targets

A comma separated list of **IP** addresses to send **ARP** requests to.

4.7. ADDITIONAL RESOURCES

Installed Documentation

- **nmcli(1)** man page – Describes **NetworkManager**'s command-line tool.
- **nmcli-examples(5)** man page – Gives examples of **nmcli** commands.
- **nm-settings(5)** man page – Description of settings and parameters of **NetworkManager** connections.

Online Documentation

Red Hat Enterprise Linux System Administrator's Guide

Explains the use of kernel module capabilities.

https://access.redhat.com/site/node/28421/Configuring_VLAN_devices_over_a_bonded_interface

A Red Hat Knowledgebase article about Configuring VLAN devices over a bonded interface.

CHAPTER 5. CONFIGURE NETWORK TEAMING

5.1. UNDERSTANDING NETWORK TEAMING

The combining or aggregating of network links to provide a logical link with higher throughput, or to provide redundancy, is known by many names, for example *channel bonding*, *Ethernet bonding*, *port trunking*, *channel teaming*, *NIC teaming*, or *link aggregation*. This concept as originally implemented in the Linux kernel is widely referred to as **bonding**. The term *Network Teaming* has been chosen to refer to this new implementation of the concept. The existing bonding driver is unaffected, Network Teaming is offered as an alternative and does not replace bonding in Red Hat Enterprise Linux 7.



NOTE

Regarding the Mode 4 Link Aggregation Control Protocol (LACP) teaming mode, requires configuring the switch to aggregate the links. For more details, see <https://www.kernel.org/doc/Documentation/networking/bonding.txt>

Network Teaming, or Team, is designed to implement the concept in a different way by providing a small kernel driver to implement the fast handling of packet flows, and various user-space applications to do everything else in user space. The driver has an *Application Programming Interface* (API), referred to as “Team Netlink API”, which implements Netlink communications. User-space applications can use this API to communicate with the driver. A library, referred to as “lib”, has been provided to do user space wrapping of Team Netlink communications and RT Netlink messages. An application daemon, **teamd**, which uses the **libteam** library is also available. One instance of **teamd** can control one instance of the Team driver. The daemon implements the load-balancing and active-backup logic, such as round-robin, by using additional code referred to as “runners”. By separating the code in this way, the Network Teaming implementation presents an easily extensible and scalable solution for load-balancing and redundancy requirements. For example, custom runners can be relatively easily written to implement new logic through **teamd**, and even **teamd** is optional, users can write their own application to use **libteam**.

The **teamdctl** utility is available to control a running instance of **teamd** using D-bus. **teamdctl** provides a D-Bus wrapper around the **teamd** D-Bus API. By default, **teamd** listens and communicates using Unix Domain Sockets but still monitors D-Bus. This is to ensure that **teamd** can be used in environments where D-Bus is not present or not yet loaded. For example, when booting over **teamd** links, D-Bus would not yet be loaded. The **teamdctl** utility can be used during run time to read the configuration, the state of link-watchers, check and change the state of ports, add and remove ports, and to change ports between active and backup states.

Team Netlink API communicates with user-space applications using Netlink messages. The **libteam** user-space library does not directly interact with the API, but uses **libnl** or **teamnl** to interact with the driver API.

To sum up, the instances of Team driver, running in the kernel, do not get configured or controlled directly. All configuration is done with the aid of user space applications, such as the **teamd** application. The application then directs the kernel driver part accordingly.



NOTE

In the context of network teaming, the term **port** is also known as **slave**. **Port** is preferred when using **teamd** directly while **slave** is used when using **NetworkManager** to refer to interfaces which create a team.

5.2. UNDERSTANDING THE DEFAULT BEHAVIOR OF MASTER AND SLAVE INTERFACES

When controlling teamed port interfaces using the `NetworkManager` daemon, and especially when fault finding, keep the following in mind:

1. Starting the master interface does not automatically start the port interfaces.
2. Starting a port interface always starts the master interface.
3. Stopping the master interface also stops the port interfaces.
4. A master without ports can start static **IP** connections.
5. A master without ports waits for ports when starting **DHCP** connections.
6. A master with a **DHCP** connection waiting for ports completes when a port with a carrier is added.
7. A master with a **DHCP** connection waiting for ports continues waiting when a port without a carrier is added.



WARNING

The use of direct cable connections without network switches is not supported for teaming. The failover mechanisms described here will not work as expected without the presence of network switches. See the Red Hat Knowledgebase article [Why is bonding not supported with direct connection using crossover cables?](#) for more information.

5.3. COMPARISON OF NETWORK TEAMING TO BONDING

Table 5.1. A Comparison of Features in Bonding and Team

Feature	Bonding	Team
broadcast Tx policy	Yes	Yes
round-robin Tx policy	Yes	Yes
active-backup Tx policy	Yes	Yes
LACP (802.3ad) support	Yes (active only)	Yes
Hash-based Tx policy	Yes	Yes
User can set hash function	No	Yes

Feature	Bonding	Team
Tx load-balancing support (TLB)	Yes	Yes
LACP hash port select	Yes	Yes
load-balancing for LACP support	No	Yes
Ethtool link monitoring	Yes	Yes
ARP link monitoring	Yes	Yes
NS/NA (IPv6) link monitoring	No	Yes
ports up/down delays	Yes	Yes
port priorities and stickiness ("primary" option enhancement)	No	Yes
separate per-port link monitoring setup	No	Yes
multiple link monitoring setup	Limited	Yes
lockless Tx/Rx path	No (rwlock)	Yes (RCU)
VLAN support	Yes	Yes
user-space runtime control	Limited	Full
Logic in user-space	No	Yes
Extensibility	Hard	Easy
Modular design	No	Yes
Performance overhead	Low	Very Low
D-Bus interface	No	Yes
multiple device stacking	Yes	Yes
zero config using LLDP	No	(in planning)
NetworkManager support	Yes	Yes

5.4. UNDERSTANDING THE NETWORK TEAMING DAEMON AND THE "RUNNERS"

The Team daemon, **teamd**, uses **libteam** to control one instance of the team driver. This instance of the team driver adds instances of a hardware device driver to form a “team” of network links. The team driver presents a network interface, **team0** for example, to the other parts of the kernel. The interfaces created by instances of the team driver are given names such as **team0**, **team1**, and so forth in the documentation. This is for ease of understanding and other names can be used. The logic common to all methods of teaming is implemented by **teamd**; those functions that are unique to the different load sharing and backup methods, such as round-robin, are implemented by separate units of code referred to as “runners”. Because words such as “module” and “mode” already have specific meanings in relation to the kernel, the word “runner” was chosen to refer to these units of code. The user specifies the runner in the JSON format configuration file and the code is then compiled into an instance of **teamd** when the instance is created. A runner is not a plug-in because the code for a runner is compiled into an instance of **teamd** as it is being created. Code could be created as a plug-in for **teamd** should the need arise.

The following runners are available at time of writing.

- **broadcast** (data is transmitted over all ports)
- **round-robin** (data is transmitted over all ports in turn)
- **active-backup** (one port or link is used while others are kept as a backup)
- **loadbalance** (with active Tx load balancing and BPF-based Tx port selectors)
- **lacp** (implements the 802.3ad Link Aggregation Control Protocol)

In addition, the following link-watchers are available:

- **ethtool** (Libteam lib uses **ethtool** to watch for link state changes). This is the default if no other link-watcher is specified in the configuration file.
- **arp_ping** (The **arp_ping** utility is used to monitor the presence of a far-end hardware address using ARP packets.)
- **nsna_ping** (Neighbor Advertisements and Neighbor Solicitation from the **IPv6** Neighbor Discovery protocol are used to monitor the presence of a neighbor's interface)

There are no restrictions in the code to prevent a particular link-watcher from being used with a particular runner, however when using the **lacp** runner, **ethtool** is the only recommended link-watcher.

5.5. INSTALL THE NETWORK TEAMING DAEMON

The networking teaming daemon, **teamd**, is not installed by default. To install **teamd**, issue the following command as **root**:

```
~]# yum install teamd
```

5.6. CONVERTING A BOND TO A TEAM

It is possible to convert existing bonding configuration files to team configuration files using the **bond2team** tool. It can convert bond configuration files in **ifcfg** format to team configuration files in either **ifcfg** or JSON format. Note that firewall rules, alias interfaces, and anything that might be tied

to the original interface name can break after the renaming because the tool will only change the `ifcfg` file, nothing else.

To see some examples of the command format, issue the following command:

```
~]$ bond2team --examples
```

New files will be created in a directory whose name starts with `/tmp/bond2team.XXXXXX/`, where `XXXXXX` is a random string. After creating the new configuration files, move the old bonding files to a backup folder and then move the new files to the `/etc/sysconfig/network-scripts/` directory.

Example 5.1. Convert a Bond to a Team

To convert a current `bond0` configuration to team `ifcfg`, issue a command as `root`:

```
~]# /usr/bin/bond2team --master bond0
```

Note that this will retain the name `bond0`. To use a new name to save the configuration, use the `--rename` as follows:

```
~]# /usr/bin/bond2team --master bond0 --rename team0
```

add the `--json` option to output JSON format files instead of `ifcfg` files. See the `teamd.conf(5)` man page for examples of JSON format.

Example 5.2. Convert a Bond to a Team and Specify the File Path

To convert a current `bond0` configuration to team `ifcfg`, and to manually specify the path to the `ifcfg` file, issue a command as `root`:

```
~]# /usr/bin/bond2team --master bond0 --configdir /path/to/ifcfg-file
```

add the `--json` option to output JSON format files instead of `ifcfg` files.

Example 5.3. Create a Team Configuration Using Bond2team

It is also possible to create a team configuration by supplying the `bond2team` tool with a list of bonding parameters. For example:

```
~]# /usr/bin/bond2team --bonding_opts "mode=1 miimon=500"
```

Ports can also be supplied on the command line as follows:

```
~]# /usr/bin/bond2team --bonding_opts "mode=1 miimon=500 primary=eth1 \
    primary_reselect=0" --port eth1 --port eth2 --port eth3 --port eth4
```

See the `bond2team(1)` man page for further details. For an explanation of bonding parameters, see [Section 4.5, “Using Channel Bonding”](#)

5.7. SELECTING INTERFACES TO USE AS PORTS FOR A NETWORK TEAM

To view the available interfaces, issue the following command:

```
~]$ ip link show
1: lo: <LOOPBACK,UP,LOWER_UP > mtu 65536 qdisc noqueue state UNKNOWN mode
  DEFAULT
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
2: em1: <BROADCAST,MULTICAST,UP,LOWER_UP > mtu 1500 qdisc pfifo_fast
  state UP mode DEFAULT qlen 1000
    link/ether 52:54:00:6a:02:8a brd ff:ff:ff:ff:ff:ff
3: em2: <BROADCAST,MULTICAST,UP,LOWER_UP > mtu 1500 qdisc pfifo_fast
  state UP mode DEFAULT qlen 1000
    link/ether 52:54:00:9b:6d:2a brd ff:ff:ff:ff:ff:ff
```

From the available interfaces, determine which are suitable for adding to your network team and then proceed to [Section 5.8, “Selecting Network Team Configuration Methods”](#)

5.8. SELECTING NETWORK TEAM CONFIGURATION METHODS

To configure a network team using NetworkManager’s text user interface tool, `nmtui`, proceed to [Section 5.9, “Configure a Network Team Using the Text User Interface, `nmtui`”](#)

To create a network team using the command-line tool, `nmcli`, proceed to [Section 5.10.1, “Configure Network Teaming Using `nmcli`”](#).

To create a network team using the Team daemon, `teamd`, proceed to [Section 5.10.2, “Creating a Network Team Using `teamd`”](#).

To create a network team using configuration files, proceed to [Section 5.10.3, “Creating a Network Team Using `ifcfg` Files”](#).

To configure a network team using a graphical user interface, see [Section 5.13, “Creating a Network Team Using a GUI”](#)

5.9. CONFIGURE A NETWORK TEAM USING THE TEXT USER INTERFACE, NMTUI

The text user interface tool `nmtui` can be used to configure teaming in a terminal window. Issue the following command to start the tool:

```
~]$ nmtui
```

The text user interface appears. Any invalid command prints a usage message.

To navigate, use the arrow keys or press `Tab` to step forwards and press `Shift+Tab` to step back through the options. Press `Enter` to select an option. The `Space` bar toggles the status of a check box.

1. From the starting menu, select `Edit a connection`. Select `Add, the New Connection` screen opens.




Figure 5.1. The NetworkManager Text User Interface Add a Team Connection menu

2. Select Team, the Edit connection screen opens.




Figure 5.2. The NetworkManager Text User Interface Configuring a Team Connection menu

3. To add port interfaces to the team select **Add**, the **New Connection** screen opens. Once the type of Connection has been chosen select the **Create** button to cause the team's **Edit Connection** display to appear.




Figure 5.3. The NetworkManager Text User Interface Configuring a new Team Port Interface Connection menu

4. Enter the desired slave's device name or MAC address in the **Device** section. If required, enter a clone MAC address to be used as the team's MAC address by selecting **Show** to the right of the **Ethernet** label. Select the **OK** button.



NOTE

If the device is specified without a MAC address the **Device** section will be automatically populated once the **Edit Connection** window is reloaded, but only if it successfully finds the device.




Figure 5.4. The NetworkManager Text User Interface Configuring a Team's Port Interface Connection menu

5. The name of the teamed slave appears in the **Slaves** section. Repeat the above steps to add further slave connections.
6. If custom port settings are to be applied select the **Edit** button under the **JSON configuration** section. This will launch a **vim** console where changes may be applied. Once finished write the changes from **vim** and then confirm that the displayed JSON string under **JSON configuration** matches what is intended.
7. Review and confirm the settings before selecting the **OK** button.



Figure 5.5. The NetworkManager Text User Interface Configuring a Team Connection menu

See [Section 5.12, “Configure teamd Runners”](#) for examples of JSON strings. Note that only the relevant sections from the example strings should be used for a team or port configuration using **nmcli**. Do not specify the “Device” as part of the JSON string. For example, only the JSON string after “device” but before “port” should be used in the Team JSON configuration field. All JSON strings relevant to a port must only be added in the port configuration field.

See [Section 1.5, “Network Configuration Using a Text User Interface \(nmcli\)”](#) for information on installing **nmcli**.

5.10. CONFIGURE A NETWORK TEAM USING THE COMMAND LINE

5.10.1. Configure Network Teaming Using nmcli

To view the connections available on the system, run the following command:

```
~]$ nmcli connection show
NAME    UUID                                  TYPE      DEVICE
eth1    0e8185a1-f0fd-4802-99fb-bedbb31c689b 802-3-ethernet --
eth0    dfe1f57b-419d-4d1c-aaf5-245deab82487 802-3-ethernet --
```

To view the devices available on the system, run the following command:

```
~]$ nmcli device status
DEVICE      TYPE      STATE      CONNECTION
virbr0      bridge    connected  virbr0
ens3        ethernet  connected  ens3
```

To create a new team interface, with name *ServerA*, run a command as follows:

```
~]$ nmcli connection add type team ifname ServerA
Connection 'team-ServerA' (b954c62f-5fdd-4339-97b0-40efac734c50)
successfully added.
```

NetworkManager will set its internal parameter `connection.autoconnect` to `yes` and as no IP address was given `ipv4.method` will be set to `auto`. **NetworkManager** will also write a configuration file to `/etc/sysconfig/network-scripts/ifcfg-team-ServerA` where the corresponding `ONBOOT` will be set to `yes` and `BOOTPROTO` will be set to `dhcp`.

Note that manual changes to the `ifcfg` file will not be noticed by **NetworkManager** until the interface is next brought up. See [Section 1.9, “Network Configuration Using sysconfig Files”](#) for more information on using configuration files.

To view the other values assigned, issue a command as follows:

```
~]$ nmcli con show team-ServerA
connection.id:                team-ServerA
connection.uuid:              b954c62f-5fdd-4339-97b0-
40efac734c50
connection.interface-name:    ServerA
connection.type:              team
connection.autoconnect:       yes
...
ipv4.method:                  auto
[output truncated]
```

As no JSON configuration file was specified the default values apply. See the `teamd.conf(5)` man page for more information on the team JSON parameters and their default values. Notice that the name was derived from the interface name by prepending the type. Alternatively, specify a name with the `con-name` option as follows:

```
~]$ nmcli connection add type team con-name Team0 ifname ServerB
Connection 'Team0' (5f7160a1-09f6-4204-8ff0-6d96a91218a7) successfully
added.
```

To view the team interfaces just configured, issue a command as follows:

```
~]$ nmcli con show
NAME      UUID                                  TYPE
DEVICE
team-ServerA  b954c62f-5fdd-4339-97b0-40efac734c50  team
ServerA
eth1        0e8185a1-f0fd-4802-99fb-bedbb31c689b  802-3-ethernet
--
eth0        dfe1f57b-419d-4d1c-aaf5-245deab82487  802-3-ethernet
```

```
--  
Team0          5f7160a1-09f6-4204-8ff0-6d96a91218a7  team  
ServerB
```

To change the name assigned to a team, issue a command in the following format:

```
nmcli con mod old-team-name connection.id new-team-name
```

To load a team configuration file for a team that already exists, issue a command in the following format:

```
nmcli connection modify team-name team.config JSON-config
```

You can specify the team configuration either as a JSON string or provide a file name containing the configuration. The file name can include the path. In both cases, what is stored in the *team.config* property is the JSON string. In the case of a JSON string, use single quotes around the string and paste the entire string to the command line.

To review the *team.config* property, enter a command in the following format:

```
nmcli con show team-name | grep team.config
```

To add an interface *eth0* to *Team0*, with the name *Team0-port1*, issue a command as follows:

```
~]$ nmcli con add type ethernet con-name Team0-port1 ifname eth0 master  
Team0  
Connection 'Team0-port1' (ccd87704-c866-459e-8fe7-01b06cf1cffc)  
successfully added.
```

Similarly, to add another interface, *eth1*, with the name *Team0-port2*, issue a command as follows:

```
~]$ nmcli con add type team-slave con-name Team0-port2 ifname eth1 master  
Team0  
Connection 'Team0-port2' (a89ccff8-8202-411e-8ca6-2953b7db52dd)  
successfully added.
```

At time of writing, *nmcli* only supports Ethernet ports.

In order to open a team, the ports must be brought up first as follows:

```
~]$ nmcli connection up Team0-port1  
Connection successfully activated (D-Bus active path:  
/org/freedesktop/NetworkManager/ActiveConnection/2)
```

```
~]$ nmcli connection up Team0-port2  
Connection successfully activated (D-Bus active path:  
/org/freedesktop/NetworkManager/ActiveConnection/3)
```

You can verify that the team interface was brought up by the activation of the ports, as follows:

```
~]$ ip link  
3: Team0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state  
UP mode DEFAULT
```

```
link/ether 52:54:00:76:6f:f0 brd ff:ff:ff:ff:ff:f
```

Alternatively, issue a command to open the team as follows:

```
~]$ nmcli connection up Team0
Connection successfully activated (D-Bus active path:
/org/freedesktop/NetworkManager/ActiveConnection/4)
```

See [Section 2.1.5, “Using the NetworkManager Command Line Tool, nmcli”](#) for an introduction to nmcli

5.10.2. Creating a Network Team Using teamd



NOTE

Configurations created using teamd are not persistent, and as such it may be necessary to create a team using the steps defined in [Section 5.10.1, “Configure Network Teaming Using nmcli”](#) or [Section 5.10.3, “Creating a Network Team Using ifcfg Files”](#).

To create a network team, a JSON format configuration file is required for the virtual interface that will serve as the interface to the team of ports or links. A quick way is to copy the example configuration files and then edit them using an editor running with root privileges. To list the available example configurations, enter the following command:

```
~]$ ls /usr/share/doc/teamd-*/example_configs/
activebackup_arp_ping_1.conf  activebackup_multi_lw_1.conf
loadbalance_2.conf
activebackup_arp_ping_2.conf  activebackup_nsna_ping_1.conf
loadbalance_3.conf
activebackup_ethtool_1.conf  broadcast.conf                random.conf
activebackup_ethtool_2.conf  lacp_1.conf
roundrobin_2.conf
activebackup_ethtool_3.conf  loadbalance_1.conf
roundrobin.conf
```

To view one of the included files, such as `activebackup_ethtool_1.conf`, enter the following command:

```
~]$ cat /usr/share/doc/teamd-*/example_configs/activebackup_ethtool_1.conf
{
  "device": "team0",
  "runner": {"name": "activebackup"},
  "link_watch": {"name": "ethtool"},
  "ports": {
    "eth1": {
      "prio": -10,
      "sticky": true
    },
    "eth2": {
      "prio": 100
    }
  }
}
```

Create a working configurations directory to store **teamd** configuration files. For example, as normal user, enter a command with the following format:

```
~]$ mkdir ~/teamd_working_configs
```

Copy the file you have chosen to your working directory and edit it as necessary. As an example, you could use a command with the following format:

```
~]$ cp /usr/share/doc/teamd-*/example_configs/activebackup_ethtool_1.conf  
  \ ~/teamd_working_configs/activebackup_ethtool_1.conf
```

To edit the file to suit your environment, for example to change the interfaces to be used as ports for the network team, open the file for editing as follows:

```
~]$ vi ~/teamd_working_configs/activebackup_ethtool_1.conf
```

Make any necessary changes and save the file. See the **vi(1)** man page for help on using the **vi** editor or use your preferred editor.

Note that it is essential that the interfaces to be used as ports within the team must not be active, that is to say, they must be “down”, when adding them into a team device. To check their status, issue the following command:

```
~]$ ip link show  
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN mode  
  DEFAULT  
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00  
2: em1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state  
  UP mode DEFAULT qlen 1000  
    link/ether 52:54:00:d5:f7:d4 brd ff:ff:ff:ff:ff:ff  
3: em2: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state  
  UP mode DEFAULT qlen 1000  
    link/ether 52:54:00:d8:04:70 brd ff:ff:ff:ff:ff:ff
```

In this example we see that both the interfaces we plan to use are “UP”.

To take down an interface, issue a command as **root** in the following format:

```
~]# ip link set down em1
```

Repeat for each interface as necessary.

To create a team interface based on the configuration file, as **root** user, change to the working configurations directory (*teamd_working_configs* in this example):

```
~]# cd /home/user/teamd_working_configs
```

Then issue a command in the following format:

```
~]# teamd -g -f activebackup_ethtool_1.conf -d  
Using team device "team0".  
Using PID file "/var/run/teamd/team0.pid"  
Using config file  
"/home/user/teamd_working_configs/activebackup_ethtool_1.conf"
```


The **-g** option is for debug messages, **-f** option is to specify the configuration file to load, and the **-d** option is to make the process run as a daemon after startup. See the **teamd(8)** man page for other options.

To check the status of the team, issue the following command as **root**:

```
~]# teamdctl team0 state
setup:
  runner: activebackup
ports:
  em1
    link watches:
      link summary: up
      instance[link_watch_0]:
        name: ethtool
        link: up
  em2
    link watches:
      link summary: up
      instance[link_watch_0]:
        name: ethtool
        link: up
runner:
  active port: em1
```

To apply an address to the network team interface, **team0**, issue a command as **root** in the following format:

```
~]# ip addr add 192.168.23.2/24 dev team0
```

To check the IP address of a team interface, issue a command as follows:

```
~]$ ip addr show team0
4: team0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP
    link/ether 16:38:57:60:20:6f brd ff:ff:ff:ff:ff:ff
    inet 192.168.23.2/24 scope global team0
        valid_lft forever preferred_lft forever
    inet6 2620:52:0:221d:1438:57ff:fe60:206f/64 scope global dynamic
        valid_lft 2591880sec preferred_lft 604680sec
    inet6 fe80::1438:57ff:fe60:206f/64 scope link
        valid_lft forever preferred_lft forever
```

To activate the team interface, or to bring it “up”, issue a command as **root** in the following format:

```
~]# ip link set dev team0 up
```

To temporarily deactivate the team interface, or to take it “down”, issue a command as **root** in the following format:

```
~]# ip link set dev team0 down
```

To terminate, or kill, an instance of the team daemon, as **root** user, issue a command in the following format:

```
~]# teamd -t team0 -k
```

The `-k` option is to specify that the instance of the daemon associated with the device `team0` is to be killed. See the `teamd(8)` man page for other options.

For help on command-line options for `teamd`, issue the following command:

```
~]$ teamd -h
```

In addition, see the `teamd(8)` man page.

5.10.3. Creating a Network Team Using `ifcfg` Files

To create a networking team using `ifcfg` files, create a file in the `/etc/sysconfig/network-scripts/` directory as follows:

```
DEVICE=team0
DEVICETYPE=Team
ONBOOT=yes
BOOTPROTO=none
IPADDR=192.168.11.1
PREFIX=24
TEAM_CONFIG='{"runner": {"name": "activebackup"}, "link_watch": {"name":
"ethtool"}}'
```

This creates the interface to the team, in other words, this is the master.

To create a port to be a member of `team0`, create one or more files in the `/etc/sysconfig/network-scripts/` directory as follows:

```
DEVICE=eth1
HWADDR=D4:85:64:01:46:9E
DEVICETYPE=TeamPort
ONBOOT=yes
TEAM_MASTER=team0
TEAM_PORT_CONFIG='{"prio": 100}'
```

Add additional port interfaces similar to the above as required, changing the `DEVICE` and `HWADDR` field to match the ports (the network devices) being added. If port priority is not specified by `prio` it defaults to `0`; it accepts negative and positive values in the range `-32,767` to `+32,767`.

Specifying the hardware or MAC address using the `HWADDR` directive will influence the device naming procedure. This is explained in [Chapter 8, Consistent Network Device Naming](#)

To open the network team, issue the following command as `root`:

```
~]# ifup team0
```

To view the network team, issue the following command:

```
~]$ ip link show
```

5.10.4. Add a Port to a Network Team Using `iputils`

To add a port `em1` to a network team `team0`, using the `ip` utility, issue the following commands as **root**:

```
~]# ip link set dev em1 down
~]# ip link set dev em1 master team0
```

Add additional ports as required. Team driver will bring ports up automatically.

5.10.5. Listing the ports of a Team Using `teamnl`

To view or list the ports in a network team, using the `teamnl` utility, issue the following command as **root**:

```
~]# teamnl team0 ports
em2: up 100 full duplex
em1: up 100 full duplex
```

5.10.6. Configuring Options of a Team Using `teamnl`

To view or list all currently available options, using the `teamnl` utility, issue the following command as **root**:

```
~]# teamnl team0 options
```

To configure a team to use active backup mode, issue the following command as **root**:

```
~]# teamnl team0 setoption mode activebackup
```

5.10.7. Add an Address to a Network Team Using `iputils`

To add an address to a team `team0`, using the `ip` utility, issue the following command as **root**:

```
~]# ip addr add 192.168.252.2/24 dev team0
```

5.10.8. open an Interface to a Network Team Using `iputils`

To activate or “open” an interface to a network team, `team0`, using the `ip` utility, issue the following command as **root**:

```
~]# ip link set team0 up
```

5.10.9. Viewing the Active Port Options of a Team Using `teamnl`

To view or list the `activeport` option in a network team, using the `teamnl` utility, issue the following command as **root**:

```
~]# teamnl team0 getoption activeport
0
```

5.10.10. Setting the Active Port Options of a Team Using `teamnl`

To set the **activeport** option in a network team, using the **teamnl** utility, issue the following command as **root**:

```
~]# teamnl team0 setoption activeport 5
```

To check the change in team port options, issue the following command as **root**:

```
~]# teamnl team0 getoption activeport  
5
```

5.11. CONTROLLING TEAMD WITH TEAMDCTL

In order to query a running instance of **teamd** for statistics or configuration information, or to make changes, the control tool **teamdctl** is used.

To view the current team state of a team **team0**, enter the following command as **root**:

```
~]# teamdctl team0 state view
```

For a more verbose output:

```
~]# teamdctl team0 state view -v
```

For a complete state dump in JSON format (useful for machine processing) of **team0**, use the following command:

```
~]# teamdctl team0 state dump
```

For a configuration dump in JSON format of **team0**, use the following command:

```
~]# teamdctl team0 config dump
```

To view the configuration of a port **em1**, that is part of a team **team0**, enter the following command:

```
~]# teamdctl team0 port config dump em1
```

5.11.1. Add a Port to a Network Team

To add a port **em1** to a network team **team0**, issue the following command as **root**:

```
~]# teamdctl team0 port add em1
```



IMPORTANT

If using **teamdctl** directly to enslave a port, the slave port must be set to *down*. Otherwise the **teamdctl team0 port add em1** command will fail.

5.11.2. Remove a Port From a Network Team

To remove an interface **em1** from a network team **team0**, issue the following command as **root**:

-

```
~]# teamdctl team0 port remove em1
```

5.11.3. Apply a Configuration to a Port in a Network Team

To apply a JSON format configuration to a port `em1` in a network team `team0`, issue a command as `root` in the following format:

```
~]# teamdctl team0 port config update em1 JSON-config-string
```

Where *JSON-config-string* is the configuration as a string of text in JSON format. This will update the configuration of the port using the JSON format string supplied. An example of a valid JSON string for configuring a port would be the following:

```
{
  "prio": -10,
  "sticky": true
}
```

Use single quotes around the JSON configuration string and omit the line breaks.

Note that the old configuration will be overwritten and that any options omitted will be reset to the default values. See the `teamdctl(8)` man page for more team daemon control tool command examples.

5.11.4. View the Configuration of a Port in a Network Team

To copy the configuration of a port `em1` in a network team `team0`, issue the following command as `root`:

```
~]# teamdctl team0 port config dump em1
```

This will dump the JSON format configuration of the port to standard output.

5.12. CONFIGURE TEAMD RUNNERS

Runners are units of code which are compiled into the Team daemon when an instance of the daemon is created. For an introduction to the `teamd` runners, see [Section 5.4, “Understanding the Network Teaming Daemon and the “Runners”](#)”.

5.12.1. Configure the broadcast Runner

To configure the broadcast runner, using an editor as `root`, add the following to the team JSON format configuration file:

```
{
  "device": "team0",
  "runner": {"name": "broadcast"},
  "ports": {"em1": {}, "em2": {}}
}
```

Please see the `teamd.conf(5)` man page for more information.

5.12.2. Configure the random Runner

The random runner behaves similarly to the round-robin runner.

To configure the random runner, using an editor as `root`, add the following to the team JSON format configuration file:

```
{
  "device": "team0",
  "runner": {"name": "random"},
  "ports": {"em1": {}, "em2": {}}
}
```

Please see the `teamd.conf(5)` man page for more information.

5.12.3. Configure the Round-robin Runner

To configure the round-robin runner, using an editor as `root`, add the following to the team JSON format configuration file:

```
{
  "device": "team0",
  "runner": {"name": "roundrobin"},
  "ports": {"em1": {}, "em2": {}}
}
```

A very basic configuration for round-robin.

Please see the `teamd.conf(5)` man page for more information.

5.12.4. Configure the activebackup Runner

The active backup runner can use all of the link-watchers to determine the status of links in a team. Any one of the following examples can be added to the team JSON format configuration file:

```
{
  "device": "team0",
  "runner": {
    "name": "activebackup"
  },
  "link_watch": {
    "name": "ethtool"
  },
  "ports": {
    "em1": {
      "prio": -10,
      "sticky": true
    },
    "em2": {
      "prio": 100
    }
  }
}
```

This example configuration uses the active-backup runner with **ethtool** as the link watcher. Port `em2` has higher priority. The sticky flag ensures that if `em1` becomes active, it stays active as long as the link remains up.

```
{
  "device": "team0",
  "runner": {
    "name": "activebackup"
  },
  "link_watch": {
    "name": "ethtool"
  },
  "ports": {
    "em1": {
      "prio": -10,
      "sticky": true,
      "queue_id": 4
    },
    "em2": {
      "prio": 100
    }
  }
}
```

This example configuration adds a queue ID of 4. It uses active-backup runner with **ethtool** as the link watcher. Port `em2` has higher priority. But the sticky flag ensures that if `em1` becomes active, it will stay active as long as the link remains up.

To configure the activebackup runner using **ethtool** as the link watcher and applying a delay, using an editor as **root**, add the following to the team JSON format configuration file:

```
{
  "device": "team0",
  "runner": {
    "name": "activebackup"
  },
  "link_watch": {
    "name": "ethtool",
    "delay_up": 2500,
    "delay_down": 1000
  },
  "ports": {
    "em1": {
      "prio": -10,
      "sticky": true
    },
    "em2": {
      "prio": 100
    }
  }
}
```

This example configuration uses the active-backup runner with **ethtool** as the link watcher. Port `em2` has higher priority. But the sticky flag ensures that if `em1` becomes active, it stays active while the link remains up. Link changes are not propagated to the runner immediately, but delays are applied.

Please see the `teamd.conf(5)` man page for more information.

5.12.5. Configure the loadbalance Runner

This runner can be used for two types of load balancing, active and passive. In active mode, constant re-balancing of traffic is done by using statistics of recent traffic to share out traffic as evenly as possible. In static mode, streams of traffic are distributed randomly across the available links. This has a speed advantage due to lower processing overhead. In high volume traffic applications this is often preferred as traffic usually consists of multiple stream which will be distributed randomly between the available links, in this way load sharing is accomplished without intervention by `teamd`.

To configure the loadbalance runner for passive transmit (Tx) load balancing, using an editor as `root`, add the following to the team JSON format configuration file:

```
{
  "device": "team0",
  "runner": {
    "name": "loadbalance",
    "tx_hash": ["eth", "ipv4", "ipv6"]
  },
  "ports": {"em1": {}, "em2": {}}
}
```

Configuration for hash-based passive transmit (Tx) load balancing.

To configure the loadbalance runner for active transmit (Tx) load balancing, using an editor as `root`, add the following to the team JSON format configuration file:

```
{
  "device": "team0",
  "runner": {
    "name": "loadbalance",
    "tx_hash": ["eth", "ipv4", "ipv6"],
    "tx_balancer": {
      "name": "basic"
    }
  },
  "ports": {"em1": {}, "em2": {}}
}
```

Configuration for active transmit (Tx) load balancing using basic load balancer.

Please see the `teamd.conf(5)` man page for more information.

5.12.6. Configure the LACP (802.3ad) Runner

To configure the LACP runner using `ethtool` as a link watcher, using an editor as `root`, add the following to the team JSON format configuration file:

```
{
  "device": "team0",
  "runner": {
    "name": "lacp",
    "active": true,
    "fast_rate": true,
```



```

        "tx_hash": ["eth", "ipv4", "ipv6"]
    },
    "link_watch": {"name": "ethtool"},
    "ports": {"em1": {}, "em2": {}}
}

```

Configuration for connection to a *link aggregation control protocol* (LACP) capable counterpart. The LACP runner should use **ethtool** to monitor the status of a link. Note that only **ethtool** can be used for link monitoring because, for example in the case of **arp_ping**, the link would never come up. The reason is that the link has to be established first and only after that can packets, ARP included, go through. Using **ethtool** prevents this because it monitors each link layer individually.

Active load balancing is possible with this runner in the same way as it is done for the loadbalance runner. To enable active transmit (Tx) load balancing, add the following section:

```

"tx_balancer": {
    "name": "basic"
}

```

Please see the `teamd.conf(5)` man page for more information.

5.12.7. Configure Monitoring of the Link State

The following methods of link state monitoring are available. To implement one of the methods, add the JSON format string to the team JSON format configuration file using an editor running with **root** privileges.

5.12.7.1. Configure Ethtool for link-state Monitoring

To add or edit an existing delay, in milliseconds, between the link coming up and the runner being notified about it, add or edit a section as follows:

```

"link_watch": {
    "name": "ethtool",
    "delay_up": 2500
}

```

To add or edit an existing delay, in milliseconds, between the link going down and the runner being notified about it, add or edit a section as follows:

```

"link_watch": {
    "name": "ethtool",
    "delay_down": 1000
}

```

5.12.7.2. Configure ARP Ping for Link-state Monitoring

The team daemon **teamd** sends an ARP REQUEST to an address at the remote end of the link in order to determine if the link is up. The method used is the same as the **arping** utility but it does not use that utility.

Prepare a file containing the new configuration in JSON format similar to the following example:

```

{

```

```

    "device": "team0",
    "runner": {"name": "activebackup"},
    "link_watch": {
        "name": "arp_ping",
        "interval": 100,
        "missed_max": 30,
        "source_host": "192.168.23.2",
        "target_host": "192.168.23.1"
    },
    "ports": {
        "em1": {
            "prio": -10,
            "sticky": true
        },
        "em2": {
            "prio": 100
        }
    }
}

```

This configuration uses **arp_ping** as the link watcher. The **missed_max** option is a limit value of the maximum allowed number of missed replies (ARP replies for example). It should be chosen in conjunction with the **interval** option in order to determine the total time before a link is reported as down.

To load a new configuration for a team port **em2**, from a file containing a JSON configuration, issue the following command as **root**:

```
~]# teamdctl port config update em2 JSON-config-file
```

Note that the old configuration will be overwritten and that any options omitted will be reset to the default values. See the **teamdctl(8)** man page for more team daemon control tool command examples.

5.12.7.3. Configure IPv6 NA/NS for Link-state Monitoring

```

{
    "device": "team0",
    "runner": {"name": "activebackup"},
    "link_watch": {
        "name": "nsna_ping",
        "interval": 200,
        "missed_max": 15,
        "target_host": "fe80::210:18ff:feaa:bbcc"
    },
    "ports": {
        "em1": {
            "prio": -10,
            "sticky": true
        },
        "em2": {
            "prio": 100
        }
    }
}

```

To configure the interval between sending NS/NA packets, add or edit a section as follows:

```
"link_watch": {
    "name": "nsna_ping",
    "interval": 200
}
```

Value is positive number in milliseconds. It should be chosen in conjunction with the `missed_max` option in order to determine the total time before a link is reported as down.

To configure the maximum number of missed NS/NA reply packets to allow before reporting the link as down, add or edit a section as follows:

```
"link_watch": {
    "name": "nsna_ping",
    "missed_max": 15
}
```

Maximum number of missed NS/NA reply packets. If this number is exceeded, the link is reported as down. The `missed_max` option is a limit value of the maximum allowed number of missed replies (ARP replies for example). It should be chosen in conjunction with the `interval` option in order to determine the total time before a link is reported as down.

To configure the host name that is resolved to the **IPv6** address target address for the NS/NA packets, add or edit a section as follows:

```
"link_watch": {
    "name": "nsna_ping",
    "target_host": "MyStorage"
}
```

The “`target_host`” option contains the host name to be converted to an **IPv6** address which will be used as the target address for the NS/NA packets. An **IPv6** address can be used in place of a host name.

Please see the `teamd.conf(5)` man page for more information.

5.12.8. Configure Port Selection Override

The physical port which transmits a frame is normally selected by the kernel part of the team driver, and is not relevant to the user or system administrator. The output port is selected using the policies of the selected team mode (`teamd` runner). On occasion however, it is helpful to direct certain classes of outgoing traffic to certain physical interfaces to implement slightly more complex policies. By default the team driver is multiqueue aware and 16 queues are created when the driver initializes. If more or less queues are required, the Netlink attribute `tx_queues` can be used to change this value during the team driver instance creation.

The queue ID for a port can be set by the port configuration option `queue_id` as follows:

```
{
    "queue_id": 3
}
```

These queue ID's can be used in conjunction with the `tc` utility to configure a multiqueue queue

discipline and filters to bias certain traffic to be transmitted on certain port devices. For example, if using the above configuration and wanting to force all traffic bound to **192.168.1.100** to use **eth1** in the team as its output device, issue commands as **root** in the following format:

```
~]# tc qdisc add dev team0 handle 1 root multiq
~]# tc filter add dev team0 protocol ip parent 1: prio 1 u32 match ip dst \
    192.168.1.100 action skbedit queue_mapping 3
```

This mechanism of overriding runner selection logic in order to bind traffic to a specific port can be used with all runners.

5.12.9. Configure BPF-based Tx Port Selectors

The loadbalance and LACP runners use hashes of packets to sort network traffic flow. The hash computation mechanism is based on the *Berkeley Packet Filter* (BPF) code. The BPF code is used to generate a hash rather than make a policy decision for outgoing packets. The hash length is 8 bits giving 256 variants. This means many different *socket buffers* (SKB) can have the same hash and therefore pass traffic over the same link. The use of a short hash is a quick way to sort traffic into different streams for the purposes of load balancing across multiple links. In static mode, the hash is only used to decide out of which port the traffic should be sent. In active mode, the runner will continually reassign hashes to different ports in an attempt to reach a perfect balance.

The following fragment types or strings can be used for packet Tx hash computation:

- **eth** – Uses source and destination MAC addresses.
- **vlan** – Uses VLAN ID.
- **ipv4** – Uses source and destination **IPv4** addresses.
- **ipv6** – Uses source and destination **IPv6** addresses.
- **ip** – Uses source and destination **IPv4** and **IPv6** addresses.
- **l3** – Uses source and destination **IPv4** and **IPv6** addresses.
- **tcp** – Uses source and destination **TCP** ports.
- **udp** – Uses source and destination **UDP** ports.
- **sctp** – Uses source and destination **SCTP** ports.
- **l4** – Uses source and destination **TCP** and **UDP** and **SCTP** ports.

These strings can be used by adding a line in the following format to the load balance runner:

```
"tx_hash": ["eth", "ipv4", "ipv6"]
```

See [Section 5.12.5, “Configure the loadbalance Runner”](#) for an example.

5.13. CREATING A NETWORK TEAM USING A GUI

5.13.1. Establishing a Team Connection

You can use the GNOME **control-center** utility to direct **NetworkManager** to create a team from two or more Wired or InfiniBand connections. It is not necessary to create the connections to be teamed first. They can be configured as part of the process to configure the team. You must have the MAC addresses of the interfaces available in order to complete the configuration process.

Procedure 5.1. Adding a New Team Connection

Follow the below steps to add a new team connection.

1. Press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears. This step is fully covered in [Section 2.3, “Using NetworkManager with the GNOME Graphical User Interface”](#).
2. Select **Team**. The **Editing Team Connection 1** window appears.

The screenshot shows the 'Editing Team connection 1' window. At the top, the title is 'Editing Team connection 1'. Below the title bar, there's a text field for 'Connection name:' containing 'Team connection 1'. Underneath is a tabbed interface with four tabs: 'General', 'Team' (which is selected and underlined), 'IPv4 Settings', and 'IPv6 Settings'. In the 'Team' tab, there's a text field for 'Interface name:' containing 'team0'. Below that is an 'MTU:' section with a dropdown menu showing 'automatic', a minus button, a plus button, and the text 'bytes'. Further down is a section titled 'Teamed connections:' which contains an empty rectangular box. To the right of this box are three buttons: 'Add', 'Edit', and 'Delete'. At the bottom right of the main content area is a button labeled 'Advanced...' with a gear icon. At the very bottom of the window are two buttons: 'Cancel' and 'Save'.

Figure 5.6. The NetworkManager Graphical User Interface Add a menu

3. On the **Team** tab, click **Add** and select the type of interface you want to use with the team

connection. Click the **Create** button. Note that the dialog to select the port type only comes up when you create the first port; after that, it will automatically use that same type for all further ports.

4. The **Editing team0 slave 1** window appears.

The screenshot shows the 'Editing team1 slave 1' dialog box. At the top, the title is 'Editing team1 slave 1'. Below the title bar, there's a 'Connection name:' label followed by a text box containing 'team1 slave 1'. Below this is a tabbed interface with five tabs: 'General', 'Ethernet' (which is selected and highlighted with a blue underline), '802.1X Security', 'DCB', and 'Team Port'. The 'Ethernet' tab contains several settings: 'Device:' with a dropdown menu, 'Cloned MAC address:' with a text box, 'MTU:' with a text box containing 'automatic' and buttons for '-' and '+', and 'bytes' to the right. Below these is the 'Wake on LAN:' section with a grid of checkboxes: 'Default' (checked), 'Phy', 'Unicast', 'Multicast', 'Ignore', 'Broadcast', 'Arp', and 'Magic'. At the bottom of the tab is a 'Wake on LAN password:' text box. At the very bottom of the dialog are 'Cancel' and 'Save' buttons.

Figure 5.7. The NetworkManager Graphical User Interface Add a Slave Connection

5. If custom port settings are to be applied, click on the **Team Port** tab and enter a JSON configuration string or import it from a file.
6. Click the **Save** button.
7. The name of the teamed port appears in the **Teamed connections** window. Click the **Add** button to add further port connections.
8. Review and confirm the settings and then click the **Save** button.
9. Edit the team-specific settings by referring to [Section 5.13.1.1, “Configuring the Team Tab”](#) below.

Procedure 5.2. Editing an Existing Team Connection

Follow the below steps to edit an existing team connection.

1. Press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears.
2. Select the connection you want to edit and click the **Options** button.

3. Select the **General** tab.
4. If you are using the nm-connection-editor, five settings in the **Editing** dialog are common to the most connection types. See the **General** tab:
 - **Connection name** – Enter a descriptive name for your network connection. This name will be used to list this connection in the menu of the **Network** window.
 - **Automatically connect to this network when it is available** – Select this box if you want **NetworkManager** to auto-connect to this connection when it is available. See [Section 2.3.3, “Connecting to a Network Automatically”](#) for more information.
 - **All users may connect to this network** – Select this box to create a connection available to all users on the system. Changing this setting may require root privileges. See [Section 2.3.5, “System-wide and Private Connection Profiles”](#) for details.
 - **Automatically connect to VPN when using this connection** – Select this box if you want **NetworkManager** to auto-connect to a VPN connection when it is available. Select the VPN from the drop-down menu.
 - **Firewall Zone** – Select the firewall zone from the drop-down menu. See the [Red Hat Enterprise Linux 7 Security Guide](#) for more information on firewall zones.
5. Edit the team-specific settings by referring to [Section 5.13.1.1, “Configuring the Team Tab”](#) below.

Saving Your New (or Modified) Connection and Making Further Configurations

Once you have finished editing your team connection, click the **Save** button to save your customized configuration. If the profile was in use while being edited, power cycle the connection to make **NetworkManager** apply the changes. If the profile is OFF, set it to ON or select it in the network connection icon's menu. See [Section 2.3.1, “Connecting to a Network Using a GUI”](#) for information on using your new or altered connection.

You can further configure an existing connection by selecting it in the **Network** window and clicking **Options** to return to the **Editing** dialog.

Then, to configure:

- **IPv4** settings for the connection, click the **IPv4 Settings** tab and proceed to [Section 2.7.6, “Configuring IPv4 Settings”](#); or,
- **IPv6** settings for the connection, click the **IPv6 Settings** tab and proceed to [Section 2.7.7, “Configuring IPv6 Settings”](#).

Once saved the Team will appear in the Network settings tool.




Figure 5.8. The NetworkManager Graphical User Interface with Team

5.13.1.1. Configuring the Team Tab

If you have already added a new team connection you can enter a custom JSON configuration string in the text box or import a configuration file. Click **Save** to apply the JSON configuration to the team interface.

For examples of JSON strings, see [Section 5.12, “Configure teamd Runners”](#)

See [Procedure 5.1, “Adding a New Team Connection”](#) for instructions on how to add a new team.

5.14. ADDITIONAL RESOURCES

Installed Documentation

- `teamd(8)` man page – Describes the `teamd` service.
- `teamdctl(8)` man page – Describes the `teamd` control tool.
- `teamd.conf(5)` man page – Describes the `teamd` configuration file.
- `teamnl(8)` man page – Describes the `teamd` Netlink library.
- `bond2team(1)` man page – Describes a tool to convert bonding options to team.

Online Documentation

http://www.w3schools.com/js/js_json_syntax.asp

An explanation of JSON syntax.

CHAPTER 6. CONFIGURE NETWORK BRIDGING

A network bridge is a link-layer device which forwards traffic between networks based on MAC addresses. It makes forwarding decisions based on a table of MAC addresses which it builds by listening to network traffic and thereby learning what hosts are connected to each network. A software bridge can be used within a Linux host in order to emulate a hardware bridge, for example in virtualization applications for sharing a NIC with one or more virtual NICs.

Note that a bridge cannot be established over Wi-Fi networks operating in *Ad-Hoc* or *Infrastructure* modes. This is due to the IEEE 802.11 standard that specifies the use of 3-address frames in Wi-Fi for the efficient use of airtime.

6.1. CONFIGURE BRIDGING USING THE TEXT USER INTERFACE, NMTUI

The text user interface tool `nmtui` can be used to configure bridging in a terminal window. Issue the following command to start the tool:

```
~]$ nmtui
```

The text user interface appears. Any invalid command prints a usage message.

To navigate, use the arrow keys or press **Tab** to step forwards and press **Shift+Tab** to step back through the options. Press **Enter** to select an option. The **Space** bar toggles the status of a check box.

1. From the starting menu, select **Edit a connection**. Select **Add**, the **New Connection** screen opens.




Figure 6.1. The NetworkManager Text User Interface Add a Bridge Connection menu

2. Select **Bridge**, the **Edit connection** screen opens.

- To add slave interfaces to the bridge select **Add**, the **New Connection** screen opens. Once the type of Connection has been chosen select the **Create** button to cause the bridge's **Edit Connection** display to appear.




Figure 6.2. The NetworkManager Text User Interface Adding a new Bridge Slave Connection menu

- Enter the desired slave's device name or MAC address in the **Device** section. If required, enter a clone MAC address to be used as the bridge's MAC address by selecting **Show** to the right of the **Ethernet** label. Select the **OK** button.



NOTE

If the device is specified without a MAC address the **Device** section will be automatically populated once the **Edit Connection** window is reloaded, but only if it successfully finds the device.

Edit connection

Profile name Ethernet connection 1
 Device ens3

ETHERNET
 Cloned MAC address
 MTU (default)

<Hide>

BRIDGE PORT
 Priority 32
 Path cost 100
☐ Hairpin mode

<Hide>

☒ Automatically connect
☒ Available to all users

<Cancel> OK

Figure 6.3. The NetworkManager Text User Interface Configuring a Bridge Slave Connection menu

5. The name of the bridge slave appears in the **Slaves** section. Repeat the above steps to add further slave connections.
6. Review and confirm the settings before selecting the **OK** button.




Figure 6.4. The NetworkManager Text User Interface Configuring a Bridge menu

See [Section 6.4.1.1, “Configuring the Bridge Tab”](#) for definitions of the bridge terms.

See [Section 1.5, “Network Configuration Using a Text User Interface \(nmcli\)”](#) for information on installing **nmcli**.

6.2. USING THE NETWORKMANAGER COMMAND LINE TOOL, NMCLI

To create a bridge, named **bridge-br0**, issue a command as follows as **root**:

```
~]# nmcli con add type bridge ifname br0
Connection 'bridge-br0' (6ad5bba6-98a0-4f20-839d-c997ba7668ad)
successfully added.
```

If no interface name is specified, the name will default to **bridge**, **bridge-1**, **bridge-2**, and so on.

To view the connections, issue the following command:

```
~]$ nmcli con show
NAME          UUID                                  TYPE
DEVICE
bridge-br0    79cf6a3e-0310-4a78-b759-bda1cc3eef8d bridge      br0
eth0          4d5c449a-a6c5-451c-8206-3c9a4ec88bca 802-3-ethernet eth0
```

Spanning tree protocol (STP) is enabled by default. The values used are from the IEEE 802.1D-1998 standard. To disable **STP** for this bridge, issue a command as follows as **root**:

```
~]# nmcli con modify bridge-br0 bridge.stp no
```

To re-enable **802.1D STP** for this bridge, issue a command as follows as **root**:

```
~]# nmcli con modify bridge-br0 bridge.stp yes
```

The default bridge priority for **802.1D STP** is **32768**. The lower number is preferred in root bridge selection. For example, a bridge with priority of **28672** would be selected as the root bridge in preference to a bridge with priority value of **32768** (the default). To create a bridge with a non-default value, issue a command as follows:

```
~]$ nmcli con add type bridge ifname br5 stp yes priority 28672
Connection 'bridge-br5' (86b83ad3-b466-4795-aeb6-4a66eb1856c7)
successfully added.
```

The allowed values are in the range **0** to **65535**.

To change the bridge priority of an existing bridge to a non-default value, issue a command in the following format:

```
~]$ nmcli connection modify bridge-br5 bridge.priority 36864
```

The allowed values are in the range **0** to **65535**.

To view the bridge settings, issue the following command:

```
~]$ nmcli -f bridge con show bridge-br0
```

Further options for **802.1D STP** are listed in the bridge section of the **nmcli(1)** man page.

To add, or enslave an interface, for example **eth1**, to the bridge **bridge-br0**, issue a command as follows:

```
~]$ nmcli con add type ethernet ifname eth1 master bridge-br0
Connection 'bridge-slave-eth1' (70ffae80-7428-4d9c-8cbd-2e35de72476e)
successfully added.
```

At time of writing, **nmcli** only supports Ethernet slaves.

To change a value using interactive mode, issue the following command:

```
~]$ nmcli connection edit bridge-br0
```

You will be placed at the **nmcli** prompt.

```
nmcli> set bridge.priority 4096
nmcli> save
Connection 'bridge-br0' (79cf6a3e-0310-4a78-b759-bda1cc3eef8d)
successfully saved.
nmcli> quit
```

See [Section 2.1.5, “Using the NetworkManager Command Line Tool, nmcli”](#) for an introduction to nmcli.

6.3. USING THE COMMAND LINE INTERFACE (CLI)

6.3.1. Check if Bridging Kernel Module is Installed

In Red Hat Enterprise Linux 7, the bridging module is loaded by default. If necessary, you can make sure that the module is loaded by issuing the following command as **root**:

```
~]# modprobe --first-time bridge
modprobe: ERROR: could not insert 'bridge': Module already in kernel
```

To display information about the module, issue the following command:

```
~]$ modinfo bridge
```

See the **modprobe(8)** man page for more command options.

6.3.2. Create a Network Bridge

To create a network bridge, create a file in the `/etc/sysconfig/network-scripts/` directory called **ifcfg-brN**, replacing *N* with the number for the interface, such as **0**.

The contents of the file is similar to whatever type of interface is getting bridged to, such as an Ethernet interface. The differences in this example are as follows:

- The **DEVICE** directive is given an interface name as its argument in the format **brN**, where *N* is replaced with the number of the interface.
- The **TYPE** directive is given an argument **Bridge**. This directive determines the device type and the argument is case sensitive.
- The bridge interface configuration file is given an **IP** address whereas the physical interface configuration file must only have a MAC address (see below).
- An extra directive, **DELAY=0**, is added to prevent the bridge from waiting while it monitors traffic, learns where hosts are located, and builds a table of MAC addresses on which to base its filtering decisions. The default delay of 15 seconds is not needed if no routing loops are possible.

Example 6.1. Example ifcfg-br0 Interface Configuration File

The following is an example of a bridge interface configuration file using a static **IP** address:

```
DEVICE=br0
TYPE=Bridge
IPADDR=192.168.1.1
PREFIX=24
BOOTPROTO=none
ONBOOT=yes
DELAY=0
```


To complete the bridge another interface is created, or an existing interface is modified, and pointed to the bridge interface.

Example 6.2. Example ifcfg-ethX Interface Configuration File

The following is an example of an Ethernet interface configuration file pointing to a bridge interface. Configure your physical interface in `/etc/sysconfig/network-scripts/ifcfg-ethX`, where `X` is a unique number corresponding to a specific interface, as follows:

```
DEVICE=ethX
TYPE=Ethernet
HWADDR=AA:BB:CC:DD:EE:FF
BOOTPROTO=none
ONBOOT=yes
BRIDGE=br0
```

Optionally specify a name using the `NAME` directive. If no name is specified, the **NetworkManager** plug-in, `ifcfg-rh`, will create a name for the connection profile in the form “Type Interface”. In this example, this means the bridge will be named **Bridge br0**. Alternately, if `NAME=bridge-br0` is added to the `ifcfg-br0` file the connection profile will be named **bridge-br0**.



NOTE

For the **DEVICE** directive, almost any interface name could be used as it does not determine the device type. **TYPE=Ethernet** is not strictly required. If the **TYPE** directive is not set, the device is treated as an Ethernet device (unless its name explicitly matches a different interface configuration file).

The directives are case sensitive.

Specifying the hardware or MAC address using the **HWADDR** directive will influence the device naming procedure as explained in [Chapter 8, Consistent Network Device Naming](#).



WARNING

If you are configuring bridging on a remote host, and you are connected to that host over the physical NIC you are configuring, consider the implications of losing connectivity before proceeding. You will lose connectivity when restarting the service and may not be able to regain connectivity if any errors have been made. Console, or out-of-band access is advised.

To open the new or recently configured interfaces, issue a command as **root** in the following format:

```
ifup device
```

This command will detect if **NetworkManager** is running and call `nmcli con load UUID` and then call `nmcli con up UUID`.

Alternatively, to reload all interfaces, issue the following command as **root**:

```
~]# systemctl restart network
```

This command will stop the network service, start the network service, and then call **ifup** for all **ifcfg** files with **ONBOOT=yes**.



NOTE

The default behavior is for **NetworkManager** not to be aware of changes to **ifcfg** files and to continue using the old configuration data until the interface is next brought up. This is set by the **monitor-connection-files** option in the **NetworkManager.conf** file. See the **NetworkManager.conf(5)** manual page for more information.

6.3.3. Network Bridge with Bond

An example of a network bridge formed from two or more bonded Ethernet interfaces will now be given as this is another common application in a virtualization environment. If you are not very familiar with the configuration files for bonded interfaces, see [Section 4.4.2, “Create a Channel Bonding Interface”](#)

Create or edit two or more Ethernet interface configuration files, which are to be bonded, as follows:

```
DEVICE=ethX
TYPE=Ethernet
SLAVE=yes
MASTER=bond0
BOOTPROTO=none
HWADDR=AA:BB:CC:DD:EE:FF
```



NOTE

Using **ethX** as the interface name is common practice but almost any name could be used.

Create or edit one interface configuration file, **/etc/sysconfig/network-scripts/ifcfg-bond0**, as follows:

```
DEVICE=bond0
ONBOOT=yes
BONDING_OPTS='mode=1 miimon=100'
BRIDGE=brbond0
```

For further instructions and advice on configuring the bonding module and to view the list of bonding parameters, see [Section 4.5, “Using Channel Bonding”](#).

Create or edit one interface configuration file, **/etc/sysconfig/network-scripts/ifcfg-brbond0**, as follows:

```
DEVICE=brbond0
ONBOOT=yes
TYPE=Bridge
```



```
IPADDR=192.168.1.1
PREFIX=24
```

We now have two or more interface configuration files with the **MASTER=bond0** directive. These point to the configuration file named `/etc/sysconfig/network-scripts/ifcfg-bond0`, which contains the **DEVICE=bond0** directive. This `ifcfg-bond0` in turn points to the `/etc/sysconfig/network-scripts/ifcfg-brbond0` configuration file, which contains the **IP** address, and acts as an interface to the virtual networks inside the host.

To open the new or recently configured interfaces, issue a command as **root** in the following format:

```
ifup device
```

This command will detect if **NetworkManager** is running and call `nmcli con load UUID` and then call `nmcli con up UUID`.

Alternatively, to reload all interfaces, issue the following command as **root**:

```
~]# systemctl restart network
```

This command will stop the network service, start the network service, and then call **ifup** for all `ifcfg` files with **ONBOOT=yes**.



NOTE

The default behavior is for **NetworkManager** not to be aware of changes to `ifcfg` files and to continue using the old configuration data until the interface is next brought up. This is set by the `monitor-connection-files` option in the `NetworkManager.conf` file. See the `NetworkManager.conf(5)` manual page for more information.

6.4. CONFIGURE NETWORK BRIDGING USING A GUI

When starting a bridge interface, **NetworkManager** waits for at least one port to enter the “forwarding” state before beginning any network-dependent **IP** configuration such as **DHCP** or **IPv6** autoconfiguration. Static **IP** addressing is allowed to proceed before any slaves or ports are connected or begin forwarding packets.

6.4.1. Establishing a Bridge Connection

Procedure 6.1. Adding a New Bridge Connection

Follow the below instructions to create a new bridge connection.

1. To use the graphical **Network** settings tool, press the **Super** key to enter the Activities Overview, type `control network` and then press **Enter**. The **Network** settings tool appears. This steps is fully covered in [Section 2.3, “Using NetworkManager with the GNOME Graphical User Interface”](#).
2. Select the plus symbol below the menu. The **Add Network Connection** window appears.
3. Select the **Bridge** menu entry. The **Editing Bridge connection 1** window appears.

Editing Bridge connection 1

Connection name:

General **Bridge** IPv4 Settings IPv6 Settings

Interface name:

Bridged connections:

Aging time: s

☒ Enable STP (Spanning Tree Protocol)

Priority:

Forward delay: s

Hello time: s

Max age: s

Figure 6.5. Editing Bridge Connection 1

4. Add slave devices by referring to [Procedure 6.3, “Adding a Slave Interface to a Bridge”](#) below.

Procedure 6.2. Editing an Existing Bridge Connection

You can configure an existing bridge connection by opening the **Network** window and selecting the name of the connection from the list. Then click the **Edit** button.

1. Press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears.
2. Select the **Bridge** connection you want to edit from the left hand menu.

3. Click the **Options** button.

Configuring the Connection Name, Auto-Connect Behavior, and Availability Settings

Five settings in the **Editing** dialog are common to all connection types, see the **General** tab:

- **Connection name** – Enter a descriptive name for your network connection. This name will be used to list this connection in the menu of the **Network** window.
- **Automatically connect to this network when it is available** – Select this box if you want **NetworkManager** to auto-connect to this connection when it is available. See [Section 2.3.3, “Connecting to a Network Automatically”](#) for more information.
- **All users may connect to this network** – Select this box to create a connection available to all users on the system. Changing this setting may require root privileges. See [Section 2.3.5, “System-wide and Private Connection Profiles”](#) for details.
- **Automatically connect to VPN when using this connection** – Select this box if you want **NetworkManager** to auto-connect to a VPN connection when it is available. Select the VPN from the dropdown menu.
- **Firewall Zone** – Select the Firewall Zone from the dropdown menu. See the [Red Hat Enterprise Linux 7 Security Guide](#) for more information on Firewall Zones.

6.4.1.1. Configuring the Bridge Tab

Interface name

The name of the interface to the bridge.

Bridged connections

One or more slave interfaces.

Aging time

The time, in seconds, a MAC address is kept in the MAC address forwarding database.

Enable STP (Spanning Tree Protocol)

If required, select the check box to enable STP.

Priority

The bridge priority; the bridge with the lowest priority will be elected as the root bridge.

Forward delay

The time, in seconds, spent in both the Listening and Learning states before entering the Forwarding state. The default is 15 seconds.

Hello time

The time interval, in seconds, between sending configuration information in bridge protocol data units (BPDU).

Max age

The maximum time, in seconds, to store the configuration information from BPDUs. This value should be twice the Hello Time plus 1 but less than twice the Forwarding delay minus 1.

Procedure 6.3. Adding a Slave Interface to a Bridge

1. To add a port to a bridge, select the **Bridge** tab in the **Editing Bridge connection 1** window. If necessary, open this window by following the procedure in [Procedure 6.2, “Editing an Existing Bridge Connection”](#).
2. Click **Add**. The **Choose a Connection Type** menu appears.
3. Select the type of connection to be created from the list. Click **Create**. A window appropriate to the connection type selected appears.

The screenshot shows a window titled "Editing bridge0 slave 1". At the top, there is a text field for "Connection name:" containing "bridge0 slave 1". Below this are five tabs: "General", "Ethernet", "802.1x Security", "DCB", and "Bridge Port". The "Ethernet" tab is currently selected. Under the "Ethernet" tab, there are three main fields: "Device MAC address:" with a dropdown menu showing "52:54:00:FC:12:D9 (ens9)", "Cloned MAC address:" with an empty text field, and "MTU:" with a dropdown menu showing "automatic" and a "bytes" label. At the bottom right of the window are two buttons: "Cancel" and "Save...".

Figure 6.6. The NetworkManager Graphical User Interface Add a Bridge Connection

4. Select the **Bridge Port** tab. Configure **Priority** and **Path cost** as required. Note the STP priority for a bridge port is limited by the Linux kernel. Although the standard allows a range of 0 to 255, Linux only allows 0 to 63. The default is 32 in this case.




Figure 6.7. The NetworkManager Graphical User Interface Bridge Port tab

5. If required, select the **Hairpin mode** check box to enable forwarding of frames for external processing. Also known as *virtual Ethernet port aggregator (VEPA)* mode.

Then, to configure:

- An Ethernet slave, click the **Ethernet** tab and proceed to [the section called “Basic Configuration Options”](#), or;
- A Bond slave, click the **Bond** tab and proceed to [Section 4.6.1.1, “Configuring the Bond Tab”](#), or;
- A Team slave, click the **Team** tab and proceed to [Section 5.13.1.1, “Configuring the Team Tab”](#), or;
- An VLAN slave, click the **VLAN** tab and proceed to [Section 7.5.1.1, “Configuring the VLAN Tab”](#), or;

Saving Your New (or Modified) Connection and Making Further Configurations

Once you have finished editing your new bridge connection, click the **Save** button to save your customized configuration. If the profile was in use while being edited, power cycle the connection to make **NetworkManager** apply the changes. If the profile is OFF, set it to ON or select it in the network connection icon's menu. See [Section 2.3.1, “Connecting to a Network Using a GUI”](#) for information on using your new or altered connection.

You can further configure an existing connection by selecting it in the **Network** window and clicking **Options** to return to the **Editing** dialog.

Then, to configure:

- **IPv4** settings for the connection, click the **IPv4 Settings** tab and proceed to [Section 2.7.6](#), “Configuring IPv4 Settings”, or;
- **IPv6** settings for the connection, click the **IPv6 Settings** tab and proceed to [Section 2.7.7](#), “Configuring IPv6 Settings”.

Once saved the Bridge will appear in the Network settings tool with each slave showing in the display.




Figure 6.8. The NetworkManager Graphical User Interface with Bridge

6.5. ETHERNET BRIDGE CONFIGURATION USING IPROUTE

The `iproute` package can be used as an alternative to the `bridge-utils`. It allows to set bridge port options such as **priority**, **cost** or **state**.

To set port options for an interface `eth0` enslaved in a bridge device, using the `ip` utility, issue the following command as **root**:

```
~]# ip link set eth0 type bridge_slave option
```

To select the available options, using the `ip` utility, issue the following command as **root**:

```
~]# ip link help bridge_slave
Usage: ... bridge_slave [ state STATE ] [ priority PRIO ] [ cost COST ]
[ guard {on | off} ]
[ hairpin {on | off} ]
[ fastleave {on | off} ]
[ root_block {on | off} ]
[ learning {on | off} ]
[ flood {on | off} ]
```

For more details on the port options, see the `ip-link(8)` man page.

6.6. ADDITIONAL RESOURCES

- `nmcli(1)` man page – Describes **NetworkManager**'s command-line tool.
- `nmcli-examples(5)` man page – Gives examples of `nmcli` commands.
- `nm-settings(5)` man page – Description of settings and parameters of **NetworkManager** connections.
- `ip-link(8)` man page – Description of the bridge port options.

CHAPTER 7. CONFIGURE 802.1Q VLAN TAGGING

To create a VLAN, an interface is created on top of another interface referred to as the *parent interface*. The VLAN interface will tag packets with the VLAN ID as they pass through the interface, and returning packets will be untagged. VLAN interface can be configured similarly to any other interface. The parent interface does not need to be an Ethernet interface. An 802.1Q VLAN tagging interface can be created on top of bridge, bond, and team interfaces, however there are some things to note:

- In the case of VLANs over bonds, it is important that the bond has slaves and that they are “up” before bringing up the VLAN interface. Adding a VLAN interface to a bond without slaves does not work.
- A VLAN slave cannot be configured on a bond with the `fail_over_mac=follow` option, because the VLAN virtual device cannot change its MAC address to match the parent's new MAC address. In such a case, traffic would still be sent with the now incorrect source MAC address.
- Sending VLAN tagged packets through a network switch requires the switch to be properly configured. For example, ports on Cisco switches must be assigned to one VLAN or be configured as trunk ports to accept tagged packets from multiple VLANs. Some vendor switches allow untagged frames of the *native VLAN* to be processed by a trunk port. Some devices allow you to enable or disable the *native VLAN*, other devices have it disabled by default. Consequence of this disparity may result in *native VLAN* misconfiguration between two different switches, posing a security risk. For example:

One switch uses *native VLAN 1* while the other uses *native VLAN 10*. If the frames are allowed to pass without the tag being inserted, an attacker is able to jump VLANs - this common network penetration technique is also known as *VLAN hopping*.

To minimize security risks, configure your interface as follows:

Switches

- Unless you need them, disable trunk ports.
- If you need trunk ports, disable *native VLAN*, so that untagged frames are not allowed.

Red Hat Enterprise Linux server

- Use the `nftables` or `ebtables` utilities to drop untagged frames in ingress filtering.
- Some older network interface cards, loopback interfaces, Wimax cards, and some InfiniBand devices, are said to be *VLAN challenged*, meaning they cannot support VLANs. This is usually because the devices cannot cope with VLAN headers and the larger MTU size associated with tagged packets.

NOTE

If you are using the **nmcli** tool, it is easier to create the **bridge**, **team**, **bond** interfaces on top of the VLANs. For example in **bridge**:

```
nmcli c add con-name br0 type bridge
```

```
nmcli c add con-name vlan1 br0 type vlan
```

or

```
nmcli c add con-name vlan2 br0 type vlan
```

7.1. SELECTING VLAN INTERFACE CONFIGURATION METHODS

- To configure a VLAN interface using NetworkManager's text user interface tool, **nmtui**, proceed to [Section 7.2, “Configure 802.1Q VLAN tagging Using the Text User Interface, nmtui”](#)
- To configure a VLAN interface using NetworkManager's command-line tool, **nmcli**, proceed to [Section 7.3, “Configure 802.1Q VLAN Tagging Using the Command Line Tool, nmcli”](#)
- To configure a network interface manually, see [Section 7.4, “Configure 802.1Q VLAN Tagging Using the Command Line”](#).
- To configure a network using graphical user interface tools, proceed to [Section 7.5, “Configure 802.1Q VLAN Tagging Using a GUI”](#)

7.2. CONFIGURE 802.1Q VLAN TAGGING USING THE TEXT USER INTERFACE, NMTUI

The text user interface tool **nmtui** can be used to configure 802.1Q VLANs in a terminal window. Issue the following command to start the tool:

```
~]$ nmtui
```

The text user interface appears. Any invalid command prints a usage message.

To navigate, use the arrow keys or press **Tab** to step forwards and press **Shift+Tab** to step back through the options. Press **Enter** to select an option. The **Space** bar toggles the status of a check box.

From the starting menu, select **Edit a connection**. Select **Add, the New Connection** screen opens.




Figure 7.1. The NetworkManager Text User Interface Add a VLAN Connection menu

Select **VLAN**, the **Edit connection** screen opens. Follow the on-screen prompts to complete the configuration.




Figure 7.2. The NetworkManager Text User Interface Configuring a VLAN Connection menu

See [Section 7.5.1.1, “Configuring the VLAN Tab”](#) for definitions of the VLAN terms.

See [Section 1.5, “Network Configuration Using a Text User Interface \(nmtui\)”](#) for information on installing `nmtui`.

7.3. CONFIGURE 802.1Q VLAN TAGGING USING THE COMMAND LINE TOOL, NMCLI

To view the available interfaces on the system, issue a command as follows:

```
~]$ nmcli con show
NAME                UUID                                TYPE
DEVICE
System eth1         9c92fad9-6ecb-3e6c-eb4d-8a47c6f50c04  802-3-ethernet  eth1
System eth0         5fb06bd0-0bb0-7ffb-45f1-d6edd65f3e03  802-3-ethernet  eth0
```

Note that the NAME field in the output always denotes the connection ID. It is not the interface name even though it might look the same. The ID can be used in `nmcli connection` commands to identify a connection. Use the DEVICE name with other applications such as `firewalld`.

To create an 802.1Q VLAN interface on Ethernet interface `eth0`, with VLAN interface `VLAN10` and ID `10`, issue a command as follows:

```
~]$ nmcli con add type vlan ifname VLAN10 dev eth0 id 10
Connection 'vlan-VLAN10' (37750b4a-8ef5-40e6-be9b-4fb21a4b6d17)
successfully added.
```

Note that as no `con-name` was given for the VLAN interface, the name was derived from the interface name by prepending the type. Alternatively, specify a name with the `con-name` option as follows:

```
~]$ nmcli con add type vlan con-name VLAN12 dev eth0 id 12
Connection 'VLAN12' (b796c16a-9f5f-441c-835c-f594d40e6533) successfully
added.
```

Assigning Addresses to VLAN Interfaces

You can use the same `nmcli` commands to assign static and dynamic interface addresses as with any other interface.

For example, a command to create a VLAN interface with a static **IPv4** address and gateway is as follows:

```
~]$ nmcli con add type vlan con-name VLAN20 dev eth0 id 20 ip4
10.10.10.10/24 \
gw4 10.10.10.254
```

To create a VLAN interface with dynamically assigned addressing, issue a command as follows:

```
~]$ nmcli con add type vlan con-name VLAN30 dev eth0 id 30
```

See [Section 2.1.7, “Connecting to a Network Using nmcli”](#) for examples of using `nmcli` commands to configure interfaces.

To review the VLAN interfaces created, issue a command as follows:

```

~]$ nmcli con show
NAME                UUID                                TYPE
DEVICE
VLAN12              4129a37d-4feb-4be5-ac17-14a193821755  vlan
eth0.12
System eth1         9c92fad9-6ecb-3e6c-eb4d-8a47c6f50c04  802-3-ethernet  eth1
System eth0         5fb06bd0-0bb0-7ffb-45f1-d6edd65f3e03  802-3-ethernet  eth0
vlan-VLAN10         1be91581-11c2-461a-b40d-893d42fed4f4  vlan            VLAN10

```

To view detailed information about the newly configured connection, issue a command as follows:

```

~]$ nmcli -p con show VLAN12
=====
=====
                                Connection profile details (VLAN12)
=====
=====
connection.id:                                VLAN12
connection.uuid:                              4129a37d-4feb-4be5-ac17-
14a193821755
connection.interface-name:                    --
connection.type:                              vlan
connection.autoconnect:                       yes
...
-----
-----
802-3-ethernet.port:                          --
802-3-ethernet.speed:                         0
802-3-ethernet.duplex:                        --
802-3-ethernet.auto-negotiate:                 yes
802-3-ethernet.mac-address:                   --
802-3-ethernet.cloned-mac-address:             --
802-3-ethernet.mac-address-blacklist:
802-3-ethernet.mtu:                           auto
...
vlan.interface-name:                          --
vlan.parent:                                  eth0
vlan.id:                                       12
vlan.flags:                                   0 (NONE)
vlan.ingress-priority-map:
vlan.egress-priority-map:
-----
-----
=====
=====
                                Activate connection details (4129a37d-4feb-4be5-ac17-14a193821755)
=====
=====
GENERAL.NAME:                                VLAN12
GENERAL.UUID:                                4129a37d-4feb-4be5-ac17-
14a193821755
GENERAL.DEVICES:                             eth0.12
GENERAL.STATE:                                activating
[output truncated]

```

Further options for the VLAN command are listed in the VLAN section of the `nmcli(1)` man page. In the man pages the device on which the VLAN is created is referred to as the parent device. In the example above the device was specified by its interface name, `eth0`, it can also be specified by the connection UUID or MAC address.

To create an 802.1Q VLAN connection profile with ingress priority mapping on Ethernet interface `eth1`, with name `VLAN1` and ID `13`, issue a command as follows:

```
~]$ nmcli con add type vlan con-name VLAN1 dev eth2 id 13 ingress
"2:3,3:5"
```

To view all the parameters associated with the VLAN created above, issue a command as follows:

```
~]$ nmcli connection show vlan-VLAN10
```

To change the MTU, issue a command as follows:

```
~]$ nmcli connection modify vlan-VLAN10 802.mtu 1496
```

The MTU setting determines the maximum size of the network layer packet. The maximum size of the payload the link-layer frame can carry in turn limits the network layer MTU. For standard Ethernet frames this means an MTU of 1500 bytes. It should not be necessary to change the MTU when setting up a VLAN as the link-layer header is increased in size by 4 bytes to accommodate the 802.1Q tag.

At time of writing, `connection.interface-name` and `vlan.interface-name` have to be the same (if they are set). They must therefore be changed simultaneously using `nmcli`'s interactive mode. To change a VLAN connections name, issue commands as follows:

```
~]$ nmcli con edit vlan-VLAN10
nmcli> set vlan.interface-name superVLAN
nmcli> set connection.interface-name superVLAN
nmcli> save
nmcli> quit
```

The `nmcli` utility can be used to set and clear `ioct1` flags which change the way the 802.1Q code functions. The following VLAN flags are supported by **NetworkManager**:

- 0x01 - reordering of output packet headers
- 0x02 - use GVRP protocol
- 0x04 - loose binding of the interface and its master

The state of the VLAN is synchronized to the state of the parent or master interface (the interface or device on which the VLAN is created). If the parent interface is set to the “down” administrative state then all associated VLANs are set down and all routes are flushed from the routing table. Flag `0x04` enables a *loose binding* mode, in which only the operational state is passed from the parent to the associated VLANs, but the VLAN device state is not changed.

To set a VLAN flag, issue a command as follows:

```
~]$ nmcli connection modify vlan-VLAN10 vlan.flags 1
```

See [Section 2.1.5, “Using the NetworkManager Command Line Tool, nmcli”](#) for an introduction to `nmcli`.

7.4. CONFIGURE 802.1Q VLAN TAGGING USING THE COMMAND LINE

In Red Hat Enterprise Linux 7, the `8021q` module is loaded by default. If necessary, you can make sure that the module is loaded by issuing the following command as `root`:

```
~]# modprobe --first-time 8021q
modprobe: ERROR: could not insert '8021q': Module already in kernel
```

To display information about the module, issue the following command:

```
~]$ modinfo 8021q
```

See the `modprobe(8)` man page for more command options.

7.4.1. Setting Up 802.1Q VLAN Tagging Using `ifcfg` Files

1. Configure the parent interface in `/etc/sysconfig/network-scripts/ifcfg-ethX`, where `X` is a unique number corresponding to a specific interface, as follows:

```
DEVICE=ethX
TYPE=Ethernet
BOOTPROTO=none
ONBOOT=yes
```

2. Configure the VLAN interface configuration in the `/etc/sysconfig/network-scripts/` directory. The configuration file name should be the parent interface plus a `.` character plus the VLAN ID number. For example, if the VLAN ID is 192, and the parent interface is `eth0`, then the configuration file name should be `ifcfg-eth0.192`:

```
DEVICE=ethX.192
BOOTPROTO=none
ONBOOT=yes
IPADDR=192.168.1.1
PREFIX=24
NETWORK=192.168.1.0
VLAN=yes
```

If there is a need to configure a second VLAN, with for example, VLAN ID 193, on the same interface, `eth0`, add a new file with the name `eth0.193` with the VLAN configuration details.

3. Restart the networking service in order for the changes to take effect. As `root` issue the following command:

```
~]# systemctl restart network
```

7.4.2. Configure 802.1Q VLAN Tagging Using `ip` Commands

To create an 802.1Q VLAN interface on Ethernet interface `eth0`, with name `VLAN8` and ID `8`, issue a command as `root` as follows:

```
~]# ip link add link eth0 name eth0.8 type vlan id 8
```

To view the VLAN, issue the following command:

```
~]$ ip -d link show eth0.8
4: eth0.8@eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue
state UP mode DEFAULT
    link/ether 52:54:00:ce:5f:6c brd ff:ff:ff:ff:ff:ff promiscuity 0
    vlan protocol 802.1Q id 8 <REORDER_HDR>
```

Note that the **ip** utility interprets the VLAN ID as a hexadecimal value if it is preceded by **0x** and as an octal value if it has a leading **0**. This means that in order to assign a VLAN ID with a decimal value of **22**, you must not add any leading zeros.

To remove the VLAN, issue a command as **root** as follows:

```
~]# ip link delete eth0.8
```

To use multiple interfaces belonging to multiple VLANs, create locally *eth0.1* and *eth0.2* with the appropriate VLAN ID on top of a physical interface *eth0*:

```
~]# ip link add link eth0 name eth0.1 type vlan id 1
    ip link set dev eth0.1 up
~]# ip link add link eth0 name eth0.2 type vlan id 2
    ip link set dev eth0.2 up
```

Note that running a network sniffer on a physical device, you can capture the tagged frames reaching the physical device, even if no VLAN device is configured on top of *eth0*. For example:

```
tcpdump -nnei eth0 -vvv
```



NOTE

VLAN interfaces created using **ip** commands at the command prompt will be lost if the system is shutdown or restarted. To configure VLAN interfaces to be persistent after a system restart, use **ifcfg** files. See [Section 7.4.1, “Setting Up 802.1Q VLAN Tagging Using ifcfg Files”](#)

7.5. CONFIGURE 802.1Q VLAN TAGGING USING A GUI

7.5.1. Establishing a VLAN Connection

You can use the GNOME **control-center** utility to direct **NetworkManager** to create a VLAN using an existing interface as the parent interface. At time of writing, you can only make VLANs on Ethernet devices. Note that VLAN devices are only created automatically if the parent interface is set to connect automatically.

Procedure 7.1. Adding a New VLAN Connection

You can configure a VLAN connection by opening the **Network** window, clicking the plus symbol, and selecting **VLAN** from the list.

1. Press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears.
2. Click the plus symbol to open the selection list. Select **VLAN**. The **Editing VLAN Connection 1** window appears.
3. On the **VLAN** tab, select the parent interface from the drop-down list you want to use for the VLAN connection.
4. Enter the VLAN ID
5. Enter a VLAN interface name. This is the name of the VLAN interface that will be created. For example, **eth0.1** or **vlan2**. (Normally this is either the parent interface name plus “.” and the VLAN ID, or “**vlan**” plus the VLAN ID.)
6. Review and confirm the settings and then click the **Save** button.
7. To edit the VLAN-specific settings see [Section 7.5.1.1, “Configuring the VLAN Tab”](#).

Figure 7.3. Adding a New VLAN Connection

Procedure 7.2. Editing an Existing VLAN Connection

Follow these steps to edit an existing VLAN connection.

1. Press the **Super** key to enter the Activities Overview, type **control network** and then press **Enter**. The **Network** settings tool appears.
2. Select the connection you want to edit and click the **Options** button.
3. Select the **General** tab.

4. Configure the connection name, auto-connect behavior, and availability settings.

These settings in the **Editing** dialog are common to all connection types:

- **Connection name** – Enter a descriptive name for your network connection. This name will be used to list this connection in the **VLAN** section of the **Network** window.
- **Automatically connect to this network when it is available** – Select this box if you want **NetworkManager** to auto-connect to this connection when it is available. Refer to [Section 2.3.3, “Connecting to a Network Automatically”](#) for more information.
- **Available to all users** – Select this box to create a connection available to all users on the system. Changing this setting may require root privileges. Refer to [Section 2.3.5, “System-wide and Private Connection Profiles”](#) for details.

5. To edit the VLAN-specific settings see [Section 7.5.1.1, “Configuring the VLAN Tab”](#).

Saving Your New (or Modified) Connection and Making Further Configurations

Once you have finished editing your VLAN connection, click the **Save** button to save your customized configuration. If the profile was in use while being edited, power cycle the connection to make **NetworkManager** apply the changes. If the profile is OFF, set it to ON or select it in the network connection icon's menu. See [Section 2.3.1, “Connecting to a Network Using a GUI”](#) for information on using your new or altered connection.

You can further configure an existing connection by selecting it in the **Network** window and clicking **Options** to return to the **Editing** dialog.

Then, to configure:

- IPv4 settings for the connection, click the **IPv4 Settings** tab and proceed to [Section 2.7.6, “Configuring IPv4 Settings”](#).

7.5.1.1. Configuring the VLAN Tab

If you have already added a new VLAN connection (refer to [Procedure 7.1, “Adding a New VLAN Connection”](#) for instructions), you can edit the **VLAN** tab to set the parent interface and the VLAN ID.

Parent Interface

A previously configured interface can be selected in the drop-down list.

VLAN ID

The identification number to be used to tag the VLAN network traffic.

VLAN interface name

The name of the VLAN interface that will be created. For example, **eth0.1** or **vlan2**.

Cloned MAC address

Optionally sets an alternate MAC address to use for identifying the VLAN interface. This can be used to change the source MAC address for packets sent on this VLAN.

MTU

Optionally sets a Maximum Transmission Unit (MTU) size to be used for packets to be sent over the VLAN connection.

7.6. VLAN ON BOND AND BRIDGE USING IP COMMANDS

To use VLANs over bonds and bridges, proceed as follows:

1. Add a bond device as **root**:

```
# ip link add bond0 type bond
# ip link set bond0 type bond miimon 100 mode active-backup
# ip link set em1 down
# ip link set em1 master bond0
# ip link set em2 down
# ip link set em2 master bond0
# ip link set bond0 up
```

2. Set VLAN on the bond device:

```
# ip link add link bond0 name bond0.2 type vlan id 2
# ip link set bond0.2 up
```

3. Add the bridge device and attach VLAN to it:

```
# ip link add br0 type bridge
# ip link set bond0.2 master br0
# ip link set br0 up
```

7.7. VLAN ON BOND AND BRIDGE USING THE NETWORKMANAGER COMMAND LINE TOOL, NMCLI

To use VLANs over bonds and bridges, proceed as follows:

1. Add a bond device:

```
~]$ nmcli connection add type bond con-name Bond0 ifname bond0
bond.options "mode=active-backup,miimon=100" ipv4.method disabled
ipv6.method ignore
```

Note that in this case a bond connection serves only as a "lower interface" for VLAN, and does not get any IP address. Therefore, the **ipv4.method disabled** and **ipv6.method ignore** parameters have been added on the command line.

2. Add slaves to the bond device:

```
~]$ nmcli connection add type ethernet con-name Slave1 ifname em1
master bond0 slave-type bond
~]$ nmcli connection add type ethernet con-name Slave2 ifname em2
master bond0 slave-type bond
```

3. Add a bridge device:

```
~]$ nmcli connection add type bridge con-name Bridge0 ifname br0 ip4
192.0.2.1/24
```

4. Add a VLAN interface on top of bond, enslaved to the bridge device:

```
~]$ nmcli connection add type vlan con-name Vlan2 ifname bond0.2 dev
bond0 id 2 master br0 slave-type bridge
```

5. View the created connections:

```
~]$ nmcli connection show
```

NAME	UUID	TYPE	
DEVICE			
Bond0	f05806fa-72c3-4803-8743-2377f0c10bed	bond	
bond0			
Bridge0	22d3c0de-d79a-4779-80eb-10718c2bed61	bridge	br0
Slave1	e59e13cb-d749-4df2-ae6-de3bfaec698c	802-3-ethernet	em1
Slave2	25361a76-6b3c-4ae5-9073-005be5ab8b1c	802-3-ethernet	em2
Vlan2	e2333426-eea4-4f5d-a589-336f032ec822	vlan	
bond0.2			

7.8. CONFIGURING VLAN SWITCHPORT MODE

Red Hat Enterprise Linux machines are often used as routers and enable an advanced VLAN configuration on their network interfaces. You need to set **switchport mode** when the Ethernet interface is connected to a switch and there are VLANs running over the physical interface. A Red Hat Enterprise Linux server or workstation is usually connected to only one VLAN, which makes **switchport mode access** suitable, and the default setting.

In certain scenarios, multiple tagged VLANs use the same physical link, that is Ethernet between the switch and Red Hat Enterprise Linux machine, which requires **switchport mode trunk** to be configured on both ends.

For example, when a Red Hat Enterprise Linux machine is used as a router, the machine needs to forward tagged packets from the various VLANs behind the router to the switch over the same physical Ethernet, and maintain separation between those VLANs.

With the setup described, for example, in [Section 7.3, “Configure 802.1Q VLAN Tagging Using the Command Line Tool, nmcli”](#), use the Cisco **switchport mode trunk**. If you only set an IP address on an interface, use Cisco **switchport mode access**.

7.9. ADDITIONAL RESOURCES

- **ip-link(8)** man page – Describes the **ip** utility's network device configuration commands.
- **nmcli(1)** man page – Describes **NetworkManager**'s command-line tool.
- **nmcli-examples(5)** man page – Gives examples of **nmcli** commands.
- **nm-settings(5)** man page – Description of settings and parameters of **NetworkManager** connections.
- **nm-settings-ifcfg-rh(5)** man page – Description of **ifcfg-rh** settings in the **/etc/sysconfig/network-scripts/ifcfg-*** files.

CHAPTER 8. CONSISTENT NETWORK DEVICE NAMING

Red Hat Enterprise Linux provides methods for consistent and predictable network device naming for network interfaces. These features change the name of network interfaces on a system in order to make locating and differentiating the interfaces easier.

Traditionally, network interfaces in Linux are enumerated as `eth[0123...]`, but these names do not necessarily correspond to actual labels on the chassis. Modern server platforms with multiple network adapters can encounter non-deterministic and counter-intuitive naming of these interfaces. This affects both network adapters embedded on the motherboard (*Lan-on-Motherboard*, or *LOM*) and add-in (single and multiport) adapters.

In Red Hat Enterprise Linux, `udev` supports a number of different naming schemes. The default is to assign fixed names based on firmware, topology, and location information. This has the advantage that the names are fully automatic, fully predictable, that they stay fixed even if hardware is added or removed (no re-enumeration takes place), and that broken hardware can be replaced seamlessly. The disadvantage is that they are sometimes harder to read than the `eth0` or `wlan0` names traditionally used. For example: `enp5s0`.



WARNING

Do not disable consistent network device naming because it allows the system using `ethX` style names, where `X` is a unique number corresponding to a specific interface and may have different names of network interfaces during the boot process. For more details, see [Section 8.10, “Troubleshooting Network Device Naming”](#).

8.1. NAMING SCHEMES HIERARCHY

By default, `systemd` will name interfaces using the following policy to apply the supported naming schemes:

- **Scheme 1:** Names incorporating Firmware or BIOS provided index numbers for on-board devices (example: `eno1`), are applied if that information from the firmware or BIOS is applicable and available, else falling back to scheme 2.
- **Scheme 2:** Names incorporating Firmware or BIOS provided PCI Express hotplug slot index numbers (example: `ens1`) are applied if that information from the firmware or BIOS is applicable and available, else falling back to scheme 3.
- **Scheme 3:** Names incorporating physical location of the connector of the hardware (example: `enp2s0`), are applied if applicable, else falling directly back to scheme 5 in all other cases.
- **Scheme 4:** Names incorporating interface's MAC address (example: `enx78e7d1ea46da`), is not used by default, but is available if the user chooses.
- **Scheme 5:** The traditional unpredictable kernel naming scheme, is used if all other methods fail (example: `eth0`).

This policy, the procedure outlined above, is the default. If the system has `biosdevname` enabled, it will

be used. Note that enabling **biosdevname** requires passing **biosdevname=1** as a kernel command-line parameter, except in the case of a Dell system, where **biosdevname** will be used by default as long as it is installed. If the user has added **udev** rules which change the name of the kernel devices, those rules will take precedence.

8.2. UNDERSTANDING THE DEVICE RENAMING PROCEDURE

The device name procedure in detail is as follows:

1. A rule in `/usr/lib/udev/rules.d/60-net.rules` instructs the **udev** helper utility, `/lib/udev/rename_device`, to look into all `/etc/sysconfig/network-scripts/ifcfg-suffix` files. If it finds an `ifcfg` file with a `HWADDR` entry matching the MAC address of an interface it renames the interface to the name given in the `ifcfg` file by the **DEVICE** directive.
2. A rule in `/usr/lib/udev/rules.d/71-biosdevname.rules` instructs **biosdevname** to rename the interface according to its naming policy, provided that it was not renamed in a previous step, **biosdevname** is installed, and **biosdevname=0** was not given as a kernel command on the boot command line.
3. A rule in `/lib/udev/rules.d/75-net-description.rules` instructs **udev** to fill in the internal **udev** device property values `ID_NET_NAME_ONBOARD`, `ID_NET_NAME_SLOT`, `ID_NET_NAME_PATH`, `ID_NET_NAME_MAC` by examining the network interface device. Note, that some device properties might be undefined.
4. A rule in `/usr/lib/udev/rules.d/80-net-name-slot.rules` instructs **udev** to rename the interface, provided that it was not renamed in step 1 or 2, and the kernel parameter `net.ifnames=0` was not given, according to the following priority: `ID_NET_NAME_ONBOARD`, `ID_NET_NAME_SLOT`, `ID_NET_NAME_PATH`. It falls through to the next in the list, if one is unset. If none of these are set, then the interface will not be renamed.

Steps 3 and 4 are implementing the naming schemes 1, 2, 3, and optionally 4, described in [Section 8.1, “Naming Schemes Hierarchy”](#). Step 2 is explained in more detail in [Section 8.6, “Consistent Network Device Naming Using biosdevname”](#).

8.3. UNDERSTANDING THE PREDICTABLE NETWORK INTERFACE DEVICE NAMES

The names have two-character prefixes based on the type of interface:

1. **en** for Ethernet,
2. **wl** for wireless LAN (WLAN),
3. **ww** for wireless wide area network (WWAN).

The names have the following types:

o<index>

on-board device index number

s<slot>[**f**<function>][**d**<dev_id>]

hotplug slot index number. All multi-function PCI devices will carry the [**f**<function>] number in the device name, including the function 0 device.

x<MAC>

MAC address

[P<domain>]p<bus>s<slot>[f<function>][d<dev_id>]

PCI geographical location. In PCI geographical location, the [P<domain>] number is only mentioned if the value is not 0. For example:

ID_NET_NAME_PATH=P1enp5s0

[P<domain>]p<bus>s<slot>[f<function>][u<port>][..][c<config>][i<interface>]

USB port number chain. For USB devices, the full chain of port numbers of hubs is composed. If the name gets longer than the maximum number of 15 characters, the name is not exported. If there are multiple USB devices in the chain, the default values for USB configuration descriptors (c1) and USB interface descriptors (i0) are suppressed.

8.4. NAMING SCHEME FOR NETWORK DEVICES AVAILABLE FOR LINUX ON SYSTEM Z

Use the bus-ID to create predictable device names for network interfaces in Linux on System z instances. The bus-ID identifies a device in the s390 channel subsystem. A bus ID identifies the device within the scope of a Linux instance. For a CCW device, the bus ID is the device's device number with a leading 0.n, where n is the subchannel set ID. For example, 0.1.0ab1.

Network interfaces of device type Ethernet are named as follows:

```
enccw0.0.1234
```

CTC network devices of device type SLIP are named as follows:

```
slccw0.0.1234
```

Use the `znetconf -c` command or the `lscss -a` command to display available network devices and their bus-IDs.

Table 8.1. Device Name Types for Linux on System z

Format	Description
<code>enccwbus-ID</code>	device type Ethernet
<code>slccwbus-ID</code>	CTC network devices of device type SLIP

8.5. NAMING SCHEME FOR VLAN INTERFACES

Traditionally, VLAN interface names in the format: *interface-name.VLAN-ID* are used. The **VLAN-ID** ranges from 0 to 4096, which is a maximum of four characters and the total interface name has a limit of 15 characters. The maximum interface name length is defined by the kernel headers and is a global

limit, affecting all applications.

In Red Hat Enterprise Linux 7, four naming conventions for VLAN interface names are supported:

VLAN plus VLAN ID

The word `vlan` plus the VLAN ID. For example: `vlan0005`

VLAN plus VLAN ID without padding

The word `vlan` plus the VLAN ID without padding by means of additional leading zeros. For example: `vlan5`

Device name plus VLAN ID

The name of the parent interface plus the VLAN ID. For example: `eth0.0005`

Device name plus VLAN ID without padding

The name of the parent interface plus the VLAN ID without padding by means of additional leading zeros. For example: `eth0.5`

8.6. CONSISTENT NETWORK DEVICE NAMING USING BIOSDEVNAME

This feature, implemented through the `biosdevname` `udev` helper utility, will change the name of all embedded network interfaces, PCI card network interfaces, and virtual function network interfaces from the existing `eth[0123...]` to the new naming convention as shown in [Table 8.2, “The biosdevname Naming Convention”](#). Note that unless the system is a Dell system, or `biosdevname` is explicitly enabled as described in [Section 8.6.2, “Enabling and Disabling the Feature”](#), the `systemd` naming scheme will take precedence.

Table 8.2. The biosdevname Naming Convention

Device	Old Name	New Name
Embedded network interface (LOM)	<code>eth[0123...]</code>	<code>em[1234...]^[a]</code>
PCI card network interface	<code>eth[0123...]</code>	<code>p<slot>p<ethernet port>^[b]</code>
Virtual function	<code>eth[0123...]</code>	<code>p<slot>p<ethernet port>_<virtual interface>^[c]</code>
<p>^[a] New enumeration starts at 1.</p> <p>^[b] For example: p3p4</p> <p>^[c] For example: p3p4_1</p>		

8.6.1. System Requirements

The `biosdevname` program uses information from the system's BIOS, specifically the `type 9` (System

Slot) and *type 41* (Onboard Devices Extended Information) fields contained within the SMBIOS. If the system's BIOS does not have SMBIOS version 2.6 or higher and this data, the new naming convention will not be used. Most older hardware does not support this feature because of a lack of BIOSes with the correct SMBIOS version and field information. For BIOS or SMBIOS version information, contact your hardware vendor.

For this feature to take effect, the `biosdevname` package must also be installed. To install it, issue the following command as `root`:

```
~]# yum install biosdevname
```

8.6.2. Enabling and Disabling the Feature

To disable this feature, pass the following option on the boot command line, both during and after installation:

```
biosdevname=0
```

To enable this feature, pass the following option on the boot command line, both during and after installation:

```
biosdevname=1
```

Unless the system meets the minimum requirements, this option will be ignored and the system will use the `systemd` naming scheme as described in the beginning of the chapter.

If the `biosdevname` install option is specified, it must remain as a boot option for the lifetime of the system.

8.7. NOTES FOR ADMINISTRATORS

Many system customization files can include network interface names, and thus will require updates if moving a system from the old convention to the new convention. If you use the new naming convention, you will also need to update network interface names in areas such as custom `iptables` rules, scripts altering `irqbalance`, and other similar configuration files. Also, enabling this change for installation will require modification to existing `kickstart` files that use device names through the `ksdevice` parameter; these `kickstart` files will need to be updated to use the network device's MAC address or the network device's new name.



NOTE

The maximum interface name length is defined by the kernel headers and is a global limit, affecting all applications.

8.8. CONTROLLING THE SELECTION OF NETWORK DEVICE NAMES

Device naming can be controlled in the following manner:

By identifying the network interface device

Setting the MAC address in an `ifcfg` file using the `HWADDR` directive enables it to be identified by `udev`. The name will be taken from the string given by the `DEVICE` directive, which by convention is the same as the `ifcfg` suffix. For example, `ifcfg-eth0`.

By turning on or off biosdevname

The name provided by **biosdevname** will be used (if **biosdevname** can determine one).

By turning on or off the systemd-udev naming scheme

The name provided by **systemd-udev** will be used (if **systemd-udev** can determine one).

8.9. DISABLING CONSISTENT NETWORK DEVICE NAMING

To disable consistent network device naming, is only recommended for special scenarios. See [Chapter 8, Consistent Network Device Naming](#) and [Section 8.10, “Troubleshooting Network Device Naming”](#) for more information.

To disable consistent network device naming, choose from one of the following:

- Disable the assignment of fixed names by "masking" **udev**'s rule file for the default policy. This can be done by creating a symbolic link to **/dev/null**. As a result, unpredictable kernel names will be used. As **root**, enter the following command:

```
~]# ln -s /dev/null /etc/udev/rules.d/80-net-name-slot.rules
```

- Create your own manual naming scheme, for example by naming your interfaces **internet0**, **dmz0** or **lan0**. To do that, create your own **udev** rules file and set the **NAME** property for the devices. Make sure to order the new file above the default policy file, for example by naming it **/etc/udev/rules.d/70-my-net-names.rules**.
- Alter the default policy file to pick a different naming scheme, for example to name all interfaces after their MAC address by default. As **root**, copy the default policy file as follows:

```
~]# cp /usr/lib/udev/rules.d/80-net-name-slot.rules
/etc/udev/rules.d/80-net-name-slot.rules
```

Edit the file in the **/etc/udev/rules.d/** directory and change the lines as necessary.

- Open the **/etc/default/grub/** file and find the **GRUB_CMDLINE_LINUX** variable.

**NOTE**

GRUB_CMDLINE_LINUX is a variable that includes entries which are added to the kernel command line. It might already contain additional configuration depending on your system settings.

Add both **net.ifnames=0** and **biosdevname=0** as kernel parameter values to the **GRUB_CMDLINE_LINUX** variable:

```
~]# cat /etc/default/grub
GRUB_TIMEOUT=5
GRUB_DISTRIBUTOR="$(sed 's, release .*$,,g' /etc/system-
release)"
GRUB_DEFAULT=saved
GRUB_DISABLE_SUBMENU=true
GRUB_TERMINAL_OUTPUT="console"
```

```
GRUB_CMDLINE_LINUX="rd.lvm.lv=rhel_7/swap rd.luks.uuid=luks-
cc387312-6da6-469a-8e49-b40cd58ad67a crashkernel=auto
vconsole.keymap=us vconsole.font=latarcyrheb-sun16
rd.lvm.lv=rhel_7/root rhgb quiet net.ifnames=0 biosdevname=0"
GRUB_DISABLE_RECOVERY="true"
```

Rebuild the `/boot/grub2/grub.cfg` file by running the `grub2-mkconfig` command:

```
~]# grub2-mkconfig -o /boot/grub2/grub.cfg/
```



NOTE

For systems booted using UEFI:

```
~]# grub2-mkconfig -o /boot/efi/EFI/redhat/grub.cfg
```

View the current device name. For example, `eno1`:

```
~]# nmcli connection show
NAME      UUID                                  TYPE
DEVICE
Wired     63cba8b2-60f7-4317-bc80-949e800a23cb 802-3-ethernet eno1
```

Modify the device name to `eth0`, and reboot the system:

```
~]# nmcli connection modify Wired connection.interface-name eth0
```

```
~]# reboot
```

The **grubby** utility is used for updating and displaying information about the configuration files for the **grub** boot loader. See the **grubby(8)** man page for more details. For more information about working with GRUB 2, see the [Red Hat Enterprise Linux System Administrator's Guide](#)

8.10. TROUBLESHOOTING NETWORK DEVICE NAMING

Predictable interface names will be assigned for each interface, if applicable, as per the procedure described in [Section 8.2, “Understanding the Device Renaming Procedure”](#). To view the list of possible names **udev** will use, issue a command in the following form as **root**:

```
~]# udevadm info /sys/class/net/ifname | grep ID_NET_NAME
```

where *ifname* is one of the interfaces listed by the following command:

```
~]$ ls /sys/class/net/
```

One of the possible names will be applied by **udev** according to the rules as described in [Section 8.2, “Understanding the Device Renaming Procedure”](#), and summarized here:

- `/usr/lib/udev/rules.d/60-net.rules` - from `initscripts`,
- `/usr/lib/udev/rules.d/71-biosdevname.rules` - from `biosdevname`,

- `/usr/lib/udev/rules.d/80-net-name-slot.rules` - from `systemd`

From the above list of rule files it can be seen that if interface naming is done through `initscripts` or `biosdevname` it always takes precedence over `udev` native naming. However if `initscripts` renaming is not taking place and `biosdevname` is disabled, then to alter the interface names copy the `80-net-name-slot.rules` from `/usr` to `/etc` and edit the file appropriately. In other words, comment out or arrange schemes to be used in a certain order.

Example 8.1. Some Interfaces Have Names from the Kernel Namespace (`eth[0,1,2,...]`) While Others Are Successfully Renamed by `udev`

Mixed up schemes most likely means that either for some hardware there is no usable information provided by the kernel to `udev`, thus it could not figure out any names, or the information provided to `udev` is not suitable, for example non-unique device IDs. The latter is more common and the solution is to use a custom naming scheme in `ifcfg` files or alter which `udev` scheme is in use by editing `80-net-name-slot.rules`.

Example 8.2. In `/var/log/messages` or the `systemd` Journal, Renaming Is Seen to Be Done Twice for Each Interface

Systems with the naming scheme encoded in `ifcfg` files but which do not have a regenerated `initrd` image are likely to encounter this issue. The interface name is initially assigned (through `biosdevname` or `udev` or `dracut` parameters on the kernel command line) during early-boot while still in `initrd`. Then after switching to real `rootfs`, renaming is done a second time and a new interface name is determined by the `/usr/lib/udev/rename_device` binary spawned by `udev` because of processing `60-net.rules`. You can safely ignore such messages.

Example 8.3. Using Naming Scheme in `ifcfg` Files with `ethX` Names Does Not Work

Red Hat Enterprise Linux does not provide a way to consistently apply the `ethX` naming convention except under very specific circumstances.

The `udev` rules, which set an interface to a specific name, fail if the requested name is already in use by some other interface. This includes the functionality provided by the `/usr/lib/udev/rules.d/60-net.rules` file.

Kernel uses the `ethX` naming convention at boot time when it enumerates network devices. The `ethx` names are inconsistent across various reboots, and thus they are unpredictable. Consequently, attempting to use `udev` to rename an interface to an `ethX` name or to reorder the unpredictable `ethX` names given by the kernel fails.

Using the `ethX` names works correctly for the following scenarios:

- The system has only one network interface.
- When used for virtio NICs in Red Hat Enterprise Linux 7 virtual machine guests. See the [KVM Paravirtualized \(virtio\) Drivers and Network Configuration](#) chapters in the [Virtualization Deployment and Administration Guide](#)

Example 8.4. Setting `net.ifnames=0` Results in Inconsistent `ethX` Names

If both **systemd** predictable interface naming (`net.ifnames`) and **biosdevname** naming schemes are disabled, network interfaces continue to use the unpredictable and potentially inconsistent `ethX` name originally given by the kernel.

Kernel always uses the `ethX` naming convention at boot when it enumerates network devices. Due to parallelization, the order of the kernel interface enumeration is expected to vary across reboots. Red Hat Enterprise Linux relies on either **systemd** predictable interface naming scheme or the **biosdevname** naming scheme to rename the kernel unpredictable `ethX` interfaces in a predictable way to a name which is always consistent across reboots.

For more information about network adapter naming conventions, see the [Is it safe to set `net.ifnames=0` in RHEL7?](#) Knowledge Centered Support article on the Red Hat Customer Portal.

8.11. ADDITIONAL RESOURCES

Installed Documentation

- **udev(7)** man page – Describes the Linux dynamic device management daemon, **udev**.
- **systemd(1)** man page – Describes **systemd** system and service manager.
- **biosdevname(1)** man page – Describes the utility for obtaining the BIOS-given name of a device.

Online Documentation

- The IBM Knowledge Center Publication SC34-2710-00 [Device Drivers, Features, and Commands on Red Hat Enterprise Linux 7](#) includes information on “Predictable network device names” for IBM System z devices and attachments.

PART II. INFINIBAND AND RDMA NETWORKING

This part discusses how to set up RDMA, InfiniBand, and IP over InfiniBand network connections.

CHAPTER 9. CONFIGURE INFINIBAND AND RDMA NETWORKS

9.1. UNDERSTANDING INFINIBAND AND RDMA TECHNOLOGIES

InfiniBand refers to two distinctly different things. The first is a physical link-layer protocol for InfiniBand networks. The second is a higher level programming API called the InfiniBand Verbs API. The InfiniBand Verbs API is an implementation of a *remote direct memory access* (RDMA) technology.

RDMA communications differ from normal IP communications because they bypass kernel intervention in the communication process, and in the process greatly reduce the CPU overhead normally needed to process network communications. In a typical IP data transfer, application X on machine A will send some data to application Y on machine B. As part of the transfer, the kernel on machine B must first receive the data, decode the packet headers, determine that the data belongs to application Y, wake up application Y, wait for application Y to perform a read syscall into the kernel, then it must manually copy the data from the kernel's own internal memory space into the buffer provided by application Y. This process means that most network traffic must be copied across the system's main memory bus at least twice (once when the host adapter uses DMA to put the data into the kernel-provided memory buffer, and again when the kernel moves the data to the application's memory buffer) and it also means the computer must execute a number of context switches to switch between kernel context and application Y context. Both of these things impose extremely high CPU loads on the system when network traffic is flowing at very high rates.

The RDMA protocol allows the host adapter in the machine to know when a packet comes in from the network, just which application should receive that packet, and just where in the application's memory space it should go. Instead of sending the packet to the kernel to be processed and then copied into the user application's memory, it places the contents of the packet directly in the application's buffer without any further intervention necessary. This tremendously reduces the overhead of high speed network communications. However, it cannot be accomplished using the standard Berkeley Sockets API that most IP networking applications are built upon, so it must provide its own API, the InfiniBand Verbs API, and applications must be ported to this API before they can use RDMA technology directly.

Red Hat Enterprise Linux 7 supports both the InfiniBand hardware and the InfiniBand Verbs API. In addition, there are two additional supported technologies that allow the InfiniBand Verbs API to be utilized on non-InfiniBand hardware. They are iWARP (Internet Wide Area RDMA Protocol) and RoCE/IBoE (RDMA over Converged Ethernet, which was later renamed to InfiniBand over Ethernet). Both of these technologies have a normal IP network link layer as their underlying technology, and so the majority of their configuration is actually covered in the [Chapter 2, Configure IP Networking](#) chapter of this document. For the most part, once their IP networking features are properly configured, their RDMA features are all automatic and will show up as long as the proper drivers for the hardware are installed. The kernel drivers are always included with each kernel Red Hat provides, however the user-space drivers must be installed manually if the InfiniBand package group was not selected at machine install time.

These are the necessary user-space packages:

iWARP

Chelsio hardware – `libcxgb3` or `libcxgb4` depending on version of hardware

RoCE/IBoE

Mellanox hardware – `libmlx4` or `libmlx5` depending on hardware version.

If you are using Priority Flow Control (PFC) and mlx4-based cards, then edit `/etc/modprobe.d/mlx4.conf` to instruct the driver which packet priority is configured for the “no-drop” service on the Ethernet switches the cards are plugged into and rebuild the `initramfs`

to include the modified file. Newer mlx5-based cards auto-negotiate PFC settings with the switch and do not need any module option to inform them of the “no-drop” priority or priorities.

To set the Mellanox cards to use one or both ports in Ethernet mode, see [Section 9.3.4, “Configuring Mellanox cards for Ethernet operation”](#).

With these driver packages installed (in addition to the normal RDMA packages typically installed for any InfiniBand installation), a user should be able to utilize most of the normal RDMA applications to test and see RDMA protocol communication taking place on their adapters. However, not all of the programs included in Red Hat Enterprise Linux 7 will properly support iWARP or RoCE/IBoE devices. This is because the connection establishment protocol on iWARP in particular is different than it is on real InfiniBand link-layer connections. If the program in question uses the `librdmacm` connection management library, it will handle the differences between iWARP and InfiniBand silently and the program should work. If the application tries to do its own connection management, then it must specifically support iWARP or else it will not work.

9.2. INFINIBAND AND RDMA RELATED SOFTWARE PACKAGES

Because RDMA applications are so different from Berkeley Sockets based applications, and from normal IP networking, most applications that are used on an IP network cannot be used directly on an RDMA network. Red Hat Enterprise Linux 7 comes with a number of different software packages for RDMA network administration, testing and debugging, high level software development APIs, and performance analysis.

In order to utilize these networks, some or all of these packages need to be installed (this list is not exhaustive, but does cover the most important packages related to RDMA).

Required packages:

- **rdma** – responsible for kernel initialization of the RDMA stack.
- **libibverbs** – provides the InfiniBand Verbs API.
- **opensm** – subnet manager (only required on one machine, and only if there is no subnet manager active on the fabric).
- **user space driver for installed hardware** – one or more of: `infinipath-psm`, `libcxgb3`, `libcxgb4`, `libehca`, `libipathverbs`, `libmthca`, `libmlx4`, `libmlx5`, `libnes`, and `libocrdma`. Note that `libehca` is only available for IBM Power Systems servers.

Recommended packages:

- **librdmacm**, **librdmacm-utils**, and **ibacm** – Connection management library that is aware of the differences between InfiniBand, iWARP, and RoCE and is able to properly open connections across all of these hardware types, some simple test programs for verifying the operation of the network, and a caching daemon that integrates with the library to make remote host resolution faster in large clusters.
- **libibverbs-utils** – Simple Verbs based programs for querying the installed hardware and verifying communications over the fabric.
- **infiniband-diags** and **ibutils** – Provide a number of useful debugging tools for InfiniBand fabric management. These provide only very limited functionality on iWARP or RoCE as most of the tools work at the InfiniBand link layer, not the Verbs API layer.

- **perftest** and **qperf** – Performance testing applications for various types of RDMA communications.

Optional packages:

These packages are available in the Optional channel. Before installing packages from the Optional channel, see [Scope of Coverage Details](#). Information on subscribing to the Optional channel can be found in the Red Hat Knowledgebase solution [How to access Optional and Supplementary channels](#).

- **dapl**, **dapl-devel**, and **dapl-utils** – Provide a different API for RDMA than the Verbs API. There is both a runtime component and a development component to these packages.
- **openmpi**, **mvapich2**, and **mvapich2-psm** – MPI stacks that have the ability to use RDMA communications. User-space applications writing to these stacks are not necessarily aware that RDMA communications are taking place.

9.3. CONFIGURING THE BASE RDMA SUBSYSTEM

Startup of the **rdma** service is automatic. When RDMA capable hardware, whether InfiniBand or iWARP or RoCE/IBoE is detected, **udev** instructs **systemd** to start the **rdma** service.

```
~]# systemctl status rdma
● rdma.service - Initialize the iWARP/InfiniBand/RDMA stack in the kernel
   Loaded: loaded (/usr/lib/systemd/system/rdma.service; disabled; vendor
  preset: disabled)
   Active: inactive (dead)
     Docs: file:/etc/rdma/rdma.conf
```

Users need not enable the **rdma** service, but they can if they want to force it on all the time. To do that, enter the following command as root:

```
~]# systemctl enable rdma
```

9.3.1. Configuration of the **rdma.conf** file

The **rdma** service reads **/etc/rdma/rdma.conf** to find out which kernel-level and user-level RDMA protocols the administrator wants to be loaded by default. Users should edit this file to turn various drivers on or off.

The various drivers that can be enabled and disabled are:

- **IPoIB** – This is an **IP** network emulation layer that allows **IP** applications to run over InfiniBand networks.
- **SRP** – This is the SCSI Request Protocol. It allows a machine to mount a remote drive or drive array that is exported through the **SRP** protocol on the machine as though it were a local hard disk.
- **SRPT** – This is the target mode, or server mode, of the **SRP** protocol. This loads the kernel support necessary for exporting a drive or drive array for other machines to mount as though it were local on their machine. Further configuration of the target mode support is required before any devices will actually be exported. See the documentation in the **targetd** and **targetcli** packages for further information.

- **ISER** – This is a low-level driver for the general iSCSI layer of the Linux kernel that provides transport over InfiniBand networks for iSCSI devices.
- **RDS** – This is the Reliable Datagram Service in the Linux kernel. It is not enabled in Red Hat Enterprise Linux 7 kernels and so cannot be loaded.

9.3.2. Usage of 70-persistent-ipoib.rules

The `rdma` package provides the file `/etc/udev.d/rules.d/70-persistent-ipoib.rules`. This `udev` rules file is used to rename IPoIB devices from their default names (such as `ib0` and `ib1`) to more descriptive names. Users must edit this file to change how their devices are named. First, find out the GUID address for the device to be renamed:

```
~]$ ip link show ib0
8: ib0: >BROADCAST,MULTICAST,UP,LOWER_UP< mtu 65520 qdisc pfifo_fast state
UP mode DEFAULT qlen 256
    link/infiniband
    80:00:02:00:fe:80:00:00:00:00:00:00:f4:52:14:03:00:7b:cb:a1 brd
    00:ff:ff:ff:ff:12:40:1b:ff:ff:00:00:00:00:00:00:ff:ff:ff:ff
```

Immediately after `link/infiniband` is the 20 byte hardware address for the IPoIB interface. The final 8 bytes of the address, marked in bold above, is all that is required to make a new name. Users can make up whatever naming scheme suits them. For example, use a `device_fabric` naming convention such as `mlx4_ib0` if a `mlx4` device is connected to an `ib0` subnet fabric. The only thing that is not recommended is to use the standard names, like `ib0` or `ib1`, as these can conflict with the kernel assigned automatic names. Next, add an entry in the rules file. Copy the existing example in the rules file, replace the 8 bytes in the `ATTR{address}` entry with the highlighted 8 bytes from the device to be renamed, and enter the new name to be used in the `NAME` field.

9.3.3. Relaxing memlock restrictions for users

RDMA communications require that physical memory in the computer be pinned (meaning that the kernel is not allowed to swap that memory out to a paging file in the event that the overall computer starts running short on available memory). Pinning memory is normally a very privileged operation. In order to allow users other than `root` to run large RDMA applications, it will likely be necessary to increase the amount of memory that non-`root` users are allowed to pin in the system. This is done by adding a file in the `/etc/security/limits.d/` directory with contents such as the following:

```
~]$ more /etc/security/limits.d/rdma.conf
# configuration for rdma tuning
*          soft      memlock          unlimited
*          hard      memlock          unlimited
# rdma tuning end
```

9.3.4. Configuring Mellanox cards for Ethernet operation

Certain hardware from Mellanox is capable of running in either InfiniBand or Ethernet mode. These cards generally default to InfiniBand. Users can set the cards to Ethernet mode. There is currently support for setting the mode only on ConnectX family hardware (which uses either the `mlx5` or `mlx4` driver).

To configure Mellanox `mlx5` cards, use the `mstconfig` program from the `mstflint` package. For more details, see the [Configuring Mellanox `mlx5` cards in Red Hat Enterprise Linux 7](#) Knowledge Base article on the Red Hat Customer Portal.

To configure Mellanox mlx4 cards, use **mstconfig** to set the port types on the card as described in [the Knowledge Base article](#). If **mstconfig** does not support your card, edit the `/etc/rdma/mlx4.conf` file and follow the instructions in that file to set the port types properly for RoCE/IBoE usage. In this case is also necessary to rebuild the `initramfs` to make sure the updated port settings are copied into the `initramfs`.

Once the port type has been set, if one or both ports are set to Ethernet and **mstconfig** was not used to set the port types, then users might see this message in their logs:

```
mlx4_core 0000:05:00.0: Requested port type for port 1 is not supported on
this HCA
```

This is normal and does not affect operation. The script responsible for setting the port type has no way of knowing when the driver has finished switching port 2 to the requested type internally, and from the time that the script issues a request for port 2 to switch until that switch is complete, the attempts to set port 1 to a different type get rejected. The script retries until the command succeeds or until a timeout has passed indicating that the port switch never completed.

9.3.5. Connecting to a Remote Linux SRP Target

The SCSI RDMA Protocol (SRP) is a network protocol that enables a system to use RDMA to access SCSI devices that are attached to another system. To allow an SRP initiator to connect an SRP target on the SRP target side, you must add an access control list (ACL) entry for the host channel adapter (HCA) port used in the initiator.

ACL IDs for HCA ports are not unique. The ACL IDs depend on the GID format of the HCAs. HCAs that use the same driver, for example `ib_qib`, can have different format of GIDs. The ACL ID also depends on how you initiate the connection request.

Connecting to a Remote Linux SRP Target: High-Level Overview

1. Prepare the target side:

1. Create storage back end. For example get the `/dev/sdc1` partition:

```
/> /backstores/block create vol1 /dev/sdc1
```

- ## 2. Create an SRP target:

```
/> /srpt create 0xfe80000000000000001175000077dd7e
```

3. Create a LUN based on the back end created in step a:

```
/> /srpt/ib.fe800000000000000001175000077dd7e/luns create  
/backstores/block/vol1
```

- #### 4. Create a Node ACL for the remote SRP client:

```
/> /srpt/ib.fe80000000000000001175000077dd7e/acs create
0x7edd770000751100001175000077d708
```

Note that the Node ACL is different for `srp_daemon` and `ibsrpdm`.

2. Initiate an SRP connection with `srp_daemon` or `ibsrpdm` for the client side:

```
[root@initiator]# srp_daemon -e -n -i qib0 -p 1 -R 60 &
```

```
[root@initiator]# ibsrpdm -c -d /dev/infiniband/umad0 >
/sys/class/infiniband_srp/srp-qib0-1/add_target
```

3. Optional. It is recommended to verify the SRP connection with different tools, such as `lsscsi` or `dmesg`.

Procedure 9.1. Connecting to a Remote Linux SRP Target with `srp_daemon` or `ibsrpdm`

1. Use the `ibstat` command on the target to determine the **State** and **Port GUID** values. The HCA must be in **Active** state. The ACL ID is based on the **Port GUID**:

```
[root@target]# ibstat
CA 'qib0'
CA type: InfiniPath_QLE7342
Number of ports: 1
Firmware version:
Hardware version: 2
Node GUID: 0x001175000077dd7e
System image GUID: 0x001175000077dd7e
Port 1:
  State: Active
  Physical state: LinkUp
  Rate: 40
  Base lid: 1
  LMC: 0
  SM lid: 1
  Capability mask: 0x0769086a
  Port GUID: 0x001175000077dd7e
  Link layer: InfiniBand
```

2. Get the SRP target ID, which is based on the GUID of the HCA port. Note that you need a dedicated disk partition as a back end for a SRP target, for example `/dev/sdc1`. The following command replaces the default prefix of `fe80`, removes the colon, and adds the new prefix to the remainder of the string:

```
[root@target]# ibstatus | grep '<default-gid>' | sed -e 's/<default-
gid>:/' -e 's:/' -e 's:/' | grep 001175000077dd7e
fe8000000000000000000000000000001175000077dd7e
```

3. Use the `targetcli` tool to create the LUN `vol1` on the block device, create an SRP target, and export the LUN:

```
[root@target]# targetcli

/> /backstores/block create vol1 /dev/sdc1
Created block storage object vol1 using /dev/sdc1.
/> /srpt create 0xfe8000000000000000000000000000001175000077dd7e
Created target ib.fe8000000000000000000000000000001175000077dd7e.
/> /srpt/ib.fe8000000000000000000000000000001175000077dd7e/luns create
/backstores/block/vol1
```

```

Created LUN 0.
/> ls /
o- /
.....
..... [...]
    o- backstores
.....
[...]
    | o- block .....
[Storage Objects: 1]
    | | o- vol1 ..... [/dev/sdc1 (77.8GiB)
write-thru activated]
    | o- fileio .....
[Storage Objects: 0]
    | o- pscsi .....
[Storage Objects: 0]
    | o- ramdisk .....
[Storage Objects: 0]
    o- iscsi
.....
[Targets: 0]
    o- loopback
.....
[Targets: 0]
    o- srpt
.....
[Targets: 1]
    o- ib.fe80000000000000001175000077dd7e
..... [no-gen-acls]
    o- acls
.....
[ACLs: 0]
    o- luns
.....
[LUNs: 1]
    o- lun0 .....
[block/vol1 (/dev/sdc1)]
/>

```

4. Use the **ibstat** command on the initiator to check if the state is **Active** and determine the **Port GUID**:

```

[root@initiator]# ibstat
CA 'qib0'
CA type: InfiniPath_QLE7342
Number of ports: 1
Firmware version:
Hardware version: 2
Node GUID: 0x001175000077d708
System image GUID: 0x001175000077d708
Port 1:
  State: Active
  Physical state: LinkUp
  Rate: 40
  Base lid: 2
  LMC: 0

```

```
SM lid: 1
Capability mask: 0x07690868
Port GUID: 0x001175000077d708
Link layer: InfiniBand
```

5. Use the following command to scan without connecting to a remote SRP target. The target GUID shows that the initiator had found remote target. The ID string shows that the remote target is a Linux software target (**ib_srpt.ko**).

```
[root@initiator]# srp_daemon -a -o
IO Unit Info:
  port LID:          0001
  port GUID:         fe800000000000000000001175000077dd7e
  change ID:         0001
  max controllers:   0x10

  controller[ 1]
    GUID:            001175000077dd7e
    vendor ID:       000011
    device ID:       007322
    IO class :       0100
    ID:              Linux SRP target
    service entries: 1
                    service[ 0]: 001175000077dd7e /
SRP.T10:001175000077dd7e
```

6. To verify the SRP connection, use the **lsscsi** command to list SCSI devices and compare the **lsscsi** output before and after the initiator connects to target.

```
[root@initiator]# lsscsi
[0:0:10:0]    disk      IBM-ESXS ST9146803SS      B53C   /dev/sda
```

7. To connect to a remote target without configuring a valid ACL for the initiator port, which is expected to fail, use the following commands for **srp_daemon** or **ibsrpdm**:

```
[root@initiator]# srp_daemon -e -n -i qib0 -p 1 -R 60 &
[1] 4184
```

```
[root@initiator]# ibsrpdm -c -d /dev/infiniband/umad0 >
/sys/class/infiniband_srp/srp-qib0-1/add_target
```

8. The output of the **dmesg** shows why the SRP connection operation failed. In a later step, the **dmesg** command on the target side is used to make the situation clear.

```
[root@initiator]# dmesg -c
[ 1230.059652] scsi host5: ib_srp: REJ received
[ 1230.059659] scsi host5: ib_srp: SRP LOGIN from
fe80:0000:0000:0000:0011:7500:0077:d708 to
fe80:0000:0000:0000:0011:7500:0077:dd7e REJECTED, reason 0x00010006
[ 1230.073792] scsi host5: ib_srp: Connection 0/2 failed
[ 1230.078848] scsi host5: ib_srp: Sending CM DREQ failed
```

9. Because of failed LOGIN, the output of the **lsscsi** command is the same as in the earlier step.

```
[root@initiator]# lsscsi
[0:0:10:0] disk IBM-ESXS ST9146803SS B53C /dev/sda
```

10. Using the **dmesg** on the target side (**ib_srpt.ko**) provides an explanation of why LOGIN failed. Also, the output contains the valid ACL ID provided by **srp_daemon**:
0x7edd770000751100001175000077d708.

```
[root@target]# dmesg
[ 1200.303001] ib_srpt Received SRP_LOGIN_REQ with i_port_id
0x7edd770000751100:0x1175000077d708, t_port_id
0x1175000077dd7e:0x1175000077dd7e and it_iu_len 260 on port 1
(guid=0xfe80000000000000:0x1175000077dd7e)
[ 1200.322207] ib_srpt Rejected login because no ACL has been
configured yet for initiator 0x7edd770000751100001175000077d708.
```

11. Use the **targetcli** tool to add a valid ACL:

```
[root@target]# targetcli
targetcli shell version 2.1.fb41
Copyright 2011-2013 by Datera, Inc and others.
For help on commands, type 'help'.

/> /srpt/ib.fe80000000000000000000001175000077dd7e/acls create
0x7edd770000751100001175000077d708
Created Node ACL for ib.7edd770000751100001175000077d708
Created mapped LUN 0.
```

12. Verify the SRP LOGIN operation:

- a. Wait for 60 seconds to allow **srp_daemon** to re-try logging in:

```
[root@initiator]# sleep 60
```

- b. Verify the SRP LOGIN operation:

```
[root@initiator]# lsscsi
[0:0:10:0] disk IBM-ESXS ST9146803SS B53C /dev/sda
[7:0:0:0] disk LIO-ORG vol1 4.0 /dev/sdb
```

- c. For a kernel log of SRP target discovery, use:

```
[root@initiator]# dmesg -c
[ 1354.182072] scsi host7: SRP.T10:001175000077DD7E
[ 1354.187258] scsi 7:0:0:0: Direct-Access LIO-ORG vol1
4.0 PQ: 0 ANSI: 5
[ 1354.208688] scsi 7:0:0:0: alua: supports implicit and explicit
TPGS
[ 1354.215698] scsi 7:0:0:0: alua: port group 00 rel port 01
[ 1354.221409] scsi 7:0:0:0: alua: port group 00 state A non-
preferred supports TOLUSNA
[ 1354.229147] scsi 7:0:0:0: alua: Attached
[ 1354.233402] sd 7:0:0:0: Attached scsi generic sg1 type 0
[ 1354.233694] sd 7:0:0:0: [sdb] 163258368 512-byte logical
```

```

blocks: (83.5 GB/77.8 GiB)
[ 1354.235127] sd 7:0:0:0: [sdb] Write Protect is off
[ 1354.235128] sd 7:0:0:0: [sdb] Mode Sense: 43 00 00 08
[ 1354.235550] sd 7:0:0:0: [sdb] Write cache: disabled, read
cache: enabled, doesn't support DPO or FUA
[ 1354.255491] sd 7:0:0:0: [sdb] Attached SCSI disk
[ 1354.265233] scsi host7: ib_srp: new target: id_ext
001175000077dd7e ioc_guid 001175000077dd7e pkey ffff service_id
001175000077dd7e sgid fe80:0000:0000:0000:0011:7500:0077:d708
dgid fe80:0000:0000:0000:0011:7500:0077:dd7e
xyx

```

9.4. CONFIGURING THE SUBNET MANAGER

9.4.1. Determining Necessity

Most InfiniBand switches come with an embedded subnet manager. However, if a more up to date subnet manager is required than the one in the switch firmware, or if more complete control than the switch manager allows is required, Red Hat Enterprise Linux 7 includes the **opensm** subnet manager. All InfiniBand networks **must** have a subnet manager running for the network to function. This is true even when doing a simple network of two machines with no switch and the cards are plugged in back to back, a subnet manager is required for the link on the cards to come up. It is possible to have more than one, in which case one will act as master, and any other subnet managers will act as slaves that will take over should the master subnet manager fail.

9.4.2. Configuring the opensm master configuration file

The **opensm** program keeps its master configuration file in `/etc/rdma/opensm.conf`. Users may edit this file at any time and edits will be kept on upgrade. There is extensive documentation of the options in the file itself. However, for the two most common edits needed, setting the GUID to bind to and the PRIORITY to run with, it is highly recommended that the **opensm.conf** file is not edited but instead edit `/etc/sysconfig/opensm`. If there are no edits to the base `/etc/rdma/opensm.conf` file, it will get upgraded whenever the **opensm** package is upgraded. As new options are added to this file regularly, this makes it easier to keep the current configuration up to date. If the **opensm.conf** file has been changed, then on upgrade, it might be necessary to merge new options into the edited file.

9.4.3. Configuring the opensm startup options

The options in the `/etc/sysconfig/opensm` file control how the subnet manager is actually started, as well as how many copies of the subnet manager are started. For example, a dual port InfiniBand card, with each port plugged into physically separate networks, will need a copy of the subnet manager running on each port. The **opensm** subnet manager will only manage one subnet per instance of the application and must be started once for each subnet that needs to be managed. In addition, if there is more than one **opensm** server, then set the priorities on each server to control which are to be slaves and which are to be master.

The file `/etc/sysconfig/opensm` is used to provide a simple means to set the priority of the subnet manager and to control which GUID the subnet manager binds to. There is an extensive explanation of the options in the `/etc/sysconfig/opensm` file itself. Users need only read and follow the directions in the file itself to enable failover and multifabric operation of **opensm**.

9.4.4. Creating a P_Key definition

By default, `opensm.conf` looks for the file `/etc/rdma/partitions.conf` to get a list of partitions to create on the fabric. All fabrics must contain the `0x7fff` subnet, and all switches and all hosts must belong to that fabric. Any other partition can be created in addition to that, and all hosts and all switches do not have to be members of these additional partitions. This allows an administrator to create subnets akin to Ethernet's VLANs on InfiniBand fabrics. If a partition is defined with a given speed, such as 40 Gbps, and there is a host on the network unable to do 40 Gbps, then that host will be unable to join the partition even if it has permission to do so as it will be unable to match the speed requirements, therefore it is recommended that the speed of a partition be set to the slowest speed of any host with permission to join the partition. If a faster partition for some subset of hosts is required, create a different partition with the higher speed.

The following partition file would result in a default `0x7fff` partition at a reduced speed of 10 Gbps, and a partition of `0x0002` with a speed of 40 Gbps:

```
~]$ more /etc/rdma/partitions.conf
# For reference:
# IPv4 IANA reserved multicast addresses:
#   http://www.iana.org/assignments/multicast-addresses/multicast-
addresses.txt
# IPv6 IANA reserved multicast addresses:
#   http://www.iana.org/assignments/ipv6-multicast-addresses/ipv6-
multicast-addresses.xml
#
# mtu =
#   1 = 256
#   2 = 512
#   3 = 1024
#   4 = 2048
#   5 = 4096
#
# rate =
#   2 = 2.5 GBit/s
#   3 = 10 GBit/s
#   4 = 30 GBit/s
#   5 = 5 GBit/s
#   6 = 20 GBit/s
#   7 = 40 GBit/s
#   8 = 60 GBit/s
#   9 = 80 GBit/s
#  10 = 120 GBit/s

Default=0x7fff, rate=3, mtu=4, scope=2, defmember=full:
    ALL, ALL_SWITCHES=full;
Default=0x7fff, ipoib, rate=3, mtu=4, scope=2:
    mgid=ff12:401b::ffff:ffff      # IPv4 Broadcast address
    mgid=ff12:401b::1             # IPv4 All Hosts group
    mgid=ff12:401b::2             # IPv4 All Routers group
    mgid=ff12:401b::16            # IPv4 IGMP group
    mgid=ff12:401b::fb            # IPv4 mDNS group
    mgid=ff12:401b::fc            # IPv4 Multicast Link Local Name
Resolution group
    mgid=ff12:401b::101           # IPv4 NTP group
    mgid=ff12:401b::202           # IPv4 Sun RPC
    mgid=ff12:601b::1             # IPv6 All Hosts group
    mgid=ff12:601b::2             # IPv6 All Routers group
    mgid=ff12:601b::16            # IPv6 MLDv2-capable Routers
```



```

group
    mgid=ff12:601b::fb          # IPv6 mDNS group
    mgid=ff12:601b::101        # IPv6 NTP group
    mgid=ff12:601b::202        # IPv6 Sun RPC group
    mgid=ff12:601b::1:3        # IPv6 Multicast Link Local Name
Resolution group
    ALL=full, ALL_SWITCHES=full;

ib0_2=0x0002, rate=7, mtu=4, scope=2, defmember=full:
    ALL, ALL_SWITCHES=full;
ib0_2=0x0002, ipoib, rate=7, mtu=4, scope=2:
    mgid=ff12:401b::ffff:ffff  # IPv4 Broadcast address
    mgid=ff12:401b::1          # IPv4 All Hosts group
    mgid=ff12:401b::2          # IPv4 All Routers group
    mgid=ff12:401b::16         # IPv4 IGMP group
    mgid=ff12:401b::fb         # IPv4 mDNS group
    mgid=ff12:401b::fc         # IPv4 Multicast Link Local Name
Resolution group
    mgid=ff12:401b::101        # IPv4 NTP group
    mgid=ff12:401b::202        # IPv4 Sun RPC
    mgid=ff12:601b::1          # IPv6 All Hosts group
    mgid=ff12:601b::2          # IPv6 All Routers group
    mgid=ff12:601b::16         # IPv6 MLDv2-capable Routers
group
    mgid=ff12:601b::fb          # IPv6 mDNS group
    mgid=ff12:601b::101        # IPv6 NTP group
    mgid=ff12:601b::202        # IPv6 Sun RPC group
    mgid=ff12:601b::1:3        # IPv6 Multicast Link Local Name
Resolution group
    ALL=full, ALL_SWITCHES=full;

```

9.4.5. Enabling opensm

Users need to enable the **opensm** service as it is not enabled by default when installed. Issue the following command as **root**:

```
~]# systemctl enable opensm
```

9.5. TESTING EARLY INFINIBAND RDMA OPERATION



NOTE

This section applies only to InfiniBand devices. Since iWARP and RoCE/IBoE devices are **IP** based devices, users should proceed to the section on testing RDMA operations once IPoIB has been configured and the devices have **IP** addresses.

Once the **rdma** service is enabled, and the **opensm** service (if needed) is enabled, and the proper user-space library for the specific hardware has been installed, user space **rdma** operation should be possible. Simple test programs from the **libibverbs-utils** package are helpful in determining that RDMA operations are working properly. The **ibv_devices** program will show which devices are present in the system and the **ibv_devinfo** command will give detailed information about each device. For example:

```
~]$ ibv_devices
```

```

device                node GUID
-----
mlx4_0                0002c903003178f0
mlx4_1                f4521403007bcba0
~]$ ibv_devinfo -d mlx4_1
hca_id: mlx4_1
  transport:          InfiniBand (0)
  fw_ver:             2.30.8000
  node_guid:          f452:1403:007b:cba0
  sys_image_guid:     f452:1403:007b:cba3
  vendor_id:          0x02c9
  vendor_part_id:     4099
  hw_ver:             0x0
  board_id:           MT_1090120019
  phys_port_cnt:      2
    port: 1
      state:           PORT_ACTIVE (4)
      max_mtu:         4096 (5)
      active_mtu:      2048 (4)
      sm_lid:          2
      port_lid:        2
      port_lmc:        0x01
      link_layer:      InfiniBand
    port: 2
      state:           PORT_ACTIVE (4)
      max_mtu:         4096 (5)
      active_mtu:      4096 (5)
      sm_lid:          0
      port_lid:        0
      port_lmc:        0x00
      link_layer:      Ethernet
~]$ ibstat mlx4_1
CA 'mlx4_1'
  CA type: MT4099
  Number of ports: 2
  Firmware version: 2.30.8000
  Hardware version: 0
  Node GUID: 0xf4521403007bcba0
  System image GUID: 0xf4521403007bcba3
  Port 1:
    State: Active
    Physical state: LinkUp
    Rate: 56
    Base lid: 2
    LMC: 1
    SM lid: 2
    Capability mask: 0x0251486a
    Port GUID: 0xf4521403007bcba1
    Link layer: InfiniBand
  Port 2:
    State: Active
    Physical state: LinkUp
    Rate: 40
    Base lid: 0
    LMC: 0

```

```
SM lid: 0
Capability mask: 0x04010000
Port GUID: 0xf65214fffe7bcba2
Link layer: Ethernet
```

The `ibv_devinfo` and `ibstat` commands output slightly different information (such as port MTU exists in `ibv_devinfo` but not in `ibstat` output, and the Port GUID exists in `ibstat` output but not in `ibv_devinfo` output), and a few things are named differently (for example, the Base *local identifier* (LID) in `ibstat` output is the same as the `port_lid` output of `ibv_devinfo`)

Simple ping programs, such as `ibping` from the `infiniband-diags` package, can be used to test RDMA connectivity. The `ibping` program uses a client-server model. You must first start an `ibping` server on one machine, then run `ibping` as a client on another machine and tell it to connect to the `ibping` server. Since we are wanting to test the base RDMA capability, we need to use an RDMA specific address resolution method instead of IP addresses for specifying the server.

On the server machine, the user can use the `ibv_devinfo` and `ibstat` commands to print out the `port_lid` (or Base lid) and the Port GUID of the port they want to test (assuming port 1 of the above interface, the `port_lid`/Base LID is 2 and Port GUID is `0xf4521403007bcba1`). Then start `ibping` with the necessary options to bind specifically to the card and port to be tested, and also specifying `ibping` should run in server mode. You can see the available options to `ibping` by passing `-?` or `--help`, but in this instance we will need either the `-S` or `--Server` option and for binding to the specific card and port we will need either `-C` or `--Ca` and `-P` or `--Port`. Note: port in this instance does not denote a network port number, but denotes the physical port number on the card when using a multi-port card. To test connectivity to the RDMA fabric using, for example, the second port of a multi-port card, requires telling `ibping` to bind to port 2 on the card. When using a single port card, or testing the first port on a card, this option is not needed. For example:

```
~]$ ibping -S -C mlx4_1 -P 1
```

Then change to the client machine and run `ibping`. Make note of either the port GUID of the port the server `ibping` program is bound to, or the *local identifier* (LID) of the port the server `ibping` program is bound to. Also, take note which card and port in the client machine is physically connected to the same network as the card and port that was bound to on the server. For example, if the second port of the first card on the server was bound to, and that port is connected to a secondary RDMA fabric, then on the client specify whichever card and port are necessary to also be connected to that secondary fabric. Once these things are known, run the `ibping` program as a client and connect to the server using either the port LID or GUID that was collected on the server as the address to connect to. For example:

```
~]$ ibping -c 10000 -f -C mlx4_0 -P 1 -L 2
--- rdma-host.example.com.(none) (Lid 2) ibping statistics ---
10000 packets transmitted, 10000 received, 0% packet loss, time 816 ms
rtt min/avg/max = 0.032/0.081/0.446 ms
```

or

```
~]$ ibping -c 10000 -f -C mlx4_0 -P 1 -G 0xf4521403007bcba1 \
--- rdma-host.example.com.(none) (Lid 2) ibping statistics ---
10000 packets transmitted, 10000 received, 0% packet loss, time 769 ms
rtt min/avg/max = 0.027/0.076/0.278 ms
```

This outcome verifies that end to end RDMA communications are working for user space applications.

The following error may be encountered:

-

```
~]$ ibv_devinfo
libibverbs: Warning: no userspace device-specific driver found for
/sys/class/infiniband_verbs/uverbs0
No IB devices found
```

This error indicates that the necessary user-space library is not installed. The administrator will need to install one of the user-space libraries (as appropriate for their hardware) listed in section [Section 9.2, “InfiniBand and RDMA related software packages”](#). On rare occasions, this can happen if a user installs the wrong arch type for the driver or for `libibverbs`. For example, if `libibverbs` is of arch `x86_64`, and `libmlx4` is installed but is of type `i686`, then this error can result.



NOTE

Many sample applications prefer to use host names or addresses instead of LIDs to open communication between the server and client. For those applications, it is necessary to set up IPoIB before attempting to test end-to-end RDMA communications. The `ibping` application is unusual in that it will accept simple LIDs as a form of addressing, and this allows it to be a simple test that eliminates possible problems with IPoIB addressing from the test scenario and therefore gives us a more isolated view of whether or not simple RDMA communications are working.

9.6. CONFIGURING IPOIB

9.6.1. Understanding the role of IPoIB

As mentioned in [Section 1.2, “IP Networks versus non-IP Networks”](#), most networks are **IP** networks. InfiniBand is not. The role of IPoIB is to provide an **IP** network emulation layer on top of InfiniBand RDMA networks. This allows existing applications to run over InfiniBand networks unmodified. However, the performance of those applications is considerably lower than if the application were written to use RDMA communication natively. Since most InfiniBand networks have some set of applications that really must get all of the performance they can out of the network, and then some other applications for which a degraded rate of performance is acceptable if it means that the application does not need to be modified to use RDMA communications, IPoIB is there to allow those less critical applications to run on the network as they are.

Because both iWARP and RoCE/IBoE networks are actually **IP** networks with RDMA layered on top of their **IP** link layer, they have no need of IPoIB. As a result, the kernel will refuse to create any IPoIB devices on top of iWARP or RoCE/IBoE RDMA devices.

9.6.2. Understanding IPoIB communication modes

IPoIB devices can be configured to run in either datagram or connected mode. The difference is in what type of queue pair the IPoIB layer attempts to open with the machine at the other end of the communication. For datagram mode, an unreliable, disconnected queue pair is opened. For connected mode, a reliable, connected queue pair is opened.

When using datagram mode, the unreliable, disconnected queue pair type does not allow any packets larger than the InfiniBand link-layer’s MTU. The IPoIB layer adds a 4 byte IPoIB header on top of the **IP** packet being transmitted. As a result, the IPoIB MTU must be 4 bytes less than the InfiniBand link-layer MTU. As 2048 is a common InfiniBand link-layer MTU, the common IPoIB device MTU in datagram mode is 2044.

When using connected mode, the reliable, connected queue pair type allows messages that are larger than the InfiniBand link-layer MTU and the host adapter handles packet segmentation and reassembly

at each end. As a result, there is no size limit imposed on the size of IPoIB messages that can be sent by the InfiniBand adapters in connected mode. However, there is still the limitation that an IP packet only has a 16 bit size field, and is therefore limited to 65535 as the maximum byte count. The maximum allowed MTU is actually smaller than that because we have to account for various TCP/IP headers that must also fit in that size. As a result, the IPoIB MTU in connected mode is capped at 65520 in order to make sure there is sufficient room for all needed TCP headers.

The connected mode option generally has higher performance, but it also consumes more kernel memory. Because most systems care more about performance than memory consumption, connected mode is the most commonly used mode.

However, if a system is configured for connected mode, it must still send multicast traffic in datagram mode (the InfiniBand switches and fabric cannot pass multicast traffic in connected mode) and it will also fall back to datagram mode when communicating with any hosts not configured for connected mode. Administrators should be aware that if they intend to run programs that send multicast data, and those programs try to send multicast data up to the maximum MTU on the interface, then it is necessary to configure the interface for datagram operation or find some way to configure the multicast application to cap their packet send size at a size that will fit in datagram sized packets.

9.6.3. Understanding IPoIB hardware addresses

IPoIB devices have a 20 byte hardware addresses. The deprecated utility `ifconfig` is unable to read all 20 bytes and should never be used to try and find the correct hardware address for an IPoIB device. The `ip` utilities from the `iproute` package work properly.

The first 4 bytes of the IPoIB hardware address are flags and the queue pair number. The next 8 bytes are the subnet prefix. When the IPoIB device is first created, it will have the default subnet prefix of `0xfe:80:00:00:00:00:00:00`. The device will use the default subnet prefix (`0xfe80000000000000`) until it makes contact with the subnet manager, at which point it will reset the subnet prefix to match what the subnet manager has configured it to be. The final 8 bytes are the GUID address of the InfiniBand port that the IPoIB device is attached to. Because both the first 4 bytes and the next 8 bytes can change from time to time, they are not used or matched against when specifying the hardware address for an IPoIB interface. [Section 9.3.2, “Usage of 70-persistent-ipoib.rules”](#) explains how to derive the address by leaving the first 12 bytes out of the `ATTR{address}` field in the `udev` rules file so that device matching will happen reliably. When configuring IPoIB interfaces, the `HWADDR` field of the configuration file can contain all 20 bytes, but only the last 8 bytes are actually used to match against and find the hardware specified by a configuration file. However, if the `TYPE=InfiniBand` entry is not spelled correctly in the device configuration file, and `ifup-ib` is not the actual script used to open the IPoIB interface, then an error about the system being unable to find the hardware specified by the configuration will be issued. For IPoIB interfaces, the `TYPE=` field of the configuration file must be either `InfiniBand` or `infiniband` (the entry is case sensitive, but the scripts will accept these two specific spellings).

9.6.4. Understanding InfiniBand P_Key subnets

An InfiniBand fabric can be logically segmented into virtual subnets by the use of different `P_Key` subnets. This is highly analogous to using VLANs on Ethernet interfaces. All switches and hosts must be a member of the default `P_Key` subnet, but administrators can create additional subnets and limit members of those subnets to subsets of the hosts or switches in the fabric. A `P_Key` subnet must be defined by the subnet manager before a host can use it. See [section 9.4.4, “Creating a P_Key definition”](#) for information on how to define a `P_Key` subnet using the `opensm` subnet manager. For IPoIB interfaces, once a `P_Key` subnet has been created, we can create additional IPoIB configuration files specifically for those `P_Key` subnets. Just like VLAN interfaces on Ethernet devices, each IPoIB interface will behave as though it were on a completely different fabric from other IPoIB interfaces that share the same link but have different `P_Key` values.

There are special requirements for the names of IPoIB **P_Key** interfaces. All IPoIB **P_Keys** range from **0x0000** to **0x7fff**, and the high bit, **0x8000**, denotes that membership in a **P_Key** is full membership instead of partial membership. The Linux kernel's IPoIB driver only supports full membership in **P_Key** subnets, so for any subnet that Linux can connect to, the high bit of the **P_Key** number will always be set. That means that if a Linux computer joins **P_Key 0x0002**, its actual **P_Key** number once joined will be **0x8002**, denoting that we are full members of **P_Key 0x0002**. For this reason, when creating a **P_Key** definition in an **opensm partitions.conf** file as depicted in section [Section 9.4.4, "Creating a P_Key definition"](#), it is required to specify a **P_Key** value without **0x8000**, but when defining the **P_Key** IPoIB interfaces on the Linux clients, add the **0x8000** value to the base **P_Key** value.

9.7. CONFIGURE INFINIBAND USING THE TEXT USER INTERFACE, NMTUI

The text user interface tool **nmtui** can be used to configure InfiniBand in a terminal window. Issue the following command to start the tool:

```
~]$ nmtui
```

The text user interface appears. Any invalid command prints a usage message.

To navigate, use the arrow keys or press **Tab** to step forwards and press **Shift+Tab** to step back through the options. Press **Enter** to select an option. The **Space** bar toggles the status of a check box.

From the starting menu, select **Edit a connection**. Select **Add**, the **New Connection** screen opens.




Figure 9.1. The NetworkManager Text User Interface Add an InfiniBand Connection menu

Select **InfiniBand**, the **Edit connection** screen opens. Follow the on-screen prompts to complete the configuration.

The screenshot shows the 'Edit connection' window in the NetworkManager Text User Interface. The window has a title bar with 'Edit connection'. Inside, the 'Profile name' is 'InfiniBand connection 1' and the 'Device' is highlighted in blue. A tree view on the left shows 'INFINIBAND' selected. The main area displays the configuration for the selected connection: 'Transport mode' is '<Datagram>' and 'MTU' is '(default)'. There are expandable sections for 'IPv4 CONFIGURATION' and 'IPv6 CONFIGURATION', both currently set to '<Automatic>'. At the bottom, there are checkboxes for 'Automatically connect' and 'Available to all users', both of which are checked. Navigation buttons '<Cancel>' and '<OK>' are at the bottom right. A '<Hide>' button is next to the 'INFINIBAND' section header.

Figure 9.2. The NetworkManager Text User Interface Configuring a InfiniBand Connection menu

See [Section 9.11.1, “Configuring the InfiniBand Tab”](#) for definitions of the InfiniBand terms.

See [Section 1.5, “Network Configuration Using a Text User Interface \(nmcli\)”](#) for information on installing **nmcli**.

9.8. CONFIGURE IPOIB USING THE COMMAND-LINE TOOL, NMCLI

First determine if renaming the default IPoIB device(s) is required, and if so, follow the instructions in [Section 9.3.2, “Usage of 70-persistent-ipoib.rules”](#) to rename the devices using **udev** renaming rules. Users can force the IPoIB interfaces to be renamed without performing a reboot by removing the **ib_ipoib** kernel module and then reloading it as follows:

```
~]$ rmmod ib_ipoib
~]$ modprobe ib_ipoib
```

Once the devices have the name required, use the **nmcli** tool to create the IPoIB interface(s). The following examples display two ways:

Example 9.1. Creating and modifying IPoIB in two separate commands.

```
~]$ nmcli con add type infiniband con-name mlx4_ib0 ifname mlx4_ib0
transport-mode connected mtu 65520
Connection 'mlx4_ib0' (8029a0d7-8b05-49ff-a826-2a6d722025cc)
successfully added.
~]$ nmcli con edit mlx4_ib0

===| nmcli interactive connection editor |===
```

```
Editing existing 'infiniband' connection: 'mlx4_ib0'
```

```
Type 'help' or '?' for available commands.
```

```
Type 'describe [>setting<.>prop<'] for detailed property description.
```

```
You may edit the following settings: connection, infiniband, ipv4, ipv6
```

```
nmcli> set infiniband.mac-address
```

```
80:00:02:00:fe:80:00:00:00:00:00:00:f4:52:14:03:00:7b:cb:a3
```

```
nmcli> save
```

```
Connection 'mlx4_ib3' (8029a0d7-8b05-49ff-a826-2a6d722025cc)
successfully updated.
```

```
nmcli> quit
```

or you can run `nmcli c add` and `nmcli c modify` in one command, as follows:

Example 9.2. Creating and modifying IPoIB in one command.

```
nmcli con add type infiniband con-name mlx4_ib0 ifname mlx4_ib0
transport-mode connected mtu 65520 infiniband.mac-address
80:00:02:00:fe:80:00:00:00:00:00:00:f4:52:14:03:00:7b:cb:a3
```

At these points, an IPoIB interface named `mlx4_ib0` has been created and set to use connected mode, with the maximum connected mode MTU, **DHCP** for **IPv4** and **IPv6**. If using IPoIB interfaces for cluster traffic and an Ethernet interface for out-of-cluster communications, it is likely that disabling default routes and any default name server on the IPoIB interfaces will be required. This can be done as follows:

```
~]$ nmcli con edit mlx4_ib0
```

```
===| nmcli interactive connection editor |===
```

```
Editing existing 'infiniband' connection: 'mlx4_ib0'
```

```
Type 'help' or '?' for available commands.
```

```
Type 'describe [>setting<.>prop<'] for detailed property description.
```

```
You may edit the following settings: connection, infiniband, ipv4, ipv6
```

```
nmcli> set ipv4.ignore-auto-dns yes
```

```
nmcli> set ipv4.ignore-auto-routes yes
```

```
nmcli> set ipv4.never-default true
```

```
nmcli> set ipv6.ignore-auto-dns yes
```

```
nmcli> set ipv6.ignore-auto-routes yes
```

```
nmcli> set ipv6.never-default true
```

```
nmcli> save
```

```
Connection 'mlx4_ib0' (8029a0d7-8b05-49ff-a826-2a6d722025cc) successfully
updated.
```

```
nmcli> quit
```

If a **P_Key** interface is required, create one using `nmcli` as follows:

```
~]$ nmcli con add type infiniband con-name mlx4_ib0.8002 ifname
mlx4_ib0.8002 parent mlx4_ib0 p-key 0x8002
```



```

Connection 'mlx4_ib0.8002' (4a9f5509-7bd9-4e89-87e9-77751a1c54b4)
successfully added.
~]$ nmcli con modify mlx4_ib0.8002 infiniband.mtu 65520
infiniband.transport-mode connected ipv4.ignore-auto-dns yes ipv4.ignore-
auto-routes yes ipv4.never-default true ipv6.ignore-auto-dns yes
ipv6.ignore-auto-routes yes ipv6.never-default true

```

9.9. CONFIGURE IPOIB USING THE COMMAND LINE

First determine if renaming the default IPoIB device(s) is required, and if so, follow the instructions in [Section 9.3.2, “Usage of 70-persistent-ipoib.rules”](#) to rename the devices using `udev` renaming rules. Users can force the IPoIB interfaces to be renamed without performing a reboot by removing the `ib_ipoib` kernel module and then reloading it as follows:

```

~]$ rmmod ib_ipoib
~]$ modprobe ib_ipoib

```

Once the devices have the name required, administrators can create `ifcfg` files with their preferred editor to control the devices. A typical IPoIB configuration file with static IPv4 addressing looks as follows:

```

~]$ more ifcfg-mlx4_ib0
DEVICE=mlx4_ib0
TYPE=InfiniBand
ONBOOT=yes
HWADDR=80:00:00:4c:fe:80:00:00:00:00:00:00:f4:52:14:03:00:7b:cb:a1
BOOTPROTO=none
IPADDR=172.31.0.254
PREFIX=24
NETWORK=172.31.0.0
BROADCAST=172.31.0.255
IPV4_FAILURE_FATAL=yes
IPV6INIT=no
MTU=65520
CONNECTED_MODE=yes
NAME=mlx4_ib0

```

The `DEVICE` field must match the custom name created in any `udev` renaming rules. The `NAME` entry need not match the device name. If the GUI connection editor is started, the `NAME` field is what is used to present a name for this connection to the user. The `TYPE` field must be `InfiniBand` in order for InfiniBand options to be processed properly. `CONNECTED_MODE` is either `yes` or `no`, where `yes` will use connected mode and `no` will use datagram mode for communications (see [Section 9.6.2, “Understanding IPoIB communication modes”](#)).

For `P_Key` interfaces, this is a typical configuration file:

```

~]$ more ifcfg-mlx4_ib0.8002
DEVICE=mlx4_ib0.8002
PHYSDEV=mlx4_ib0
PKEY=yes
PKEY_ID=2
TYPE=InfiniBand
ONBOOT=yes
HWADDR=80:00:00:4c:fe:80:00:00:00:00:00:00:f4:52:14:03:00:7b:cb:a1

```

```
BOOTPROTO=none
IPADDR=172.31.2.254
PREFIX=24
NETWORK=172.31.2.0
BROADCAST=172.31.2.255
IPV4_FAILURE_FATAL=yes
IPV6INIT=no
MTU=65520
CONNECTED_MODE=yes
NAME=mlx4_ib0.8002
```

For all **P_Key** interface files, the **PHYSDEV** directive is required and must be the name of the parent device. The **PKEY** directive must be set to **yes**, and **PKEY_ID** must be the number of the interface (either with or without the **0x8000** membership bit added in). The device name, however, must be the four digit hexadecimal representation of the **PKEY_ID** combined with the **0x8000** membership bit using the logical OR operator as follows:

```
NAME=${PHYSDEV}.$((0x8000 | $PKEY_ID))
```

By default, the **PKEY_ID** in the file is treated as a decimal number and converted to hexadecimal and then combined using the logical OR operator with **0x8000** to arrive at the proper name for the device, but users may specify the **PKEY_ID** in hexadecimal by prepending the standard **0x** prefix to the number.

9.10. TESTING AN RDMA NETWORK AFTER IPOIB IS CONFIGURED

Once IPoIB is configured, it is possible to use **IP** addresses to specify RDMA devices. Due to the ubiquitous nature of using **IP** addresses and host names to specify machines, most RDMA applications use this as their preferred, or in some cases only, way of specifying remote machines or local devices to connect to.

To test the functionality of the IPoIB layer, it is possible to use any standard **IP** network test tool and provide the **IP** address of the IPoIB devices to be tested. For example, the ping command between the **IP** addresses of the IPoIB devices should now work.

There are two different RDMA performance testing packages included with Red Hat Enterprise Linux, **qperf** and **perftest**. Either of these may be used to further test the performance of an RDMA network.

However, when using any of the applications that are part of the **perftest** package, or using the **qperf** application, there is a special note on address resolution. Even though the remote host is specified using an **IP** address or host name of the IPoIB device, it is allowed for the test application to actually connect through a different RDMA interface. The reason for this is because the process of converting from the host name or **IP** address to an RDMA address allows any valid RDMA address pair between the two machines to be used. If there are multiple ways for the client to connect to the server, then the programs might choose to use a different path if there is a problem with the path specified. For example, if there are two ports on each machine connected to the same InfiniBand subnet, and an **IP** address for the second port on each machine is given, it is likely that the program will find the first port on each machine is a valid connection method and use them instead. In this case, command-line options to any of the **perftest** programs can be used to tell them which card and port to bind to, as was done with **ibping** in [Section 9.5, “Testing Early InfiniBand RDMA operation”](#), in order to ensure that testing occurs over the specific ports required to be tested. For **qperf**, the method of binding to ports is slightly different. The **qperf** program operates as a server on one machine, listening on all devices (including non-RDMA devices). The client may connect to **qperf** using any valid **IP** address or host name for the server. **Qperf** will first attempt to open a data connection and run the requested test(s)

over the **IP** address or host name given on the client command line, but if there is any problem using that address, **qperf** will fall back to attempting to run the test on any valid path between the client and server. For this reason, to force **qperf** to test over a specific link, use the **-loc_id** and **-rem_id** options to the **qperf** client in order to force the test to run on a specific link.

9.11. CONFIGURE IPOIB USING A GUI

To configure an InfiniBand connection using a graphical tool, use the **Network Connections** tool.

Procedure 9.2. Adding a New InfiniBand Connection

1. To use the graphical **Network Connections** tool, press the **Super** key to enter the Activities Overview, type **Network Connections** and then press **Enter**. The **Network Connections** tool appears.
2. Click the **Add** button to open the selection list. Select **InfiniBand** and then click **Create**. The **Editing InfiniBand Connection 1** window appears.
3. On the **InfiniBand** tab, select the transport mode from the drop-down list you want to use for the InfiniBand connection.
4. Enter the InfiniBand MAC address.
5. Review and confirm the settings and then click the **Save** button.
6. Edit the InfiniBand-specific settings by referring to [Section 9.11.1, “Configuring the InfiniBand Tab”](#).

Procedure 9.3. Editing an Existing InfiniBand Connection

Follow these steps to edit an existing InfiniBand connection.

1. Press the **Super** key to enter the Activities Overview, type **Network Connections** and then press **Enter**. The **Network Connections** tool appears.
2. Select the connection you want to edit and click the **Edit** button.
3. Select the **General** tab.
4. Configure the connection name, auto-connect behavior, and availability settings.

Five settings in the **Editing** dialog are common to all connection types, see the **General** tab:

- **Connection name** – Enter a descriptive name for your network connection. This name will be used to list this connection in the menu of the **Network** window.
- **Automatically connect to this network when it is available** – Select this box if you want **NetworkManager** to auto-connect to this connection when it is available. See [Section 2.3.3, “Connecting to a Network Automatically”](#) for more information.
- **All users may connect to this network** – Select this box to create a connection available to all users on the system. Changing this setting may require root privileges. See [Section 2.3.5, “System-wide and Private Connection Profiles”](#) for details.

- **Automatically connect to VPN when using this connection** – Select this box if you want **NetworkManager** to auto-connect to a VPN connection when it is available. Select the VPN from the drop-down menu.
 - **Firewall Zone** – Select the Firewall Zone from the drop-down menu. See the [Red Hat Enterprise Linux 7 Security Guide](#) for more information on Firewall Zones.
5. Edit the InfiniBand-specific settings by referring to the [Section 9.11.1, “Configuring the InfiniBand Tab”](#).

Saving Your New (or Modified) Connection and Making Further Configurations

Once you have finished editing your InfiniBand connection, click the **Save** button to save your customized configuration. If the profile was in use while being edited, power cycle the connection to make **NetworkManager** apply the changes. If the profile is OFF, set it to ON or select it in the network connection icon's menu. See [Section 2.3.1, “Connecting to a Network Using a GUI”](#) for information on using your new or altered connection.

You can further configure an existing connection by selecting it in the **Network Connections** window and clicking **Edit** to return to the **Editing** dialog.

Then, to configure:

- IPv4 settings for the connection, click the **IPv4 Settings** tab and proceed to [Section 2.7.6, “Configuring IPv4 Settings”](#); or,
- IPv6 settings for the connection, click the **IPv6 Settings** tab and proceed to [Section 2.7.7, “Configuring IPv6 Settings”](#).

9.11.1. Configuring the InfiniBand Tab

If you have already added a new InfiniBand connection (see [Procedure 9.2, “Adding a New InfiniBand Connection”](#) for instructions), you can edit the **InfiniBand** tab to set the parent interface and the InfiniBand ID.

Transport mode

Datagram or Connected mode can be selected from the drop-down list. Select the same mode the rest of your IPoIB network is using.

Device MAC address

The MAC address of the InfiniBand capable device to be used for the InfiniBand network traffic. This hardware address field will be pre-filled if you have InfiniBand hardware installed.

MTU

Optionally sets a Maximum Transmission Unit (MTU) size to be used for packets to be sent over the InfiniBand connection.

9.12. ADDITIONAL RESOURCES

Installed Documentation

- `/usr/share/doc/ini-scripts-version/sysconfig.txt` – Describes configuration files and their directives.

Online Documentation

<https://www.kernel.org/doc/Documentation/infiniband/ipoib.txt>

A description of the IPoIB driver. Includes references to relevant RFCs.

PART III. SERVERS

This part discusses how to set up servers normally required for networking.



NOTE

To monitor and administer servers through a web browser, see the [Red Hat Enterprise Linux Getting Started with Cockpit](#).

CHAPTER 10. DHCP SERVERS

Dynamic Host Configuration Protocol (DHCP) is a network protocol that automatically assigns TCP/IP information to client machines. Each **DHCP** client connects to the centrally located **DHCP** server, which returns the network configuration (including the **IP** address, gateway, and **DNS** servers) of that client.

10.1. WHY USE DHCP?

DHCP is useful for automatic configuration of client network interfaces. When configuring the client system, you can choose **DHCP** instead of specifying an **IP** address, netmask, gateway, or **DNS** servers. The client retrieves this information from the **DHCP** server. **DHCP** is also useful if you want to change the **IP** addresses of a large number of systems. Instead of reconfiguring all the systems, you can just edit one configuration file on the server for the new set of **IP** addresses. If the **DNS** servers for an organization changes, the changes happen on the **DHCP** server, not on the **DHCP** clients. When you restart the network or reboot the clients, the changes go into effect.

If an organization has a functional **DHCP** server correctly connected to a network, laptops and other mobile computer users can move these devices from office to office.

Note that administrators of **DNS** and **DHCP** servers, as well as any provisioning applications, should agree on the host name format used in an organization. See [Section 3.1.1, “Recommended Naming Practices”](#) for more information on the format of host names.

10.2. CONFIGURING A DHCP SERVER

The `dhcp` package contains an *Internet Systems Consortium* (ISC) **DHCP** server. Install the package as **root**:

```
~]# yum install dhcp
```

Installing the `dhcp` package creates a file, `/etc/dhcp/dhcpd.conf`, which is merely an empty configuration file. As **root**, issue the following command:

```
~]# cat /etc/dhcp/dhcpd.conf
#
# DHCP Server Configuration file.
#   see /usr/share/doc/dhcp*/dhcpd.conf.example
#   see dhcpd.conf(5) man page
#
```

The example configuration file can be found at `/usr/share/doc/dhcp-version;/dhcpd.conf.example`. You should use this file to help you configure `/etc/dhcp/dhcpd.conf`, which is explained in detail below.

DHCP also uses the file `/var/lib/dhcpd/dhcpd.leases` to store the client lease database. Refer to [Section 10.2.2, “Lease Database”](#) for more information.

10.2.1. Configuration File

The first step in configuring a **DHCP** server is to create the configuration file that stores the network information for the clients. Use this file to declare options for client systems.

The configuration file can contain extra tabs or blank lines for easier formatting. Keywords are case-

insensitive and lines beginning with a hash sign (#) are considered comments.

There are two types of statements in the configuration file:

- **Parameters** – State how to perform a task, whether to perform a task, or what network configuration options to send to the client.
- **Declarations** – Describe the topology of the network, describe the clients, provide addresses for the clients, or apply a group of parameters to a group of declarations.

The parameters that start with the keyword *option* are referred to as *options*. These options control **DHCP** options; whereas, parameters configure values that are not optional or control how the **DHCP** server behaves.

Parameters (including options) declared before a section enclosed in curly brackets ({ }) are considered global parameters. Global parameters apply to all the sections below it.



IMPORTANT

If the configuration file is changed, the changes do not take effect until the **DHCP** daemon is restarted with the command `systemctl restart dhcpd`.



NOTE

Instead of changing a **DHCP** configuration file and restarting the service each time, using the `omshell` command provides an interactive way to connect to, query, and change the configuration of a **DHCP** server. By using `omshell`, all changes can be made while the server is running. For more information on `omshell`, see the `omshell` man page.

In [Example 10.1, “Subnet Declaration”](#), the `routers`, `subnet-mask`, `domain-search`, `domain-name-servers`, and `time-offset` options are used for any `host` statements declared below it.

For every subnet which will be served, and for every subnet to which the **DHCP** server is connected, there must be one `subnet` declaration, which tells the **DHCP** daemon how to recognize that an address is on that subnet. A `subnet` declaration is required for each subnet even if no addresses will be dynamically allocated to that subnet.

In this example, there are global options for every **DHCP** client in the subnet and a `range` declared. Clients are assigned an **IP** address within the `range`.

Example 10.1. Subnet Declaration

```
subnet 192.168.1.0 netmask 255.255.255.0 {
    option routers                192.168.1.254;
    option subnet-mask            255.255.255.0;
    option domain-search          "example.com";
    option domain-name-servers    192.168.1.1;
    option time-offset            -18000;      # Eastern Standard
Time
    range 192.168.1.10 192.168.1.100;
}
```


To configure a **DHCP** server that leases a dynamic **IP** address to a system within a subnet, modify the example values from [Example 10.2, “Range Parameter”](#). It declares a default lease time, maximum lease time, and network configuration values for the clients. This example assigns **IP** addresses in the range **192.168.1.10** and **192.168.1.100** to client systems.

Example 10.2. Range Parameter

```
default-lease-time 600;
max-lease-time 7200;
option subnet-mask 255.255.255.0;
option broadcast-address 192.168.1.255;
option routers 192.168.1.254;
option domain-name-servers 192.168.1.1, 192.168.1.2;
option domain-search "example.com";
subnet 192.168.1.0 netmask 255.255.255.0 {
    range 192.168.1.10 192.168.1.100;
}
```

To assign an **IP** address to a client based on the **MAC** address of the network interface card, use the **hardware ethernet** parameter within a **host** declaration. As demonstrated in [Example 10.3, “Static IP Address Using DHCP”](#), the **host apex** declaration specifies that the network interface card with the **MAC** address **00:A0:78:8E:9E:AA** always receives the **IP** address **192.168.1.4**.

Note that you can also use the optional parameter **host-name** to assign a host name to the client.

Example 10.3. Static IP Address Using DHCP

```
host apex {
    option host-name "apex.example.com";
    hardware ethernet 00:A0:78:8E:9E:AA;
    fixed-address 192.168.1.4;
}
```

Red Hat Enterprise Linux 7 supports assigning static **IP** addresses to InfiniBand **IPoIB** interfaces. However, as these interfaces do not have a normal hardware Ethernet address, a different method of specifying a unique identifier for the **IPoIB** interface must be used. The standard is to use the option **dhcp-client-identifier=** construct to specify the **IPoIB** interface’s **dhcp-client-identifier** field. The **DHCP** server host construct supports at most one hardware Ethernet and one **dhcp-client-identifier** entry per host stanza. However, there may be more than one **fixed-address** entry and the **DHCP** server will automatically respond with an address that is appropriate for the network that the **DHCP** request was received on.

Example 10.4. Static IP Address Using DHCP on Multiple Interfaces

If a machine has a complex configuration, for example two InfiniBand interfaces, and **P_Key** interfaces on each physical interface, plus an Ethernet connection, the following static **IP** construct could be used to serve this configuration:

```
Host apex.0 {
    option host-name "apex.example.com";
    hardware ethernet 00:A0:78:8E:9E:AA;
```

```

    option dhcp-client-
    identifier=ff:00:00:00:00:00:02:00:00:02:c9:00:00:02:c9:03:00:31:7b:11;
    fixed-address 172.31.0.50,172.31.2.50,172.31.1.50,172.31.3.50;
}

host apex.1 {
    option host-name "apex.example.com";
    hardware ethernet 00:A0:78:8E:9E:AB;
    option dhcp-client-
    identifier=ff:00:00:00:00:00:02:00:00:02:c9:00:00:02:c9:03:00:31:7b:12;
    fixed-address 172.31.0.50,172.31.2.50,172.31.1.50,172.31.3.50;
}

```

In order to find the right `dhcp-client-identifier` for your device, you can usually use the prefix `ff:00:00:00:00:00:02:00:00:02:c9:00` and then add the last 8 bytes of the IPoIB interface (which happens to also be the 8 byte GUID of the InfiniBand port the IPoIB interface is on). On some older controllers, this prefix is not correct. In that case, we recommend using `tcpdump` on the **DHCP** server to capture the incoming IPoIB **DHCP** request and gather the right `dhcp-client-identifier` from that capture. For example:

```

]$ tcpdump -vv -i mlx4_ib0
tcpdump: listening on mlx4_ib0, link-type LINUX_SLL (Linux cooked),
capture size 65535 bytes
23:42:44.131447 IP (tos 0x10, ttl 128, id 0, offset 0, flags [none],
proto UDP (17), length 328)
    0.0.0.0.bootpc > 255.255.255.255.bootps: [udp sum ok] BOOTP/DHCP,
Request, length 300, htype 32, hlen 0, xid 0x975cb024, Flags [Broadcast]
(0x8000)
    Vendor-rfc1048 Extensions
        Magic Cookie 0x63825363
        DHCP-Message Option 53, length 1: Discover
        Hostname Option 12, length 10: "rdma-qe-03"
        Parameter-Request Option 55, length 18:
            Subnet-Mask, BR, Time-Zone, Classless-Static-Route
            Domain-Name, Domain-Name-Server, Hostname, YD
            YS, NTP, MTU, Option 119
            Default-Gateway, Classless-Static-Route, Classless-
Static-Route-Microsoft, Static-Route
            Option 252, NTP
            Client-ID Option 61, length 20: hardware-type 255,
00:00:00:00:00:02:00:00:02:c9:00:00:02:c9:02:00:21:ac:c1

```

The above dump shows the Client-ID field. The hardware-type **255** corresponds to the initial `ff:` of the ID, the rest of the ID is then quoted exactly as it needs to appear in the **DHCP** configuration file.

All subnets that share the same physical network should be declared within a **shared-network** declaration as shown in [Example 10.5, “Shared-network Declaration”](#). Parameters within the **shared-network**, but outside the enclosed subnet declarations, are considered to be global parameters. The name assigned to **shared-network** must be a descriptive title for the network, such as using the title “test-lab” to describe all the subnets in a test lab environment.

Example 10.5. Shared-network Declaration

```

shared-network name {
    option domain-search          "test.redhat.com";
    option domain-name-servers    ns1.redhat.com, ns2.redhat.com;
    option routers                192.168.0.254;
    #more parameters for EXAMPLE shared-network
    subnet 192.168.1.0 netmask 255.255.252.0 {
        #parameters for subnet
        range 192.168.1.1 192.168.1.254;
    }
    subnet 192.168.2.0 netmask 255.255.252.0 {
        #parameters for subnet
        range 192.168.2.1 192.168.2.254;
    }
}

```

As demonstrated in [Example 10.6, “Group Declaration”](#), the **group** declaration is used to apply global parameters to a group of declarations. For example, shared networks, subnets, and hosts can be grouped.

Example 10.6. Group Declaration

```

group {
    option routers                192.168.1.254;
    option subnet-mask            255.255.255.0;
    option domain-search          "example.com";
    option domain-name-servers    192.168.1.1;
    option time-offset            -18000;      # Eastern Standard Time
    host apex {
        option host-name "apex.example.com";
        hardware ethernet 00:A0:78:8E:9E:AA;
        fixed-address 192.168.1.4;
    }
    host raleigh {
        option host-name "raleigh.example.com";
        hardware ethernet 00:A1:DD:74:C3:F2;
        fixed-address 192.168.1.6;
    }
}

```

NOTE

You can use the provided example configuration file as a starting point and add custom configuration options to it. To copy this file to the proper location, use the following command as **root**:

```
~]# cp /usr/share/doc/dhcp-version_number/dhcpd.conf.example /etc/dhcp/dhcpd.conf
```

... where *version_number* is the **DHCP** version number.

For a complete list of option statements and what they do, see the **dhcp-options(5)** man page.

10.2.2. Lease Database


On the **DHCP** server, the file `/var/lib/dhcpd/dhcpd.leases` stores the **DHCP** client lease database. Do not change this file. **DHCP** lease information for each recently assigned **IP** address is automatically stored in the lease database. The information includes the length of the lease, to whom the **IP** address has been assigned, the start and end dates for the lease, and the MAC address of the network interface card that was used to retrieve the lease.

All times in the lease database are in Coordinated Universal Time (UTC), not local time.

The lease database is recreated from time to time so that it is not too large. First, all known leases are saved in a temporary lease database. The `dhcpd.leases` file is renamed `dhcpd.leases~` and the temporary lease database is written to `dhcpd.leases`.

The **DHCP** daemon could be killed or the system could crash after the lease database has been renamed to the backup file but before the new file has been written. If this happens, the `dhcpd.leases` file does not exist, but it is required to start the service. Do not create a new lease file. If you do, all old leases are lost which causes many problems. The correct solution is to rename the `dhcpd.leases~` backup file to `dhcpd.leases` and then start the daemon.

10.2.3. Starting and Stopping the Server



IMPORTANT

When the **DHCP** server is started for the first time, it fails unless the `dhcpd.leases` file exists. You can use the command `touch /var/lib/dhcpd/dhcpd.leases` to create the file if it does not exist. If the same server is also running BIND as a **DNS** server, this step is not necessary, as starting the `named` service automatically checks for a `dhcpd.leases` file.

Do not create a new lease file on a system that was previously running. If you do, all old leases are lost which causes many problems. The correct solution is to rename the `dhcpd.leases~` backup file to `dhcpd.leases` and then start the daemon.

To start the **DHCP** service, use the following command:

```
systemctl start dhcpd.service
```

To stop the **DHCP** server, type:

```
systemctl stop dhcpd.service
```

By default, the **DHCP** service does not start at boot time. For information on how to configure the daemon to start automatically at boot time, see [Red Hat Enterprise Linux System Administrator's Guide](#)

If more than one network interface is attached to the system, but the **DHCP** server should only listen for **DHCP** requests on one of the interfaces, configure the **DHCP** server to listen only on that device. The **DHCP** daemon will only listen on interfaces for which it finds a subnet declaration in the `/etc/dhcp/dhcpd.conf` file.

This is useful for a firewall machine with two network cards. One network card can be configured as a **DHCP** client to retrieve an **IP** address to the Internet. The other network card can be used as a **DHCP** server for the internal network behind the firewall. Specifying only the network card connected to the

internal network makes the system more secure because users cannot connect to the daemon through the Internet.

To specify command-line options, copy and then edit the `dhcpd.service` file as the `root` user. For example, as follows:

```
~]# cp /usr/lib/systemd/system/dhcpd.service /etc/systemd/system/
~]# vi /etc/systemd/system/dhcpd.service
```

Edit the line under section [Service]:

```
ExecStart=/usr/sbin/dhcpd -f -cf /etc/dhcp/dhcpd.conf -user dhcpd -group
dhcpd --no-pid your_interface_name(s)
```

Then, as the `root` user, restart the service:

```
~]# systemctl --system daemon-reload
~]# systemctl restart dhcpd
```

Command line options can be appended to `ExecStart=/usr/sbin/dhcpd` in the `/etc/systemd/system/dhcpd.service` unit file under section [Service]. They include:

- **-p *portnum*** – Specifies the UDP port number on which `dhcpd` should listen. The default is port 67. The **DHCP** server transmits responses to the **DHCP** clients at a port number one greater than the UDP port specified. For example, if the default port 67 is used, the server listens on port 67 for requests and responds to the client on port 68. If a port is specified here and the **DHCP** relay agent is used, the same port on which the **DHCP** relay agent should listen must be specified. See [Section 10.3, “DHCP Relay Agent”](#) for details.
- **-f** – Runs the daemon as a foreground process. This is mostly used for debugging.
- **-d** – Logs the **DHCP** server daemon to the standard error descriptor. This is mostly used for debugging. If this is not specified, the log is written to `/var/log/messages`.
- **-cf *filename*** – Specifies the location of the configuration file. The default location is `/etc/dhcp/dhcpd.conf`.
- **-lf *filename*** – Specifies the location of the lease database file. If a lease database file already exists, it is very important that the same file be used every time the **DHCP** server is started. It is strongly recommended that this option only be used for debugging purposes on non-production machines. The default location is `/var/lib/dhcpd/dhcpd.leases`.
- **-q** – Do not print the entire copyright message when starting the daemon.

10.3. DHCP RELAY AGENT

The DHCP Relay Agent (`dhcrelay`) enables the relay of **DHCP** and **BOOTP** requests from a subnet with no **DHCP** server on it to one or more **DHCP** servers on other subnets.

When a **DHCP** client requests information, the DHCP Relay Agent forwards the request to the list of **DHCP** servers specified when the DHCP Relay Agent is started. When a **DHCP** server returns a reply, the reply is broadcast or unicast on the network that sent the original request.

The DHCP Relay Agent for **IPv4**, `dhcrelay`, listens for **DHCPv4** and **BOOTP** requests on all interfaces

unless the interfaces are specified in `/etc/sysconfig/dhcrelay` with the **INTERFACES** directive. See [Section 10.3.1, “Configure dhcrelay as a DHCPv4 and BOOTP relay agent”](#). The DHCP Relay Agent for **IPv6**, `dhcrelay6`, does not have this default behavior and interfaces to listen for **DHCPv6** requests must be specified. See [Section 10.3.2, “Configure dhcrelay as a DHCPv6 relay agent”](#).

`dhcrelay` can either be run as a **DHCPv4** and **BOOTP** relay agent (by default) or as a **DHCPv6** relay agent (with `-6` argument). To see the usage message, issue the command `dhcrelay -h`.

10.3.1. Configure dhcrelay as a DHCPv4 and BOOTP relay agent

To run `dhcrelay` in **DHCPv4** and **BOOTP** mode specify the servers to which the requests should be forwarded to. Copy and then edit the `dhcrelay.service` file as the **root** user:

```
~]# cp /lib/systemd/system/dhcrelay.service /etc/systemd/system/  
~]# vi /etc/systemd/system/dhcrelay.service
```

Edit the **ExecStart** option under section **[Service]** and add one or more server **IPv4** addresses to the end of the line, for example:

```
ExecStart=/usr/sbin/dhcrelay -d --no-pid 192.168.1.1
```

If you also want to specify interfaces where the DHCP Relay Agent listens for **DHCP** requests, add them to the **ExecStart** option with `-i` argument (otherwise it will listen on all interfaces), for example:

```
ExecStart=/usr/sbin/dhcrelay -d --no-pid 192.168.1.1 -i em1
```

For other options see the `dhcrelay(8)` man page.

To activate the changes made, as the **root** user, restart the service:

```
~]# systemctl --system daemon-reload  
~]# systemctl restart dhcrelay
```

10.3.2. Configure dhcrelay as a DHCPv6 relay agent

To run `dhcrelay` in **DHCPv6** mode add the `-6` argument and specify the “lower interface” (on which queries will be received from clients or from other relay agents) and the “upper interface” (to which queries from clients and other relay agents should be forwarded). Copy `dhcrelay.service` to `dhcrelay6.service` and edit it as the **root** user:

```
~]# cp /lib/systemd/system/dhcrelay.service  
/etc/systemd/system/dhcrelay6.service  
~]# vi /etc/systemd/system/dhcrelay6.service
```

Edit the **ExecStart** option under section **[Service]** add `-6` argument and add the “lower interface” and “upper interface” interface, for example:

```
ExecStart=/usr/sbin/dhcrelay -d --no-pid -6 -l em1 -u em2
```

For other options see the `dhcrelay(8)` man page.

To activate the changes made, as the **root** user, restart the service:

```
~]# systemctl --system daemon-reload
~]# systemctl restart dhcrelay6
```

10.4. CONFIGURING A MULTIHOMED DHCP SERVER

A multihomed **DHCP** server serves multiple networks, that is, multiple subnets. The examples in these sections detail how to configure a **DHCP** server to serve multiple networks, select which network interfaces to listen on, and how to define network settings for systems that move networks.

Before making any changes, back up the existing `/etc/dhcp/dhcpd.conf` file.

The **DHCP** daemon will only listen on interfaces for which it finds a subnet declaration in the `/etc/dhcp/dhcpd.conf` file.

The following is a basic `/etc/dhcp/dhcpd.conf` file, for a server that has two network interfaces, `eth0` in a `10.0.0.0/24` network, and `eth1` in a `172.16.0.0/24` network. Multiple **subnet** declarations allow you to define different settings for multiple networks:

```
default-lease-time 600;
max-lease-time 7200;
subnet 10.0.0.0 netmask 255.255.255.0 {
    option subnet-mask 255.255.255.0;
    option routers 10.0.0.1;
    range 10.0.0.5 10.0.0.15;
}
subnet 172.16.0.0 netmask 255.255.255.0 {
    option subnet-mask 255.255.255.0;
    option routers 172.16.0.1;
    range 172.16.0.5 172.16.0.15;
}
```

subnet 10.0.0.0 netmask 255.255.255.0;

A **subnet** declaration is required for every network your **DHCP** server is serving. Multiple subnets require multiple **subnet** declarations. If the **DHCP** server does not have a network interface in a range of a **subnet** declaration, the **DHCP** server does not serve that network.

If there is only one **subnet** declaration, and no network interfaces are in the range of that subnet, the **DHCP** daemon fails to start, and an error such as the following is logged to `/var/log/messages`:

```
dhcpd: No subnet declaration for eth0 (0.0.0.0).
dhcpd: ** Ignoring requests on eth0.  If this is not what
dhcpd:    you want, please write a subnet declaration
dhcpd:    in your dhcpd.conf file for the network segment
dhcpd:    to which interface eth1 is attached.  **
dhcpd:
dhcpd:
dhcpd: Not configured to listen on any interfaces!
```

option subnet-mask 255.255.255.0;

The **option subnet-mask** option defines a subnet mask, and overrides the **netmask** value in the **subnet** declaration. In simple cases, the subnet and netmask values are the same.

option routers 10.0.0.1;

The **option routers** option defines the default gateway for the subnet. This is required for systems to reach internal networks on a different subnet, as well as external networks.

range 10.0.0.5 10.0.0.15;

The **range** option specifies the pool of available **IP** addresses. Systems are assigned an address from the range of specified **IP** addresses.

For further information, see the **dhcpcd.conf(5)** man page.



WARNING

To avoid misconfiguration when DHCP server gives IP addresses from one IP range to another physical Ethernet segment, make sure you do not enclose more subnets in a shared-network declaration.

10.4.1. Host Configuration

Before making any changes, back up the existing **/etc/sysconfig/dhcpd** and **/etc/dhcp/dhcpd.conf** files.

Configuring a Single System for Multiple Networks

The following **/etc/dhcp/dhcpd.conf** example creates two subnets, and configures an **IP** address for the same system, depending on which network it connects to:

```
default-lease-time 600;
max-lease-time 7200;
subnet 10.0.0.0 netmask 255.255.255.0 {
    option subnet-mask 255.255.255.0;
    option routers 10.0.0.1;
    range 10.0.0.5 10.0.0.15;
}
subnet 172.16.0.0 netmask 255.255.255.0 {
    option subnet-mask 255.255.255.0;
    option routers 172.16.0.1;
    range 172.16.0.5 172.16.0.15;
}
host example0 {
    hardware ethernet 00:1A:6B:6A:2E:0B;
    fixed-address 10.0.0.20;
}
host example1 {
    hardware ethernet 00:1A:6B:6A:2E:0B;
    fixed-address 172.16.0.20;
}
```

host example0

The **host** declaration defines specific parameters for a single system, such as an **IP** address. To configure specific parameters for multiple hosts, use multiple **host** declarations.

Most **DHCP** clients ignore the name in **host** declarations, and as such, this name can be anything, as long as it is unique to other **host** declarations. To configure the same system for multiple networks, use a different name for each **host** declaration, otherwise the **DHCP** daemon fails to start. Systems are identified by the **hardware ethernet** option, not the name in the **host** declaration.

```
hardware ethernet 00:1A:6B:6A:2E:0B;
```

The **hardware ethernet** option identifies the system. To find this address, run the **ip link** command.

```
fixed-address 10.0.0.20;
```

The **fixed-address** option assigns a valid **IP** address to the system specified by the **hardware ethernet** option. This address must be outside the **IP** address pool specified with the **range** option.

If **option** statements do not end with a semicolon, the **DHCP** daemon fails to start, and an error such as the following is logged to **/var/log/messages**:

```
/etc/dhcp/dhcpd.conf line 20: semicolon expected.
dhcpd: }
dhcpd: ^
dhcpd: /etc/dhcp/dhcpd.conf line 38: unexpected end of file
dhcpd:
dhcpd: ^
dhcpd: Configuration file errors encountered -- exiting
```

Configuring Systems with Multiple Network Interfaces

The following **host** declarations configure a single system, which has multiple network interfaces, so that each interface receives the same **IP** address. This configuration will not work if both network interfaces are connected to the same network at the same time:

```
host interface0 {
    hardware ethernet 00:1a:6b:6a:2e:0b;
    fixed-address 10.0.0.18;
}
host interface1 {
    hardware ethernet 00:1A:6B:6A:27:3A;
    fixed-address 10.0.0.18;
}
```

For this example, **interface0** is the first network interface, and **interface1** is the second interface. The different **hardware ethernet** options identify each interface.

If such a system connects to another network, add more **host** declarations, remembering to:

- assign a valid **fixed-address** for the network the host is connecting to.
- make the name in the **host** declaration unique.

When a name given in a **host** declaration is not unique, the **DHCP** daemon fails to start, and an error

such as the following is logged to `/var/log/messages`:

```
dhcpd: /etc/dhcp/dhcpd.conf line 31: host interface0: already exists
dhcpd: }
dhcpd: ^
dhcpd: Configuration file errors encountered -- exiting
```

This error was caused by having multiple `host interface0` declarations defined in `/etc/dhcp/dhcpd.conf`.

10.5. DHCP FOR IPV6 (DHCPV6)

The ISC **DHCP** includes support for **IPv6 (DHCPv6)** since the 4.x release with a **DHCPv6** server, client, and relay agent functionality. The agents support both **IPv4** and **IPv6**, however the agents can only manage one protocol at a time; for dual support they must be started separately for **IPv4** and **IPv6**. For example, configure both **DHCPv4** and **DHCPv6** by editing their respective configuration files `/etc/dhcp/dhcpd.conf` and `/etc/dhcp/dhcpd6.conf` and then issue the following commands:

```
~]# systemctl start dhcpd
~]# systemctl start dhcpd6
```

The **DHCPv6** server configuration file can be found at `/etc/dhcp/dhcpd6.conf`.

The example server configuration file can be found at `/usr/share/doc/dhcp-version/dhcpd6.conf.example`.

A simple **DHCPv6** server configuration file can look like this:

```
subnet6 2001:db8:0:1::/64 {
    range6 2001:db8:0:1::129 2001:db8:0:1::254;
    option dhcp6.name-servers fec0:0:0:1::1;
    option dhcp6.domain-search "domain.example";
}
```

To assign a **fixed-address** to a client, based on the MAC address of the network interface card, use the **hardware ethernet** parameter:

```
host otherclient {
    hardware ethernet 01:00:80:a2:55:67;
    fixed-address6 3ffe:501:ffff:100::4321;
}
```

The configuration options in the **shared-network**, and **group** declaration for IPv6 are the same as IPv4. For more details, see the examples as demonstrated in [Example 10.5, “Shared-network Declaration”](#), and [Example 10.6, “Group Declaration”](#).

10.6. CONFIGURING THE RADVD DAEMON FOR IPV6 ROUTERS

The router advertisement daemon (**radvd**) sends router advertisement messages which are required for IPv6 stateless autoconfiguration. This allows users to automatically configure their addresses, settings, routes and choose a default router based on these advertisements. To configure the **radvd** daemon:

1. Install the **radvd** daemon:

```
~]# sudo yum install radvd
```

2. Set up the `/etc/radvd.conf` file. For example:

```
interface eth0
{
  AdvSendAdvert on;
  MinRtrAdvInterval 30;
  MaxRtrAdvInterval 100;
  prefix 2001:db8:1:0::/64
  {
    AdvOnLink on;
    AdvAutonomous on;
    AdvRouterAddr off;
  };
};
```

**NOTE**

If you want to additionally advertise DNS resolvers along with the router advertisements, add the **RDNSS** `<ip> <ip> <ip> { };` option in the `/etc/radvd.conf` file. To configure a DHCPv6 service for your subnets, you can set the **AdvManagedFlag** to `on`, so the router advertisements allow clients to automatically obtain an IPv6 address when a DHCPv6 service is available. For more details on configuring the DHCPv6 service, see [Section 10.5, “DHCP for IPv6 \(DHCPv6\)”](#)

3. Enable the **radvd** daemon:

```
~]# sudo systemctl enable radvd.service
```

4. Start the **radvd** daemon immediately:

```
~]# sudo systemctl start radvd.service
```

To display the content of router advertisement packages and the configured values sent by the **radvd** daemon, use the **radvdump** command:

```
~]# radvdump
Router advertisement from fe80::280:c8ff:feb9:cef9 (hoplimit 255)
  AdvCurHopLimit: 64
  AdvManagedFlag: off
  AdvOtherConfigFlag: off
  AdvHomeAgentFlag: off
  AdvReachableTime: 0
  AdvRetransTimer: 0
  Prefix 2002:0102:0304:f101::/64
    AdvValidLifetime: 30
    AdvPreferredLifetime: 20
    AdvOnLink: off
```

```
AdvAutonomous: on
AdvRouterAddr: on
Prefix 2001:0db8:100:f101::/64
AdvValidLifetime: 2592000
AdvPreferredLifetime: 604800
AdvOnLink: on
AdvAutonomous: on
AdvRouterAddr: on
AdvSourceLLAddress: 00 80 12 34 56 78
```

For more information on the `radvd` daemon, see the `radvd(8)`, `radvd.conf(5)`, `radvdump(8)` man pages.

10.7. COMPARISON OF DHCPV6 TO RADVD

Dynamic Host configuration for IPv4 is mainly applied with DHCPv4. However, for IPv6 the following options are available:

- Manually
- Using the `radvd` daemon
- Using the **DHCPv6** server

Manually

Manual addressing is always available. You can assign IPv6 addresses to a system using the tools described in [Section 2.1.7, “Connecting to a Network Using nmcli”](#), [Section 4.2, “Configure Bonding Using the Text User Interface, nmtui”](#), [Section 2.2.3, “Configuring a Network Interface Using ip Commands”](#).

Using the radvd Daemon

A standards-compliant IPv6 network must provide router advertisements, thus IPv6 configuration options can be applied running the router advertisement daemon (`radvd`). The router advertisements provide the on-link information on which prefix is actually available locally on a physical LAN. On top of router advertisements, you can select either manual IPv6 configuration, automatic IPv6 configuration through router advertisements or the Dynamic Host Configuration Protocol (DHCPv6). For more details on configuring the `radvd` daemon, see [Section 10.6, “Configuring the radvd daemon for IPv6 routers”](#).

Using the DHCPv6 Server

When address management is under central administration, the user can set up a DHCPv6 server. The availability of DHCPv6 is announced by flags in the router advertisement packets.

Table 10.1. Comparison of DHCPv6 to `radvd`

DHCPv6	radvd
Guarantee random addresses to protect privacy.	Provide information on a default gateway.

DHCPv6	radvd
Send further network configuration options to clients. For example, Network Time Protocol (NTP) servers, Session Initiation Protocol (SIP) servers, Preboot Execution Environment (iPXE) configuration.	
Map MAC addresses to IPv6 addresses.	



NOTE

To correctly configure a network, use DHCPv6 in conjunction with radvd, as only router advertisements provide information on a default gateway.

10.8. ADDITIONAL RESOURCES

- **dhcpcd(8)** man page – Describes how the **DHCP** daemon works.
- **dhcpcd.conf(5)** man page – Explains how to configure the **DHCP** configuration file; includes some examples.
- **dhcpcd.leases(5)** man page – Describes a persistent database of leases.
- **dhcp-options(5)** man page – Explains the syntax for declaring **DHCP** options in **dhcpcd.conf**; includes some examples.
- **dhcrelay(8)** man page – Explains the **DHCP** Relay Agent and its configuration options.
- **/usr/share/doc/dhcp-version/** – Contains example files, README files, and release notes for current versions of the **DHCP** service.

CHAPTER 11. DNS SERVERS

DNS (Domain Name System), is a distributed database system that is used to associate host names with their respective **IP** addresses. For users, this has the advantage that they can refer to machines on the network by names that are usually easier to remember than the numerical network addresses. For system administrators, using a **DNS** server, also known as a *name server*, enables changing the **IP** address for a host without ever affecting the name-based queries. The use of the **DNS** databases is not only for resolving **IP** addresses to domain names and their use is becoming broader and broader as DNSSEC is deployed.

11.1. INTRODUCTION TO DNS

DNS is usually implemented using one or more centralized servers that are authoritative for certain domains. When a client host requests information from a name server, it usually connects to port 53. The name server then attempts to resolve the name requested. If the name server is configured to be a recursive name servers and it does not have an authoritative answer, or does not already have the answer cached from an earlier query, it queries other name servers, called *root name servers*, to determine which name servers are authoritative for the name in question, and then queries them to get the requested name. Name servers configured as purely authoritative, with recursion disabled, will not do lookups on behalf of clients.

11.1.1. Name server Zones

In a **DNS** server, all information is stored in basic data elements called *resource records* (RR). Resource records are defined in [RFC 1034](#). The domain names are organized into a tree structure. Each level of the hierarchy is divided by a period (.). For example: The root domain, denoted by ., is the root of the **DNS** tree, which is at level zero. The domain name **com**, referred to as the *top-level domain* (TLD) is a child of the root domain (.) so it is the first level of the hierarchy. The domain name **example.com** is at the second level of the hierarchy.

Example 11.1. A Simple Resource Record

An example of a simple *resource record* (RR):

```
example.com.      86400      IN          A           192.0.2.1
```

The domain name, **example.com**, is the *owner* for the RR. The value **86400** is the *time to live* (TTL). The letters **IN**, meaning “the Internet system”, indicate the *class* of the RR. The letter **A** indicates the *type* of RR (in this example, a host address). The host address **192.0.2.1** is the data contained in the final section of this RR. This one line example is a RR. A set of RRs with the same type, owner, and class is called a *resource record set* (RRSet).

Zones are defined on authoritative name servers through the use of *zone files*, which contain definitions of the resource records in each zone. Zone files are stored on *primary name servers* (also called *master name servers*), where changes are made to the files, and *secondary name servers* (also called *slave name servers*), which receive zone definitions from the primary name servers. Both primary and secondary name servers are authoritative for the zone and look the same to clients. Depending on the configuration, any name server can also serve as a primary or secondary server for multiple zones at the same time.

Note that administrators of **DNS** and **DHCP** servers, as well as any provisioning applications, should agree on the host name format used in an organization. See [Section 3.1.1, “Recommended Naming Practices”](#) for more information on the format of host names.

11.1.2. Name server Types

There are two name server configuration types:

authoritative

Authoritative name servers answer to resource records that are part of their zones only. This category includes both primary (master) and secondary (slave) name servers.

recursive

Recursive name servers offer resolution services, but they are not authoritative for any zone. Answers for all resolutions are cached in a memory for a fixed period of time, which is specified by the retrieved resource record.

Although a name server can be both authoritative and recursive at the same time, it is recommended not to combine the configuration types. To be able to perform their work, authoritative servers should be available to all clients all the time. On the other hand, since the recursive lookup takes far more time than authoritative responses, recursive servers should be available to a restricted number of clients only, otherwise they are prone to distributed denial of service (DDoS) attacks.

11.1.3. BIND as a Name server

BIND consists of a set of DNS-related programs. It contains a name server called `named`, an administration utility called `rndc`, and a debugging tool called `dig`. See [Red Hat Enterprise Linux System Administrator's Guide](#) for more information on how to run a service in Red Hat Enterprise Linux.

11.2. BIND

This section covers **BIND** (Berkeley Internet Name Domain), the **DNS** server included in Red Hat Enterprise Linux. It focuses on the structure of its configuration files, and describes how to administer it both locally and remotely.

11.2.1. Empty Zones

BIND configures a number of “empty zones” to prevent recursive servers from sending unnecessary queries to Internet servers that cannot handle them (thus creating delays and SERVFAIL responses to clients who query for them). These empty zones ensure that immediate and authoritative NXDOMAIN responses are returned instead. The configuration option `empty-zones-enable` controls whether or not empty zones are created, whilst the option `disable-empty-zone` can be used in addition to disable one or more empty zones from the list of default prefixes that would be used.

The number of empty zones created for [RFC 1918](#) prefixes has been increased, and users of **BIND 9.9** and above will see the [RFC 1918](#) empty zones both when `empty-zones-enable` is unspecified (defaults to `yes`), and when it is explicitly set to `yes`.

11.2.2. Configuring the named Service

When the `named` service is started, it reads the configuration from the files as described in [Table 11.1, “The named Service Configuration Files”](#).

Table 11.1. The named Service Configuration Files

Path	Description
<code>/etc/named.conf</code>	The main configuration file.
<code>/etc/named/</code>	An auxiliary directory for configuration files that are included in the main configuration file.

The configuration file consists of a collection of statements with nested options surrounded by opening and closing curly brackets (`{` and `}`). Note that when editing the file, you have to be careful not to make any syntax error, otherwise the `named` service will not start. A typical `/etc/named.conf` file is organized as follows:

```
statement-1 ["statement-1-name"] [statement-1-class] {
    option-1;
    option-2;
    option-N;
};
statement-2 ["statement-2-name"] [statement-2-class] {
    option-1;
    option-2;
    option-N;
};
statement-N ["statement-N-name"] [statement-N-class] {
    option-1;
    option-2;
    option-N;
};
```


NOTE

If you have installed the `bind-chroot` package, the BIND service will run in the `chroot` environment. In that case, the initialization script will mount the above configuration files using the `mount --bind` command, so that you can manage the configuration outside this environment. There is no need to copy anything into the `/var/named/chroot/` directory because it is mounted automatically. This simplifies maintenance since you do not need to take any special care of BIND configuration files if it is run in a `chroot` environment. You can organize everything as you would with BIND not running in a `chroot` environment.

The following directories are automatically mounted into the `/var/named/chroot/` directory if the corresponding mount point directories underneath `/var/named/chroot/` are empty:

- `/etc/named`
- `/etc/pki/dnssec-keys`
- `/run/named`
- `/var/named`
- `/usr/lib64/bind` or `/usr/lib/bind` (architecture dependent).

The following files are also mounted if the target file does not exist in `/var/named/chroot/`:

- `/etc/named.conf`
- `/etc/rndc.conf`
- `/etc/rndc.key`
- `/etc/named.rfc1912.zones`
- `/etc/named.dnssec.keys`
- `/etc/named.iscdlv.key`
- `/etc/named.root.key`

IMPORTANT

Editing files which have been mounted in a `chroot` environment requires creating a backup copy and then editing the original file. Alternatively, use an editor with “edit-a-copy” mode disabled. For example, to edit the BIND's configuration file, `/etc/named.conf`, with Vim while it is running in a `chroot` environment, issue the following command as root:

```
~]# vim -c "set backupcopy=yes" /etc/named.conf
```

11.2.2.1. Installing BIND in a chroot Environment

To install **BIND** to run in a **chroot** environment, issue the following command as **root**:

```
~]# yum install bind-chroot
```

To enable the **named-chroot** service, first check if the **named** service is running by issuing the following command:

```
~]$ systemctl status named
```

If it is running, it must be disabled.

To disable **named**, issue the following commands as **root**:

```
~]# systemctl stop named
```

```
~]# systemctl disable named
```

Then, to enable the **named-chroot** service, issue the following commands as **root**:

```
~]# systemctl enable named-chroot
```

```
~]# systemctl start named-chroot
```

To check the status of the **named-chroot** service, issue the following command as **root**:

```
~]# systemctl status named-chroot
```

11.2.2.2. Common Statement Types

The following types of statements are commonly used in `/etc/named.conf`:

acl

The **acl** (Access Control List) statement allows you to define groups of hosts, so that they can be permitted or denied access to the nameserver. It takes the following form:

```
acl acl-name {
    match-element;
    ...
};
```

The *acl-name* statement name is the name of the access control list, and the *match-element* option is usually an individual **IP** address (such as `10.0.1.1`) or a *Classless Inter-Domain Routing* (CIDR) network notation (for example, `10.0.1.0/24`). For a list of already defined keywords, see [Table 11.2, “Predefined Access Control Lists”](#).

Table 11.2. Predefined Access Control Lists

Keyword	Description
any	Matches every IP address.

Keyword	Description
localhost	Matches any IP address that is in use by the local system.
localnets	Matches any IP address on any network to which the local system is connected.
none	Does not match any IP address.

The **acl** statement can be especially useful in conjunction with other statements such as **options**. [Example 11.2, “Using acl in Conjunction with Options”](#) defines two access control lists, **black-hats** and **red-hats**, and adds **black-hats** on the blacklist while granting **red-hats** normal access.

Example 11.2. Using acl in Conjunction with Options

```
acl black-hats {
    10.0.2.0/24;
    192.168.0.0/24;
    1234:5678::9abc/24;
};
acl red-hats {
    10.0.1.0/24;
};
options {
    blackhole { black-hats; };
    allow-query { red-hats; };
    allow-query-cache { red-hats; };
};
```

include

The **include** statement allows you to include files in the `/etc/named.conf`, so that potentially sensitive data can be placed in a separate file with restricted permissions. It takes the following form:

```
include "file-name"
```

The *file-name* statement name is an absolute path to a file.

Example 11.3. Including a File to `/etc/named.conf`

```
include "/etc/named.rfc1912.zones";
```

options

The **options** statement allows you to define global server configuration options as well as to set defaults for other statements. It can be used to specify the location of the **named** working directory, the types of queries allowed, and much more. It takes the following form:

```
options {
    option;
    ...
};
```

For a list of frequently used *option* directives, see [Table 11.3, “Commonly Used Configuration Options”](#) below.

Table 11.3. Commonly Used Configuration Options

Option	Description
allow-query	Specifies which hosts are allowed to query the nameserver for authoritative resource records. It accepts an access control list, a collection of IP addresses, or networks in the CIDR notation. All hosts are allowed by default.
allow-query-cache	Specifies which hosts are allowed to query the nameserver for non-authoritative data such as recursive queries. Only localhost and localnets are allowed by default.
blackhole	Specifies which hosts are <i>not</i> allowed to query the nameserver. This option should be used when a particular host or network floods the server with requests. The default option is none .
directory	Specifies a working directory for the named service. The default option is /var/named/ .
disable-empty-zone	Used to disable one or more empty zones from the list of default prefixes that would be used. Can be specified in the options statement and also in view statements. It can be used multiple times.
dnssec-enable	Specifies whether to return DNSSEC related resource records. The default option is yes .
dnssec-validation	Specifies whether to prove that resource records are authentic via DNSSEC. The default option is yes .
empty-zones-enable	Controls whether or not empty zones are created. Can be specified only in the options statement.
forwarders	Specifies a list of valid IP addresses for nameservers to which the requests should be forwarded for resolution.

Option	Description
forward	<p>Specifies the behavior of the forwarders directive. It accepts the following options:</p> <ul style="list-style-type: none"> • first – The server will query the nameservers listed in the forwarders directive before attempting to resolve the name on its own. • only – When unable to query the nameservers listed in the forwarders directive, the server will not attempt to resolve the name on its own.
listen-on	<p>Specifies the IPv4 network interface on which to listen for queries. On a DNS server that also acts as a gateway, you can use this option to answer queries originating from a single network only. All IPv4 interfaces are used by default.</p>
listen-on-v6	<p>Specifies the IPv6 network interface on which to listen for queries. On a DNS server that also acts as a gateway, you can use this option to answer queries originating from a single network only. All IPv6 interfaces are used by default.</p>
max-cache-size	<p>Specifies the maximum amount of memory to be used for server caches. When the limit is reached, the server causes records to expire prematurely so that the limit is not exceeded. In a server with multiple views, the limit applies separately to the cache of each view. The default option is 32M.</p>
notify	<p>Specifies whether to notify the secondary nameservers when a zone is updated. It accepts the following options:</p> <ul style="list-style-type: none"> • yes – The server will notify all secondary nameservers. • no – The server will <i>not</i> notify any secondary nameserver. • master-only – The server will notify primary server for the zone only. • explicit – The server will notify only the secondary servers that are specified in the also-notify list within a zone statement.
pid-file	<p>Specifies the location of the process ID file created by the named service.</p>
recursion	<p>Specifies whether to act as a recursive server. The default option is yes.</p>
statistics-file	<p>Specifies an alternate location for statistics files. The /var/named/named.stats file is used by default.</p>

**NOTE**

The directory used by `named` for runtime data has been moved from the BIND default location, `/var/run/named/`, to a new location `/run/named/`. As a result, the PID file has been moved from the default location `/var/run/named/named.pid` to the new location `/run/named/named.pid`. In addition, the session-key file has been moved to `/run/named/session.key`. These locations need to be specified by statements in the options section. See [Example 11.4, “Using the options Statement”](#).

**IMPORTANT**

To prevent distributed denial of service (DDoS) attacks, it is recommended that you use the `allow-query-cache` option to restrict recursive DNS services for a particular subset of clients only.

See the *BIND 9 Administrator Reference Manual* referenced in [Section 11.2.8.1, “Installed Documentation”](#), and the `named.conf` manual page for a complete list of available options.

Example 11.4. Using the options Statement

```
options {
    allow-query          { localhost; };
    listen-on port      53 { 127.0.0.1; };
    listen-on-v6 port   53 { ::1; };
    max-cache-size      256M;
    directory            "/var/named";
    statistics-file      "/var/named/data/named_stats.txt";

    recursion            yes;
    dnssec-enable        yes;
    dnssec-validation    yes;

    pid-file             "/run/named/named.pid";
    session-keyfile       "/run/named/session.key";
};
```

zone

The `zone` statement allows you to define the characteristics of a zone, such as the location of its configuration file and zone-specific options, and can be used to override the global `options` statements. It takes the following form:

```
zone zone-name [zone-class] {
    option;
    ...
};
```

The `zone-name` attribute is the name of the zone, `zone-class` is the optional class of the zone, and `option` is a `zone` statement option as described in [Table 11.4, “Commonly Used Options in Zone Statements”](#).

The `zone-name` attribute is particularly important, as it is the default value assigned for the

\$ORIGIN directive used within the corresponding zone file located in the `/var/named/` directory. The **named** daemon appends the name of the zone to any non-fully qualified domain name listed in the zone file. For example, if a **zone** statement defines the namespace for **example.com**, use **example.com** as the *zone-name* so that it is placed at the end of host names within the **example.com** zone file.

For more information about zone files, see [Section 11.2.3, “Editing Zone Files”](#).

Table 11.4. Commonly Used Options in Zone Statements

Option	Description
allow-query	Specifies which clients are allowed to request information about this zone. This option overrides global allow-query option. All query requests are allowed by default.
allow-transfer	Specifies which secondary servers are allowed to request a transfer of the zone's information. All transfer requests are allowed by default.
allow-update	<p>Specifies which hosts are allowed to dynamically update information in their zone. The default option is to deny all dynamic update requests.</p> <p>Note that you should be careful when allowing hosts to update information about their zone. Do not set IP addresses in this option unless the server is in the trusted network. Instead, use TSIG key as described in Section 11.2.6.3, “Transaction SIGnatures (TSIG)”.</p>
file	Specifies the name of the file in the named working directory that contains the zone's configuration data.
masters	Specifies from which IP addresses to request authoritative zone information. This option is used only if the zone is defined as type slave .
notify	<p>Specifies whether to notify the secondary nameservers when a zone is updated. It accepts the following options:</p> <ul style="list-style-type: none"> • yes – The server will notify all secondary nameservers. • no – The server will <i>not</i> notify any secondary nameserver. • master-only – The server will notify primary server for the zone only. • explicit – The server will notify only the secondary servers that are specified in the also-notify list within a zone statement.

Option	Description
type	<p>Specifies the zone type. It accepts the following options:</p> <ul style="list-style-type: none"> • delegation-only – Enforces the delegation status of infrastructure zones such as COM, NET, or ORG. Any answer that is received without an explicit or implicit delegation is treated as NXDOMAIN. This option is only applicable in TLDs (Top-Level Domain) or root zone files used in recursive or caching implementations. • forward – Forwards all requests for information about this zone to other nameservers. • hint – A special type of zone used to point to the root nameservers which resolve queries when a zone is not otherwise known. No configuration beyond the default is necessary with a hint zone. • master – Designates the nameserver as authoritative for this zone. A zone should be set as the master if the zone's configuration files reside on the system. • slave – Designates the nameserver as a slave server for this zone. Master server is specified in masters directive.

Most changes to the `/etc/named.conf` file of a primary or secondary nameserver involve adding, modifying, or deleting zone statements, and only a small subset of zone statement options is usually needed for a nameserver to work efficiently.

In [Example 11.5, “A Zone Statement for a Primary nameserver”](#), the zone is identified as `example.com`, the type is set to `master`, and the `named` service is instructed to read the `/var/named/example.com.zone` file. It also allows only a secondary nameserver (`192.168.0.2`) to transfer the zone.

Example 11.5. A Zone Statement for a Primary nameserver

```
zone "example.com" IN {
    type master;
    file "example.com.zone";
    allow-transfer { 192.168.0.2; };
};
```

A secondary server's zone statement is slightly different. The type is set to `slave`, and the `masters` directive is telling `named` the IP address of the master server.

In [Example 11.6, “A Zone Statement for a Secondary nameserver”](#), the `named` service is configured to query the primary server at the `192.168.0.1` IP address for information about the `example.com` zone. The received information is then saved to the `/var/named/slaves/example.com.zone` file. Note that you have to put all slave zones in the `/var/named/slaves/` directory, otherwise the service will fail to transfer the zone.

Example 11.6. A Zone Statement for a Secondary nameserver


```
zone "example.com" {
    type slave;
    file "slaves/example.com.zone";
    masters { 192.168.0.1; };
};
```

11.2.2.3. Other Statement Types

The following types of statements are less commonly used in `/etc/named.conf`:

controls

The **controls** statement allows you to configure various security requirements necessary to use the **rndc** command to administer the **named** service.

See [Section 11.2.4, “Using the rndc Utility”](#) for more information on the **rndc** utility and its usage.

key

The **key** statement allows you to define a particular key by name. Keys are used to authenticate various actions, such as secure updates or the use of the **rndc** command. Two options are used with **key**:

- **algorithm** *algorithm-name* – The type of algorithm to be used (for example, **hmac-md5**).
- **secret** *"key-value"* – The encrypted key.

Refer to [Section 11.2.4, “Using the rndc Utility”](#) for more information on the **rndc** utility and its usage.

logging

The **logging** statement allows you to use multiple types of logs, so called *channels*. By using the **channel** option within the statement, you can construct a customized type of log with its own file name (**file**), size limit (**size**), version number (**version**), and level of importance (**severity**). Once a customized channel is defined, a **category** option is used to categorize the channel and begin logging when the **named** service is restarted.

By default, **named** sends standard messages to the **rsyslog** daemon, which places them in `/var/log/messages`. Several standard channels are built into BIND with various severity levels, such as **default_syslog** (which handles informational logging messages) and **default_debug** (which specifically handles debugging messages). A default category, called **default**, uses the built-in channels to do normal logging without any special configuration.

Customizing the logging process can be a very detailed process and is beyond the scope of this chapter. For information on creating custom BIND logs, refer to the *BIND 9 Administrator Reference Manual* referenced in [Section 11.2.8.1, “Installed Documentation”](#).

server

The **server** statement allows you to specify options that affect how the **named** service should respond to remote nameservers, especially with regard to notifications and zone transfers.

The **transfer-format** option controls the number of resource records that are sent with each message. It can be either **one-answer** (only one resource record), or **many-answers** (multiple resource records). Note that while the **many-answers** option is more efficient, it is not supported by older versions of BIND.

trusted-keys

The **trusted-keys** statement allows you to specify assorted public keys used for secure **DNS** (DNSSEC). Refer to [Section 11.2.6.4, “DNS Security Extensions \(DNSSEC\)”](#) for more information on this topic.

view

The **view** statement allows you to create special views depending upon which network the host querying the nameserver is on. This allows some hosts to receive one answer regarding a zone while other hosts receive totally different information. Alternatively, certain zones may only be made available to particular trusted hosts while non-trusted hosts can only make queries for other zones.

Multiple views can be used as long as their names are unique. The **match-clients** option allows you to specify the **IP** addresses that apply to a particular view. If the **options** statement is used within a view, it overrides the already configured global options. Finally, most **view** statements contain multiple **zone** statements that apply to the **match-clients** list.

Note that the order in which the **view** statements are listed is important, as the first statement that matches a particular client's **IP** address is used. For more information on this topic, refer to [Section 11.2.6.1, “Multiple Views”](#).

11.2.2.4. Comment Tags

Additionally to statements, the `/etc/named.conf` file can also contain comments. Comments are ignored by the **named** service, but can prove useful when providing additional information to a user. The following are valid comment tags:

`//`

Any text after the `//` characters to the end of the line is considered a comment. For example:

```
notify yes; // notify all secondary nameservers
```

`#`

Any text after the `#` character to the end of the line is considered a comment. For example:

```
notify yes; # notify all secondary nameservers
```

`/* and */`

Any block of text enclosed in `/*` and `*/` is considered a comment. For example:

```
notify yes; /* notify all secondary nameservers */
```

11.2.3. Editing Zone Files

As outlined in [Section 11.1.1, “Name server Zones”](#), zone files contain information about a namespace. They are stored in the **named** working directory located in `/var/named/` by default. Each zone file is named according to the `file` option in the `zone` statement, usually in a way that relates to the domain in and identifies the file as containing zone data, such as `example.com.zone`.

Table 11.5. The named Service Zone Files

Path	Description
<code>/var/named/</code>	The working directory for the named service. The nameserver is <i>not</i> allowed to write to this directory.
<code>/var/named/slaves/</code>	The directory for secondary zones. This directory is writable by the named service.
<code>/var/named/dynamic/</code>	The directory for other files, such as dynamic DNS (DDNS) zones or managed DNSSEC keys. This directory is writable by the named service.
<code>/var/named/data/</code>	The directory for various statistics and debugging files. This directory is writable by the named service.

A zone file consists of directives and resource records. Directives tell the nameserver to perform tasks or apply special settings to the zone, resource records define the parameters of the zone and assign identities to individual hosts. While the directives are optional, the resource records are required in order to provide name service to a zone.

All directives and resource records should be entered on individual lines.

11.2.3.1. Common Directives

Directives begin with the dollar sign character (\$) followed by the name of the directive, and usually appear at the top of the file. The following directives are commonly used in zone files:

\$INCLUDE

The **\$INCLUDE** directive allows you to include another file at the place where it appears, so that other zone settings can be stored in a separate zone file.

Example 11.7. Using the \$INCLUDE Directive

```
$INCLUDE /var/named/penguin.example.com
```

\$ORIGIN

The **\$ORIGIN** directive allows you to append the domain name to unqualified records, such as those with the host name only. Note that the use of this directive is not necessary if the zone is specified in `/etc/named.conf`, since the zone name is used by default.

In [Example 11.8, “Using the \\$ORIGIN Directive”](#), any names used in resource records that do not end in a trailing period (the `.` character) are appended with `example.com`.

Example 11.8. Using the \$ORIGIN Directive

```
$ORIGIN example.com.
```

\$TTL

The **\$TTL** directive allows you to set the default *Time to Live* (TTL) value for the zone, that is, how long is a zone record valid. Each resource record can contain its own TTL value, which overrides this directive.

Increasing this value allows remote nameservers to cache the zone information for a longer period of time, reducing the number of queries for the zone and lengthening the amount of time required to propagate resource record changes.

Example 11.9. Using the \$TTL Directive

```
$TTL 1D
```

11.2.3.2. Common Resource Records

The following resource records are commonly used in zone files:

A

The *Address* record specifies an **IP** address to be assigned to a name. It takes the following form:

```
hostname IN A IP-address
```

If the *hostname* value is omitted, the record will point to the last specified *hostname*.

In [Example 11.10, “Using the A Resource Record”](#), the requests for `server1.example.com` are pointed to `10.0.1.3` or `10.0.1.5`.

Example 11.10. Using the A Resource Record

```
server1 IN A 10.0.1.3
        IN A 10.0.1.5
```

CNAME

The *Canonical Name* record maps one name to another. Because of this, this type of record is sometimes referred to as an *alias record*. It takes the following form:

```
alias-name IN CNAME real-name
```

CNAME records are most commonly used to point to services that use a common naming scheme, such as `www` for Web servers. However, there are multiple restrictions for their usage:

- CNAME records should not point to other CNAME records. This is mainly to avoid possible infinite loops.
- CNAME records should not contain other resource record types (such as A, NS, MX, and so on). The only exception are DNSSEC related records (RRSIG, NSEC, and so on) when the zone is signed.
- Other resource records that point to the fully qualified domain name (FQDN) of a host (NS, MX, PTR) should not point to a CNAME record.

In [Example 11.11, “Using the CNAME Resource Record”](#), the A record binds a host name to an IP address, while the CNAME record points the commonly used `www` host name to it.

Example 11.11. Using the CNAME Resource Record

```
server1  IN  A      10.0.1.5
www      IN  CNAME  server1
```

MX

The *Mail Exchange* record specifies where the mail sent to a particular namespace controlled by this zone should go. It takes the following form:

```
IN MX preference-value email-server-name
```

The *email-server-name* is a fully qualified domain name (FQDN). The *preference-value* allows numerical ranking of the email servers for a namespace, giving preference to some email systems over others. The MX resource record with the lowest *preference-value* is preferred over the others. However, multiple email servers can possess the same value to distribute email traffic evenly among them.

In [Example 11.12, “Using the MX Resource Record”](#), the first `mail.example.com` email server is preferred to the `mail2.example.com` email server when receiving email destined for the `example.com` domain.

Example 11.12. Using the MX Resource Record

```
example.com.  IN  MX  10  mail.example.com.
              IN  MX  20  mail2.example.com.
```

NS

The *Nameserver* record announces authoritative nameservers for a particular zone. It takes the following form:

```
IN NS nameserver-name
```

The *nameserver-name* should be a fully qualified domain name (FQDN). Note that when two nameservers are listed as authoritative for the domain, it is not important whether these nameservers are secondary nameservers, or if one of them is a primary server. They are both still considered authoritative.

Example 11.13. Using the NS Resource Record

```
IN  NS  dns1.example.com.  
IN  NS  dns2.example.com.
```

PTR

The *Pointer* record points to another part of the namespace. It takes the following form:

```
last-IP-digit IN PTR FQDN-of-system
```

The *last-IP-digit* directive is the last number in an **IP** address, and the *FQDN-of-system* is a fully qualified domain name (FQDN).

PTR records are primarily used for reverse name resolution, as they point **IP** addresses back to a particular name. Refer to [Section 11.2.3.4.2, “A Reverse Name Resolution Zone File”](#) for examples of **PTR** records in use.

SOA

The *Start of Authority* record announces important authoritative information about a namespace to the nameserver. Located after the directives, it is the first resource record in a zone file. It takes the following form:

```
@  IN  SOA  primary-name-server hostmaster-email (  
    serial-number  
    time-to-refresh  
    time-to-retry  
    time-to-expire  
    minimum-TTL )
```

The directives are as follows:

- The **@** symbol places the **\$ORIGIN** directive (or the zone's name if the **\$ORIGIN** directive is not set) as the namespace being defined by this **SOA** resource record.
- The *primary-name-server* directive is the host name of the primary nameserver that is authoritative for this domain.
- The *hostmaster-email* directive is the email of the person to contact about the namespace.
- The *serial-number* directive is a numerical value incremented every time the zone file is altered to indicate it is time for the **named** service to reload the zone.
- The *time-to-refresh* directive is the numerical value secondary nameservers use to determine how long to wait before asking the primary nameserver if any changes have been made to the zone.
- The *time-to-retry* directive is a numerical value used by secondary nameservers to determine the length of time to wait before issuing a refresh request in the event that the primary nameserver is not answering. If the primary server has not replied to a refresh request before the amount of time specified in the *time-to-expire* directive elapses, the secondary servers stop responding as an authority for requests concerning that namespace.

- In BIND 4 and 8, the *minimum-TTL* directive is the amount of time other nameservers cache the zone's information. In BIND 9, it defines how long negative answers are cached for. Caching of negative answers can be set to a maximum of 3 hours (3H).

When configuring BIND, all times are specified in seconds. However, it is possible to use abbreviations when specifying units of time other than seconds, such as minutes (M), hours (H), days (D), and weeks (W). [Table 11.6, “Seconds compared to other time units”](#) shows an amount of time in seconds and the equivalent time in another format.

Table 11.6. Seconds compared to other time units

Seconds	Other Time Units
60	1M
1800	30M
3600	1H
10800	3H
21600	6H
43200	12H
86400	1D
259200	3D
604800	1W
31536000	365D

Example 11.14. Using the SOA Resource Record

```
@ IN SOA dns1.example.com. hostmaster.example.com. (
    2001062501 ; serial
    21600      ; refresh after 6 hours
    3600       ; retry after 1 hour
    604800     ; expire after 1 week
    86400 )    ; minimum TTL of 1 day
```

11.2.3.3. Comment Tags

Additionally to resource records and directives, a zone file can also contain comments. Comments are ignored by the `named` service, but can prove useful when providing additional information to the user. Any text after the semicolon character to the end of the line is considered a comment. For example:

```
604800 ; expire after 1 week
```

11.2.3.4. Example Usage

The following examples show the basic usage of zone files.

11.2.3.4.1. A Simple Zone File

[Example 11.15, “A simple zone file”](#) demonstrates the use of standard directives and SOA values.

Example 11.15. A simple zone file

```
$ORIGIN example.com.
$TTL 86400
@           IN  SOA  dns1.example.com.  hostmaster.example.com. (
                2001062501  ; serial
                21600       ; refresh after 6 hours
                3600        ; retry after 1 hour
                604800      ; expire after 1 week
                86400 )     ; minimum TTL of 1 day
;
;
                IN  NS   dns1.example.com.
                IN  NS   dns2.example.com.
dns1           IN  A     10.0.1.1
                IN  AAAA  aaaa:bbbb::1
dns2           IN  A     10.0.1.2
                IN  AAAA  aaaa:bbbb::2
;
;
@           IN  MX     10  mail.example.com.
                IN  MX     20  mail2.example.com.
mail        IN  A       10.0.1.5
                IN  AAAA  aaaa:bbbb::5
mail2       IN  A       10.0.1.6
                IN  AAAA  aaaa:bbbb::6
;
;
; This sample zone file illustrates sharing the same IP addresses
; for multiple services:
;
services    IN  A       10.0.1.10
                IN  AAAA  aaaa:bbbb::10
                IN  A       10.0.1.11
                IN  AAAA  aaaa:bbbb::11

ftp          IN  CNAME   services.example.com.
www          IN  CNAME   services.example.com.
;
;
```


In this example, the authoritative nameservers are set as `dns1.example.com` and `dns2.example.com`, and are tied to the `10.0.1.1` and `10.0.1.2` IP addresses respectively using the A record.

The email servers configured with the MX records point to `mail` and `mail2` via A records. Since these names do not end in a trailing period, the `$ORIGIN` domain is placed after them, expanding them to `mail.example.com` and `mail2.example.com`.

Services available at the standard names, such as `www.example.com` (WWW), are pointed at the appropriate servers using the CNAME record.

This zone file would be called into service with a `zone` statement in the `/etc/named.conf` similar to the following:

```
zone "example.com" IN {
    type master;
    file "example.com.zone";
    allow-update { none; };
};
```

11.2.3.4.2. A Reverse Name Resolution Zone File

A reverse name resolution zone file is used to translate an IP address in a particular namespace into a fully qualified domain name (FQDN). It looks very similar to a standard zone file, except that the PTR resource records are used to link the IP addresses to a fully qualified domain name as shown in [Example 11.16, “A reverse name resolution zone file”](#).

Example 11.16. A reverse name resolution zone file

```
$ORIGIN 1.0.10.in-addr.arpa.
$TTL 86400
@ IN SOA dns1.example.com. hostmaster.example.com. (
    2001062501 ; serial
    21600      ; refresh after 6 hours
    3600       ; retry after 1 hour
    604800     ; expire after 1 week
    86400 )    ; minimum TTL of 1 day
;
@ IN NS dns1.example.com.
;
1 IN PTR dns1.example.com.
2 IN PTR dns2.example.com.
;
5 IN PTR server1.example.com.
6 IN PTR server2.example.com.
;
3 IN PTR ftp.example.com.
4 IN PTR ftp.example.com.
```

In this example, IP addresses `10.0.1.1` through `10.0.1.6` are pointed to the corresponding fully qualified domain name.

This zone file would be called into service with a `zone` statement in the `/etc/named.conf` file similar to the following:

```
zone "1.0.10.in-addr.arpa" IN {
    type master;
    file "example.com.rr.zone";
    allow-update { none; };
};
```

There is very little difference between this example and a standard `zone` statement, except for the zone name. Note that a reverse name resolution zone requires the first three blocks of the `IP` address reversed followed by `.in-addr.arpa`. This allows the single block of `IP` numbers used in the reverse name resolution zone file to be associated with the zone.

11.2.4. Using the `rndc` Utility

The `rndc` utility is a command-line tool that allows you to administer the `named` service, both locally and from a remote machine. Its usage is as follows:

```
rndc [option...] command [command-option]
```

11.2.4.1. Configuring the Utility

To prevent unauthorized access to the service, `named` must be configured to listen on the selected port (953 by default), and an identical key must be used by both the service and the `rndc` utility.


Table 11.7. Relevant files

Path	Description
<code>/etc/named.conf</code>	The default configuration file for the <code>named</code> service.
<code>/etc/rndc.conf</code>	The default configuration file for the <code>rndc</code> utility.
<code>/etc/rndc.key</code>	The default key location.

The `rndc` configuration is located in `/etc/rndc.conf`. If the file does not exist, the utility will use the key located in `/etc/rndc.key`, which was generated automatically during the installation process using the `rndc-confgen -a` command.

The `named` service is configured using the `controls` statement in the `/etc/named.conf` configuration file as described in [Section 11.2.2.3, “Other Statement Types”](#). Unless this statement is present, only the connections from the loopback address (`127.0.0.1`) will be allowed, and the key located in `/etc/rndc.key` will be used.

For more information on this topic, refer to manual pages and the *BIND 9 Administrator Reference Manual* listed in [Section 11.2.8, “Additional Resources”](#).



IMPORTANT

To prevent unprivileged users from sending control commands to the service, make sure only **root** is allowed to read the `/etc/rndc.key` file:

```
~]# chmod o-rwx /etc/rndc.key
```

11.2.4.2. Checking the Service Status

To check the current status of the **named** service, use the following command:

```
~]# rndc status
version: 9.7.0-P2-RedHat-9.7.0-5.P2.el6
CPUs found: 1
worker threads: 1
number of zones: 16
debug level: 0
xfers running: 0
xfers deferred: 0
soa queries in progress: 0
query logging is OFF
recursive clients: 0/0/1000
tcp clients: 0/100
server is up and running
```

11.2.4.3. Reloading the Configuration and Zones

To reload both the configuration file and zones, type the following at a shell prompt:

```
~]# rndc reload
server reload successful
```


This will reload the zones while keeping all previously cached responses, so that you can make changes to the zone files without losing all stored name resolutions.

To reload a single zone, specify its name after the **reload** command, for example:

```
~]# rndc reload localhost
zone reload up-to-date
```

Finally, to reload the configuration file and newly added zones only, type:

```
~]# rndc reconfig
```

**NOTE**

If you intend to manually modify a zone that uses Dynamic DNS (DDNS), make sure you run the **freeze** command first:

```
~]# rndc freeze localhost
```

Once you are finished, run the **thaw** command to allow the **DDNS** again and reload the zone:

```
~]# rndc thaw localhost
The zone reload and thaw was successful.
```

11.2.4.4. Updating Zone Keys

To update the DNSSEC keys and sign the zone, use the **sign** command. For example:

```
~]# rndc sign localhost
```

Note that to sign a zone with the above command, the **auto-dnssec** option has to be set to **maintain** in the zone statement. For example:

```
zone "localhost" IN {
    type master;
    file "named.localhost";
    allow-update { none; };
    auto-dnssec maintain;
};
```

11.2.4.5. Enabling the DNSSEC Validation

To enable the DNSSEC validation, issue the following command as **root**:

```
~]# rndc validation on
```

Similarly, to disable this option, type:

```
~]# rndc validation off
```

Refer to the **options** statement described in [Section 11.2.2.2, “Common Statement Types”](#) for information on how to configure this option in `/etc/named.conf`.

The [Red Hat Enterprise Linux 7 Security Guide](#) has a comprehensive section on DNSSEC.

11.2.4.6. Enabling the Query Logging

To enable (or disable in case it is currently enabled) the query logging, issue the following command as **root**:

```
~]# rndc querylog
```

To check the current setting, use the `status` command as described in [Section 11.2.4.2, “Checking the Service Status”](#).

11.2.5. Using the dig Utility

The `dig` utility is a command-line tool that allows you to perform DNS lookups and debug a nameserver configuration. Its typical usage is as follows:

```
dig [@server] [option...] name type
```

Refer to [Section 11.2.3.2, “Common Resource Records”](#) for a list of common values to use for `type`.

11.2.5.1. Looking Up a Nameserver

To look up a nameserver for a particular domain, use the command in the following form:

```
dig name NS
```

In [Example 11.17, “A sample nameserver lookup”](#), the `dig` utility is used to display nameservers for `example.com`.

Example 11.17. A sample nameserver lookup

```
~]$ dig example.com NS

; <<>> DiG 9.7.1-P2-RedHat-9.7.1-2.P2.fc13 <<>> example.com NS
;; global options: +cmd
;; Got answer:
;; ->>HEADER<<- opcode: QUERY, status: NOERROR, id: 57883
;; flags: qr rd ra; QUERY: 1, ANSWER: 2, AUTHORITY: 0, ADDITIONAL: 0

;; QUESTION SECTION:
;example.com.                IN      NS

;; ANSWER SECTION:
example.com.                 99374   IN      NS      a.iana-servers.net.
example.com.                 99374   IN      NS      b.iana-servers.net.

;; Query time: 1 msec
;; SERVER: 10.34.255.7#53(10.34.255.7)
;; WHEN: Wed Aug 18 18:04:06 2010
;; MSG SIZE rcvd: 77
```

11.2.5.2. Looking Up an IP Address

To look up an IP address assigned to a particular domain, use the command in the following form:

```
dig name A
```

In [Example 11.18, “A sample IP address lookup”](#), the `dig` utility is used to display the IP address of `example.com`.

Example 11.18. A sample IP address lookup

```

~]$ dig example.com A

; <<>> DiG 9.7.1-P2-RedHat-9.7.1-2.P2.fc13 <<>> example.com A
;; global options: +cmd
;; Got answer:
;; ->>HEADER<<- opcode: QUERY, status: NOERROR, id: 4849
;; flags: qr rd ra; QUERY: 1, ANSWER: 1, AUTHORITY: 2, ADDITIONAL: 0

;; QUESTION SECTION:
;example.com.                IN      A

;; ANSWER SECTION:
example.com.                 155606  IN      A      192.0.32.10

;; AUTHORITY SECTION:
example.com.                 99175   IN      NS      a.iana-servers.net.
example.com.                 99175   IN      NS      b.iana-servers.net.

;; Query time: 1 msec
;; SERVER: 10.34.255.7#53(10.34.255.7)
;; WHEN: Wed Aug 18 18:07:25 2010
;; MSG SIZE rcvd: 93

```

11.2.5.3. Looking Up a Host Name

To look up a host name for a particular IP address, use the command in the following form:

```
dig -x address
```

In [Example 11.19, “A Sample Host Name Lookup”](#), the **dig** utility is used to display the host name assigned to **192.0.32.10**.

Example 11.19. A Sample Host Name Lookup

```

~]$ dig -x 192.0.32.10

; <<>> DiG 9.7.1-P2-RedHat-9.7.1-2.P2.fc13 <<>> -x 192.0.32.10
;; global options: +cmd
;; Got answer:
;; ->>HEADER<<- opcode: QUERY, status: NOERROR, id: 29683
;; flags: qr rd ra; QUERY: 1, ANSWER: 1, AUTHORITY: 5, ADDITIONAL: 6

;; QUESTION SECTION:
;10.32.0.192.in-addr.arpa.    IN      PTR

;; ANSWER SECTION:
10.32.0.192.in-addr.arpa. 21600  IN      PTR      www.example.com.

;; AUTHORITY SECTION:
32.0.192.in-addr.arpa.    21600  IN      NS      b.iana-servers.org.
32.0.192.in-addr.arpa.    21600  IN      NS      c.iana-servers.net.

```

```

32.0.192.in-addr.arpa. 21600 IN NS d.iana-servers.net.
32.0.192.in-addr.arpa. 21600 IN NS ns.icann.org.
32.0.192.in-addr.arpa. 21600 IN NS a.iana-servers.net.


;; ADDITIONAL SECTION:
a.iana-servers.net. 13688 IN A 192.0.34.43
b.iana-servers.org. 5844 IN A 193.0.0.236
b.iana-servers.org. 5844 IN AAAA 2001:610:240:2::c100:ec
c.iana-servers.net. 12173 IN A 139.91.1.10
c.iana-servers.net. 12173 IN AAAA 2001:648:2c30::1:10
ns.icann.org. 12884 IN A 192.0.34.126

;; Query time: 156 msec
;; SERVER: 10.34.255.7#53(10.34.255.7)
;; WHEN: Wed Aug 18 18:25:15 2010
;; MSG SIZE rcvd: 310

```

11.2.6. Advanced Features of BIND

Most BIND implementations only use the `named` service to provide name resolution services or to act as an authority for a particular domain. However, BIND version 9 has a number of advanced features that allow for a more secure and efficient DNS service.



IMPORTANT

Before attempting to use advanced features like DNSSEC, TSIG, or IXFR (Incremental Zone Transfer), make sure that the particular feature is supported by all nameservers in the network environment, especially when you use older versions of BIND or non-BIND servers.

All of the features mentioned are discussed in greater detail in the *BIND 9 Administrator Reference Manual* referenced in [Section 11.2.8.1, “Installed Documentation”](#).

11.2.6.1. Multiple Views

Optionally, different information can be presented to a client depending on the network a request originates from. This is primarily used to deny sensitive DNS entries from clients outside of the local network, while allowing queries from clients inside the local network.

To configure multiple views, add the `view` statement to the `/etc/named.conf` configuration file. Use the `match-clients` option to match IP addresses or entire networks and give them special options and zone data.

11.2.6.2. Incremental Zone Transfers (IXFR)


Incremental Zone Transfers (IXFR) allow a secondary nameserver to only download the updated portions of a zone modified on a primary nameserver. Compared to the standard transfer process, this makes the notification and update process much more efficient.

Note that IXFR is only available when using dynamic updating to make changes to master zone records. If manually editing zone files to make changes, *Automatic Zone Transfer (AXFR)* is used.

11.2.6.3. Transaction SIGnatures (TSIG)

Transaction SIGnatures (TSIG) ensure that a shared secret key exists on both primary and secondary nameservers before allowing a transfer. This strengthens the standard **IP** address-based method of transfer authorization, since attackers would not only need to have access to the **IP** address to transfer the zone, but they would also need to know the secret key.

Since version 9, BIND also supports *TKEY*, which is another shared secret key method of authorizing zone transfers.



IMPORTANT

When communicating over an insecure network, do not rely on **IP** address-based authentication only.

11.2.6.4. DNS Security Extensions (DNSSEC)

Domain Name System Security Extensions (DNSSEC) provide origin authentication of **DNS** data, authenticated denial of existence, and data integrity. When a particular domain is marked as secure, the **SERVFAIL** response is returned for each resource record that fails the validation.

Note that to debug a DNSSEC-signed domain or a DNSSEC-aware resolver, you can use the **dig** utility as described in [Section 11.2.5, “Using the dig Utility”](#). Useful options are **+dnssec** (requests DNSSEC-related resource records by setting the DNSSEC OK bit), **+cd** (tells recursive nameserver not to validate the response), and **+bufsize=512** (changes the packet size to 512B to get through some firewalls).

11.2.6.5. Internet Protocol version 6 (IPv6)

Internet Protocol version 6 (IPv6) is supported through the use of **AAAA** resource records, and the **listen-on-v6** directive as described in [Table 11.3, “Commonly Used Configuration Options”](#).

11.2.7. Common Mistakes to Avoid

The following is a list of recommendations on how to avoid common mistakes users make when configuring a nameserver:

Use semicolons and curly brackets correctly

An omitted semicolon or unmatched curly bracket in the `/etc/named.conf` file can prevent the **named** service from starting.

Use period (the `.` character) correctly

In zone files, a period at the end of a domain name denotes a fully qualified domain name. If omitted, the **named** service will append the name of the zone or the value of `$ORIGIN` to complete it.

Increment the serial number when editing a zone file

If the serial number is not incremented, the primary nameserver will have the correct, new information, but the secondary nameservers will never be notified of the change, and will not attempt to refresh their data of that zone.

Configure the firewall

If a firewall is blocking connections from the **named** service to other nameservers, the recommended practice is to change the firewall settings.



WARNING

Using a fixed **UDP** source port for **DNS** queries is a potential security vulnerability that could allow an attacker to conduct cache-poisoning attacks more easily. To prevent this, by default **DNS** sends from a random ephemeral port. Configure your firewall to allow outgoing queries from a random **UDP** source port. The range **1024** to **65535** is used by default.

11.2.8. Additional Resources

The following sources of information provide additional resources regarding BIND.

11.2.8.1. Installed Documentation

BIND features a full range of installed documentation covering many different topics, each placed in its own subject directory. For each item below, replace *version* with the version of the `bind` package installed on the system:

`/usr/share/doc/bind-version/`

The main directory containing the most recent documentation. The directory contains the *BIND 9 Administrator Reference Manual* in HTML and PDF formats, which details BIND resource requirements, how to configure different types of nameservers, how to perform load balancing, and other advanced topics.

`/usr/share/doc/bind-version/sample/etc/`

The directory containing examples of **named** configuration files.

`rndc(8)`

The manual page for the **rndc** name server control utility, containing documentation on its usage.

`named(8)`

The manual page for the Internet domain name server **named**, containing documentation on assorted arguments that can be used to control the BIND nameserver daemon.

`lwresd(8)`

The manual page for the lightweight resolver daemon **lwresd**, containing documentation on the daemon and its usage.

`named.conf(5)`

The manual page with a comprehensive list of options available within the **named** configuration file.

`rndc.conf(5)`

The manual page with a comprehensive list of options available within the `rndc` configuration file.

11.2.8.2. Online Resources

<https://access.redhat.com/site/articles/770133>

A Red Hat Knowledgebase article about running BIND in a `chroot` environment, including the differences compared to Red Hat Enterprise Linux 6.

https://access.redhat.com/documentation/en-US/Red_Hat_Enterprise_Linux/7/html/Security_Guide/

The *Red Hat Enterprise Linux 7 Security Guide* has a comprehensive section on DNSSEC.

<https://www.icann.org/namecollision>

The *ICANN FAQ on domain name collision*.

CHAPTER 12. SQUID

This chapter deals with **Squid**, a high performance proxy caching server for web clients. In this section, you can read on how to configure **Squid**, how to authenticate, and block access with **Squid**.

12.1. INTRODUCTION TO SQUID

Squid is a proxy web server that optimizes website operation by caching pages so that they load more quickly, thereby improving the response time for the pages that users access most frequently. **Squid** provides proxy and cache services for Hypertext Transport Protocol (HTTP), File Transfer Protocol (FTP), and other popular protocols. **Squid** is mostly used for speeding up a web server by caching repeated requests, aiding security by filtering traffic, or for limiting user access to specific pages.

Squid supports **FTP**, **gopher**, **ICAP**, **ICP**, **HTCP**, and **HTTP** data objects.

Squid consists of:

- a main server program **Squid**
- optional programs for custom processing and authentication
- management and client tools

12.2. INSTALLING AND RUNNING SQUID

In Red Hat Enterprise Linux, the **squid** package provides the **Squid** Caching Proxy. Run the **rpm -q squid** command to see if the **squid** package is installed. If not, enter the following command as the **root** user to install it:

```
~]# yum install squid
```

Run the **systemctl start squid** command as the **root** user to start **Squid**:

```
~]# systemctl start squid
```

Squid will start listening on port 3128 (default) on all network interfaces on the machine.

Run the **systemctl status squid** command to confirm whether **Squid** is running. An example output is attached.

```
~]# systemctl status squid
• squid.service - Squid caching proxy
   Loaded: loaded (/usr/lib/systemd/system/squid.service; disabled; vendor
  preset: disabled)
   Active: active (running) since Wed 2016-04-06 13:15:05 CEST; 2min 17s
  ago
 [output truncated]
```

Run the **ps -eZ | grep squid** command to view the **Squid** processes:

```
~]# ps -eZ | grep squid
unconfined_u:system_r:squid_t:s0 2522 ?        00:00:00 squid
unconfined_u:system_r:squid_t:s0 2524 ?        00:00:00 squid
```

```
unconfined_u:system_r:squid_t:s0 2526 ? 00:00:00 ncsa_auth
unconfined_u:system_r:squid_t:s0 2527 ? 00:00:00 ncsa_auth
unconfined_u:system_r:squid_t:s0 2528 ? 00:00:00 ncsa_auth
unconfined_u:system_r:squid_t:s0 2529 ? 00:00:00 ncsa_auth
unconfined_u:system_r:squid_t:s0 2530 ? 00:00:00 ncsa_auth
unconfined_u:system_r:squid_t:s0 2531 ? 00:00:00 unlinkd
```

If you are interested in detailed performance statistics about **Squid** from a command line environment, use the **squidclient** tool that can access the **Squid** service and retrieve its statistics. For example, to get some general performance statistic, enter the following command on the **Squid** server:

```
~]# squidclient -p squid-port mgr:info
```

To stop **Squid**, issue this command:

```
~]# systemctl stop squid
```

Squid Log Files

The **Squid** proxy server log files are stored in the `/var/log/squid/` directory. The log file that stores information about proxied requests is the `/var/log/squid/access.log` file.

12.3. SQUID CONFIGURATION

To configure **Squid**, adjust the directives in the configuration file. **Squid** is normally configured according to the requirements of a given network using the command line and editing the **Squid** configuration file, located at `/etc/squid/squid.conf`, which contains recommended minimum configuration.

12.3.1. Basic Configuration and `/etc/squid/squid.conf`

Procedure 12.1. Basic configuration

1. Backup the original config file.

```
mv /etc/squid/squid.conf /etc/squid/squid.conf.org
```

2. Create a new `/etc/squid/squid.conf` file with the following contents. Edit the Access Control List (ACL) line for *mynetwork* to define source network for your local network. This is the network where client systems use the **Squid** server as their proxy.



NOTE

The order of the items in the `/etc/squid/squid.conf` configuration file is important as **Squid** reads it from the beginning.

```
acl mynetwork src xxx.xxx.xxx.0/24
http_access allow mynetwork

#defaults
acl localnet src 10.0.0.0/8
```

```

acl localnet src 172.16.0.0/12
acl localnet src 192.168.0.0/16
acl localnet src fc00::/7
acl localnet src fe80::/10
acl SSL_ports port 443
acl Safe_ports port 80
acl Safe_ports port 21
acl Safe_ports port 443
acl Safe_ports port 70
acl Safe_ports port 210
acl Safe_ports port 1025-65535
acl Safe_ports port 280
acl Safe_ports port 488
acl Safe_ports port 591
acl Safe_ports port 777
acl CONNECT method CONNECT
http_access allow manager localhost
http_access deny manager
http_access deny !Safe_ports
http_access deny CONNECT !SSL_ports
http_access allow localnet
http_access allow localhost
http_access deny all
http_port 3128
hierarchy_stoplist cgi-bin ?
coredump_dir /var/spool/squid
refresh_pattern ^ftp:      1440      20% 10080
refresh_pattern ^gopher:   1440      0%  1440
refresh_pattern -i (/cgi-bin/|\?) 0 0%  0
refresh_pattern .          0        20% 4320

```

3. Start the service and enable it on boot:

```

~]# systemctl enable squid
~]# systemctl start squid

```

4. If firewall is enabled, allow the **Squid** port.

```

~]# firewall-cmd --add-port=3128/tcp --permanent

```

5. Configure your web browser to use the proxy. This depends on the browser you use and its version. For example, to configure **Firefox** version 46.0.0:

Procedure 12.2. Configuring Firefox with Proxy

1. In the Firefox menu located in the top right corner, select **Preferences**, from the tabs on the left, select **Advanced**, and then select **Network** from the tabs located on the top bar.
2. In the **Connection** section, open **Settings**.
3. In the new window that opens up, tick **Manual proxy configuration** and enter the proxy server that you are connecting to in the **HTTP Proxy** field. If you need to enter a specific port, enter it into the **Port** field.

For more information on `/etc/squid/squid.conf`, see the `squid(8)` man page.

12.3.2. Configuring Squid as an HTTP proxy server

Procedure 12.3. Configuring Squid as an HTTP proxy server

1. Add the following lines to the top of the `/etc/squid/squid.conf` file replacing the example IP address :

```
cache_dir ufs /var/spool/squid 500 16 256
acl my_machine src 192.0.2.21 # Replace with your IP address
http_access allow my_machine
```

2. Create cache directories using the following command:

```
~]# systemctl restart squid
```

Squid now starts listening on port 3128 (default) on all network interfaces on the machine.

3. Configure your browser, for example **Firefox**, to use **Squid** as an HTTP proxy server with the host as the IP address of the machine and port 3128: for details, see [Procedure 12.2, “Configuring Firefox with Proxy”](#)

12.3.2.1. Setting the HTTP Port

The `http_port` directive is used to specify the port where **Squid** will listen for client connections. The default behavior is to listen on port 3128 on all the available interfaces on a machine. You can force **Squid** to listen on multiple interfaces and on different ports, on different interfaces.

Example 12.1. Specifying the HTTP Port

Open `/etc/squid/squid.conf` and edit the respective line. In this example, **Squid** is set up to listen on port 8080.


```
# Squid normally listens to port 3128
http_port 8080
```

The **Squid** server can listen on multiple ports at the same time.

Example 12.2. Specifying Two or More Ports

With the following setting, **Squid** listens on both port 8080 and port 9090:

```
http_port 8080 9090
```

**NOTE**

Do not forget to restart **Squid** server to apply new settings by running:

```
~]# systemctl restart squid
```

You can also specify the IP address and port combination in `/etc/squid/squid.conf`. Normally, this approach is used when you have multiple interfaces on the machine and want **Squid** to listen only on the interface connected to a local area network (LAN).

Example 12.3. Setting IP addresses

The following command instructs **Squid** to listen on port 3128 on the interface with the IP address 192.0.2.25:

```
http_port 192.0.2.25:3128
```

In addition, you can specify `http_port` by using *host name* and *port* combination. The host name will be translated to an IP address by **Squid**, which will then listen on port 8080 on that particular IP address.

```
http_port myproxy.example.com:8080
```

Another aspect of the `http_port` directive is that it can take multiple values on separate lines. The following lines will trigger **Squid** to listen on three different IP addresses and port combinations. This is generally helpful when you have clients in different LANs, which are configured to use different ports for the proxy server. Edit the `/etc/squid/squid.conf` file as follows:

```
http_port 192.0.2.25:8080
http_port lan1.example.com:3128
http_port lan2.example.com:8081
```

12.3.2.2. ACLs and HTTP access control

Access Control Lists (ACLs) are the base elements for access control and are normally used in combination with other directives, such as `http_access`, to control access to various **Squid** components and web resources.

Example 12.4. Constructing an ACL for a Domain Name

This example shows how to edit the following general instruction:

```
acl example_site dstdomain example.com
```

as follows. Name your ACL by replacing *example_site* with any name. The type used here is **dstdomain**, which specifies that the value (the website) is a domain name.

```
acl FB dstdomain facebook.com
```

If you need to construct an ACL covering a number of websites, you can:

- Write values on a single line:

```
acl example_sites dstdomain example.com example.net example.org
```

- Write values on multiple lines in case the list of values grows significantly:


```
acl example_sites dstdomain example.com example.net
acl example_sites dstdomain example.org
```

- You can put the values in a dedicated file and then instruct **Squid** to read the values from that file:

```
acl example_sites dstdomain '/etc/squid/example_sites.txt'
```

The content of `/etc/squid/example_sites.txt` looks as follows:

```
# Write one value (domain name) per line
example.net
example.org # Temporarily remove example.org from example_sites acl
example.com
```



IMPORTANT

ACLs must be combined with access control directives to allow or deny access to various resources. `http_access` is one such directive which is used to grant access to perform HTTP transactions through **Squid**:

Controlling HTTP access using ACLs

To allow or deny access to clients, you need to combine ACLs with the `http_access` directive.

In the `/etc/squid/squid.conf` file, edit the `http_access` directive, where `ACL_NAME` signifies the requests for which the access must be granted or revoked:

```
http_access allow|deny [!]ACL_NAME
```

Example 12.5. Allowing or denying Access to Clients

The following configuration setting grants access to localhost:

```
http_access allow localhost
```

This configuration denies access to localhost:

```
http_access deny localhost
```

Some ACL names start with an exclamation mark, in such case include the mark as well:

```
http_access deny !Safe_ports
```


12.4. SQUID AUTHENTICATION

For authentication, the **Squid** source code connects with a few authentication back ends, also called **helpers**, such as SMB (SMB server like Windows NT or Samba), DB (an SQL database), or LDAP (Lightweight Directory Access Protocol). Users are authenticated if **Squid** is configured to use **proxy_auth** ACLs.

Instruct **Squid** which authentication helper program to use with the **auth_param** directive in **/etc/squid/squid.conf**. Specify the name of the program and any command line options if necessary.

```
auth_param scheme parameter [setting]
```

Example 12.6. Adding proxy_auth ACLs

Add **proxy_auth** ACL entries to your **Squid** configuration by specifying individual user names. In this example, users named lisa, sarah, joe, and frank are allowed to use the proxy at all times. Other users are allowed only during daytime hours.

```
acl foo proxy_auth REQUIRED
acl bar proxy_auth lisa sarah frank joe
acl daytime time 08:00-17:00
http_access allow foo daytime
http_access allow bar
http_access deny all
```

12.4.1. Authentication with LDAP

In this setup, **Squid** uses LDAP to authenticate users before allowing them to surf the Internet. The **Squid** source code connects to an authentication back end (LDAP) for authentication. Users then need to enter their user name and password before they are allowed to proceed to web pages. **Squid** makes use of the **Squid** LDAP authentication helper, **squid_ldap_auth**, which allows **Squid** to connect to an LDAP directory to validate the user name and password of basic HTTP authentication.

Edit **/etc/squid/squid.conf** as follows to connect **Squid** to **ldap.example.com**:

```
auth_param basic program /usr/lib64/squid/basic_ldap_auth -b
"dc=example,dc=com" -f "uid=%s" -c 2 -t 2 -h ldap.example.com
otherldap.example.com
```

In case you wish to authenticate **Squid** users on an LDAP server through a SSL/TLS secure channel, pass the **-ZZ** argument to the **squid_ldap_auth** program.

```
auth_param basic program /usr/lib64/squid/basic_ldap_auth -v 3 -ZZ -b
"dc=yourcompany,dc=com" -D uid=some-user,ou=People,dc=yourcompany,dc=com
-w password -f uid=%s ldap.yourcompany.com
```

If you want to authenticate against multiple OpenLDAP servers, for example TLS and SSL, you need to specify **auth_param** in the **/etc/squid/squid.conf** file:

1. Edit the `/etc/squid/squid.conf` for TLS:

```
auth_param basic program /usr/lib64/squid/basic_ldap_auth -Z -b
"dc=example,dc=com" -f "uid=%s" -c 2 -t 2 -h ldap.example.com
```

and for SSL:

```
auth_param basic program /usr/lib64/squid/basic_ldap_auth -b
"dc=example,dc=com" -f "uid=%s" -c 2 -t 2 -H
ldaps://ldap.example.com
```

Where

```
-b - Specifies the base DN under which the users are located.
-f - Specifies LDAP search filter to locate the user DN.
-c - Specifies timeout used when connecting to LDAP servers.
-t - Specifies time limit on LDAP search operations.
-h - Specifies the LDAP server to connect to.
-H - Specifies the LDAP server to connect to by LDAP URI
```

2. Restart the **Squid** service

```
~]# systemctl restart squid
```

12.4.2. Authentication with Kerberos

Follow the procedure to configure **Squid** proxy on Red Hat Enterprise Linux 7 to use **Kerberos** authentication. Also, as a prerequisite, first install Samba, Common Internet File System (CIFS) file server for Red Hat Enterprise Linux. For more information on installing Samba, see section [Samba](#) in the Red Hat Enterprise Linux 7 System Administrator's Guide.

Procedure 12.4. Configure Squid on Red Hat Enterprise Linux 7 to use Kerberos authentication

1. Configure **Squid** to join an Active Directory (AD) domain.

1. Edit the `/etc/krb5.conf` file:

```
[libdefaults]
    default_realm = EXAMPLE.COM
    dns_lookup_kdc = no
    dns_lookup_realm = no
    default_keytab_name = /etc/krb5.keytab
; for Windows 2003
    default_tgs_etypes = rc4-hmac des-cbc-crc des-cbc-md5
    default_tkt_etypes = rc4-hmac des-cbc-crc des-cbc-md5
    permitted_etypes = rc4-hmac des-cbc-crc des-cbc-md5

; for Windows 2008 with AES
;    default_tgs_etypes = aes256-cts-hmac-sha1-96 rc4-
hmac des-cbc-crc des-cbc-md5
;    default_tkt_etypes = aes256-cts-hmac-sha1-96 rc4-
hmac des-cbc-crc des-cbc-md5
;    permitted_etypes = aes256-cts-hmac-sha1-96 rc4-hmac
```

```

des-cbc-crc des-cbc-md5

[realms]
EXAMPLE.COM = {
    kdc = 192.168.0.1
    admin_server = 192.168.0.1
}

[domain_realm]
example.com = EXAMPLE.COM
.example.com = EXAMPLE.COM

[logging]
kdc = FILE:/var/log/kdc.log
admin_server = FILE:/var/log/kadmin.log
default = FILE:/var/log/krb5lib.log

```

2. Verify with the **kinit** command:

```
~]# kinit testuser1
```

```
~]# kinit administrator
```

3. Edit the **/etc/samba/smb.conf** file as follows:

```

[global]
workgroup = EXAMPLE
password server = 192.168.0.1
# Remember to put the realm all in CAPS:
realm = EXAMPLE.COM
security = ads
idmap uid = 16777216-33554431
idmap gid = 16777216-33554431
template shell = /bin/bash
winbind use default domain = true
winbind offline logon = false
winbind enum users = yes
winbind enum groups = yes
encrypt passwords = yes
log file = /var/log/samba/log.%m
max log size = 50
passdb backend = tdbsam
load printers = yes
cups options = raw
kerberos method = system keytab

```

4. Join the AD domain

```
~]# net ads join -U Administrator
```

2. Create keytab for HTTP/fqdn with the **net ads keytab** command

```
~]# kinit administrator
```

```
~]# export KRB5_KTNAME=FILE:/etc/squid/HTTP.keytab
~]# net ads keytab CREATE
~]# net ads keytab ADD HTTP
```

and verify the *keytab* file

```
~]# klist -k /etc/squid/HTTP.keytab
```



NOTE

Make sure host name is properly set in */etc/hosts* file

3. Make sure the files are included in Squid.

```
~]# rpm -q squid
squid-3.1.10-1.el6.x86_64

~]# rpm -ql squid | grep kerb

/usr/lib64/squid/negotiate_kerberos_auth
/usr/lib64/squid/negotiate_kerberos_auth_test
/usr/lib64/squid/squid_kerb_auth
/usr/lib64/squid/squid_kerb_auth_test
```

4. Modify */etc/squid/squid.conf* as follows

```
auth_param negotiate program /usr/lib64/squid/squid_kerb_auth -d -s
HTTP/squid.example.com@EXAMPLE.COM
auth_param negotiate children 10
auth_param negotiate keep_alive on
acl kerb_auth proxy_auth REQUIRED
(content truncated)

http_access allow kerb_auth
http_access allow manager localhost
http_access deny manager
http_access deny !Safe_ports
http_access deny CONNECT !SSL_ports
http_access allow localnet
http_access allow localhost
http_access deny all
(content truncated)
```

5. Set the *.keytab* file readable by the Squid process owner:

```
~]# chgrp squid /etc/squid/HTTP.keytab

~]# chmod g+r /etc/squid/HTTP.keytab
```

6. Add the below lines to the */etc/sysconfig/squid* file:

```
KRB5_KTNAME="/etc/squid/HTTP.keytab "
export KRB5_KTNAME
```

7. Start the **Squid** service

```
~]# service squid start
```

8. Configure a Kerberos client, and configure your web browser to use the **Squid** proxy. Get a Kerberos ticket from Key Distribution Center (KDC).

```
~]# kinit testuser1
```

Try to access any website. The web browser should not prompt for any user name or password.

12.5. USING SQUID FOR RESTRICTING ACCESS

Mostly, **Squid** is used for blocking access to certain web content. Typically, either certain ports are blocked or particular web sites.

12.5.1. Restricting Access by Blocking a Port

By this method, also called port filtering, you can block a specific port number with the **Squid** proxy server. Doing so, you can restrict the use of some protocols, services, websites, applications. For example, to block FTP traffic, it is enough to block port 21/TCP. In the same way you can block all HTTPS sites by blocking port 443/TCP.

Procedure 12.5. Blocking Port Numbers

1. Log in as the root user and open the **Squid** configuration file:

```
~]# vi /etc/squid/squid.conf
```

2. Block ports using ACLs.

```
acl Bad_ports port 443                #(create acl for port 443/tcp)
```

3. Save the changes.

4. Restart **Squid** to apply the new configuration:

```
~]# service squid reload
```

The **Squid** configuration file contains lines with *acl Safe_ports port*. By default, these port numbers are added as "Safe_Ports" and open for browsing.

```
acl Safe_ports port 80
acl Safe_ports port 21
acl Safe_ports port 443
acl Safe_ports port 70
acl Safe_ports port 210
acl Safe_ports port 1025-65535
```

```
acl Safe_ports port 280
acl Safe_ports port 488
acl Safe_ports port 591
acl Safe_ports port 777
```

You can disable each of the lines in `/etc/squid/squid.conf` to block the appropriate ports.

Example 12.7. Blocking port 777/tcp

To block port 777/tcp, add a hash sign in front of the respective line as follows:

```
#acl Safe_ports port 777          # multiling http
```

12.5.2. Restricting Access by Blocking Specific Sites or Addresses

Configure Squid for your network to disable access to specific sites.

Procedure 12.6. Blocking a Specific Website

1. Enable access to Squid on your network. Open the `/etc/squid/squid.conf` file and search for "Access Controls". Scroll down to *INSERT YOUR OWN RULE(S) HERE TO ALLOW ACCESS FROM YOUR CLIENTS*. Make sure you adapt the list to your internal IP networks from where browsing should be allowed. In this example, ACL allows access from the local networks 192.168.1.0/24 and 192.168.2.0/24.

```
# INSERT YOUR OWN RULE(S) HERE TO ALLOW ACCESS FROM YOUR CLIENTS
acl our_networks src 192.168.1.0/24 192.168.2.0/24
http_access allow our_networks
```

2. Create a file containing a list of sites you want to block. Name the files, for example, `/usr/local/etc/allowed-sites.squid` and `/usr/local/etc/restricted-sites.squid`.

```
~]# cat /usr/local/etc/allowed-sites.squid
www.redhat.com
fedoraproject.org
```

```
~]# cat /usr/local/etc/restricted-sites.squid
www.badsites.com
illegal.com
```

These can then be used to block the restricted sites.

```
~]# vi /etc/squid/squid.conf
```

```
acl our_networks src 192.168.1.0/24 192.168.2.0/24
acl GoodSites dstdomain "/usr/local/etc/allowed-sites.squid"
acl BadSites dstdomain "/usr/local/etc/restricted-sites.squid"
```

```
http_access allow our_networks
http_access deny BadSites
http_access allow home_network business_hours GoodSites
```

Save and close the file.

3. Restart the **Squid** proxy server:

```
~]# systemctl restart squid
```

4. Configure your web browser to use the DNS name or IP address of your **Squid** server and match the running port.

12.6. ADDITIONAL RESOURCES

- `squid(8)`
- `squidclient(1)`
- `basic_ldap_auth(8)`
- `ext_ldap_group_acl(8)`
- `ext_session_acl(8)`
- `ext_unix_group_acl(8)`
- `negotiate_kerberos_auth(8)`

APPENDIX A. RED HAT CUSTOMER PORTAL LABS RELEVANT TO NETWORKING

Red Hat Customer Portal Labs are tools designed to help you improve performance, troubleshoot issues, identify security problems, and optimize configuration. This appendix provides an overview of Red Hat Customer Portal Labs relevant to networking. All Red Hat Customer Portal Labs are available at <https://access.redhat.com/labs/>.

BRIDGE CONFIGURATION

The [Bridge Configuration](#) is designed to configure a bridged network interface for applications such as KVM using Red Hat Enterprise Linux 5.4 or later.

NETWORK BONDING HELPER

The [Network Bonding Helper](#) allows administrators to bind multiple Network Interface Controllers together into a single channel using the bonding kernel module and the bonding network interface.

Use the **Network Bonding Helper** to enable two or more network interfaces to act as one bonding interface.

PACKET CAPTURE SYNTAX GENERATOR

The [Packet capture syntax generator](#) helps you to capture network packets.

Use the **Packet capture syntax generator** to generate the `tcpdump` command that selects an interface and then prints information to the console. You need **root** access to enter the command.

APPENDIX B. REVISION HISTORY

Revision 0.10-02 Async release with misc.updates	Mon 14 Aug 2017	Ioanna Gkioka
Revision 0.10-01 Version for 7.4 GA publication.	Tue 25 Jul 2017	Mirek Jahoda
Revision 0.9-30 Version for 7.3 GA publication.	Tue 18 Oct 2016	Mirek Jahoda
Revision 0.9-25 Version for 7.2 GA release.	Wed 11 Nov 2015	Jana Heves
Revision 0.9-15 Version for 7.1 GA release	Tue 17 Feb 2015	Christian Huffman
Revision 0.9-14 Updated the nmtui and NetworkManager GUI sections.	Fri Dec 05 2014	Christian Huffman
Revision 0.9-12 Improved <i>IP Networking</i> , <i>802.1Q VLAN tagging</i> , and <i>Teaming</i> .	Wed Nov 05 2014	Stephen Wadeley
Revision 0.9-11 Improved <i>Bonding</i> , <i>Bridging</i> , and <i>Teaming</i> .	Tues Oct 21 2014	Stephen Wadeley
Revision 0.9-9 Improved <i>Bonding</i> and <i>Consistent Network Device Naming</i> .	Tue Sep 2 2014	Stephen Wadeley
Revision 0.9-8 Red Hat Enterprise Linux 7.0 GA release of the Networking Guide.	Tue July 8 2014	Stephen Wadeley
Revision 0-0 Initialization of the Red Hat Enterprise Linux 7 Networking Guide.	Wed Dec 12 2012	Stephen Wadeley

B.1. ACKNOWLEDGMENTS

Certain portions of this text first appeared in the *Red Hat Enterprise Linux 6 Deployment Guide*, copyright © 2014 Red Hat, Inc., available at https://access.redhat.com/documentation/en-US/Red_Hat_Enterprise_Linux/6/html/Deployment_Guide/index.html.

INDEX

Symbols

`/etc/named.conf` (see BIND)

A

authoritative name server (see BIND)

B

Berkeley Internet Name Domain (see BIND)

BIND

additional resources, [Online Resources](#)

installed documentation, [Installed Documentation](#)

common mistakes, [Common Mistakes to Avoid](#)

configuration

acl statement, [Common Statement Types](#)

comment tags, [Comment Tags](#)

controls statement, [Other Statement Types](#)

include statement, [Common Statement Types](#)

key statement, [Other Statement Types](#)

logging statement, [Other Statement Types](#)

options statement, [Common Statement Types](#)

server statement, [Other Statement Types](#)

trusted-keys statement, [Other Statement Types](#)

view statement, [Other Statement Types](#)

zone statement, [Common Statement Types](#)

directories

`/etc/named/`, [Configuring the named Service](#)

`/var/named/`, [Editing Zone Files](#)

`/var/named/data/`, [Editing Zone Files](#)

`/var/named/dynamic/`, [Editing Zone Files](#)

`/var/named/slaves/`, [Editing Zone Files](#)

features

Automatic Zone Transfer (AXFR), [Incremental Zone Transfers \(IXFR\)](#)

DNS Security Extensions (DNSSEC), [DNS Security Extensions \(DNSSEC\)](#)

Incremental Zone Transfer (IXFR), [Incremental Zone Transfers \(IXFR\)](#)

Internet Protocol version 6 (IPv6), [Internet Protocol version 6 \(IPv6\)](#)

multiple views, [Multiple Views](#)

Transaction SIGNature (TSIG), [Transaction SIGNatures \(TSIG\)](#)

files

`/etc/named.conf`, [Configuring the named Service](#) , [Configuring the Utility](#)
`/etc/rndc.conf`, [Configuring the Utility](#)
`/etc/rndc.key`, [Configuring the Utility](#)

resource record, [Name server Zones](#)

types

authoritative name server, [Name server Types](#)
primary (master) name server, [Name server Zones](#) , [Name server Types](#)
recursive name server, [Name server Types](#)
secondary (slave) name server, [Name server Zones](#) , [Name server Types](#)

utilities

`dig`, [BIND as a Name server](#) , [Using the dig Utility](#) , [DNS Security Extensions \(DNSSEC\)](#)
`named`, [BIND as a Name server](#) , [Configuring the named Service](#)
`rndc`, [BIND as a Name server](#) , [Using the rndc Utility](#)

zones

`$INCLUDE` directive, [Common Directives](#)
`$ORIGIN` directive, [Common Directives](#)
`$TTL` directive, [Common Directives](#)
A (Address) resource record, [Common Resource Records](#)
CNAME (Canonical Name) resource record, [Common Resource Records](#)
comment tags, [Comment Tags](#)
description, [Name server Zones](#)
example usage, [A Simple Zone File](#) , [A Reverse Name Resolution Zone File](#)
MX (Mail Exchange) resource record, [Common Resource Records](#)
NS (Nameserver) resource record, [Common Resource Records](#)
PTR (Pointer) resource record, [Common Resource Records](#)
SOA (Start of Authority) resource record, [Common Resource Records](#)

bonding (see channel bonding)

C**channel bonding**

configuration, [Using Channel Bonding](#)
description, [Using Channel Bonding](#)
parameters to bonded interfaces, [Bonding Module Directives](#)

channel bonding interface (see kernel module)

D

default gateway, [Static Routes and the Default Gateway](#)

DHCP, [DHCP Servers](#)

additional resources, [Additional Resources](#)
command-line options, [Starting and Stopping the Server](#)
dhcpd.conf, [Configuration File](#)
dhcpd.leases, [Starting and Stopping the Server](#)
dhcpd6.conf, [DHCP for IPv6 \(DHCPv6\)](#)
DHCPv6, [DHCP for IPv6 \(DHCPv6\)](#)
dhcrelay, [DHCP Relay Agent](#)
global parameters, [Configuration File](#)
group, [Configuration File](#)
options, [Configuration File](#)
reasons for using, [Why Use DHCP?](#)
Relay Agent, [DHCP Relay Agent](#)
server configuration, [Configuring a DHCP Server](#)
shared-network, [Configuration File](#)
starting the server, [Starting and Stopping the Server](#)
stopping the server, [Starting and Stopping the Server](#)
subnet, [Configuration File](#)

dhcpd.conf, [Configuration File](#)
dhcpd.leases, [Starting and Stopping the Server](#)
dhcrelay, [DHCP Relay Agent](#)
dig (see BIND)

DNS

definition, [DNS Servers](#)
(see also BIND)

Dynamic Host Configuration Protocol (see DHCP)

K**kernel module**

bonding module, [Using Channel Bonding](#)
description, [Using Channel Bonding](#)
parameters to bonded interfaces, [Bonding Module Directives](#)

module parameters
bonding module parameters, [Bonding Module Directives](#)

M**Multihomed DHCP**

host configuration, [Host Configuration](#)

server configuration, [Configuring a Multihomed DHCP Server](#)

N

name server (see DNS)

named (see BIND)

NIC

binding into single channel, [Using Channel Bonding](#)

P

primary name server (see BIND)

R

recursive name server (see BIND)

resource record (see BIND)

rndc (see BIND)

root name server (see BIND)

S

secondary name server (see BIND)

Squid, [Squid](#)

static route, [Static Routes and the Default Gateway](#)