

OSAL User's Guide

Generated by Doxygen 1.8.13

Contents

1	Osai API Documentation	2
2	OSAL Introduction	3
3	File System Overview	3
4	File Descriptors In Osai	4
5	Timer Overview	5
6	Deprecated List	5
7	Module Index	7
7.1	Modules	7
8	Data Structure Index	8
8.1	Data Structures	8
9	File Index	10
9.1	File List	10
10	Module Documentation	10
10.1	OSAL Object Type Defines	10
10.1.1	Detailed Description	11
10.1.2	Macro Definition Documentation	11
10.2	OSAL Semaphore State Defines	14
10.2.1	Detailed Description	14
10.2.2	Macro Definition Documentation	14
10.3	OSAL Core Operation APIs	15
10.3.1	Detailed Description	15
10.3.2	Function Documentation	15
10.4	OSAL Object Utility APIs	18

10.4.1 Detailed Description	18
10.4.2 Function Documentation	18
10.5 OSAL Task APIs	21
10.5.1 Detailed Description	21
10.5.2 Function Documentation	21
10.6 OSAL Message Queue APIs	28
10.6.1 Detailed Description	28
10.6.2 Function Documentation	28
10.7 OSAL Semaphore APIs	33
10.7.1 Detailed Description	34
10.7.2 Function Documentation	34
10.8 OSAL Time/Tick APIs	49
10.8.1 Detailed Description	49
10.8.2 Function Documentation	49
10.9 OSAL Exception APIs	52
10.9.1 Detailed Description	52
10.9.2 Function Documentation	52
10.10 OSAL Floating Point Unit Exception APIs	53
10.10.1 Detailed Description	53
10.10.2 Function Documentation	53
10.11 OSAL Interrupt APIs	57
10.11.1 Detailed Description	57
10.11.2 Function Documentation	57
10.12 OSAL Shared memory APIs	63
10.12.1 Detailed Description	63
10.12.2 Function Documentation	63
10.13 OSAL Heap APIs	65
10.13.1 Detailed Description	65

10.13.2 Function Documentation	65
10.14 OSAL Error Info APIs	66
10.14.1 Detailed Description	66
10.14.2 Function Documentation	66
10.15 OSAL Select APIs	67
10.15.1 Detailed Description	67
10.15.2 Function Documentation	67
10.16 OSAL Printf APIs	70
10.16.1 Detailed Description	70
10.16.2 Function Documentation	70
10.17 OSAL File Access Option Defines	72
10.17.1 Detailed Description	72
10.17.2 Macro Definition Documentation	72
10.18 OSAL Reference Point For Seek Offset Defines	73
10.18.1 Detailed Description	73
10.18.2 Macro Definition Documentation	73
10.19 OSAL Volume Type Defines	74
10.19.1 Detailed Description	74
10.19.2 Macro Definition Documentation	74
10.20 OSAL Standard File APIs	75
10.20.1 Detailed Description	75
10.20.2 Function Documentation	75
10.21 OSAL Directory APIs	89
10.21.1 Detailed Description	89
10.21.2 Function Documentation	89
10.22 OSAL File System Level APIs	94
10.22.1 Detailed Description	94
10.22.2 Function Documentation	94

10.23	OSAL Shell APIs	103
10.23.1	Detailed Description	103
10.23.2	Function Documentation	103
10.24	OSAL Dynamic Loader and Symbol APIs	104
10.24.1	Detailed Description	104
10.24.2	Function Documentation	104
10.25	OSAL Socket Address APIs	109
10.25.1	Detailed Description	109
10.25.2	Function Documentation	109
10.26	OSAL Socket Management APIs	113
10.26.1	Detailed Description	113
10.26.2	Function Documentation	113
10.27	OSAL Timer APIs	121
10.27.1	Detailed Description	121
10.27.2	Function Documentation	121
10.28	OSAL Return Code Defines	131
10.28.1	Detailed Description	132
10.28.2	Macro Definition Documentation	132
11	Data Structure Documentation	142
11.1	OS_bin_sem_prop_t Struct Reference	142
11.1.1	Detailed Description	142
11.1.2	Field Documentation	142
11.2	OS_count_sem_prop_t Struct Reference	143
11.2.1	Detailed Description	143
11.2.2	Field Documentation	143
11.3	os_dirent_t Struct Reference	144
11.3.1	Detailed Description	144

11.3.2	Field Documentation	144
11.4	OS_FdSet Struct Reference	144
11.4.1	Detailed Description	145
11.4.2	Field Documentation	145
11.5	OS_file_prop_t Struct Reference	145
11.5.1	Detailed Description	145
11.5.2	Field Documentation	146
11.6	os_fsinfo_t Struct Reference	146
11.6.1	Detailed Description	147
11.6.2	Field Documentation	147
11.7	os_fstat_t Struct Reference	148
11.7.1	Detailed Description	148
11.7.2	Field Documentation	148
11.8	OS_heap_prop_t Struct Reference	149
11.8.1	Detailed Description	149
11.8.2	Field Documentation	149
11.9	OS_module_address_t Struct Reference	150
11.9.1	Detailed Description	150
11.9.2	Field Documentation	150
11.10	OS_module_prop_t Struct Reference	152
11.10.1	Detailed Description	152
11.10.2	Field Documentation	152
11.11	OS_mut_sem_prop_t Struct Reference	153
11.11.1	Detailed Description	154
11.11.2	Field Documentation	154
11.12	OS_queue_prop_t Struct Reference	154
11.12.1	Detailed Description	155
11.12.2	Field Documentation	155

11.13OS_SockAddr_t Struct Reference	155
11.13.1 Detailed Description	156
11.13.2 Field Documentation	156
11.14OS_SockAddrData_t Union Reference	156
11.14.1 Detailed Description	157
11.14.2 Field Documentation	157
11.15OS_socket_prop_t Struct Reference	158
11.15.1 Detailed Description	158
11.15.2 Field Documentation	158
11.16OS_static_symbol_record_t Struct Reference	159
11.16.1 Detailed Description	159
11.16.2 Field Documentation	159
11.17OS_task_prop_t Struct Reference	160
11.17.1 Detailed Description	160
11.17.2 Field Documentation	160
11.18OS_time_t Struct Reference	161
11.18.1 Detailed Description	162
11.18.2 Field Documentation	162
11.19OS_timebase_prop_t Struct Reference	162
11.19.1 Detailed Description	162
11.19.2 Field Documentation	163
11.20OS_timer_prop_t Struct Reference	164
11.20.1 Detailed Description	164
11.20.2 Field Documentation	164
11.21OS_VolumeInfo_t Struct Reference	165
11.21.1 Detailed Description	165
11.21.2 Field Documentation	166

12 File Documentation	167
12.1 build/doc/osconfig-example.h File Reference	167
12.1.1 Macro Definition Documentation	168
12.2 cfe/docs/src/osafs.dox File Reference	175
12.3 cfe/docs/src/osaf_timer.dox File Reference	175
12.4 cfe/docs/src/osafmain.dox File Reference	175
12.5 osal/src/os/inc/common_types.h File Reference	175
12.5.1 Macro Definition Documentation	176
12.5.2 Typedef Documentation	178
12.5.3 Function Documentation	181
12.6 osal/src/os/inc/osapi-os-core.h File Reference	182
12.6.1 Macro Definition Documentation	188
12.6.2 Typedef Documentation	189
12.6.3 Enumeration Type Documentation	190
12.6.4 Function Documentation	191
12.7 osal/src/os/inc/osapi-os-filesys.h File Reference	192
12.7.1 Macro Definition Documentation	195
12.7.2 Typedef Documentation	198
12.7.3 Enumeration Type Documentation	199
12.8 osal/src/os/inc/osapi-os-loader.h File Reference	200
12.8.1 Typedef Documentation	200
12.9 osal/src/os/inc/osapi-os-net.h File Reference	201
12.9.1 Macro Definition Documentation	202
12.9.2 Enumeration Type Documentation	202
12.10 osal/src/os/inc/osapi-os-timer.h File Reference	203
12.10.1 Typedef Documentation	204
12.11 osal/src/os/inc/osapi-version.h File Reference	205
12.11.1 Macro Definition Documentation	205
12.12 osal/src/os/inc/osapi.h File Reference	206
12.12.1 Macro Definition Documentation	208

1 Osal API Documentation

- General Information and Concepts
 - [OSAL Introduction](#)
- Core OS Module
 - [OSAL Return Code Defines](#)
 - [OSAL Object Type Defines](#)
 - [OSAL Semaphore State Defines](#)
 - APIs
 - * [OSAL Core Operation APIs](#)
 - * [OSAL Object Utility APIs](#)
 - * [OSAL Task APIs](#)
 - * [OSAL Message Queue APIs](#)
 - * [OSAL Semaphore APIs](#)
 - * [OSAL Time/Tick APIs](#)
 - * [OSAL Exception APIs](#)
 - * [OSAL Floating Point Unit Exception APIs](#)
 - * [OSAL Interrupt APIs](#)
 - * [OSAL Shared memory APIs](#)
 - * [OSAL Heap APIs](#)
 - * [OSAL Error Info APIs](#)
 - * [OSAL Select APIs](#)
 - * [OSAL Printf APIs](#)
 - [Core OS Module Reference](#)
- OS File System
 - [File System Overview](#)
 - [File Descriptors In Osal](#)
 - [OSAL File Access Option Defines](#)
 - [OSAL Reference Point For Seek Offset Defines](#)
 - [OSAL Volume Type Defines](#)
 - APIs
 - * [OSAL Standard File APIs](#)
 - * [OSAL Directory APIs](#)
 - * [OSAL File System Level APIs](#)
 - * [OSAL Shell APIs](#)
 - [File System Module Reference](#)
- Object File Loader
 - APIs
 - * [OSAL Dynamic Loader and Symbol APIs](#)

- [File Loader Module Reference](#)
- Network Module
 - APIs
 - * [OSAL Socket Address APIs](#)
 - * [OSAL Socket Management APIs](#)
 - [Network Module Reference](#)
- Timer
 - [Timer Overview](#)
 - APIs
 - * [OSAL Timer APIs](#)
 - [Timer Module Reference](#)

2 OSAL Introduction

The goal of this library is to promote the creation of portable and reusable real time embedded system software. Given the necessary OS abstraction layer implementations, the same embedded software should compile and run on a number of platforms ranging from spacecraft computer systems to desktop PCs.

The OS Application Program Interfaces (APIs) are broken up into core, file system, loader, network, and timer APIs. See the related document sections for full descriptions.

Note

The majority of these APIs should be called from a task running in the context of an OSAL application and in general should not be called from an ISR. There are a few exceptions, such as the ability to give a binary semaphore from an ISR.

3 File System Overview

The File System API is a thin wrapper around a selection of POSIX file APIs. In addition the File System API presents a common directory structure and volume view regardless of the underlying system type. For example, vxWorks uses MS-DOS style volume names and directories where a vxWorks RAM disk might have the volume “RAM:0”. With this File System API, volumes are represented as Unix-style paths where each volume is mounted on the root file system:

- RAM:0/file1.dat becomes /mnt/ram/file1.dat
- FL:0/file2.dat becomes /mnt/fl/file2.dat

This abstraction allows the applications to use the same paths regardless of the implementation and it also allows file systems to be simulated on a desktop system for testing. On a desktop Linux system, the file system abstraction can be set up to map virtual devices to a regular directory. This is accomplished through the OS_mkfs call, OS_mount call, and a BSP specific volume table that maps the virtual devices to real devices or underlying file systems.

In order to make this file system volume abstraction work, a “Volume Table” needs to be provided in the Board Support Package of the application. The table has the following fields:

- **Device Name:** This is the name of the virtual device that the Application uses. Common names are "ramdisk1", "flash1", or "volatile1" etc. But the name can be any unique string.
- **Physical Device Name:** This is an implementation specific field. For vxWorks it is not needed and can be left blank. For a File system based implementation, it is the "mount point" on the root file system where all of the volume will be mounted. A common place for this on Linux could be a user's home directory, "/tmp", or even the current working directory ".". In the example of "/tmp" all of the directories created for the volumes would be under "/tmp" on the Linux file system. For a real disk device in Linux, such as a RAM disk, this field is the device name "/dev/ram0".
- **Volume Type:** This field defines the type of volume. The types are: FS_BASED which uses the existing file system, RAM_DISK which uses a RAM_DISK device in vxWorks, RTEMS, or Linux, FLASH_DISK_FORMAT which uses a flash disk that is to be formatted before use, FLASH_DISK_INIT which uses a flash disk with an existing format that is just to be initialized before it's use, EEPROM which is for an EEPROM or PROM based system.
- **Volatile Flag:** This flag indicates that the volume or disk is a volatile disk (RAM disk) or a non-volatile disk, that retains its contents when the system is rebooted. This should be set to TRUE or FALSE.
- **Free Flag:** This is an internal flag that should be set to FALSE or zero.
- **Is Mounted Flag:** This is an internal flag that should be set to FALSE or zero. Note that a "pre-mounted" FS_BASED path can be set up by setting this flag to one.
- **Volume Name:** This is an internal field and should be set to a space character " ".
- **Mount Point Field:** This is an internal field and should be set to a space character " ".
- **Block Size Field:** This is used to record the block size of the device and does not need to be set by the user.

4 File Descriptors In Osal

The OSAL uses abstracted file descriptors. This means that the file descriptors passed back from the OS_open and OS_creat calls will only work with other OSAL OS_* calls. The reasoning for this is as follows:

Because the OSAL now keeps track of all file descriptors, OSAL specific information can be associated with a specific file descriptor in an OS independent way. For instance, the path of the file that the file descriptor points to can be easily retrieved. Also, the OSAL task ID of the task that opened the file can also be retrieved easily. Both of these pieces of information are very useful when trying to determine statistics for a task, or the entire system. This information can all be retrieved with a single API, OS_FDGetInfo.

All of possible file system calls are not implemented. "Special" files requiring OS specific control/operations are by nature not portable. Abstraction in this case is not possible, so the raw OS calls should be used (including open/close/etc). Mixing with OSAL calls is not supported for such cases. [OS_TranslatePath](#) is available to support using open directly by an app and maintain abstraction on the file system.

There are some small drawbacks with the OSAL file descriptors. Because the related information is kept in a table, there is a define called OS_MAX_NUM_OPEN_FILES that defines the maximum number of file descriptors available. This is a configuration parameter, and can be changed to fit your needs.

Also, if you open or create a file not using the OSAL calls (OS_open or OS_creat) then none of the other OS_* calls that accept a file descriptor as a parameter will work (the results of doing so are undefined). Therefore, if you open a file with the underlying OS's open call, you must continue to use the OS's calls until you close the file descriptor. Be aware that by doing this your software may no longer be OS agnostic.

5 Timer Overview

The timer API is a generic interface to the OS timer facilities. It is implemented using the POSIX timers on Linux and vxWorks and the native timer API on RTEMS. The number of timers supported is controlled by the configuration parameter `OS_MAX_TIMERS`.

6 Deprecated List

Global `ATA_DISK`

Volume type ATA disk

Global `boolean`

Use `bool`

Global `EEPROM_DISK`

Volume type EEPROM disk

Global `FALSE`

Use `false`

Global `FS_BASED`

Volume type FS based

Global `NUM_FILE_SYSTEMS`

Global `os_dirp_t`

Global `OS_ExcAttachHandler` (uint32 ExceptionNumber, void(*ExceptionHandler)(uint32, const void *, uint32), int32 parameter)

Planning move to PSP due to platform dependencies

Global `OS_ExcDisable` (int32 ExceptionNumber)

Planning move to PSP due to platform dependencies

Global `OS_ExcEnable` (int32 ExceptionNumber)

Planning move to PSP due to platform dependencies

Global `OS_FDTableEntry`

Use `OS_file_prop_t`

Global `OS_FPUExcAttachHandler` (uint32 ExceptionNumber, osal_task_entry ExceptionHandler, int32 parameter)

Planning move to PSP due to platform dependencies

Global `OS_FPUExcDisable` (int32 ExceptionNumber)

Planning move to PSP due to platform dependencies

Global `OS_FPUExcEnable` (int32 ExceptionNumber)

Planning move to PSP due to platform dependencies

Global `OS_FPUExcGetMask` (uint32 *mask)

Planning move to PSP due to platform dependencies

Global `OS_FPUExcSetMask` (uint32 mask)

Planning move to PSP due to platform dependencies

Global [OS_FS_ERR_INVALID_FD](#)

Invalid ID

Global [OS_FS_ERR_INVALID_POINTER](#)

Invalid pointer

Global [OS_FS_ERR_NO_FREE_FDS](#)

No free IDs

Global [OS_FS_ERROR](#)

Failed execution

Global [OS_FS_SUCCESS](#)

Successful execution

Global [OS_FS_UNIMPLEMENTED](#)

Not implemented

Global [os_fshealth_t](#)

type no longer used

Global [OS_IntAck](#) (int32 InterruptNumber)

platform dependencies, removing from OSAL

Global [OS_IntAttachHandler](#) (uint32 InterruptNumber, osal_task_entry InterruptHandler, int32 parameter)

platform dependencies, removing from OSAL

Global [OS_IntDisable](#) (int32 Level)

platform dependencies, removing from OSAL

Global [OS_IntEnable](#) (int32 Level)

platform dependencies, removing from OSAL

Global [OS_IntGetMask](#) (uint32 *mask)

platform dependencies, removing from OSAL

Global [OS_IntLock](#) (void)

platform dependencies, removing from OSAL

Global [OS_IntSetMask](#) (uint32 mask)

platform dependencies, removing from OSAL

Global [OS_IntUnlock](#) (int32 IntLevel)

platform dependencies, removing from OSAL

Global [OS_module_record_t](#)

Use [OS_module_prop_t](#)

Global [OS_opendir](#) (const char *path)

Replaced by [OS_DirectoryOpen\(\)](#)

Global [OS_ShMemAttach](#) (cpuaddr *Address, uint32 Id)

Never implemented

Global [OS_ShMemCreate](#) (uint32 *Id, uint32 NBytes, const char *SegName)

Never implemented

Global [OS_ShMemGetIdByName](#) (uint32 *ShMemId, const char *SegName)

Never implemented

Global [OS_ShMemInit](#) (void)

Never implemented

Global [OS_ShMemSemGive](#) (uint32 Id)

Never implemented

Global [OS_ShMemSemTake](#) (uint32 Id)

Never implemented

Global [OS_task_prop_t::OSTask_id](#)

Global [OS_TaskRegister](#) (void)

Explicit registration call no longer needed

Class [OS_VolumeInfo_t](#)

Use the OSAL file system API to register volumes

Global [osalbool](#)

Use bool

Module [OSAPIExc](#)

Planning move to PSP due to platform dependencies

Module [OSAPIFPUExc](#)

Planning move to PSP due to platform dependencies

Module [OSAPIInterrupt](#)

Platform dependencies

Module [OSAPIShMem](#)

Not in current implementations

Global [RAM_DISK](#)

Volume type RAM disk

Global [TRUE](#)

Use true

7 Module Index

7.1 Modules

Here is a list of all modules:

OSAL Object Type Defines	10
OSAL Semaphore State Defines	14
OSAL Core Operation APIs	15
OSAL Object Utility APIs	18
OSAL Task APIs	21
OSAL Message Queue APIs	28
OSAL Semaphore APIs	33

OSAL Time/Tick APIs	49
OSAL Exception APIs	52
OSAL Floating Point Unit Exception APIs	53
OSAL Interrupt APIs	57
OSAL Shared memory APIs	63
OSAL Heap APIs	65
OSAL Error Info APIs	66
OSAL Select APIs	67
OSAL Printf APIs	70
OSAL File Access Option Defines	72
OSAL Reference Point For Seek Offset Defines	73
OSAL Volume Type Defines	74
OSAL Standard File APIs	75
OSAL Directory APIs	89
OSAL File System Level APIs	94
OSAL Shell APIs	103
OSAL Dynamic Loader and Symbol APIs	104
OSAL Socket Address APIs	109
OSAL Socket Management APIs	113
OSAL Timer APIs	121
OSAL Return Code Defines	131

8 Data Structure Index

8.1 Data Structures

Here are the data structures with brief descriptions:

OS_bin_sem_prop_t OSAL binary semaphore properties	142
OS_count_sem_prop_t OSAL counting semaphore properties	143

os_dirent_t	Directory entry	144
OS_FdSet	An abstract structure capable of holding several OSAL IDs	144
OS_file_prop_t	OSAL file properties	145
os_fsinfo_t	OSAL file system info	146
os_fstat_t	File system status	148
OS_heap_prop_t	OSAL heap properties	149
OS_module_address_t	OSAL module address properties	150
OS_module_prop_t	OSAL module properties	152
OS_mut_sem_prop_t	OSAL mutex properties	153
OS_queue_prop_t	OSAL queue properties	154
OS_SockAddr_t	Encapsulates a generic network address	155
OS_SockAddrData_t	Storage buffer for generic network address	156
OS_socket_prop_t	Encapsulates socket properties	158
OS_static_symbol_record_t	Associates a single symbol name with a memory address	159
OS_task_prop_t	OSAL task properties	160
OS_time_t	OSAL time	161
OS_timebase_prop_t	Time base properties	162
OS_timer_prop_t	Timer properties	164
OS_VolumeInfo_t	Internal structure of the OS volume table for mounted file systems and path translation	165

9 File Index

9.1 File List

Here is a list of all files with brief descriptions:

build/doc/osconfig-example.h	167
osal/src/os/inc/common_types.h	175
osal/src/os/inc/osapi-os-core.h	182
osal/src/os/inc/osapi-os-filesys.h	192
osal/src/os/inc/osapi-os-loader.h	200
osal/src/os/inc/osapi-os-net.h	201
osal/src/os/inc/osapi-os-timer.h	203
osal/src/os/inc/osapi-version.h	205
osal/src/os/inc/osapi.h	206

10 Module Documentation

10.1 OSAL Object Type Defines

Macros

- `#define OS_OBJECT_TYPE_UNDEFINED 0x00`
Object type undefined.
- `#define OS_OBJECT_TYPE_OS_TASK 0x01`
Object task type.
- `#define OS_OBJECT_TYPE_OS_QUEUE 0x02`
Object queue type.
- `#define OS_OBJECT_TYPE_OS_COUNTSEM 0x03`
Object counting semaphore type.
- `#define OS_OBJECT_TYPE_OS_BINSEM 0x04`
Object binary semaphore type.
- `#define OS_OBJECT_TYPE_OS_MUTEX 0x05`
Object mutex type.
- `#define OS_OBJECT_TYPE_OS_STREAM 0x06`
Object stream type.
- `#define OS_OBJECT_TYPE_OS_DIR 0x07`
Object directory type.
- `#define OS_OBJECT_TYPE_OS_TIMEBASE 0x08`
Object timebase type.

- `#define OS_OBJECT_TYPE_OS_TIMECB 0x09`
Object timer callback type.
- `#define OS_OBJECT_TYPE_OS_MODULE 0x0A`
Object module type.
- `#define OS_OBJECT_TYPE_OS_FILESYS 0x0B`
Object file system type.
- `#define OS_OBJECT_TYPE_OS_CONSOLE 0x0C`
Object console type.
- `#define OS_OBJECT_TYPE_USER 0x10`
Object user type.

10.1.1 Detailed Description

10.1.2 Macro Definition Documentation

10.1.2.1 OS_OBJECT_TYPE_OS_BINSEM

```
#define OS_OBJECT_TYPE_OS_BINSEM 0x04
```

Object binary semaphore type.

Definition at line 46 of file osapi-os-core.h.

10.1.2.2 OS_OBJECT_TYPE_OS_CONSOLE

```
#define OS_OBJECT_TYPE_OS_CONSOLE 0x0C
```

Object console type.

Definition at line 54 of file osapi-os-core.h.

10.1.2.3 OS_OBJECT_TYPE_OS_COUNTSEM

```
#define OS_OBJECT_TYPE_OS_COUNTSEM 0x03
```

Object counting semaphore type.

Definition at line 45 of file osapi-os-core.h.

10.1.2.4 OS_OBJECT_TYPE_OS_DIR

```
#define OS_OBJECT_TYPE_OS_DIR 0x07
```

Object directory type.

Definition at line 49 of file osapi-os-core.h.

10.1.2.5 OS_OBJECT_TYPE_OS_FILESYS

```
#define OS_OBJECT_TYPE_OS_FILESYS 0x0B
```

Object file system type.

Definition at line 53 of file osapi-os-core.h.

10.1.2.6 OS_OBJECT_TYPE_OS_MODULE

```
#define OS_OBJECT_TYPE_OS_MODULE 0x0A
```

Object module type.

Definition at line 52 of file osapi-os-core.h.

10.1.2.7 OS_OBJECT_TYPE_OS_MUTEX

```
#define OS_OBJECT_TYPE_OS_MUTEX 0x05
```

Object mutex type.

Definition at line 47 of file osapi-os-core.h.

10.1.2.8 OS_OBJECT_TYPE_OS_QUEUE

```
#define OS_OBJECT_TYPE_OS_QUEUE 0x02
```

Object queue type.

Definition at line 44 of file osapi-os-core.h.

10.1.2.9 OS_OBJECT_TYPE_OS_STREAM

```
#define OS_OBJECT_TYPE_OS_STREAM 0x06
```

Object stream type.

Definition at line 48 of file osapi-os-core.h.

10.1.2.10 OS_OBJECT_TYPE_OS_TASK

```
#define OS_OBJECT_TYPE_OS_TASK 0x01
```

Object task type.

Definition at line 43 of file osapi-os-core.h.

10.1.2.11 OS_OBJECT_TYPE_OS_TIMEBASE

```
#define OS_OBJECT_TYPE_OS_TIMEBASE 0x08
```

Object timebase type.

Definition at line 50 of file osapi-os-core.h.

10.1.2.12 OS_OBJECT_TYPE_OS_TIMECB

```
#define OS_OBJECT_TYPE_OS_TIMECB 0x09
```

Object timer callback type.

Definition at line 51 of file osapi-os-core.h.

10.1.2.13 OS_OBJECT_TYPE_UNDEFINED

```
#define OS_OBJECT_TYPE_UNDEFINED 0x00
```

Object type undefined.

Definition at line 42 of file osapi-os-core.h.

10.1.2.14 OS_OBJECT_TYPE_USER

```
#define OS_OBJECT_TYPE_USER 0x10
```

Object user type.

Definition at line 55 of file osapi-os-core.h.

10.2 OSAL Semaphore State Defines

Macros

- `#define OS_SEM_FULL 1`
Semaphore full state.
- `#define OS_SEM_EMPTY 0`
Semaphore empty state.

10.2.1 Detailed Description

10.2.2 Macro Definition Documentation

10.2.2.1 OS_SEM_EMPTY

```
#define OS_SEM_EMPTY 0
```

Semaphore empty state.

Definition at line 72 of file osapi-os-core.h.

10.2.2.2 OS_SEM_FULL

```
#define OS_SEM_FULL 1
```

Semaphore full state.

Definition at line 71 of file osapi-os-core.h.

10.3 OSAL Core Operation APIs

Functions

- void [OS_Application_Startup](#) (void)
Application startup.
- void [OS_Application_Run](#) (void)
Application run.
- [int32 OS_API_Init](#) (void)
Initialization of API.
- void [OS_IdleLoop](#) (void)
Background thread implementation - waits forever for events to occur.
- void [OS_DeleteAllObjects](#) (void)
delete all resources created in OSAL.
- void [OS_ApplicationShutdown](#) (uint8 flag)
Initiate orderly shutdown.
- void [OS_ApplicationExit](#) (int32 Status)
Exit/Abort the application.

10.3.1 Detailed Description

These are for OSAL core operations for startup/initialization, running, and shutdown. Typically only used in bsps, unit tests, psps, etc.

Not intended for user application use

10.3.2 Function Documentation

10.3.2.1 OS_API_Init()

```
int32 OS_API_Init (  
    void )
```

Initialization of API.

This function returns initializes the internal data structures of the OS Abstraction Layer. It must be called in the application startup code before calling any other OS routines.

Returns

Execution status, see [OSAL Return Code Defines](#). Any error code (negative) means the OSAL can not be initialized. Typical platform specific response is to abort since additional OSAL calls will have undefined behavior.

Return values

<i>OS_SUCCESS</i>	Successful execution.
<i>OS_ERROR</i>	Failed execution.

10.3.2.2 OS_Application_Run()

```
void OS_Application_Run (
    void )
```

Application run.

Run abstraction such that the same BSP can be used for operations and testing.

10.3.2.3 OS_Application_Startup()

```
void OS_Application_Startup (
    void )
```

Application startup.

Startup abstraction such that the same BSP can be used for operations and testing.

10.3.2.4 OS_ApplicationExit()

```
void OS_ApplicationExit (
    int32 Status )
```

Exit/Abort the application.

Indicates that the OSAL application should exit and return control to the OS This is intended for e.g. scripted unit testing where the test needs to end without user intervention.

This function does not return. Production code typically should not ever call this.

Note

This exits the entire process including tasks that have been created.

10.3.2.5 OS_ApplicationShutdown()

```
void OS_ApplicationShutdown (
    uint8 flag )
```

Initiate orderly shutdown.

Indicates that the OSAL application should perform an orderly shutdown of ALL tasks, clean up all resources, and exit the application.

This allows the task currently blocked in [*OS_IdleLoop\(\)*](#) to wake up, and for that function to return to its caller.

This is preferred over e.g. [*OS_ApplicationExit\(\)*](#) which exits immediately and does not provide for any means to clean up first.

Parameters

in	<i>flag</i>	set to true to initiate shutdown, false to cancel
----	-------------	---

10.3.2.6 OS_DeleteAllObjects()

```
void OS_DeleteAllObjects (  
    void )
```

delete all resources created in OSAL.

provides a means to clean up all resources allocated by this instance of OSAL. It would typically be used during an orderly shutdown but may also be helpful for testing purposes.

10.3.2.7 OS_IdleLoop()

```
void OS_IdleLoop (  
    void )
```

Background thread implementation - waits forever for events to occur.

This should be called from the BSP main routine or initial thread after all other board and application initialization has taken place and all other tasks are running.

Typically just waits forever until "OS_shutdown" flag becomes true.

10.4 OSAL Object Utility APIs

Functions

- [int32 OS_GetResourceName](#) (uint32 object_id, char *buffer, [uint32](#) buffer_size)
Obtain the name of an object given an arbitrary object ID.
- [uint32 OS_IdentifyObject](#) (uint32 object_id)
Obtain the type of an object given an arbitrary object ID.
- [int32 OS_ConvertToArrayIndex](#) (uint32 object_id, [uint32](#) *ArrayIndex)
Converts an abstract ID into a number suitable for use as an array index.
- void [OS_ForEachObject](#) (uint32 creator_id, [OS_ArgCallback_t](#) callback_ptr, void *callback_arg)
call the supplied callback function for all valid object IDs

10.4.1 Detailed Description

10.4.2 Function Documentation

10.4.2.1 OS_ConvertToArrayIndex()

```
int32 OS_ConvertToArrayIndex (
    uint32 object_id,
    uint32 * ArrayIndex )
```

Converts an abstract ID into a number suitable for use as an array index.

This will return a unique zero-based integer number in the range of [0,MAX) for any valid object ID. This may be used by application code as an array index for indexing into local tables.

Note

This does NOT verify the validity of the ID, that is left to the caller. This is only the conversion logic.

Parameters

in	<i>object_id</i>	The object ID to operate on
out	<i>*ArrayIndex</i>	The Index to return

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INCORRECT_OBJ_TYPE	Incorrect object type.

10.4.2.2 OS_ForEachObject()

```
void OS_ForEachObject (
    uint32 creator_id,
    OS_ArgCallback_t callback_ptr,
    void * callback_arg )
```

call the supplied callback function for all valid object IDs

Loops through all defined OSAL objects of all types and calls callback_ptr on each one. If creator_id is nonzero then only objects with matching creator id are processed.

Parameters

in	<i>creator_id</i>	Filter objects to those created by a specific task. This may be passed as OS_OBJECT_CREATOR_ANY to return all objects.
in	<i>callback_ptr</i>	Function to invoke for each matching object ID.
in	<i>callback_arg</i>	Opaque Argument to pass to callback function.

10.4.2.3 OS_GetResourceName()

```
int32 OS_GetResourceName (
    uint32 object_id,
    char * buffer,
    uint32 buffer_size )
```

Obtain the name of an object given an arbitrary object ID.

All OSAL resources generally have a name associated with them. This allows application code to retrieve the name of any valid OSAL object ID.

Parameters

in	<i>object_id</i>	The object ID to operate on.
out	<i>buffer</i>	Buffer in which to store the name.
in	<i>buffer_size</i>	Size of the output storage buffer.

Returns

OS_SUCCESS if successful. OS_ERR_INVALID_ID if the passed-in ID is not a valid OSAL ID. OS_INVALID↵_POINTER if the passed-in buffer is invalid. OS_ERR_NAME_TOO_LONG if the name will not fit in the buffer provided.

10.4.2.4 OS_IdentifyObject()

```
uint32 OS_IdentifyObject (
    uint32 object_id )
```

Obtain the type of an object given an arbitrary object ID.

Given an arbitrary object ID, get the type of the object

Parameters

in	<i>object_id</i>	The object ID to operate on
----	------------------	-----------------------------

Returns

The object type portion of the object_id, see [OSAL Object Type Defines](#) for expected values

10.5 OSAL Task APIs

Functions

- `int32 OS_TaskCreate (uint32 *task_id, const char *task_name, osal_task_entry function_pointer, uint32 *stack_pointer, uint32 stack_size, uint32 priority, uint32 flags)`
Creates a task and starts running it.
- `int32 OS_TaskDelete (uint32 task_id)`
Deletes the specified Task.
- `void OS_TaskExit (void)`
Exits the calling task.
- `int32 OS_TaskInstallDeleteHandler (osal_task_entry function_pointer)`
Installs a handler for when the task is deleted.
- `int32 OS_TaskDelay (uint32 millisecond)`
Delay a task for specified amount of milliseconds.
- `int32 OS_TaskSetPriority (uint32 task_id, uint32 new_priority)`
Sets the given task to a new priority.
- `int32 OS_TaskRegister (void)`
Obsolete.
- `uint32 OS_TaskGetId (void)`
Obtain the task id of the calling task.
- `int32 OS_TaskGetIdByName (uint32 *task_id, const char *task_name)`
Find an existing task ID by name.
- `int32 OS_TaskGetInfo (uint32 task_id, OS_task_prop_t *task_prop)`
Fill a property object buffer with details regarding the resource.
- `int32 OS_TaskFindIdBySystemData (uint32 *task_id, const void *sysdata, size_t sysdata_size)`
Reverse-lookup the OSAL task ID from an operating system ID.

10.5.1 Detailed Description

10.5.2 Function Documentation

10.5.2.1 OS_TaskCreate()

```
int32 OS_TaskCreate (
    uint32 * task_id,
    const char * task_name,
    osal_task_entry function_pointer,
    uint32 * stack_pointer,
    uint32 stack_size,
    uint32 priority,
    uint32 flags )
```

Creates a task and starts running it.

Creates a task and passes back the id of the task created. Task names must be unique; if the name already exists this function fails. Names cannot be NULL.

Parameters

out	<i>task_id</i>	will be set to the non-zero ID of the newly-created resource
in	<i>task_name</i>	the name of the new resource to create
in	<i>function_pointer</i>	the entry point of the new task
in	<i>stack_pointer</i>	pointer to the stack for the task, or NULL to allocate a stack from the system memory heap
in	<i>stack_size</i>	the size of the stack, or 0 to use a default stack size.
in	<i>priority</i>	initial priority of the new task
in	<i>flags</i>	initial options for the new task

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if any of the necessary pointers are NULL
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_INVALID_PRIORITY	if the priority is bad
OS_ERR_NO_FREE_IDS	if there can be no more tasks created
OS_ERR_NAME_TAKEN	if the name specified is already used by a task
OS_ERROR	if an unspecified/other error occurs

10.5.2.2 OS_TaskDelay()

```
int32 OS_TaskDelay (
    uint32 millisecond )
```

Delay a task for specified amount of milliseconds.

Causes the current thread to be suspended from execution for the period of millisecond.

Parameters

in	<i>millisecond</i>	Amount of time to delay
----	--------------------	-------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERROR	if sleep fails or millisecond = 0

10.5.2.3 OS_TaskDelete()

```
int32 OS_TaskDelete (
    uint32 task_id )
```

Deletes the specified Task.

The task will be removed from the local tables. and the OS will be configured to stop executing the task at the next opportunity.

Parameters

in	<i>task_id</i>	The object ID to operate on
----	----------------	-----------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the ID given to it is invalid
OS_ERROR	if the OS delete call fails

10.5.2.4 OS_TaskExit()

```
void OS_TaskExit (
    void )
```

Exits the calling task.

The calling thread is terminated. This function does not return.

10.5.2.5 OS_TaskFindIdBySystemData()

```
int32 OS_TaskFindIdBySystemData (
    uint32 * task_id,
    const void * sysdata,
    size_t sysdata_size )
```

Reverse-lookup the OSAL task ID from an operating system ID.

This provides a method by which an external entity may find the OSAL task ID corresponding to a system-defined identifier (e.g. TASK_ID, pthread_t, rtems_id, etc).

Normally OSAL does not expose the underlying OS-specific values to the application, but in some circumstances, such as exception handling, the OS may provide this information directly to handler outside of the normal OSAL API.

Parameters

out	<i>task_id</i>	The buffer where the task id output is stored
in	<i>sysdata</i>	Pointer to the system-provided identification data
in	<i>sysdata_size</i>	Size of the system-provided identification data

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
----------------------------	-----------------------

10.5.2.6 OS_TaskGetId()

```
uint32 OS_TaskGetId (
    void )
```

Obtain the task id of the calling task.

This function returns the task id of the calling task

Returns

Task ID, or zero if the operation failed (zero is never a valid task ID)

10.5.2.7 OS_TaskGetIdByName()

```
int32 OS_TaskGetIdByName (
    uint32 * task_id,
    const char * task_name )
```

Find an existing task ID by name.

This function tries to find a task Id given the name of a task

Parameters

out	<i>task_id</i>	will be set to the ID of the existing resource
in	<i>task_name</i>	the name of the existing resource to find

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if the pointers passed in are NULL
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_NAME_NOT_FOUND	if the name wasn't found in the table

10.5.2.8 OS_TaskGetInfo()

```
int32 OS_TaskGetInfo (
    uint32 task_id,
    OS_task_prop_t * task_prop )
```

Fill a property object buffer with details regarding the resource.

This function will pass back a pointer to structure that contains all of the relevant info (creator, stack size, priority, name) about the specified task.

Parameters

in	<i>task_id</i>	The object ID to operate on
out	<i>task_prop</i>	The property object buffer to fill

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the ID passed to it is invalid
OS_INVALID_POINTER	if the task_prop pointer is NULL

10.5.2.9 OS_TaskInstallDeleteHandler()

```
int32 OS_TaskInstallDeleteHandler (
    osal_task_entry function_pointer )
```

Installs a handler for when the task is deleted.

This function is used to install a callback that is called when the task is deleted. The callback is called when `OS_TaskDelete` is called with the task ID. A task delete handler is useful for cleaning up resources that a task creates, before the task is removed from the system.

Parameters

in	<i>function_pointer</i>	function to be called when task exits
----	-------------------------	---------------------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

10.5.2.10 OS_TaskRegister()

```
int32 OS_TaskRegister (
    void )
```

Obsolete.

Deprecated Explicit registration call no longer needed

Obsolete function retained for compatibility purposes. Does Nothing in the current implementation.

Returns

`OS_SUCCESS` (always), see [OSAL Return Code Defines](#)

10.5.2.11 OS_TaskSetPriority()

```
int32 OS_TaskSetPriority (
    uint32 task_id,
    uint32 new_priority )
```

Sets the given task to a new priority.

Parameters

in	<i>task_id</i>	The object ID to operate on
in	<i>new_priority</i>	Set the new priority

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

<i>OS_SUCCESS</i>	Successful execution.
<i>OS_ERR_INVALID_ID</i>	if the ID passed to it is invalid
<i>OS_ERR_INVALID_PRIORITY</i>	if the priority is greater than the max allowed
<i>OS_ERROR</i>	if the OS call to change the priority fails

10.6 OSAL Message Queue APIs

Functions

- `int32 OS_QueueCreate` (`uint32 *queue_id`, `const char *queue_name`, `uint32 queue_depth`, `uint32 data_size`, `uint32 flags`)
Create a message queue.
- `int32 OS_QueueDelete` (`uint32 queue_id`)
Deletes the specified message queue.
- `int32 OS_QueueGet` (`uint32 queue_id`, `void *data`, `uint32 size`, `uint32 *size_copied`, `int32 timeout`)
Receive a message on a message queue.
- `int32 OS_QueuePut` (`uint32 queue_id`, `const void *data`, `uint32 size`, `uint32 flags`)
Put a message on a message queue.
- `int32 OS_QueueGetIdByName` (`uint32 *queue_id`, `const char *queue_name`)
Find an existing queue ID by name.
- `int32 OS_QueueGetInfo` (`uint32 queue_id`, `OS_queue_prop_t *queue_prop`)
Fill a property object buffer with details regarding the resource.

10.6.1 Detailed Description

10.6.2 Function Documentation

10.6.2.1 OS_QueueCreate()

```
int32 OS_QueueCreate (
    uint32 * queue_id,
    const char * queue_name,
    uint32 queue_depth,
    uint32 data_size,
    uint32 flags )
```

Create a message queue.

This is the function used to create a queue in the operating system. Depending on the underlying operating system, the memory for the queue will be allocated automatically or allocated by the code that sets up the queue. Queue names must be unique; if the name already exists this function fails. Names cannot be NULL.

Parameters

out	<code>queue_id</code>	will be set to the non-zero ID of the newly-created resource
in	<code>queue_name</code>	the name of the new resource to create
in	<code>queue_depth</code>	the maximum depth of the queue
in	<code>data_size</code>	the size of each entry in the queue
in	<code>flags</code>	options for the queue (reserved for future use, pass as 0)

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if a pointer passed in is NULL
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_NO_FREE_IDS	if there are already the max queues created
OS_ERR_NAME_TAKEN	if the name is already being used on another queue
OS_QUEUE_INVALID_SIZE	if the queue depth exceeds the limit
OS_ERROR	if the OS create call fails

10.6.2.2 OS_QueueDelete()

```
int32 OS_QueueDelete (
    uint32 queue_id )
```

Deletes the specified message queue.

This is the function used to delete a queue in the operating system. This also frees the respective queue_id to be used again when another queue is created.

Note

If There are messages on the queue, they will be lost and any subsequent calls to QueueGet or QueuePut to this queue will result in errors

Parameters

in	<i>queue_id</i>	The object ID to delete
----	-----------------	-------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the id passed in does not exist
OS_ERROR	if the OS call to delete the queue fails

10.6.2.3 OS_QueueGet()

```
int32 OS_QueueGet (
    uint32 queue_id,
    void * data,
    uint32 size,
    uint32 * size_copied,
    int32 timeout )
```

Receive a message on a message queue.

If a message is pending, it is returned immediately. Otherwise the calling task will block until a message arrives or the timeout expires.

Parameters

in	<i>queue_id</i>	The object ID to operate on
out	<i>data</i>	The buffer to store the received message
in	<i>size</i>	The size of the data buffer
out	<i>size_copied</i>	Set to the actual size of the message
in	<i>timeout</i>	The maximum amount of time to block, or OS_PEND to wait forever

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the given ID does not exist
OS_INVALID_POINTER	if a pointer passed in is NULL
OS_QUEUE_EMPTY	if the Queue has no messages on it to be recieved
OS_QUEUE_TIMEOUT	if the timeout was OS_PEND and the time expired
OS_QUEUE_INVALID_SIZE	if the size copied from the queue was not correct

10.6.2.4 OS_QueueGetIdByName()

```
int32 OS_QueueGetIdByName (
    uint32 * queue_id,
    const char * queue_name )
```

Find an existing queue ID by name.

This function tries to find a queue Id given the name of the queue. The id of the queue is passed back in queue_id.

Parameters

out	<i>queue_id</i>	will be set to the ID of the existing resource
in	<i>queue_name</i>	the name of the existing resource to find

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if the name or id pointers are NULL
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_NAME_NOT_FOUND	the name was not found in the table

10.6.2.5 OS_QueueGetInfo()

```
int32 OS_QueueGetInfo (
    uint32 queue_id,
    OS_queue_prop_t * queue_prop )
```

Fill a property object buffer with details regarding the resource.

This function will pass back a pointer to structure that contains all of the relevant info (name and creator) about the specified queue.

Parameters

in	<i>queue_id</i>	The object ID to operate on
out	<i>queue_prop</i>	The property object buffer to fill

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if queue_prop is NULL
OS_ERR_INVALID_ID	if the ID given is not a valid queue

10.6.2.6 OS_QueuePut()

```
int32 OS_QueuePut (
    uint32 queue_id,
    const void * data,
    uint32 size,
    uint32 flags )
```

Put a message on a message queue.

Parameters

in	<i>queue_id</i>	The object ID to operate on
in	<i>data</i>	The buffer containing the message to put
in	<i>size</i>	The size of the data buffer
in	<i>flags</i>	Currently reserved/unused, should be passed as 0

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the queue id passed in is not a valid queue
OS_INVALID_POINTER	if the data pointer is NULL
OS_QUEUE_FULL	if the queue cannot accept another message
OS_ERROR	if the OS call returns an error

10.7 OSAL Semaphore APIs

Functions

- `int32 OS_BinSemCreate (uint32 *sem_id, const char *sem_name, uint32 sem_initial_value, uint32 options)`
Creates a binary semaphore.
- `int32 OS_BinSemFlush (uint32 sem_id)`
Unblock all tasks pending on the specified semaphore.
- `int32 OS_BinSemGive (uint32 sem_id)`
Increment the semaphore value.
- `int32 OS_BinSemTake (uint32 sem_id)`
Decrement the semaphore value.
- `int32 OS_BinSemTimedWait (uint32 sem_id, uint32 msecs)`
Decrement the semaphore value with a timeout.
- `int32 OS_BinSemDelete (uint32 sem_id)`
Deletes the specified Binary Semaphore.
- `int32 OS_BinSemGetIdByName (uint32 *sem_id, const char *sem_name)`
Find an existing semaphore ID by name.
- `int32 OS_BinSemGetInfo (uint32 sem_id, OS_bin_sem_prop_t *bin_prop)`
Fill a property object buffer with details regarding the resource.
- `int32 OS_CountSemCreate (uint32 *sem_id, const char *sem_name, uint32 sem_initial_value, uint32 options)`
Creates a counting semaphore.
- `int32 OS_CountSemGive (uint32 sem_id)`
Increment the semaphore value.
- `int32 OS_CountSemTake (uint32 sem_id)`
Decrement the semaphore value.
- `int32 OS_CountSemTimedWait (uint32 sem_id, uint32 msecs)`
Decrement the semaphore value with timeout.
- `int32 OS_CountSemDelete (uint32 sem_id)`
Deletes the specified counting Semaphore.
- `int32 OS_CountSemGetIdByName (uint32 *sem_id, const char *sem_name)`
Find an existing semaphore ID by name.
- `int32 OS_CountSemGetInfo (uint32 sem_id, OS_count_sem_prop_t *count_prop)`
Fill a property object buffer with details regarding the resource.
- `int32 OS_MutSemCreate (uint32 *sem_id, const char *sem_name, uint32 options)`
Creates a mutex semaphore.
- `int32 OS_MutSemGive (uint32 sem_id)`
Releases the mutex object referenced by sem_id.
- `int32 OS_MutSemTake (uint32 sem_id)`
Acquire the mutex object referenced by sem_id.
- `int32 OS_MutSemDelete (uint32 sem_id)`
Deletes the specified Mutex Semaphore.
- `int32 OS_MutSemGetIdByName (uint32 *sem_id, const char *sem_name)`
Find an existing mutex ID by name.
- `int32 OS_MutSemGetInfo (uint32 sem_id, OS_mut_sem_prop_t *mut_prop)`
Fill a property object buffer with details regarding the resource.

10.7.1 Detailed Description

10.7.2 Function Documentation

10.7.2.1 OS_BinSemCreate()

```
int32 OS_BinSemCreate (
    uint32 * sem_id,
    const char * sem_name,
    uint32 sem_initial_value,
    uint32 options )
```

Creates a binary semaphore.

Creates a binary semaphore with initial value specified by `sem_initial_value` and name specified by `sem_name`. `sem_id` will be returned to the caller

Parameters

out	<i>sem_id</i>	will be set to the non-zero ID of the newly-created resource
in	<i>sem_name</i>	the name of the new resource to create
in	<i>sem_initial_value</i>	the initial value of the binary semaphore
in	<i>options</i>	Reserved for future use, should be passed as 0.

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if <code>sem_name</code> or <code>sem_id</code> are NULL
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_NO_FREE_IDS	if all of the semaphore ids are taken
OS_ERR_NAME_TAKEN	if this is already the name of a binary semaphore
OS_SEM_FAILURE	if the OS call failed

10.7.2.2 OS_BinSemDelete()

```
int32 OS_BinSemDelete (
    uint32 sem_id )
```

Deletes the specified Binary Semaphore.

This is the function used to delete a binary semaphore in the operating system. This also frees the respective `sem_id` to be used again when another semaphore is created.

Parameters

in	<i>sem</i> ↔ _id	The object ID to delete
----	---------------------	-------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the id passed in is not a valid binary semaphore
OS_SEM_FAILURE	the OS call failed

10.7.2.3 OS_BinSemFlush()

```
int32 OS_BinSemFlush (
    uint32 sem_id )
```

Unblock all tasks pending on the specified semaphore.

The function unblocks all tasks pending on the specified semaphore. However, this function does not change the state of the semaphore.

Parameters

in	<i>sem</i> ↔ _id	The object ID to operate on
----	---------------------	-----------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the id passed in is not a binary semaphore
OS_SEM_FAILURE	if an unspecified failure occurs

10.7.2.4 OS_BinSemGetIdByName()

```
int32 OS_BinSemGetIdByName (
```

```
uint32 * sem_id,
const char * sem_name )
```

Find an existing semaphore ID by name.

This function tries to find a binary sem Id given the name of a bin_sem The id is returned through sem_id

Parameters

out	<i>sem_id</i>	will be set to the ID of the existing resource
in	<i>sem_name</i>	the name of the existing resource to find

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	is semid or sem_name are NULL pointers
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_NAME_NOT_FOUND	if the name was not found in the table

10.7.2.5 OS_BinSemGetInfo()

```
int32 OS_BinSemGetInfo (
    uint32 sem_id,
    OS_bin_sem_prop_t * bin_prop )
```

Fill a property object buffer with details regarding the resource.

This function will pass back a pointer to structure that contains all of the relevant info(name and creator) about the specified binary semaphore.

Parameters

in	<i>sem_id</i>	The object ID to operate on
out	<i>bin_prop</i>	The property object buffer to fill

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

<i>OS_SUCCESS</i>	Successful execution.
<i>OS_ERR_INVALID_ID</i>	if the id passed in is not a valid semaphore
<i>OS_INVALID_POINTER</i>	if the bin_prop pointer is null

10.7.2.6 OS_BinSemGive()

```
int32 OS_BinSemGive (
    uint32 sem_id )
```

Increment the semaphore value.

The function unlocks the semaphore referenced by sem_id by performing a semaphore unlock operation on that semaphore. If the semaphore value resulting from this operation is positive, then no threads were blocked waiting for the semaphore to become unlocked; the semaphore value is simply incremented for this semaphore.

Parameters

in	<i>sem</i> ↔ <i>_id</i>	The object ID to operate on
----	----------------------------	-----------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

<i>OS_SUCCESS</i>	Successful execution.
<i>OS_SEM_FAILURE</i>	the semaphore was not previously initialized or is not in the array of semaphores defined by the system
<i>OS_ERR_INVALID_ID</i>	if the id passed in is not a binary semaphore

10.7.2.7 OS_BinSemTake()

```
int32 OS_BinSemTake (
    uint32 sem_id )
```

Decrement the semaphore value.

The locks the semaphore referenced by sem_id by performing a semaphore lock operation on that semaphore. If the semaphore value is currently zero, then the calling thread shall not return from the call until it either locks the semaphore or the call is interrupted.

Parameters

in	<i>sem</i> ↔ <i>_id</i>	The object ID to operate on
----	----------------------------	-----------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	the Id passed in is not a valid binary semaphore
OS_SEM_FAILURE	if the OS call failed

10.7.2.8 OS_BinSemTimedWait()

```
int32 OS_BinSemTimedWait (
    uint32 sem_id,
    uint32 msec )
```

Decrement the semaphore value with a timeout.

The function locks the semaphore referenced by *sem_id*. However, if the semaphore cannot be locked without waiting for another process or thread to unlock the semaphore, this wait shall be terminated when the specified timeout, msec, expires.

Parameters

in	<i>sem</i> ↔ <i>_id</i>	The object ID to operate on
in	<i>msec</i>	The maximum amount of time to block, in milliseconds

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_SEM_TIMEOUT	if semaphore was not relinquished in time
OS_SEM_FAILURE	the semaphore was not previously initialized or is not in the array of semaphores defined by the system
OS_ERR_INVALID_ID	if the ID passed in is not a valid semaphore ID

10.7.2.9 OS_CountSemCreate()

```
int32 OS_CountSemCreate (
    uint32 * sem_id,
    const char * sem_name,
    uint32 sem_initial_value,
    uint32 options )
```

Creates a counting semaphore.

Creates a counting semaphore with initial value specified by `sem_initial_value` and name specified by `sem_name`. `sem_id` will be returned to the caller

Parameters

out	<i>sem_id</i>	will be set to the non-zero ID of the newly-created resource
in	<i>sem_name</i>	the name of the new resource to create
in	<i>sem_initial_value</i>	the initial value of the counting semaphore
in	<i>options</i>	Reserved for future use, should be passed as 0.

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if <code>sem_name</code> or <code>sem_id</code> are NULL
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_NO_FREE_IDS	if all of the semaphore ids are taken
OS_ERR_NAME_TAKEN	if this is already the name of a counting semaphore
OS_SEM_FAILURE	if the OS call failed
OS_INVALID_SEM_VALUE	if the semaphore value is too high

10.7.2.10 OS_CountSemDelete()

```
int32 OS_CountSemDelete (
    uint32 sem_id )
```

Deletes the specified counting Semaphore.

Parameters

in	<i>sem_id</i>	The object ID to delete
----	---------------	-------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the id passed in is not a valid counting semaphore
OS_SEM_FAILURE	the OS call failed

10.7.2.11 OS_CountSemGetIdByName()

```
int32 OS_CountSemGetIdByName (
    uint32 * sem_id,
    const char * sem_name )
```

Find an existing semaphore ID by name.

This function tries to find a counting sem Id given the name of a count_sem The id is returned through sem_id

Parameters

out	<i>sem_id</i>	will be set to the ID of the existing resource
in	<i>sem_name</i>	the name of the existing resource to find

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	is semid or sem_name are NULL pointers
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_NAME_NOT_FOUND	if the name was not found in the table

10.7.2.12 OS_CountSemGetInfo()

```
int32 OS_CountSemGetInfo (
    uint32 sem_id,
    OS_count_sem_prop_t * count_prop )
```

Fill a property object buffer with details regarding the resource.

This function will pass back a pointer to structure that contains all of the relevant info(name and creator) about the specified counting semaphore.

Parameters

in	<i>sem_id</i>	The object ID to operate on
out	<i>count_prop</i>	The property object buffer to fill

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the id passed in is not a valid semaphore
OS_INVALID_POINTER	if the count_prop pointer is null

10.7.2.13 OS_CountSemGive()

```
int32 OS_CountSemGive (
    uint32 sem_id )
```

Increment the semaphore value.

The function unlocks the semaphore referenced by sem_id by performing a semaphore unlock operation on that semaphore. If the semaphore value resulting from this operation is positive, then no threads were blocked waiting for the semaphore to become unlocked; the semaphore value is simply incremented for this semaphore.

Parameters

in	<i>sem_id</i>	The object ID to operate on
----	---------------	-----------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

<i>OS_SUCCESS</i>	Successful execution.
<i>OS_SEM_FAILURE</i>	the semaphore was not previously initialized or is not in the array of semaphores defined by the system
<i>OS_ERR_INVALID_ID</i>	if the id passed in is not a counting semaphore

10.7.2.14 OS_CountSemTake()

```
int32 OS_CountSemTake (
    uint32 sem_id )
```

Decrement the semaphore value.

The locks the semaphore referenced by sem_id by performing a semaphore lock operation on that semaphore. If the semaphore value is currently zero, then the calling thread shall not return from the call until it either locks the semaphore or the call is interrupted.

Parameters

in	<i>sem_id</i>	The object ID to operate on
----	---------------	-----------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

<i>OS_SUCCESS</i>	Successful execution.
<i>OS_ERR_INVALID_ID</i>	the Id passed in is not a valid counting semaphore
<i>OS_SEM_FAILURE</i>	if the OS call failed

10.7.2.15 OS_CountSemTimedWait()

```
int32 OS_CountSemTimedWait (
    uint32 sem_id,
    uint32 msec )
```

Decrement the semaphore value with timeout.

The function locks the semaphore referenced by sem_id. However, if the semaphore cannot be locked without waiting for another process or thread to unlock the semaphore, this wait shall be terminated when the specified timeout, msec, expires.

Parameters

in	<i>sem_id</i>	The object ID to operate on
in	<i>msecs</i>	The maximum amount of time to block, in milliseconds

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_SEM_TIMEOUT	if semaphore was not relinquished in time
OS_SEM_FAILURE	the semaphore was not previously initialized or is not in the array of semaphores defined by the system
OS_ERR_INVALID_ID	if the ID passed in is not a valid semaphore ID

10.7.2.16 OS_MutSemCreate()

```
int32 OS_MutSemCreate (
    uint32 * sem_id,
    const char * sem_name,
    uint32 options )
```

Creates a mutex semaphore.

Mutex semaphores are always created in the unlocked (full) state.

Parameters

out	<i>sem_id</i>	will be set to the non-zero ID of the newly-created resource
in	<i>sem_name</i>	the name of the new resource to create
in	<i>options</i>	reserved for future use. Should be passed as 0.

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if <i>sem_id</i> or <i>sem_name</i> are NULL
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME

Return values

OS_ERR_NO_FREE_IDS	if there are no more free mutex Ids
OS_ERR_NAME_TAKEN	if there is already a mutex with the same name
OS_SEM_FAILURE	if the OS call failed

10.7.2.17 OS_MutSemDelete()

```
int32 OS_MutSemDelete (
    uint32 sem_id )
```

Deletes the specified Mutex Semaphore.

Delete the semaphore. This also frees the respective sem_id such that it can be used again when another is created.

Parameters

in	<i>sem_id</i>	The object ID to delete
----	---------------	-------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the id passed in is not a valid mutex
OS_SEM_FAILURE	if the OS call failed

10.7.2.18 OS_MutSemGetIdByName()

```
int32 OS_MutSemGetIdByName (
    uint32 * sem_id,
    const char * sem_name )
```

Find an existing mutex ID by name.

This function tries to find a mutex sem Id given the name of a mut_sem. The id is returned through sem_id

Parameters

out	<i>sem_id</i>	will be set to the ID of the existing resource
in	<i>sem_name</i>	the name of the existing resource to find

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	is semid or sem_name are NULL pointers
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_NAME_NOT_FOUND	if the name was not found in the table

10.7.2.19 OS_MutSemGetInfo()

```
int32 OS_MutSemGetInfo (
    uint32 sem_id,
    OS_mut_sem_prop_t * mut_prop )
```

Fill a property object buffer with details regarding the resource.

This function will pass back a pointer to structure that contains all of the relevant info(name and creator) about the specified mutex semaphore.

Parameters

in	<i>sem_id</i>	The object ID to operate on
out	<i>mut_prop</i>	The property object buffer to fill

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the id passed in is not a valid semaphore
OS_INVALID_POINTER	if the mut_prop pointer is null

10.7.2.20 OS_MutSemGive()

```
int32 OS_MutSemGive (
    uint32 sem_id )
```

Releases the mutex object referenced by sem_id.

If there are threads blocked on the mutex object referenced by `mutex` when this function is called, resulting in the mutex becoming available, the scheduling policy shall determine which thread shall acquire the mutex.

Parameters

in	<i>sem</i> ↔ <i>_id</i>	The object ID to operate on
----	----------------------------	-----------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the id passed in is not a valid mutex
OS_SEM_FAILURE	if an unspecified error occurs

10.7.2.21 OS_MutSemTake()

```
int32 OS_MutSemTake (
    uint32 sem_id )
```

Acquire the mutex object referenced by *sem_id*.

If the mutex is already locked, the calling thread shall block until the mutex becomes available. This operation shall return with the mutex object referenced by *mutex* in the locked state with the calling thread as its owner.

Parameters

in	<i>sem</i> ↔ <i>_id</i>	The object ID to operate on
----	----------------------------	-----------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_SEM_FAILURE	if the semaphore was not previously initialized or is not in the array of semaphores defined by the system
OS_ERR_INVALID_ID	the id passed in is not a valid mutex

10.8 OSAL Time/Tick APIs

Functions

- [int32 OS_Milli2Ticks](#) ([uint32](#) milli_seconds)
Convert time units from milliseconds to system ticks.
- [int32 OS_Tick2Micros](#) (void)
Get the system tick size, in microseconds.
- [int32 OS_GetLocalTime](#) ([OS_time_t](#) *time_struct)
Get the local time.
- [int32 OS_SetLocalTime](#) ([OS_time_t](#) *time_struct)
Set the local time.

10.8.1 Detailed Description

10.8.2 Function Documentation

10.8.2.1 OS_GetLocalTime()

```
int32 OS_GetLocalTime (
    OS_time_t * time_struct )
```

Get the local time.

This function gets the local time from the underlying OS.

Note

Mission time management typically uses the cFE Time Service

Parameters

out	<i>time_struct</i>	An OS_time_t that will be set to the current time
-----	--------------------	---

Returns

Get local time status, see [OSAL Return Code Defines](#)

10.8.2.2 OS_Milli2Ticks()

```
int32 OS_Milli2Ticks (
    uint32 milli_seconds )
```


Convert time units from milliseconds to system ticks.

This function accepts a time interval in milliseconds and returns the tick equivalent. If the result is not an exact number of system ticks, the result will be rounded up to the nearest tick.

Parameters

in	<i>milli_seconds</i>	the number of milliseconds
----	----------------------	----------------------------

Returns

The number of ticks

10.8.2.3 OS_SetLocalTime()

```
int32 OS_SetLocalTime (
    OS_time_t * time_struct )
```

Set the local time.

This function sets the local time on the underlying OS.

Note

Mission time management typically uses the cFE Time Services

Parameters

in	<i>time_struct</i>	An OS_time_t containing the current time
----	--------------------	--

Returns

Set local time status, see [OSAL Return Code Defines](#)

10.8.2.4 OS_Tick2Micros()

```
int32 OS_Tick2Micros (
    void )
```

Get the system tick size, in microseconds.

This function returns the duration of a system tick in micro seconds

Note

care is taken to ensure this does not return "0" since it is often used as the divisor in mathematical operations

Returns

Duration of a system tick in microseconds

10.9 OSAL Exception APIs

Functions

- `int32 OS_ExcAttachHandler (uint32 ExceptionNumber, void(*ExceptionHandler)(uint32, const void *, uint32), int32 parameter)`
placeholder; not currently implemented
- `int32 OS_ExcEnable (int32 ExceptionNumber)`
placeholder; not currently implemented
- `int32 OS_ExcDisable (int32 ExceptionNumber)`
placeholder; not currently implemented

10.9.1 Detailed Description

Note

Not implemented in current OSAL version

Deprecated Planning move to PSP due to platform dependencies

10.9.2 Function Documentation

10.9.2.1 OS_ExcAttachHandler()

```
int32 OS_ExcAttachHandler (
    uint32 ExceptionNumber,
    void(*) (uint32, const void *, uint32) ExceptionHandler,
    int32 parameter )
```

placeholder; not currently implemented

Deprecated Planning move to PSP due to platform dependencies

10.9.2.2 OS_ExcDisable()

```
int32 OS_ExcDisable (
    int32 ExceptionNumber )
```

placeholder; not currently implemented

Deprecated Planning move to PSP due to platform dependencies

10.9.2.3 OS_ExcEnable()

```
int32 OS_ExcEnable (
    int32 ExceptionNumber )
```

placeholder; not currently implemented

Deprecated Planning move to PSP due to platform dependencies

10.10 OSAL Floating Point Unit Exception APIs

Functions

- [int32 OS_FPUExcAttachHandler](#) (uint32 ExceptionNumber, osal_task_entry ExceptionHandler, [int32](#) parameter)
Set an FPU exception handler function.
- [int32 OS_FPUExcEnable](#) (int32 ExceptionNumber)
Enable FPU exceptions.
- [int32 OS_FPUExcDisable](#) (int32 ExceptionNumber)
Disable FPU exceptions.
- [int32 OS_FPUExcSetMask](#) (uint32 mask)
Sets the FPU exception mask.
- [int32 OS_FPUExcGetMask](#) (uint32 *mask)
Gets the FPU exception mask.

10.10.1 Detailed Description

Deprecated Planning move to PSP due to platform dependencies

10.10.2 Function Documentation

10.10.2.1 OS_FPUExcAttachHandler()

```
int32 OS_FPUExcAttachHandler (
    uint32 ExceptionNumber,
    osal_task_entry ExceptionHandler,
    int32 parameter )
```

Set an FPU exception handler function.

The call associates a specified C routine to a specified FPU exception number. When the specified FPU Exception occurs , the ExceptionHandler routine will be called and passed the parameter.

Deprecated Planning move to PSP due to platform dependencies

Parameters

in	<i>ExceptionNumber</i>	The exception number to attach to
in	<i>ExceptionHandler</i>	Pointer to handler function
in	<i>parameter</i>	Argument to pass to handler

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_NOT_IMPLEMENTED	Not implemented.

10.10.2.2 OS_FPUExcDisable()

```
int32 OS_FPUExcDisable (
    int32 ExceptionNumber )
```

Disable FPU exceptions.

Deprecated Planning move to PSP due to platform dependencies

Parameters

in	<i>ExceptionNumber</i>	The exception number to disable
----	------------------------	---------------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_NOT_IMPLEMENTED	Not implemented.

10.10.2.3 OS_FPUExcEnable()

```
int32 OS_FPUExcEnable (
    int32 ExceptionNumber )
```

Enable FPU exceptions.

Deprecated Planning move to PSP due to platform dependencies

Parameters

in	<i>ExceptionNumber</i>	The exception number to enable
----	------------------------	--------------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_NOT_IMPLEMENTED	Not implemented.

10.10.2.4 OS_FPUExcGetMask()

```
int32 OS_FPUExcGetMask (
    uint32 * mask )
```

Gets the FPU exception mask.

Deprecated Planning move to PSP due to platform dependencies

This function gets the FPU exception mask

Note

The exception environment is local to each task Therefore this must be called for each task that that wants to do floating point and catch exceptions.

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_NOT_IMPLEMENTED	Not implemented.

10.10.2.5 OS_FPUExcSetMask()

```
int32 OS_FPUExcSetMask (
```

```
uint32 mask )
```

Sets the FPU exception mask.

Deprecated Planning move to PSP due to platform dependencies

This function sets the FPU exception mask

Note

The exception environment is local to each task Therefore this must be called for each task that that wants to do floating point and catch exceptions.

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_NOT_IMPLEMENTED	Not implemented.

10.11 OSAL Interrupt APIs

Functions

- `int32 OS_IntAttachHandler (uint32 InterruptNumber, osal_task_entry InterruptHandler, int32 parameter)`
DEPRECATED; Associate an interrupt number to a specified handler routine.
- `int32 OS_IntUnlock (int32 IntLevel)`
DEPRECATED; Enable interrupts.
- `int32 OS_IntLock (void)`
DEPRECATED; Disable interrupts.
- `int32 OS_IntEnable (int32 Level)`
DEPRECATED; Enables interrupts through Level.
- `int32 OS_IntDisable (int32 Level)`
DEPRECATED; Disable interrupts through Level.
- `int32 OS_IntSetMask (uint32 mask)`
DEPRECATED; Set the CPU interrupt mask register.
- `int32 OS_IntGetMask (uint32 *mask)`
DEPRECATED; Get the CPU interrupt mask register.
- `int32 OS_IntAck (int32 InterruptNumber)`
DEPRECATED; Acknowledge the corresponding interrupt number.

10.11.1 Detailed Description

Deprecated Platform dependencies

10.11.2 Function Documentation

10.11.2.1 OS_IntAck()

```
int32 OS_IntAck (
    int32 InterruptNumber )
```

DEPRECATED; Acknowledge the corresponding interrupt number.

Deprecated platform dependencies, removing from OSAL

Note

: placeholder; not currently implemented in sample implementations

Parameters

in	<i>InterruptNumber</i>	The interrupt number to be acknowledged.
----	------------------------	--

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_INT_NUM	Invalid Interrupt number.
OS_ERR_NOT_IMPLEMENTED	Not implemented.

10.11.2.2 OS_IntAttachHandler()

```
int32 OS_IntAttachHandler (
    uint32 InterruptNumber,
    osal_task_entry InterruptHandler,
    int32 parameter )
```

DEPRECATED; Associate an interrupt number to a specified handler routine.

Deprecated platform dependencies, removing from OSAL

The call associates a specified C routine to a specified interrupt number. Upon occurring of the InterruptNumber, the InterruptHandler routine will be called and passed the parameter.

Parameters

in	<i>InterruptNumber</i>	The Interrupt Number that will cause the start of the ISR
in	<i>InterruptHandler</i>	The ISR associated with this interrupt
in	<i>parameter</i>	Argument that is passed to the ISR

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	The Interrupt handler pointer is NULL
OS_ERR_NOT_IMPLEMENTED	Not implemented.

10.11.2.3 OS_IntDisable()

```
int32 OS_IntDisable (
    int32 Level )
```

DEPRECATED; Disable interrupts through Level.

Deprecated platform dependencies, removing from OSAL

Parameters

in	<i>Level</i>	the interrupts to disable
----	--------------	---------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_NOT_IMPLEMENTED	Not implemented.

10.11.2.4 OS_IntEnable()

```
int32 OS_IntEnable (
    int32 Level )
```

DEPRECATED; Enables interrupts through Level.

Deprecated platform dependencies, removing from OSAL

Parameters

in	<i>Level</i>	the interrupts to enable
----	--------------	--------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

<i>OS_SUCCESS</i>	Successful execution.
<i>OS_ERR_NOT_IMPLEMENTED</i>	Not implemented.

10.11.2.5 OS_IntGetMask()

```
int32 OS_IntGetMask (
    uint32 * mask )
```

DEPRECATED; Get the CPU interrupt mask register.

Deprecated platform dependencies, removing from OSAL

Note

The interrupt bits are architecture-specific.

Parameters

out	<i>mask</i>	The register value will be stored to this location
-----	-------------	--

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

<i>OS_SUCCESS</i>	Successful execution.
<i>OS_ERR_NOT_IMPLEMENTED</i>	Not implemented.

10.11.2.6 OS_IntLock()

```
int32 OS_IntLock (
    void )
```

DEPRECATED; Disable interrupts.

Deprecated platform dependencies, removing from OSAL

Returns

An key value to be passed to [OS_IntUnlock\(\)](#) to restore interrupts or error status, see [OSAL Return Code Defines](#)

Return values

<code>OS_SUCCESS</code>	Successful execution.
<code>OS_ERR_NOT_IMPLEMENTED</code>	Not implemented.

10.11.2.7 OS_IntSetMask()

```
int32 OS_IntSetMask (
    uint32 mask )
```

DEPRECATED; Set the CPU interrupt mask register.

Deprecated platform dependencies, removing from OSAL

Note

The interrupt bits are architecture-specific.

Parameters

in	<i>mask</i>	The value to set in the register
----	-------------	----------------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

<code>OS_SUCCESS</code>	Successful execution.
<code>OS_ERR_NOT_IMPLEMENTED</code>	Not implemented.

10.11.2.8 OS_IntUnlock()

```
int32 OS_IntUnlock (
    int32 IntLevel )
```

DEPRECATED; Enable interrupts.

Deprecated platform dependencies, removing from OSAL

Parameters

in	<i>IntLevel</i>	value from previous call to OS_IntLock()
----	-----------------	--

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_NOT_IMPLEMENTED	Not implemented.

10.12 OSAL Shared memory APIs

Functions

- `int32 OS_ShMemInit (void)`
DEPRECATED - platform dependent, never implemented in framework OSALs.
- `int32 OS_ShMemCreate (uint32 *Id, uint32 NBytes, const char *SegName)`
DEPRECATED - platform dependent, never implemented in framework OSALs.
- `int32 OS_ShMemSemTake (uint32 Id)`
DEPRECATED - platform dependent, never implemented in framework OSALs.
- `int32 OS_ShMemSemGive (uint32 Id)`
DEPRECATED - platform dependent, never implemented in framework OSALs.
- `int32 OS_ShMemAttach (cpuaddr *Address, uint32 Id)`
DEPRECATED - platform dependent, never implemented in framework OSALs.
- `int32 OS_ShMemGetIdByName (uint32 *ShMemId, const char *SegName)`
DEPRECATED - platform dependent, never implemented in framework OSALs.

10.12.1 Detailed Description

Deprecated Not in current implementations

10.12.2 Function Documentation

10.12.2.1 OS_ShMemAttach()

```
int32 OS_ShMemAttach (
    cpuaddr * Address,
    uint32 Id )
```

DEPRECATED - platform dependent, never implemented in framework OSALs.

Deprecated Never implemented

10.12.2.2 OS_ShMemCreate()

```
int32 OS_ShMemCreate (
    uint32 * Id,
    uint32 NBytes,
    const char * SegName )
```

DEPRECATED - platform dependent, never implemented in framework OSALs.

Deprecated Never implemented

10.12.2.3 OS_ShMemGetIdByName()

```
int32 OS_ShMemGetIdByName (
    uint32 * ShMemId,
    const char * SegName )
```

DEPRECATED - platform dependent, never implemented in framework OSALs.

Deprecated Never implemented

10.12.2.4 OS_ShMemInit()

```
int32 OS_ShMemInit (
    void )
```

DEPRECATED - platform dependent, never implemented in framework OSALs.

Deprecated Never implemented

10.12.2.5 OS_ShMemSemGive()

```
int32 OS_ShMemSemGive (
    uint32 Id )
```

DEPRECATED - platform dependent, never implemented in framework OSALs.

Deprecated Never implemented

10.12.2.6 OS_ShMemSemTake()

```
int32 OS_ShMemSemTake (
    uint32 Id )
```

DEPRECATED - platform dependent, never implemented in framework OSALs.

Deprecated Never implemented

10.13 OSAL Heap APIs

Functions

- [int32 OS_HeapGetInfo](#) ([OS_heap_prop_t](#) *heap_prop)
Return current info on the heap.

10.13.1 Detailed Description

10.13.2 Function Documentation

10.13.2.1 OS_HeapGetInfo()

```
int32 OS_HeapGetInfo (  
    OS_heap_prop_t * heap_prop )
```

Return current info on the heap.

Parameters

out	<i>heap_prop</i>	Storage buffer for heap info
-----	------------------	------------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

10.14 OSAL Error Info APIs

Functions

- [int32 OS_GetErrorName](#) ([int32](#) error_num, [os_err_name_t](#) *err_name)
Convert an error number to a string.

10.14.1 Detailed Description

10.14.2 Function Documentation

10.14.2.1 OS_GetErrorName()

```
int32 OS_GetErrorName (
    int32 error_num,
    os_err_name_t * err_name )
```

Convert an error number to a string.

Parameters

in	<i>error_num</i>	Error number to convert
out	<i>err_name</i>	Buffer to store error string

Returns

Execution status, see [OSAL Return Code Defines](#)

10.15 OSAL Select APIs

Functions

- `int32 OS_SelectMultiple (OS_FdSet *ReadSet, OS_FdSet *WriteSet, int32 msec)`
Wait for events across multiple file handles.
- `int32 OS_SelectSingle (uint32 objid, uint32 *StateFlags, int32 msec)`
Wait for events on a single file handle.
- `int32 OS_SelectFdZero (OS_FdSet *Set)`
Clear a FdSet structure.
- `int32 OS_SelectFdAdd (OS_FdSet *Set, uint32 objid)`
Add an ID to an FdSet structure.
- `int32 OS_SelectFdClear (OS_FdSet *Set, uint32 objid)`
Clear an ID from an FdSet structure.
- `bool OS_SelectFdsSet (OS_FdSet *Set, uint32 objid)`
Check if an FdSet structure contains a given ID.

10.15.1 Detailed Description

10.15.2 Function Documentation

10.15.2.1 OS_SelectFdAdd()

```
int32 OS_SelectFdAdd (
    OS_FdSet * Set,
    uint32 objid )
```

Add an ID to an FdSet structure.

After this call the set will contain the given OSAL ID

Returns

Execution status, see [OSAL Return Code Defines](#)

10.15.2.2 OS_SelectFdClear()

```
int32 OS_SelectFdClear (
    OS_FdSet * Set,
    uint32 objid )
```

Clear an ID from an FdSet structure.

After this call the set will no longer contain the given OSAL ID

Returns

Execution status, see [OSAL Return Code Defines](#)

10.15.2.3 OS_SelectFdsSet()

```
bool OS_SelectFdsSet (
    OS_FdSet * Set,
    uint32 objid )
```

Check if an FdSet structure contains a given ID.

Returns

Boolean set status

Return values

<i>true</i>	FdSet structure contains ID
<i>false</i>	FdSet structure does not contain ID

10.15.2.4 OS_SelectFdZero()

```
int32 OS_SelectFdZero (
    OS_FdSet * Set )
```

Clear a FdSet structure.

After this call the set will contain no OSAL IDs

Returns

Execution status, see [OSAL Return Code Defines](#)

10.15.2.5 OS_SelectMultiple()

```
int32 OS_SelectMultiple (
    OS_FdSet * ReadSet,
    OS_FdSet * WriteSet,
    int32 msec )
```

Wait for events across multiple file handles.

Wait for any of the given sets of IDs to become readable or writable

This function will block until any of the following occurs:

- At least one OSAL ID in the ReadSet is readable
- At least one OSAL ID in the WriteSet is writable
- The timeout has elapsed

The sets are input/output parameters. On entry, these indicate the file handle(s) to wait for. On exit, these are set to the actual file handle(s) that have activity.

If the timeout occurs this returns an error code and all output sets should be empty.

Note

This does not lock or otherwise protect the file handles in the given sets. If a filehandle supplied via one of the FdSet arguments is closed or modified by another while this function is in progress, the results are undefined. Because of this limitation, it is recommended to use [OS_SelectSingle\(\)](#) whenever possible.

Returns

Execution status, see [OSAL Return Code Defines](#)

10.15.2.6 OS_SelectSingle()

```
int32 OS_SelectSingle (
    uint32 objid,
    uint32 * StateFlags,
    int32 msec )
```

Wait for events on a single file handle.

Wait for a single OSAL filehandle to change state

This function can be used to wait for a single OSAL stream ID to become readable or writable. On entry, the "StateFlags" parameter should be set to the desired state (OS_STREAM_STATE_READABLE and/or OS_STREAM_STATE_WRITEABLE) and upon return the flags will be set to the state actually detected.

As this operates on a single ID, the filehandle is protected during this call, such that another thread accessing the same handle will return an error. However, it is important to note that once the call returns then other threads may then also read/write and affect the state before the current thread can service it.

To mitigate this risk the application may prefer to use the OS_TimedRead/OS_TimedWrite calls.

Returns

Execution status, see [OSAL Return Code Defines](#)

10.16 OSAL Printf APIs

Functions

- void [OS_printf](#) (const char *string,...) [OS_PRINTF](#)(1
Abstraction for the system printf() call.
- void void [OS_printf_disable](#) (void)
This function disables the output from OS_printf.
- void [OS_printf_enable](#) (void)
This function enables the output from OS_printf.

10.16.1 Detailed Description

10.16.2 Function Documentation

10.16.2.1 OS_printf()

```
void OS_printf (
    const char * string,
    ... )
```

Abstraction for the system printf() call.

This function abstracts out the printf type statements. This is useful for using OS- specific thats that will allow non-pollled print statements for the real time systems.

Operates in a manner similar to the printf() call defined by the standard C library and takes all the parameters and formatting options of printf. This abstraction may implement additional buffering, if necessary, to improve the real-time performance of the call.

Strings (including terminator) longer than [OS_BUFFER_SIZE](#) will be truncated.

The output of this routine also may be dynamically enabled or disabled by the [OS_printf_enable\(\)](#) and [OS_printf_disable\(\)](#) calls, respectively.

Parameters

in	<i>string</i>	Format string, followed by additional arguments
----	---------------	---

10.16.2.2 OS_printf_disable()

```
void void OS_printf_disable (
    void )
```

This function disables the output from OS_printf.

10.16.2.3 OS_printf_enable()

```
void OS_printf_enable (
    void )
```

This function enables the output from OS_printf.

10.17 OSAL File Access Option Defines

Macros

- `#define OS_READ_ONLY 0`
- `#define OS_WRITE_ONLY 1`
- `#define OS_READ_WRITE 2`

10.17.1 Detailed Description

10.17.2 Macro Definition Documentation

10.17.2.1 OS_READ_ONLY

```
#define OS_READ_ONLY 0
```

Read only file access

Definition at line 36 of file osapi-os-filesys.h.

10.17.2.2 OS_READ_WRITE

```
#define OS_READ_WRITE 2
```

Read write file access

Definition at line 38 of file osapi-os-filesys.h.

10.17.2.3 OS_WRITE_ONLY

```
#define OS_WRITE_ONLY 1
```

Write only file access

Definition at line 37 of file osapi-os-filesys.h.

10.18 OSAL Reference Point For Seek Offset Defines

Macros

- `#define OS_SEEK_SET 0`
- `#define OS_SEEK_CUR 1`
- `#define OS_SEEK_END 2`

10.18.1 Detailed Description

10.18.2 Macro Definition Documentation

10.18.2.1 OS_SEEK_CUR

```
#define OS_SEEK_CUR 1
```

Seek offset current

Definition at line 45 of file `osapi-os-filesys.h`.

10.18.2.2 OS_SEEK_END

```
#define OS_SEEK_END 2
```

Seek offset end

Definition at line 46 of file `osapi-os-filesys.h`.

10.18.2.3 OS_SEEK_SET

```
#define OS_SEEK_SET 0
```

Seek offset set

Definition at line 44 of file `osapi-os-filesys.h`.

10.19 OSAL Volume Type Defines

Macros

- `#define FS_BASED 0`
- `#define RAM_DISK 1`
- `#define EEPROM_DISK 2`
- `#define ATA_DISK 3`

10.19.1 Detailed Description

10.19.2 Macro Definition Documentation

10.19.2.1 ATA_DISK

```
#define ATA_DISK 3
```

Deprecated Volume type ATA disk

Definition at line 60 of file osapi-os-filesys.h.

10.19.2.2 EEPROM_DISK

```
#define EEPROM_DISK 2
```

Deprecated Volume type EEPROM disk

Definition at line 59 of file osapi-os-filesys.h.

10.19.2.3 FS_BASED

```
#define FS_BASED 0
```

Deprecated Volume type FS based

Definition at line 57 of file osapi-os-filesys.h.

10.19.2.4 RAM_DISK

```
#define RAM_DISK 1
```

Deprecated Volume type RAM disk

Definition at line 58 of file osapi-os-filesys.h.

10.20 OSAL Standard File APIs

Functions

- [int32 OS_creat](#) (const char *path, [int32](#) access)
Creates a file specified by path.
- [int32 OS_open](#) (const char *path, [int32](#) access, [uint32](#) mode)
Opens a file.
- [int32 OS_close](#) ([uint32](#) fidedes)
Closes an open file handle.
- [int32 OS_read](#) ([uint32](#) fidedes, void *buffer, [uint32](#) nbytes)
Read from a file handle.
- [int32 OS_write](#) ([uint32](#) fidedes, const void *buffer, [uint32](#) nbytes)
Write to a file handle.
- [int32 OS_TimedRead](#) ([uint32](#) fidedes, void *buffer, [uint32](#) nbytes, [int32](#) timeout)
File/Stream input read with a timeout.
- [int32 OS_TimedWrite](#) ([uint32](#) fidedes, const void *buffer, [uint32](#) nbytes, [int32](#) timeout)
File/Stream output write with a timeout.
- [int32 OS_chmod](#) (const char *path, [uint32](#) access)
Changes the permissions of a file.
- [int32 OS_stat](#) (const char *path, [os_fstat_t](#) *filestats)
Obtain information about a file or directory.
- [int32 OS_lseek](#) ([uint32](#) fidedes, [int32](#) offset, [uint32](#) whence)
Seeks to the specified position of an open file.
- [int32 OS_remove](#) (const char *path)
Removes a file from the file system.
- [int32 OS_rename](#) (const char *old_filename, const char *new_filename)
Renames a file.
- [int32 OS_cp](#) (const char *src, const char *dest)
Copies a single file from src to dest.
- [int32 OS_mv](#) (const char *src, const char *dest)
Move a single file from src to dest.
- [int32 OS_FDGetInfo](#) ([uint32](#) fidedes, [OS_file_prop_t](#) *fd_prop)
Obtain information about an open file.
- [int32 OS_FileOpenCheck](#) (const char *Filename)
Checks to see if a file is open.
- [int32 OS_CloseAllFiles](#) (void)
Close all open files.
- [int32 OS_CloseFileByName](#) (const char *Filename)
Close a file by filename.

10.20.1 Detailed Description

10.20.2 Function Documentation

10.20.2.1 OS_chmod()

```
int32 OS_chmod (
    const char * path,
    uint32 access )
```

Changes the permissions of a file.

Parameters

in	<i>path</i>	File to change
in	<i>access</i>	Desired access mode - see OSAL File Access Option Defines

Note

Some file systems do not implement permissions

Returns

Execution status, see [OSAL Return Code Defines](#)

10.20.2.2 OS_close()

```
int32 OS_close (
    uint32 filedes )
```

Closes an open file handle.

This closes regular file handles and any other file-like resource, such as network streams or pipes.

Parameters

in	<i>filedes</i>	The handle ID to operate on
----	----------------	-----------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERROR	if file descriptor could not be closed
OS_ERR_INVALID_ID	if the file descriptor passed in is invalid

10.20.2.3 OS_CloseAllFiles()

```
int32 OS_CloseAllFiles (
    void )
```

Close all open files.

Closes All open files that were opened through the OSAL

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERROR	if one or more file close returned an error

10.20.2.4 OS_CloseFileByName()

```
int32 OS_CloseFileByName (
    const char * Filename )
```

Close a file by filename.

Allows a file to be closed by name. This will only work if the name passed in is the same name used to open the file.

Parameters

in	<i>Filename</i>	The file to close
----	-----------------	-------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_FS_ERR_PATH_INVALID	if the file is not found
OS_ERROR	if the file close returned an error

10.20.2.5 OS_cp()

```
int32 OS_cp (
    const char * src,
    const char * dest )
```

Copies a single file from src to dest.

Note

The behavior of this API on an open file is not defined at the OSAL level due to dependencies on the underlying OS which may or may not allow the related operation based on a variety of potential configurations. For portability, it is recommended that applications ensure the file is closed prior to removal.

Parameters

in	<i>src</i>	The source file to operate on
in	<i>dest</i>	The destination file

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERROR	if the file could not be accessed
OS_INVALID_POINTER	if src or dest are NULL
OS_FS_ERR_PATH_INVALID	if path cannot be parsed
OS_FS_ERR_PATH_TOO_LONG	if the paths given are too long to be stored locally
OS_FS_ERR_NAME_TOO_LONG	if the dest name is too long to be stored locally

10.20.2.6 OS_creat()

```
int32 OS_creat (
    const char * path,
    int32 access )
```

Creates a file specified by path.

Creates a file specified by const char *path, with read/write permissions by access. The file is also automatically opened by the create call.

Parameters

in	<i>path</i>	File name to create
in	<i>access</i>	Intended access mode - see OSAL File Access Option Defines

Note

Valid handle IDs are never negative. Failure of this call can be checked by testing if the result is less than 0.

Returns

A file handle ID or appropriate error code, see [OSAL Return Code Defines](#)

Return values

OS_INVALID_POINTER	if path is NULL
OS_FS_ERR_PATH_TOO_LONG	if path exceeds the maximum number of chars
OS_FS_ERR_PATH_INVALID	if path cannot be parsed
OS_FS_ERR_NAME_TOO_LONG	if the name of the file is too long
OS_ERROR	if permissions are unknown or OS call fails
OS_ERR_NO_FREE_IDS	if there are no free file descriptors left

10.20.2.7 OS_FDGetInfo()

```
int32 OS_FDGetInfo (
    uint32 filedес,
    OS_file_prop_t * fd_prop )
```

Obtain information about an open file.

Copies the information of the given file descriptor into a structure passed in

Parameters

in	<i>filedes</i>	The handle ID to operate on
out	<i>fd_prop</i>	Storage buffer for file information

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the file descriptor passed in is invalid

10.20.2.8 OS_FileOpenCheck()

```
int32 OS_FileOpenCheck (
    const char * Filename )
```

Checks to see if a file is open.

This function takes a filename and determines if the file is open. The function will return success if the file is open.

Parameters

in	<i>Filename</i>	The file to operate on
----	-----------------	------------------------

Returns

OS_SUCCESS if the file is open, or appropriate error code

Return values

OS_ERROR	if the file is not open
--------------------------	-------------------------

10.20.2.9 OS_lseek()

```
int32 OS_lseek (
    uint32 filedес,
    int32 offset,
    uint32 whence )
```

Seeks to the specified position of an open file.

Sets the read/write pointer to a specific offset in a specific file.

Parameters

in	<i>filedes</i>	The handle ID to operate on
in	<i>offset</i>	The file offset to seek to
in	<i>whence</i>	The reference point for offset, see OSAL Reference Point For Seek Offset Defines

Returns

Byte offset from the beginning of the file or appropriate error code, see [OSAL Return Code Defines](#)

Return values

OS_ERR_INVALID_ID	if the file descriptor passed in is invalid
OS_ERROR	if OS call failed

10.20.2.10 OS_mv()

```
int32 OS_mv (
    const char * src,
    const char * dest )
```

Move a single file from src to dest.

This first attempts to rename the file, which is faster if the source and destination reside on the same file system.

If this fails, it falls back to copying the file and removing the original.

Note

The behavior of this API on an open file is not defined at the OSAL level due to dependencies on the underlying OS which may or may not allow the related operation based on a variety of potential configurations. For portability, it is recommended that applications ensure the file is closed prior to removal.

Parameters

in	<i>src</i>	The source file to operate on
in	<i>dest</i>	The destination file

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERROR	if the file could not be renamed.
OS_INVALID_POINTER	if src or dest are NULL
OS_FS_ERR_PATH_INVALID	if path cannot be parsed
OS_FS_ERR_PATH_TOO_LONG	if the paths given are too long to be stored locally
OS_FS_ERR_NAME_TOO_LONG	if the dest name is too long to be stored locally

10.20.2.11 OS_open()

```
int32 OS_open (
    const char * path,
    int32 access,
    uint32 mode )
```


Opens a file.

Opens a file.

Parameters

in	<i>path</i>	File name to create
in	<i>access</i>	Intended access mode - see OSAL File Access Option Defines
in	<i>mode</i>	The file permissions. This parameter is passed through to the native open call, but will be ignored. The file mode (or permissions) are ignored by the POSIX open call when the O_CREAT access flag is not passed in.

Note

Valid handle IDs are never negative. Failure of this call can be checked by testing if the result is less than 0.

Returns

A file handle ID or appropriate error code, see [OSAL Return Code Defines](#)

Return values

OS_INVALID_POINTER	if path is NULL
OS_FS_ERR_PATH_TOO_LONG	if path exceeds the maximum number of chars
OS_FS_ERR_PATH_INVALID	if path cannot be parsed
OS_FS_ERR_NAME_TOO_LONG	if the name of the file is too long
OS_ERROR	if permissions are unknown or OS call fails
OS_ERR_NO_FREE_IDS	if there are no free file descriptors left

10.20.2.12 OS_read()

```
int32 OS_read (
    uint32 filedes,
    void * buffer,
    uint32 nbytes )
```

Read from a file handle.

Reads up to nbytes from a file, and puts them into buffer.

Parameters

in	<i>filedes</i>	The handle ID to operate on
out	<i>buffer</i>	Storage location for file data
in	<i>nbytes</i>	Maximum number of bytes to read

Note

All OSAL error codes are negative int32 values. Failure of this call can be checked by testing if the result is less than 0.

Returns

A non-negative byte count or appropriate error code, see [OSAL Return Code Defines](#)

Return values

OS_INVALID_POINTER	if buffer is a null pointer
OS_ERROR	if OS call failed
OS_ERR_INVALID_ID	if the file descriptor passed in is invalid

10.20.2.13 OS_remove()

```
int32 OS_remove (
    const char * path )
```

Removes a file from the file system.

Removes a given filename from the drive

Note

The behavior of this API on an open file is not defined at the OSAL level due to dependencies on the underlying OS which may or may not allow the related operation based on a variety of potential configurations. For portability, it is recommended that applications ensure the file is closed prior to removal.

Parameters

in	<i>path</i>	The file to operate on
----	-------------	------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERROR	if there is no device or the driver returns error
OS_INVALID_POINTER	if path is NULL
OS_FS_ERR_PATH_TOO_LONG	if path is too long to be stored locally
OS_FS_ERR_PATH_INVALID	if path cannot be parsed
OS_FS_ERR_NAME_TOO_LONG	if the name of the file to remove is too long

10.20.2.14 OS_rename()

```
int32 OS_rename (
    const char * old_filename,
    const char * new_filename )
```

Renames a file.

Changes the name of a file, where the source and destination reside on the same file system.

Note

The behavior of this API on an open file is not defined at the OSAL level due to dependencies on the underlying OS which may or may not allow the related operation based on a variety of potential configurations. For portability, it is recommended that applications ensure the file is closed prior to removal.

Parameters

in	<i>old_filename</i>	The original filename
in	<i>new_filename</i>	The desired filename

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERROR	if the file could not be opened or renamed.
OS_INVALID_POINTER	if old or new are NULL
OS_FS_ERR_PATH_INVALID	if path cannot be parsed
OS_FS_ERR_PATH_TOO_LONG	if the paths given are too long to be stored locally
OS_FS_ERR_NAME_TOO_LONG	if the new name is too long to be stored locally

10.20.2.15 OS_stat()

```
int32 OS_stat (
    const char * path,
    os_fstat_t * filestats )
```

Obtain information about a file or directory.

Returns information about a file or directory in a [os_fstat_t](#) structure

Parameters

in	<i>path</i>	The file to operate on
out	<i>filestats</i>	Buffer to store file information

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if path or filestats is NULL
OS_FS_ERR_PATH_TOO_LONG	if the path is too long to be stored locally
OS_FS_ERR_NAME_TOO_LONG	if the name of the file is too long to be stored
OS_FS_ERR_PATH_INVALID	if path cannot be parsed
OS_ERROR	if the OS call failed

10.20.2.16 OS_TimedRead()

```
int32 OS_TimedRead (
    uint32 filedес,
    void * buffer,
    uint32 nbytes,
    int32 timeout )
```

File/Stream input read with a timeout.

This implements a time-limited read and is primarily intended for use with sockets but may also work with any other stream-like resource that the underlying OS supports.

If data is immediately available on the file/socket, this will return that data along with the actual number of bytes that were immediately available. It will not block.

If no data is immediately available, this will wait up to the given timeout for data to appear. If no data appears within the timeout period, then this returns an error code (not zero).

In all cases this will return successfully as soon as at least 1 byte of actual data is available. It will not attempt to read the entire input buffer.

If an EOF condition occurs prior to timeout, this function returns zero.

Parameters

in	<i>filedes</i>	The handle ID to operate on
in	<i>buffer</i>	Source location for file data
in	<i>nbytes</i>	Maximum number of bytes to read
in	<i>timeout</i>	Maximum time to wait, in milliseconds (OS_PEND = forever)

Returns

Byte count on success, zero for timeout, or appropriate error code, see [OSAL Return Code Defines](#)

10.20.2.17 OS_TimedWrite()

```
int32 OS_TimedWrite (
    uint32 filedes,
    const void * buffer,
    uint32 nbytes,
    int32 timeout )
```

File/Stream output write with a timeout.

This implements a time-limited write and is primarily intended for use with sockets but may also work with any other stream-like resource that the underlying OS supports.

If output buffer space is immediately available on the file/socket, this will place data into the buffer and return the actual number of bytes that were queued for output. It will not block.

If no output buffer space is immediately available, this will wait up to the given timeout for space to become available. If no space becomes available within the timeout period, then this returns an error code (not zero).

In all cases this will return successfully as soon as at least 1 byte of actual data is output. It will *not* attempt to write the entire output buffer.

If an EOF condition occurs prior to timeout, this function returns zero.

Parameters

in	<i>filedes</i>	The handle ID to operate on
in	<i>buffer</i>	Source location for file data
in	<i>nbytes</i>	Maximum number of bytes to read
in	<i>timeout</i>	Maximum time to wait, in milliseconds (OS_PEND = forever)

Returns

Byte count on success, zero for timeout, or appropriate error code, see [OSAL Return Code Defines](#)

10.20.2.18 OS_write()

```
int32 OS_write (
    uint32 filedes,
    const void * buffer,
    uint32 nbytes )
```

Write to a file handle.

Writes to a file. copies up to a maximum of nbytes of buffer to the file described in filedes

Parameters

in	<i>filedes</i>	The handle ID to operate on
in	<i>buffer</i>	Source location for file data
in	<i>nbytes</i>	Maximum number of bytes to read

Note

All OSAL error codes are negative int32 values. Failure of this call can be checked by testing if the result is less than 0.

Returns

A non-negative byte count or appropriate error code, see [OSAL Return Code Defines](#)

Return values

OS_INVALID_POINTER	if buffer is NULL
OS_ERROR	if OS call failed
OS_ERR_INVALID_ID	if the file descriptor passed in is invalid

10.21 OSAL Directory APIs

Functions

- `os_dirp_t OS_opendir` (const char *path)
Opens a directory for searching.
- `int32 OS_closedir` (os_dirp_t directory)
- `void OS_rewinddir` (os_dirp_t directory)
- `os_dirent_t * OS_readdir` (os_dirp_t directory)
- `int32 OS_DirectoryOpen` (uint32 *dir_id, const char *path)
Opens a directory.
- `int32 OS_DirectoryClose` (uint32 dir_id)
Closes an open directory.
- `int32 OS_DirectoryRewind` (uint32 dir_id)
Rewinds an open directory.
- `int32 OS_DirectoryRead` (uint32 dir_id, os_dirent_t *dirent)
Reads the next name in the directory.
- `int32 OS_mkdir` (const char *path, uint32 access)
Makes a new directory.
- `int32 OS_rmdir` (const char *path)
Removes a directory from the file system.

10.21.1 Detailed Description

10.21.2 Function Documentation

10.21.2.1 OS_closedir()

```
int32 OS_closedir (
    os_dirp_t directory )
```

10.21.2.2 OS_DirectoryClose()

```
int32 OS_DirectoryClose (
    uint32 dir_id )
```

Closes an open directory.

The directory referred to by dir_id will be closed

Parameters

in	<i>dir↔ _id</i>	The handle ID of the directory
----	---------------------	--------------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

10.21.2.3 OS_DirectoryOpen()

```
int32 OS_DirectoryOpen (
    uint32 * dir_id,
    const char * path )
```

Opens a directory.

Prepares for reading the files within a directory

Parameters

out	<i>dir↔ _id</i>	The non-zero handle ID of the directory
in	<i>path</i>	The directory to open

Returns

Execution status, see [OSAL Return Code Defines](#)

10.21.2.4 OS_DirectoryRead()

```
int32 OS_DirectoryRead (
    uint32 dir_id,
    os_dirent_t * dirent )
```

Reads the next name in the directory.

Obtains directory entry data for the next file from an open directory

Parameters

in	<i>dir↔ _id</i>	The handle ID of the directory
out	<i>dirent</i>	Buffer to store directory entry information

Returns

Execution status, see [OSAL Return Code Defines](#)

10.21.2.5 OS_DirectoryRewind()

```
int32 OS_DirectoryRewind (
    uint32 dir_id )
```

Rewinds an open directory.

Resets a directory read handle back to the first file.

Parameters

in	<i>dir_id</i>	The handle ID of the directory
----	---------------	--------------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

10.21.2.6 OS_mkdir()

```
int32 OS_mkdir (
    const char * path,
    uint32 access )
```

Makes a new directory.

Makes a directory specified by path.

Parameters

in	<i>path</i>	The new directory name
in	<i>access</i>	The permissions for the directory (reserved for future use)

Note

Current implementations do not utilize the "access" parameter. Applications should still pass the intended value ([OS_READ_WRITE](#) or [OS_READ_ONLY](#)) to be compatible with future implementations.

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

<i>OS_SUCCESS</i>	Successful execution.
<i>OS_INVALID_POINTER</i>	if path is NULL
<i>OS_FS_ERR_PATH_TOO_LONG</i>	if the path is too long to be stored locally
<i>OS_FS_ERR_PATH_INVALID</i>	if path cannot be parsed
<i>OS_ERROR</i>	if the OS call fails

10.21.2.7 OS_opendir()

```
os_dirp_t OS_opendir (
    const char * path )
```

Opens a directory for searching.

Deprecated Replaced by [*OS_DirectoryOpen\(\)*](#)

10.21.2.8 OS_readdir()

```
os_dirent_t* OS_readdir (
    os_dirp_t directory )
```

10.21.2.9 OS_rewinddir()

```
void OS_rewinddir (
    os_dirp_t directory )
```

10.21.2.10 OS_rmdir()

```
int32 OS_rmdir (
    const char * path )
```

Removes a directory from the file system.

Removes a directory from the structure. The directory must be empty prior to this operation.

Parameters

in	<i>path</i>	The directory to remove
----	-------------	-------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if path is NULL
OS_FS_ERR_PATH_INVALID	if path cannot be parsed
OS_FS_ERR_PATH_TOO_LONG	
OS_ERROR	if the directory remove operation failed

10.22 OSAL File System Level APIs

Functions

- [int32 OS_FileSysAddFixedMap](#) ([uint32](#) *fileSYS_id, const char *phys_path, const char *virt_path)
Create a fixed mapping between an existing directory and a virtual OSAL mount point.
- [int32 OS_mkfs](#) (char *address, const char *devname, const char *volname, [uint32](#) blocksize, [uint32](#) numblocks)
Makes a file system on the target.
- [int32 OS_mount](#) (const char *devname, const char *mountpoint)
Mounts a file system.
- [int32 OS_initfs](#) (char *address, const char *devname, const char *volname, [uint32](#) blocksize, [uint32](#) numblocks)
Initializes an existing file system.
- [int32 OS_rmfs](#) (const char *devname)
Removes a file system.
- [int32 OS_unmount](#) (const char *mountpoint)
Unmounts a mounted file system.
- [int32 OS_fsBlocksFree](#) (const char *name)
Obtain number of blocks free.
- [int32 OS_fsBytesFree](#) (const char *name, [uint64](#) *bytes_free)
Obtains the number of free bytes in a volume.
- [int32 OS_chkfs](#) (const char *name, bool repair)
Checks the health of a file system and repairs it if necessary.
- [int32 OS_FS_GetPhysDriveName](#) (char *PhysDriveName, const char *MountPoint)
Obtains the physical drive name associated with a mount point.
- [int32 OS_TranslatePath](#) (const char *VirtualPath, char *LocalPath)
Translates a OSAL Virtual file system path to a host Local path.
- [int32 OS_GetFsInfo](#) ([os_fsinfo_t](#) *fileSYS_info)
Returns information about the file system.

10.22.1 Detailed Description

10.22.2 Function Documentation

10.22.2.1 OS_chkfs()

```
int32 OS_chkfs (
    const char * name,
    bool repair )
```

Checks the health of a file system and repairs it if necessary.

Checks the drives for inconsistencies and optionally also repairs it

Note

not all operating systems implement this function

Parameters

in	<i>name</i>	The device/path to operate on
in	<i>repair</i>	Whether to also repair inconsistencies

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	Name is NULL
OS_ERR_NOT_IMPLEMENTED	Not implemented.
OS_ERROR	Failed execution.

10.22.2.2 OS_FileSysAddFixedMap()

```
int32 OS_FileSysAddFixedMap (
    uint32 * filesys_id,
    const char * phys_path,
    const char * virt_path )
```

Create a fixed mapping between an existing directory and a virtual OSAL mount point.

This mimics the behavior of a "FS_BASED" entry in the VolumeTable but is registered at runtime. It is intended to be called by the PSP/BSP prior to starting the application.

Parameters

out	<i>filesys_id</i>	A non-zero OSAL ID reflecting the file system
in	<i>phys_path</i>	The native system directory (an existing mount point)
in	<i>virt_path</i>	The virtual mount point of this filesystem

Returns

Execution status, see [OSAL Return Code Defines](#)

10.22.2.3 OS_FS_GetPhysDriveName()

```
int32 OS_FS_GetPhysDriveName (
    char * PhysDriveName,
    const char * MountPoint )
```

Obtains the physical drive name associated with a mount point.

Returns the name of the physical volume associated with the drive, when given the OSAL mount point of the drive

Parameters

out	<i>PhysDriveName</i>	Buffer to store physical drive name
in	<i>MountPoint</i>	OSAL mount point

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if either parameter is NULL
OS_ERROR	if the mountpoint could not be found

10.22.2.4 OS_fsBlocksFree()

```
int32 OS_fsBlocksFree (
    const char * name )
```

Obtain number of blocks free.

Returns the number of free blocks in a volume

Parameters

in	<i>name</i>	The device/path to operate on
----	-------------	-------------------------------

Returns

Block count or appropriate error code, see [OSAL Return Code Defines](#)

Return values

OS_INVALID_POINTER	if name is NULL
OS_FS_ERR_PATH_TOO_LONG	if the name is too long
OS_ERROR	if the OS call failed

10.22.2.5 OS_fsBytesFree()

```
int32 OS_fsBytesFree (
    const char * name,
    uint64 * bytes_free )
```

Obtains the number of free bytes in a volume.

Returns the number of free bytes in a volume

Note

uses a 64 bit data type to support filesystems that are greater than 4 Gigabytes

Parameters

in	<i>name</i>	The device/path to operate on
out	<i>bytes_free</i>	The number of free bytes

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if name is NULL
OS_FS_ERR_PATH_TOO_LONG	if the name is too long
OS_ERROR	if the OS call failed

10.22.2.6 OS_GetFsInfo()

```
int32 OS_GetFsInfo (
    os_fsinfo_t * filesystem_info )
```

Returns information about the file system.

Returns information about the file system in an [os_fsinfo_t](#). This includes the number of open files and file systems

Parameters

out	<i>filesystem_info</i>	Buffer to store filesystem information
-----	------------------------	--

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if fileys_info is NULL

10.22.2.7 OS_initfs()

```
int32 OS_initfs (
    char * address,
    const char * devname,
    const char * volname,
    uint32 blocksize,
    uint32 numblocks )
```

Initializes an existing file system.

Initializes a file system on the target.

Note

The "volname" parameter of RAM disks should always begin with the string "RAM", e.g. "RAMDISK" or "RAM0", "RAM1", etc if multiple devices are created. The underlying implementation uses this to select the correct filesystem type/format, and this may also be used to differentiate between RAM disks and real physical disks.

Parameters

in	<i>address</i>	The address at which to start the new disk. If address == 0, then space will be allocated by the OS
in	<i>devname</i>	The underlying kernel device to use, if applicable.
in	<i>volname</i>	The name of the volume (see note)
in	<i>blocksize</i>	The size of a single block on the drive
in	<i>numblocks</i>	The number of blocks to allocate for the drive

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if devname or volname are NULL
OS_FS_ERR_PATH_TOO_LONG	if the name is too long
OS_FS_ERR_DEVICE_NOT_FREE	if the volume table is full
OS_FS_ERR_DRIVE_NOT_CREATED	on error

10.22.2.8 OS_mkfs()

```
int32 OS_mkfs (
    char * address,
    const char * devname,
    const char * volname,
    uint32 blocksize,
    uint32 numblocks )
```

Makes a file system on the target.

Makes a file system on the target. Highly dependent on underlying OS and dependent on OS volume table definition.

Note

The "volname" parameter of RAM disks should always begin with the string "RAM", e.g. "RAMDISK" or "RAM0", "RAM1", etc if multiple devices are created. The underlying implementation uses this to select the correct filesystem type/format, and this may also be used to differentiate between RAM disks and real physical disks.

Parameters

in	<i>address</i>	The address at which to start the new disk. If address == 0 space will be allocated by the OS.
in	<i>devname</i>	The underlying kernel device to use, if applicable.
in	<i>volname</i>	The name of the volume (see note)
in	<i>blocksize</i>	The size of a single block on the drive
in	<i>numblocks</i>	The number of blocks to allocate for the drive

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

<i>OS_INVALID_POINTER</i>	if devname is NULL
<i>OS_FS_ERR_DRIVE_NOT_CREATED</i>	if the OS calls to create the the drive failed
<i>OS_FS_ERR_DEVICE_NOT_FREE</i>	if the volume table is full
<i>OS_SUCCESS</i>	on creating the disk

10.22.2.9 OS_mount()

```
int32 OS_mount (
    const char * devname,
    const char * mountpoint )
```

Mounts a file system.

Mounts a file system / block device at the given mount point.

Parameters

in	<i>devname</i>	The name of the drive to mount. devname is the same from OS_mkfs
in	<i>mountpoint</i>	The name to call this disk from now on

Returns

Execution status, see [OSAL Return Code Defines](#)

10.22.2.10 OS_rmfs()

```
int32 OS_rmfs (
    const char * devname )
```

Removes a file system.

This function will remove or un-map the target file system. Note that this is not the same as un-mounting the file system.

Parameters

in	<i>devname</i>	The name of the "generic" drive
----	----------------	---------------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if devname is NULL
OS_ERROR	is the drive specified cannot be located

10.22.2.11 OS_TranslatePath()

```
int32 OS_TranslatePath (
    const char * VirtualPath,
    char * LocalPath )
```

Translates a OSAL Virtual file system path to a host Local path.

Translates a virtual path to an actual system path name

Parameters

in	<i>VirtualPath</i>	OSAL virtual path name
out	<i>LocalPath</i>	Buffer to store native/translated path name

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if either parameter is NULL

10.22.2.12 OS_unmount()

```
int32 OS_unmount (
    const char * mountpoint )
```

Unmounts a mounted file system.

This function will unmount a drive from the file system and make all open file descriptors useless.

Note

Any open file descriptors referencing this file system should be closed prior to unmounting a drive

Parameters

in	<i>mountpoint</i>	The mount point to remove from OS_mount
----	-------------------	---

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if name is NULL
OS_FS_ERR_PATH_TOO_LONG	if the absolute path given is too long
OS_ERROR	if the OS calls failed

10.23 OSAL Shell APIs

Functions

- [int32 OS_ShellOutputToFile](#) (const char *Cmd, [uint32](#) filedes)
Executes the command and sends output to a file.

10.23.1 Detailed Description

10.23.2 Function Documentation

10.23.2.1 OS_ShellOutputToFile()

```
int32 OS_ShellOutputToFile (
    const char * Cmd,
    uint32 filedes )
```

Executes the command and sends output to a file.

Takes a shell command in and writes the output of that command to the specified file The output file must be opened previously with write access (OS_WRITE_ONLY or OS_READ_WRITE).

Parameters

in	<i>Cmd</i>	Command to pass to shell
in	<i>filedes</i>	File to send output to.

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERROR	if the command was not executed properly
OS_ERR_INVALID_ID	if the file descriptor passed in is invalid

10.24 OSAL Dynamic Loader and Symbol APIs

Functions

- [int32 OS_SymbolLookup](#) ([cpuaddr](#) *symbol_address, const char *symbol_name)
Find the Address of a Symbol.
- [int32 OS_SymbolTableDump](#) (const char *filename, [uint32](#) size_limit)
Dumps the system symbol table to a file.
- [int32 OS_ModuleLoad](#) ([uint32](#) *module_id, const char *module_name, const char *filename)
Loads an object file.
- [int32 OS_ModuleUnload](#) ([uint32](#) module_id)
Unloads the module file.
- [int32 OS_ModuleInfo](#) ([uint32](#) module_id, [OS_module_prop_t](#) *module_info)
Obtain information about a module.

10.24.1 Detailed Description

10.24.2 Function Documentation

10.24.2.1 OS_ModuleInfo()

```
int32 OS_ModuleInfo (
    uint32 module_id,
    OS_module_prop_t * module_info )
```

Obtain information about a module.

Returns information about the loadable module

Parameters

in	<i>module_id</i>	OSAL ID of the previously the loaded module
out	<i>module_info</i>	Buffer to store module information

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the module id invalid
OS_INVALID_POINTER	if the pointer to the ModuleInfo structure is invalid

10.24.2.2 OS_ModuleLoad()

```
int32 OS_ModuleLoad (
    uint32 * module_id,
    const char * module_name,
    const char * filename )
```

Loads an object file.

Loads an object file into the running operating system

Parameters

out	<i>module_id</i>	Non-zero OSAL ID corresponding to the loaded module
in	<i>module_name</i>	Name of module
in	<i>filename</i>	File containing the object code to load

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERROR	if the module cannot be loaded
OS_INVALID_POINTER	if one of the parameters is NULL
OS_ERR_NO_FREE_IDS	if the module table is full
OS_ERR_NAME_TAKEN	if the name is in use

10.24.2.3 OS_ModuleUnload()

```
int32 OS_ModuleUnload (
    uint32 module_id )
```

Unloads the module file.

Unloads the module file from the running operating system

Parameters

in	<i>module_id</i>	OSAL ID of the previously the loaded module
----	------------------	---

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERROR	if the module is invalid or cannot be unloaded

10.24.2.4 OS_SymbolLookup()

```
int32 OS_SymbolLookup (
    cpuaddr * symbol_address,
    const char * symbol_name )
```

Find the Address of a Symbol.

This calls to the OS dynamic symbol lookup implementation, and/or checks a static symbol table for a matching symbol name.

The static table is intended to support embedded targets that do not have module loading capability or have it disabled.

Parameters

out	<i>symbol_address</i>	Set to the address of the symbol
in	<i>symbol_name</i>	Name of the symbol to look up

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERROR	if the symbol could not be found
OS_INVALID_POINTER	if one of the pointers passed in are NULL

10.24.2.5 OS_SymbolTableDump()

```
int32 OS_SymbolTableDump (
    const char * filename,
    uint32 size_limit )
```

Dumps the system symbol table to a file.

Dumps the system symbol table to the specified filename

Parameters

in	<i>filename</i>	File to write to
in	<i>size_limit</i>	Maximum number of bytes to write

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_NOT_IMPLEMENTED	Not implemented.
OS_ERROR	if the symbol table could not be read or dumped

10.25 OSAL Socket Address APIs

Functions

- `int32 OS_SocketAddrInit (OS_SockAddr_t *Addr, OS_SocketDomain_t Domain)`
Initialize a socket address structure to hold an address of the given family.
- `int32 OS_SocketAddrToString (char *buffer, uint32 buflen, const OS_SockAddr_t *Addr)`
Get a string representation of a network host address.
- `int32 OS_SocketAddrFromString (OS_SockAddr_t *Addr, const char *string)`
Set a network host address from a string representation.
- `int32 OS_SocketAddrGetPort (uint16 *PortNum, const OS_SockAddr_t *Addr)`
Get the port number of a network address.
- `int32 OS_SocketAddrSetPort (OS_SockAddr_t *Addr, uint16 PortNum)`
Set the port number of a network address.

10.25.1 Detailed Description

These functions provide a means to manipulate network addresses in a manner that is (mostly) agnostic to the actual network address type.

Every network address should be representable as a string (i.e. dotted decimal IP, etc). This can serve as a the "common denominator" to all address types.

10.25.2 Function Documentation

10.25.2.1 OS_SocketAddrFromString()

```
int32 OS_SocketAddrFromString (
    OS_SockAddr_t * Addr,
    const char * string )
```

Set a network host address from a string representation.

The specific format of the output string depends on the address family.

The address structure should have been previously initialized using `OS_SocketAddrInit()` to set the address family type.

Note

For IPv4, this would typically be the dotted-decimal format (X.X.X.X). It is up to the discretion of the underlying implementation whether to accept hostnames, as this depends on the availability of DNS services. Since many embedded deployments do not have name services, this should not be relied upon.

Parameters

out	<i>Addr</i>	The address buffer to initialize
in	<i>string</i>	The string to initialize the address from.

Returns

Execution status, see [OSAL Return Code Defines](#)

10.25.2.2 OS_SocketAddrGetPort()

```
int32 OS_SocketAddrGetPort (
    uint16 * PortNum,
    const OS_SockAddr_t * Addr )
```

Get the port number of a network address.

For network protocols that have the concept of a port number (such as TCP/IP and UDP/IP) this function gets the port number from the address structure.

Parameters

out	<i>PortNum</i>	Buffer to store the port number
in	<i>Addr</i>	The network address buffer

Returns

Execution status, see [OSAL Return Code Defines](#)

10.25.2.3 OS_SocketAddrInit()

```
int32 OS_SocketAddrInit (
    OS_SockAddr_t * Addr,
    OS_SocketDomain_t Domain )
```

Initialize a socket address structure to hold an address of the given family.

The address is set to a suitable default value for the family.

Parameters

out	<i>Addr</i>	The address buffer to initialize
in	<i>Domain</i>	The address family

Returns

Execution status, see [OSAL Return Code Defines](#)

10.25.2.4 OS_SocketAddrSetPort()

```
int32 OS_SocketAddrSetPort (
    OS_SockAddr_t * Addr,
    uint16 PortNum )
```

Set the port number of a network address.

For network protocols that have the concept of a port number (such as TCP/IP and UDP/IP) this function sets the port number from the address structure.

Parameters

in	<i>PortNum</i>	The port number to set
out	<i>Addr</i>	The network address buffer

Returns

Execution status, see [OSAL Return Code Defines](#)

10.25.2.5 OS_SocketAddrToString()

```
int32 OS_SocketAddrToString (
    char * buffer,
    uint32 buflen,
    const OS_SockAddr_t * Addr )
```

Get a string representation of a network host address.

The specific format of the output string depends on the address family.

This string should be suitable to pass back into [OS_SocketAddrFromString\(\)](#) which should recreate the same network address, and it should also be meaningful to a user of printed or logged as a C string.

Note

For IPv4, this would typically be the dotted-decimal format (X.X.X.X).

Parameters

out	<i>buffer</i>	Buffer to hold the output string
in	<i>buflen</i>	Maximum length of the output string
in	<i>Addr</i>	The network address buffer to convert

Returns

Execution status, see [OSAL Return Code Defines](#)

10.26 OSAL Socket Management APIs

Functions

- `int32 OS_SocketOpen (uint32 *sock_id, OS_SocketDomain_t Domain, OS_SocketType_t Type)`
Opens a socket.
- `int32 OS_SocketBind (uint32 sock_id, const OS_SockAddr_t *Addr)`
Binds a socket to a given local address.
- `int32 OS_SocketConnect (uint32 sock_id, const OS_SockAddr_t *Addr, int32 timeout)`
Connects a socket to a given remote address.
- `int32 OS_SocketAccept (uint32 sock_id, uint32 *connsock_id, OS_SockAddr_t *Addr, int32 timeout)`
Waits for and accept the next incoming connection on the given socket.
- `int32 OS_SocketRecvFrom (uint32 sock_id, void *buffer, uint32 buflen, OS_SockAddr_t *RemoteAddr, int32 timeout)`
Reads data from a message-oriented (datagram) socket.
- `int32 OS_SocketSendTo (uint32 sock_id, const void *buffer, uint32 buflen, const OS_SockAddr_t *RemoteAddr)`
Sends data to a message-oriented (datagram) socket.
- `int32 OS_SocketGetIdByName (uint32 *sock_id, const char *sock_name)`
Gets an OSAL ID from a given name.
- `int32 OS_SocketGetInfo (uint32 sock_id, OS_socket_prop_t *sock_prop)`
Gets information about an OSAL Socket ID.
- `int32 OS_NetworkGetID (void)`
Gets the network ID of the local machine.
- `int32 OS_NetworkGetHostName (char *host_name, uint32 name_len)`
Gets the local machine network host name.

10.26.1 Detailed Description

These functions are loosely related to the BSD Sockets API but made to be more consistent with other OSAL API functions. That is, they operate on OSAL IDs (32-bit opaque number values) and return an OSAL error code.

OSAL Socket IDs are very closely related to File IDs and share the same ID number space. Additionally, the file `OS_read()` / `OS_write()` / `OS_close()` calls also work on sockets.

Note that all of functions may return `OS_ERR_NOT_IMPLEMENTED` if network support is not configured at compile time.

10.26.2 Function Documentation

10.26.2.1 OS_NetworkGetHostName()

```
int32 OS_NetworkGetHostName (
    char * host_name,
    uint32 name_len )
```

Gets the local machine network host name.

If configured in the underlying network stack, this function retrieves the local hostname of the system.

Parameters

out	<i>host_name</i>	Buffer to hold name information
in	<i>name_len</i>	Maximum length of host name buffer

Returns

Execution status, see [OSAL Return Code Defines](#)

10.26.2.2 OS_NetworkGetID()

```
int32 OS_NetworkGetID (
    void )
```

Gets the network ID of the local machine.

The ID is an implementation-defined value and may not be consistent in meaning across different platform types.

Note

This API may be removed in a future version of OSAL due to inconsistencies between platforms.

Returns

The ID or fixed value of -1 if the host id could not be found. Note it is not possible to differentiate between error codes and valid network IDs here. It is assumed, however, that -1 is never a valid ID.

10.26.2.3 OS_SocketAccept()

```
int32 OS_SocketAccept (
    uint32 sock_id,
    uint32 * connsock_id,
    OS_SockAddr_t * Addr,
    int32 timeout )
```

Waits for and accept the next incoming connection on the given socket.

This is used for sockets operating in a "server" role. The socket must be a stream type (connection-oriented) and previously bound to a local address using [OS_SocketBind\(\)](#). This will block the caller up to the given timeout or until an incoming connection request occurs, whichever happens first.

The new stream connection is then returned to the caller and the original server socket ID can be reused for the next connection.

Parameters

in	<i>sock_id</i>	The server socket ID, previously bound using OS_SocketBind()
out	<i>connsock↔ _id</i>	The connection socket, a new ID that can be read/written
in	<i>Addr</i>	The remote address of the incoming connection
in	<i>timeout</i>	The maximum amount of time to wait, or OS_PEND to wait forever

Returns

Execution status, see [OSAL Return Code Defines](#)

10.26.2.4 OS_SocketBind()

```
int32 OS_SocketBind (
    uint32 sock_id,
    const OS_SockAddr_t * Addr )
```

Binds a socket to a given local address.

The specified socket will be bound to the local address and port, if available.

If the socket is connectionless, then it only binds to the local address.

If the socket is connection-oriented (stream), then this will also put the socket into a listening state for incoming connections at the local address.

Parameters

in	<i>sock↔ _id</i>	The socket ID
in	<i>Addr</i>	The local address to bind to

Returns

Execution status, see [OSAL Return Code Defines](#)

10.26.2.5 OS_SocketConnect()

```
int32 OS_SocketConnect (
    uint32 sock_id,
    const OS_SockAddr_t * Addr,
    int32 timeout )
```

Connects a socket to a given remote address.

The socket will be connected to the remote address and port, if available. This only applies to stream-oriented sockets. Calling this on a datagram socket will return an error (these sockets should use `SendTo/RecvFrom`).

Parameters

in	<i>sock_id</i>	The socket ID
in	<i>Addr</i>	The remote address to connect to
in	<i>timeout</i>	The maximum amount of time to wait, or OS_PEND to wait forever

Returns

Execution status, see [OSAL Return Code Defines](#)

10.26.2.6 OS_SocketGetIdByName()

```
int32 OS_SocketGetIdByName (
    uint32 * sock_id,
    const char * sock_name )
```

Gets an OSAL ID from a given name.

Note

OSAL Sockets use generated names according to the address and type.

See also

[OS_SocketGetInfo\(\)](#)

Parameters

out	<i>sock_id</i>	Buffer to hold result
in	<i>sock_name</i>	Name of socket to find

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	is id or name are NULL pointers
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_NAME_NOT_FOUND	if the name was not found in the table

10.26.2.7 OS_SocketGetInfo()

```
int32 OS_SocketGetInfo (
    uint32 sock_id,
    OS_socket_prop_t * sock_prop )
```

Gets information about an OSAL Socket ID.

OSAL Sockets use generated names according to the address and type. This allows applications to find the name of a given socket.

Parameters

in	<i>sock_id</i>	The socket ID
out	<i>sock_prop</i>	Buffer to hold socket information

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the id passed in is not a valid semaphore
OS_INVALID_POINTER	if the count_prop pointer is null

10.26.2.8 OS_SocketOpen()

```
int32 OS_SocketOpen (
    uint32 * sock_id,
    OS_SocketDomain_t Domain,
    OS_SocketType_t Type )
```

Opens a socket.

A new, unconnected and unbound socket is allocated of the given domain and type.

Parameters

out	<i>sock_id</i>	Buffer to hold the non-zero OSAL ID
in	<i>Domain</i>	The domain / address family of the socket (INET or INET6, etc)
in	<i>Type</i>	The type of the socket (STREAM or DATAGRAM)

Returns

Execution status, see [OSAL Return Code Defines](#)

10.26.2.9 OS_SocketRecvFrom()

```
int32 OS_SocketRecvFrom (
    uint32 sock_id,
    void * buffer,
    uint32 buflen,
    OS_SockAddr_t * RemoteAddr,
    int32 timeout )
```

Reads data from a message-oriented (datagram) socket.

If a message is already available on the socket, this should immediately return that data without blocking. Otherwise, it may block up to the given timeout.

Parameters

in	<i>sock_id</i>	The socket ID, previously bound using OS_SocketBind()
out	<i>buffer</i>	Pointer to message data receive buffer
in	<i>buflen</i>	The maximum length of the message data to receive
out	<i>RemoteAddr</i>	Buffer to store the remote network address (may be NULL)
in	<i>timeout</i>	The maximum amount of time to wait, or OS_PEND to wait forever

Returns

Count of actual bytes received or error status, see [OSAL Return Code Defines](#)

10.26.2.10 OS_SocketSendTo()

```
int32 OS_SocketSendTo (
    uint32 sock_id,
    const void * buffer,
    uint32 buflen,
    const OS_SockAddr_t * RemoteAddr )
```

Sends data to a message-oriented (datagram) socket.

This sends data in a non-blocking mode. If the socket is not currently able to queue the message, such as if its outbound buffer is full, then this returns an error code.

Parameters

in	<i>sock_id</i>	The socket ID, which must be of the datagram type
in	<i>buffer</i>	Pointer to message data to send
in	<i>buflen</i>	The length of the message data to send
in	<i>RemoteAddr</i>	Buffer containing the remote network address to send to

Returns

Count of actual bytes sent or error status, see [OSAL Return Code Defines](#)

10.27 OSAL Timer APIs

Functions

- `int32 OS_TimeBaseCreate (uint32 *timebase_id, const char *timebase_name, OS_TimerSync_t external_sync)`
Create an abstract Time Base resource.
- `int32 OS_TimeBaseSet (uint32 timebase_id, uint32 start_time, uint32 interval_time)`
Sets the tick period for simulated time base objects.
- `int32 OS_TimeBaseDelete (uint32 timebase_id)`
Deletes a time base object.
- `int32 OS_TimeBaseGetIdByName (uint32 *timebase_id, const char *timebase_name)`
Find the ID of an existing time base resource.
- `int32 OS_TimeBaseGetInfo (uint32 timebase_id, OS_timebase_prop_t *timebase_prop)`
Obtain information about a timebase resource.
- `int32 OS_TimeBaseGetFreeRun (uint32 timebase_id, uint32 *freerun_val)`
Read the value of the timebase free run counter.
- `int32 OS_TimerCreate (uint32 *timer_id, const char *timer_name, uint32 *clock_accuracy, OS_TimerCallback↵
↵_t callback_ptr)`
Create a timer object.
- `int32 OS_TimerAdd (uint32 *timer_id, const char *timer_name, uint32 timebase_id, OS_ArgCallback↵
↵_t callback_ptr, void *callback_arg)`
Add a timer object based on an existing TimeBase resource.
- `int32 OS_TimerSet (uint32 timer_id, uint32 start_time, uint32 interval_time)`
Configures a periodic or one shot timer.
- `int32 OS_TimerDelete (uint32 timer_id)`
Deletes a timer resource.
- `int32 OS_TimerGetIdByName (uint32 *timer_id, const char *timer_name)`
Locate an existing timer resource by name.
- `int32 OS_TimerGetInfo (uint32 timer_id, OS_timer_prop_t *timer_prop)`
Gets information about an existing timer.

10.27.1 Detailed Description

10.27.2 Function Documentation

10.27.2.1 OS_TimeBaseCreate()

```
int32 OS_TimeBaseCreate (
    uint32 * timebase_id,
    const char * timebase_name,
    OS_TimerSync_t external_sync )
```

Create an abstract Time Base resource.

An OSAL time base is an abstraction of a "timer tick" that can, in turn, be used for measurement of elapsed time between events.

Time bases can be simulated by the operating system using the OS kernel-provided timing facilities, or based on a hardware timing source if provided by the BSP.

A time base object has a servicing task associated with it, that runs at elevated priority and will thereby interrupt user-level tasks when timing ticks occur.

If the external_sync function is passed as NULL, the operating system kernel timing resources will be utilized for a simulated timer tick.

If the external_sync function is not NULL, this should point to a BSP-provided function that will block the calling task until the next tick occurs. This can be used for synchronizing with hardware events.

Note

When provisioning a tunable RTOS kernel, such as RTEMS, the kernel should be configured to support at least (OS_MAX_TASKS + OS_MAX_TIMEBASES) threads, to account for the helper threads associated with time base objects.

Parameters

out	<i>timebase_id</i>	A non-zero ID corresponding to the timebase resource
in	<i>timebase_name</i>	The name of the time base
in	<i>external_sync</i>	A synchronization function for BSP hardware-based timer ticks

Returns

Execution status, see [OSAL Return Code Defines](#)

10.27.2.2 OS_TimeBaseDelete()

```
int32 OS_TimeBaseDelete (
    uint32 timebase_id )
```

Deletes a time base object.

The helper task and any other resources associated with the time base abstraction will be freed.

Parameters

in	<i>timebase↔ _id</i>	The timebase resource to delete
----	--------------------------	---------------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

10.27.2.3 OS_TimeBaseGetFreeRun()

```
int32 OS_TimeBaseGetFreeRun (
    uint32 timebase_id,
    uint32 * freerun_val )
```

Read the value of the timebase free run counter.

Poll the timer free-running time counter in a lightweight fashion.

The free run count is a monotonically increasing value reflecting the total time elapsed since the timebase inception. Units are the same as the timebase itself, usually microseconds.

Applications may quickly and efficiently calculate relative time differences by polling this value and subtracting the previous counter value.

The absolute value of this counter is not relevant, because it will "roll over" after 2^{32} units of time. For a timebase with microsecond units, this occurs approximately every 4294 seconds, or about 1.2 hours.

Note

To ensure consistency of results, the application should sample the value at a minimum of two times the roll over frequency, and calculate the difference between the consecutive samples.

Parameters

in	<i>timebase↔ _id</i>	The timebase to operate on
out	<i>freerun_val</i>	Buffer to store the free run counter

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the id passed in is not a valid timebase

10.27.2.4 OS_TimeBaseGetIdByName()

```
int32 OS_TimeBaseGetIdByName (
    uint32 * timebase_id,
    const char * timebase_name )
```

Find the ID of an existing time base resource.

Given a time base name, find and output the ID associated with it.

Parameters

out	<i>timebase_id</i>	The timebase resource ID
in	<i>timebase_name</i>	The name of the timebase resource to find

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if timebase_id or timebase_name are NULL pointers
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_NAME_NOT_FOUND	if the name was not found in the table

10.27.2.5 OS_TimeBaseGetInfo()

```
int32 OS_TimeBaseGetInfo (
    uint32 timebase_id,
    OS_timebase_prop_t * timebase_prop )
```

Obtain information about a timebase resource.

Fills the buffer referred to by the timebase_prop parameter with relevant information about the time base resource.

This function will pass back a pointer to structure that contains all of the relevant info(name and creator) about the specified timebase.

Parameters

in	<i>timebase_id</i>	The timebase resource ID
out	<i>timebase_prop</i>	Buffer to store timebase properties

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the id passed in is not a valid timebase
OS_INVALID_POINTER	if the timebase_prop pointer is null

10.27.2.6 OS_TimeBaseSet()

```
int32 OS_TimeBaseSet (
    uint32 timebase_id,
    uint32 start_time,
    uint32 interval_time )
```

Sets the tick period for simulated time base objects.

This sets the actual tick period for timing ticks that are simulated by the RTOS kernel (i.e. the "external_sync" parameter on the call to [OS_TimeBaseCreate\(\)](#) is NULL).

The RTOS will be configured to wake up the helper thread at the requested interval.

This function has no effect for time bases that are using a BSP-provided external_sync function.

Parameters

in	<i>timebase_id</i>	The timebase resource to configure
in	<i>start_time</i>	The amount of delay for the first tick, in microseconds.
in	<i>interval_time</i>	The amount of delay between ticks, in microseconds.

Returns

Execution status, see [OSAL Return Code Defines](#)

10.27.2.7 OS_TimerAdd()

```
int32 OS_TimerAdd (
    uint32 * timer_id,
    const char * timer_name,
    uint32 timebase_id,
    OS_ArgCallback_t callback_ptr,
    void * callback_arg )
```

Add a timer object based on an existing TimeBase resource.

A timer object is a resource that invokes the specified application-provided function upon timer expiration. Timers may be one-shot or periodic in nature.

This function uses an existing time base object to service this timer, which must exist prior to adding the timer. The precision of the timer is the same as that of the underlying time base object. Multiple timer objects can be created referring to a single time base object.

This routine also uses a different callback function prototype from [OS_TimerCreate\(\)](#), allowing a single opaque argument to be passed to the callback routine. The OSAL implementation does not use this parameter, and may be set NULL.

Warning

Depending on the OS, the `callback_ptr` function may be similar to an interrupt service routine. Calls that cause the code to block or require an application context (like sending events) are generally not supported.

Parameters

out	<i>timer_id</i>	The non-zero resource ID of the timer object
in	<i>timer_name</i>	Name of the timer object
in	<i>timebase_id</i>	The time base resource to use as a reference
in	<i>callback_ptr</i>	Application-provided function to invoke
in	<i>callback_arg</i>	Opaque argument to pass to callback function

Returns

Execution status, see [OSAL Return Code Defines](#)

10.27.2.8 OS_TimerCreate()

```
int32 OS_TimerCreate (
    uint32 * timer_id,
    const char * timer_name,
    uint32 * clock_accuracy,
    OS_TimerCallback_t callback_ptr )
```

Create a timer object.

A timer object is a resource that invokes the specified application-provided function upon timer expiration. Timers may be one-shot or periodic in nature.

This function creates a dedicated (hidden) time base object to service this timer, which is created and deleted with the timer object itself. The internal time base is configured for an OS simulated timer tick at the same interval as the timer.

Note

clock_accuracy comes from the underlying OS tick value. The nearest integer microsecond value is returned, so may not be exact.

Warning

Depending on the OS, the callback_ptr function may be similar to an interrupt service routine. Calls that cause the code to block or require an application context (like sending events) are generally not supported.

Parameters

out	<i>timer_id</i>	The non-zero resource ID of the timer object
in	<i>timer_name</i>	Name of the timer object
out	<i>clock_accuracy</i>	Expected precision of the timer, in microseconds. This is the underlying tick value rounded to the nearest microsecond integer.
in	<i>callback_ptr</i>	The function pointer of the timer callback or ISR that will be called by the timer. The user's function is declared as follows: void timer_callback(uint32 timer_id) Where the timer_id is passed in to the function by the OSAL

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if any parameters are NULL
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_NAME_TAKEN	if the name is already in use by another timer.
OS_ERR_NO_FREE_IDS	if all of the timers are already allocated.
OS_TIMER_ERR_INVALID_ARGS	if the callback pointer is zero.
OS_TIMER_ERR_UNAVAILABLE	if the timer cannot be created.

10.27.2.9 OS_TimerDelete()

```
int32 OS_TimerDelete (
    uint32 timer_id )
```

Deletes a timer resource.

The application callback associated with the timer will be stopped, and the resources freed for future use.

Parameters

in	<i>timer_id</i>	The timer ID to operate on
----	-----------------	----------------------------

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the <i>timer_id</i> is invalid.
OS_TIMER_ERR_INTERNAL	if there was a problem deleting the timer in the host OS.

10.27.2.10 OS_TimerGetIdByName()

```
int32 OS_TimerGetIdByName (
    uint32 * timer_id,
    const char * timer_name )
```

Locate an existing timer resource by name.

Outputs the ID associated with the given timer, if it exists.

Parameters

out	<i>timer_id</i>	The timer ID corresponding to the name
in	<i>timer_name</i>	The timer name to find

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_INVALID_POINTER	if <i>timer_id</i> or <i>timer_name</i> are NULL pointers
OS_ERR_NAME_TOO_LONG	name length including null terminator greater than OS_MAX_API_NAME
OS_ERR_NAME_NOT_FOUND	if the name was not found in the table

10.27.2.11 OS_TimerGetInfo()

```
int32 OS_TimerGetInfo (
    uint32 timer_id,
    OS_timer_prop_t * timer_prop )
```

Gets information about an existing timer.

This function takes `timer_id`, and looks it up in the OS table. It puts all of the information known about that timer into a structure pointer to by `timer_prop`.

Parameters

in	<i>timer_id</i>	The timer ID to operate on
out	<i>timer_prop</i>	Buffer containing timer properties <ul style="list-style-type: none"> • creator: the OS task ID of the task that created this timer • name: the string name of the timer • start_time: the start time in microseconds, if any • interval_time: the interval time in microseconds, if any • accuracy: the accuracy of the timer in microseconds

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the id passed in is not a valid timer
OS_INVALID_POINTER	if the timer_prop pointer is null

10.27.2.12 OS_TimerSet()

```
int32 OS_TimerSet (
    uint32 timer_id,
    uint32 start_time,
    uint32 interval_time )
```

Configures a periodic or one shot timer.

This function programs the timer with a start time and an optional interval time. The start time is the time in microseconds when the user callback function will be called. If the interval time is non-zero, the timer will be reprogrammed with that interval in microseconds to call the user callback function periodically. If the start time and interval time are zero, the function will return an error.

For a "one-shot" timer, the `start_time` configures the expiration time, and the `interval_time` should be passed as zero to indicate the timer is not to be automatically reset.

Note

The resolution of the times specified is limited to the clock accuracy returned in the `OS_TimerCreate` call. If the times specified in the `start_msec` or `interval_msec` parameters are less than the accuracy, they will be rounded up to the accuracy of the timer.

Parameters

in	<i>timer_id</i>	The timer ID to operate on
in	<i>start_time</i>	Time in microseconds to the first expiration
in	<i>interval_time</i>	Time in microseconds between subsequent intervals, value of zero will only call the user callback function once after the <code>start_msec</code> time.

Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

OS_SUCCESS	Successful execution.
OS_ERR_INVALID_ID	if the <code>timer_id</code> is not valid.
OS_TIMER_ERR_INTERNAL	if there was an error programming the OS timer.
OS_ERROR	if both start time and interval time are zero.

10.28 OSAL Return Code Defines

Macros

- #define `OS_FS_ERR_PATH_TOO_LONG` (-103)
FS path too long.
- #define `OS_FS_ERR_NAME_TOO_LONG` (-104)
FS name too long.
- #define `OS_FS_ERR_DRIVE_NOT_CREATED` (-106)
FS drive not created.
- #define `OS_FS_ERR_DEVICE_NOT_FREE` (-107)
FS device not free.
- #define `OS_FS_ERR_PATH_INVALID` (-108)
FS path invalid.
- #define `OS_FS_SUCCESS` `OS_SUCCESS`
- #define `OS_FS_ERROR` `OS_ERROR`
- #define `OS_FS_ERR_INVALID_POINTER` `OS_INVALID_POINTER`
- #define `OS_FS_ERR_NO_FREE_FDS` `OS_ERR_NO_FREE_IDS`
- #define `OS_FS_ERR_INVALID_FD` `OS_ERR_INVALID_ID`
- #define `OS_FS_UNIMPLEMENTED` `OS_ERR_NOT_IMPLEMENTED`
- #define `OS_SUCCESS` (0)
Successful execution.
- #define `OS_ERROR` (-1)
Failed execution.
- #define `OS_INVALID_POINTER` (-2)
Invalid pointer.
- #define `OS_ERROR_ADDRESS_MISALIGNED` (-3)
Address misalignment.
- #define `OS_ERROR_TIMEOUT` (-4)
Error timeout.
- #define `OS_INVALID_INT_NUM` (-5)
Invalid Interrupt number.
- #define `OS_SEM_FAILURE` (-6)
Semaphore failure.
- #define `OS_SEM_TIMEOUT` (-7)
Semaphore timeout.
- #define `OS_QUEUE_EMPTY` (-8)
Queue empty.
- #define `OS_QUEUE_FULL` (-9)
Queue full.
- #define `OS_QUEUE_TIMEOUT` (-10)
Queue timeout.
- #define `OS_QUEUE_INVALID_SIZE` (-11)
Queue invalid size.
- #define `OS_QUEUE_ID_ERROR` (-12)
Queue ID error.
- #define `OS_ERR_NAME_TOO_LONG` (-13)

- name length including null terminator greater than [OS_MAX_API_NAME](#)*
- [#define OS_ERR_NO_FREE_IDS](#) (-14)
 - No free IDs.*
- [#define OS_ERR_NAME_TAKEN](#) (-15)
 - Name taken.*
- [#define OS_ERR_INVALID_ID](#) (-16)
 - Invalid ID.*
- [#define OS_ERR_NAME_NOT_FOUND](#) (-17)
 - Name not found.*
- [#define OS_ERR_SEM_NOT_FULL](#) (-18)
 - Semaphore not full.*
- [#define OS_ERR_INVALID_PRIORITY](#) (-19)
 - Invalid priority.*
- [#define OS_INVALID_SEM_VALUE](#) (-20)
 - Invalid semaphore value.*
- [#define OS_ERR_FILE](#) (-27)
 - File error.*
- [#define OS_ERR_NOT_IMPLEMENTED](#) (-28)
 - Not implemented.*
- [#define OS_TIMER_ERR_INVALID_ARGS](#) (-29)
 - Timer invalid arguments.*
- [#define OS_TIMER_ERR_TIMER_ID](#) (-30)
 - Timer ID error.*
- [#define OS_TIMER_ERR_UNAVAILABLE](#) (-31)
 - Timer unavailable.*
- [#define OS_TIMER_ERR_INTERNAL](#) (-32)
 - Timer internal error.*
- [#define OS_ERR_OBJECT_IN_USE](#) (-33)
 - Object in use.*
- [#define OS_ERR_BAD_ADDRESS](#) (-34)
 - Bad address.*
- [#define OS_ERR_INCORRECT_OBJ_STATE](#) (-35)
 - Incorrect object state.*
- [#define OS_ERR_INCORRECT_OBJ_TYPE](#) (-36)
 - Incorrect object type.*
- [#define OS_ERR_STREAM_DISCONNECTED](#) (-37)
 - Stream disconnected.*
- [#define OS_ERR_OPERATION_NOT_SUPPORTED](#) (-38)
 - Requested operation is not support on the supplied object(s)*

10.28.1 Detailed Description

10.28.2 Macro Definition Documentation

10.28.2.1 OS_ERR_BAD_ADDRESS

```
#define OS_ERR_BAD_ADDRESS (-34)
```

Bad address.

Definition at line 87 of file osapi.h.

10.28.2.2 OS_ERR_FILE

```
#define OS_ERR_FILE (-27)
```

File error.

Definition at line 80 of file osapi.h.

10.28.2.3 OS_ERR_INCORRECT_OBJ_STATE

```
#define OS_ERR_INCORRECT_OBJ_STATE (-35)
```

Incorrect object state.

Definition at line 88 of file osapi.h.

10.28.2.4 OS_ERR_INCORRECT_OBJ_TYPE

```
#define OS_ERR_INCORRECT_OBJ_TYPE (-36)
```

Incorrect object type.

Definition at line 89 of file osapi.h.

10.28.2.5 OS_ERR_INVALID_ID

```
#define OS_ERR_INVALID_ID (-16)
```

Invalid ID.

Definition at line 75 of file osapi.h.

10.28.2.6 OS_ERR_INVALID_PRIORITY

```
#define OS_ERR_INVALID_PRIORITY (-19)
```

Invalid priority.

Definition at line 78 of file osapi.h.

10.28.2.7 OS_ERR_NAME_NOT_FOUND

```
#define OS_ERR_NAME_NOT_FOUND (-17)
```

Name not found.

Definition at line 76 of file osapi.h.

10.28.2.8 OS_ERR_NAME_TAKEN

```
#define OS_ERR_NAME_TAKEN (-15)
```

Name taken.

Definition at line 74 of file osapi.h.

10.28.2.9 OS_ERR_NAME_TOO_LONG

```
#define OS_ERR_NAME_TOO_LONG (-13)
```

name length including null terminator greater than [OS_MAX_API_NAME](#)

Definition at line 72 of file osapi.h.

10.28.2.10 OS_ERR_NO_FREE_IDS

```
#define OS_ERR_NO_FREE_IDS (-14)
```

No free IDs.

Definition at line 73 of file osapi.h.

10.28.2.11 OS_ERR_NOT_IMPLEMENTED

```
#define OS_ERR_NOT_IMPLEMENTED (-28)
```

Not implemented.

Definition at line 81 of file osapi.h.

10.28.2.12 OS_ERR_OBJECT_IN_USE

```
#define OS_ERR_OBJECT_IN_USE (-33)
```

Object in use.

Definition at line 86 of file osapi.h.

10.28.2.13 OS_ERR_OPERATION_NOT_SUPPORTED

```
#define OS_ERR_OPERATION_NOT_SUPPORTED (-38)
```

Requested operation is not support on the supplied object(s)

Definition at line 91 of file osapi.h.

10.28.2.14 OS_ERR_SEM_NOT_FULL

```
#define OS_ERR_SEM_NOT_FULL (-18)
```

Semaphore not full.

Definition at line 77 of file osapi.h.

10.28.2.15 OS_ERR_STREAM_DISCONNECTED

```
#define OS_ERR_STREAM_DISCONNECTED (-37)
```

Stream disconnected.

Definition at line 90 of file osapi.h.

10.28.2.16 OS_ERROR

```
#define OS_ERROR (-1)
```

Failed execution.

Definition at line 60 of file osapi.h.

10.28.2.17 OS_ERROR_ADDRESS_MISALIGNED

```
#define OS_ERROR_ADDRESS_MISALIGNED (-3)
```

Address misalignment.

Definition at line 62 of file osapi.h.

10.28.2.18 OS_ERROR_TIMEOUT

```
#define OS_ERROR_TIMEOUT (-4)
```

Error timeout.

Definition at line 63 of file osapi.h.

10.28.2.19 OS_FS_ERR_DEVICE_NOT_FREE

```
#define OS_FS_ERR_DEVICE_NOT_FREE (-107)
```

FS device not free.

Definition at line 100 of file osapi-os-filesys.h.

10.28.2.20 OS_FS_ERR_DRIVE_NOT_CREATED

```
#define OS_FS_ERR_DRIVE_NOT_CREATED (-106)
```

FS drive not created.

Definition at line 99 of file osapi-os-filesys.h.

10.28.2.21 OS_FS_ERR_INVALID_FD

```
#define OS_FS_ERR_INVALID_FD OS_ERR_INVALID_ID
```

Deprecated Invalid ID

Definition at line 112 of file osapi-os-filesystem.h.

10.28.2.22 OS_FS_ERR_INVALID_POINTER

```
#define OS_FS_ERR_INVALID_POINTER OS_INVALID_POINTER
```

Deprecated Invalid pointer

Definition at line 110 of file osapi-os-filesystem.h.

10.28.2.23 OS_FS_ERR_NAME_TOO_LONG

```
#define OS_FS_ERR_NAME_TOO_LONG (-104)
```

FS name too long.

Definition at line 98 of file osapi-os-filesystem.h.

10.28.2.24 OS_FS_ERR_NO_FREE_FDS

```
#define OS_FS_ERR_NO_FREE_FDS OS_ERR_NO_FREE_IDS
```

Deprecated No free IDs

Definition at line 111 of file osapi-os-filesystem.h.

10.28.2.25 OS_FS_ERR_PATH_INVALID

```
#define OS_FS_ERR_PATH_INVALID (-108)
```

FS path invalid.

Definition at line 101 of file osapi-os-filesystem.h.

10.28.2.26 OS_FS_ERR_PATH_TOO_LONG

```
#define OS_FS_ERR_PATH_TOO_LONG (-103)
```

FS path too long.

Definition at line 97 of file osapi-os-filesys.h.

10.28.2.27 OS_FS_ERROR

```
#define OS_FS_ERROR OS_ERROR
```

Deprecated Failed execution

Definition at line 109 of file osapi-os-filesys.h.

10.28.2.28 OS_FS_SUCCESS

```
#define OS_FS_SUCCESS OS_SUCCESS
```

Deprecated Successful execution

Definition at line 108 of file osapi-os-filesys.h.

10.28.2.29 OS_FS_UNIMPLEMENTED

```
#define OS_FS_UNIMPLEMENTED OS_ERR_NOT_IMPLEMENTED
```

Deprecated Not implemented

Definition at line 113 of file osapi-os-filesys.h.

10.28.2.30 OS_INVALID_INT_NUM

```
#define OS_INVALID_INT_NUM (-5)
```

Invalid Interrupt number.

Definition at line 64 of file osapi.h.

10.28.2.31 OS_INVALID_POINTER

```
#define OS_INVALID_POINTER (-2)
```

Invalid pointer.

Definition at line 61 of file osapi.h.

10.28.2.32 OS_INVALID_SEM_VALUE

```
#define OS_INVALID_SEM_VALUE (-20)
```

Invalid semaphore value.

Definition at line 79 of file osapi.h.

10.28.2.33 OS_QUEUE_EMPTY

```
#define OS_QUEUE_EMPTY (-8)
```

Queue empty.

Definition at line 67 of file osapi.h.

10.28.2.34 OS_QUEUE_FULL

```
#define OS_QUEUE_FULL (-9)
```

Queue full.

Definition at line 68 of file osapi.h.

10.28.2.35 OS_QUEUE_ID_ERROR

```
#define OS_QUEUE_ID_ERROR (-12)
```

Queue ID error.

Definition at line 71 of file osapi.h.

10.28.2.36 OS_QUEUE_INVALID_SIZE

```
#define OS_QUEUE_INVALID_SIZE (-11)
```

Queue invalid size.

Definition at line 70 of file osapi.h.

10.28.2.37 OS_QUEUE_TIMEOUT

```
#define OS_QUEUE_TIMEOUT (-10)
```

Queue timeout.

Definition at line 69 of file osapi.h.

10.28.2.38 OS_SEM_FAILURE

```
#define OS_SEM_FAILURE (-6)
```

Semaphore failure.

Definition at line 65 of file osapi.h.

10.28.2.39 OS_SEM_TIMEOUT

```
#define OS_SEM_TIMEOUT (-7)
```

Semaphore timeout.

Definition at line 66 of file osapi.h.

10.28.2.40 OS_SUCCESS

```
#define OS_SUCCESS (0)
```

Successful execution.

Definition at line 59 of file osapi.h.

10.28.2.41 OS_TIMER_ERR_INTERNAL

```
#define OS_TIMER_ERR_INTERNAL (-32)
```

Timer internal error.

Definition at line 85 of file osapi.h.

10.28.2.42 OS_TIMER_ERR_INVALID_ARGS

```
#define OS_TIMER_ERR_INVALID_ARGS (-29)
```

Timer invalid arguments.

Definition at line 82 of file osapi.h.

10.28.2.43 OS_TIMER_ERR_TIMER_ID

```
#define OS_TIMER_ERR_TIMER_ID (-30)
```

Timer ID error.

Definition at line 83 of file osapi.h.

10.28.2.44 OS_TIMER_ERR_UNAVAILABLE

```
#define OS_TIMER_ERR_UNAVAILABLE (-31)
```

Timer unavailable.

Definition at line 84 of file osapi.h.

11 Data Structure Documentation

11.1 OS_bin_sem_prop_t Struct Reference

OSAL binary semaphore properties.

```
#include <osapi-os-core.h>
```

Data Fields

- char [name](#) [[OS_MAX_API_NAME](#)]
- [uint32](#) [creator](#)
- [int32](#) [value](#)

11.1.1 Detailed Description

OSAL binary semaphore properties.

Definition at line 107 of file [osapi-os-core.h](#).

11.1.2 Field Documentation

11.1.2.1 creator

```
uint32 OS_bin_sem_prop_t::creator
```

Definition at line 110 of file [osapi-os-core.h](#).

11.1.2.2 name

```
char OS_bin_sem_prop_t::name [OS\_MAX\_API\_NAME]
```

Definition at line 109 of file [osapi-os-core.h](#).

11.1.2.3 value

```
int32 OS_bin_sem_prop_t::value
```

Definition at line 111 of file [osapi-os-core.h](#).

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-os-core.h](#)

11.2 OS_count_sem_prop_t Struct Reference

OSAL counting semaphore properties.

```
#include <osapi-os-core.h>
```

Data Fields

- char [name](#) [[OS_MAX_API_NAME](#)]
- [uint32](#) [creator](#)
- [int32](#) [value](#)

11.2.1 Detailed Description

OSAL counting semaphore properties.

Definition at line 115 of file [osapi-os-core.h](#).

11.2.2 Field Documentation

11.2.2.1 creator

[uint32](#) [OS_count_sem_prop_t::creator](#)

Definition at line 118 of file [osapi-os-core.h](#).

11.2.2.2 name

char [OS_count_sem_prop_t::name](#) [[OS_MAX_API_NAME](#)]

Definition at line 117 of file [osapi-os-core.h](#).

11.2.2.3 value

[int32](#) [OS_count_sem_prop_t::value](#)

Definition at line 119 of file [osapi-os-core.h](#).

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-os-core.h](#)

11.3 `os_dirent_t` Struct Reference

Directory entry.

```
#include <osapi-os-filesys.h>
```

Data Fields

- char [FileName](#) [[OS_MAX_FILE_NAME](#)]

11.3.1 Detailed Description

Directory entry.

Definition at line 219 of file `osapi-os-filesys.h`.

11.3.2 Field Documentation

11.3.2.1 `FileName`

```
char os_dirent_t::FileName[OS_MAX_FILE_NAME]
```

Definition at line 221 of file `osapi-os-filesys.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-os-filesys.h`

11.4 `OS_FdSet` Struct Reference

An abstract structure capable of holding several OSAL IDs.

```
#include <osapi-os-core.h>
```

Data Fields

- [uint8 object_ids](#) [[\(OS_MAX_NUM_OPEN_FILES+7\)/8](#)]

11.4.1 Detailed Description

An abstract structure capable of holding several OSAL IDs.

This is part of the select API and is manipulated using the related API calls. It should not be modified directly by applications.

See also

[OS_SelectFdZero\(\)](#), [OS_SelectFdAdd\(\)](#), [OS_SelectFdClear\(\)](#), [OS_SelectFdsSet\(\)](#)

Definition at line 156 of file `osapi-os-core.h`.

11.4.2 Field Documentation

11.4.2.1 object_ids

```
uint8 OS_FdSet::object_ids[(OS_MAX_NUM_OPEN_FILES+7)/8]
```

Definition at line 158 of file `osapi-os-core.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-os-core.h`

11.5 OS_file_prop_t Struct Reference

OSAL file properties.

```
#include <osapi-os-filesys.h>
```

Data Fields

- char [Path](#) [[OS_MAX_PATH_LEN](#)]
- [uint32](#) [User](#)
- [uint8](#) [IsValid](#)

11.5.1 Detailed Description

OSAL file properties.

Definition at line 165 of file `osapi-os-filesys.h`.

11.5.2 Field Documentation

11.5.2.1 IsValid

`uint8 OS_file_prop_t::IsValid`

Definition at line 169 of file `osapi-os-filesys.h`.

11.5.2.2 Path

`char OS_file_prop_t::Path[OS_MAX_PATH_LEN]`

Definition at line 167 of file `osapi-os-filesys.h`.

11.5.2.3 User

`uint32 OS_file_prop_t::User`

Definition at line 168 of file `osapi-os-filesys.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-os-filesys.h`

11.6 `os_fsinfo_t` Struct Reference

OSAL file system info.

```
#include <osapi-os-filesys.h>
```

Data Fields

- `uint32 MaxFds`
Total number of file descriptors.
- `uint32 FreeFds`
Total number that are free.
- `uint32 MaxVolumes`
Maximum number of volumes.
- `uint32 FreeVolumes`
Total number of volumes free.

11.6.1 Detailed Description

OSAL file system info.

Definition at line 156 of file osapi-os-filesys.h.

11.6.2 Field Documentation

11.6.2.1 FreeFds

```
uint32 os_fsinfo_t::FreeFds
```

Total number that are free.

Definition at line 159 of file osapi-os-filesys.h.

11.6.2.2 FreeVolumes

```
uint32 os_fsinfo_t::FreeVolumes
```

Total number of volumes free.

Definition at line 161 of file osapi-os-filesys.h.

11.6.2.3 MaxFds

```
uint32 os_fsinfo_t::MaxFds
```

Total number of file descriptors.

Definition at line 158 of file osapi-os-filesys.h.

11.6.2.4 MaxVolumes

```
uint32 os_fsinfo_t::MaxVolumes
```

Maximum number of volumes.

Definition at line 160 of file osapi-os-filesys.h.

The documentation for this struct was generated from the following file:

- osal/src/os/inc/[osapi-os-filesys.h](#)

11.7 os_fstat_t Struct Reference

File system status.

```
#include <osapi-os-filesys.h>
```

Data Fields

- [uint32 FileModeBits](#)
- [int32 FileTime](#)
- [uint32 FileSize](#)

11.7.1 Detailed Description

File system status.

Note

This used to be directly typedef'ed to the "struct stat" from the C library

Some C libraries (glibc in particular) actually define member names to reference into sub-structures, so attempting to reuse a name like "st_mtime" might not work.

Definition at line 180 of file osapi-os-filesys.h.

11.7.2 Field Documentation

11.7.2.1 FileModeBits

```
uint32 os_fstat_t::FileModeBits
```

Definition at line 182 of file osapi-os-filesys.h.

11.7.2.2 FileSize

```
uint32 os_fstat_t::FileSize
```

Definition at line 184 of file osapi-os-filesys.h.

11.7.2.3 FileTime

```
int32 os_fstat_t::FileTime
```

Definition at line 183 of file osapi-os-filesys.h.

The documentation for this struct was generated from the following file:

- osal/src/os/inc/[osapi-os-filesys.h](#)

11.8 OS_heap_prop_t Struct Reference

OSAL heap properties.

```
#include <osapi-os-core.h>
```

Data Fields

- [uint32 free_bytes](#)
- [uint32 free_blocks](#)
- [uint32 largest_free_block](#)

11.8.1 Detailed Description

OSAL heap properties.

See also

[OS_HeapGetInfo\(\)](#)

Definition at line 141 of file osapi-os-core.h.

11.8.2 Field Documentation

11.8.2.1 free_blocks

```
uint32 OS_heap_prop_t::free_blocks
```

Definition at line 144 of file osapi-os-core.h.

11.8.2.2 `free_bytes`

```
uint32 OS_heap_prop_t::free_bytes
```

Definition at line 143 of file `osapi-os-core.h`.

11.8.2.3 `largest_free_block`

```
uint32 OS_heap_prop_t::largest_free_block
```

Definition at line 145 of file `osapi-os-core.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-os-core.h`

11.9 `OS_module_address_t` Struct Reference

OSAL module address properties.

```
#include <osapi-os-loader.h>
```

Data Fields

- `uint32 valid`
- `uint32 flags`
- `cpuaddr code_address`
- `cpuaddr code_size`
- `cpuaddr data_address`
- `cpuaddr data_size`
- `cpuaddr bss_address`
- `cpuaddr bss_size`

11.9.1 Detailed Description

OSAL module address properties.

Definition at line 43 of file `osapi-os-loader.h`.

11.9.2 Field Documentation

11.9.2.1 bss_address

`cpuaddr OS_module_address_t::bss_address`

Definition at line 51 of file osapi-os-loader.h.

11.9.2.2 bss_size

`cpuaddr OS_module_address_t::bss_size`

Definition at line 52 of file osapi-os-loader.h.

11.9.2.3 code_address

`cpuaddr OS_module_address_t::code_address`

Definition at line 47 of file osapi-os-loader.h.

11.9.2.4 code_size

`cpuaddr OS_module_address_t::code_size`

Definition at line 48 of file osapi-os-loader.h.

11.9.2.5 data_address

`cpuaddr OS_module_address_t::data_address`

Definition at line 49 of file osapi-os-loader.h.

11.9.2.6 data_size

`cpuaddr OS_module_address_t::data_size`

Definition at line 50 of file osapi-os-loader.h.

11.9.2.7 flags

`uint32 OS_module_address_t::flags`

Definition at line 46 of file `osapi-os-loader.h`.

11.9.2.8 valid

`uint32 OS_module_address_t::valid`

Definition at line 45 of file `osapi-os-loader.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-os-loader.h`

11.10 OS_module_prop_t Struct Reference

OSAL module properties.

```
#include <osapi-os-loader.h>
```

Data Fields

- `cpuaddr entry_point`
- `cpuaddr host_module_id`
- `char filename [OS_MAX_PATH_LEN]`
- `char name [OS_MAX_API_NAME]`
- `OS_module_address_t addr`

11.10.1 Detailed Description

OSAL module properties.

Definition at line 56 of file `osapi-os-loader.h`.

11.10.2 Field Documentation

11.10.2.1 addr

`OS_module_address_t OS_module_prop_t::addr`

Definition at line 62 of file `osapi-os-loader.h`.

11.10.2.2 entry_point

`cpuaddr OS_module_prop_t::entry_point`

Definition at line 58 of file `osapi-os-loader.h`.

11.10.2.3 filename

`char OS_module_prop_t::filename[OS_MAX_PATH_LEN]`

Definition at line 60 of file `osapi-os-loader.h`.

11.10.2.4 host_module_id

`cpuaddr OS_module_prop_t::host_module_id`

Definition at line 59 of file `osapi-os-loader.h`.

11.10.2.5 name

`char OS_module_prop_t::name[OS_MAX_API_NAME]`

Definition at line 61 of file `osapi-os-loader.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-os-loader.h`

11.11 OS_mut_sem_prop_t Struct Reference

OSAL mutex properties.

```
#include <osapi-os-core.h>
```


Data Fields

- char [name](#) [[OS_MAX_API_NAME](#)]
- [uint32](#) [creator](#)

11.11.1 Detailed Description

OSAL mutex properties.

Definition at line 123 of file [osapi-os-core.h](#).

11.11.2 Field Documentation

11.11.2.1 creator

[uint32](#) [OS_mut_sem_prop_t::creator](#)

Definition at line 126 of file [osapi-os-core.h](#).

11.11.2.2 name

char [OS_mut_sem_prop_t::name](#) [[OS_MAX_API_NAME](#)]

Definition at line 125 of file [osapi-os-core.h](#).

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-os-core.h](#)

11.12 OS_queue_prop_t Struct Reference

OSAL queue properties.

```
#include <osapi-os-core.h>
```

Data Fields

- char [name](#) [[OS_MAX_API_NAME](#)]
- [uint32](#) [creator](#)

11.12.1 Detailed Description

OSAL queue properties.

Definition at line 100 of file osapi-os-core.h.

11.12.2 Field Documentation

11.12.2.1 creator

`uint32 OS_queue_prop_t::creator`

Definition at line 103 of file osapi-os-core.h.

11.12.2.2 name

`char OS_queue_prop_t::name[OS_MAX_API_NAME]`

Definition at line 102 of file osapi-os-core.h.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-os-core.h`

11.13 OS_SockAddr_t Struct Reference

Encapsulates a generic network address.

```
#include <osapi-os-net.h>
```

Data Fields

- `uint32 ActualLength`
Length of the actual address data.
- `OS_SockAddrData_t AddrData`
Abstract Address data.

11.13.1 Detailed Description

Encapsulates a generic network address.

This is just an abstract buffer type that holds a network address. It is allocated for the worst-case size defined by `OS_SOCKADDR_MAX_LEN`, and the real size is stored within.

Definition at line 104 of file `osapi-os-net.h`.

11.13.2 Field Documentation

11.13.2.1 ActualLength

`uint32 OS_SockAddr_t::ActualLength`

Length of the actual address data.

Definition at line 106 of file `osapi-os-net.h`.

11.13.2.2 AddrData

`OS_SockAddrData_t OS_SockAddr_t::AddrData`

Abstract Address data.

Definition at line 107 of file `osapi-os-net.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-os-net.h`

11.14 OS_SockAddrData_t Union Reference

Storage buffer for generic network address.

```
#include <osapi-os-net.h>
```

Data Fields

- `uint8 Buffer [OS_SOCKADDR_MAX_LEN]`
Ensures length of at least OS_SOCKADDR_MAX_LEN.
- `uint32 AlignU32`
Ensures uint32 alignment.
- `void * AlignPtr`
Ensures pointer alignment.

11.14.1 Detailed Description

Storage buffer for generic network address.

This is a union type that helps to ensure a minimum alignment value for the data storage, such that it can be cast to the system-specific type without increasing alignment requirements.

Definition at line 90 of file `osapi-os-net.h`.

11.14.2 Field Documentation

11.14.2.1 AlignPtr

```
void* OS_SockAddrData_t::AlignPtr
```

Ensures pointer alignment.

Definition at line 94 of file `osapi-os-net.h`.

11.14.2.2 AlignU32

```
uint32 OS_SockAddrData_t::AlignU32
```

Ensures uint32 alignment.

Definition at line 93 of file `osapi-os-net.h`.

11.14.2.3 Buffer

```
uint8 OS_SockAddrData_t::Buffer[OS_SOCKADDR_MAX_LEN]
```

Ensures length of at least `OS_SOCKADDR_MAX_LEN`.

Definition at line 92 of file `osapi-os-net.h`.

The documentation for this union was generated from the following file:

- `osal/src/os/inc/osapi-os-net.h`

11.15 OS_socket_prop_t Struct Reference

Encapsulates socket properties.

```
#include <osapi-os-net.h>
```

Data Fields

- char [name](#) [[OS_MAX_API_NAME](#)]
Name of the socket.
- [uint32](#) [creator](#)
OSAL TaskID which opened the socket.

11.15.1 Detailed Description

Encapsulates socket properties.

This is for consistency with other OSAL resource types. Currently no extra properties are exposed here but this could change in a future revision of OSAL as needed.

Definition at line 117 of file `osapi-os-net.h`.

11.15.2 Field Documentation

11.15.2.1 creator

```
uint32 OS_socket_prop_t::creator
```

OSAL TaskID which opened the socket.

Definition at line 120 of file `osapi-os-net.h`.

11.15.2.2 name

```
char OS_socket_prop_t::name [OS\_MAX\_API\_NAME]
```

Name of the socket.

Definition at line 119 of file `osapi-os-net.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-os-net.h`

11.16 OS_static_symbol_record_t Struct Reference

Associates a single symbol name with a memory address.

```
#include <osapi-os-loader.h>
```

Data Fields

- const char * [Name](#)
- void(* [Address](#))(void)
- const char * [Module](#)

11.16.1 Detailed Description

Associates a single symbol name with a memory address.

If the OS_STATIC_SYMBOL_TABLE feature is enabled, then an array of these structures should be provided by the application. When the application needs to find a symbol address, the static table will be checked in addition to (or instead of) the OS/library-provided lookup function.

This static symbol allows systems that do not implement dynamic module loading to maintain the same semantics as dynamically loaded modules.

Definition at line 78 of file osapi-os-loader.h.

11.16.2 Field Documentation

11.16.2.1 Address

```
void(* OS_static_symbol_record_t::Address) (void)
```

Definition at line 81 of file osapi-os-loader.h.

11.16.2.2 Module

```
const char* OS_static_symbol_record_t::Module
```

Definition at line 82 of file osapi-os-loader.h.

11.16.2.3 Name

```
const char* OS_static_symbol_record_t::Name
```

Definition at line 80 of file `osapi-os-loader.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-os-loader.h`

11.17 OS_task_prop_t Struct Reference

OSAL task properties.

```
#include <osapi-os-core.h>
```

Data Fields

- char `name` [`OS_MAX_API_NAME`]
- `uint32` `creator`
- `uint32` `stack_size`
- `uint32` `priority`
- `uint32` `OStask_id`

11.17.1 Detailed Description

OSAL task properties.

Definition at line 88 of file `osapi-os-core.h`.

11.17.2 Field Documentation

11.17.2.1 creator

```
uint32 OS_task_prop_t::creator
```

Definition at line 91 of file `osapi-os-core.h`.

11.17.2.2 name

```
char OS_task_prop_t::name[OS_MAX_API_NAME]
```

Definition at line 90 of file osapi-os-core.h.

11.17.2.3 OStask_id

```
uint32 OS_task_prop_t::OStask_id
```

Deprecated

Definition at line 95 of file osapi-os-core.h.

11.17.2.4 priority

```
uint32 OS_task_prop_t::priority
```

Definition at line 93 of file osapi-os-core.h.

11.17.2.5 stack_size

```
uint32 OS_task_prop_t::stack_size
```

Definition at line 92 of file osapi-os-core.h.

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-os-core.h](#)

11.18 OS_time_t Struct Reference

OSAL time.

```
#include <osapi-os-core.h>
```

Data Fields

- [uint32 seconds](#)
- [uint32 microsecs](#)

11.18.1 Detailed Description

OSAL time.

Definition at line 131 of file osapi-os-core.h.

11.18.2 Field Documentation

11.18.2.1 microsecs

`uint32 OS_time_t::microsecs`

Definition at line 134 of file osapi-os-core.h.

11.18.2.2 seconds

`uint32 OS_time_t::seconds`

Definition at line 133 of file osapi-os-core.h.

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-os-core.h](#)

11.19 OS_timebase_prop_t Struct Reference

Time base properties.

```
#include <osapi-os-timer.h>
```

Data Fields

- `char name [OS_MAX_API_NAME]`
- `uint32 creator`
- `uint32 nominal_interval_time`
- `uint32 freerun_time`
- `uint32 accuracy`

11.19.1 Detailed Description

Time base properties.

Definition at line 51 of file osapi-os-timer.h.

11.19.2 Field Documentation

11.19.2.1 accuracy

`uint32 OS_timebase_prop_t::accuracy`

Definition at line 57 of file `osapi-os-timer.h`.

11.19.2.2 creator

`uint32 OS_timebase_prop_t::creator`

Definition at line 54 of file `osapi-os-timer.h`.

11.19.2.3 freerun_time

`uint32 OS_timebase_prop_t::freerun_time`

Definition at line 56 of file `osapi-os-timer.h`.

11.19.2.4 name

`char OS_timebase_prop_t::name[OS_MAX_API_NAME]`

Definition at line 53 of file `osapi-os-timer.h`.

11.19.2.5 nominal_interval_time

`uint32 OS_timebase_prop_t::nominal_interval_time`

Definition at line 55 of file `osapi-os-timer.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-os-timer.h`

11.20 OS_timer_prop_t Struct Reference

Timer properties.

```
#include <osapi-os-timer.h>
```

Data Fields

- char [name](#) [[OS_MAX_API_NAME](#)]
- [uint32](#) [creator](#)
- [uint32](#) [start_time](#)
- [uint32](#) [interval_time](#)
- [uint32](#) [accuracy](#)

11.20.1 Detailed Description

Timer properties.

Definition at line 40 of file `osapi-os-timer.h`.

11.20.2 Field Documentation

11.20.2.1 accuracy

```
uint32 OS_timer_prop_t::accuracy
```

Definition at line 46 of file `osapi-os-timer.h`.

11.20.2.2 creator

```
uint32 OS_timer_prop_t::creator
```

Definition at line 43 of file `osapi-os-timer.h`.

11.20.2.3 interval_time

```
uint32 OS_timer_prop_t::interval_time
```

Definition at line 45 of file `osapi-os-timer.h`.

11.20.2.4 name

```
char OS_timer_prop_t::name[OS_MAX_API_NAME]
```

Definition at line 42 of file osapi-os-timer.h.

11.20.2.5 start_time

```
uint32 OS_timer_prop_t::start_time
```

Definition at line 44 of file osapi-os-timer.h.

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-os-timer.h](#)

11.21 OS_VolumeInfo_t Struct Reference

Internal structure of the OS volume table for mounted file systems and path translation.

```
#include <osapi-os-filesystem.h>
```

Data Fields

- char [DeviceName](#) [OS_FS_DEV_NAME_LEN]
- char [PhysDevName](#) [OS_FS_PHYS_NAME_LEN]
- [uint32](#) [VolumeType](#)
- [uint8](#) [VolatileFlag](#)
- [uint8](#) [FreeFlag](#)
- [uint8](#) [IsMounted](#)
- char [VolumeName](#) [OS_FS_VOL_NAME_LEN]
- char [MountPoint](#) [OS_MAX_PATH_LEN]
- [uint32](#) [BlockSize](#)

11.21.1 Detailed Description

Internal structure of the OS volume table for mounted file systems and path translation.

Deprecated Use the OSAL file system API to register volumes

Definition at line 138 of file osapi-os-filesystem.h.

11.21.2 Field Documentation

11.21.2.1 BlockSize

`uint32 OS_VolumeInfo_t::BlockSize`

Definition at line 148 of file `osapi-os-fs.h`.

11.21.2.2 DeviceName

`char OS_VolumeInfo_t::DeviceName[OS_FS_DEV_NAME_LEN]`

Definition at line 140 of file `osapi-os-fs.h`.

11.21.2.3 FreeFlag

`uint8 OS_VolumeInfo_t::FreeFlag`

Definition at line 144 of file `osapi-os-fs.h`.

11.21.2.4 IsMounted

`uint8 OS_VolumeInfo_t::IsMounted`

Definition at line 145 of file `osapi-os-fs.h`.

11.21.2.5 MountPoint

`char OS_VolumeInfo_t::MountPoint[OS_MAX_PATH_LEN]`

Definition at line 147 of file `osapi-os-fs.h`.

11.21.2.6 PhysDevName

`char OS_VolumeInfo_t::PhysDevName[OS_FS_PHYS_NAME_LEN]`

Definition at line 141 of file `osapi-os-fs.h`.

11.21.2.7 VolatileFlag

```
uint8 OS_VolumeInfo_t::VolatileFlag
```

Definition at line 143 of file `osapi-os-filesys.h`.

11.21.2.8 VolumeName

```
char OS_VolumeInfo_t::VolumeName[OS_FS_VOL_NAME_LEN]
```

Definition at line 146 of file `osapi-os-filesys.h`.

11.21.2.9 VolumeType

```
uint32 OS_VolumeInfo_t::VolumeType
```

Definition at line 142 of file `osapi-os-filesys.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-os-filesys.h`

12 File Documentation

12.1 build/doc/osconfig-example.h File Reference

Macros

- `#define OS_MAX_TASKS`
Configuration file Operating System Abstraction Layer.
- `#define OS_MAX_QUEUES`
The maximum number of queues to support.
- `#define OS_MAX_COUNT_SEMAPHORES`
The maximum number of counting semaphores to support.
- `#define OS_MAX_BIN_SEMAPHORES`
The maximum number of binary semaphores to support.
- `#define OS_MAX_MUTEXES`
The maximum number of mutexes to support.
- `#define OS_MAX_MODULES`
The maximum number of modules to support.
- `#define OS_MAX_TIMEBASES`
The maximum number of timebases to support.
- `#define OS_MAX_TIMERS`

- The maximum number of timer callbacks to support.*

 - #define `OS_MAX_NUM_OPEN_FILES`

The maximum number of concurrently open files to support.
- #define `OS_MAX_NUM_OPEN_DIRS`

The maximum number of concurrently open directories to support.
- #define `OS_MAX_FILE_SYSTEMS`

The maximum number of file systems to support.
- #define `OS_MAX_SYM_LEN`

The maximum length of symbols.
- #define `OS_MAX_FILE_NAME`

The maximum length of OSAL file names.
- #define `OS_MAX_PATH_LEN`

The maximum length of OSAL path names.
- #define `OS_MAX_API_NAME`

The maximum length of OSAL resource names.
- #define `OS_SOCKADDR_MAX_LEN`

The maximum size of the socket address structure.
- #define `OS_BUFFER_SIZE`

The maximum size of output produced by a single `OS_printf()`
- #define `OS_BUFFER_MSG_DEPTH`

The maximum number of `OS_printf()` output strings to buffer.
- #define `OS_UTILITYTASK_PRIORITY`

Priority level of the background utility task.
- #define `OS_UTILITYTASK_STACK_SIZE`

The stack size of the background utility task.
- #define `OS_MAX_CMD_LEN`

The maximum size of a shell command.
- #define `OS_QUEUE_MAX_DEPTH`

The maximum depth of OSAL queues.
- #define `OS_SHELL_CMD_INPUT_FILE_NAME` ""

The name of the temporary file used to store shell commands.
- #define `OS_PRINTF_CONSOLE_NAME` ""

The name of the primary console device.
- #define `OS_MAX_CONSOLES` 1

The maximum number of console devices to support.
- #define `OS_MODULE_FILE_EXTENSION` ".so"

The system-specific file extension used on loadable module files.

12.1.1 Macro Definition Documentation

12.1.1.1 OS_BUFFER_MSG_DEPTH

```
#define OS_BUFFER_MSG_DEPTH
```

The maximum number of [OS_printf\(\)](#) output strings to buffer.

Based on the OSAL_CONFIG_PRINTF_BUFFER_DEPTH configuration option

Definition at line 196 of file osconfig-example.h.

12.1.1.2 OS_BUFFER_SIZE

```
#define OS_BUFFER_SIZE
```

The maximum size of output produced by a single [OS_printf\(\)](#)

Based on the OSAL_CONFIG_PRINTF_BUFFER_SIZE configuration option

Definition at line 189 of file osconfig-example.h.

12.1.1.3 OS_MAX_API_NAME

```
#define OS_MAX_API_NAME
```

The maximum length of OSAL resource names.

Based on the OSAL_CONFIG_MAX_API_NAME configuration option

Note

This value must include a terminating NUL character

Definition at line 172 of file osconfig-example.h.

12.1.1.4 OS_MAX_BIN_SEMAPHORES

```
#define OS_MAX_BIN_SEMAPHORES
```

The maximum number of binary semaphores to support.

Based on the OSAL_CONFIG_MAX_BIN_SEMAPHORES configuration option

Definition at line 81 of file osconfig-example.h.

12.1.1.5 OS_MAX_CMD_LEN

```
#define OS_MAX_CMD_LEN
```

The maximum size of a shell command.

This limit is only applicable if shell support is enabled.

Based on the OSAL_CONFIG_MAX_CMD_LEN configuration option

Note

This value must include a terminating NUL character

Definition at line 227 of file osconfig-example.h.

12.1.1.6 OS_MAX_CONSOLES

```
#define OS_MAX_CONSOLES 1
```

The maximum number of console devices to support.

Fixed value based on current OSAL implementation, not user configurable.

Definition at line 269 of file osconfig-example.h.

12.1.1.7 OS_MAX_COUNT_SEMAPHORES

```
#define OS_MAX_COUNT_SEMAPHORES
```

The maximum number of counting semaphores to support.

Based on the OSAL_CONFIG_MAX_COUNT_SEMAPHORES configuration option

Definition at line 74 of file osconfig-example.h.

12.1.1.8 OS_MAX_FILE_NAME

```
#define OS_MAX_FILE_NAME
```

The maximum length of OSAL file names.

This limit applies specifically to the file name portion, not the directory portion, of a path name.

Based on the OSAL_CONFIG_MAX_FILE_NAME configuration option

Note

This value must include a terminating NUL character

Definition at line 151 of file osconfig-example.h.

12.1.1.9 OS_MAX_FILE_SYSTEMS

```
#define OS_MAX_FILE_SYSTEMS
```

The maximum number of file systems to support.

Based on the OSAL_CONFIG_MAX_FILE_SYSTEMS configuration option

Definition at line 130 of file osconfig-example.h.

12.1.1.10 OS_MAX_MODULES

```
#define OS_MAX_MODULES
```

The maximum number of modules to support.

Based on the OSAL_CONFIG_MAX_MODULES configuration option

Definition at line 95 of file osconfig-example.h.

12.1.1.11 OS_MAX_MUTEXES

```
#define OS_MAX_MUTEXES
```

The maximum number of mutexes to support.

Based on the OSAL_CONFIG_MAX_MUTEXES configuration option

Definition at line 88 of file osconfig-example.h.

12.1.1.12 OS_MAX_NUM_OPEN_DIRS

```
#define OS_MAX_NUM_OPEN_DIRS
```

The maximum number of concurrently open directories to support.

Based on the OSAL_CONFIG_MAX_NUM_OPEN_DIRS configuration option

Definition at line 123 of file osconfig-example.h.

12.1.1.13 OS_MAX_NUM_OPEN_FILES

```
#define OS_MAX_NUM_OPEN_FILES
```

The maximum number of concurrently open files to support.

Based on the OSAL_CONFIG_MAX_NUM_OPEN_FILES configuration option

Definition at line 116 of file osconfig-example.h.

12.1.1.14 OS_MAX_PATH_LEN

```
#define OS_MAX_PATH_LEN
```

The maximum length of OSAL path names.

This limit applies to the overall length of a path name, including the file name and directory portions.

Based on the OSAL_CONFIG_MAX_PATH_LEN configuration option

Note

This value must include a terminating NUL character

Definition at line 163 of file osconfig-example.h.

12.1.1.15 OS_MAX_QUEUES

```
#define OS_MAX_QUEUES
```

The maximum number of queues to support.

Based on the OSAL_CONFIG_MAX_QUEUES configuration option

Definition at line 67 of file osconfig-example.h.

12.1.1.16 OS_MAX_SYM_LEN

```
#define OS_MAX_SYM_LEN
```

The maximum length of symbols.

Based on the OSAL_CONFIG_MAX_SYM_LEN configuration option

Note

This value must include a terminating NUL character

Definition at line 139 of file osconfig-example.h.

12.1.1.17 OS_MAX_TASKS

```
#define OS_MAX_TASKS
```

Configuration file Operating System Abstraction Layer.

The specific definitions in this file may only be modified by setting the respective OSAL configuration options in the CMake build.

Any direct modifications to the generated copy will be overwritten each time CMake executes.

Note

This file was automatically generated by CMake from /home/travis/build/nasa/cFS/cfe/default_config.cmake The maximum number of to support

Based on the OSAL_CONFIG_MAX_TASKS configuration option

Definition at line 60 of file osconfig-example.h.

12.1.1.18 OS_MAX_TIMEBASES

```
#define OS_MAX_TIMEBASES
```

The maximum number of timebases to support.

Based on the OSAL_CONFIG_MAX_TIMEBASES configuration option

Definition at line 102 of file osconfig-example.h.

12.1.1.19 OS_MAX_TIMERS

```
#define OS_MAX_TIMERS
```

The maximum number of timer callbacks to support.

Based on the OSAL_CONFIG_MAX_TIMERS configuration option

Definition at line 109 of file osconfig-example.h.

12.1.1.20 OS_MODULE_FILE_EXTENSION

```
#define OS_MODULE_FILE_EXTENSION ".so"
```

The system-specific file extension used on loadable module files.

Fixed value based on system selection, not user configurable.

Definition at line 276 of file osconfig-example.h.

12.1.1.21 OS_PRINTF_CONSOLE_NAME

```
#define OS_PRINTF_CONSOLE_NAME ""
```

The name of the primary console device.

This is the device to which [OS_printf\(\)](#) output is written. The output may be configured to tag each line with this prefix for identification.

Based on the OSAL_CONFIG_PRINTF_CONSOLE_NAME configuration option

Definition at line 254 of file osconfig-example.h.

12.1.1.22 OS_QUEUE_MAX_DEPTH

```
#define OS_QUEUE_MAX_DEPTH
```

The maximum depth of OSAL queues.

Based on the OSAL_CONFIG_QUEUE_MAX_DEPTH configuration option

Definition at line 234 of file osconfig-example.h.

12.1.1.23 OS_SHELL_CMD_INPUT_FILE_NAME

```
#define OS_SHELL_CMD_INPUT_FILE_NAME ""
```

The name of the temporary file used to store shell commands.

This configuration is only applicable if shell support is enabled, and only necessary/relevant on some OS implementations.

Based on the OSAL_CONFIG_SHELL_CMD_INPUT_FILE_NAME configuration option

Definition at line 244 of file osconfig-example.h.

12.1.1.24 OS_SOCKADDR_MAX_LEN

```
#define OS_SOCKADDR_MAX_LEN
```

The maximum size of the socket address structure.

This is part of the Socket API, and should be set large enough to hold the largest address type in use on the target system.

Based on the OSAL_CONFIG_SOCKADDR_MAX_LEN configuration option

Definition at line 182 of file osconfig-example.h.

12.1.1.25 OS_UTILITYTASK_PRIORITY

```
#define OS_UTILITYTASK_PRIORITY
```

Priority level of the background utility task.

This task is responsible for writing buffered output of OS_printf to the actual console device, and any other future maintenance task.

Based on the OSAL_CONFIG_UTILITYTASK_PRIORITY configuration option

Definition at line 206 of file osconfig-example.h.

12.1.1.26 OS_UTILITYTASK_STACK_SIZE

```
#define OS_UTILITYTASK_STACK_SIZE
```

The stack size of the background utility task.

This task is responsible for writing buffered output of OS_printf to the actual console device, and any other future maintenance task.

Based on the OSAL_CONFIG_UTILITYTASK_STACK_SIZE configuration option

Definition at line 216 of file osconfig-example.h.

12.2 cfe/docs/src/osal_fs.dox File Reference

12.3 cfe/docs/src/osal_timer.dox File Reference

12.4 cfe/docs/src/osalmain.dox File Reference

12.5 osal/src/os/inc/common_types.h File Reference

```
#include <stdint.h>
#include <stddef.h>
#include <stdbool.h>
```

Macros

- `#define CompileTimeAssert(Condition, Message) typedef char Message[(Condition) ? 1 : -1]`
- `#define _EXTENSION_`
- `#define OS_PACK`
- `#define OS_ALIGN(n)`
- `#define OS_USED`
- `#define OS_PRINTF(n, m)`
- `#define TRUE true`
- `#define FALSE false`
- `#define NULL ((void *) 0)`

Typedefs

- `typedef int8_t int8`
- `typedef int16_t int16`
- `typedef int32_t int32`
- `typedef int64_t int64`
- `typedef uint8_t uint8`
- `typedef uint16_t uint16`
- `typedef uint32_t uint32`
- `typedef uint64_t uint64`
- `typedef intptr_t intptr`
- `typedef uintptr_t cpuaddr`
- `typedef size_t cpusize`
- `typedef ptrdiff_t cpudiff`
- `typedef bool osalbool`
- `typedef osalbool boolean`

Functions

- `CompileTimeAssert (sizeof(uint8)==1, TypeUint8WrongSize)`
- `CompileTimeAssert (sizeof(uint16)==2, TypeUint16WrongSize)`
- `CompileTimeAssert (sizeof(uint32)==4, TypeUint32WrongSize)`
- `CompileTimeAssert (sizeof(uint64)==8, TypeUint64WrongSize)`
- `CompileTimeAssert (sizeof(int8)==1, Typeint8WrongSize)`
- `CompileTimeAssert (sizeof(int16)==2, Typeint16WrongSize)`
- `CompileTimeAssert (sizeof(int32)==4, Typeint32WrongSize)`
- `CompileTimeAssert (sizeof(int64)==8, Typeint64WrongSize)`
- `CompileTimeAssert (sizeof(cpuaddr) >=sizeof(void *), TypePtrWrongSize)`

12.5.1 Macro Definition Documentation

12.5.1.1 `_EXTENSION_`

```
#define _EXTENSION_
```

Definition at line 70 of file common_types.h.

12.5.1.2 `CompileTimeAssert`

```
#define CompileTimeAssert(  
    Condition,  
    Message ) typedef char Message[(Condition) ? 1 : -1]
```

Definition at line 49 of file common_types.h.

12.5.1.3 `FALSE`

```
#define FALSE false
```

Deprecated Use false

Definition at line 132 of file common_types.h.

12.5.1.4 `NULL`

```
#define NULL ((void *) 0)
```

Definition at line 140 of file common_types.h.

12.5.1.5 `OS_ALIGN`

```
#define OS_ALIGN(  
    n )
```

Definition at line 72 of file common_types.h.

12.5.1.6 `OS_PACK`

```
#define OS_PACK
```

Definition at line 71 of file common_types.h.

12.5.1.7 OS_PRINTF

```
#define OS_PRINTF(  
    n,  
    m )
```

Definition at line 74 of file common_types.h.

12.5.1.8 OS_USED

```
#define OS_USED
```

Definition at line 73 of file common_types.h.

12.5.1.9 TRUE

```
#define TRUE true
```

Deprecated Use true

Definition at line 128 of file common_types.h.

12.5.2 Typedef Documentation

12.5.2.1 boolean

```
typedef osalbool boolean
```

Deprecated Use bool

Definition at line 124 of file common_types.h.

12.5.2.2 cpuaddr

```
typedef uintptr_t cpuaddr
```

Definition at line 95 of file common_types.h.

12.5.2.3 cpudiff

```
typedef ptrdiff_t cpudiff
```

Definition at line 97 of file common_types.h.

12.5.2.4 cpusize

```
typedef size_t cpusize
```

Definition at line 96 of file common_types.h.

12.5.2.5 int16

```
typedef int16_t int16
```

Definition at line 87 of file common_types.h.

12.5.2.6 int32

```
typedef int32_t int32
```

Definition at line 88 of file common_types.h.

12.5.2.7 int64

```
typedef int64_t int64
```

Definition at line 89 of file common_types.h.

12.5.2.8 int8

```
typedef int8_t int8
```

Definition at line 86 of file common_types.h.

12.5.2.9 intptr

```
typedef intptr_t intptr
```

Definition at line 94 of file common_types.h.

12.5.2.10 osalbool

```
typedef bool osalbool
```

Deprecated Use bool

Definition at line 105 of file common_types.h.

12.5.2.11 uint16

```
typedef uint16_t uint16
```

Definition at line 91 of file common_types.h.

12.5.2.12 uint32

```
typedef uint32_t uint32
```

Definition at line 92 of file common_types.h.

12.5.2.13 uint64

```
typedef uint64_t uint64
```

Definition at line 93 of file common_types.h.

12.5.2.14 uint8

```
typedef uint8_t uint8
```

Definition at line 90 of file common_types.h.

12.5.3 Function Documentation

12.5.3.1 CompileTimeAssert() [1/9]

```
CompileTimeAssert (
    sizeof(uint8)  = 1,
    TypeUint8WrongSize )
```

12.5.3.2 CompileTimeAssert() [2/9]

```
CompileTimeAssert (
    sizeof(uint16) = 2,
    TypeUint16WrongSize )
```

12.5.3.3 CompileTimeAssert() [3/9]

```
CompileTimeAssert (
    sizeof(uint32) = 4,
    TypeUint32WrongSize )
```

12.5.3.4 CompileTimeAssert() [4/9]

```
CompileTimeAssert (
    sizeof(uint64) = 8,
    TypeUint64WrongSize )
```

12.5.3.5 CompileTimeAssert() [5/9]

```
CompileTimeAssert (
    sizeof(int8)  = 1,
    Typeint8WrongSize )
```

12.5.3.6 CompileTimeAssert() [6/9]

```
CompileTimeAssert (
    sizeof(int16) = 2,
    Typeint16WrongSize )
```

12.5.3.7 CompileTimeAssert() [7/9]

```
CompileTimeAssert (
    sizeof(int32) == 4,
    Typeint32WrongSize )
```

12.5.3.8 CompileTimeAssert() [8/9]

```
CompileTimeAssert (
    sizeof(int64) == 8,
    Typeint64WrongSize )
```

12.5.3.9 CompileTimeAssert() [9/9]

```
CompileTimeAssert (
    sizeof(cpuaddr) >= sizeof(void *) ,
    TypePtrWrongSize )
```

12.6 osal/src/os/inc/osapi-os-core.h File Reference

```
#include <stdarg.h>
```

Data Structures

- struct [OS_task_prop_t](#)
OSAL task properties.
- struct [OS_queue_prop_t](#)
OSAL queue properties.
- struct [OS_bin_sem_prop_t](#)
OSAL binary semaphore properties.
- struct [OS_count_sem_prop_t](#)
OSAL counting semaphore properties.
- struct [OS_mut_sem_prop_t](#)
OSAL mutex properties.
- struct [OS_time_t](#)
OSAL time.
- struct [OS_heap_prop_t](#)
OSAL heap properties.
- struct [OS_FdSet](#)
An abstract structure capable of holding several OSAL IDs.

Macros

- #define `OS_OBJECT_INDEX_MASK` 0xFFFF
Object index mask.
- #define `OS_OBJECT_TYPE_SHIFT` 16
Object type shift.
- #define `OS_OBJECT_TYPE_UNDEFINED` 0x00
Object type undefined.
- #define `OS_OBJECT_TYPE_OS_TASK` 0x01
Object task type.
- #define `OS_OBJECT_TYPE_OS_QUEUE` 0x02
Object queue type.
- #define `OS_OBJECT_TYPE_OS_COUNTSEM` 0x03
Object counting semaphore type.
- #define `OS_OBJECT_TYPE_OS_BINSEM` 0x04
Object binary semaphore type.
- #define `OS_OBJECT_TYPE_OS_MUTEX` 0x05
Object mutex type.
- #define `OS_OBJECT_TYPE_OS_STREAM` 0x06
Object stream type.
- #define `OS_OBJECT_TYPE_OS_DIR` 0x07
Object directory type.
- #define `OS_OBJECT_TYPE_OS_TIMEBASE` 0x08
Object timebase type.
- #define `OS_OBJECT_TYPE_OS_TIMECB` 0x09
Object timer callback type.
- #define `OS_OBJECT_TYPE_OS_MODULE` 0x0A
Object module type.
- #define `OS_OBJECT_TYPE_OS_FILESYS` 0x0B
Object file system type.
- #define `OS_OBJECT_TYPE_OS_CONSOLE` 0x0C
Object console type.
- #define `OS_OBJECT_TYPE_USER` 0x10
Object user type.
- #define `OS_MAX_TASK_PRIORITY` 255
Upper limit for OSAL task priorities.
- #define `OS_OBJECT_CREATOR_ANY` 0
Constant that may be passed to `OS_ForEachObject()`/`OS_ForEachObjectOfType()` to match any creator (i.e. get all objects)
- #define `OS_SEM_FULL` 1
Semaphore full state.
- #define `OS_SEM_EMPTY` 0
Semaphore empty state.
- #define `OS_FP_ENABLED` 1
Floating point enabled state for a task.
- #define `OS_ERROR_NAME_LENGTH` 35
Error string name length.

Typedefs

- typedef char [os_err_name_t](#)[[OS_ERROR_NAME_LENGTH](#)]
For the [OS_GetErrorName\(\)](#) function, to ensure everyone is making an array of the same length.
- typedef void [osal_task](#)
For task entry point.
- typedef void(* [OS_ArgCallback_t](#)) (uint32 object_id, void *arg)
General purpose OSAL callback function.

Enumerations

- enum [OS_StreamState_t](#) { [OS_STREAM_STATE_BOUND](#) = 0x01, [OS_STREAM_STATE_CONNECTED](#) = 0x02, [OS_STREAM_STATE_READABLE](#) = 0x04, [OS_STREAM_STATE_WRITABLE](#) = 0x08 }
- For the [OS_SelectSingle\(\)](#) function's in/out StateFlags parameter, the state(s) of the stream and the result of the select is a combination of one or more of these states.*

Functions

- typedef [osal_task](#) ((*osal_task_entry)(void))
For task entry point.
- void [OS_Application_Startup](#) (void)
Application startup.
- void [OS_Application_Run](#) (void)
Application run.
- int32 [OS_API_Init](#) (void)
Initialization of API.
- void [OS_IdleLoop](#) (void)
Background thread implementation - waits forever for events to occur.
- void [OS_DeleteAllObjects](#) (void)
delete all resources created in OSAL.
- void [OS_ApplicationShutdown](#) (uint8 flag)
Initiate orderly shutdown.
- void [OS_ApplicationExit](#) (int32 Status)
Exit/Abort the application.
- int32 [OS_GetResourceName](#) (uint32 object_id, char *buffer, uint32 buffer_size)
Obtain the name of an object given an arbitrary object ID.
- uint32 [OS_IdentifyObject](#) (uint32 object_id)
Obtain the type of an object given an arbitrary object ID.
- int32 [OS_ConvertToArrayIndex](#) (uint32 object_id, uint32 *ArrayIndex)
Converts an abstract ID into a number suitable for use as an array index.
- void [OS_ForEachObject](#) (uint32 creator_id, [OS_ArgCallback_t](#) callback_ptr, void *callback_arg)
call the supplied callback function for all valid object IDs
- void [OS_ForEachObjectOfType](#) (uint32 objtype, uint32 creator_id, [OS_ArgCallback_t](#) callback_ptr, void *callback_arg)
call the supplied callback function for valid object IDs of a specific type
- int32 [OS_TaskCreate](#) (uint32 *task_id, const char *task_name, osal_task_entry function_pointer, uint32 *stack_ptr, uint32 stack_size, uint32 priority, uint32 flags)

- Creates a task and starts running it.*

 - [int32 OS_TaskDelete](#) ([uint32](#) task_id)

Deletes the specified Task.
- [void OS_TaskExit](#) (void)

Exits the calling task.
- [int32 OS_TaskInstallDeleteHandler](#) (osal_task_entry function_pointer)

Installs a handler for when the task is deleted.
- [int32 OS_TaskDelay](#) ([uint32](#) millisecond)

Delay a task for specified amount of milliseconds.
- [int32 OS_TaskSetPriority](#) ([uint32](#) task_id, [uint32](#) new_priority)

Sets the given task to a new priority.
- [int32 OS_TaskRegister](#) (void)

Obsolete.
- [uint32 OS_TaskGetId](#) (void)

Obtain the task id of the calling task.
- [int32 OS_TaskGetIdByName](#) ([uint32](#) *task_id, const char *task_name)

Find an existing task ID by name.
- [int32 OS_TaskGetInfo](#) ([uint32](#) task_id, [OS_task_prop_t](#) *task_prop)

Fill a property object buffer with details regarding the resource.
- [int32 OS_TaskFindIdBySystemData](#) ([uint32](#) *task_id, const void *sysdata, [size_t](#) sysdata_size)

Reverse-lookup the OSAL task ID from an operating system ID.
- [int32 OS_QueueCreate](#) ([uint32](#) *queue_id, const char *queue_name, [uint32](#) queue_depth, [uint32](#) data_size, [uint32](#) flags)

Create a message queue.
- [int32 OS_QueueDelete](#) ([uint32](#) queue_id)

Deletes the specified message queue.
- [int32 OS_QueueGet](#) ([uint32](#) queue_id, void *data, [uint32](#) size, [uint32](#) *size_copied, [int32](#) timeout)

Receive a message on a message queue.
- [int32 OS_QueuePut](#) ([uint32](#) queue_id, const void *data, [uint32](#) size, [uint32](#) flags)

Put a message on a message queue.
- [int32 OS_QueueGetIdByName](#) ([uint32](#) *queue_id, const char *queue_name)

Find an existing queue ID by name.
- [int32 OS_QueueGetInfo](#) ([uint32](#) queue_id, [OS_queue_prop_t](#) *queue_prop)

Fill a property object buffer with details regarding the resource.
- [int32 OS_BinSemCreate](#) ([uint32](#) *sem_id, const char *sem_name, [uint32](#) sem_initial_value, [uint32](#) options)

Creates a binary semaphore.
- [int32 OS_BinSemFlush](#) ([uint32](#) sem_id)

Unblock all tasks pending on the specified semaphore.
- [int32 OS_BinSemGive](#) ([uint32](#) sem_id)

Increment the semaphore value.
- [int32 OS_BinSemTake](#) ([uint32](#) sem_id)

Decrement the semaphore value.
- [int32 OS_BinSemTimedWait](#) ([uint32](#) sem_id, [uint32](#) msecs)

Decrement the semaphore value with a timeout.
- [int32 OS_BinSemDelete](#) ([uint32](#) sem_id)

Deletes the specified Binary Semaphore.
- [int32 OS_BinSemGetIdByName](#) ([uint32](#) *sem_id, const char *sem_name)

- Find an existing semaphore ID by name.*

 - `int32 OS_BinSemGetInfo (uint32 sem_id, OS_bin_sem_prop_t *bin_prop)`

Fill a property object buffer with details regarding the resource.
- `int32 OS_CountSemCreate (uint32 *sem_id, const char *sem_name, uint32 sem_initial_value, uint32 options)`

Creates a counting semaphore.
- `int32 OS_CountSemGive (uint32 sem_id)`

Increment the semaphore value.
- `int32 OS_CountSemTake (uint32 sem_id)`

Decrement the semaphore value.
- `int32 OS_CountSemTimedWait (uint32 sem_id, uint32 msec)`

Decrement the semaphore value with timeout.
- `int32 OS_CountSemDelete (uint32 sem_id)`

Deletes the specified counting Semaphore.
- `int32 OS_CountSemGetIdByName (uint32 *sem_id, const char *sem_name)`

Find an existing semaphore ID by name.
- `int32 OS_CountSemGetInfo (uint32 sem_id, OS_count_sem_prop_t *count_prop)`

Fill a property object buffer with details regarding the resource.
- `int32 OS_MutSemCreate (uint32 *sem_id, const char *sem_name, uint32 options)`

Creates a mutex semaphore.
- `int32 OS_MutSemGive (uint32 sem_id)`

Releases the mutex object referenced by sem_id.
- `int32 OS_MutSemTake (uint32 sem_id)`

Acquire the mutex object referenced by sem_id.
- `int32 OS_MutSemDelete (uint32 sem_id)`

Deletes the specified Mutex Semaphore.
- `int32 OS_MutSemGetIdByName (uint32 *sem_id, const char *sem_name)`

Find an existing mutex ID by name.
- `int32 OS_MutSemGetInfo (uint32 sem_id, OS_mut_sem_prop_t *mut_prop)`

Fill a property object buffer with details regarding the resource.
- `int32 OS_Milli2Ticks (uint32 milli_seconds)`

Convert time units from milliseconds to system ticks.
- `int32 OS_Tick2Micros (void)`

Get the system tick size, in microseconds.
- `int32 OS_GetLocalTime (OS_time_t *time_struct)`

Get the local time.
- `int32 OS_SetLocalTime (OS_time_t *time_struct)`

Set the local time.
- `int32 OS_ExcAttachHandler (uint32 ExceptionNumber, void(*ExceptionHandler)(uint32, const void *, uint32), int32 parameter)`

placeholder; not currently implemented
- `int32 OS_ExcEnable (int32 ExceptionNumber)`

placeholder; not currently implemented
- `int32 OS_ExcDisable (int32 ExceptionNumber)`

placeholder; not currently implemented
- `int32 OS_FPUExcAttachHandler (uint32 ExceptionNumber, osal_task_entry ExceptionHandler, int32 parameter)`

Set an FPU exception handler function.
- `int32 OS_FPUExcEnable (int32 ExceptionNumber)`

- Enable FPU exceptions.*

 - [int32 OS_FPUExcDisable](#) ([int32](#) ExceptionNumber)
- Disable FPU exceptions.*

 - [int32 OS_FPUExcSetMask](#) ([uint32](#) mask)
- Sets the FPU exception mask.*

 - [int32 OS_FPUExcGetMask](#) ([uint32](#) *mask)
- Gets the FPU exception mask.*

 - [int32 OS_IntAttachHandler](#) ([uint32](#) InterruptNumber, [osal_task_entry](#) InterruptHandler, [int32](#) parameter)
- DEPRECATED; Associate an interrupt number to a specified handler routine.*

 - [int32 OS_IntUnlock](#) ([int32](#) IntLevel)
- DEPRECATED; Enable interrupts.*

 - [int32 OS_IntLock](#) (void)
- DEPRECATED; Disable interrupts.*

 - [int32 OS_IntEnable](#) ([int32](#) Level)
- DEPRECATED; Enables interrupts through Level.*

 - [int32 OS_IntDisable](#) ([int32](#) Level)
- DEPRECATED; Disable interrupts through Level.*

 - [int32 OS_IntSetMask](#) ([uint32](#) mask)
- DEPRECATED; Set the CPU interrupt mask register.*

 - [int32 OS_IntGetMask](#) ([uint32](#) *mask)
- DEPRECATED; Get the CPU interrupt mask register.*

 - [int32 OS_IntAck](#) ([int32](#) InterruptNumber)
- DEPRECATED; Acknowledge the corresponding interrupt number.*

 - [int32 OS_ShMemInit](#) (void)
- DEPRECATED - platform dependent, never implemented in framework OSALs.*

 - [int32 OS_ShMemCreate](#) ([uint32](#) *Id, [uint32](#) NBytes, const char *SegName)
- DEPRECATED - platform dependent, never implemented in framework OSALs.*

 - [int32 OS_ShMemSemTake](#) ([uint32](#) Id)
- DEPRECATED - platform dependent, never implemented in framework OSALs.*

 - [int32 OS_ShMemSemGive](#) ([uint32](#) Id)
- DEPRECATED - platform dependent, never implemented in framework OSALs.*

 - [int32 OS_ShMemAttach](#) ([cpuaddr](#) *Address, [uint32](#) Id)
- DEPRECATED - platform dependent, never implemented in framework OSALs.*

 - [int32 OS_ShMemGetIdByName](#) ([uint32](#) *ShMemId, const char *SegName)
- DEPRECATED - platform dependent, never implemented in framework OSALs.*

 - [int32 OS_HeapGetInfo](#) ([OS_heap_prop_t](#) *heap_prop)
- Return current info on the heap.*

 - [int32 OS_GetErrorName](#) ([int32](#) error_num, [os_err_name_t](#) *err_name)
- Convert an error number to a string.*

 - [int32 OS_SelectMultiple](#) ([OS_FdSet](#) *ReadSet, [OS_FdSet](#) *WriteSet, [int32](#) msecs)
- Wait for events across multiple file handles.*

 - [int32 OS_SelectSingle](#) ([uint32](#) objid, [uint32](#) *StateFlags, [int32](#) msecs)
- Wait for events on a single file handle.*

 - [int32 OS_SelectFdZero](#) ([OS_FdSet](#) *Set)
- Clear a FdSet structure.*

 - [int32 OS_SelectFdAdd](#) ([OS_FdSet](#) *Set, [uint32](#) objid)
- Add an ID to an FdSet structure.*

- `int32 OS_SelectFdClear (OS_FdSet *Set, uint32 objid)`
Clear an ID from an FdSet structure.
- `bool OS_SelectFdsSet (OS_FdSet *Set, uint32 objid)`
Check if an FdSet structure contains a given ID.
- `void OS_printf (const char *string,...) OS_PRINTF(1`
Abstraction for the system printf() call.
- `void OS_printf_disable (void)`
This function disables the output from OS_printf.
- `void OS_printf_enable (void)`
This function enables the output from OS_printf.
- `uint32 OS_BSP_GetArgC (void)`
- `char *const * OS_BSP_GetArgV (void)`
- `void OS_BSP_SetExitCode (int32 code)`

12.6.1 Macro Definition Documentation

12.6.1.1 OS_ERROR_NAME_LENGTH

```
#define OS_ERROR_NAME_LENGTH 35
```

Error string name length.

The sizes of strings in OSAL functions are built with this limit in mind. Always check the uses of `os_err_name_t` when changing this value.

Definition at line 83 of file `osapi-os-core.h`.

12.6.1.2 OS_FP_ENABLED

```
#define OS_FP_ENABLED 1
```

Floating point enabled state for a task.

Definition at line 76 of file `osapi-os-core.h`.

12.6.1.3 OS_MAX_TASK_PRIORITY

```
#define OS_MAX_TASK_PRIORITY 255
```

Upper limit for OSAL task priorities.

Definition at line 59 of file `osapi-os-core.h`.

12.6.1.4 OS_OBJECT_CREATOR_ANY

```
#define OS_OBJECT_CREATOR_ANY 0
```

Constant that may be passed to [OS_ForEachObject\(\)](#)/[OS_ForEachObjectOfType\(\)](#) to match any creator (i.e. get all objects)

Definition at line 65 of file osapi-os-core.h.

12.6.1.5 OS_OBJECT_INDEX_MASK

```
#define OS_OBJECT_INDEX_MASK 0xFFFF
```

Object index mask.

Definition at line 36 of file osapi-os-core.h.

12.6.1.6 OS_OBJECT_TYPE_SHIFT

```
#define OS_OBJECT_TYPE_SHIFT 16
```

Object type shift.

Definition at line 37 of file osapi-os-core.h.

12.6.2 Typedef Documentation

12.6.2.1 OS_ArgCallback_t

```
typedef void(* OS_ArgCallback_t) (uint32 object_id, void *arg)
```

General purpose OSAL callback function.

This may be used by multiple APIS

Definition at line 199 of file osapi-os-core.h.

12.6.2.2 `os_err_name_t`

```
typedef char os_err_name_t[OS_ERROR_NAME_LENGTH]
```

For the [OS_GetErrorName\(\)](#) function, to ensure everyone is making an array of the same length.

Implementation note for developers:

The sizes of strings in OSAL functions are built with this [OS_ERROR_NAME_LENGTH](#) limit in mind. Always check the uses of `os_err_name_t` when changing this value.

Definition at line 186 of file `osapi-os-core.h`.

12.6.2.3 `osal_task`

```
typedef void osal_task
```

For task entry point.

Definition at line 191 of file `osapi-os-core.h`.

12.6.3 Enumeration Type Documentation

12.6.3.1 `OS_StreamState_t`

```
enum OS_StreamState_t
```

For the [OS_SelectSingle\(\)](#) function's in/out `StateFlags` parameter, the state(s) of the stream and the result of the select is a combination of one or more of these states.

See also

[OS_SelectSingle\(\)](#)

Enumerator

<code>OS_STREAM_STATE_BOUND</code>	whether the stream is bound
<code>OS_STREAM_STATE_CONNECTED</code>	whether the stream is connected
<code>OS_STREAM_STATE_READABLE</code>	whether the stream is readable
<code>OS_STREAM_STATE_WRITABLE</code>	whether the stream is writable

Definition at line 168 of file `osapi-os-core.h`.

12.6.4 Function Documentation

12.6.4.1 OS_BSP_GetArgC()

```
uint32 OS_BSP_GetArgC (
    void )
```

12.6.4.2 OS_BSP_GetArgV()

```
char* const* OS_BSP_GetArgV (
    void )
```

12.6.4.3 OS_BSP_SetExitCode()

```
void OS_BSP_SetExitCode (
    int32 code )
```

12.6.4.4 OS_ForEachObjectOfType()

```
void OS_ForEachObjectOfType (
    uint32 objtype,
    uint32 creator_id,
    OS_ArgCallback_t callback_ptr,
    void * callback_arg )
```

call the supplied callback function for valid object IDs of a specific type

Loops through all defined OSAL objects of a specific type and calls callback_ptr on each one. If creator_id is nonzero then only objects with matching creator id are processed.

Parameters

in	<i>objtype</i>	The type of objects to iterate
in	<i>creator_id</i>	Filter objects to those created by a specific task. This may be passed as OS_OBJECT_CREATOR_ANY to return all objects.
in	<i>callback_ptr</i>	Function to invoke for each matching object ID.
in	<i>callback_arg</i>	Opaque Argument to pass to callback function.

12.6.4.5 osal_task()

```
typedef osal_task (
    (*) (void) osal_task_entry )
```

For task entry point.

12.7 osal/src/os/inc/osapi-os-filesys.h File Reference

Data Structures

- struct [OS_VolumeInfo_t](#)
Internal structure of the OS volume table for mounted file systems and path translation.
- struct [os_fsinfo_t](#)
OSAL file system info.
- struct [OS_file_prop_t](#)
OSAL file properties.
- struct [os_fstat_t](#)
File system status.
- struct [os_dirent_t](#)
Directory entry.

Macros

- `#define OS_READ_ONLY 0`
- `#define OS_WRITE_ONLY 1`
- `#define OS_READ_WRITE 2`
- `#define OS_SEEK_SET 0`
- `#define OS_SEEK_CUR 1`
- `#define OS_SEEK_END 2`
- `#define OS_CHK_ONLY 0`
- `#define OS_REPAIR 1`
- `#define FS_BASED 0`
- `#define RAM_DISK 1`
- `#define EEPROM_DISK 2`
- `#define ATA_DISK 3`
- `#define NUM_FILE_SYSTEMS OS_MAX_FILE_SYSTEMS`
Number of entries in the internal volume table.
- `#define OS_FS_DEV_NAME_LEN 32`
- `#define OS_FS_PHYS_NAME_LEN 64`
- `#define OS_FS_VOL_NAME_LEN 32`
- `#define OS_MAX_LOCAL_PATH_LEN (OS_MAX_PATH_LEN + OS_FS_PHYS_NAME_LEN)`
Maximum length of a local/native path name string.
- `#define OS_FS_ERR_PATH_TOO_LONG (-103)`
FS path too long.
- `#define OS_FS_ERR_NAME_TOO_LONG (-104)`
FS name too long.

- #define `OS_FS_ERR_DRIVE_NOT_CREATED` (-106)
FS drive not created.
- #define `OS_FS_ERR_DEVICE_NOT_FREE` (-107)
FS device not free.
- #define `OS_FS_ERR_PATH_INVALID` (-108)
FS path invalid.
- #define `OS_FS_SUCCESS` `OS_SUCCESS`
- #define `OS_FS_ERROR` `OS_ERROR`
- #define `OS_FS_ERR_INVALID_POINTER` `OS_INVALID_POINTER`
- #define `OS_FS_ERR_NO_FREE_FDS` `OS_ERR_NO_FREE_IDS`
- #define `OS_FS_ERR_INVALID_FD` `OS_ERR_INVALID_ID`
- #define `OS_FS_UNIMPLEMENTED` `OS_ERR_NOT_IMPLEMENTED`
- #define `OS_FILESTAT_MODE`(x) ((x).FileModeBits)
Access file stat mode bits.
- #define `OS_FILESTAT_ISDIR`(x) ((x).FileModeBits & `OS_FILESTAT_MODE_DIR`)
File stat is directory logical.
- #define `OS_FILESTAT_EXEC`(x) ((x).FileModeBits & `OS_FILESTAT_MODE_EXEC`)
File stat is executable logical.
- #define `OS_FILESTAT_WRITE`(x) ((x).FileModeBits & `OS_FILESTAT_MODE_WRITE`)
File stat is write enabled logical.
- #define `OS_FILESTAT_READ`(x) ((x).FileModeBits & `OS_FILESTAT_MODE_READ`)
File stat is read enabled logical.
- #define `OS_FILESTAT_SIZE`(x) ((x).FileSize)
Access file stat size field.
- #define `OS_FILESTAT_TIME`(x) ((x).FileTime)
Access file stat time field.
- #define `OS_DIRENTRY_NAME`(x) ((x).FileName)
Access filename part of the dirent structure.

Typedefs

- typedef `os_err_name_t` `os_fs_err_name_t`
- typedef void * `os_dirp_t`
- typedef `int32` `os_fshealth_t`
- typedef `OS_file_prop_t` `OS_FDTableEntry`

Enumerations

- enum { `OS_FILESTAT_MODE_EXEC` = 0x00001, `OS_FILESTAT_MODE_WRITE` = 0x00002, `OS_FILESTAT_MODE_READ` = 0x00004, `OS_FILESTAT_MODE_DIR` = 0x10000 }
- File stat mode bits.*

Functions

- [int32 OS_creat](#) (const char *path, [int32](#) access)
Creates a file specified by path.
- [int32 OS_open](#) (const char *path, [int32](#) access, [uint32](#) mode)
Opens a file.
- [int32 OS_close](#) ([uint32](#) filedes)
Closes an open file handle.
- [int32 OS_read](#) ([uint32](#) filedes, void *buffer, [uint32](#) nbytes)
Read from a file handle.
- [int32 OS_write](#) ([uint32](#) filedes, const void *buffer, [uint32](#) nbytes)
Write to a file handle.
- [int32 OS_TimedRead](#) ([uint32](#) filedes, void *buffer, [uint32](#) nbytes, [int32](#) timeout)
File/Stream input read with a timeout.
- [int32 OS_TimedWrite](#) ([uint32](#) filedes, const void *buffer, [uint32](#) nbytes, [int32](#) timeout)
File/Stream output write with a timeout.
- [int32 OS_chmod](#) (const char *path, [uint32](#) access)
Changes the permissions of a file.
- [int32 OS_stat](#) (const char *path, [os_fstat_t](#) *filestats)
Obtain information about a file or directory.
- [int32 OS_lseek](#) ([uint32](#) filedes, [int32](#) offset, [uint32](#) whence)
Seeks to the specified position of an open file.
- [int32 OS_remove](#) (const char *path)
Removes a file from the file system.
- [int32 OS_rename](#) (const char *old_filename, const char *new_filename)
Renames a file.
- [int32 OS_cp](#) (const char *src, const char *dest)
Copies a single file from src to dest.
- [int32 OS_mv](#) (const char *src, const char *dest)
Move a single file from src to dest.
- [int32 OS_FDGetInfo](#) ([uint32](#) filedes, [OS_file_prop_t](#) *fd_prop)
Obtain information about an open file.
- [int32 OS_FileOpenCheck](#) (const char *Filename)
Checks to see if a file is open.
- [int32 OS_CloseAllFiles](#) (void)
Close all open files.
- [int32 OS_CloseFileByName](#) (const char *Filename)
Close a file by filename.
- [os_dirp_t OS_opendir](#) (const char *path)
Opens a directory for searching.
- [int32 OS_closedir](#) ([os_dirp_t](#) directory)
- void [OS_rewinddir](#) ([os_dirp_t](#) directory)
- [os_dirent_t](#) * [OS_readdir](#) ([os_dirp_t](#) directory)
- [int32 OS_DirectoryOpen](#) ([uint32](#) *dir_id, const char *path)
Opens a directory.
- [int32 OS_DirectoryClose](#) ([uint32](#) dir_id)
Closes an open directory.

- [int32 OS_DirectoryRewind](#) (uint32 dir_id)
Rewinds an open directory.
- [int32 OS_DirectoryRead](#) (uint32 dir_id, [os_dirent_t](#) *dirent)
Reads the next name in the directory.
- [int32 OS_mkdir](#) (const char *path, uint32 access)
Makes a new directory.
- [int32 OS_rmdir](#) (const char *path)
Removes a directory from the file system.
- [int32 OS_FileSysAddFixedMap](#) (uint32 *filesystem_id, const char *phys_path, const char *virt_path)
Create a fixed mapping between an existing directory and a virtual OSAL mount point.
- [int32 OS_mkfs](#) (char *address, const char *devname, const char *volname, uint32 blocksize, uint32 numblocks)
Makes a file system on the target.
- [int32 OS_mount](#) (const char *devname, const char *mountpoint)
Mounts a file system.
- [int32 OS_initfs](#) (char *address, const char *devname, const char *volname, uint32 blocksize, uint32 numblocks)
Initializes an existing file system.
- [int32 OS_rmfs](#) (const char *devname)
Removes a file system.
- [int32 OS_unmount](#) (const char *mountpoint)
Unmounts a mounted file system.
- [int32 OS_fsBlocksFree](#) (const char *name)
Obtain number of blocks free.
- [int32 OS_fsBytesFree](#) (const char *name, uint64 *bytes_free)
Obtains the number of free bytes in a volume.
- [int32 OS_chkfs](#) (const char *name, bool repair)
Checks the health of a file system and repairs it if necessary.
- [int32 OS_FS_GetPhysDriveName](#) (char *PhysDriveName, const char *MountPoint)
Obtains the physical drive name associated with a mount point.
- [int32 OS_TranslatePath](#) (const char *VirtualPath, char *LocalPath)
Translates a OSAL Virtual file system path to a host Local path.
- [int32 OS_GetFsInfo](#) ([os_fsinfo_t](#) *filesystem_info)
Returns information about the file system.
- [int32 OS_ShellOutputToFile](#) (const char *Cmd, uint32 filedes)
Executes the command and sends output to a file.

12.7.1 Macro Definition Documentation

12.7.1.1 NUM_FILE_SYSTEMS

```
#define NUM_FILE_SYSTEMS OS_MAX_FILE_SYSTEMS
```

Number of entries in the internal volume table.

Deprecated

Definition at line 67 of file osapi-os-filesystem.h.

12.7.1.2 OS_CHK_ONLY

```
#define OS_CHK_ONLY 0
```

Unused, API takes bool

Definition at line 49 of file osapi-os-filesys.h.

12.7.1.3 OS_DIRENTRY_NAME

```
#define OS_DIRENTRY_NAME(  
    x ) ((x).FileName)
```

Access filename part of the dirent structure.

Definition at line 234 of file osapi-os-filesys.h.

12.7.1.4 OS_FILESTAT_EXEC

```
#define OS_FILESTAT_EXEC(  
    x ) ((x).FileModeBits & OS_FILESTAT_MODE_EXEC)
```

File stat is executable logical.

Definition at line 208 of file osapi-os-filesys.h.

12.7.1.5 OS_FILESTAT_ISDIR

```
#define OS_FILESTAT_ISDIR(  
    x ) ((x).FileModeBits & OS_FILESTAT_MODE_DIR)
```

File stat is directory logical.

Definition at line 206 of file osapi-os-filesys.h.

12.7.1.6 OS_FILESTAT_MODE

```
#define OS_FILESTAT_MODE(  
    x ) ((x).FileModeBits)
```

Access file stat mode bits.

Definition at line 204 of file osapi-os-filesys.h.

12.7.1.7 OS_FILESTAT_READ

```
#define OS_FILESTAT_READ(  
    x ) ((x).FileModeBits & OS_FILESTAT_MODE_READ)
```

File stat is read enabled logical.

Definition at line 212 of file osapi-os-filesys.h.

12.7.1.8 OS_FILESTAT_SIZE

```
#define OS_FILESTAT_SIZE(  
    x ) ((x).FileSize)
```

Access file stat size field.

Definition at line 214 of file osapi-os-filesys.h.

12.7.1.9 OS_FILESTAT_TIME

```
#define OS_FILESTAT_TIME(  
    x ) ((x).FileTime)
```

Access file stat time field.

Definition at line 216 of file osapi-os-filesys.h.

12.7.1.10 OS_FILESTAT_WRITE

```
#define OS_FILESTAT_WRITE(  
    x ) ((x).FileModeBits & OS_FILESTAT_MODE_WRITE)
```

File stat is write enabled logical.

Definition at line 210 of file osapi-os-filesys.h.

12.7.1.11 OS_FS_DEV_NAME_LEN

```
#define OS_FS_DEV_NAME_LEN 32
```

Device name length

Definition at line 73 of file osapi-os-filesys.h.

12.7.1.12 OS_FS_PHYS_NAME_LEN

```
#define OS_FS_PHYS_NAME_LEN 64
```

Physical drive name length

Definition at line 74 of file osapi-os-filesys.h.

12.7.1.13 OS_FS_VOL_NAME_LEN

```
#define OS_FS_VOL_NAME_LEN 32
```

Volume name length

Definition at line 75 of file osapi-os-filesys.h.

12.7.1.14 OS_MAX_LOCAL_PATH_LEN

```
#define OS_MAX_LOCAL_PATH_LEN (OS_MAX_PATH_LEN + OS_FS_PHYS_NAME_LEN)
```

Maximum length of a local/native path name string.

This is a concatenation of the OSAL virtual path with the system mount point or device name

Definition at line 83 of file osapi-os-filesys.h.

12.7.1.15 OS_REPAIR

```
#define OS_REPAIR 1
```

Unused, API takes bool

Definition at line 50 of file osapi-os-filesys.h.

12.7.2 Typedef Documentation

12.7.2.1 os_dirp_t

```
typedef void* os_dirp_t
```

Deprecated

Definition at line 230 of file osapi-os-filesys.h.

12.7.2.2 OS_FDTableEntry

```
typedef OS_file_prop_t OS_FDTableEntry
```

Deprecated Use OS_file_prop_t

Definition at line 241 of file osapi-os-filesys.h.

12.7.2.3 os_fs_err_name_t

```
typedef os_err_name_t os_fs_err_name_t
```

Definition at line 130 of file osapi-os-filesys.h.

12.7.2.4 os_fshealth_t

```
typedef int32 os_fshealth_t
```

Deprecated type no longer used

Definition at line 240 of file osapi-os-filesys.h.

12.7.3 Enumeration Type Documentation

12.7.3.1 anonymous enum

```
anonymous enum
```

File stat mode bits.

We must also define replacements for the stat structure's mode bits. This is currently just a small subset since the OSAL just presents a very simplified view of the filesystem to the upper layers. And since not all OS'es are POSIX, the more POSIX-specific bits are not relevant anyway.

Enumerator

OS_FILESTAT_MODE_EXEC	
OS_FILESTAT_MODE_WRITE	
OS_FILESTAT_MODE_READ	
OS_FILESTAT_MODE_DIR	

Definition at line 195 of file osapi-os-filesys.h.

12.8 osal/src/os/inc/osapi-os-loader.h File Reference

Data Structures

- struct [OS_module_address_t](#)
OSAL module address properties.
- struct [OS_module_prop_t](#)
OSAL module properties.
- struct [OS_static_symbol_record_t](#)
Associates a single symbol name with a memory address.

Typedefs

- typedef [OS_module_prop_t](#) [OS_module_record_t](#)

Functions

- [int32 OS_SymbolLookup](#) ([cpuaddr](#) *symbol_address, const char *symbol_name)
Find the Address of a Symbol.
- [int32 OS_SymbolTableDump](#) (const char *filename, [uint32](#) size_limit)
Dumps the system symbol table to a file.
- [int32 OS_ModuleLoad](#) ([uint32](#) *module_id, const char *module_name, const char *filename)
Loads an object file.
- [int32 OS_ModuleUnload](#) ([uint32](#) module_id)
Unloads the module file.
- [int32 OS_ModuleInfo](#) ([uint32](#) module_id, [OS_module_prop_t](#) *module_info)
Obtain information about a module.

12.8.1 Typedef Documentation

12.8.1.1 OS_module_record_t

```
typedef OS_module_prop_t OS_module_record_t
```

Deprecated Use [OS_module_prop_t](#)

Definition at line 97 of file osapi-os-loader.h.

12.9 osal/src/os/inc/osapi-os-net.h File Reference

```
#include <osconfig.h>
```

Data Structures

- union [OS_SockAddrData_t](#)
Storage buffer for generic network address.
- struct [OS_SockAddr_t](#)
Encapsulates a generic network address.
- struct [OS_socket_prop_t](#)
Encapsulates socket properties.

Macros

- `#define` [OS_SOCKADDR_MAX_LEN](#) 28

Enumerations

- enum [OS_SocketDomain_t](#) { [OS_SocketDomain_INVALID](#), [OS_SocketDomain_INET](#), [OS_SocketDomain_INET6](#), [OS_SocketDomain_MAX](#) }
Socket domain.
- enum [OS_SocketType_t](#) { [OS_SocketType_INVALID](#), [OS_SocketType_DATAGRAM](#), [OS_SocketType_STREAM](#), [OS_SocketType_MAX](#) }
Socket type.

Functions

- `int32 OS_SocketAddrInit (OS_SockAddr_t *Addr, OS_SocketDomain_t Domain)`
Initialize a socket address structure to hold an address of the given family.
- `int32 OS_SocketAddrToString (char *buffer, uint32 buflen, const OS_SockAddr_t *Addr)`
Get a string representation of a network host address.
- `int32 OS_SocketAddrFromString (OS_SockAddr_t *Addr, const char *string)`
Set a network host address from a string representation.
- `int32 OS_SocketAddrGetPort (uint16 *PortNum, const OS_SockAddr_t *Addr)`
Get the port number of a network address.
- `int32 OS_SocketAddrSetPort (OS_SockAddr_t *Addr, uint16 PortNum)`
Set the port number of a network address.
- `int32 OS_SocketOpen (uint32 *sock_id, OS_SocketDomain_t Domain, OS_SocketType_t Type)`
Opens a socket.
- `int32 OS_SocketBind (uint32 sock_id, const OS_SockAddr_t *Addr)`
Binds a socket to a given local address.
- `int32 OS_SocketConnect (uint32 sock_id, const OS_SockAddr_t *Addr, int32 timeout)`
Connects a socket to a given remote address.
- `int32 OS_SocketAccept (uint32 sock_id, uint32 *connsock_id, OS_SockAddr_t *Addr, int32 timeout)`
Waits for and accept the next incoming connection on the given socket.
- `int32 OS_SocketRecvFrom (uint32 sock_id, void *buffer, uint32 buflen, OS_SockAddr_t *RemoteAddr, int32 timeout)`
Reads data from a message-oriented (datagram) socket.
- `int32 OS_SocketSendTo (uint32 sock_id, const void *buffer, uint32 buflen, const OS_SockAddr_t *RemoteAddr)`
Sends data to a message-oriented (datagram) socket.
- `int32 OS_SocketGetIdByName (uint32 *sock_id, const char *sock_name)`
Gets an OSAL ID from a given name.
- `int32 OS_SocketGetInfo (uint32 sock_id, OS_socket_prop_t *sock_prop)`
Gets information about an OSAL Socket ID.
- `int32 OS_NetworkGetID (void)`
Gets the network ID of the local machine.
- `int32 OS_NetworkGetHostName (char *host_name, uint32 name_len)`
Gets the local machine network host name.

12.9.1 Macro Definition Documentation

12.9.1.1 OS_SOCKADDR_MAX_LEN

```
#define OS_SOCKADDR_MAX_LEN 28
```

Definition at line 49 of file `osapi-os-net.h`.

12.9.2 Enumeration Type Documentation

12.9.2.1 OS_SocketDomain_t

```
enum OS_SocketDomain_t
```

Socket domain.

Enumerator

OS_SocketDomain_INVALID	Invalid.
OS_SocketDomain_INET	IPv4 address family, most commonly used)
OS_SocketDomain_INET6	IPv6 address family, depends on OS/network stack support.
OS_SocketDomain_MAX	Maximum.

Definition at line 65 of file osapi-os-net.h.

12.9.2.2 OS_SocketType_t

```
enum OS_SocketType_t
```

Socket type.

Enumerator

OS_SocketType_INVALID	Invalid.
OS_SocketType_DATAGRAM	A connectionless, message-oriented socket.
OS_SocketType_STREAM	A stream-oriented socket with the concept of a connection.
OS_SocketType_MAX	Maximum.

Definition at line 74 of file osapi-os-net.h.

12.10 osal/src/os/inc/osapi-os-timer.h File Reference**Data Structures**

- struct [OS_timer_prop_t](#)
Timer properties.
- struct [OS_timebase_prop_t](#)
Time base properties.

Typedefs

- typedef void(* [OS_TimerCallback_t](#)) (uint32 timer_id)
Timer callback.
- typedef uint32(* [OS_TimerSync_t](#)) (uint32 timer_id)
Timer sync.

Functions

- `int32 OS_TimeBaseCreate (uint32 *timebase_id, const char *timebase_name, OS_TimerSync_t external_sync)`
Create an abstract Time Base resource.
- `int32 OS_TimeBaseSet (uint32 timebase_id, uint32 start_time, uint32 interval_time)`
Sets the tick period for simulated time base objects.
- `int32 OS_TimeBaseDelete (uint32 timebase_id)`
Deletes a time base object.
- `int32 OS_TimeBaseGetIdByName (uint32 *timebase_id, const char *timebase_name)`
Find the ID of an existing time base resource.
- `int32 OS_TimeBaseGetInfo (uint32 timebase_id, OS_timebase_prop_t *timebase_prop)`
Obtain information about a timebase resource.
- `int32 OS_TimeBaseGetFreeRun (uint32 timebase_id, uint32 *freerun_val)`
Read the value of the timebase free run counter.
- `int32 OS_TimerCreate (uint32 *timer_id, const char *timer_name, uint32 *clock_accuracy, OS_TimerCallback_t callback_ptr)`
Create a timer object.
- `int32 OS_TimerAdd (uint32 *timer_id, const char *timer_name, uint32 timebase_id, OS_ArgCallback_t callback_ptr, void *callback_arg)`
Add a timer object based on an existing TimeBase resource.
- `int32 OS_TimerSet (uint32 timer_id, uint32 start_time, uint32 interval_time)`
Configures a periodic or one shot timer.
- `int32 OS_TimerDelete (uint32 timer_id)`
Deletes a timer resource.
- `int32 OS_TimerGetIdByName (uint32 *timer_id, const char *timer_name)`
Locate an existing timer resource by name.
- `int32 OS_TimerGetInfo (uint32 timer_id, OS_timer_prop_t *timer_prop)`
Gets information about an existing timer.

12.10.1 Typedef Documentation

12.10.1.1 OS_TimerCallback_t

```
typedef void(* OS_TimerCallback_t) (uint32 timer_id)
```

Timer callback.

Definition at line 36 of file osapi-os-timer.h.

12.10.1.2 OS_TimerSync_t

```
typedef uint32(* OS_TimerSync_t) (uint32 timer_id)
```

Timer sync.

Definition at line 37 of file osapi-os-timer.h.

12.11 osal/src/os/inc/osapi-version.h File Reference

Macros

- `#define OS_MAJOR_VERSION 5`
Major version number.
- `#define OS_MINOR_VERSION 0`
Minor version number.
- `#define OS_REVISION 21`
Revision number.
- `#define OS_MISSION_REV 0`
Mission revision.
- `#define OSAL_API_VERSION ((OS_MAJOR_VERSION * 10000) + (OS_MINOR_VERSION * 100) + OS_REVISION)`

12.11.1 Macro Definition Documentation

12.11.1.1 OS_MAJOR_VERSION

```
#define OS_MAJOR_VERSION 5
```

Major version number.

Definition at line 31 of file osapi-version.h.

12.11.1.2 OS_MINOR_VERSION

```
#define OS_MINOR_VERSION 0
```

Minor version number.

Definition at line 32 of file osapi-version.h.

12.11.1.3 OS_MISSION_REV

```
#define OS_MISSION_REV 0
```

Mission revision.

Definition at line 34 of file osapi-version.h.

12.11.1.4 OS_REVISION

```
#define OS_REVISION 21
```

Revision number.

Definition at line 33 of file osapi-version.h.

12.11.1.5 OSAL_API_VERSION

```
#define OSAL_API_VERSION ((OS_MAJOR_VERSION * 10000) + (OS_MINOR_VERSION * 100) + OS_REVISION)
```

Combine the revision components into a single value that application code can check against e.g. "#if OSAL_API_VERSION >= 40100" would check if some feature added in OSAL 4.1 is present.

Definition at line 40 of file osapi-version.h.

12.12 osal/src/os/inc/osapi.h File Reference

```
#include <stdio.h>
#include <stdlib.h>
#include "common_types.h"
#include "osapi-version.h"
#include "osconfig.h"
#include "osapi-os-core.h"
#include "osapi-os-filesys.h"
#include "osapi-os-net.h"
#include "osapi-os-loader.h"
#include "osapi-os-timer.h"
```

Macros

- #define OS_SUCCESS (0)
Successful execution.
- #define OS_ERROR (-1)
Failed execution.
- #define OS_INVALID_POINTER (-2)
Invalid pointer.
- #define OS_ERROR_ADDRESS_MISALIGNED (-3)
Address misalignment.
- #define OS_ERROR_TIMEOUT (-4)
Error timeout.
- #define OS_INVALID_INT_NUM (-5)
Invalid Interrupt number.
- #define OS_SEM_FAILURE (-6)

- Semaphore failure.
- #define `OS_SEM_TIMEOUT` (-7)
- Semaphore timeout.
- #define `OS_QUEUE_EMPTY` (-8)
- Queue empty.
- #define `OS_QUEUE_FULL` (-9)
- Queue full.
- #define `OS_QUEUE_TIMEOUT` (-10)
- Queue timeout.
- #define `OS_QUEUE_INVALID_SIZE` (-11)
- Queue invalid size.
- #define `OS_QUEUE_ID_ERROR` (-12)
- Queue ID error.
- #define `OS_ERR_NAME_TOO_LONG` (-13)
- name length including null terminator greater than `OS_MAX_API_NAME`
- #define `OS_ERR_NO_FREE_IDS` (-14)
- No free IDs.
- #define `OS_ERR_NAME_TAKEN` (-15)
- Name taken.
- #define `OS_ERR_INVALID_ID` (-16)
- Invalid ID.
- #define `OS_ERR_NAME_NOT_FOUND` (-17)
- Name not found.
- #define `OS_ERR_SEM_NOT_FULL` (-18)
- Semaphore not full.
- #define `OS_ERR_INVALID_PRIORITY` (-19)
- Invalid priority.
- #define `OS_INVALID_SEM_VALUE` (-20)
- Invalid semaphore value.
- #define `OS_ERR_FILE` (-27)
- File error.
- #define `OS_ERR_NOT_IMPLEMENTED` (-28)
- Not implemented.
- #define `OS_TIMER_ERR_INVALID_ARGS` (-29)
- Timer invalid arguments.
- #define `OS_TIMER_ERR_TIMER_ID` (-30)
- Timer ID error.
- #define `OS_TIMER_ERR_UNAVAILABLE` (-31)
- Timer unavailable.
- #define `OS_TIMER_ERR_INTERNAL` (-32)
- Timer internal error.
- #define `OS_ERR_OBJECT_IN_USE` (-33)
- Object in use.
- #define `OS_ERR_BAD_ADDRESS` (-34)
- Bad address.
- #define `OS_ERR_INCORRECT_OBJ_STATE` (-35)
- Incorrect object state.

- `#define OS_ERR_INCORRECT_OBJ_TYPE` (-36)
Incorrect object type.
- `#define OS_ERR_STREAM_DISCONNECTED` (-37)
Stream disconnected.
- `#define OS_ERR_OPERATION_NOT_SUPPORTED` (-38)
Requested operation is not support on the supplied object(s)
- `#define OS_PEND` (-1)
- `#define OS_CHECK` (0)

12.12.1 Macro Definition Documentation

12.12.1.1 OS_CHECK

```
#define OS_CHECK (0)
```

Definition at line 98 of file osapi.h.

12.12.1.2 OS_PEND

```
#define OS_PEND (-1)
```

Definition at line 97 of file osapi.h.

Index

- [_EXTENSION_](#)
 - [common_types.h, 176](#)
- [ATA_DISK](#)
 - [OSAL Volume Type Defines, 74](#)
- [accuracy](#)
 - [OS_timebase_prop_t, 163](#)
 - [OS_timer_prop_t, 164](#)
- [ActualLength](#)
 - [OS_SockAddr_t, 156](#)
- [addr](#)
 - [OS_module_prop_t, 152](#)
- [AddrData](#)
 - [OS_SockAddr_t, 156](#)
- [Address](#)
 - [OS_static_symbol_record_t, 159](#)
- [AlignPtr](#)
 - [OS_SockAddrData_t, 157](#)
- [AlignU32](#)
 - [OS_SockAddrData_t, 157](#)
- [BlockSize](#)
 - [OS_VolumeInfo_t, 166](#)
- [boolean](#)
 - [common_types.h, 178](#)
- [bss_address](#)
 - [OS_module_address_t, 150](#)
- [bss_size](#)
 - [OS_module_address_t, 151](#)
- [Buffer](#)
 - [OS_SockAddrData_t, 157](#)
- [build/doc/osconfig-example.h, 167](#)
- [cfe/docs/src/osal_fs.dox, 175](#)
- [cfe/docs/src/osal_timer.dox, 175](#)
- [cfe/docs/src/osalmain.dox, 175](#)
- [code_address](#)
 - [OS_module_address_t, 151](#)
- [code_size](#)
 - [OS_module_address_t, 151](#)
- [common_types.h](#)
 - [_EXTENSION_, 176](#)
 - [boolean, 178](#)
 - [CompileTimeAssert, 177, 181, 182](#)
 - [cpuaddr, 178](#)
 - [cpudiff, 178](#)
 - [cpusize, 179](#)
 - [FALSE, 177](#)
 - [int16, 179](#)
 - [int32, 179](#)
 - [int64, 179](#)
 - [int8, 179](#)
 - [intptr, 179](#)
 - [NULL, 177](#)
 - [OS_ALIGN, 177](#)
 - [OS_PACK, 177](#)
 - [OS_PRINTF, 177](#)
 - [OS_USED, 178](#)
 - [osalbool, 180](#)
 - [TRUE, 178](#)
 - [uint16, 180](#)
 - [uint32, 180](#)
 - [uint64, 180](#)
 - [uint8, 180](#)
- [CompileTimeAssert](#)
 - [common_types.h, 177, 181, 182](#)
- [cpuaddr](#)
 - [common_types.h, 178](#)
- [cpudiff](#)
 - [common_types.h, 178](#)
- [cpusize](#)
 - [common_types.h, 179](#)
- [creator](#)
 - [OS_bin_sem_prop_t, 142](#)
 - [OS_count_sem_prop_t, 143](#)
 - [OS_mut_sem_prop_t, 154](#)
 - [OS_queue_prop_t, 155](#)
 - [OS_socket_prop_t, 158](#)
 - [OS_task_prop_t, 160](#)
 - [OS_timebase_prop_t, 163](#)
 - [OS_timer_prop_t, 164](#)
- [data_address](#)
 - [OS_module_address_t, 151](#)
- [data_size](#)
 - [OS_module_address_t, 151](#)
- [DeviceName](#)
 - [OS_VolumeInfo_t, 166](#)
- [EEPROM_DISK](#)
 - [OSAL Volume Type Defines, 74](#)
- [entry_point](#)
 - [OS_module_prop_t, 153](#)
- [FALSE](#)
 - [common_types.h, 177](#)
- [FS_BASED](#)
 - [OSAL Volume Type Defines, 74](#)
- [FileModeBits](#)
 - [os_fstat_t, 148](#)
- [FileName](#)
 - [os_dirent_t, 144](#)
- [FileSize](#)
 - [os_fstat_t, 148](#)

- FileTime
 - os_fstat_t, [148](#)
- filename
 - OS_module_prop_t, [153](#)
- flags
 - OS_module_address_t, [151](#)
- free_blocks
 - OS_heap_prop_t, [149](#)
- free_bytes
 - OS_heap_prop_t, [149](#)
- FreeFds
 - os_fsinfo_t, [147](#)
- FreeFlag
 - OS_VolumeInfo_t, [166](#)
- FreeVolumes
 - os_fsinfo_t, [147](#)
- freerun_time
 - OS_timebase_prop_t, [163](#)
- host_module_id
 - OS_module_prop_t, [153](#)
- int16
 - common_types.h, [179](#)
- int32
 - common_types.h, [179](#)
- int64
 - common_types.h, [179](#)
- int8
 - common_types.h, [179](#)
- interval_time
 - OS_timer_prop_t, [164](#)
- intptr
 - common_types.h, [179](#)
- IsMounted
 - OS_VolumeInfo_t, [166](#)
- IsValid
 - OS_file_prop_t, [146](#)
- largest_free_block
 - OS_heap_prop_t, [150](#)
- MaxFds
 - os_fsinfo_t, [147](#)
- MaxVolumes
 - os_fsinfo_t, [147](#)
- microsecs
 - OS_time_t, [162](#)
- Module
 - OS_static_symbol_record_t, [159](#)
- MountPoint
 - OS_VolumeInfo_t, [166](#)
- NULL
 - common_types.h, [177](#)
- NUM_FILE_SYSTEMS
 - osapi-os-filesys.h, [195](#)
- Name
 - OS_static_symbol_record_t, [159](#)
- name
 - OS_bin_sem_prop_t, [142](#)
 - OS_count_sem_prop_t, [143](#)
 - OS_module_prop_t, [153](#)
 - OS_mut_sem_prop_t, [154](#)
 - OS_queue_prop_t, [155](#)
 - OS_socket_prop_t, [158](#)
 - OS_task_prop_t, [160](#)
 - OS_timebase_prop_t, [163](#)
 - OS_timer_prop_t, [164](#)
- nominal_interval_time
 - OS_timebase_prop_t, [163](#)
- OS_ALIGN
 - common_types.h, [177](#)
- OS_API_Init
 - OSAL Core Operation APIs, [15](#)
- OS_Application_Run
 - OSAL Core Operation APIs, [16](#)
- OS_Application_Startup
 - OSAL Core Operation APIs, [16](#)
- OS_ApplicationExit
 - OSAL Core Operation APIs, [16](#)
- OS_ApplicationShutdown
 - OSAL Core Operation APIs, [16](#)
- OS_ArgCallback_t
 - osapi-os-core.h, [189](#)
- OS_BSP_GetArgC
 - osapi-os-core.h, [191](#)
- OS_BSP_GetArgV
 - osapi-os-core.h, [191](#)
- OS_BSP_SetExitCode
 - osapi-os-core.h, [191](#)
- OS_BUFFER_MSG_DEPTH
 - osconfig-example.h, [168](#)
- OS_BUFFER_SIZE
 - osconfig-example.h, [169](#)
- OS_BinSemCreate
 - OSAL Semaphore APIs, [34](#)
- OS_BinSemDelete
 - OSAL Semaphore APIs, [34](#)
- OS_BinSemFlush
 - OSAL Semaphore APIs, [36](#)
- OS_BinSemGetIdByName
 - OSAL Semaphore APIs, [36](#)
- OS_BinSemGetInfo
 - OSAL Semaphore APIs, [37](#)
- OS_BinSemGive
 - OSAL Semaphore APIs, [38](#)
- OS_BinSemTake

- OSAL Semaphore APIs, 38
- OS_BinSemTimedWait
 - OSAL Semaphore APIs, 39
- OS_CHECK
 - osapi.h, 208
- OS_CHK_ONLY
 - osapi-os-filesys.h, 195
- OS_CloseAllFiles
 - OSAL Standard File APIs, 77
- OS_CloseFileByName
 - OSAL Standard File APIs, 77
- OS_ConvertToArrayIndex
 - OSAL Object Utility APIs, 18
- OS_CountSemCreate
 - OSAL Semaphore APIs, 40
- OS_CountSemDelete
 - OSAL Semaphore APIs, 40
- OS_CountSemGetIdByName
 - OSAL Semaphore APIs, 41
- OS_CountSemGetInfo
 - OSAL Semaphore APIs, 41
- OS_CountSemGive
 - OSAL Semaphore APIs, 42
- OS_CountSemTake
 - OSAL Semaphore APIs, 43
- OS_CountSemTimedWait
 - OSAL Semaphore APIs, 43
- OS_DIRENTRY_NAME
 - osapi-os-filesys.h, 196
- OS_DeleteAllObjects
 - OSAL Core Operation APIs, 17
- OS_DirectoryClose
 - OSAL Directory APIs, 89
- OS_DirectoryOpen
 - OSAL Directory APIs, 90
- OS_DirectoryRead
 - OSAL Directory APIs, 90
- OS_DirectoryRewind
 - OSAL Directory APIs, 91
- OS_ERR_BAD_ADDRESS
 - OSAL Return Code Defines, 132
- OS_ERR_FILE
 - OSAL Return Code Defines, 133
- OS_ERR_INCORRECT_OBJ_STATE
 - OSAL Return Code Defines, 133
- OS_ERR_INCORRECT_OBJ_TYPE
 - OSAL Return Code Defines, 133
- OS_ERR_INVALID_ID
 - OSAL Return Code Defines, 133
- OS_ERR_INVALID_PRIORITY
 - OSAL Return Code Defines, 133
- OS_ERR_NAME_NOT_FOUND
 - OSAL Return Code Defines, 134
- OS_ERR_NAME_TAKEN
 - OSAL Return Code Defines, 134
- OS_ERR_NAME_TOO_LONG
 - OSAL Return Code Defines, 134
- OS_ERR_NO_FREE_IDS
 - OSAL Return Code Defines, 134
- OS_ERR_NOT_IMPLEMENTED
 - OSAL Return Code Defines, 134
- OS_ERR_OBJECT_IN_USE
 - OSAL Return Code Defines, 135
- OS_ERR_OPERATION_NOT_SUPPORTED
 - OSAL Return Code Defines, 135
- OS_ERR_SEM_NOT_FULL
 - OSAL Return Code Defines, 135
- OS_ERR_STREAM_DISCONNECTED
 - OSAL Return Code Defines, 135
- OS_ERROR_ADDRESS_MISALIGNED
 - OSAL Return Code Defines, 136
- OS_ERROR_NAME_LENGTH
 - osapi-os-core.h, 188
- OS_ERROR_TIMEOUT
 - OSAL Return Code Defines, 136
- OS_ERROR
 - OSAL Return Code Defines, 135
- OS_ExcAttachHandler
 - OSAL Exception APIs, 52
- OS_ExcDisable
 - OSAL Exception APIs, 52
- OS_ExcEnable
 - OSAL Exception APIs, 52
- OS_FDGetInfo
 - OSAL Standard File APIs, 79
- OS_FDTableEntry
 - osapi-os-filesys.h, 199
- OS_FILESTAT_EXEC
 - osapi-os-filesys.h, 196
- OS_FILESTAT_ISDIR
 - osapi-os-filesys.h, 196
- OS_FILESTAT_MODE
 - osapi-os-filesys.h, 196
- OS_FILESTAT_READ
 - osapi-os-filesys.h, 196
- OS_FILESTAT_SIZE
 - osapi-os-filesys.h, 197
- OS_FILESTAT_TIME
 - osapi-os-filesys.h, 197
- OS_FILESTAT_WRITE
 - osapi-os-filesys.h, 197
- OS_FP_ENABLED
 - osapi-os-core.h, 188
- OS_FPUExcAttachHandler
 - OSAL Floating Point Unit Exception APIs, 53
- OS_FPUExcDisable
 - OSAL Floating Point Unit Exception APIs, 54
- OS_FPUExcEnable

- OSAL Floating Point Unit Exception APIs, [54](#)
- OS_FPUExcGetMask
 - OSAL Floating Point Unit Exception APIs, [55](#)
- OS_FPUExcSetMask
 - OSAL Floating Point Unit Exception APIs, [55](#)
- OS_FS_DEV_NAME_LEN
 - osapi-os-filesys.h, [197](#)
- OS_FS_ERR_DEVICE_NOT_FREE
 - OSAL Return Code Defines, [136](#)
- OS_FS_ERR_DRIVE_NOT_CREATED
 - OSAL Return Code Defines, [136](#)
- OS_FS_ERR_INVALID_FD
 - OSAL Return Code Defines, [136](#)
- OS_FS_ERR_INVALID_POINTER
 - OSAL Return Code Defines, [137](#)
- OS_FS_ERR_NAME_TOO_LONG
 - OSAL Return Code Defines, [137](#)
- OS_FS_ERR_NO_FREE_FDS
 - OSAL Return Code Defines, [137](#)
- OS_FS_ERR_PATH_INVALID
 - OSAL Return Code Defines, [137](#)
- OS_FS_ERR_PATH_TOO_LONG
 - OSAL Return Code Defines, [137](#)
- OS_FS_ERROR
 - OSAL Return Code Defines, [138](#)
- OS_FS_GetPhysDriveName
 - OSAL File System Level APIs, [95](#)
- OS_FS_PHYS_NAME_LEN
 - osapi-os-filesys.h, [197](#)
- OS_FS_SUCCESS
 - OSAL Return Code Defines, [138](#)
- OS_FS_UNIMPLEMENTED
 - OSAL Return Code Defines, [138](#)
- OS_FS_VOL_NAME_LEN
 - osapi-os-filesys.h, [198](#)
- OS_FdSet, [144](#)
 - object_ids, [145](#)
- OS_FileOpenCheck
 - OSAL Standard File APIs, [79](#)
- OS_FileSysAddFixedMap
 - OSAL File System Level APIs, [95](#)
- OS_ForEachObject
 - OSAL Object Utility APIs, [19](#)
- OS_ForEachObjectOfType
 - osapi-os-core.h, [191](#)
- OS_GetErrorName
 - OSAL Error Info APIs, [66](#)
- OS_GetFsInfo
 - OSAL File System Level APIs, [97](#)
- OS_GetLocalTime
 - OSAL Time/Tick APIs, [49](#)
- OS_GetResourceName
 - OSAL Object Utility APIs, [19](#)
- OS_HeapGetInfo
 - OSAL Heap APIs, [65](#)
- OS_INVALID_INT_NUM
 - OSAL Return Code Defines, [138](#)
- OS_INVALID_POINTER
 - OSAL Return Code Defines, [138](#)
- OS_INVALID_SEM_VALUE
 - OSAL Return Code Defines, [139](#)
- OS_IdentifyObject
 - OSAL Object Utility APIs, [19](#)
- OS_IdleLoop
 - OSAL Core Operation APIs, [17](#)
- OS_IntAck
 - OSAL Interrupt APIs, [57](#)
- OS_IntAttachHandler
 - OSAL Interrupt APIs, [58](#)
- OS_IntDisable
 - OSAL Interrupt APIs, [59](#)
- OS_IntEnable
 - OSAL Interrupt APIs, [59](#)
- OS_IntGetMask
 - OSAL Interrupt APIs, [60](#)
- OS_IntLock
 - OSAL Interrupt APIs, [60](#)
- OS_IntSetMask
 - OSAL Interrupt APIs, [61](#)
- OS_IntUnlock
 - OSAL Interrupt APIs, [61](#)
- OS_MAJOR_VERSION
 - osapi-version.h, [205](#)
- OS_MAX_API_NAME
 - osconfig-example.h, [169](#)
- OS_MAX_BIN_SEMAPHORES
 - osconfig-example.h, [169](#)
- OS_MAX_CMD_LEN
 - osconfig-example.h, [169](#)
- OS_MAX_CONSOLES
 - osconfig-example.h, [170](#)
- OS_MAX_COUNT_SEMAPHORES
 - osconfig-example.h, [170](#)
- OS_MAX_FILE_NAME
 - osconfig-example.h, [170](#)
- OS_MAX_FILE_SYSTEMS
 - osconfig-example.h, [170](#)
- OS_MAX_LOCAL_PATH_LEN
 - osapi-os-filesys.h, [198](#)
- OS_MAX_MODULES
 - osconfig-example.h, [171](#)
- OS_MAX_MUTEXES
 - osconfig-example.h, [171](#)
- OS_MAX_NUM_OPEN_DIRS
 - osconfig-example.h, [171](#)
- OS_MAX_NUM_OPEN_FILES
 - osconfig-example.h, [171](#)
- OS_MAX_PATH_LEN

- osconfig-example.h, [172](#)
- OS_MAX_QUEUES
 - osconfig-example.h, [172](#)
- OS_MAX_SYM_LEN
 - osconfig-example.h, [172](#)
- OS_MAX_TASK_PRIORITY
 - osapi-os-core.h, [188](#)
- OS_MAX_TASKS
 - osconfig-example.h, [172](#)
- OS_MAX_TIMEBASES
 - osconfig-example.h, [173](#)
- OS_MAX_TIMERS
 - osconfig-example.h, [173](#)
- OS_MINOR_VERSION
 - osapi-version.h, [205](#)
- OS_MISSION_REV
 - osapi-version.h, [205](#)
- OS_MODULE_FILE_EXTENSION
 - osconfig-example.h, [173](#)
- OS_Milli2Ticks
 - OSAL Time/Tick APIs, [49](#)
- OS_ModuleInfo
 - OSAL Dynamic Loader and Symbol APIs, [104](#)
- OS_ModuleLoad
 - OSAL Dynamic Loader and Symbol APIs, [105](#)
- OS_ModuleUnload
 - OSAL Dynamic Loader and Symbol APIs, [105](#)
- OS_MutSemCreate
 - OSAL Semaphore APIs, [44](#)
- OS_MutSemDelete
 - OSAL Semaphore APIs, [45](#)
- OS_MutSemGetIdByName
 - OSAL Semaphore APIs, [45](#)
- OS_MutSemGetInfo
 - OSAL Semaphore APIs, [46](#)
- OS_MutSemGive
 - OSAL Semaphore APIs, [46](#)
- OS_MutSemTake
 - OSAL Semaphore APIs, [48](#)
- OS_NetworkGetHostName
 - OSAL Socket Management APIs, [113](#)
- OS_NetworkGetID
 - OSAL Socket Management APIs, [114](#)
- OS_OBJECT_CREATOR_ANY
 - osapi-os-core.h, [188](#)
- OS_OBJECT_INDEX_MASK
 - osapi-os-core.h, [189](#)
- OS_OBJECT_TYPE_OS_BINSEM
 - OSAL Object Type Defines, [11](#)
- OS_OBJECT_TYPE_OS_CONSOLE
 - OSAL Object Type Defines, [11](#)
- OS_OBJECT_TYPE_OS_COUNTSEM
 - OSAL Object Type Defines, [11](#)
- OS_OBJECT_TYPE_OS_DIR
 - OSAL Object Type Defines, [11](#)
- OS_OBJECT_TYPE_OS_FILESYS
 - OSAL Object Type Defines, [12](#)
- OS_OBJECT_TYPE_OS_MODULE
 - OSAL Object Type Defines, [12](#)
- OS_OBJECT_TYPE_OS_MUTEX
 - OSAL Object Type Defines, [12](#)
- OS_OBJECT_TYPE_OS_QUEUE
 - OSAL Object Type Defines, [12](#)
- OS_OBJECT_TYPE_OS_STREAM
 - OSAL Object Type Defines, [12](#)
- OS_OBJECT_TYPE_OS_TASK
 - OSAL Object Type Defines, [13](#)
- OS_OBJECT_TYPE_OS_TIMEBASE
 - OSAL Object Type Defines, [13](#)
- OS_OBJECT_TYPE_OS_TIMECB
 - OSAL Object Type Defines, [13](#)
- OS_OBJECT_TYPE_SHIFT
 - osapi-os-core.h, [189](#)
- OS_OBJECT_TYPE_UNDEFINED
 - OSAL Object Type Defines, [13](#)
- OS_OBJECT_TYPE_USER
 - OSAL Object Type Defines, [13](#)
- OS_PACK
 - common_types.h, [177](#)
- OS_PEND
 - osapi.h, [208](#)
- OS_PRINTF_CONSOLE_NAME
 - osconfig-example.h, [174](#)
- OS_PRINTF
 - common_types.h, [177](#)
- OS_QUEUE_EMPTY
 - OSAL Return Code Defines, [139](#)
- OS_QUEUE_FULL
 - OSAL Return Code Defines, [139](#)
- OS_QUEUE_ID_ERROR
 - OSAL Return Code Defines, [139](#)
- OS_QUEUE_INVALID_SIZE
 - OSAL Return Code Defines, [139](#)
- OS_QUEUE_MAX_DEPTH
 - osconfig-example.h, [174](#)
- OS_QUEUE_TIMEOUT
 - OSAL Return Code Defines, [140](#)
- OS_QueueCreate
 - OSAL Message Queue APIs, [28](#)
- OS_QueueDelete
 - OSAL Message Queue APIs, [29](#)
- OS_QueueGet
 - OSAL Message Queue APIs, [30](#)
- OS_QueueGetIdByName
 - OSAL Message Queue APIs, [30](#)
- OS_QueueGetInfo
 - OSAL Message Queue APIs, [31](#)
- OS_QueuePut

- OSAL Message Queue APIs, [31](#)
- OS_READ_ONLY
 - OSAL File Access Option Defines, [72](#)
- OS_READ_WRITE
 - OSAL File Access Option Defines, [72](#)
- OS_REPAIR
 - osapi-os-filesys.h, [198](#)
- OS_REVISION
 - osapi-version.h, [205](#)
- OS_SEEK_CUR
 - OSAL Reference Point For Seek Offset Defines, [73](#)
- OS_SEEK_END
 - OSAL Reference Point For Seek Offset Defines, [73](#)
- OS_SEEK_SET
 - OSAL Reference Point For Seek Offset Defines, [73](#)
- OS_SEM_EMPTY
 - OSAL Semaphore State Defines, [14](#)
- OS_SEM_FAILURE
 - OSAL Return Code Defines, [140](#)
- OS_SEM_FULL
 - OSAL Semaphore State Defines, [14](#)
- OS_SEM_TIMEOUT
 - OSAL Return Code Defines, [140](#)
- OS_SHELL_CMD_INPUT_FILE_NAME
 - osconfig-example.h, [174](#)
- OS_SOCKADDR_MAX_LEN
 - osapi-os-net.h, [202](#)
 - osconfig-example.h, [174](#)
- OS_SUCCESS
 - OSAL Return Code Defines, [140](#)
- OS_SelectFdAdd
 - OSAL Select APIs, [67](#)
- OS_SelectFdClear
 - OSAL Select APIs, [67](#)
- OS_SelectFdsSet
 - OSAL Select APIs, [67](#)
- OS_SelectFdZero
 - OSAL Select APIs, [68](#)
- OS_SelectMultiple
 - OSAL Select APIs, [68](#)
- OS_SelectSingle
 - OSAL Select APIs, [69](#)
- OS_SetLocalTime
 - OSAL Time/Tick APIs, [50](#)
- OS_ShMemAttach
 - OSAL Shared memory APIs, [63](#)
- OS_ShMemCreate
 - OSAL Shared memory APIs, [63](#)
- OS_ShMemGetIdByName
 - OSAL Shared memory APIs, [63](#)
- OS_ShMemInit
 - OSAL Shared memory APIs, [64](#)
- OS_ShMemSemGive
 - OSAL Shared memory APIs, [64](#)
- OS_ShMemSemTake
 - OSAL Shared memory APIs, [64](#)
- OS_ShellOutputToFile
 - OSAL Shell APIs, [103](#)
- OS_SockAddr_t, [155](#)
 - ActualLength, [156](#)
 - AddrData, [156](#)
- OS_SockAddrData_t, [156](#)
 - AlignPtr, [157](#)
 - AlignU32, [157](#)
 - Buffer, [157](#)
- OS_SocketAccept
 - OSAL Socket Management APIs, [114](#)
- OS_SocketAddrFromString
 - OSAL Socket Address APIs, [109](#)
- OS_SocketAddrGetPort
 - OSAL Socket Address APIs, [110](#)
- OS_SocketAddrInit
 - OSAL Socket Address APIs, [110](#)
- OS_SocketAddrSetPort
 - OSAL Socket Address APIs, [111](#)
- OS_SocketAddrToString
 - OSAL Socket Address APIs, [111](#)
- OS_SocketBind
 - OSAL Socket Management APIs, [115](#)
- OS_SocketConnect
 - OSAL Socket Management APIs, [115](#)
- OS_SocketDomain_t
 - osapi-os-net.h, [202](#)
- OS_SocketGetIdByName
 - OSAL Socket Management APIs, [117](#)
- OS_SocketGetInfo
 - OSAL Socket Management APIs, [118](#)
- OS_SocketOpen
 - OSAL Socket Management APIs, [118](#)
- OS_SocketRecvFrom
 - OSAL Socket Management APIs, [119](#)
- OS_SocketSendTo
 - OSAL Socket Management APIs, [119](#)
- OS_SocketType_t
 - osapi-os-net.h, [203](#)
- OS_StreamState_t
 - osapi-os-core.h, [190](#)
- OS_SymbolLookup
 - OSAL Dynamic Loader and Symbol APIs, [106](#)
- OS_SymbolTableDump
 - OSAL Dynamic Loader and Symbol APIs, [106](#)
- OS_TIMER_ERR_INTERNAL
 - OSAL Return Code Defines, [140](#)
- OS_TIMER_ERR_INVALID_ARGS
 - OSAL Return Code Defines, [141](#)
- OS_TIMER_ERR_TIMER_ID
 - OSAL Return Code Defines, [141](#)
- OS_TIMER_ERR_UNAVAILABLE

- OSAL Return Code Defines, [141](#)
- OS_TaskCreate
 - OSAL Task APIs, [21](#)
- OS_TaskDelay
 - OSAL Task APIs, [22](#)
- OS_TaskDelete
 - OSAL Task APIs, [23](#)
- OS_TaskExit
 - OSAL Task APIs, [23](#)
- OS_TaskFindIdBySystemData
 - OSAL Task APIs, [23](#)
- OS_TaskGetId
 - OSAL Task APIs, [24](#)
- OS_TaskGetIdByName
 - OSAL Task APIs, [24](#)
- OS_TaskGetInfo
 - OSAL Task APIs, [25](#)
- OS_TaskInstallDeleteHandler
 - OSAL Task APIs, [25](#)
- OS_TaskRegister
 - OSAL Task APIs, [26](#)
- OS_TaskSetPriority
 - OSAL Task APIs, [26](#)
- OS_Tick2Micros
 - OSAL Time/Tick APIs, [50](#)
- OS_TimeBaseCreate
 - OSAL Timer APIs, [121](#)
- OS_TimeBaseDelete
 - OSAL Timer APIs, [122](#)
- OS_TimeBaseGetFreeRun
 - OSAL Timer APIs, [123](#)
- OS_TimeBaseGetIdByName
 - OSAL Timer APIs, [124](#)
- OS_TimeBaseGetInfo
 - OSAL Timer APIs, [124](#)
- OS_TimeBaseSet
 - OSAL Timer APIs, [125](#)
- OS_TimedRead
 - OSAL Standard File APIs, [86](#)
- OS_TimedWrite
 - OSAL Standard File APIs, [87](#)
- OS_TimerAdd
 - OSAL Timer APIs, [125](#)
- OS_TimerCallback_t
 - osapi-os-timer.h, [204](#)
- OS_TimerCreate
 - OSAL Timer APIs, [126](#)
- OS_TimerDelete
 - OSAL Timer APIs, [127](#)
- OS_TimerGetIdByName
 - OSAL Timer APIs, [128](#)
- OS_TimerGetInfo
 - OSAL Timer APIs, [128](#)
- OS_TimerSet
 - OSAL Timer APIs, [129](#)
- OS_TimerSync_t
 - osapi-os-timer.h, [204](#)
- OS_TranslatePath
 - OSAL File System Level APIs, [100](#)
- OS_USED
 - common_types.h, [178](#)
- OS_UTILITYTASK_PRIORITY
 - osconfig-example.h, [175](#)
- OS_UTILITYTASK_STACK_SIZE
 - osconfig-example.h, [175](#)
- OS_VolumeInfo_t, [165](#)
 - BlockSize, [166](#)
 - DeviceName, [166](#)
 - FreeFlag, [166](#)
 - IsMounted, [166](#)
 - MountPoint, [166](#)
 - PhysDevName, [166](#)
 - VolatileFlag, [166](#)
 - VolumeName, [167](#)
 - VolumeType, [167](#)
- OS_WRITE_ONLY
 - OSAL File Access Option Defines, [72](#)
- OS_bin_sem_prop_t, [142](#)
 - creator, [142](#)
 - name, [142](#)
 - value, [142](#)
- OS_chkfs
 - OSAL File System Level APIs, [94](#)
- OS_chmod
 - OSAL Standard File APIs, [75](#)
- OS_close
 - OSAL Standard File APIs, [76](#)
- OS_closedir
 - OSAL Directory APIs, [89](#)
- OS_count_sem_prop_t, [143](#)
 - creator, [143](#)
 - name, [143](#)
 - value, [143](#)
- OS_cp
 - OSAL Standard File APIs, [77](#)
- OS_creat
 - OSAL Standard File APIs, [78](#)
- OS_file_prop_t, [145](#)
 - IsValid, [146](#)
 - Path, [146](#)
 - User, [146](#)
- OS_fsBlocksFree
 - OSAL File System Level APIs, [96](#)
- OS_fsBytesFree
 - OSAL File System Level APIs, [96](#)
- OS_heap_prop_t, [149](#)
 - free_blocks, [149](#)
 - free_bytes, [149](#)

- largest_free_block, 150
- OS_initfs
 - OSAL File System Level APIs, 98
- OS_lseek
 - OSAL Standard File APIs, 80
- OS_mkdir
 - OSAL Directory APIs, 91
- OS_mkfs
 - OSAL File System Level APIs, 99
- OS_module_address_t, 150
 - bss_address, 150
 - bss_size, 151
 - code_address, 151
 - code_size, 151
 - data_address, 151
 - data_size, 151
 - flags, 151
 - valid, 152
- OS_module_prop_t, 152
 - addr, 152
 - entry_point, 153
 - filename, 153
 - host_module_id, 153
 - name, 153
- OS_module_record_t
 - osapi-os-loader.h, 200
- OS_mount
 - OSAL File System Level APIs, 99
- OS_mut_sem_prop_t, 153
 - creator, 154
 - name, 154
- OS_mv
 - OSAL Standard File APIs, 81
- OS_open
 - OSAL Standard File APIs, 81
- OS_opendir
 - OSAL Directory APIs, 92
- OS_printf
 - OSAL Printf APIs, 70
- OS_printf_disable
 - OSAL Printf APIs, 70
- OS_printf_enable
 - OSAL Printf APIs, 71
- OS_queue_prop_t, 154
 - creator, 155
 - name, 155
- OS_read
 - OSAL Standard File APIs, 83
- OS_readdir
 - OSAL Directory APIs, 92
- OS_remove
 - OSAL Standard File APIs, 84
- OS_rename
 - OSAL Standard File APIs, 85
- OS_rewinddir
 - OSAL Directory APIs, 92
- OS_rmdir
 - OSAL Directory APIs, 92
- OS_rmfs
 - OSAL File System Level APIs, 100
- OS_socket_prop_t, 158
 - creator, 158
 - name, 158
- OS_stat
 - OSAL Standard File APIs, 85
- OS_static_symbol_record_t, 159
 - Address, 159
 - Module, 159
 - Name, 159
- OS_task_prop_t, 160
 - creator, 160
 - name, 160
 - OSTask_id, 161
 - priority, 161
 - stack_size, 161
- OS_time_t, 161
 - microsecs, 162
 - seconds, 162
- OS_timebase_prop_t, 162
 - accuracy, 163
 - creator, 163
 - freerun_time, 163
 - name, 163
 - nominal_interval_time, 163
- OS_timer_prop_t, 164
 - accuracy, 164
 - creator, 164
 - interval_time, 164
 - name, 164
 - start_time, 165
- OS_unmount
 - OSAL File System Level APIs, 102
- OS_write
 - OSAL Standard File APIs, 87
- OSAL Core Operation APIs, 15
 - OS_API_Init, 15
 - OS_Application_Run, 16
 - OS_Application_Startup, 16
 - OS_ApplicationExit, 16
 - OS_ApplicationShutdown, 16
 - OS_DeleteAllObjects, 17
 - OS_IdleLoop, 17
- OSAL Directory APIs, 89
 - OS_DirectoryClose, 89
 - OS_DirectoryOpen, 90
 - OS_DirectoryRead, 90
 - OS_DirectoryRewind, 91
 - OS_closedir, 89

- OS_mkdir, [91](#)
- OS_opendir, [92](#)
- OS_readdir, [92](#)
- OS_rewinddir, [92](#)
- OS_rmdir, [92](#)
- OSAL Dynamic Loader and Symbol APIs, [104](#)
 - OS_ModuleInfo, [104](#)
 - OS_ModuleLoad, [105](#)
 - OS_ModuleUnload, [105](#)
 - OS_SymbolLookup, [106](#)
 - OS_SymbolTableDump, [106](#)
- OSAL Error Info APIs, [66](#)
 - OS_GetErrorName, [66](#)
- OSAL Exception APIs, [52](#)
 - OS_ExcAttachHandler, [52](#)
 - OS_ExcDisable, [52](#)
 - OS_ExcEnable, [52](#)
- OSAL File Access Option Defines, [72](#)
 - OS_READ_ONLY, [72](#)
 - OS_READ_WRITE, [72](#)
 - OS_WRITE_ONLY, [72](#)
- OSAL File System Level APIs, [94](#)
 - OS_FS_GetPhysDriveName, [95](#)
 - OS_FileSysAddFixedMap, [95](#)
 - OS_GetFsInfo, [97](#)
 - OS_TranslatePath, [100](#)
 - OS_chkfs, [94](#)
 - OS_fsBlocksFree, [96](#)
 - OS_fsBytesFree, [96](#)
 - OS_initfs, [98](#)
 - OS_mkfs, [99](#)
 - OS_mount, [99](#)
 - OS_rmfs, [100](#)
 - OS_unmount, [102](#)
- OSAL Floating Point Unit Exception APIs, [53](#)
 - OS_FPUExcAttachHandler, [53](#)
 - OS_FPUExcDisable, [54](#)
 - OS_FPUExcEnable, [54](#)
 - OS_FPUExcGetMask, [55](#)
 - OS_FPUExcSetMask, [55](#)
- OSAL Heap APIs, [65](#)
 - OS_HeapGetInfo, [65](#)
- OSAL Interrupt APIs, [57](#)
 - OS_IntAck, [57](#)
 - OS_IntAttachHandler, [58](#)
 - OS_IntDisable, [59](#)
 - OS_IntEnable, [59](#)
 - OS_IntGetMask, [60](#)
 - OS_IntLock, [60](#)
 - OS_IntSetMask, [61](#)
 - OS_IntUnlock, [61](#)
- OSAL Message Queue APIs, [28](#)
 - OS_QueueCreate, [28](#)
 - OS_QueueDelete, [29](#)
 - OS_QueueGet, [30](#)
 - OS_QueueGetIdByName, [30](#)
 - OS_QueueGetInfo, [31](#)
 - OS_QueuePut, [31](#)
- OSAL Object Type Defines, [10](#)
 - OS_OBJECT_TYPE_OS_BINSEM, [11](#)
 - OS_OBJECT_TYPE_OS_CONSOLE, [11](#)
 - OS_OBJECT_TYPE_OS_COUNTSEM, [11](#)
 - OS_OBJECT_TYPE_OS_DIR, [11](#)
 - OS_OBJECT_TYPE_OS_FILESYS, [12](#)
 - OS_OBJECT_TYPE_OS_MODULE, [12](#)
 - OS_OBJECT_TYPE_OS_MUTEX, [12](#)
 - OS_OBJECT_TYPE_OS_QUEUE, [12](#)
 - OS_OBJECT_TYPE_OS_STREAM, [12](#)
 - OS_OBJECT_TYPE_OS_TASK, [13](#)
 - OS_OBJECT_TYPE_OS_TIMEBASE, [13](#)
 - OS_OBJECT_TYPE_OS_TIMECB, [13](#)
 - OS_OBJECT_TYPE_UNDEFINED, [13](#)
 - OS_OBJECT_TYPE_USER, [13](#)
- OSAL Object Utility APIs, [18](#)
 - OS_ConvertToArrayIndex, [18](#)
 - OS_ForEachObject, [19](#)
 - OS_GetResourceName, [19](#)
 - OS_IdentifyObject, [19](#)
- OSAL Printf APIs, [70](#)
 - OS_printf, [70](#)
 - OS_printf_disable, [70](#)
 - OS_printf_enable, [71](#)
- OSAL Reference Point For Seek Offset Defines, [73](#)
 - OS_SEEK_CUR, [73](#)
 - OS_SEEK_END, [73](#)
 - OS_SEEK_SET, [73](#)
- OSAL Return Code Defines, [131](#)
 - OS_ERR_BAD_ADDRESS, [132](#)
 - OS_ERR_FILE, [133](#)
 - OS_ERR_INCORRECT_OBJ_STATE, [133](#)
 - OS_ERR_INCORRECT_OBJ_TYPE, [133](#)
 - OS_ERR_INVALID_ID, [133](#)
 - OS_ERR_INVALID_PRIORITY, [133](#)
 - OS_ERR_NAME_NOT_FOUND, [134](#)
 - OS_ERR_NAME_TAKEN, [134](#)
 - OS_ERR_NAME_TOO_LONG, [134](#)
 - OS_ERR_NO_FREE_IDS, [134](#)
 - OS_ERR_NOT_IMPLEMENTED, [134](#)
 - OS_ERR_OBJECT_IN_USE, [135](#)
 - OS_ERR_OPERATION_NOT_SUPPORTED, [135](#)
 - OS_ERR_SEM_NOT_FULL, [135](#)
 - OS_ERR_STREAM_DISCONNECTED, [135](#)
 - OS_ERROR_ADDRESS_MISALIGNED, [136](#)
 - OS_ERROR_TIMEOUT, [136](#)
 - OS_ERROR, [135](#)
 - OS_FS_ERR_DEVICE_NOT_FREE, [136](#)
 - OS_FS_ERR_DRIVE_NOT_CREATED, [136](#)
 - OS_FS_ERR_INVALID_FD, [136](#)

- OS_FS_ERR_INVALID_POINTER, [137](#)
- OS_FS_ERR_NAME_TOO_LONG, [137](#)
- OS_FS_ERR_NO_FREE_FDS, [137](#)
- OS_FS_ERR_PATH_INVALID, [137](#)
- OS_FS_ERR_PATH_TOO_LONG, [137](#)
- OS_FS_ERROR, [138](#)
- OS_FS_SUCCESS, [138](#)
- OS_FS_UNIMPLEMENTED, [138](#)
- OS_INVALID_INT_NUM, [138](#)
- OS_INVALID_POINTER, [138](#)
- OS_INVALID_SEM_VALUE, [139](#)
- OS_QUEUE_EMPTY, [139](#)
- OS_QUEUE_FULL, [139](#)
- OS_QUEUE_ID_ERROR, [139](#)
- OS_QUEUE_INVALID_SIZE, [139](#)
- OS_QUEUE_TIMEOUT, [140](#)
- OS_SEM_FAILURE, [140](#)
- OS_SEM_TIMEOUT, [140](#)
- OS_SUCCESS, [140](#)
- OS_TIMER_ERR_INTERNAL, [140](#)
- OS_TIMER_ERR_INVALID_ARGS, [141](#)
- OS_TIMER_ERR_TIMER_ID, [141](#)
- OS_TIMER_ERR_UNAVAILABLE, [141](#)
- OSAL Select APIs, [67](#)
 - OS_SelectFdAdd, [67](#)
 - OS_SelectFdClear, [67](#)
 - OS_SelectFdsSet, [67](#)
 - OS_SelectFdZero, [68](#)
 - OS_SelectMultiple, [68](#)
 - OS_SelectSingle, [69](#)
- OSAL Semaphore APIs, [33](#)
 - OS_BinSemCreate, [34](#)
 - OS_BinSemDelete, [34](#)
 - OS_BinSemFlush, [36](#)
 - OS_BinSemGetIdByName, [36](#)
 - OS_BinSemGetInfo, [37](#)
 - OS_BinSemGive, [38](#)
 - OS_BinSemTake, [38](#)
 - OS_BinSemTimedWait, [39](#)
 - OS_CountSemCreate, [40](#)
 - OS_CountSemDelete, [40](#)
 - OS_CountSemGetIdByName, [41](#)
 - OS_CountSemGetInfo, [41](#)
 - OS_CountSemGive, [42](#)
 - OS_CountSemTake, [43](#)
 - OS_CountSemTimedWait, [43](#)
 - OS_MutSemCreate, [44](#)
 - OS_MutSemDelete, [45](#)
 - OS_MutSemGetIdByName, [45](#)
 - OS_MutSemGetInfo, [46](#)
 - OS_MutSemGive, [46](#)
 - OS_MutSemTake, [48](#)
- OSAL Semaphore State Defines, [14](#)
 - OS_SEM_EMPTY, [14](#)
 - OS_SEM_FULL, [14](#)
- OSAL Shared memory APIs, [63](#)
 - OS_ShMemAttach, [63](#)
 - OS_ShMemCreate, [63](#)
 - OS_ShMemGetIdByName, [63](#)
 - OS_ShMemInit, [64](#)
 - OS_ShMemSemGive, [64](#)
 - OS_ShMemSemTake, [64](#)
- OSAL Shell APIs, [103](#)
 - OS_ShellOutputToFile, [103](#)
- OSAL Socket Address APIs, [109](#)
 - OS_SocketAddrFromString, [109](#)
 - OS_SocketAddrGetPort, [110](#)
 - OS_SocketAddrInit, [110](#)
 - OS_SocketAddrSetPort, [111](#)
 - OS_SocketAddrToString, [111](#)
- OSAL Socket Management APIs, [113](#)
 - OS_NetworkGetHostName, [113](#)
 - OS_NetworkGetID, [114](#)
 - OS_SocketAccept, [114](#)
 - OS_SocketBind, [115](#)
 - OS_SocketConnect, [115](#)
 - OS_SocketGetIdByName, [117](#)
 - OS_SocketGetInfo, [118](#)
 - OS_SocketOpen, [118](#)
 - OS_SocketRecvFrom, [119](#)
 - OS_SocketSendTo, [119](#)
- OSAL Standard File APIs, [75](#)
 - OS_CloseAllFiles, [77](#)
 - OS_CloseFileByName, [77](#)
 - OS_FDGetInfo, [79](#)
 - OS_FileOpenCheck, [79](#)
 - OS_TimedRead, [86](#)
 - OS_TimedWrite, [87](#)
 - OS_chmod, [75](#)
 - OS_close, [76](#)
 - OS_cp, [77](#)
 - OS_creat, [78](#)
 - OS_lseek, [80](#)
 - OS_mv, [81](#)
 - OS_open, [81](#)
 - OS_read, [83](#)
 - OS_remove, [84](#)
 - OS_rename, [85](#)
 - OS_stat, [85](#)
 - OS_write, [87](#)
- OSAL Task APIs, [21](#)
 - OS_TaskCreate, [21](#)
 - OS_TaskDelay, [22](#)
 - OS_TaskDelete, [23](#)
 - OS_TaskExit, [23](#)
 - OS_TaskFindIdBySystemData, [23](#)
 - OS_TaskGetId, [24](#)
 - OS_TaskGetIdByName, [24](#)

- OS_TaskGetInfo, 25
- OS_TaskInstallDeleteHandler, 25
- OS_TaskRegister, 26
- OS_TaskSetPriority, 26
- OSAL Time/Tick APIs, 49
 - OS_GetLocalTime, 49
 - OS_Milli2Ticks, 49
 - OS_SetLocalTime, 50
 - OS_Tick2Micros, 50
- OSAL Timer APIs, 121
 - OS_TimeBaseCreate, 121
 - OS_TimeBaseDelete, 122
 - OS_TimeBaseGetFreeRun, 123
 - OS_TimeBaseGetIdByName, 124
 - OS_TimeBaseGetInfo, 124
 - OS_TimeBaseSet, 125
 - OS_TimerAdd, 125
 - OS_TimerCreate, 126
 - OS_TimerDelete, 127
 - OS_TimerGetIdByName, 128
 - OS_TimerGetInfo, 128
 - OS_TimerSet, 129
- OSAL Volume Type Defines, 74
 - ATA_DISK, 74
 - EEPROM_DISK, 74
 - FS_BASED, 74
 - RAM_DISK, 74
- OSAL_API_VERSION
 - osapi-version.h, 206
- OStask_id
 - OS_task_prop_t, 161
- object_ids
 - OS_FdSet, 145
- os_dirent_t, 144
 - FileName, 144
- os_dirp_t
 - osapi-os-filesys.h, 198
- os_err_name_t
 - osapi-os-core.h, 189
- os_fs_err_name_t
 - osapi-os-filesys.h, 199
- os_fshealth_t
 - osapi-os-filesys.h, 199
- os_fsinfo_t, 146
 - FreeFds, 147
 - FreeVolumes, 147
 - MaxFds, 147
 - MaxVolumes, 147
- os_fstat_t, 148
 - FileModeBits, 148
 - FileSize, 148
 - FileTime, 148
- osal/src/os/inc/common_types.h, 175
- osal/src/os/inc/osapi-os-core.h, 182
- osal/src/os/inc/osapi-os-filesys.h, 192
- osal/src/os/inc/osapi-os-loader.h, 200
- osal/src/os/inc/osapi-os-net.h, 201
- osal/src/os/inc/osapi-os-timer.h, 203
- osal/src/os/inc/osapi-version.h, 205
- osal/src/os/inc/osapi.h, 206
- osal_task
 - osapi-os-core.h, 190, 191
- osalbool
 - common_types.h, 180
- osapi-os-core.h
 - OS_ArgCallback_t, 189
 - OS_BSP_GetArgC, 191
 - OS_BSP_GetArgV, 191
 - OS_BSP_SetExitCode, 191
 - OS_ERROR_NAME_LENGTH, 188
 - OS_FP_ENABLED, 188
 - OS_ForEachObjectOfType, 191
 - OS_MAX_TASK_PRIORITY, 188
 - OS_OBJECT_CREATOR_ANY, 188
 - OS_OBJECT_INDEX_MASK, 189
 - OS_OBJECT_TYPE_SHIFT, 189
 - OS_StreamState_t, 190
 - os_err_name_t, 189
 - osal_task, 190, 191
- osapi-os-filesys.h
 - NUM_FILE_SYSTEMS, 195
 - OS_CHK_ONLY, 195
 - OS_DIRENTRY_NAME, 196
 - OS_FDTableEntry, 199
 - OS_FILESTAT_EXEC, 196
 - OS_FILESTAT_ISDIR, 196
 - OS_FILESTAT_MODE, 196
 - OS_FILESTAT_READ, 196
 - OS_FILESTAT_SIZE, 197
 - OS_FILESTAT_TIME, 197
 - OS_FILESTAT_WRITE, 197
 - OS_FS_DEV_NAME_LEN, 197
 - OS_FS_PHYS_NAME_LEN, 197
 - OS_FS_VOL_NAME_LEN, 198
 - OS_MAX_LOCAL_PATH_LEN, 198
 - OS_REPAIR, 198
 - os_dirp_t, 198
 - os_fs_err_name_t, 199
 - os_fshealth_t, 199
- osapi-os-loader.h
 - OS_module_record_t, 200
- osapi-os-net.h
 - OS_SOCKETADDR_MAX_LEN, 202
 - OS_SocketDomain_t, 202
 - OS_SocketType_t, 203
- osapi-os-timer.h
 - OS_TimerCallback_t, 204
 - OS_TimerSync_t, 204

osapi-version.h
 OS_MAJOR_VERSION, [205](#)
 OS_MINOR_VERSION, [205](#)
 OS_MISSION_REV, [205](#)
 OS_REVISION, [205](#)
 OSAL_API_VERSION, [206](#)
 osapi.h
 OS_CHECK, [208](#)
 OS_PEND, [208](#)
 osconfig-example.h
 OS_BUFFER_MSG_DEPTH, [168](#)
 OS_BUFFER_SIZE, [169](#)
 OS_MAX_API_NAME, [169](#)
 OS_MAX_BIN_SEMAPHORES, [169](#)
 OS_MAX_CMD_LEN, [169](#)
 OS_MAX_CONSOLES, [170](#)
 OS_MAX_COUNT_SEMAPHORES, [170](#)
 OS_MAX_FILE_NAME, [170](#)
 OS_MAX_FILE_SYSTEMS, [170](#)
 OS_MAX_MODULES, [171](#)
 OS_MAX_MUTEXES, [171](#)
 OS_MAX_NUM_OPEN_DIRS, [171](#)
 OS_MAX_NUM_OPEN_FILES, [171](#)
 OS_MAX_PATH_LEN, [172](#)
 OS_MAX_QUEUES, [172](#)
 OS_MAX_SYM_LEN, [172](#)
 OS_MAX_TASKS, [172](#)
 OS_MAX_TIMEBASES, [173](#)
 OS_MAX_TIMERS, [173](#)
 OS_MODULE_FILE_EXTENSION, [173](#)
 OS_PRINTF_CONSOLE_NAME, [174](#)
 OS_QUEUE_MAX_DEPTH, [174](#)
 OS_SHELL_CMD_INPUT_FILE_NAME, [174](#)
 OS_SOCKADDR_MAX_LEN, [174](#)
 OS_UTILITYTASK_PRIORITY, [175](#)
 OS_UTILITYTASK_STACK_SIZE, [175](#)

 Path
 OS_file_prop_t, [146](#)
 PhysDevName
 OS_VolumeInfo_t, [166](#)
 priority
 OS_task_prop_t, [161](#)

 RAM_DISK
 OSAL Volume Type Defines, [74](#)

 seconds
 OS_time_t, [162](#)
 stack_size
 OS_task_prop_t, [161](#)
 start_time
 OS_timer_prop_t, [165](#)

 TRUE

 common_types.h, [178](#)
 uint16
 common_types.h, [180](#)
 uint32
 common_types.h, [180](#)
 uint64
 common_types.h, [180](#)
 uint8
 common_types.h, [180](#)
 User
 OS_file_prop_t, [146](#)

 valid
 OS_module_address_t, [152](#)
 value
 OS_bin_sem_prop_t, [142](#)
 OS_count_sem_prop_t, [143](#)
 VolatileFlag
 OS_VolumeInfo_t, [166](#)
 VolumeName
 OS_VolumeInfo_t, [167](#)
 VolumeType
 OS_VolumeInfo_t, [167](#)