



QDYN

Quasi-DYNamic earthquake simulator

User's Manual

V 1.3.0



code.google.com/p/qdyn/

Developers

QuakeID Group, Caltech Seismo Lab:

Yingdi Luo (http://www.seismolab.caltech.edu/luo_y.html)

Jean-Paul Ampuero (http://www.seismolab.caltech.edu/ampuero_jp.html)

Bryan Riel (http://www.seismolab.caltech.edu/riel_b.html)

Last modified on 10/30/2014

[Click here](#) to access the most recent version

Table of contents

- [1. Introduction](#)
 - [1.1. Summary](#)
 - [1.2. Main features](#)
 - [1.3. Documentation](#)
 - [1.4. Support](#)
 - [1.5. License](#)
 - [1.6. Acknowledgements](#)
 - [1.6.1. Code contributions](#)
 - [1.6.2. Funding](#)
 - [1.7. Suggested references](#)
- [2. Installation](#)
 - [2.1. Requirements](#)
 - [2.2. Download QDYN](#)
 - [2.3. Install QDYN](#)
 - [2.4. Update QDYN](#)
- [3. Running a simulation](#)
 - [3.1. The Matlab wrapper](#)
 - [3.2. Simulation parameters structure \(pars\)](#)
 - [3.3. Output structures \(ot, ox\)](#)
 - [3.4. Examples](#)
 - [3.4.1. A simple 2D example](#)
 - [3.4.2. Two asperities interacting](#)
 - [3.4.3. 3D simulations](#)
- [4. Optimizing Performance](#)
 - [4.1. Running simulations outside the Matlab environment](#)
 - [4.2. Managing parallel computing](#)
 - [4.2.1. OpenMP](#)
 - [4.2.2. MPI](#)
 - [4.3. Managing outputs of large simulations](#)
- [5. Visualizing simulation results](#)

1. Introduction

1.1. Summary

QDYN is a boundary element software to simulate earthquake cycles (seismic and aseismic slip on tectonic faults) under the quasi-dynamic approximation (quasi-static elasticity combined with radiation damping) on faults governed by rate-and-state friction and embedded in elastic media.

QDYN includes various forms of rate-and-state friction and state evolution laws, and handles non-planar fault geometry in 3D and 2D media, as well as spring-block simulations. Loading is controlled by remote displacement, steady creep or oscillatory load. In 3D it handles free surface effects in a half-space, including normal stress coupling. The medium surrounding the fault is uniform, linear, isotropic and elastic.

QDYN implements adaptive time stepping, shared-memory parallelization, and can deal with multi-scale earthquake cycle simulations with fine details in both time and space. It is equipped with a user-friendly Matlab interface and graphical output utilities.

1.2. Main features

- Rate-and-state friction, with velocity cut-offs, aging and slip laws
- Arbitrarily heterogeneous frictional properties
- Slow and fast, aseismic and seismic slip transients (adaptive timestep)
- Non-planar faults (currently limited to variable dip, rectangular elements)
- 3D, 2D and 1D (spring-block)
- Steady and oscillatory loads
- Matlab wrapper and graphic output display utilities
- Parallelized for shared memory systems (OpenMP)
- Normal stress coupling

1.3. Documentation

Documentation for QDYN is available through the following resources:

- This User's Manual. [Click here](#) to access the most recent version.
- The `examples` directory contains several examples, some have a `README` file
- The Matlab tools provided with the QDYN package are documented through

Matlab's help. For instance `help qdyn` provides an overview of the usage of the `qdyn` Matlab interface.

- The `ToDo` file contains a list of known issues.

1.4. Support

Support for QDYN users (reporting bugs, installation problems, documentation issues, feature requests, etc) is available at:

<https://code.google.com/p/qdyn/issues/list>

Before submitting an issue please make sure that:

- you have read the QDYN documentation (see section 1.3)
- you are running the most recent version of QDYN (see sections 2.2 and 2.4)
- your problem has not been treated in previous issues. You can browse the issues titles or search the issues database for keywords at <https://code.google.com/p/qdyn/issues/list>

New issues are submitted via <https://code.google.com/p/qdyn/issues/entry>. Please include all information needed to reproduce your problem (input files, operating system, etc).

1.5. License

This software is freely available for academic research purposes. If you use QDYN please include proper attributions to its authors and cite one of the references in section 1.7 in your scientific papers and reports.

This program is free software: you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program. If not, see <http://www.gnu.org/licenses/>.

1.6. Acknowledgements

1.6.1. Code contributions

QDYN outgrew from a 2D code written by Allan Rubin (Princeton University) in the early 2000s.

The subroutines implementing Okada's formulas were provided by Shinichi Miyazaki (Kyoto University).

The FFT subroutines are based on the [General Purpose FFT Package](#) written by Takuya Ooura (Kyoto University).

1.6.2. Funding

The development of QDYN is/was partially supported by the US National Science Foundation, the Southern California Earthquake Center, and Japan's Nuclear Regulation Authority (formerly Japan Nuclear Energy Safety Organization).

1.7. Suggested references

Y. Luo, J. P. Ampuero (2011), *Numerical Simulation of Tremor Migration Triggered by Slow Slip and Rapid Tremor Reversals*, AGU Fall Meeting 2011 Abstract S33C-02

Y. Luo, J. P. Ampuero (2012), *Simulation of Complex Tremor Migration Patterns*, AGU Fall Meeting 2012 Abstract S44B-02

2. Installation

2.1. Requirements

- [Make](#) and [Subversion](#) for easier code installation and updates. Both are standard Linux tools.
- A Fortran compiler.
- Matlab or Octave.

We mostly develop and use QDYN with Linux, the Intel Fortran compiler (ifort) and Matlab. The code has been successfully compiled and used on Windows or Mac, with gfortran and Octave.

2.2. Download QDYN

QDYN is managed under the [Subversion](#) version control system. To get the most current version of QDYN execute the following command on Linux (first time only):

```
svn checkout http://qdyn.googlecode.com/svn/trunk/ qdyn-read-only
```

This creates a directory `qdyn-read-only` which contains the whole QDYN package. You can create a directory with a different name.

You can also manually download the QDYN source files and pre-compiled executables for Windows or Mac OS directly from [this link](#). However, note that these may not be most up-to-date versions, and that pre-compiled executables may run slower than if you compile the code by yourself.

2.3. Install QDYN

1. Move to the `qdyn-read-only/src` directory
2. Modify the section “User Settings” of file `Makefile` following the instructions and examples therein:
 - a. In section 1, set the executable file name and its path: set the variable `EXEC = [your executable file name, with its full path]`. By default, the executable file is named `~/bin/qdyn`. Make sure the path points to an existing directory. For instance, if the `~/bin/` directory does not exist, create it.
 - b. In section 2, adjust your Fortran compiler settings: set the variables `F90 = [your compiler name]` and `OPT = [your compiler optimisation flags]`. Intel Fortran (ifort) is the

default compiler, but settings for several commonly used compilers are provided.

3. Modify the section “User Settings” in `constants.f90` following the instructions therein:
 - a. If you plan to use the option `FINITE=1` with $N > 32768$ (see section 3.2) update the name of the file `kernel*tab`
 - b. If you plan to use Octave instead of Matlab set `OCTAVE_OUTPUT=.true.`
4. Run `make`
5. If in step 2 you changed the path or name of the executable file, modify accordingly the line `status = system('~bin/qdyn')` of file `qdyn.m`

2.4. Update QDYN

After the first-time checkout, you can update the package by executing the following command in your `qdyn-read-only` directory:

```
svn update
```

and then following the steps in the [“Install QDYN” section](#) again.

If you have made modifications to the code and/or user settings and want to keep these modifications, please choose to keep your own version when prompted when you execute the `svn update` command

3. Running a simulation

3.1. The Matlab wrapper

The core of QDYN is a Fortran code. While the format of its input and output files is well defined, we find it more convenient to set up the input parameters, perform simulations and read the output data within the Matlab environment through the Matlab wrapper `qdyn.m`. Its general usage syntax is:

```
[pars,ot,ox] = qdyn(mode,[parsin],['Property',Value,...])
```

The default input values can be examined by executing:

```
pars = qdyn('set')
```

The input parameters are:

<i>mode</i>	<p>One of the following execution modes:</p> <p>'set' Outputs the default parameter structure (<i>pars</i>) or overrides it with fields present in the structure <i>parsin</i> or with <i>Property/Value</i> pairs</p> <p>'write' Sets parameters and writes the qdyn input file</p> <p>'run' Sets parameters, writes the input file and runs a simulation</p> <p>'read' Reads parameters and outputs from a previous simulation</p>
<i>parsin</i>	Parameter structure to override the default parameters (see section 3.2 for details)
' <i>Property</i> '	Name of a field to be set in the parameter structure (see section 3.2)
<i>Value</i>	Value to override the default value and the value in <i>parsin</i>

The output variables are:

<i>pars</i>	Structure containing the parameters (see section 3.2)
<i>ot</i>	Structure containing time series outputs, global or at selected points (see section 3.3)
<i>ox</i>	Structure containing snapshot outputs, i.e. quantities over the whole fault, output at selected times (see section 3.3)

3.2. Simulation parameters structure (*pars*)

The parameters in the structure *pars*, that can be set through 'parsin' or 'Prop/Value' pairs are:

Parameters defining the geometry of the problem and loading:

<i>MESHDIM</i>	Dimension of the problem:
----------------	---------------------------

	<p>0 = Spring-block model</p> <p>1 = 1D fault in a 2D elastic medium</p> <p>2 = 2D fault in a 3D elastic medium</p> <p>4 = Same as 2 but fault stresses computed via 2D-FFT (works only if the grid spacings and dip angle are uniform)</p>
<i>MU</i>	Shear modulus (Pa)
<i>LAM</i>	Elastic modulus lambda for 3D simulations (Pa)
<i>VS</i>	Shear wave speed (m/s). If <i>VS</i> =0, radiation damping is turned off
<i>L</i>	If <i>MESHDIM</i> =1, <i>L</i> is the fault length (or spatial period) If <i>MESHDIM</i> =0, <i>MU/L</i> is the spring stiffness
<i>FINITE</i>	<p>Boundary conditions when <i>MESHDIM</i>=1</p> <p>0 = The fault is infinitely long but slip is spatially periodic with period <i>L</i>, loaded by steady displacement at distance <i>W</i> from the fault</p> <p>1 = The fault is infinitely long but only a segment of length <i>L</i> has rate-and-state friction, the rest has steady slip. If running the code with this option gives the error message “finite kernel is too small”, you should create a larger “kernel file” with the matlab function <i>TabKernelFiniteFlt.m</i>, update the file name in <code>src/constants.f90</code>, and re-compile the code</p>
<i>W</i>	Distance between displacement loading and fault, only if <i>MESHDIM</i> =1 and <i>FINITE</i> =0
<i>DIP_W</i>	Fault dip angle (degree) if <i>MESHDIM</i> =2 or 4. If depth-dependent, values must be given from deeper to shallower depth.
<i>Z_CORNER</i>	Fault bottom depth (km, negative down) if <i>MESHDIM</i> =2 or 4
<i>SIGMA_CPL</i>	Normal stress coupling: 0 = disable, 1 = enable
<i>APER</i>	Amplitude of additional time-dependent oscillatory shear stress loading (Pa)

<i>TPER</i>	Period of oscillatory loading (s)
-------------	-----------------------------------

Rate-and-state friction parameters:

<i>A</i>	Direct effect coefficient
<i>B</i>	Evolution effect coefficient
<i>DC</i>	Characteristic slip distance (m)
<i>MU_SS</i>	Reference steady-state friction coefficient
<i>V_SS</i>	Reference steady-state slip velocity (m/s)
<i>TH_SS</i>	Reference steady-state state. The default is $TH_SS = DC/V_SS$.
<i>RNS_LAW</i>	Type of rate-and-state friction law: 0 = original 1 = with cut-off velocities <i>V1</i> and <i>V2</i>
<i>V1</i>	Cut-off velocity of direct effect (m/s)
<i>V2</i>	Cut-off velocity of evolution effect (m/s), controls the transition from weakening to strengthening when $a < b$. <i>V2</i> should be $\leq V1$.
<i>THETA_LAW</i>	Type of evolution law for the state variable: 0 = ageing law in the "no-healing" approximation 1 = ageing law 2 = slip law

Initial conditions:

<i>SIGMA</i>	Initial effective normal stress (Pa). Remains constant unless $SIGMA_CPL = 1$
<i>V_0</i>	Initial slip velocity (m/s)
<i>TH_0</i>	Initial state (s)

Discretization and accuracy parameters:

N	Number of fault elements if MESHDIM=1
NX	Number of fault elements along-strike, in 3D
NW	Number of fault elements along-dip, in 3D
DW	Along-dip length (km) of each element, from deep to shallow
TMAX	Total simulation time (s)
NSTOP	Stopping criterion 0 = Stop at t=TMAX 1 = Stop at end of slip localization phase 2 = Stop at first slip rate peak
DTRY	First trial timestep (s)
DTMAX	Maximum timestep (0=unrestricted)
ACC	Solver accuracy

Output control parameters:

OX_SEQ	Type of snapshot outputs 0 = All snapshots in a single output file (fort.19) 1 = One output file per snapshot (fort.1001, ...)
NXOUT	Spatial interval for snapshot outputs (in number of elements)
NTOUT	Temporal interval (in number of time steps) for snapshot outputs
OX_DYN	Output specific snapshots of dynamic events defined by thresholds on peak slip velocity DYN_TH_ON and DYN_TH_OFF (see below) 0 = Disable

	1 = Enable outputs for event #i: Event start: fort.19998+3i Event end: fort.19999+3i Rupture time: fort.20000+3i
NXOUT_DYN	Spatial interval (in number of elements) for dynamic snapshot outputs
DYN_TH_ON	Peak slip rate threshold (m/s) to define the beginning of a dynamic event
DYN_TH_OFF	Peak slip rate threshold (m/s) to define the end of a dynamic event
IC	Index of selected element for time series outputs

Parameters for integration with dynamic code:

DYN_FLAG	Integration with dynamic code 0 = Disable 1 = Enable: stop QDYN at the DYN_SKIP+1-th event with seismic moment > DYN_M
DYN_M	Target seismic moment of a dynamic event
DYN_SKIP	Number of dynamic events to skip (warm up cycles)

3.3. Output structures (ot, ox)

The outputs are:

pars	Structure containing the same fields as <i>parsin</i> (see above) plus the positions of the fault elements (X,Y,Z)
ot	Structure of time series outputs, with the following fields: t Output times (s)

	<p> locl Localization length (distance between stressing rate maxima) cl Crack length (distance between slip rate maxima) p Seismic potency pdot Seismic potency rate </p> <p>Outputs at the fault location with maximum slip rate:</p> <p> xm Location of maximum slip rate v Maximum slip rate th State variable theta om (slip rate)*theta/DC tau Shear stress d Slip </p> <p>Outputs at selected fault element with index IC:</p> <p> vc slip rate thc state variable omc (slip rate)*theta/DC tauc shear stress dc slip </p>
ox	<p>Structure of snapshot outputs, with the following fields:</p> <p> x fault coordinates t output times v slip rate th state variable theta vd slip acceleration </p>

	dtau	shear stress relative to initial stress
	dtaud	shear stress rate
	d	slip
	sigma	effective normal stress


3.4. Examples

3.4.1. A simple 2D example

A 2D run with initial velocity slightly above the default steady state. In Matlab:



```
p = qdyn('set');
[p,ot,ox] = qdyn('run','V_0',1.01*p.V_SS);
semilogy(ot.t,ot.v); xlabel('time (s)');ylabel('v
(m/s)');
```

The estimated simulation time is shorter than 10 s on a single thread machine.



3.4.2. Two asperities interacting

This example is in directory `examples/double_asperities`. A large asperity (size/ $L_c = 4$) with long recurrence interval interacts with a small asperity (size/ $L_c = 2$) with short recurrence interval. When the large asperity breaks, its post-seismic slip propagates bi-laterally and triggers rupture of the small asperity. During the interseismic period of the large asperity, the smaller asperity breaks twice with a decreasing recurrence interval. The estimated simulation time is about 6 mins on a single thread machine.





3.4.3. 3D simulations

An upper-layer Matlab wrapper for the base-layer Matlab wrapper `qdyn.m` is recommended for complicated simulations. We have included some examples for reference:

a) A 3D simulation: `src/test3dfft.m`

The estimated simulation time is about 10 mins on a single thread machine for the first earthquake cycle. The figures shown below are for a complete multi-cycle simulation, comprising 4 warm-up cycles and one cycle output.





b) A simplified model for the Tohoku earthquake (2D along-dip and 3D simulations):
[examples/Tohoku](#)

For more examples and real-world applications please refer to the wiki page
on the website [here](#).

4. Optimizing Performance

4.1. *Running simulations outside the Matlab environment*

Under certain circumstances, you may want to perform simulations outside the Matlab environment (e.g. while computing on a HPC). In this case, use Matlab wrapper separately first to generate an input file (qdyn.in), then run the qdyn executable directly.

4.2. *Managing parallel computing*

4.2.1. OpenMP

QDYN is efficiently parallelized with OpenMP (shared memory parallelization). You should set the following environment variable before performing parallel simulations:

```
setenv OMP_NUM_THREADS 8
```

This command allows QDYN to run on 8 threads, which will roughly speed up calculations by a factor of 8. The number of threads should be set according to demand. In general, set this value to the maximum number of threads available on your shared memory system.

4.2.2. MPI

Features will be available in the next major update.

4.3. *Managing outputs of large simulations*

QDYN by default outputs results as a single ASCII file (fort.19) that may be too cumbersome to handle in large simulations. In practice, that is the case for most multi-cycle 3D simulations. It is then helpful to set `OX_SEQ = 1` when calling `qdyn.m`, to generate separate “ox” files outputs for each snapshot (fort.1001, ...). Also, setting `OX_DYN = 1` will automatically detect seismic events (according to parameters `DYN_TH_ON` and `DYN_TH_OFF`) and generate 3 snapshots for each event.

5. Visualizing simulation results

The QDYN software package includes several Matlab scripts to visualize simulation results in directory `src/`. These scripts are all self-documented:

<code>plot_default.m</code>	Plots slip rate of a 2D problem (along-strike)
<code>plot2d_slip.m</code>	Plots slip of a 2D problem (along-dip)
<code>plot3d_m.m</code>	Plots a sequence of snapshots of slip rate of a 3D simulation
<code>plot3d_faultview3.m</code>	Plots several snapshots of slip rate for 3D simulation in a single figure