

nomad
BSD



nomad BSD | HANDBOOK

Check our website for more information

www.nomadbsd.org

Last Update: 29/03/2022

nomad
BSD



Intro

NomadBSD is a 64bit live system for USB flash drives, based on FreeBSD®. Together with automatic hardware detection and setup, it is configured to be used as a desktop system that works out of the box, but can also be used for data recovery, for educational purposes, or to test FreeBSD®'s hardware compatibility.

Installation

1- Choosing USB Flash Device

NomadBSD performs well on USB 2.X flash drives, but writing many small files can be very slow. To improve performance, you should consider using a USB 3.X flash drive even on a USB 2.X port, as they tend to be faster. See [USB 3.0 Flash Drive Roundup](#). Do not use cheap no-name thumb drives they sell at super markets and drug stores. These drives are very slow and unreliable.

2- Downloading & Writing The Image

Instructions for writing the image to a flash drive from different operating systems can be found at www.nomadbsd.org/download.html


The NomadBSD Setup

When you boot NomadBSD for the first time, it will run the setup wizard which allows you to set your locale, timezone, keyboard settings, password, encryption, and default applications. The setup creates a new partition for the /data directory which uses the remaining space on the storage device. Depending on the size, creating the file system can take several minutes.

nomad BSD



Overview



1- Openbox menu. You can reach it by pressing the Windows® key (or Super key)/⌘ key (Mac®), or by right-clicking on the background image (root window).

2- DSBBatmon. By hovering over the icon you can see the battery's current status and charge. Clicking on it brings up the configuration menu.

3- DSBMixer. By hovering over the icon you can see the current volume of the master channel. Using the mouse wheel on it lets you change the master volume. Clicking on it brings up the main window of **DSBMixer**.

The logo for nomad BSD, featuring the text "nomad" in a sans-serif font above "BSD" in a larger, bold sans-serif font.

4- DSBMC. Clicking on the icon brings up the main window in which you can see all the mountable storage devices attached to the system. Use the context menu of the device icons to select an action (un/mounting, opening, playing, ejecting) or double click to mount and open the device in your default file manager. You can use the preferences menu to change the file manager, autoplay setting, and multimedia programs.

5- NetworkMgr. Clicking on the icon shows the menu from which you can connect to wireless networks.

6- Date and time. Clicking in that area brings up a calendar.



Key Bindings

1- Global Key Bindings

KEYS

ALT+F2

CTRL+ALT+L

CTRL+SPACE

PRINT

FUNCTION

Open DSBExec to execute a command.

Lock the screen.

Open dmenu-run to execute a command.

Open XFCE 4 screenshooter.

2- Terminal Key Bindings

KEYS

CTRL++

CTRL+-

SHIFT+CTRL+C

SHIFT+CTRL+V

SHIFT+CTRL+T

SHIFT+CTRL+W

ALT+LEFT CURSOR

ALT+RIGHT CURSOR

ALT+[1-9]

CTRL+SHIFT+S

CTRL+SHIFT+LEFT MOUSE BUTTON

F11

SHIFT+PAGEUP

SHIFT+PAGEDOWN

CTRL+SHIFT+UP

CTRL+SHIFT+DOWN

FUNCTION

Increase font size.

Decrease font size

Copy selected text

Paste copied text

Open a new tab

Close current tab

Previous tab

Next tab

Switch to tab N (1-9)

Toggle scrollbar

Open link

Fullscreen

Scroll up one page

Scroll down on page


Scroll up one line

Scroll down one line



Enable/Disable Desktop Components & Auto-Start Programs

The program **DSBAutostart** (Openbox menu → **Settings** → **Autostart Settings**) allows you to control which programs are automatically executed when the graphical interface starts. Further, it allows you to enable/disable some components of the NomadBSD desktop. The changes take place after logging out and in again.






Adding Applications to the *Plank* Panel

Open your preferred graphical file manager, and navigate to `/usr/local/share/applications`. You can also get there by clicking the shortcut Applications on the side pane. Use Drag&Drop to add application icons to the plank panel.

Display Manager Settings: Auto Login, Default User & Theme



The display manager, SLiM, used by NomadBSD is configured to automatically log in the default user `nomad`. The program `nomadbsd-dmconfig` (Openbox menu → Settings → Display manager settings) allows you to change/disable the default user, and to enable/disable auto login. Furthermore, it lets you change the theme. If you want to add a new theme, copy the theme's directory to `/usr/local/share/slim/themes/`. To see a preview in `nomadbsd-dmconfig` copy a screenshot of the login screen to

`/usr/local/share/slim/themes/your-theme-name/preview.png`.



Adding A Preconfigured User Account

If you want to add a further preconfigured user account use `nomadbsd-adduser` (**Openbox menu → System → Add user**). Since NomadBSD is configured to automatically log in the user `nomad` you need to change that behaviour in order to be able to log in as another user. See `nomadbsd-dmconfig`.

Filesystems

NomadBSD comes with a bunch of pre-installed filesystems (CD9660, FAT, HFS+, NTFS, Ext2/3/4). You can mount storage devices via DSBMC (see Overview), which is a graphical client for DSBMD.

1- Automount

You can enable automount in DSBMC under **File → Preferences → Automatically mount devices**

Alternatively, you can use `dsbmc-cli`: Execute the command `dsbmc-cli -a` to automount all currently connected storage devices, and to enable automounting on devices attached later to the system. To start this command automatically on session start, open `DSBAutostart`, and add a new entry for the above command.

2- Extending Filesystem Support

The following subsections describe how to extend the filesystems support. Rebooting the system, or restarting DSBMD is not necessary.



2.1- ExFat

Unfortunately, sysutils/fusefs-exfat requires a license from Microsoft®, and so it can't be pre-installed. You have to build it yourself by using the ports:

```
# pkg install autoconf automake
# svnlite co https://svn.freebsd.org/ports/head/Mk /usr/ports/Mk
# svnlite co https://svn.freebsd.org/ports/head/Templates /usr/ports/Templates
# svnlite co https://svn.freebsd.org/ports/head/sysutils/fusefs-exfat /tmp/fusefs-exfat
# cd /tmp/fusefs-exfat
# make DISTDIR=/tmp install
```

or the [Git repo](#):

```
# pkg install autoconf automake
# git clone https://github.com/relan/exfat.git
# cd exfat
# autoreconf --install
# ./configure
# make && make install
```

2.2- BTRFS & XFS

Install the package fusefs-lkl for BTRFS and XFS support.

```
# pkg install fusefs-lkl
```

nomad
BSD



Networking

Wireless Networking

The program networkmgr, which runs in the tray, allows you to connect to wireless networks.

Installing Software Packages

You can install and upgrade software packages with OctoPkg (Openbox menu → System → OctoPkg) which is a graphical front-end to FreeBSD's pkg.

Installing Linux® Browsers for Watching Netflix, Prime Video, etc.

The program lbi-gui (Openbox menu → Network → Linux Browser Installer GUI) allows you to install Widevine capable Linux versions of the Chromium and Brave browser.




Graphics

1- Multihead setup

By default, NomadBSD enables all connected outputs (monitors). The tool Arandr (Openbox menu→ Settings → Arandr) allows you to configure the position, resolution, etc. of your monitors. Save your changes to `~/.screenlayout/default.sh` which is automatically executed on session start.

2- Changing Display Settings

The program (Openbox menu→ Settings → Display Settings) allows you to change the brightness, gamma, screen mode, display power management (DPMS) settings, etc.





Sound

Selecting The Default Audio Device

Right-click on the speaker/volume indicator icon in the panel, and choose Preferences from the menu. In the preferences window go to the Default device tab, select the sound card/device, and click on Ok. In order to take effect make sure to restart your audio application(s).

Use An Alternative Window Manager

You can install different window managers and desktop environments on NomadBSD. Select the one you want to start by pressing <F1> in the graphical login manager (SLiM).

Advanced Topic

You can install different window managers and desktop environments on NomadBSD. Select the one you want to start by pressing <F1> in the graphical login manager (SLiM).

1- Resetting NomadBSD

If you are a tester, or your experiments with the systems left a total mess, you might want to reset NomadBSD.

Warning: The reset will delete /home, /private, /etc, /var, /root, and /usr.local/etc. Make a backup if there are any files you want to keep.

nomad BSD



You can reset NomadBSD as follows:

1. Boot into single-user mode by (re)booting and choosing 2 in the boot menu.
2. Execute `/usr/libexec/nomadbsd-reset`

After rebooting you'll be greeted by the setup again.

1.1- Limitations

If you have modified or deleted system files from directory trees other than `/home`, `/private`, `/etc`, `/var`, `/root`, `/tmp`, and `/usr.local/etc`, you might not be able to cleanly reset NomadBSD.

2- Disabling The Automatic Graphics Driver Setup

If you want to create your own graphics driver settings, you can disable `initgfx` by adding:

`initgfx_enable="NO"` to `/etc/rc.conf`.

3- Installing NomadBSD on A Hard Disk

Start Openbox menu → System → NomadBSD Installer and follow the instructions.

Note: The NomadBSD installer will use the entire disk. Installing to a single partition is currently not possible.

nomad BSD



NomadBSD Installation Wizard

Please select the device you want to install NomadBSD on

ada0 - TOSHIBA MK3252GSX LV010M

Target filesystem type

☒ UFS
☐ ZFS

☐ Enable lenovofix

Desired size of the swap partition

2048 MB

Username*

settler

☐ Auto-login user

* The installation script will adopt nomad's complete account. Only the username changes.

Back Next Cancel

4- Running NomadBSD in Virtualbox™

1- Download and extract an image you intend to run.

2- Create a virtual harddisk (VDI) from the image:

```
VBoxManage convertfromraw nomadbsd-  
x.y.z.img \  
nomadbsd-x.y.z.vdi --format VDI
```

3- Change the size of the virtual harddisk, so that you have enough space to store files, and install packages. NomadBSD's base system requires approx.


4 GB, so resizing the VDI to 8 GB (8000 MB), which is the minimum recommended size, will give you about 4 GB for your files.

```
VBoxManage modifyhd nomadbsd-x.y.z.vdi --resize 8000
```

Note: Increasing the size of the VDI after running the NomadBSD setup will not have any effect on NomadBSD's filesystem capacity.

4- Start VirtualBox™, and create a new virtual machine. Select Use an existing virtual hard disk file in the Hard disk settings, and choose nomadbsd-x.y.z.vdi which we created in 2. step.

nomad BSD



5- Go to Settings → Display and set the video memory to 128MB or more.

6- Go to Settings → System → Processor and set the number of processors to 2.

Installing Linux® Packages

Before you can install Linux® packages it is necessary to enable Linux® binary compatibility. Let's say you want to install linux-sublime you can proceed as follows:

```
# sysrc linux_enable=YES  
# service abi start  
# pkg install linux-sublime
```

Troubleshooting

1- Errata

If you experience any problems, consult the NomadBSD Errata first.



2- Boot Problems

The boot process stops at the mountroot prompt

If you are using a USB 3.X port, try to use a USB 2.X port instead.

3- Graphics

Automatic graphics card detection crashes the system

If the graphics driver detection crashes the system, you can use a non-accelerated fallback driver (VESA or SCFB) by disabling the automatic detection in the boot menu. Press g or 7 to toggle it.

ATI/AMD

If you are booting a system with ATI/AMD graphics via UEFI, you might experience some problems. Due to a conflict with the EFI framebuffer, NomadBSD might crash or hang when the graphics driver gets loaded, or it just isn't able to start the X window system.

Try the following workaround:

- 1- (Re)boot and enter the boot submenu Boot Options (6).
- 2- Change Disable syscons to On by pressing the key matching the item number.
- 3- Go back to main menu, and press <Enter> to boot.

Note: You won't see any boot messages until the graphics driver gets loaded.

NVIDIA

If you see an error message like device_attach: nvidia0 attach returned 6 you could try to add debug.acpi.disabled="sysres" to /boot/loader.conf.



Distorted/squished EFI framebuffer screen

If you happened to see that the screen content seems to be squished into the upper 1/3 of your monitor you can try the following:

- 1- Reboot, and then enter the loader prompt by pressing 3 at the boot menu.
- 2- Type:

```
gop set 0  
boot
```

If that didn't solve the problem, enter the loader prompt as described above, and type `list gop` to see a list of supported modes. According to the list try another mode number for the `gop set` command in 2.). If you found a mode that resolves the problem, you can save that setting by adding the line `exec="gop set X"` to `/boot/loader.conf`, where X is the mode number.

Another way to solve this problem is to boot your system in legacy mode. Consult your EFI/BIOS manual.

Hybrid Combination/Switchable Graphics

NomadBSD doesn't support switchable graphics like Optimus yet. If the Xorg server fails to start, disable one of the GPUs in your system's BIOS/UEFI.

nomad
BSD



nomad BSD | HANDBOOK

Check our website for more information

www.nomadbsd.org