



## **NSO 5.7 User Guide**

**Release:** NSO 5.7.1

**Published:** May 17, 2010

**Last Modified:** January 26, 2022

### **Americas Headquarters**

Cisco Systems, Inc.  
170 West Tasman Drive  
San Jose, CA 95134-1706  
USA  
<http://www.cisco.com>  
Tel: 408 526-4000  
800 553-NETS (6387)  
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: <https://www.cisco.com/go/trademarks>. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

This product includes software developed by the NetBSD Foundation, Inc. and its contributors.

This product includes cryptographic software written by Eric Young (eay@cryptsoft.com).

This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit <http://www.openssl.org/>.

This product includes software written by Tim Hudson (tjh@cryptsoft.com).

U.S. Pat. No. 8,533,303 and 8,913,519

Copyright © 2010, 2011, 2012, 2013, 2014, 2015, 2016, 2017, 2018, 2019, 2020, 2021, 2022 Cisco Systems, Inc. All rights reserved.



## CONTENTS

---

### CHAPTER 1

<b>NSO Introduction</b>	<b>1</b>
The Orchestration Challenge	1
How NSO Addresses the Orchestration Challenge	1
High-Availability and Clustering	3

---

### CHAPTER 2

<b>The NSO CLI</b>	<b>5</b>
CLI Quick Start	5
Overview	7
Two CLI modes	8
Operational mode	8
Configure mode	8
Starting the CLI	9
Basics	9
Two CLI styles	10
Starting the CLI in an overloaded system	11
Modifying the configuration	11
Command output processing	13
Count the Number of Lines in the Output	14
Search for a String in the Output	14
Saving the Output to a File	15
Regular expressions	15
Displaying the configuration	16
Range expressions	20
Command history	21
Command line editing	21
Moving the cursor:	21
Delete characters:	21
Insert recently deleted text:	22

Display previous command lines:	22
Capitalization:	22
Special:	22
Using CLI completion	23
Comments, annotations and tags	23
CLI messages	25
ncs.conf settings	25
CLI Environment	25
Commands	27
Operational mode commands	27
Configure mode commands	32
Customizing the CLI	36
Adding new commands	36
File access	36
Help texts	36
Quoting and escaping scheme	37
Canonical quoting scheme	37
Escape backslash handling	37
Octal numbers handling	37

---

## CHAPTER 3

<b>The NSO Device Manager</b>	<b>39</b>
Introduction	40
The Managed Device Tree	41
The NED Packages	44
Starting the NSO Daemon	45
Synchronizing Devices	45
Partial sync-from	49
Configuring Devices	50
Connection Management	51
Authentication Groups	53
Caveats	58
Device Session Pooling	58
Device Session Limits	62
Tracing Device Communication	63
Checking Device Configuration	64

Comparing Device Configurations	66
Initialize Device	67
From other	67
By Template	68
Device Templates	70
Tags	72
Debug	72
Oper State and Admin State	73
Configuration Source	75
Capabilities, Modules and Revision Management	76
Discovery of a NETCONF Device	77
Configuration Datastore Support	78
Action Proxy	79
Device Groups	80
Policies	82
Commit Queue	83
Commit Queue Scheduling	84
Viewing and Manipulating the Commit Queue	85
Commit Queue in a Cluster Environment	88
Configuring Commit Queue in a Cluster Environment	89
Error Recovery with Commit Queue	89
Commit Queue Tuning	93
NETCONF Call Home	94
Notifications	94
An Example Session	95
Subscription Status	99
SNMP Notifications	100
Inactive configuration	100

---

**CHAPTER 4**

<b>SSH Key Management</b>	<b>101</b>
General	101
NSO as SSH Server	101
Host Keys	102
Publickey Authentication	102
NSO as SSH Client	102

Host Key Verification	102
Publickey Authentication	104

---

## CHAPTER 5

<b>Managing Network Services</b>	<b>107</b>
Overview	107
A Service Example	108
Running the example	110
Service-Life Cycle Management	112
Service Changes	112
Service Impacting out-of-band changes	113
Service Deletion	114
Viewing service configurations	115
Using Commit queues	117
Un-deploying Services	118
Advanced Services Orchestration	118
RFM service plans	119
Service progress monitoring	120

---

## CHAPTER 6

<b>The Alarm Manager</b>	<b>121</b>
Alarm Manager Introduction	121
Overview of the alarm concepts	123
The Alarm Model	125
Alarm handling	128

---

## CHAPTER 7

<b>Plug-and-play scripting</b>	<b>133</b>
Introduction	133
Script storage	133
Script interface	134
Loading of scripts	134
Command scripts	135
Command section	135
Param section	135
Full command example	136
Policy scripts	139
Policy section	139
Validation	140

	Full policy example	140
	Post-commit scripts	142
	Post-commit section	142
	Full post-commit example	142
<hr/>		
<b>CHAPTER 8</b>	<b>Compliance reporting</b>	<b>145</b>
	Introduction	145
	Creating compliance report definitions	145
	Running compliance reports	148
<hr/>		
<b>CHAPTER 9</b>	<b>NSO Packages</b>	<b>153</b>
	Overview	153
	Listing Packages	153
<hr/>		
<b>CHAPTER 10</b>	<b>Life-cycle Operations - how to manipulate existing services and devices</b>	<b>155</b>
	Commit flags and device & service actions	155
	Commit Flags	155
	Device Actions	159
	Service Actions	163
<hr/>		
<b>CHAPTER 11</b>	<b>The Web User Interface</b>	<b>167</b>
	Overview	167
	Using the Web UI	167
	Transactions and Commit	167
<hr/>		
<b>CHAPTER 12</b>	<b>The Network Simulator</b>	<b>169</b>
	Overview	169
	Using Netsim	169
	Using ConfD Tools with Netsim	171
	Learn more	171







## CHAPTER

# 1

## NSO Introduction

---

Cisco Network Service Orchestrator (NSO) version 5.7.1 is an evolution of the Tail-f Network Control System (NCS). Tail-f was acquired by Cisco in 2014. The product has been enhanced and forms the base for Cisco NSO. Note that the terms 'ncs' and 'tail-f' are used extensively in file names, command-line command names, YANG models, application programming interfaces (API), etc. Throughout this document we will use NSO to mean the product, which consists of a number of tools and executables. These executable components will be referred to by their command line name, e.g. **ncs**, **ncs-netsim**, **ncs\_cli**, etc.

- [The Orchestration Challenge, page 1](#)
- [How NSO Addresses the Orchestration Challenge, page 1](#)
- [High-Availability and Clustering, page 3](#)

## The Orchestration Challenge

The industry is rapidly moving towards a service-oriented approach to network management, where complex services are supported by multi-vendor devices, physical and virtual. To manage these, operators are starting a transition from manually managing devices towards a situation where an operator is actively managing the various aspects of *services*.

*Configuring the services* and the affected devices are among the largest cost-drivers in provider networks. Still, the common orchestration and configuration management practice involves pervasive manual work or ad hoc scripting. Why do we still apply these sorts of techniques to the configuration management problem? Two of the primary reasons are the *variations of services* and the constant *change of devices*. These two underlying characteristics are, to some degree, blocking automated solutions, since it takes too long to update the solution to cope with daily changes.


Time-to-market requirements are critical for a new service to be deployed quickly and the delay in configuring the corresponding tools has a significant impact on revenue. There is an unserved need in provider networks for tools which address these complex and sometimes contradictory challenges while constructing service configurations.

## How NSO Addresses the Orchestration Challenge

NSO enables service providers to dynamically adopt the orchestration solution according to changes in the offered service portfolio. This is enabled by using a model-driven architecture where service definitions can be changed on the fly. Rather than a hard-coded orchestrator, NSO learns from the service models. Service models are written in YANG (RFC 6020).

NSO delivers an automated orchestration solution towards hybrid multi-vendor network. The network can be a mix of traditional equipment, virtual devices and SDN Controllers. This flexibility is managed by a Network Element Driver, NED, layer that abstracts the device interfaces and the Device Manager which enables generic device configuration functions.

**Figure 1. NSO Logical Architecture**



At the core of NSO is the configuration datastore, CDB, that is in sync with the actual device and service configuration. It also manages relationships between services and devices and can handle revisions of device interfaces.

The *Service Manager* addresses the following challenges:

- Transaction-safe activation of services across different multi-vendor devices.
- What-if scenarios, (dry-run), showing the effects on the network for a service creation/change.
- Maintaining relationships between services and corresponding device configurations and vice versa.
- Modeling of services
- Short development and turn-around time for new services.
- Mapping the service model to device models.

The *Device Manager* supports the following overall features:

- Deploy configuration changes to multiple devices in a fail-safe way using distributed transactions.
- Validate the integrity of configurations before deploying to the network.
- Apply configuration changes to named device groups.
- Apply templates (with variables) to named device groups.
- Easily roll back changes, if needed.
- Configuration audits: Check if device configurations are in synch with the NSO database. If they are not, what is the diff?
- Synchronize the NSO database and the configurations on devices, in case they are not in synch. This can be done in either direction (import the diff to the NSO database or deploy the diff on devices).

NSO provides user interfaces as well as northbound APIs for integration to other systems. The main user interface is the NSO network-wide CLI which gives a unified CLI towards the complete network including the network services. This User Guide will illustrate most of the functions using the CLI. NSO also provides a Web UI.

The northbound APIs are available in different language bindings (Java, Python), and as protocols, like NETCONF and REST.

In order to support dynamic updates of functionality as added or modified service models, support for a new device type etc, NSO manages extensions as well defined packages. Every NED is its own package with its own release life-cycle. Every service model with corresponding mapping is also a package of its own. These can be upgraded without upgrading NSO itself.

**Note**

---

When running NSO against real devices, (not just the NSO network simulator for educational purposes), make sure you have the correct NED package version from the delivery repository.

---

In order to learn how to use NSO and also to simplify development using NSO, NSO comes with a network simulator, **ncs-netsim**. Many of the examples will use netsim as the network.

## High-Availability and Clustering

NSO supports a 1:M high-availability mode. One NSO system can be primary and it can have any number of secondaries. Any configuration write has to go through the primary node. The configuration changes are replicated to the read-only secondaries. The replication can be done in asynchronous or synchronous mode. In the synchronous the transaction returns when the secondaries are in sync.

For large networks the network devices can be clustered across NSO systems. Say you have 100 000 devices split in two continents. You may choose to have 50 000 devices in one NSO and 50 000 in another. There are several options on how to configure clusters to see the whole network. The most common is a top NSO where also services are provisioned, and the top NSO sees the whole network.





## CHAPTER 2

# The NSO CLI

---

- [CLI Quick Start, page 5](#)
- [Overview, page 7](#)
- [Starting the CLI, page 9](#)
- [Modifying the configuration, page 11](#)
- [Command output processing, page 13](#)
- [Displaying the configuration, page 16](#)
- [Range expressions, page 20](#)
- [Command history, page 21](#)
- [Command line editing, page 21](#)
- [Using CLI completion, page 23](#)
- [Comments, annotations and tags, page 23](#)
- [CLI messages, page 25](#)
- [ncs.conf settings, page 25](#)
- [CLI Environment, page 25](#)
- [Commands, page 27](#)
- [Customizing the CLI, page 36](#)
- [Quoting and escaping scheme, page 37](#)

## CLI Quick Start

The NSO CLI (command line interface) provides a unified CLI towards the complete network. The NSO CLI is a northbound interface to the NSO representation of the network devices and network services. Do not confuse this with a cut-through CLI that reaches the devices directly. Although the network might be a mix of vendors and device interfaces with different CLI flavors, NSO provides *one* northbound CLI.

Starting the CLI:

```
$> ncs_cli -C -u admin
```

Note the use of the **-u** parameter which tells NSO which user to authenticate towards NSO. It is a common mistake to forget this. This user must be configured in NSO AAA (Authentication, Authorization and Accounting).

Like many CLI:s there is an operational mode and a configuration mode. Show commands displays different data in those modes. A show in configuration mode displays network configuration data from the NSO configuration database, the CDB. Show in operational mode shows live values from the devices and any operational data stored in the CDB. The CLI starts in operational mode. Note that different prompts are used for the modes (these can be changed in `ncs.conf` configuration file).

NSO organize all managed devices as a list of devices. The path to a specific device is **devices device *DEVICE-NAME***. The CLI sequence below does the following:

- 1 Show operational data for all devices: fetches operational data from the network devices like interface statistics, and also operational data that is maintained by NSO like alarm counters.
- 2 Move to configuration mode. Show configuration data for all devices: In this example this is done before the configuration from the real devices has been loaded in the network to NSO. At this point only the NSO configured data like IP Address, port etc. are shown.

Show device operational data and configuration data:

```
admin@ncs# show devices device
devices device ce0
...
alarm-summary indeterminates 0
alarm-summary criticals 0
alarm-summary majors 0
alarm-summary minors 0
alarm-summary warnings 0
devices device cel
...
admin@ncs# config
Entering configuration mode terminal
admin@ncs(config)# show full-configuration devices device
devices device ce0
  address 127.0.0.1
  port    10022
  ssh host-key ssh-dss
...
!
devices device cel
...
!
...
```

It can be annoying to move between modes to display configuration data and operational data. The CLI has ways around this.

Show config data in operational mode and vice versa:

```
admin@ncs# show running-config devices device
admin@ncs(config)# do show running-config devices device
```

Look at the device configuration above, there is no configuration that relates to the actual configuration on the devices. In order to boot-strap NSO and discover the device configuration it is possible to perform an action to synchronize NSO from the devices, **devices sync-from**. This reads the configuration over available device interfaces and populates the NSO data-store with the corresponding configuration. The device specific configuration is populated below the devices entry in the configuration tree and can be listed specifically.

Perform action to synchronize from devices:

```
admin@ncs(config)# devices sync-from
sync-result {
```

```

        device ce0
        result true
    }
    sync-result {
        device ce1
        result true
    }
    ...

```

Display the device configuration after the synchronization:

```

admin@ncs(config)# show full-configuration devices device ce0 config
devices device ce0
config
  no ios:service pad
  no ios:ip domain-lookup
  no ios:ip http secure-server
  ios:ip source-route
  ios:interface GigabitEthernet0/1
  exit
  ios:interface GigabitEthernet0/10
  exit
  ios:interface GigabitEthernet0/11
  exit
  ios:interface GigabitEthernet0/12
  exit
  ios:interface GigabitEthernet0/13
  exit
  ...
!
!
...

```

## Overview

NSO provides a network CLI in two different style (selectable by the user): J-style and C-style. The CLI is automatically rendered using the data models described by the YANG files. There are three distinctly different types of YANG files, the built-in NSO models describing the device manager and the service manager, models imported from the managed devices and finally service models. Regardless of model type, the NSO CLI seamlessly handles all models as a whole.

This creates a auto-generated CLI, without any extra effort, except the design of our YANG files. The auto-generated CLI supports the following features:

- Unified CLI across complete network, devices and network services.
- Command line history and command line editor.
- Tab completion for content of the configuration database.
- Monitoring and inspecting log files.
- Inspecting the system configuration and system state.
- Copying and comparing different configurations, for example, between two interfaces or two devices.
- Configuring common setting across a range of devices.

The CLI contains commands for manipulating the network configuration.

A alias provides a shortcut for a complex command.

Alias expansion is performed when a command line is entered. Aliases are part of the configuration and are manipulated accordingly. This is done by manipulating the nodes in the alias configuration tree.

Actions in the YANG files are mapped into actual commands. In J-style CLI actions are mapped to the **request** commands.

Even though the auto-generated CLI is fully functional it can be customized and extended in numerous ways:

- Built-in commands can be moved, hidden, deleted, reordered and extended.
- Confirmation prompts can be added to built-in commands.
- New commands can be implemented using the Java API, ordinary executables and shell scripts.
- New commands can be mounted freely in the existing command hierarchy.
- The built-in tab completion mechanism can be overridden using user defined callbacks.
- New command hierarchies can be created.
- A command timeout can be added, both a global timeout for all commands, and command specific timeouts.
- Actions and parts of the configuration tree can be hidden and can later be made visible when the user enters a password.

How to customize and extend the auto-generated CLI is described in the Plug-and-play scripting section [Chapter 7, Plug-and-play scripting](#).

## Two CLI modes

The CLI is entirely data model driven. The YANG model(s) define a hierarchy of configuration elements. The CLI follows this tree.

The NSO CLI provides various commands for configuring and monitoring software, hardware, and network connectivity of managed devices. The CLI supports two modes: *operational mode*, for monitoring the state of the NSO node; and *configure mode*, for changing the state of the network.

The prompt indicates which mode the CLI is in. When moving from operational mode to configure mode using the **configure** command, the prompt is changed from `host#` to `host(config)#`. The prompts can be configured using the *c-prompt1* and *c-prompt2* settings in the `ncs.conf` file.

For example:

```
admin@ncs# configure
Entering configuration mode terminal
admin@ncs(config)#
```

## Operational mode

Operational mode is the initial mode after successful login to the CLI. It is primarily used for viewing the system status, controlling the CLI environment, monitoring and troubleshooting network connectivity, and initiating the configure mode.

The list of base commands available in operational mode is listed below in the "Operational mode commands" section. Additional commands are rendered from the loaded YANG files.

## Configure mode

Configure mode can be initiated by entering the **configure** command in operational mode. All changes to the network configuration are done to a copy of the active configuration. These changes do not take effect until a successful **commit** or **commit confirm** command is entered.

The list of base commands available in configure mode is listed below in the "Configure mode commands" section. Additional commands are rendered from the loaded YANG files.



# Starting the CLI

## Basics

The CLI is started using the **ncs\_cli** program. It can be used as a login program (replacing the shell for a user), started manually once the user has logged in, or used in scripts for performing CLI operations.

In some NSO installations, ordinary users would have the **ncs\_cli** program as login shell, and the root user would have to login and then start the CLI using **ncs\_cli**, whereas in others, the **ncs\_cli** can be invoked freely as a normal shell command.

The **ncs\_cli** program supports a range of options, primarily intended for debug and development purposes (see description below).

The **ncs\_cli** program can also be used for batch processing of CLI commands, either by storing the commands in a file and running **ncs\_cli** on the file, or by having the following line at the top of the file (with the location of the program modified appropriately):

```
#!/bin/ncs_cli
```

When the CLI is run non-interactively it will terminate at the first error and will only show the output of the commands executed. It will not output the prompt or echo the commands. This is the same behavior as for shell scripts.

To run a script non-interactively, such as a script or through a pipe, and still produce prompts and echo commands, use the `--interactive` option.

Command line options:

**ncs\_cli --help**

Usage: ncs\_cli [options] [file]

Options:

```
--help, -h           display this help
--host, -H <host>    current host name (used in prompt)
--address, -A <addr> cli address to connect to
--port, -P <port>    cli port to connect to
--cwd, -c <dir>      current working directory
--proto, -p <proto>  type of connection (tcp, ssh, console)
--verbose, -v        verbose output
--ip, -i             clients source ip[/port]
--interactive, -n    force interactive mode
--escape-char, -E <C> brute force shutdown when user enters ASCII C
-J                 Juniper style CLI
-C                 Cisco XR style CLI
--user, -u <user>    clients user name
--uid, -U <uid>      clients user id
--groups, -g <groups> clients group list
--gids, -D <gids>    clients group id list
--gid, -G <gid>     clients group id
--noaaa            disable AAA
--opaque, -O <opaque> pass opaque info
```

**--host**                The argument to host should be the host name of the device. The **ncs\_cli** program will use the result of the system call `gethostname()` as default value. The host name is used in the CLI prompt.

**--address**            If NSO has been configured to listen to a different address than 127.0.0.1 for the communication between subsystems, then that address should be given as argument to address. This can be modified by using the to use the `NCS_IPC_ADDRESS`

	environment variable or recompile the <b>ncs_cli</b> program with the new address compiled in.
<code>--port</code>	If NSO has been configured to use a non-default port for the communication between subsystems, then that port number should be given as argument to <code>port</code> . This can be modified by using the <code>NCS_IPC_PORT</code> environment variable or recompile the <b>ncs_cli</b> program with the new port compiled in.
<code>--cwd</code>	Directory to use as current working directory in the CLI. Normally the user's home directory. The default is the directory where the <b>ncs_cli</b> program is started.
<code>--proto</code>	Should be the protocol used by the user to connect to the box, one of <b>tcp</b> , <b>ssh</b> , and <b>console</b> . The default is <b>ssh</b> for connections established with OpenSSH (the program inspects the <code>SSH_CONNECTION</code> environment variable), and <b>console</b> for everything else. This value is printed in the audit logs.
<code>--verbose</code>	If this argument is given, then the <b>ncs_cli</b> program will be a bit more talkative during the NSO handshake phase.
<code>--ip</code>	Should be the user's source IP address, if the user connects through SSH or telnet. The default is 127.0.0.1 to indicate the console. This value is printed in the audit logs.
<code>--interactive</code>	Force the CLI to echo commands and prompts even when not invoked from a terminal, i.e. when reading input from a file or through a pipe.
<code>--escape-char</code>	It is possible to forcefully terminate the CLI by repeating a special character three times in a row. The default character is control underscore. It can be changed to an arbitrary character using this option.
<code>-J</code>	Starts the CLI in J-style.
<code>-C</code>	Starts the CLI in C-style, Cisco XR style.
<code>--user</code>	The name of the user connecting. Used to set proper access rules and assign proper groups (if the group mapping is kept in NSO). The default is to use the login name of the user.
<code>--uid</code>	The numeric user id of the connected user. The uid will be used when executing <code>osCommands</code> , when checking file access permissions, and when creating files.
<code>--gid</code>	The numeric group id of the connected user. The gid will be used when executing <code>osCommands</code> , when checking file access permissions, and when creating files.
<code>--groups</code>	The argument to groups should be a comma-separated list of groups. The default is to send the OS groups that the user belongs to, i.e. the same as the <b>groups</b> shell command gives us.
<code>--gids</code>	The argument to gids should be a comma-separated list of numeric group ids representing the Unix supplementary groups for the user. These are used when executing <code>osCommands</code> and when checking file access permissions.
<code>--noaaa</code>	Disables AAA. This is useful during development but should be removed in a production system.
<code>--opaque</code>	Provide an opaque string that can be read by connecting data providers.

## Two CLI styles

The CLI comes in two flavors C-Style (Cisco XR style) and J-style. It is possible to choose one specifically or switch between them.

Starting the CLI (C-style, Cisco XR style):

```
$> ncs_cli -C -u admin
```

Starting the CLI (J-style):

```
$> ncs_cli -J -u admin
```

It is possible to interactively switch between these styles while inside the CLI using the builtin **switch** command:

```
admin@ncs# switch cli
```

C-style is mainly used throughout the documentation for examples etc. except if otherwise stated.

## Starting the CLI in an overloaded system

If the number of ongoing sessions have reached the configured system limit, no more CLI sessions will be allowed until one of the existing sessions have been terminated.

This makes it impossible to get into the system. A situation which may not be acceptable. The CLI therefore has a mechanism for handling this problem. When the CLI detects that the session limit has been reached it will check if the new user has privileges to execute the logout command. If the user does it will display a list of the current user sessions in NSO and ask the user if one of the sessions should be terminated to make room for the new session.

## Modifying the configuration

Once NSO synchronized with the devices configuration, done by using the **devices sync-from** command, it is possible to modify the devices. The CLI is used to modify the NSO representation of the device configuration and then committed as a transaction to the network.

As an example, to change the the speed setting on the interface GigabitEthernet0/1 across several devices:

```
admin@ncs(config)# devices device ce0..1 config ios:interface GigabitEthernet0/1 speed auto
admin@ncs(config-if)# top
admin@ncs(config)# show configuration
devices device ce0
  config
    ios:interface GigabitEthernet0/1
      speed auto
    exit
  !
!
devices device cel
  config
    ios:interface GigabitEthernet0/1
      speed auto
    exit
  !
!
admin@ncs(config)# commit ?
Possible completions:
  and-quit           Exit configuration mode
  check              Validate configuration
  comment            Add a commit comment
  commit-queue       Commit through commit queue
  label              Add a commit label
  no-confirm         No confirm
  no-networking      Send nothing to the devices
  no-out-of-sync-check Commit even if out of sync
  no-overwrite       Do not overwrite modified data on the device
  no-revision-drop   Fail if device has too old data model
  save-running       Save running to file
  ---
```

```

dry-run                Show the diff but do not perform commit
[<cr>
admin@ncs(config)# commit
Commit complete.

```

Note the availability of commit flags.

Any failure on any device will make the whole transaction fail. It is also possible to perform a manual rollback, a rollback is the undoing of a commit.

This is operational data and the CLI is in configuration mode so the way of showing operational data in config mode is used.

The command **show configuration rollback changes** can be used to view rollback changes in more detail. It will show what will be done when the rollback file is loaded, similar to loading the rollback and using **show configuration**:

```

admin@ncs(config)# show configuration rollback changes 10019
devices device ce0
config
  ios:interface GigabitEthernet0/1
    no speed auto
  exit
!
!
devices device ce1
config
  ios:interface GigabitEthernet0/1
    no speed auto
  exit
!
!

```

The command **show configuration commit changes** can be used to see which changes were done in a given commit, i.e. the roll-forward commands performed in that commit:

```

admin@ncs(config)# show configuration commit changes 10019
!
! Created by: admin
! Date: 2015-02-03 12:29:08
! Client: cli
!
devices device ce0
config
  ios:interface GigabitEthernet0/1
    speed auto
  exit
!
!
devices device ce1
config
  ios:interface GigabitEthernet0/1
    speed auto
  exit
!
!

```

The command **rollback configuration** can be used to perform the rollback:

```

admin@ncs(config)# rollback configuration 10019
admin@ncs(config)# show configuration
devices device ce0

```

```

config
  ios:interface GigabitEthernet0/1
    no speed auto
  exit
!
!
devices device cel
  config
    ios:interface GigabitEthernet0/1
      no speed auto
    exit
  !
!

```

And now the **commit** the rollback:

```

admin@nbs(config)# commit
Commit complete.

```

When the command **rollback configuration 10019** is run the changes recorded in rollback 10019-N (where N is the highest, thus the most recent rollback number) will all be undone. In other words the configuration will be rolled back to the state it was in before the commit associated with rollback 10019 was performed.

It is also possible to undo individual changes by running the command **rollback selective**. E.g. to undo the changes recorded in rollback 10019, but not the changes in 10020-N run the command **rollback selective 10019**.

This operation may fail if the commits following rollback 10019 depends on the changes made in rollback 10019.

## Command output processing

It is possible to process the output from a command using an output redirect. This is done using the `|` character (a pipe character):

```

admin@nbs# show running-config | ?
Possible completions:
  annotation      Show only statements whose annotation matches a pattern
  append          Append output text to a file
  begin           Begin with the line that matches
  best-effort      Display data even if data provider is unavailable or
                  continue loading from file in presence of failures
  context-match    Context match
  count           Count the number of lines in the output
  csv             Show table output in CSV format
  de-select        De-select columns
  details          Display show/commit details
  display          Display options
  exclude          Exclude lines that match
  extended         Display referring entries
  hide            Hide display options
  include          Include lines that match
  linnum           Enumerate lines in the output
  match-all       All selected filters must match
  match-any        At least one filter must match
  more            Paginate output
  nomore           Suppress pagination
  save            Save output text to a file
  select           Select additional columns

```

<code>sort-by</code>	Select sorting indices
<code>tab</code>	Enforce table output
<code>tags</code>	Show only statements whose tags matches a pattern
<code>until</code>	End with the line that matches

The precise list of pipe commands depends on the command executed. Some pipe commands, like `select` and `de-select` are only available for the **show** command, whereas others are universally available.

Note that the **tab** pipe target is used to enforce table output which is only suitable for the list element. Naturally the table format is not suitable to display arbitrary data output since it needs to map the data to columns and rows. For example:

```
show running-config | tab
show running-config | include aaa | tab
```

clearly are not suitable because the data has a nested structure. It could take incredibly long time to display it if you use the **tab** pipe target on a huge amount of data which is not a list element.

## Count the Number of Lines in the Output

This redirect target counts the number of lines in the output. For example:

```
admin@ncs# show running-config | count
Count: 1783 lines
admin@ncs# show running-config aaa | count
Count: 28 lines
```

## Search for a String in the Output

The **include** targets is used to only include lines matching a regular expression:

```
admin@ncs# show running-config aaa | include aaa
aaa authentication users user admin
aaa authentication users user oper
aaa authentication users user private
aaa authentication users user public
```

In the example above only lines containing `aaa` are shown. Similarly lines not containing a regular expression can be included. This is done using the **exclude** target:

```
admin@ncs# show running-config aaa authentication | exclude password
aaa authentication users user admin
  uid      1000
  gid      1000
  ssh_keydir /var/ncs/homes/admin/.ssh
  homedir   /var/ncs/homes/admin
!
aaa authentication users user oper
  uid      1000
  gid      1000
  ssh_keydir /var/ncs/homes/oper/.ssh
  homedir   /var/ncs/homes/oper
!
aaa authentication users user private
  uid      1000
  gid      1000
  ssh_keydir /var/ncs/homes/private/.ssh
  homedir   /var/ncs/homes/private
!
aaa authentication users user public
```

```
uid      1000
gid      1000
ssh_keydir /var/ncs/homes/public/.ssh
homedir   /var/ncs/homes/public
!
```

It is possible to display context for a match using the pipe command **include -c**. Matching lines will be prefixed by `<line no>:` and context lines with `<line no>.` For example:

```
admin@ncs# show running-config aaa authentication | include -c 3 homes/admin
2- uid      1000
3- gid      1000
4- password  $1$brH6BYLy$iWQA2TlI3PMonDTJ0d0Y/1
5: ssh_keydir /var/ncs/homes/admin/.ssh
6: homedir   /var/ncs/homes/admin
7-!
8-aaa authentication users user oper
9- uid      1000
```

It is possible to display context for a match using the pipe command **context-match**:

```
admin@ncs# show running-config aaa authentication | context-match homes/admin
aaa authentication users user admin
ssh_keydir /var/ncs/homes/admin/.ssh
aaa authentication users user admin
homedir    /var/ncs/homes/admin
```

It is possible to display the output starting at the first match of a regular expression. This is done using the **begin** pipe command:

```
admin@ncs# show running-config aaa authentication users | begin public
aaa authentication users user public
uid      1000
gid      1000
password  $1$DzGnyJGx$BjxoqYEj0QKxwVX5fbfDx/
ssh_keydir /var/ncs/homes/public/.ssh
homedir   /var/ncs/homes/public
!
```

## Saving the Output to a File

The output can also be saved to a file using the **save** or **append** redirect target:

```
admin@ncs# show running-config aaa | save /tmp/saved
```

Or to save the configuration, except all passwords:

```
admin@ncs# show running-config aaa | exclude password | save /tmp/saved
```

## Regular expressions

The regular expressions is a subset of the regular expressions found in `egrep` and in the `AWK` programming language. Some common operators are:

.	Matches any character.
^	Matches the beginning of a string.
\$	Matches the end of a string.
[abc...]	Character class, which matches any of the characters abc... Character ranges are specified by a pair of characters separated by a -.

[^abc...]	negated character class, which matches any character except abc....
r1   r2	Alternation. It matches either r1 or r2.
r1r2	Concatenation. It matches r1 and then r2.
r+	Matches one or more rs.
r*	Matches zero or more rs.
r?	Matches zero or one rs.
(r)	Grouping. It matches r.

For example, to only display uid and gid do the following:

```
admin@ncs# show running-config aaa | include "(uid)|(gid)"
uid      1000
gid      1000
uid      1000
gid      1000
uid      1000
gid      1000
uid      1000
gid      1000
uid      1000
gid      1000
```

## Displaying the configuration

There are several options for displaying the configuration and stats data in NSO. The most basic command consists of displaying a leaf or a subtree of the configuration by giving the path to the element.

To display the configuration of a device do:

```
admin@ncs# show running-config devices device ce0 config
devices device ce0
config
  no ios:service pad
  no ios:ip domain-lookup
  no ios:ip http secure-server
  ios:ip source-route
  ios:interface GigabitEthernet0/1
  exit
  ios:interface GigabitEthernet0/10
  exit
  ...
  !
  !
```

This can also be done for a group of devices by substituting the instance name (ce0 in this case) with a [the section called “Regular expressions”](#).

To display the config of all devices:

```
admin@ncs# show running-config devices device * config
devices device ce0
config
  no ios:service pad
  no ios:ip domain-lookup
  no ios:ip http secure-server
  ios:ip source-route
  ios:interface GigabitEthernet0/1
  exit
  ios:interface GigabitEthernet0/10
  exit
  ...
```



```

!
!
devices device ce1
  config
    ...
!
!
...

```

It is possible to limit the output even further. View only the http settings on each device:

```

admin@ncs# show running-config devices device * config ios:ip http
devices device ce0
  config
    no ios:ip http secure-server
!
!
devices device ce1
  config
    no ios:ip http secure-server
!
!
...

```

There is an alternative syntax for this using the **select** pipe command:

```

admin@ncs# show running-config devices device * | \
  select config ios:ip http
devices device ce0
  config
    no ios:ip http secure-server
!
!
devices device ce1
  config
    no ios:ip http secure-server
!
!
...

```

The **select** pipe command can be used multiple times for adding additional content:

```

admin@ncs# show running-config devices device * | \
  select config ios:ip http | \
  select config ios:ip domain-lookup
devices device ce0
  config
    no ios:ip domain-lookup
    no ios:ip http secure-server
!
!
devices device ce1
  config
    no ios:ip domain-lookup
    no ios:ip http secure-server
!
!
...

```

There is also a **de-select** pipe command that can be used to instruct the CLI to not display certain parts of the config. The above printout could also be achieved by first selecting the ip container, and then de-selecting the source-route leaf:

```

admin@ncs# show running-config devices device * | \
    select config ios:ip | \
    de-select config ios:ip source-route
devices device ce0
config
  no ios:ip domain-lookup
  no ios:ip http secure-server
!
!
devices device ce1
config
  no ios:ip domain-lookup
  no ios:ip http secure-server
!
!
...

```

A use-case for the **de-select** pipe command is to de-select the config container in order to only display the device settings without actually displaying their config:

```

admin@ncs# show running-config devices device * | de-select config
devices device ce0
  address 127.0.0.1
  port 10022
  ssh host-key ssh-dss
  ...
!
  authgroup default
  device-type cli ned-id cisco-ios
  state admin-state unlocked
!
devices device ce1
  ...
!
...

```

The above statements also work for the **save** command. To save the devices managed by NSO, but not the contents of their config container:

```

admin@ncs# show running-config devices device * | \
    de-select config | save /tmp/devices

```

It is possible to use the **select** command to select which list instances to display. To display all devices that has the interface GigabitEthernet 0/0/0/4:

```

admin@ncs# show running-config devices device * | \
    select config cisco-ios-xr:interface GigabitEthernet 0/0/0/4
devices device p0
config
  cisco-ios-xr:interface GigabitEthernet 0/0/0/4
    shutdown
  exit
!
!
devices device p1
config
  cisco-ios-xr:interface GigabitEthernet 0/0/0/4
    shutdown
  exit
!
!
...

```

This means "display all device instances that has the interface GigabitEthernet 0/0/0/4". Only the subtree defined by the select path will be displayed. It is also possible to display the entire content of the config container for each instance by using an additional select statement:

```
admin@ncs# show running-config devices device * | \
    select config cisco-ios-xr:interface GigabitEthernet 0/0/0/4 | \
    select config | match-all
devices device p0
config
  cisco-ios-xr:hostname PE1
  cisco-ios-xr:interface MgmtEth 0/0/CPU0/0
  exit
  ...
  cisco-ios-xr:interface GigabitEthernet 0/0/0/4
  shutdown
  exit
!
!
devices device p1
config
  ...
  cisco-ios-xr:interface GigabitEthernet 0/0/0/4
  shutdown
  exit
!
!
...
```

The **match-all** pipe command is used for telling the CLI to only display instances that matches all select commands. The default behavior is **match-any** which means to display instances that matches any of the given **select** commands.

The **display** command is used to format configuration and statistics data. There are several output formats available, some of these are unique to specific modes, such as configuration or operational mode. The output formats **json**, **keypath**, **xml**, and **xpath** are available in most modes and CLI styles (J, I, and C). The output formats **netconf** and **maagic** are only available if **devtools** has been set to **true** in the CLI session settings.

For instance, assuming we have a data model featuring a set of hosts, each containing a set of servers, we can display the configuration data as JSON. This is depicted in the example below.

```
admin@ncs# show running-config hosts | display json
{
  "data": {
    "pipetargets_model:hosts": {
      "host": [
        {
          "name": "host1",
          "enabled": true,
          "numberOfServers": 2,
          "servers": {
            "server": [
              {
                "name": "serv1",
                "ip": "192.168.0.1",
                "port": 5001
              },
              {
                "name": "serv2",
                "ip": "192.168.0.1",
                "port": 5000
              }
            ]
          }
        }
      ]
    }
  }
}
```

```

    }
  ]
}
},
{
  "name": "host2",
  "enabled": false,
  "numberOfServers": 0
...

```

Still working with the same data model as used in the example above, we might want to see the current configuration in keypath format. The following example shows how to do that, and shows the resulting output.

```

admin@ncs# show running-config hosts | display keypath
/hosts/host{host1} enabled
/hosts/host{host1}/numberOfServers 2
/hosts/host{host1}/servers/server{serv1}/ip 192.168.0.1
/hosts/host{host1}/servers/server{serv1}/port 5001
/hosts/host{host1}/servers/server{serv2}/ip 192.168.0.1
/hosts/host{host1}/servers/server{serv2}/port 5000
/hosts/host{host2} disabled
/hosts/host{host2}/numberOfServers 0

```

## Range expressions

To modify a range of instances at the same time use range expressions or to display a specific range of instances.

Basic range expressions are written with a combination of x..y (meaning from x to y), x,y (meaning x and y) and \* (meaning any value), example:

```
1..4,8,10..18
```

It is possible to use range expressions for all key elements of integer type, both for setting values, executing actions and displaying status and config.

Range expressions are also supported for key elements of non-integer types as long as they are restricted to the pattern `[a-zA-Z-]*[0-9]+/[0-9]+/[0-9]+/.../[0-9]+` and the annotation `tailf:cli-allow-range` is used on the key leaf. This is the case for the device list.

The following can be done in the CLI to display a subset of the devices (ce0, ce1, ce3):

```
admin@ncs# show running-config devices device ce0..1,3
```

If the devices have names with slashes, for example, Firewall/1/1, Firewall/1/2, Firewall/1/3, Firewall/2/1, Firewall/2/2, and Firewall/2/3, expressions like this are possible:

```

admin@ncs# show running-config devices device Firewall/1-2/*
admin@ncs# show running-config devices device Firewall/1-2/1,3

```

In configure mode it is possible to edit a range of instances in one command:

```
admin@ncs(config)# devices device ce0..2 config ios:ethernet cfm ieee
```

or like this:

```

admin@ncs(config)# devices device ce0..2 config
admin@ncs(config-config)# ios:ethernet cfm ieee
admin@ncs(config-config)# show config
devices device ce0

```

```
config
  ios:ethernet cfm ieee
!
!
devices device ce1
  config
    ios:ethernet cfm ieee
  !
!
devices device ce2
  config
    ios:ethernet cfm ieee
  !
!
```

## Command history

Command history is maintained separate for each mode. When entering configure mode from operational for the first time a empty history be used. It is not possible to access the command history from operational mode when in configure mode and vice versa. When exiting back into operational mode access to the command history from the preceding operational mode session will be used. Likewise the old command history from the old configure mode session will be used when re-entering configure mode.

## Command line editing

The default key strokes for editing the command line and moving around the command history are as follows.

### Moving the cursor:

Move the cursor back one character

Ctrl-b or Left Arrow

Move the cursor back one word

Esc-b or Alt-b

Move the cursor forward one character

Ctrl-f or Right Arrow

Move the cursor forward one word

Esc-f or Alt-f

Move the cursor to the beginning of the command line

Ctrl-a or Home

Move the cursor to the end of the command line

Ctrl-e or End

### Delete characters:

Delete the character before the cursor

Ctrl-h, Delete, or Backspace

Delete the character following the cursor

Ctrl-d

Delete all characters from the cursor to the end of the line

Ctrl-k

Delete the whole line  
Ctrl-u or Ctrl-x

Delete the word before the cursor  
Ctrl-w, Esc-Backspace, or Alt-Backspace

Delete the word after the cursor  
Esc-d or Alt-d

## Insert recently deleted text:

Insert the most recently deleted text at the cursor  
Ctrl-y

## Display previous command lines:

Scroll backward through the command history  
Ctrl-p or Up Arrow

Scroll forward through the command history  
Ctrl-n or Down Arrow

Search the command history in reverse order  
Ctrl-r

Show a list of previous commands  
run the "show cli history" command

## Capitalization:

Capitalize the word at the cursor, i.e. make the first character uppercase and the rest of the word lowercase  
Esc-c

Change the word at the cursor to lowercase  
Esc-l

Change the word at the cursor to uppercase  
Esc-u

## Special:

Abort a command/Clear line  
Ctrl-c

Quote insert character, i.e. do not treat the next keystroke as an edit command  
Ctrl-v/ESC-q

Redraw the screen  
Ctrl-l

Transpose characters  
Ctrl-t

Enter multi-line mode. Enables entering multi-line values when prompted for a value in the CLI  
ESC-m

Exit configuration mode.  
Ctrl-z

## Using CLI completion

It is not necessary to type the full command or option name for the CLI to recognize it. To display possible completions, type the partial command followed immediately by <tab> or <space>.

If the partially typed command uniquely identifies a command, the full command name will appear. Otherwise a list of possible completions is displayed.

Long lines can be broken into multiple lines using the backslash (\) character at the end of the line. This is primarily useful inside scripts.

Completion is disabled inside quotes. To type an argument containing spaces either quote them with a \ (e.g. **file show foo\ bar**) or with a " (e.g. **file show "foo bar"**). Space completion is disabled when entering a filename.

Command completion also applies to filenames and directories:

```
admin@ncs# <space>
Possible completions:
  alarms           Alarm management
  autowizard       Automatically query for mandatory elements
  cd               Change working directory
  clear            Clear parameter
  cluster          Cluster configuration
  compare          Compare running configuration to another
                  configuration or a file
  complete-on-space Enable/disable completion on space
  compliance       Compliance reporting
  config           Manipulate software configuration information
  describe         Display transparent command information
  devices          The managed devices and device communication settings
  display-level    Configure show command display level
  exit             Exit the management session
  file             Perform file operations
  help            Provide help information
  ...
admin@ncs# dev<space>ices <space>
Possible completions:
  check-sync        Check if the NCS config is in sync with the device
  check-yang-modules Check if NCS and the devices have compatible YANG
                  modules
  clear-trace       Clear all trace files
  commit-queue      List of queued commits
  ...
admin@ncs# devices check-s<space>ync
```

## Comments, annotations and tags

All characters following a !, up to the next newline are ignored. This makes it possible to have comments in a file containing CLI commands, and still be able to paste the file into the command-line interface. For example:

```
! Command file created by Joe Smith
! First show the configuration before we change it
show running-config
! Enter configuration mode and configure an ethernet setting on the ce0 device
config
devices device ce0 config ios:ethernet cfm global
commit
top
```

```
exit
exit
! Done
```

To enter the comment character as an argument, it has to be prefixed with a backslash (\) or used inside quotes (").

The `/* ... */` comment style is also supported.

When using large configurations it may make sense to be able to associate comments (annotations) and tags with the different parts. Then filter the configuration with respect to the annotations or tags. For example, tagging parts of the configuration that relates to a certain department or customer.

NSO has support for both tags and annotations. There is a specific set of commands available in the CLI for annotating and tagging parts of the configuration. There is also a set of pipe commands for controlling whether the tags and annotations should be displayed and for filtering depending on annotation and tag content.

The commands are:

- **annotate** <statement> <text>
- **tag add** <statement> <tag>
- **tag clear** <statement> <tag>
- **tag del** <statement> <tag>

Example:

```
admin@ncs(config)# annotate aaa authentication users user admin \
"Only allow the XX department access to this user."
admin@ncs(config)# tag add aaa authentication users user oper oper_tag
admin@ncs(config)# commit
Commit complete.
```

In order to view the placement of tags and annotations in the configuration it is recommended to use the pipe command **display curly-braces**. The annotations and tags will be displayed as comments where the tags are prefixed by **Tags:**. For example:

```
admin@ncs(config)# do show running-config aaa authentication users user | \
tags oper_tag | display curly-braces
/* Tags: oper_tag */
user oper {
    uid      1000;
    gid      1000;
    password $1$9qV138GJ$.olmolTfRbFGQhWJMz9kA0;
    ssh_keydir /var/ncs/homes/oper/.ssh;
    homedir   /var/ncs/homes/oper;
}
admin@ncs(config)# do show running-config aaa authentication users user | \
annotation XX | display curly-braces
/* Only allow the XX department access to this user. */
user admin {
    uid      1000;
    gid      1000;
    password $1$EcQwYvnP$Rvq3MPTMSz29UaVOHA/511;
    ssh_keydir /var/ncs/homes/admin/.ssh;
    homedir   /var/ncs/homes/admin;
}
```

It is possible to hide the tags and annotations when viewing the configuration, or to explicitly include them in the listing. This is done using the **display annotations/tags** and **hide annotations/tags** pipe commands. To hide all attributes (annotations, tags and FASTMAP attributes) use the **hide attributes** pipe command.



Annotations and tags are part of the configuration. When adding, removing or modifying an annotation or a tag the configuration needs to be committed similar to any other change to the configuration.

## CLI messages

Messages appear when entering and exiting configure mode, when committing a configuration and when typing a command or value that is not valid:

```
admin@ncs# show c
-----^
syntax error:
Possible alternatives starting with c:
  cli           - Display cli settings
  configuration - Commit configuration changes
admin@ncs# show configuration
-----^
syntax error: expecting
  commit - Commit configuration changes
```

When committing a configuration, the CLI first validates the configuration and if there is a problem it will indicate what the problem is.

If a missing identifier or a value is out of range a message will indicate where the errors are:

```
admin@ncs# config
Entering configuration mode terminal
admin@ncs(config)# nacm rule-list any-group rule allowrule
admin@ncs(config-rule-allowrule)# commit
Aborted: 'nacm rule-list any-group rule allowrule action' is not configured
```

## ncs.conf settings

Parts of the CLI behavior can be controlled from the `ncs.conf` file. See the `ncs.conf(5)` in *NSO 5.7 Manual Pages* manual page for a comprehensive description of all the options.

## CLI Environment

There are a number of session variables in the CLI. They are only used during the session and are not persistent. Their values are inspected using `show cli` in operational mode, and set using `set` in operational mode. Their initial values are in order derived from the content of the `ncs.conf` file, and the global defaults as configured at `/aaa:session` and user specific settings configured at `/aaa:user{<user>}/setting`.

```
admin@ncs# show cli
autowizard           false
complete-on-space    true
display-level        99999999
history              100
idle-timeout         1800
ignore-leading-space  false
output-file          terminal
paginate             true
prompt1              \h\M#
prompt2              \h(\m)#
screen-length        71
screen-width         80
service prompt config true
show-defaults        false
```

```
terminal          xterm-256color
...
```

The different values control different parts of the CLI behavior.

#### **autowizard** (*true | false*)

When enabled, the CLI will prompt the user for required settings when a new identifier is created.

For example:

```
admin@ncs(config)# aaa authentication users user John
Value for 'uid' (<int>): 1006
Value for 'gid' (<int>): 1006
Value for 'password' (<hash digest string>): *****
Value for 'ssh_keydir' (<string>): /var/ncs/homes/john/.ssh
Value for 'homedir' (<string>): /var/ncs/homes/john
```

This helps the user set all mandatory settings.

It is recommended to disable the autowizard before pasting in a list of commands, in order to avoid prompting. A good practice is to start all such scripts with a line that disables the autowizard:

```
autowizard false
...
autowizard true
```

#### **complete-on-space** (*true | false*)

Controls if command completion should be attempted when <space> is entered. Entering <tab> always results in command completion.

#### **devtools** (*true | false*)

Controls if certain commands that are useful for developers should be enabled. The command **xpath** and **timecmd** are examples of such a command.

#### **history** (<integer>)

Size of CLI command history.

#### **idle-timeout** (<seconds>)

Maximum idle time before being logged out. Use 0 (zero) for infinity.

#### **ignore-leading-space** (*true | false*)

Controls if leading spaces should be ignored or not. This is useful to turn off when pasting commands into the CLI.

#### **paginate** (*true | false*)

Some commands paginate (or MORE process) the output, for example **show running-config**. This can be disabled or enabled. It is enabled by default. Setting the screen length to 0 has the same effect as turning off pagination.

#### **screen length** (<integer>)

Current length of terminal. This is used when paginating output to get proper line count. Setting this to 0 (zero) means it becomes maximum length and turns off pagination.

#### **screen width** (<integer>)

Current width of terminal. This is used when paginating output to get proper line count. Setting this to 0 (zero) means it becomes maximum width.

#### **service prompt config**

Controls whether a prompt should be displayed in configure mode. If set to false then no prompt will be displayed. The setting is changed using the commands **no service prompt config** and **service prompt config** in configure mode.

**terminal** (*string*)

Terminal type. This setting is used for controlling how line editing is performed. Supported terminals are: dumb, vt100, xterm, linux, and ansi. Other terminals may also work but have no explicit support.

## Commands

To get a full XML listing of the commands available in a running NSO instance use the ncs option `--cli-c-dump <file>`. The generated file is only intended for documentation purposes and *cannot* be used as input to the ncsc compiler. The command **show parser dump** can be used get a command listing.

## Operational mode commands

### Invoke an action

`<path> <parameters>`

Invokes the action found at *path* using the supplied *parameters*.

*This command is auto-generated from the YANG file.*

For example, given the following action specification in a YANG file:

```
tailf:action shutdown {
  tailf:actionpoint actions;
  input {
    tailf:constant-leaf flags {
      type uint64 {
        range "1 .. max";
      }
    }
    tailf:constant-value 42;
  }
  leaf timeout {
    type xs:duration;
    default PT60S;
  }
  leaf message {
    type string;
  }
  container options {
    leaf rebootAfterShutdown {
      type boolean;
      default false;
    }
    leaf forceFsckAfterReboot {
      type boolean;
      default false;
    }
    leaf powerOffAfterShutdown {
      type boolean;
      default true;
    }
  }
}
```

The action can be invoked in the following way

```
admin@ncs> shutdown timeout 10s message reboot options { \
  forceFsckAfterReboot true }
```

## Builtin commands

### **commit** (**abort** | **confirm**)

Abort or confirm a pending confirming commit. A pending confirming commit will also be aborted if the CLI session is terminated without doing **commit confirm**. The default is confirm.

Example:

```
admin@ncs# commit abort
```

### **config** (**exclusive** | **terminal**) [**no-confirm**]

Enter configure mode. The default is **terminal**.

#### **terminal**

Edit a private copy of the running configuration, no lock is taken.

#### **no-confirm**

Enter configure mode ignoring any confirm dialog

Example:

```
admin@ncs# config terminal
Entering configuration mode terminal
```

### **file list** *<directory>*

List files in *<directory>*.

Example:

```
admin@ncs# file list /config
rollback10001
rollback10002
rollback10003
rollback10004
rollback10005
```

### **file show** *<file>*

Display contents of a *<file>*.

Example:

```
admin@ncs# file show /etc/skel/.bash_profile
# /etc/skel/.bash_profile

# This file is sourced by bash for login shells. The following line
# runs our .bashrc and is recommended by the bash info pages.
[[ -f ~/.bashrc ]] && . ~/.bashrc
```

### **help** *<command>*

Display help text related to *<command>*.

Example:

```
admin@ncs# help job
Help for command: job
Job operations
```

### **job stop** *<job id>*

Stop a specific background job. In the default CLI the only command that creates background jobs is **monitor start**.

Example:

```

admin@ncs# monitor start /var/log/messages
[ok][...]
admin@ncs# show jobs
JOB COMMAND
3  monitor start /var/log/messages
admin@ncs# job stop 3
admin@ncs# show jobs
JOB COMMAND

```

### logout session <session>

Log out a specific user session from NSO. If the user held the **configure exclusive** lock, it will be released.

<sessionid> Log out a specific user session.

Example:

```

admin@ncs# who
Session User Context From Proto Date Mode
25 oper cli 192.168.1.72 ssh 12:10:40 operational
*24 admin cli 192.168.1.72 ssh 12:05:50 operational
admin@ncs# logout session 25
admin@ncs# who
Session User Context From Proto Date Mode
*24 admin cli 192.168.1.72 ssh 12:05:50 operational

```

### logout user <username>

Log out a specific user from NSO. If the user held the **configure exclusive** lock, it will be released.

<username> Log out a specific user.

Example:

```

admin@ncs# who
Session User Context From Proto Date Mode
25 oper cli 192.168.1.72 ssh 12:10:40 operational
*24 admin cli 192.168.1.72 ssh 12:05:50 operational
admin@ncs# logout user oper
admin@ncs# who
Session User Context From Proto Date Mode
*24 admin cli 192.168.1.72 ssh 12:05:50 operational

```

### script reload

Reload scripts found in the `scripts/commanddirectory`. New scripts will be added and if a script file has been removed the corresponding CLI command will be purged. See the Plug-and-play scripting section [Chapter 7, Plug-and-play scripting](#).

### send (all | <user>) <message>

Display a message on the screens of all users who are logged in to the device or on a specific screen.

**all**

Display the message to all currently logged in users.

<user>

Display the message to a specific user.

Example:

```
admin@ncs# send oper "I will reboot system in 5 minutes."
```

In oper's session:

```
oper@ncs# Message from admin@ncs at 13:16:41...
I will reboot system in 5 minutes.
```

EOF

### show cli

Display CLI properties.

Example:

```
admin@ncs# show cli
autowizard                false
complete-on-space         true
display-level              99999999
history                    100
idle-timeout               1800
ignore-leading-space       false
output-file                terminal
paginate                   true
prompt1                    \h\M#
prompt2                    \h(\m)#
screen-length              71
screen-width               80
service prompt config     true
show-defaults              false
terminal                   xterm-256color
timestamp                  disable
```

### show history [ <limit> ]

Display CLI command history. By default the last 100 commands are listed. The size of the history list is configured using the history CLI setting. If a history limit has been specified only the last number of commands up to that limit will be shown.

Example:

```
admin@ncs# show history
06-19 14:34:02 -- ping router
06-20 14:42:35 -- show running-config
06-20 14:42:37 -- who
06-20 14:42:40 -- show history
admin@ncs# show history 3
14:42:37 -- who
14:42:40 -- show history
14:42:46 -- show history 3
```

### show jobs

Display currently running background jobs.

Example:

```
admin@ncs# show jobs
JOB  COMMAND
3    monitor start /var/log/messages
```

### show parser dump <command prefix>

Shows all possible commands starting with *command prefix*.

### show running-config [ <pathfilter> [ sort-by <idx> ] ]

Display current configuration. By default the whole configuration is displayed. It is possible to limit what is shown by supplying a pathfilter.

The *pathfilter* may be either a path pointing to a specific instance, or if an instance id is omitted, the part following the omitted instance is treated as a filter.

The **sort-by** argument can be given when the *pathfilter* points to a list element with secondary indexes. *idx* is the name of a secondary index. When given, the table will be sorted in the order

defined by the secondary index. This makes it possible for the CLI user to control in which order instances should be displayed.

To show the aaa settings for the admin user:

```
admin@ncs# show running-config aaa authentication users user admin
aaa authentication users user admin
uid          1000
gid          1000
password     $1$JA.103Tx$ZtlycpnMlg1bVMqM/zSZ7/
ssh_keydir   /var/ncs/homes/admin/.ssh
homedir      /var/ncs/homes/admin
!
```

To show all users that have group id 1000, omit the user id and instead specify gid 1000:

```
admin@ncs# show running-config aaa authentication users user * gid 1000
...
```

### **show** <path> [ **sort-by** <idx> ]

This command shows the configuration as a table provided that *path* leads to a list element and the data can be rendered as a table (ie, the table fits on the screen). It is also possible to force table formatting of a list by using the | **tab** pipe command.

The **sort-by** argument can be given when the *path* points to a list element with secondary indexes. *idx* is the name of a secondary index. When given, the table will be sorted in the order defined by the secondary index. This makes it possible for the CLI user to control in which order instances should be displayed.

Example:

```
admin@ncs# show devices device ce0 module
NAME                                REVISION    FEATURE    DEVIATION
-----
tailf-ned-cisco-ios                2015-03-16  -          -
tailf-ned-cisco-ios-stats          2015-03-16  -          -
```

### **source** <file>

Execute commands from <file> as if they had been entered by the user. The autowizard is disabled when executing commands from the file.

### **timecmd** <command>

Time command. It measures and displays the execution time of <command>.

*Note that this command will only be available if devtools has been set to true in the CLI session settings.*

Example:

```
admin@ncs# timecmd id
user = admin(501), gid=20, groups=admin, gids=12,20,33,61,79,80,81,98,100
Command executed in 0.00 sec
admin@ncs#
```

### **who**

Display currently logged on users. The current session, i.e. the session running the show status command, is marked with an asterisk.

Example:

```
admin@ncs# who
Session User Context From          Proto Date       Mode
25      oper cli      192.168.1.72 ssh    12:10:40 operational
```

```
*24      admin cli      192.168.1.72 ssh   12:05:50 operational
admin@ncs#
```

## Configure mode commands

### Configure a value

**<path> [<value>]**

Set a parameter. If a new identifier is created and **autowizard** is enabled, then the CLI will prompt the user for all mandatory sub-elements of that identifier.

*This command is auto-generated from the YANG file.*

If no **<value>** is provided, then the CLI will prompt the user for the value. No echo of the entered value will occur if **<path>** is an encrypted value, i.e. of the type *MD5DigestString*, *DESDigestString*, *DES3CBCEncryptedString*, *AESCFB128EncryptedString* or *AES256CFB128EncryptedString* as documented in the *tailf-common.yang* data-model.

### Builtin commands

**annotate** **<statement>** **<text>**

Associate an annotation with a given configuration. To remove an annotation leave the text empty.  
Only available when the system has been configured with attributes enabled.

**commit** (**check** | **and-quit** | **confirmed** | **to-startup**) [**comment** **<text>**] [**label** **<text>**]

Commit current configuration to running.

**check**

Validate current configuration.

**and-quit**

Commit to running and quit configure mode.

**comment** **<text>**

Associate a comment with the commit. The comment can later be seen when examining rollback files.

**label** **<text>**

Associate a label with the commit. The label can later be seen when examining rollback files.

**copy** **<instance path>** **<new id>**

Make a copy of an instance.

Copying between different ned-id versions works as long as the schema nodes being copied has not changed between the versions.

**copy cfg** [**merge** | **overwrite**] **<src path>** **to** **<dest path>**

Copy data from one configuration tree to another. Only data that makes sense at the destination will be copied. No error message will be generated for data that cannot be copied and the operation can fail completely without any error messages being generated.

For example to create a template from a part of a device config. First configure the device then copy the config into the template configuration tree.

```
admin@ncs(config)# devices template host_temp
admin@ncs(config-template-host_temp)# exit
admin@ncs(config)# copy cfg merge devices device ce0 config \
    ios:ethernet to devices template host_temp config ios:ethernet
admin@ncs(config)# show configuration diff
```



```
+devices template host_temp
+ config
+ ios:ethernet cfm global
+ !
+!
```

**copy compare** *<src path>* **to** *<dest path>*

Compare two arbitrary configuration trees. Items that does only appears in the src tree are ignored.

**delete** *<path>*

Delete a data element.

**do** *<command>*

Run command in operational mode.

**edit** *<path>*

Edit a sub-element. Missing elements in *path* will be created.

**exit** (**level** | **configuration-mode**)

level	Exit from this level. If performed on the top level, will exit configure mode. This is the default if no option is given.
configuration-mode	Exit from configuration mode regardless of which edit level.

**help** *<command>*

Shows help text for command.

**hide** *<hide-group>*

Re-hides the elements and actions belonging to the hide groups. No password is required for hiding. This command is hidden and not shown during command completion.

**insert** *<path>*

Inserts a new element. If the element already exists and has the indexedView option set in the data model, then the old element will be renamed to element+1 and the new element inserted in its place.

**insert** *<path>* [**first** | **last** | **before key** | **after key**]

Inject a new element into an ordered list. The element can be added first, last (default), before or after another element.

**load** (**merge** | **override** | **replace**) (**terminal** | *<file>*)

Load configuration from file or terminal.

merge	Merge content of file/terminal with current configuration.
override	Configuration from file/terminal overwrites the current configuration.
replace	Configuration from file/terminal replaces the current configuration.

If this is the current configuration:

```
devices device p1
config
  cisco-ios-xr:interface GigabitEthernet 0/0/0/0
  shutdown
exit
  cisco-ios-xr:interface GigabitEthernet 0/0/0/1
  shutdown
!
```

And the **shutdown** value for the entry **GigabitEthernet 0/0/0/0** should be deleted. As the configuration file is basically just a sequence of commands with comments in between, the configuration file should look like this:

```
devices device p1
config
```

```

cisco-ios-xr:interface GigabitEthernet 0/0/0/0
  no shutdown
exit
!
!

```

The file can then be used with the command **load merge** *FILENAME* to achieve the desired results.

**move** *<path>* [**first**|**last**|**before** *key*|**after** *key*]

Move an existing element to a new position in an ordered list. The element can be moved first, last (default), before or after another element.

**rename** *<instance path>* *<new id>*

Rename an instance.

**revert**

Copy running configuration into current configuration, eg remove all uncommitted changes.

**rload** (**merge** | **override** | **replace**) (**terminal** | *<file>*)

Load file relative to the current submode. For example, given a file with a device config it is possible to enter one device and issue the **rload merge/override/replace** *<file>* command to load the config for that device, then enter another device and load the same config file using **rload**. See also the **load** command.

**merge** Merge content of file/terminal with current configuration.

**override** Configuration from file/terminal overwrites the current configuration.

**replace** Configuration from file/terminal replaces the current configuration.

**rollback configuration** [*<number>*] [*<path>*]

Return the configuration to a previously committed configuration. The system stores a limited number of old configurations. The number of old configurations to store is configured in the `ncs.conf` file. If more than the configured number of configurations are stored, then the oldest configuration is removed before creating a new one.

The configuration changes are stored in rollback files where the most recent changes are stored in the file `rollbackN` with the highest number *N*.

Only the deltas are stored in the rollback files. When rolling back the configuration to rollback *N*, all changes stored in `rollback10001-rollbackN` are applied.

The optional path argument allows subtrees to be rolled back while the rest of the configuration tree remains unchanged.

Example:

```
admin@ncs(config)# rollback configuration 10005
```

This command is only available if rollback has been enabled in `ncs.conf`.

**rollback selective** [*<number>*] [*<path>*]

Instead of undoing all changes from `rollback10001` to `rollbackN` it is possible to undo only the changes stored in a specific rollback file. This may or may not work depending on which changes has been made to the configuration after the rollback was created. In some cases applying the rollback file may fail, or the configuration may require additional changes in order to be valid.

The optional path argument allows subtrees to be rolled back while the rest of the configuration tree remains unchanged.

**show full-configuration** [*<pathfilter>*] [**sort-by** *<idx>*]

Show current configuration, taking local changes into account. The **show** command can be limited to a part of the configuration by providing a *<pathfilter>*.

The **sort-by** argument can be given when the *pathfilter* points to a list element with secondary indexes. *idx* is the name of a secondary index. When given, the table will be sorted in the order defined by the secondary index. This makes it possible for the CLI user to control in which order instances should be displayed.

**show configuration** [*<pathfilter>*]

Show current edits to the configuration.

**show configuration merge** [*<pathfilter>*] [**sort-by** *<idx>*]

Show current configuration, taking local changes into account. The **show** command can be limited to a part of the configuration by providing a *<pathfilter>*.

The **sort-by** argument can be given when the *pathfilter* points to a list element with secondary indexes. *idx* is the name of a secondary index. When given, the table will be sorted in the order defined by the secondary index. This makes it possible for the CLI user to control in which order instances should be displayed.

**show configuration commit changes** [*<number>*] [*<path>*]

Display edits associated with a commit, identified by the rollback number created for the commit.

The changes are displayed as forward changes, as opposed to **show configuration rollback changes** which displays the commands for undoing the changes.

The optional path argument allows only edits related to a given subtree to be listed.

**show configuration commit list** [*<path>*]

List rollback files

The optional path argument allows only rollback files related to a given subtree to be listed.

**show configuration rollback listed** [*<number>*]

Display the operations needed to undo the changes performed in a commit associated with a rollback file. These are the changes that will be applied if the configuration is rolled back to that rollback number.

**show configuration running** [*<pathfilter>*]

Display running-configuration without taking uncommitted changes into account. An optional *pathfilter* can be provided to limit what is displayed.

**show configuration diff** [*<pathfilter>*]

Display uncommitted changes to the running-config in diff-style, ie with + and - in front of added and deleted configuration lines.

**show parser dump** *<command prefix>*

Shows all possible commands starting with *command prefix*.

**tag add** *<statement>* *<tag>*

Add a tag to a configuration statement.

Only available in when the system has been configured with attributes enabled.

**tag del** *<statement>* *<tag>*

Remove a tag from a configuration statement.

Only available in when the system has been configured with attributes enabled.

**tag clear** *<statement>*

Remove all tags from a configuration statement.

Only available in when the system has been configured with attributes enabled.

**timecmd** *<command>*

Time command. It measures and displays the execution time of *<command>*.

*Note that this command will only be available if **devtools** has been set to **true** in the CLI session settings.*

Example:

```
admin@ncs# timecmd id
user = admin(501), gid=20, groups=admin, gids=12,20,33,61,79,80,81,98,100
Command executed in 0.00 sec
admin@ncs#
```

#### **top** [*command*]

Exit to top level of configuration, or execute a command at the top level of the configuration.

#### **unhide** <*hide-group*>

Unhides all elements and actions belonging to the hide-group. It may be required to enter a password.

This command is hidden and not shown during command completion

#### **validate**

Validates current configuration. This is the same operation as **commit check**.

#### **xpath** [*ctx* <*path*>] (**eval** | **must** | **when**) <*expression*>

Evaluate an XPath expression. A context-path may be given to be used as the current context for the evaluation of the expression. If no context-path is given, the current sub-mode will be used as the context-path. The pipe command **trace** may be used to display debug/trace information during execution of the command.

*Note that this command will only be available if **devtools** has been set to **true** in the CLI session settings.*

**eval**

Evaluate an XPath expression.

**must**

Evaluate the expression as a YANG *must* expression.

**when**

Evaluate the expression as a YANG *when* expression.

## Customizing the CLI

### Adding new commands

New commands can be added by placing a script in the `scripts/command` directory. See the Plug-and-play scripting section [Chapter 7, Plug-and-play scripting](#).

### File access

The default behavior is to enforce Unix style access restrictions. That is, the users *uid*, *gid*, and *gids* are used to control what the user has read and write access to.

However, it is also possible to jail a CLI user to its home directory (or the directory where `ncs_cli` is started). This is controlled using the `ncs.conf` parameter *restricted-file-access*. If this is set to *true*, then the user only has access to the home directory.

### Help texts

Help and information texts are specified in a number of places. In the yang files the *tailf:info* element is used to specify a descriptive text that is shown when the user enters `?` in the CLI. The first sentence of the *info* text is used when showing one-line descriptions in the CLI.

# Quoting and escaping scheme

## Canonical quoting scheme

NCS understands multiple quoting schemes on input and de-quotes a value when parsing the command, but it uses what it considers a canonical quoting scheme when printing out this value, e.g. when pushing a configuration change to the device. However, different devices may have different quoting schemes, possibly not compatible with NCS canonical quoting scheme. For example, the following value:

```
"foo\\bar\\?baz"
```

cannot be printed out by NCS as two backslashes "\\" match "\" in quoting scheme used by NCS when encoding values.

General rules for NCS to represent backslash are as followings:

- "\"" and "\" are represented as "\"
- "\" and "\" are represented as "\"
- "\" and "\" are represented as "\"

and so on. It can only get an odd number of backslashes output from NCS.

A backslash "\" is represented as a backslash "\" when it is followed by a character that does not need to be escaped, but is represented as double backslashes "\"" if the next character could be escaped.

## Escape backslash handling

In order to let NCS to pass through a quoted string verbatim, one can do as stated below:

- Enable NCS configuration parameter `escapeBackslash` in the `ncs.conf` file. This is a global setting on NCS which affects all the NEDs.

Alternatively, a certain NED may be updated on request to be able to transform the value printed by NCS to what the device expects if one only wants to affect a certain device instead of all the connected ones.

## Octal numbers handling

If there are numeric triplets following a backslash "\", NCS will treat them as octal numbers and convert them to one character based on ASCII code. For example:

- "\123" is converted to "S"
- "\067" is converted to "7"





## CHAPTER 3

# The NSO Device Manager


---

- [Introduction, page 40](#)
- [The Managed Device Tree, page 41](#)
- [The NED Packages, page 44](#)
- [Starting the NSO Daemon, page 45](#)
- [Synchronizing Devices, page 45](#)
- [Configuring Devices, page 50](#)
- [Connection Management, page 51](#)
- [Authentication Groups, page 53](#)
- [Device Session Pooling, page 58](#)
- [Device Session Limits, page 62](#)
- [Tracing Device Communication, page 63](#)
- [Checking Device Configuration, page 64](#)
- [Comparing Device Configurations, page 66](#)
- [Initialize Device, page 67](#)
- [Device Templates, page 70](#)
- [Oper State and Admin State, page 73](#)
- [Configuration Source, page 75](#)
- [Capabilities, Modules and Revision Management, page 76](#)
- [Configuration Datastore Support, page 78](#)
- [Action Proxy, page 79](#)
- [Device Groups, page 80](#)
- [Policies, page 82](#)
- [Commit Queue, page 83](#)
- [NETCONF Call Home, page 94](#)
- [Notifications, page 94](#)
- [SNMP Notifications, page 100](#)

- [Inactive configuration, page 100](#)

## Introduction

Throughout this section we will use the examples `.ncs/service-provider/mpls-vpn` example. The example network consists of Cisco ASR 9k and Juniper core routers (P and PE) and Cisco IOS based CE routers.



NSO Example network

The NSO device manager is the centre of NSO. The device manager maintains a flat list of all managed devices. NSO keeps the master copy of the configuration for each managed device in CDB. Whenever a configuration change is done to the list of device configuration master copies, the device manager will partition this "network configuration change" into the corresponding changes for the actual managed devices. The device manager passes on the required changes to the NEDs, Network Element Drivers. A NED needs to be installed for every type of device OS, like Cisco IOS NED, Cisco XR NED, Juniper JUNOS NED etc. The NEDs communicate through the native device protocol southbound. The NEDs falls into the following categories:

- *NETCONF capable device.* The Device Manager will produce NETCONF `edit-config` RPC operations for each participating device.
- *SNMP device.* The Device Manager translates the changes made to the configuration into the corresponding SNMP SET PDUs
- *Device with Cisco CLI.* The device has a CLI with the same structure as Cisco IOS or XR routers. The Device Manager and a CLI NED is used to produce the correct sequence of CLI commands which reflects the changes made to the configuration.
- *Other devices* Devices which do not fit into any of the above mentioned categories a corresponding Generic NED is invoked. Generic NEDs are used for proprietary protocols like REST and for CLI flavours that are not resembling IOS or XR. The Device Manager will inform the Generic NED about the made changes and the NED will translate these to the appropriate operations toward the device.

NSO orchestrates an atomic transaction that has the very desirable characteristic of either the transaction as a whole ends up on all participating devices *and* in the NSO master copy, or alternatively the whole transaction is aborted and all changes are automatically rolled-back.

The architecture of the NETCONF protocol is the enabling technology making it possible to push out configuration changes to managed devices and then in the case of other errors, roll back changes. Devices



that do not support NETCONF, i.e., devices that do not have transactional capabilities can also participate, however depending on the device, error recovery may not be as good as it is for a proper NETCONF enabled device.

In order to understand the main idea behind the NSO device manager it is necessary to understand the NSO data model and how NSO incorporates the YANG data models from the different managed devices.

The NEDs will publish YANG data models even for non-NETCONF devices. In case of SNMP the YANG models are generated from the MIBs. For JunOS devices the JunOS NED generates a YANG from the JunOS XML Schema. For Schema-less devices like CLI devices the NED developer writes YANG models corresponding to the CLI structure. The result of this is the device manager and NSO CDB has YANG data models for all devices independent of underlying protocol.

## The Managed Device Tree

The central part of the NSO YANG model, in the file `tailf-ncs-devices.yang`, has the following structure:

### Example 2. `tailf-ncs-devices.yang`

```
submodule tailf-ncs-devices {
  belongs-to tailf-ncs {
    prefix ncs;
  }
  ...
  container devices {
    .....
    list device {
      key name;

      description
        "This list contains all devices managed by NCS.";

      leaf name {
        type string;
        description
          "A string uniquely identifying the managed device.";
      }

      leaf address {
        type inet:host;
        mandatory true;
        description
          "IP address or host name for the management interface on
           the device.";
      }

      leaf port {
        type inet:port-number;
        description
          "Port for the management interface on the device. If this leaf
           is not configured, NCS will use a default value based on the
           type of device. For example, a NETCONF device uses port 830,
           a CLI device over SSH uses port 22, and a SNMP device uses
           port 161.";
      }
    }
    ....
    leaf authgroup {
      .....
    }
    container device-type {
```

```

        .....
        container config {
            ...
        }
    }
}

```

Each managed device is uniquely identified by its name, which is a free form text string. This is typically the DNS name of the managed device but could equally well be the string format of the IP address of the managed device or anything else. Furthermore, each managed device has a mandatory address/port pair that together with the `authgroup` leaf provides information to NSO how to connect and authenticate over SSH/NETCONF to the device. Each device also has a mandatory parameter `device-type` that specifies which southbound protocol to use for communication with the device. The following device types are available:

- NETCONF
- CLI - a corresponding CLI NED is needed to communicate with the device. This requires YANG models with the appropriate annotations for the device CLI.
- SNMP - The device speaks SNMP, preferably in read-write mode.
- Generic NED - a corresponding Generic NED is needed to communicate with the device. This requires YANG models and Java code.

The NSO CLI command below lists the NED types for the devices in the example network.

```

ncs(config)# show full-configuration devices device device-type
devices device ce0
  device-type cli ned-id cisco-ios-cli-3.8
!
...
devices device p0
  device-type cli ned-id cisco-iosxr-cli-3.5
!
devices device p1
  device-type cli ned-id cisco-iosxr-cli-3.5
!
...
devices device pe2
  device-type netconf ned-id juniper-junos-nc-3.0
!

```

The empty container `/ncs:devices/device/config` is used as a mount point for the YANG models from the different managed devices.

As previously mentioned, NSO needs the following information in order to manage a device:

- The IP/Port of the device and authentication information.
- Some or all of the YANG data models for the device.

In the example setup, the address and authentication information is provided in the NSO database (CDB) initialization file. There are many different ways to add new managed devices. Actually, all of the NSO northbound interfaces can be used to manipulate the set of managed devices. This will be further described later.

Once NSO has started you can inspect the meta information for the managed devices through the NSO CLI. This is an example session:

### Example 3. Show device configuration in NSO CLI

```

ncs(config)# show full-configuration devices device

```

```

devices device ce0
  address 127.0.0.1
  port 10022
  ssh host-key ssh-dss
  ...
  authgroup default
  device-type cli ned-id cisco-ios-cli-3.8
  state admin-state unlocked
  config
  ...
!
!
devices device ce1
  address 127.0.0.1
  port 10023
  ssh host-key ssh-dss
  ...
!
  authgroup default
  device-type cli ned-id cisco-ios-cli-3.8
  state admin-state unlocked
  config
  ...
!
!

```

Or alternatively, this information could be retrieved from the NSO northbound NETCONF interface by running the simple Python based netconf-console program towards the NSO NETCONF server.

#### Example 4. Show device configuration in NETCONF

```

$ netconf-console --get-config -x "/devices/device[name='ce0']"
<?xml version="1.0" encoding="UTF-8"?>
<rpc-reply xmlns="urn:ietf:params:xml:ns:netconf:base:1.0" message-id="1">
  <data>
    <devices xmlns="http://tail-f.com/ns/ncs">
      <device>
        <name>ce0</name>
        <address>127.0.0.1</address>
        <port>10022</port>
        <ssh>
          <host-key>
            <algorithm>ssh-dss</algorithm>
          ...
        </ssh>
        <authgroup>default</authgroup>
        <device-type>
          <cli>
            <ned-id xmlns:cisco-ios-cli-3.8="http://tail-f.com/ns/ned-id/cisco-ios-cli-3.8">
              cisco-ios-cli-3.8:cisco-ios-cli-3.8
            </ned-id>
          </cli>
        </device-type>
        <state>
          <admin-state>unlocked</admin-state>
        </state>
        <config>
          ...
        </config>
      </device>
    </devices>
  </data>
</rpc-reply>

```

```

        </config>
    </device>
</devices>
</data>
</rpc-reply>

```

All devices in [Example 3, “Show device configuration in NSO CLI”](#) and [Example 4, “Show device configuration in NETCONF”](#) have `/devices/device/state/admin-state` set to `unlocked`, this will be described later in this chapter.

## The NED Packages

In order to communicate with a managed device, a NED for that device type needs to be loaded by NSO. A NED contains the YANG model for the device and corresponding driver code to talk CLI, REST, SNMP, etc. NEDs are distributed as packages.

### Example 5. Installed Packages

```

ncs# show packages
packages package cisco-ios-cli-3.8
  package-version 3.8.0.1
  description "NED package for Cisco IOS"
  ncs-min-version [ 3.2.2 3.3 3.4 ]
  directory ./state/packages-in-use/1/cisco-ios-cli-3.8
  component IOSDp2
    callback java-class-name [ com.tailf.packages.ned.ios.IOSDp2 ]
  component IOSDp
    callback java-class-name [ com.tailf.packages.ned.ios.IOSDp ]
  component cisco-ios
    ned cli ned-id cisco-ios-cli-3.8
    ned cli java-class-name com.tailf.packages.ned.ios.IOSNedCli
    ned device vendor Cisco
  ...
oper-status up
packages package cisco-iosxr-cli-3.5
  package-version 3.5.0.7
  description "NED package for Cisco IOS XR"
  ncs-min-version [ 3.2.2 3.3 ]
  directory ./state/packages-in-use/1/cisco-iosxr-cli-3.5
  component cisco-ios-xr
    ned cli ned-id cisco-iosxr-cli-3.5
    ned cli java-class-name com.tailf.packages.ned.iosxr.IosxrNedCli
    ned device vendor Cisco
  ...
oper-status up
packages package juniper-junos-nc-3.0
  package-version 3.0.14.2
  description "NED package for all JunOS based Juniper routers"
  ncs-min-version [ 3.0.0.1 3.1 3.2 3.3 3.4 ]
  directory ./state/packages-in-use/1/juniper-junos-nc-3.0
  component junos
    ned netconf ned-id juniper-junos-nc-3.0
    ned device vendor Juniper
oper-status up
...

```

The CLI command in [Example 5, “Installed Packages”](#) shows all the loaded packages. NSO loads packages at startup and can reload packages at run-time. By default the packages reside in the `packages` directory in the NSO run-time directory.

```
$ ls -l $NCS_DIR/examples.ncs/service-provider/mpls-vpn
total 160
...
drwxr-xr-x  8 stefan  staff    272 Oct  1 16:57 packages
...
$ ls -l $NCS_DIR/examples.ncs/service-provider/mpls-vpn/packages
total 24
cisco-ios
cisco-iosxr
juniper-junos
...
```

## Starting the NSO Daemon

Once you have access to the network information for a managed device, its IP address and authentication information, as well as the data models of the device, you can actually manage the device from NSO.

You start the **ncs** daemon in a terminal like:

```
% ncs
```

Which is the same as, NSO loads it config from a `ncs.conf` file

```
% ncs -c ./ncs.conf
```

During development it is sometimes convenient to run `ncs` in the foreground as:

```
% ncs -c ./ncs.conf --foreground --verbose
```

Once the daemon is running you can issue the command:

```
% ncs --status
vsn: 7.1
SMP support: yes, using 8 threads
Using epoll: yes
available modules: backplane,netconf,cdb,cli,snmp,webui
...
... lots of output
```

To get more information about options to **ncs** do:

```
% ncs --help
```

The **ncs --status** command produces a lengthy list describing for example which YANG modules are loaded in the system. This is a valuable debug tool.

The same information is also available in the NSO CLI (and thus through all available northbound interfaces, including Maapi for Java programmers)

```
ncs# show ncs-state
ncs-state version 7.1
ncs-state smp number-of-threads 8
ncs-state epoll true
ncs-state daemon-status started
...
```

## Synchronizing Devices

When the NSO daemon is running and has been initialized with IP/Port and authentication information as well as imported all modules you can start to manage devices through NSO.

NSO provides the ability to synchronize the configuration *to* or *from* the device. If you know that the device has the correct configuration you can choose to synchronize from a managed device whereas if you know NSO has the correct device configuration and the device is incorrect, you can choose to synchronize from NSO to the device.

In the normal case, the configuration on the device and the copy of the configuration inside NSO should be identical.

In a cold start situation like in the mpls-vpn example, where NSO is empty and there are network devices to talk to, it makes sense to synchronize from the devices. You can choose to synchronize from one device at a time or from all devices at once. Here is a CLI session to illustrate this.

### Example 6. Synchronize from Devices

```

ncs(config)# devices sync-from
sync-result {
    device ce0
    result true
}
sync-result {
    device ce1
    result true
}
sync-result {
    device ce2
    result true
}
...
ncs(config)# show full-configuration devices device ce0
devices device ce0
...
config
  no ios:service pad
  no ios:ip domain-lookup
  no ios:ip http secure-server
  ios:ip source-route
  ios:interface GigabitEthernet0/1
  exit
  ios:interface GigabitEthernet0/10
  exit
  ios:interface GigabitEthernet0/11
  exit
...
[ok][2010-04-13 16:29:15]
```

The command **devices sync-from**, in [Example 6, “Synchronize from Devices”](#), is an action that is defined in the NSO data model. It is important to understand the model-driven nature of NSO. All devices are modeled in YANG, network services like MPLS VPN are also modeled in YANG, and the same is true for NSO itself. Anything that can be performed over the NSO CLI or any north-bound is defined in the YANG files. The NSO YANG files are located here:

```
$ls $NCS_DIR/src/ncs/yang/
```

All packages comes with YANG files as well. For example the directory `packages/cisco-ios/src/yang/` contains the YANG definition of an IOS device.

The `tailf-ncs.yang` is the main part of the NSO YANG data model. The file `mode tailf-ncs.yang` includes all parts of the model from different files.

The actions `sync-from` and `sync-to` are modeled in the file `tailf-ncs-devices.yang`. The `sync` action(s) are defined as:

### Example 7. `tailf-ncs-devices.yang` sync actions

```

grouping sync-from-output {
  list sync-result {
    key device;
    leaf device {
      type leafref {
        path "/devices/device/name";
      }
    }
    uses sync-result;
  }
}

grouping sync-result {
  description
    "Common result data from a 'sync' action.";

  choice outformat {
    leaf result {
      type boolean;
    }
    anyxml result-xml;
    leaf cli {
      tailf:cli-preformatted;
      type string;
    }
  }
  leaf info {
    type string;
    description
      "If present, contains additional information about the result.";
  }
}

...

container devices {
  ...

  tailf:action sync-from {
    description
      "Synchronize the configuration by pulling from all unlocked
      devices.";
    tailf:info "Synchronize the config by pulling from the devices";
    tailf:actionpoint ncsinternal {
      tailf:internal;
    }
    input {
      leaf suppress-positive-result {
        type empty;
        description
          "Use this additional parameter to only return
          devices that failed to sync.";
      }
    }
    container dry-run {
      presence "";
      leaf outformat {

```

```

        type outformat2;
        description
            "Report what would be done towards CDB, without
            actually doing anything.";
    }
}
}
output {
    uses sync-from-output;
}
}
...

tailf:action sync-to {
    ...
}
...

list device {
    description
        "This list contains all devices managed by NCS.";

    key name;

    leaf name {
        description "A string uniquely identifying the managed device";
        type string;
    }

    ...

    tailf:action sync-from {
        description
            "Synchronize the configuration by pulling from the device.";
        tailf:info "Synchronize the config by pulling from the device";
        tailf:actionpoint ncsinternal {
            tailf:internal;
        }
        input {
            container dry-run {
                presence "";
                leaf outformat {
                    type outformat2;
                    description
                        "Report what would be done towards CDB, without
                        actually doing anything.";
                }
            }
        }
        output {
            uses sync-result;
        }
    }
    tailf:action sync-to {
        ...
    }
}

```

Synchronizing from NSO to the device is common when a device has been configured out-of-band. NSO has no means to enforce that devices are not directly reconfigured behind the scenes of NSO; however, once a out-of-band configuration has been performed, NSO has the ability to detect the fact. When this



happens it may (or may not, depending on the situation at hand) make sense to synchronize from NSO to the device, i.e. undo the rogue reconfigurations.

The command to do that is:

```
ncs# devices device ce0 sync-to
result true
```

A dry-run option is available for the action sync-to.

```
ncs# devices device ce0 sync-to dry-run
data {
    ...
}
```

This makes it possible to investigate the changes before they are transmitted to the devices.

## Partial sync-from

It is possible to synchronize a part of the configuration (a certain subtree) from the device using the partial-sync-from action located under /devices. While it is primarily intended to be used by service developers as described in the section called “Partial sync” in *NSO 5.7 Development Guide*, it is also possible to use directly from the NSO CLI (or any other northbound interface). [Example 8, “Example of running partial-sync-from action via CLI”](#) illustrates using this action via CLI, using "router" device from examples.ncs/getting-started/developing-with-ncs/0-router-network.

### Example 8. Example of running partial-sync-from action via CLI

```
$ ncs_cli -C -u admin
ncs# devices partial-sync-from path [ \
/devices/device[name='ex0']/config/r:sys/interfaces/interface[name='eth0'] \
/devices/device[name='ex1']/config/r:sys/dns/server ]
sync-result {
    device ex0
    result true
}
sync-result {
    device ex1
    result true
}
ncs# show running-config devices device ex0..1 config
devices device ex0
config
r:sys interfaces interface eth0
unit 0
enabled
!
unit 1
enabled
!
unit 2
enabled
description "My Vlan"
vlan-id 18
!
!
!
devices device ex1
config
r:sys dns server 10.2.3.4
!
```

!  
!

## Configuring Devices

It is now possible to configure several devices through the NSO inside the same network transaction. To illustrate this start the NSO CLI from a terminal application.

### Example 9. Configure Devices

```
$ ncs_cli -C -u admin
ncs# config
Entering configuration mode terminal
ncs(config)# devices device pe1 config cisco-ios-xr:snmp-server \
    community public RO
ncs(config-config)# top
ncs(config)# devices device ce0 config ios:snmp-server community public RO
ncs(config-config)# devices device pe2 config junos:configuration \
    snmp community public view RO
ncs(config-community-public)# top
ncs(config)# show configuration
devices device ce0
    config
        ios:snmp-server community public RO
    !
!
devices device pe1
    config
        cisco-ios-xr:snmp-server community public RO
    !
!
devices device pe2
    config
        ! first
        junos:configuration snmp community public
        view RO
    !
!
ncs(config)# commit dry-run outformat native
native {
    device {
        name ce0
        data snmp-server community public RO
    }
    device {
        name pe1
        data snmp-server community public RO
    }
    device {
        name pe2
        data <rpc xmlns="urn:ietf:params:xml:ns:netconf:base:1.0"
            message-id="1">
            <edit-config xmlns:nc="urn:ietf:params:xml:ns:netconf:base:1.0">
                <target>
                    <candidate/>
                </target>
                <test-option>test-then-set</test-option>
                <error-option>rollback-on-error</error-option>
                <config>
                    <configuration xmlns="http://xml.juniper.net/xnm/1.1/xnm">
                        <snmp>
```

```

        <community>
          <name>public</name>
          <view>RO</view>
        </community>
      </snmp>
    </configuration>
  </config>
</edit-config>
</rpc>
}
}
nscs(config)# commit

```

The [Example 9, “Configure Devices”](#) illustrates a multi host transaction. In the same transaction three hosts were re-configured. Had one of them failed, or been non-operational, the transaction as a whole would have failed.

As seen from the output of the command **commit dry-run outformat native**, NSO generates the native CLI and NETCONF commands which will be sent to each device when the transaction is committed.

Since the `/devices/device/config` path contains different models depending on the augmented device model NSO uses the data model prefix in the CLI names; `ios`, `cisco-ios-xr` and `junos`. Different data models might use the same name for elements and the prefix avoids name clashes.

NSO uses different underlying techniques to implement the atomic transactional behaviour in case of any error. NETCONF devices are straight-forward using confirmed commit. For CLI devices like IOS NSO calculates the reverse diff to restore the configuration to the state before the transaction was applied.

## Connection Management

Each managed device needs to be configured with the IP address and the port where the CLI, NETCONF server etc of the managed device listens for incoming requests.

Connections are established on demand as they are needed. It is possible to explicitly establish connections, but that functionality is mostly there for troubleshooting connection establishment. We can for example do:

```

nscs# devices connect
connect-result {
  device ce0
  result true
  info (admin) Connected to ce0 - 127.0.0.1:10022
}
connect-result {
  device ce1
  result true
  info (admin) Connected to ce1 - 127.0.0.1:10023
}
...

```

We were able to connect to all managed devices. It is also possible to explicitly attempt to test connections to individual managed devices:

```

nscs# devices device ce0 connect
result true
info (admin) Connected to ce0 - 127.0.0.1:10022

```

Established connections are typically not closed right away when not needed, but rather pooled according to the rules described in [the section called “Device Session Pooling”](#). This applies to NETCONF sessions as well as sessions established by CLI or generic NEDs via a connection-oriented protocol. In addition to

session pooling, underlying SSH connections for NETCONF devices are also reused. Note that a single NETCONF session occupies one SSH channel inside an SSH connection, so multiple NETCONF sessions can co-exist in a single connection. When an SSH connection has been idle (no SSH channels open) for 2 minutes, the SSH connection is closed. If a new connection is needed later, a connection is established on demand.

There are three configuration parameters which can be used to control the connection establishment, `connect-timeout`, `read-timeout` and `write-timeout`. In the NSO data model file `tailf-ncs-devices.yang` these timeouts are modeled as:

```
submodule tailf-ncs-devices {
  ...
  container devices {
    ...
    grouping timeouts {
      description
        "Timeouts used when communicating with a managed device.";

      leaf connect-timeout {
        type uint32;
        units "seconds";
        description
          "The timeout in seconds for new connections to managed
          devices.";
      }
      leaf read-timeout {
        type uint32;
        units "seconds";
        description
          "The timeout in seconds used when reading data from a
          managed device.";
      }
      leaf write-timeout {
        type uint32;
        units "seconds";
        description
          "The timeout in seconds used when writing data to a
          managed device.";
      }
    }
  }
  ...
  container global-settings {
    ...
    uses timeouts {
      description
        "These timeouts can be overridden per device.";

      refine connect-timeout {
        default 20;
      }
      refine read-timeout {
        default 20;
      }
      refine write-timeout {
        default 20;
      }
    }
  }
  ....
}
```

Thus to change these parameters (globally for all managed devices) you do:

```
ncs(config)# devices global-settings connect-timeout 30
```

```
ncs(config)# devices global-settings read-timeout 30
ncs(config)# commit
```

Or, to use a profile:

```
ncs(config)# devices profiles profile slow-devices connect-timeout 60
ncs(config-profile-slow-devices)# read-timeout 60
ncs(config-profile-slow-devices)# write-timeout 60
ncs(config-profile-slow-devices)# commit

ncs(config)# devices device ce3 device-profile slow-devices
ncs(config-device-ce3)# commit
```

## Authentication Groups

When NSO connects to a managed device, it requires authentication information for that device. The authgroups are modeled in the NSO data model:

### Example 10. tailf-ncs-devices.yang - Authgroups

```
submodule tailf-ncs-devices {
  ...
  container devices {
    ...

    container authgroups {
      description
        "Named authgroups are used to decide how to map a local NCS user to
        remote authentication credentials on a managed device.

        The list 'group' is used for NETCONF and CLI managed devices.

        The list 'snmp-group' is used for SNMP managed devices."

      list group {
        key name;

        description
          "When NCS connects to a managed device, it locates the
          authgroup configured for that device. Then NCS looks up
          the local NCS user name in the 'umap' list. If an entry is
          found, the credentials configured is used when
          authenticating to the managed device.

          If no entry is found in the 'umap' list, the credentials
          configured in 'default-map' are used.

          If no 'default-map' has been configured, and the local NCS
          user name is not found in the 'umap' list, the connection
          to the managed device fails."

        grouping remote-user-remote-auth {
          description
            "Remote authentication credentials."

          choice login-credentials {
            mandatory true;
            case stored {
              choice remote-user {
                mandatory true;
                leaf same-user {
                  type empty;
                }
              }
            }
          }
        }
      }
    }
  }
}
```

```

        description
            "If this leaf exists, the name of the local NCS user is used
            as the remote user name.";
    }
    leaf remote-name {
        type string;
        description
            "Remote user name.";
    }
}

choice remote-auth {
    mandatory true;
    leaf same-pass {
        type empty;
        description
            "If this leaf exists, the password used by the local user
            when logging in to NCS is used as the remote password.";
    }
    leaf remote-password {
        type tailf:aes-256-cfb-128-encrypted-string;
        description
            "Remote password.";
    }
    case public-key {
        uses public-key-auth;
    }
}

leaf remote-secondary-password {
    type tailf:aes-256-cfb-128-encrypted-string;
    description
        "Some CLI based devices require a second
        additional password to enter config mode";
}
}

case callback {
    leaf callback-node {
        description
            "Invoke a standalone action to retrieve login credentials for
            managed devices on the 'callback-node' instance.

            The 'action-name' action is invoked on the callback node that
            is specified by an instance identifier.";
        mandatory true;
        type instance-identifier;
    }
    leaf action-name {
        description
            "The action to call when a notification is received.

            The action must use 'authgroup-callback-input-params'
            grouping for input and 'authgroup-callback-output-params'
            grouping for output from tailf-ncs-devices.yang.";
        type yang:yang-identifier;
        mandatory true;
        tailf:validate ncs {
            tailf:internal;
            tailf:dependency "../callback-node";
        }
    }
}
}
}

```

```

    }
    leaf name {
      type string;
      description
        "The name of the authgroup.";
    }

    container default-map {
      presence "Map unknown users";
      description
        "If an authgroup has a default-map, it is used if a local
        NCS user is not found in the umap list.";
      tailf:info "Remote authentication parameters for users not in umap";
      uses remote-user-remote-auth;
    }

    list umap {
      key local-user;
      description
        "The umap is a list with the local NCS user name as key.
        It maps the local NCS user name to remote authentication
        credentials.";
      tailf:info "Map NCS users to remote authentication parameters";
      leaf local-user {
        type string;
        description
          "The local NCS user name.";
      }
      uses remote-user-remote-auth;
    }
  }
}

```

Each managed device must refer to a named authgroup. The purpose of an authgroup is to map local users to remote users together with the relevant SSH authentication information.

Southbound authentication can be done in two ways. One is to configure stored user and credential components as shown in [Example 11, “Configured authgroup”](#) and [Example 12, “authgroup default-map”](#). The other way is to configure a callback to retrieve user and credentials on demand as shown in [Example 13, “authgroup-callback”](#).

### Example 11. Configured authgroup

```

ncs(config)# show full-configuration devices authgroups
devices authgroups group default
  umap admin
    remote-name      admin
    remote-password  $4$wIo7Yd068FRwhYYI0d4IDw==
  !
  umap oper
    remote-name      oper
    remote-password  $4$zp4zerM68FRwhYYI0d4IDw==
  !
devices authgroups snmp-group default
  default-map community-name public
  umap admin
    usm remote-name admin
    usm security-level auth-priv
    usm auth md5 remote-password $4$wIo7Yd068FRwhYYI0d4IDw==
    usm priv des remote-password $4$wIo7Yd068FRwhYYI0d4IDw==
  !
!

```

In [Example 11, “Configured authgroup”](#) in the authgroup named default the two local users oper and admin shall use the remote users name oper and admin respectively with identical passwords.

Inside an authgroup, all local users need to be enumerated. Each local user name must have credentials configured which should be used for the remote host. In centralized AAA environments this is usually a bad strategy. You may also choose to instantiate a default-map. If you do that it probably only makes sense to specify the same user name/password pair should be used remotely as the pair that was used to log into NSO.

### Example 12. authgroup default-map

```

ncs(config)# devices authgroups group default default-map same-user same-pass
ncs(config-group-default)# commit
Commit complete.
ncs(config-group-default)# top
ncs(config)# show full-configuration devices authgroups
devices authgroups group default
  default-map same-user
  default-map same-pass
  umap admin
    remote-name      admin
    remote-password  $4$wIo7Yd068FRwhYYI0d4IDw==
  !
  umap oper
    remote-name      oper
    remote-password  $4$zp4zerM68FRwhYYI0d4IDw==
  !
!
devices authgroups snmp-group default
  default-map community-name public
  umap admin
    usm remote-name admin
    usm security-level auth-priv
    usm auth md5 remote-password $4$wIo7Yd068FRwhYYI0d4IDw==
    usm priv des remote-password $4$wIo7Yd068FRwhYYI0d4IDw==
  !
!

```

In [Example 11, “Configured authgroup”](#) only two users admin and oper were configured. If the default-map in [Example 12, “authgroup default-map”](#) is configured all local users not found in the umap list will end up in the default-map. For example if user rocky logs in to NSO with password "secret". Since NSO has a built-in SSH server and also a built-in HTTPS server, NSO will be able to pick up the clear text passwords and can then reuse the same password when NSO attempts to establish southbound SSH connections. The user rocky will end up in the default-map and when NSO attempts to propagate rocky's changes towards the managed devices, NSO will use the remote user name rocky with whatever password rocky used to log into NSO.

Authenticating southbound using stored configuration has two main components to define remote user and remote credentials. This is defined by the authgroup. As for southbound user, there exist two options, the same user logged in to NSO or another user, as specified in the authgroup. As for the credentials, there are three options.

- 1 Regular password.
- 2 Public key. This means that a private key, either from a file in the user's SSH key directory, or one that is configured in the /ssh/private-key list in the NSO configuration, is used for authentication. Refer to [the section called “Publickey Authentication”](#) for the details of how the private key is selected.
- 3 Finally, an interesting option is to use the 'same-pass' option. Since NSO runs its own SSH server and its own SSL server, NSO can pick up the password of a user in clear text. Hence, if the 'same-pass'



option is chosen for an authgroup, NSO will reuse the same password when attempting to connect southbound to a managed device.

In case of authenticating southbound using a callback, remote user and remote credentials are obtained by an action invocation. The action is defined by the `callback-node` and `action-name` as in [Example 13, “authgroup-callback”](#) and supported credentials are remote password and optionally a secondary password for the provided local user, authgroup and device.

### Example 13. authgroup-callback

```

ncs(config)# devices authgroups group default umap oper
ncs(config-umap-oper)# callback-node /callback action-name auth-cb
ncs(config-group-oper)# commit
Commit complete.
ncs(config-group-oper)# top
ncs(config)# show full-configuration devices authgroups
devices authgroups group default
  default-map same-user
  default-map same-pass
  umap admin
    remote-name      admin
    remote-password  $4$wIo7Yd068FRwhYYI0d4IDw==
  !
  umap oper
    callback-node /callback
    action-name  auth-cb
  !
!
devices authgroups snmp-group default
  default-map community-name public
  umap admin
    usm remote-name admin
    usm security-level auth-priv
    usm auth md5 remote-password $4$wIo7Yd068FRwhYYI0d4IDw==
    usm priv des remote-password $4$wIo7Yd068FRwhYYI0d4IDw==
  !
!

```

### Example 14. authgroup-callback.yang

```

module authgroup-callback {
  namespace "http://com/example/authgroup-callback";
  prefix authgroup-callback;

  import tailf-common {
    prefix tailf;
  }

  import tailf-ncs {
    prefix ncs;
  }

  container callback {
    description
      "Example callback that defines an action to retrieve
       remote authentication credentials";
    tailf:action auth-cb {
      tailf:actionpoint auth-cb-point;
      input {
        uses ncs:authgroup-callback-input-params;
      }
      output {

```

```

        uses ncs:authgroup-callback-output-params;
    }
}
}

```

In [Example 13, “authgroup-callback”](#), configuration for the `umap` entry of the `oper` user is changed to use a callback to retrieve southbound authentication credentials. Thus, NSO is going to invoke the action `auth-cb` defined in the `callback-node` `callback`. The `callback-node` is of type `instance-identifier` and refers to the container called `callback` defined in [Example 14, “authgroup-callback.yang”](#), which includes an action defined by `action-name` `auth-cb` and uses groupings `authgroup-callback-input-params` and `authgroup-callback-output-params` for input and output parameters respectively. In [Example 13, “authgroup-callback”](#), `authgroup-callback` module was loaded in NSO within an example package. Package development and action callbacks are not described here but more can be read in Chapter 13, *Package Development in NSO 5.7 Development Guide*, the section called “DP API” in *NSO 5.7 Development Guide* and Chapter 11, *Python API Overview in NSO 5.7 Development Guide*.

## Caveats

Authentication groups and the functionality it brings comes with some limitations on where and how it is used.

- Callback option that enables `authgroup-callback` feature is not applicable for members of `snmp-group` list.
- Generic devices that implement own authentication scheme are not using any mapping or callback functionality provided by Authgroups.
- Cluster nodes use their own Authgroups and mapping model thus functionality differ, e.g callback option is not applicable.

## Device Session Pooling

Opening a session towards a managed device is potentially time and resource consuming. Also, the probability that a recently accessed device is still subject to further request is reasonably high. These are motives for having a managed devices session pool in NSO.

The NSO device session pool is by default active and normally needs no maintenance. However under certain circumstances there might be of interest to modify its behaviour. Examples can be when some device type has characteristics that makes session pooling undesired, or when connections to a specific device is very costly and therefore the time that open sessions can stay in the pool should increase.



### Note

Changes from the default configuration of the NSO session pool should only be performed when absolutely necessary and when all effects of the change are understood.

NSO presents operational data that represent the current state of the session pool. To visualize this we use the CLI to connect to NSO and force connection to all known devices:

```
$ ncs_cli -C -u admin
```

```
admin connected from 127.0.0.1 using console on ncs
ncs# devices connect suppress-positive-result
```

We can now list all open sessions in the session-pool. But note that this is a live pool. Sessions will only remain open for a certain amount of time, the idle-time.

```
nsc# show devices session-pool
```

DEVICE	DEVICE TYPE	SESSIONS	MAX SESSIONS	IDLE TIME
ce0	cli	1	unlimited	30
ce1	cli	1	unlimited	30
ce2	cli	1	unlimited	30
ce3	cli	1	unlimited	30
ce4	cli	1	unlimited	30
ce5	cli	1	unlimited	30
pe0	cli	1	unlimited	30
pe1	cli	1	unlimited	30
pe2	cli	1	unlimited	30

In addition to the idle-time for sessions we can also see the type of device, current number of pooled sessions and maximum number of pooled session.

We can close pooled sessions for specific devices.

```
nsc# devices session-pool pooled-device pe0 close
nsc# devices session-pool pooled-device pe1 close
nsc# devices session-pool pooled-device pe2 close
nsc# show devices session-pool
```

DEVICE	DEVICE TYPE	SESSIONS	MAX SESSIONS	IDLE TIME
ce0	cli	1	unlimited	30
ce1	cli	1	unlimited	30
ce2	cli	1	unlimited	30
ce3	cli	1	unlimited	30
ce4	cli	1	unlimited	30
ce5	cli	1	unlimited	30

And we can close all pooled sessions in the session pool.

```
nsc# devices session-pool close
nsc# show devices session-pool
% No entries found.
```

The session pool configuration is found in the `tailf-ncs-devices.yang` submodel. The following part of the YANG device-profile-parameters grouping controls how the session pool is configured:

```
grouping device-profile-parameters {
    ...

    container session-pool {
        tailf:info "Control how sessions to related devices can be pooled.";
        description
            "NCS uses NED sessions when performing transactions, actions
            etc towards a device. When such a task is completed the NED
            session can either be closed or pooled.

            Pooling a NED session means that the session to the
            device is kept open for a configurable amount of
            time. During this time the session can be re-used for a new
            task. Thus the pooling concept exists to reduce the number
            of new connections needed towards a device that is often
            used.

            By default NCS uses pooling for all device types except
            SNMP. Normally there is no need to change the default
            values.";
```

```

leaf max-sessions {
  type union {
    type enumeration {
      enum unlimited;
    }
    type uint32;
  }
  description
    "Controls the maximum number of open sessions in the pool for
    a specific device. When this threshold is exceeded the oldest
    session in the pool will be closed.
    A Zero value will imply that pooling is disabled for
    this specific device. The label 'unlimited' implies that no
    upper limit exists for this specific device";
}

leaf idle-time {
  tailf:info
    "The maximum time that a session is kept open in the pool";
  type uint32 {
    range "1 .. max";
  }
  units "seconds";
  description
    "The maximum time that a session is kept open in the pool.
    If the session is not requested and used before the
    idle-time has expired, the session is closed.
    If no idle-time is set the default is 30 seconds.";
}
}
}
}

```

This grouping can be found in the NSO model under `/ncs:devices/global-settings/session-pool`, `/ncs:devices/profiles/profile/session-pool` and `/ncs:devices/device/session-pool` to be able to control session pooling for all devices, a group of devices and a specific device respectively.

In addition under `/ncs:devices/global-settings/session-pool/default` it is possible to control the global max size of the session pool, as defined by the following yang snippet:

```

container global-settings {
  tailf:info "Global settings for all managed devices.";
  description
    "Global settings for all managed devices. Some of these
    settings can be overridden per managed device.";

  uses device-profile-parameters {
    ...

    augment session-pool {
      leaf pool-max-sessions {
        type union {
          type enumeration {
            enum unlimited;
          }
          type uint32;
        }
        description
          "Controls the grand total session count in the pool."
      }
    }
  }
}

```

```

    Independently on how different devices are pooled the grand
    total session count can never exceed this value.
    A Zero value will imply that pooling is disabled for all devices.
    The label 'unlimited' implies that no upper limit exists for
    the number open sessions in the pool";
  }
}
}

```

Lets illustrate the possibilities with an example configuration of the session pool:

```

ncs# configure
ncs(config)# devices global-settings session-pool idle-time 100
ncs(config)# devices profiles profile small session-pool max-sessions 3
ncs(config-profile-small)# top
ncs(config)# devices device ce* device-profile small
ncs(config-device-ce*)# top
ncs(config)# devices device pe0 session-pool max-sessions 0
ncs(config-device-pe0)# top
ncs(config)# commit
Commit complete.
ncs(config)# exit

```

In the above configuration the default idle-time is set to 100 seconds for all devices. A device profile called small is defined which contains a max-session value of 3 sessions, this profile is set on all ce\* devices. The devices pe0 has a max-sessions 0 which implies that this device cannot be pooled. Lets connect all devices and see what happens in the session pool:

```

ncs# devices connect suppress-positive-result
ncs# show devices session-pool

```

DEVICE	TYPE	SESSIONS	MAX SESSIONS	IDLE TIME
ce0	cli	1	3	100
ce1	cli	1	3	100
ce2	cli	1	3	100
ce3	cli	1	3	100
ce4	cli	1	3	100
ce5	cli	1	3	100
pe1	cli	1	unlimited	100
pe2	cli	1	unlimited	100

Now we set an upper limit to the maximum number of sessions in the pool. Setting the value to 4 is too small for a real situation but serves the purpose of illustration:

```

ncs# configure
ncs(config)# devices global-settings session-pool pool-max-sessions 4
ncs(config)# commit
Commit complete.
ncs(config)# exit

```

The number of open sessions in the pool will be adjusted accordingly:

```

ncs# show devices session-pool

```

DEVICE	TYPE	SESSIONS	MAX SESSIONS	IDLE TIME
ce4	cli	1	3	100
ce5	cli	1	3	100
pe1	cli	1	unlimited	100
pe2	cli	1	unlimited	100

## Device Session Limits

Some devices only allow a small number of concurrent sessions, in the extreme case it only allows one (for example through a terminal server). For this reason NSO can limit the number of concurrent sessions to a device and make operations wait if the maximum number of sessions has been reached.

In other situations, we need to limit the number of concurrent connect attempts made by NSO. For example, the devices managed by NSO talk to the same server for authentication which can only handle a limited number of connections at a time.

The configuration for session limits is found in the `tailf-ncs-devices.yang` submodel. The following part of the YANG `device-profile-parameters` grouping controls how the session limits are configured:

```
grouping device-profile-parameters {
    ...

    container session-limits {
        tailf:info "Parameters for limiting concurrent access to the device.";
        leaf max-sessions {
            type union {
                type enumeration {
                    enum unlimited;
                }
                type uint32 {
                    range "1..max";
                }
            }
            default unlimited;
            description
                "Puts a limit to the total number of concurrent sessions
                 allowed for the device. The label 'unlimited' implies that no
                 upper limit exists for this device.";
        }
    }
    ...
}
```

This grouping can be found in the NSO model under `/ncs:devices/global-settings/session-limits`, `/ncs:devices/profiles/profile/session-limits` and `/ncs:devices/device/session-limits` to be able to control session limits for all devices, a group of devices and a specific device respectively.

In addition under `/ncs:devices/global-settings/session-limits` it is possible to control the number of concurrent connect attempts allowed and the maximum time to wait for a device being available to connect.

```
container global-settings {
    tailf:info "Global settings for all managed devices.";
    description
        "Global settings for all managed devices. Some of these
         settings can be overridden per managed device.";

    uses device-profile-parameters {
        ...

        augment session-limits {
```

```

description
  "Parameters for limiting concurrent access to devices.";
container connect-rate {
  leaf burst {
    type union {
      type enumeration {
        enum unlimited;
      }
      type uint32 {
        range "1..max";
      }
    }
  }
  default unlimited;
  description
    "The number of concurrent connect attempts allowed.
    For example, the devices managed by NSO talk to the same
    server for authentication which can only handle a limited
    number of connections at a time. Then we can limit
    the concurrency of connect attempts with this setting.";
}
}
leaf max-wait-time {
  tailf:info
    "Max time in seconds to wait for device to be available.";
  type union {
    type enumeration {
      enum unlimited;
    }
    type uint32 {
      range "0..max";
    }
  }
  units "seconds";
  default 10;
  description
    "Max time in seconds to wait for a device being available
    to connect. When the maximum time is reached an error
    is returned. Setting this to 0 means that the error is
    returned immediately.";
}
}
...
}

```

## Tracing Device Communication

It is possible to turn on and off NED traffic tracing. This is often a good way to troubleshoot problems. In order to understand the trace output, a basic prerequisite is a good understanding of the native device interface. For NETCONF devices an understanding NETCONF RPC is a prerequisite. Similarly for CLI NEDs, a good understanding of the CLI capabilities of the managed devices is required.

To turn on southbound traffic tracing, we need to enable the feature and we must also configure a directory where we want the trace output to be written. It is possible to have the trace output in two different formats, `pretty` and `raw`. The `pretty` mode indents all the XML data for enhanced readability and the `raw` mode does not. Sometimes when the XML is broken, `raw` mode is required.

To enable tracing do:

```
ncs(config)# devices global-settings trace raw trace-dir .logs
```

```
ncs(config)# commit
```

The trace setting only affect new NED connections, so to ensure that we get any tracing data, we can do:

```
ncs(config)# devices disconnect
```

The above command terminates all existing connections.

At this point if you execute a transaction towards one or several devices and then view the trace data.

```
ncs(config)# do file show logs/ned-cisco-ios-ce0.trace
>> 8-Oct-2014::18:23:18.512 CLI CONNECT to ce0-127.0.0.1:10022 as admin (Trace=true)

*** output 8-Oct-2014::18:23:18.514 ***
-- SSH connecting to host: 127.0.0.1:10022 --
-- SSH initializing session --

*** input 8-Oct-2014::18:23:18.547 ***

admin connected from 127.0.0.1 using ssh on ncs
...
ce0(config)#
*** output 8-Oct-2014::18:23:19.428 ***
snmp-server community topsecret RW
```

It is possible to clear all existing trace files through the command

```
ncs(config)# devices clear-trace
```

Finally, it is worth mentioning the trace functionality does not come for free. It is fairly costly to have the trace turned on. Also, there exists no trace log wrapping functionality.

## Checking Device Configuration

When managing large networks with NSO a good strategy is to consider the NSO copy of the network configuration to be the main master copy. All device configuration changes must go through NSO and all other device re-configurations are considered rogue.

NSO does not contain any functionality which disallows rogue re-configurations of managed devices, however it does contain a mechanism whereby it is a very cheap operation to discover if one or several devices have been configured out-of-band.

The underlying mechanism for the cheap check-sync is to compare time-stamps, transaction-ids, hash-sums, etc depending on what the device supports. This in order not to have to read the full configuration to check if the NSO copy is in sync.

The transaction ids are store in CDB and can be viewed as:

```
ncs# show devices device state last-transaction-id
NAME  LAST TRANSACTION ID
-----
ce0    ef3bbd344ef94b3fec5cb93ac7458c
ce1    48e91db163e294bf5c3978d154922c9
ce2    48e91db163e294bf5c3978d154922c9
ce3    48e91db163e294bf5c3978d154922c9
ce4    48e91db163e294bf5c3978d154922c9
ce5    48e91db163e294bf5c3978d154922c9
ce6    48e91db163e294bf5c3978d154922c9
ce7    48e91db163e294bf5c3978d154922c9
ce8    48e91db163e294bf5c3978d154922c9
```



```

p0      -
p1      -
p2      -
p3      -
pe0     -
pe1     -
pe2     1412-581909-661436
pe3     -

```

Some of the devices does not have a transaction-id, this is the case where the NED has not implemented the cheap check-sync mechanism. Although it is called transaction-id, the underlying value in the device can be anything to detect a config change, like for example a time-stamp.

To actually check for consistency, we execute:

```

ncl# devices check-sync
sync-result {
  device ce0
  result in-sync
}
...
sync-result {
  device p1
  result unsupported
}
...

```

Or alternatively for all (or a subset) managed devices,

```

ncl# devices device ce0..3 check-sync
devices device ce0 check-sync
  result in-sync
devices device ce1 check-sync
  result in-sync
devices device ce2 check-sync
  result in-sync
devices device ce3 check-sync
  result in-sync

```

The following YANG grouping is used for the return value from the check-sync command:

```

grouping check-sync-result {
  description
    "Common result data from a 'check-sync' action.";

  leaf result {
    type enumeration {
      enum unknown {
        description
          "NCS have no record, probably because no
          sync actions have been executed towards the device.
          This is the initial state for a device.";
      }
      enum locked {
        tailf:code-name 'sync_locked';
        description
          "The device is administratively locked, meaning that NCS
          cannot talk to it.";
      }
      enum in-sync {
        tailf:code-name 'in-sync-result';
        description
          "The configuration on the device is in sync with NCS.";
      }
    }
  }
}

```

```

    }
    enum out-of-sync {
      description
        "The device configuration is known to be out of sync, i.e.,
        it has been reconfigured out of band.";
    }
    enum unsupported {
      description
        "The device doesn't support the tailf-netconf-monitoring
        module.";
    }
    enum error {
      description
        "An error occurred when NCS tried to check the sync status.
        The leaf 'info' contains additional information.";
    }
  }
}
}

```

## Comparing Device Configurations

In the previous section we described how we can easily check if a managed device is in sync. If the device is not in sync, we are interested to know what the difference is. The CLI sequence below shows how to modify ce0 out of band using the ncs-netsim tool. Finally the sequence shows how to do an explicit configuration comparison.

```

$ ncs-netsim cli-i ce0
admin connected from 127.0.0.1 using console on ncs
ce0> enable
ce0# configure
Enter configuration commands, one per line. End with CNTL/Z.
ce0(config)# snmp-server community foobar RW
ce0(config)# exit
ce0# exit
$ ncs_cli -C -u admin

admin connected from 127.0.0.1 using console on ncs
ncs# devices device ce0 check-sync
result out-of-sync
info got: 290fa2b49608df9975c9912e4306110 expected: ef3bbd344ef94b3fec5cb93ac7458c

ncs# devices device ce0 compare-config
diff
devices {
  device ce0 {
    config {
      ios:snmp-server {
+       community foobar {
+         RW;
+       }
    }
  }
}

```

The diff in the above output should be interpreted as: what needs to be done in NSO to become in sync with the device.

Previously in [Example 6, “Synchronize from Devices”](#) NSO was brought in sync with the devices by fetching configuration from the devices. In this case where the device has a rogue re-configuration NSO

has the correct configuration. In such cases you want to reset the device configuration to what is store inside NSO.

When you decide to reset the configuration with the copy kept in NSO use the option `dry-run` in conjunction with `sync-to` and inspect what will be sent to the device:

```
ncs# devices device ce0 sync-to dry-run
data
    no snmp-server community foobar RW
ncs#
```

As this is the desired data to send to the device a `sync-to` can now safely be performed.

```
ncs# devices device ce0 sync-to
result true
ncs#
```

The device configuration should now be in sync with the copy in NSO and `compare-config` ought to yield an empty output:

```
ncs# devices device ce0 compare-config
ncs#
```

## Initialize Device

There exists several ways to initialize new devices. The two common ways are to initialize a device from another existing device or to use device-templates.

### From other

For example another CE router has been added to our example network. You want to base the configuration of that host on the configuration of the managed device `ce0` which has a valid configuration:

```
ncs(config)# show full-configuration devices device ce0
devices device ce0
  address 127.0.0.1
  port 10022
  ssh host-key ssh-dss
  key-data "AAAAB3NzaClkc3MAAACBAO9tkTdZgAqJMz8m...
  !
  authgroup default
  device-type cli ned-id cisco-ios-cli-3.8
  state admin-state unlocked
  config
    no ios:service pad
    no ios:ip domain-lookup
    no ios:ip http secure-server
    ios:ip source-route
    ios:interface GigabitEthernet0/1
    exit
    ios:interface GigabitEthernet0/10
    exit
    ios:interface GigabitEthernet0/11
    exit
    ios:interface GigabitEthernet0/12
    exit
    ios:interface GigabitEthernet0/13
    exit
    ios:interface GigabitEthernet0/14
    exit
```

....

If the configuration is accurate you can create a new managed device based on that configuration as:

### Example 15. Instantiate device from other

```

ncs(config)# devices device ce9 address 127.0.0.1 port 10031
ncs(config-device-ce9)# device-type cli ned-id cisco-ios-cli-3.8
ncs(config-device-ce9)# authgroup default
ncs(config-device-ce9)# instantiate-from-other-device device-name ce0
ncs(config-device-ce9)# top
ncs(config)# show configuration
devices device ce9
  address 127.0.0.1
  port 10031
  authgroup default
  device-type cli ned-id cisco-ios-cli-3.8
  config
    no ios:service pad
    no ios:ip domain-lookup
    no ios:ip http secure-server
    ios:ip source-route
    ios:interface GigabitEthernet0/1
  exit
....
ncs(config)# commit
Commit complete.

```

In [Example 15, “Instantiate device from other”](#) the commands first creates the new managed device, `ce9` and then populates the configuration of the new device based on the configuration of `ce0`.

This new configuration might not be entirely correct, you can modify any configuration before committing it.

The above concludes the instantiation of a new managed device. The new device configuration is committed and NSO returned OK without the device existing in the network (netsim). Try force a sync to the device:

```

ncs(config)# devices device ce9 sync-to
result false
info Device ce9 is southbound locked

```

The device is `southbound locked`, this is a mode which is used where you can reconfigure a device, but any changes done to it are never sent to the managed device. This will be thoroughly described in the next section. Devices are by default created southbound locked. Default values are not shown if not explicitly requested:

```

(config)# show full-configuration devices device ce9 state | details
devices device ce9
  state admin-state southbound-locked
!

```

## By Template

An other alternative to instantiating a device from the actual working configuration of another device is to have a number of named device templates which manipulates the configuration.

The template tree looks like:

```

submodule tailf-ncs-devices {

```

```

namespace "http://tail-f.com/ns/ncs";
...
container devices {
    .....
    list template {
        description
            "This list is used to define named template configurations that
            can be used to either instantiate the configuration for new
            devices, or to apply snippets of configurations to existing
            devices."
        ...
        ";

        key name;
        leaf name {
            description "The name of a specific template configuration";
            type string;
        }
        list ned-id {
            key id;
            leaf id {
                type identityref {
                    base ned:ned-id;
                }
            }
            container config {
                tailf:mount-point ncs-template-config;
                tailf:cli-add-mode;
                tailf:cli-expose-ns-prefix;
                description
                    "This container is augmented with data models from the devices.";
            }
        }
    }
}

```

The tree for device templates is generated from all device YANG models. All constraints are removed and the data type of all leafs is changed to string

A device template is created by setting the desired data in the configuration. The created device template is stored in NSO CDB.

### Example 16. Create ce-initialize template

```

ncs(config)# devices template ce-initialize ned-id cisco-ios-cli-3.8 config
ncs(config-config)# no ios:service pad
ncs(config-config)# no ios:ip domain-lookup
ncs(config-config)# ios:ip dns server
ncs(config-config)# no ios:ip http server
ncs(config-config)# no ios:ip http secure-server
ncs(config-config)# ios:ip source-route true
ncs(config-config)# ios:interface GigabitEthernet 0/1
ncs(config- GigabitEthernet-0/1)# exit
ncs(config-config)# ios:interface GigabitEthernet 0/2
ncs(config- GigabitEthernet-0/2)# exit
ncs(config-config)# ios:interface GigabitEthernet 0/3
ncs(config- GigabitEthernet-0/3)# exit
ncs(config-config)# ios:interface Loopback 0
ncs(config-Loopback-0)# exit
ncs(config-config)# ios:snmp-server community public RO
ncs(config-community-public)# exit
ncs(config-config)# ios:snmp-server trap-source GigabitEthernet 0/2
ncs(config-config)# top

```

```
ncs(config)# commit
```

The device template created in [Example 16, “Create ce-initialize template”](#) can now be used to initialize single devices or device groups, [the section called “Device Groups”](#)

In the following CLI session a new device `ce10` is created:

```
ncs(config)# devices device ce10 address 127.0.0.1 port 10032
ncs(config-device-ce10)# device-type cli ned-id cisco-ios-cli-3.8
ncs(config-device-ce10)# authgroup default
ncs(config-device-ce10)# top
ncs(config)# commit
```

Initialize the newly created device `ce10` with the device template `ce-initialize`:

```
ncs(config)# devices device ce10 apply-template template-name ce-initialize
apply-template-result {
  device ce10
  result no-capabilities
  info No capabilities found for device: ce10. Has a sync-from the device
    been performed?
}
```

When initializing devices NSO does not have any knowledge about the capabilities of the device, no connect has been done. This can be overridden by the option `accept-empty-capabilities`

```
ncs(config)# devices device ce10 \
apply-template template-name ce-initialize accept-empty-capabilities
apply-template-result {
  device ce10
  result ok
}
```

Inspect the changes made by the template `ce-initialize`

```
ncs(config)# show configuration
devices device ce10
config
  ios:ip dns server
  ios:interface GigabitEthernet0/1
  exit
  ios:interface GigabitEthernet0/2
  exit
  ios:interface GigabitEthernet0/3
  exit
  ios:interface Loopback0
  exit
  ios:snmp-server community public RO
  ios:snmp-server trap-source GigabitEthernet0/2
  !
  !
```

## Device Templates



### Note

This section shows how *Device-templates* can be used to create and change device configuration. See the section called “Introduction” in *NSO 5.7 Development Guide* for other ways of using templates.

*device-templates* are part of the NSO configuration. *device-templates* are created and changed in the tree `/devices/template/config` the same way as any other configuration data and are affected by

rollbacks and upgrades. *Device-templates* can only manipulate configuration data in the `/devices/device/config` tree i.e. only device data.

The `$NCS_DIR/examples.ncs/service-provider/mpls-vpn` example comes with a pre-populated template for SNMP settings.

```
ncs(config)# show full-configuration devices template
devices template snmp1
  ned-id cisco-ios-cli-3.8
  config
    ios:snmp-server community {$COMMUNITY}
    RO
    !
  !
  ned-id cisco-iosxr-cli-3.5
  config
    cisco-ios-xr:snmp-server community {$COMMUNITY}
    RO
    !
  !
  ned-id juniper-junos-nc-3.0
  config
    junos:configuration snmp community {$COMMUNITY}
    authorization read-only
    !
  !
  !
```

**Note**

The variable `$DEVICE` is used internally by NSO and can not be used in a template.

Templates can be created like any configuration data and use the CLI tab completion to navigate. Variables can be used instead of hard-coded values. In the template above the community string is a variable. The template can cover several device-types/NEDs, by making use of the namespace information. This will make sure that only devices modeled with this particular namespace will be affected by this part of the template. Hence, it is possible for one template to handle a multitude of devices from various manufacturers.

A template can be applied to a device, a device-group and a range of devices. It can be used as shown in [the section called “By Template”](#) to create the day zero config for a newly created device.

Applying the `snmp1` template, providing a value for the `COMMUNITY` template variable:

```
ncs(config)# devices device ce2 apply-template template-name \
  snmp1 variable { name COMMUNITY value 'FUZBAR' }
ncs(config)# show configuration
devices device ce2
  config
    ios:snmp-server community FUZBAR RO
    !
  !
ncs(config)# commit dry-run outformat native
native {
  device {
    name ce2
    data snmp-server community FUZBAR RO
```

```

    }
}
ncs(config)# commit
Commit complete.

```

The result of applying the template:

```

ncs(config)# show full-configuration devices device ce2 config\
    ios:snmp-server
devices device ce2
config
    ios:snmp-server community FUZBAR RO
!
!

```

## Tags

The default operation for templates is to merge the configuration. Tags can be added to templates to have the template merge, replace, delete, create or nocreate configuration. A tag is inherited to its sub-nodes until a new tag is introduced.

- *merge*: Merge with a node if it exists, otherwise create the node. This is the default operation if no operation is explicitly set.
- *replace*: Replace a node if it exists, otherwise create the node.
- *create*: Creates a node. The node can not already exist.
- *nocreate*: Merge with a node if it exists. If it does not exist, it will *not* be created.

Example on how to set a tag:

```

ncs(config)# tag add devices template snmpl ned-id cisco-ios-cli-3.8 config\
    ios:snmp-server community ${COMMUNITY} replace

```

Displaying Tags information::

```

ncs(config)# show configuration
devices template snmpl
    ned-id cisco-ios-cli-3.8
    config
        ! Tags: replace
        ios:snmp-server community ${COMMUNITY}
    !
    !
!
!

```

## Debug

By adding the CLI pipe flag `debug template` when applying a template, the CLI will output detailed information on what is happening when the template is being applied:

```

ncs(config)# devices device ce2 apply-template template-name \
    snmpl variable { name COMMUNITY value 'FUZBAR' } | debug template
Operation 'merge' on existing node: /devices/device[name='ce2']
The device /devices/device[name='ce2'] does not support
namespace 'http://tail-f.com/ned/cisco-ios-xr' for node "snmp-server"
Skipping...
The device /devices/device[name='ce2'] does not support
namespace 'http://xml.juniper.net/xnm/1.1/xnm' for node "configuration"
Skipping...

```



```
Variable $COMMUNITY is set to "FUZBAR"
Operation 'merge' on non-existing node:
/devices/device[name='ce2']/config/ios:snmp-server/community[name='FUZBAR']
Operation 'merge' on non-existing node:
/devices/device[name='ce2']/config/ios:snmp-server/community[name='FUZBAR']/RO
```

## Oper State and Admin State

NSO differentiates between oper state and admin state for a managed device. Oper state is the actual state of the device. We have chosen to implement a very simple oper state model. A managed device oper state is either enabled or disabled. Oper state can be mapped to an alarm for the device. If the device is disabled, we may have additional error information. For example the `ce9` device created from another device and `ce10` created with a device template in the previous section is disabled, no connection has been established with the device, so its state is completely unknown:

```
nsc# show devices device ce9 state oper-state
state oper-state disabled
```

Or slight more interesting, CLI usage:

```
nsc# show devices device state oper-state
      OPER
NAME  STATE
-----
ce0   enabled
ce1   enabled
ce10  disabled
ce2   enabled
ce3   enabled
ce4   enabled
ce5   enabled
ce6   enabled
ce7   enabled
ce8   enabled
ce9   disabled
p0    enabled
p1    enabled
p2    enabled
p3    enabled
pe0   enabled
pe1   enabled
pe2   enabled
pe3   enabled

nsc# show devices device ce0..9 state oper-state
      OPER
NAME  STATE
-----
ce0   enabled
ce1   enabled
ce2   enabled
ce3   enabled
ce4   enabled
ce5   enabled
ce6   enabled
ce7   enabled
ce8   enabled
ce9   disabled
```

If you manually stop a managed device, for example `ce0`, NSO doesn't immediately indicate that. NSO may have an active SSH connection to the device, but the device may voluntarily choose to close its end

of that (idle) SSH connection. Thus the fact that a socket from the device to NSO is closed by the managed device doesn't indicate anything. The only certain method NSO has to decide a managed device is non-operational - from the point of view of NSO - is NSO cannot SSH connect to it. If you manually stop managed device `ce0`, you still have:

```
$ ncs-netsim stop ce0
DEVICE ce0 STOPPED
$ ncs_cli -C -u admin
ncs# show devices device ce0 state oper-state
state oper-state enabled
```

NSO cannot draw any conclusions from the fact that a managed device closed its end of the SSH connection. It may have done so because it decided to time out an idle SSH connection. Whereas if NSO tried to initiate any operations towards the dead device, the device will be marked as oper state disabled:

```
ncs(config)# devices device ce0 config ios:snmp-server contact joe@acme.com
ncs(config-config)# commit
Aborted: Failed to connect to device ce0: connection refused: Connection refused
ncs(config-config)# *** ALARM connection-failure: Failed to
connect to device ce0: connection refused: Connection refused
```

Now, NSO has failed to connect to it, NSO knows that `ce0` is dead:

```
ncs# show devices device ce0 state oper-state
state oper-state disabled
```

This concludes the oper state discussion. Next state to be illustrated is the admin state. The admin state is what the operator configures, this is the desired state of the managed device.

In `tailf-ncs.yang` we have the following configuration definition for admin state:

#### Example 17. `tailf-ncs-devices.yang` - Admin state

```
submodule tailf-ncs-devices {
  ....

  typedef admin-state {
    type enumeration {
      enum locked {
        description
          "When a device is administratively locked, it is not possible
          to modify its configuration, and no changes are ever
          pushed to the device.";
      }
      enum unlocked {
        description
          "Device is assumed to be operational.
          All changes are attempted to be sent southbound.";
      }
      enum southbound-locked {
        description
          "It is possible to configure the device, but
          no changes are sent to the device. Useful admin mode
          when pre provisioning devices. This is the default
          when a new device is created.";
      }
      enum config-locked {
        description
          "It is possible to send live-status commands or RPCs
          but it is not possible to modify the configuration
```

```

        of the device.";
    }
}
}

....
container devices {
    ....
    container state {
        ....
        leaf admin-state {
            type admin-state;
            default southbound-locked;
        }

        leaf admin-state-description {
            type string;
            description
                "Reason for the admin state.";
        }
    }
}

```

In [Example 17, “tailf-ncs-devices.yang - Admin state”](#) you can see the four different admin states for a managed device as defined in the YANG model.

- **locked** - This means that all changes to the device are forbidden. Any transaction which attempts to manipulate the configuration of the device will fail. It is still possible to read the configuration of the device.
- **unlocked** - This is the state a device is set into when the device is operational. All changes to the device are attempted to be sent southbound.
- **southbound-locked** - This is the default value. It means that it is possible to manipulate the configuration of the device but changes done to the device configuration are never pushed to the device. This mode is useful during e.g. pre-provisioning, or when we instantiate new devices.
- **config-locked** - This means that any transaction which attempts to manipulate the configuration of the device will fail. It is still possible read the configuration of the device and send live-status commands or RPCs.

## Configuration Source

NSO manages a set of devices which are given to NSO through any means like CLI, inventory system integration through XML APIs, or configuration files at startup. The list of devices to manage in an overall integrated network management solution is shared between different tools and therefore it is important to keep an authoritative database of this and share it between different tools including NSO. The purpose of this part is to identify the source of the population of managed devices. The source attribute should indicate the source of the managed device like "inventory", "manual", "EMS".

### Example 18. tailf-ncs-devices.yang - source

```

submodule tailf-ncs-devices {
    ...
    container source {
        tailf:info "How the device was added to NCS";
        leaf added-by-user {
            type string;
        }
        leaf context {

```

```

        type string;
    }
    leaf when {
        type yang:date-and-time;
    }
    leaf from-ip {
        type inet:ip-address;
    }
    leaf source {
        type string;
        reference "TMF518 NRB Network Resource Basics";
    }
}

```

These attributes should be automatically set by the integration towards the inventory source rather than manipulated manually.

- `added-by-user` - Identify the user which loaded the managed device.
- `context` in what context was the device loaded.
- `when` - when the device was added to NSO.
- `from-ip` - from which IP the load activity was run..
- `source` - identify the source of the managed device such as the inventory system name or the name of the source file.

## Capabilities, Modules and Revision Management

The NETCONF protocol mandates that the first thing both the server and the client has to do is to send its list of NETCONF capabilities in the `<hello>` message. A capability indicates what the peer can actually do. For example the `validate:1.0` indicates that the server can validate a proposed configuration change, whereas the capability `http://acme.com/if` indicates the device implements the `http://acme.com` proprietary capability.

The NEDs report the capabilities for the devices at connection time. The NEDs also load the YANG modules for NSO. For a NETCONF/YANG device all this is straight-forward, for non NETCONF devices the NEDs does the translation.

The capabilities announced by a device also contain the YANG version 1 modules supported. In addition to this, YANG version 1.1 modules are advertised in the YANG library module on the device. NSO checks both the capabilities and the YANG library to find out which YANG modules a device supports.

The capabilities and modules detected by NSO are available in two different lists, `/devices/device/capability` and `/devices/device/module`. The `capability` list contains all capabilities announced and all YANG modules in the YANG library. The `module` list contains all YANG modules announced that are also supported by the NED in NSO.

```

nscs# show devices device ce0 capability
capability urn:ietf:params:netconf:capability:with-defaults:1.0?basic-mode=trim
capability urn:ios
revision 2015-03-16
module tailf-ned-cisco-ios
capability urn:ios-stats
revision 2015-03-16
module tailf-ned-cisco-ios-stats

```

```

nscs# show devices device ce0 capability module
NAME                                REVISION    FEATURE    DEVIATION
-----

```

```
tailf-ned-cisco-ios      2015-03-16  -      -
tailf-ned-cisco-ios-stats 2015-03-16  -      -
```

NSO can be used to handle all or some of the YANG configuration modules for a device. A device may announce several modules through its capability list which NSO ignores. NSO will only handle the YANG modules for a device which are loaded (and compiled through **ncsc --ncs-compile-bundle**) or **ncsc --ncs-compile-module**) all other modules for the device are ignored. If you require a situation where NSO is entirely responsible for a device so that complete device backup/configurations are stored in NSO you must ensure NSO indeed has support for all modules for the device. It is not possible to automate this process since a capability URI doesn't necessary indicate actual configuration.

## Discovery of a NETCONF Device

When a device is added to NSO its NED id must be set. For a NETCONF device, it is possible to configure the generic NETCONF NED id `netconf` (defined in the YANG module `tailf-ncs-ned`). If this NED id is configured, we can then ask NSO to connect to the device and then check the `capability` list to see which modules this device implements.

```
ncs(config)# devices device foo address 127.0.0.1 port 12033 authgroup default
ncs(config-device-foo)# device-type netconf ned-id netconf
ncs(config-device-foo)# state admin-state unlocked
ncs(config-device-foo)# commit
Commit complete.
ncs(config-device-foo)# exit
ncs(config)# exit
ncs# devices fetch-ssh-host-keys device foo
fetch-result {
    device foo
    result updated
    fingerprint {
        algorithm ssh-rsa
        value 14:3c:79:87:69:8e:e2:f0:6d:43:07:8c:89:41:fd:7f
    }
}
ncs# devices device foo connect
result true
info (admin) Connected to foo - 127.0.0.1:12033
ncs# show devices device foo capability
capability :candidate:1.0
capability :confirmed-commit:1.0
...
capability http://xml.juniper.net/xnm/1.1/xnm
module junos
capability urn:ietf:params:xml:ns:yang:ietf-yang-types
revision 2013-07-15
module ietf-yang-types
capability urn:juniper-rpc
module junos-rpc
...
```

We can also check which modules the loaded NEDs supports. Then we can pick the most suitable NED and configure the device with this NED id.

```
ncs# show devices ned-ids
ID              NAME              REVISION
-----
cisco-ios-xr-v2  tailf-ned-cisco-ios-xr      -
                  tailf-ned-cisco-ios-xr-stats -
lsa-netconf
netconf
```

```

snmp
alu-sr-cli-3.4      tailf-ned-alu-sr      -
                   tailf-ned-alu-sr-stats -
cisco-ios-cli-3.8   tailf-ned-cisco-ios      -
                   tailf-ned-cisco-ios-stats -
cisco-iosxr-cli-3.5 tailf-ned-cisco-ios-xr   -
                   tailf-ned-cisco-ios-xr-stats -
juniper-junos-nc-3.0 junos                    -
                   junos-rpc          -
nscs# config
Entering configuration mode terminal
nscs(config)# devices device foo device-type netconf ned-id juniper-junos-nc-3.0
nscs(config-device-foo)# commit
Commit complete.

```

## Configuration Datastore Support

NSO works best if the managed devices support the NETCONF candidate configuration datastore. However, NSO reads the capabilities of each managed devices and executes different sequences of NETCONF commands towards different types of devices.

For implementations of the NETCONF protocol that do not support the candidate datastore, and in particular devices that do not support NETCONF commit with a timeout, NSO tries to do the best of the situation.

NSO divides devices in the following groups.

- *start\_trans\_running* - This mode is used for devices that support the Tail-f proprietary transaction extension defined by <http://tail-f.com/ns/netconf/transactions/1.0>. Read more on this in the Tail-f ConfD user guide. In principle it's a means to - over the NETCONF interface - control transaction processing towards the running data store. This may be more efficient than going through the candidate data store. The downside is that it is Tail-f proprietary non-standardized technology.
- *lock\_candidate* - This mode is used for devices that support the candidate data store but disallow direct writes to the running data store.
- *lock\_reset\_candidate* - This mode is used for devices that support the candidate data and also allow direct writes to the running data store. This is the default mode for Tail-f ConfD NETCONF server. Since the running data store is configurable, we must, prior to each configuration attempt, copy all of running to the candidate. (ConfD has optimized this particular usage pattern, so this is a very cheap operation for ConfD)
- *startup* - This mode is used for devices that have writable running, no candidate but do support the startup data store. This is the typical mode for Cisco like devices.
- *running-only* - This mode is used for devices that only support writable running.
- *NED* - The transaction is controlled by a Network Element Driver. The exact transaction mode depends on the type of the NED.

Which category NSO chooses for a managed device depends on which NETCONF capabilities the devices sends to NSO in its NETCONF *hello* message. You can see in the CLI what NSO has decided for a device as in:

```

nscs# show devices device ce0 state transaction-mode
state transaction-mode ned
nscs# show devices device pe2 state transaction-mode
state transaction-mode lock-candidate

```

NSO talking to ConfD device running in its standard configuration, thus *lock-reset-candidate*

Another important discriminator between managed devices is whether they support the confirmed commit with a timeout capability, i.e. the *confirmed-commit:1.0* standard NETCONF capability. If a device supports this capability, NSO utilizes it. This is the case with for example Juniper routers.

If a managed device does not support this capability, NSO attempts to the best it can.

This is how NSO handles common failure scenarios:

- The operator aborts the transaction, or NSO loses the SSH connection to another managed device which is also participating in the same network transaction.  
If the device does support the *confirmed-commit* capability, NSO aborts the outstanding yet-uncommitted transaction simply by closing the SSH connection.  
When the device does not support the *confirmed-commit* capability, NSO has the reverse diff and simply sends the precise undo information to the device instead.
- The device rejects the transaction in the first place, i.e. the NSO attempt to modify its running data store. This is an easy case since NSO then simply aborts the transaction as a whole in the initial `commit confirmed [time]` attempt.
- NSO loses SSH connectivity to the device during the timeout period. This is a real error case and the configuration is now in an unknown state. NSO will abort the entire transaction, but the configuration of the failing managed device is now probably in error. The correct procedure once network connectivity has been restored to the device is to sync it in direction from NSO to the device. The NSO copy of the device configuration will be what was configured prior to the failed transaction.

Thus, even if not all participating devices have first class NETCONF server implementations, NSO will attempt to fake the *confirmed-commit* capability.

## Action Proxy

When the managed device defines top level NETCONF RPCs or alternatively define *tailf:action* points inside the YANG model, these RPCs and actions are also imported into the data model that resides in NSO.

For example the Juniper NED comes with a set of JunOS RPCs defined in: `$NCS_DIR/packages/neds/juniper-junos/src/yang/junos-rpc.yang`

```
module junos-rpc {
  ...
  rpc request-package-add {
    ...
  }
  rpc request-reboot {
    ...
  }
  rpc get-software-information {
    ...
  }
  rpc ping {
    ...
  }
}
```

Thus, since all RPCs and actions from the devices are accessible through the NSO data model, these actions are also accessible through all NSO northbound APIs, REST, JAVA MAAPI etc. Hence it is possible to - from user scripts/code - invoke actions and RPCs on all managed devices. The RPCs are augmented below an RPC container:

```
ncs(config)# devices device pe2 rpc rpc-
Possible completions:
  rpc-get-software-information  rpc-idle-timeout  rpc-ping \
  rpc-request-package-add  rpc-request-reboot

ncs(config)# devices device pe2 rpc \
```

```
rpc-get-software-information get-software-information brief
```

In the simulated environment of the mpls-vpn example these RPCs might not have been implemented.

## Device Groups

The NSO device manager has a concept of groups of devices. A group is nothing more than a named group of devices. What makes this interesting is that we can invoke several different actions on the group, thus implicitly invoking the the action on all members in the group. This is especially interesting for the *apply-template* action.

The definition of device groups reside at the same layer in the NSO data model as the device list, thus we have:

### Example 19. Device Groups

```
submodule tailf-ncs-devices {
  namespace "http://tail-f.com/ns/ncs";
  ...
  container devices {
    .....
    list device {
      ...
    }
    list device-group {
      key name;
      leaf name {
        type string;
      }
      description
        "A named group of devices, some actions can be
        applied to an entire group of devices, for example
        apply-template, and the sync actions.";
      leaf-list device-name {
        type leafref {
          path "/devices/device/name";
        }
      }
      leaf-list device-group {
        type leafref {
          path "/devices/device-group/name";
        }
      }
      description
        "A list of device groups contained in this device group.

        Recursive definitions are not valid.";
    }
    leaf-list member {
      type leafref {
        path "/devices/device/name";
      }
      config false;
      description
        "The current members of the device-group. This is a flat list
        of all the devices in the group.";
    }
    uses connect-grouping ;
    uses sync-grouping;
    uses check-sync-grouping;
    uses apply-template-grouping;
  }
}
```



```
}
}
```

The MPLS VPN example comes with a couple of pre-defined device-groups:

```
ncs(config)# show full-configuration devices device-group
devices device-group C
  device-name [ ce0 ce1 ce3 ce4 ce5 ce6 ce7 ce8 ]
!
devices device-group P
  device-name [ p0 p1 p2 p3 ]
!
devices device-group PE
  device-name [ pe0 pe1 pe2 pe3 ]
!
```

Device groups are created like below:

### Example 20. Create device group

```
ncs(config)# devices device-group my-group device-name ce0
ncs(config-device-group-my-group)# device-name pe
Possible completions:
  pe0 pe1 pe2 pe3
ncs(config-device-group-my-group)# device-name pe0
ncs(config-device-group-my-group)# device-name p0
ncs(config-device-group-my-group)# commit
```

Device-groups can reference other device-groups. There is an operational attribute that flattens all members in the group. The CLI sequence below adds the PE group to my-group. Then it shows the configuration of that group followed by the status for this group. The status for the group contains a members attribute that lists all device members.

```
ncs(config-device-group-my-group)# device-group PE
ncs(config-device-group-my-group)# commit

ncs(config)# show full-configuration devices device-group my-group
devices device-group my-group
  device-name [ ce0 p0 pe0 ]
  device-group [ PE ]
!
ncs(config)# exit

ncs# show devices device-group my-group
NAME          MEMBER                                INDETERMINATES  CRITICALS  MAJORS  MINORS  WARNINGS
-----
my-group [ ce0 p0 pe0 pe1 pe2 pe3 ]  0              0           1         0         0
```

Once you have a group, you can sync and check-sync the entire group.

```
ncs# devices device-group C sync-to
```

However, what makes device groups really interesting is the ability to apply a template to a group. You can use the pre-populated templates to apply SNMP settings to device-groups.

```
ncs(config)# devices device-group C apply-template \
template-name snmp1 variable { name COMMUNITY value 'cinderella' }
ncs(config)# show configuration
devices device ce0
  config
    ios:snmp-server community cinderella RO
```

```

!
!
devices device ce1
  config
    ios:snmp-server community cinderella RO
  !
!
...
ncs(config)# commit

```

## Policies

Policies allows you to specify network wide constraints that always must be true. If someone tries to apply a configuration change over any northbound interface that would evaluate to false the configuration change is rejected by NSO. Policies can be of type warning means that it is possible to override them, or error which cannot be overridden.

Assume you would like to enforce all CE routers to have a Gigabit interface 0/1.

### Example 21. Policies

```

ncs(config)# policy rule gb-one-zero
ncs(config-rule-gb-one-zero)# foreach /ncs:devices/device[starts-with(name,'ce')]/config
ncs(config-rule-gb-one-zero)# expr ios:interface/ios:GigabitEthernet[ios:name='0/1']
ncs(config-rule-gb-one-zero)# warning-message "{../name} should have 0/1 interface"
ncs(config-rule-gb-one-zero)# commit
zork(config-rule-gb-one-zero)# top
zork(config)# !
ncs(config)# show full-configuration policy
policy rule gb-one-zero
  foreach          /ncs:devices/device[starts-with(name,'ce')]/config
  expr             ios:interface/ios:GigabitEthernet[ios:name='0/1']
  warning-message  "{../name} should have 0/1 interface"
!
ncs(config)# no devices device ce0 config ios:interface GigabitEthernet 0/1
ncs(config)# validate
Validation completed with warnings:
  ce0 should have 0/1 interface
ncs(config)# no devices device ce1 config ios:interface GigabitEthernet 0/1
ncs(config)# validate
Validation completed with warnings:
  ce1 should have 0/1 interface
  ce0 should have 0/1 interface
ncs(config)# commit
The following warnings were generated:
  ce1 should have 0/1 interface
  ce0 should have 0/1 interface
Proceed? [yes,no] yes
Commit complete.

```

As seen in [Example 21, “Policies”](#) a policy rule has (an optional) for each statement and a mandatory expression and error-message. The `foreach` statement evaluates to a node set, the expression is then evaluated on each node. So in this example the expression would be evaluated for every device in NSO which begins with `ce`. The name variable in the warning-message refers to a leaf available from the for-each node-set.

Validation is always performed at commit but can also be requested interactively.

Note any configuration can be activated or deactivated. This means that in order to temporarily turn off a certain policy you can deactivate it. Note also that if the configuration was changed by any other means

than NSO by local tools to the device like a CLI, a **devices sync-from** operation might fail if the device configuration violates the policy.

## Commit Queue

One of the strengths of NSO is the concept of "network wide transactions". When you commit data to NSO that spans multiple devices in the `/ncs:devices/device` tree, NSO will - within the NSO transaction - commit the data on all devices or none, keeping the network consistent with CDB. The NSO transaction doesn't return until all participants have acknowledged the proposed configuration change. The downside of this is that the slowest device in each transaction limits the overall transactional throughput in NSO. Such things as out of sync checks, network latency, calculation of changes sent southbound or device deficiencies all affects the throughput.

Typically when automation software north of NSO generates network change requests it may very well be the case more requests arrive than what can be handled. In NSO deployments scenarios where you wish to have higher transactional throughput than what is possible using "network wide transactions", you can use the commit queue instead. The goal of the commit queue is to increase the transactional throughput of NSO while keeping an eventual consistency view of the database. With the commit queue, NSO will compute the configuration change for each participating device, put it in an outbound queue item and immediately return. The queue is then independently run.

Another use case where you can use the commit queue is when you wish to push a configuration change to a set of devices and don't care about whether all devices accept the change or not. You do not want the default behavior for transactions which is to reject the transaction as a whole if one or more participating devices fail to process its part of the transaction.

An example of the above could be you wish to set a new NTP server on all managed devices in our entire network, if one or more devices currently are non operational, you still want to push out the change. You also want the change automatically pushed to the non operational devices once they go live again.

The big upside of this scheme is that the transactional throughput through NSO is considerably higher. Also transient devices are handled better. The downsides are:

- 1 If a device rejects the proposed change, NSO and the device are now *out of sync* until any error recovery is performed. Whenever this happens, an NSO alarm (called commit-through-queue-failed) is generated.
- 2 While a transaction remains in the queue, i.e it has been accepted for delivery by NSO but is not yet delivered, the view of the network in NSO is not (yet) correct. Eventually though, the queued item will be delivered, thus achieving eventual consistency.

To facilitate the two use cases of the commit queue the outbound queue item can be either in an atomic or non-atomic mode.

In atomic mode the outbound queue item will push all configuration changes concurrently once there are no intersecting devices ahead in the queue. If any device rejects the proposed change, all device configuration changes in the queue item will be rejected as a whole, leaving the network in a consistent state. The atomic mode also allows for automatic error recovery to be performed by NSO.

In the non-atomic mode the outbound queue item will push configuration changes for a device whenever all occurrences of it is completed or it doesn't exist ahead in the queue. The drawback to this mode is that there are no automatic error recovery that can be performed by NSO.

In the following sequences the simulates device ce0 is stopped to illustrate the commit queue. This can be achieved by the following sequence including returning to the NSO CLI config mode:

```
$ ncs-netsim stop ce0
DEVICE ce0 STOPPED
$ ncs_cli -C -u admin
```

```
admin connected from 127.0.0.1 using console on ncs
ncs# config
```

By default the commit queue is turned off. You can configure NSO to run a transaction, device or device group through the commit queue in a number of different ways, either by providing a flag to the commit command as:

```
ncs(config)# commit commit-queue
Possible completions:
  async    Commit through commit queue and return immediately
  bypass    Bypass commit-queue when queue is enabled by default
  sync     Commit through commit queue and wait for reply
ncs(config)# commit commit-queue async
```

or by configuring NSO to always run all transactions through the commit queue as in:

```
ncs(config)# devices global-settings commit-queue enabled-by-default
[false,true] (false): true
ncs(config)# commit
```

or by configuring a number of devices to run through the commit queue as default:

```
ncs(config)# devices device ce0..2 commit-queue enabled-by-default
[false,true] (false): true
ncs(config)# commit
```

When enabling the commit queue as default on a per device/device group basis, a NSO transaction will compute the configuration change for each participating device, put the devices enabled for the commit queue in the outbound queue and then proceed with the normal transaction behaviour for those devices not commit queue enabled. The transaction will still be successfully committed even if some of the devices added to the outbound queue will fail. If the transaction fails in the validation phase the entire transaction will be aborted, including the configuration change for those devices added to commit queue. If the transaction fails after the validation phase, the configuration change for the devices in the commit queue will still be delivered.

Do some change and commit through the commit queue:

#### Example 22. Commit through Commit Queue

```
ncs(config)# devices device ce0..2 config ios:snmp-server \
    trap-source GigabitEthernet 0/1
ncs(config-config)# commit
commit-queue-id 9494446997
Commit complete.
ncs(config-config)# *** ALARM connection-failure: Failed to
connect to device ce0: connection refused: Connection refused
```

## Commit Queue Scheduling

In [Example 22, “Commit through Commit Queue”](#) the commit affected three devices, ce0, ce1 and ce2. If you immediately would have launched yet another transaction, as in:

```
ncs(config)# devices device ce0 config ios:interface GigabitEthernet 0/25
ncs(config-if)# commit
commit-queue-id 9494530158
Commit complete.
ncs(config-if)# *** ALARM commit-through-queue-blocked:
```

Commit Queue item 9494530158 is blocked because qitem 9494446997 cannot connect to ce0

the second one, manipulating an interface of ce2, that transaction would have been queued instead of immediately launched. The idea here is to queue entire transactions that touch any device which has anything queued ahead in the queue.

Each transaction committed through the queues becomes a *queue item*. A queue item has an id number. A bigger number means that its scheduled later. Each queue item waits for something to happen. A queue item is in either of three states.

- 1 *waiting* - The queue item is waiting for other queue items to finish. This is because the *waiting* queue item has participating devices that are part of other queue items, ahead in the queue. It is waiting for a set of devices, to not occur ahead of itself in the queue.
- 2 *executing* - The queue item is currently being processed. Multiple queue item can run currently as long as they don't share any managed devices. Transient errors might be present. These errors occur when NSO fails to communicate with some of the devices. The errors are shown in the leaf-list *transient-errors*. Retries will take place at intervals specified in `/ncs:devices/global-settings/commit-queue/retry-timeout`. Examples of transient errors are connection failures and that the changes are rejected due to the device being locked. Transient errors are potentially bad, since the queue might grow if new items are added, waiting for the same device.
- 3 *locked* - This queue item is locked and will not be processed until it has been unlocked, see the action `/ncs:devices/commit-queue/queue-item/unlock`. A locked queue item will block all subsequent queue items which are using any device in the locked queue item.

## Viewing and Manipulating the Commit Queue

You can view the queue in the CLI. There are three different view modes, *summary*, *normal* and *detailed*. Depending on the output, both the *summary* and the *normal* look good:

### Example 23. Viewing queue items

```
ncs# show devices commit-queue | notab
devices commit-queue queue-item 9494446997
  age          144
  status       executing
  kilo-bytes-size 1
  devices      [ ce0 ce1 ce2 ]
  transient-errors [ ce0 ]
  is-atomic    true
devices commit-queue queue-item 9494530158
  age          61
  status       blocked
  kilo-bytes-size 1
  devices      [ ce0 ]
  waiting-for  [ ce0 ]
  is-atomic    true
```

The *age* field indicated how many seconds a queue item has been in the queue.

You can also view the queue items in *detailed* mode:

```
ncs# show devices commit-queue queue-item 9494530158 details | notab
devices commit-queue queue-item 9494530158
  age          278
  status       blocked
  kilo-bytes-size 1
  devices      [ ce0 ]
  waiting-for  [ ce0 ]
```

```

is-atomic      true
modification ce0
data          <interface xmlns="urn:ios">
               <GigabitEthernet>
                 <name>0/25</name>
               </GigabitEthernet>
             </interface>

local-user admin

```

The queue items are stored persistently, thus if NSO is stopped and restarted, the queue remains the same. Similarly, if NSO is run in HA (High Availability) mode, the queue items are replicated, ensuring the queue is processed even in the case of failover.

**Note**

The commit queue is disabled when HA is enabled and when HA mode is `NONE`. See the section called “Mode of operation” in *NSO 5.7 Administration Guide* for more details.

A number of useful actions are available to manipulate the queue:

- 1 **devices commit-queue add-lock device [ ... ]** This adds a fictive queue-item to the commit-queue. Any queue item, affecting the same devices, which is entering the commit-queue will have to wait for this lock item to be unlocked or deleted. If no devices are specified, all devices in NSO are locked.
- 2 **devices commit-queue clear** This action clears the entire queue. All devices present in the commit queue will after this action has executed be out of sync. The `clear` action is a rather blunt tool and is not recommended to be used in any normal use case.
- 3 **devices commit-queue prune device [ ... ]** This action prunes all specified devices from all queue items in the commit queue. The affected devices will, after this action has been executed, be out of sync. Devices which are currently being committed to will not be pruned, unless the `force` option is used. Atomic queue items will not be affected, unless all devices in it are pruned.  
The `force` option will brutally kill an ongoing commit. This could leave the device in a bad state. It is not recommended in any normal use case.
- 4 **devices commit-queue set-atomic-behaviour atomic [ true,false ]** This actions sets the atomic behaviour of all queue items. If these are set to false, the devices contained in these queue items can start executing if the same devices in other non-atomic queue items ahead of it in the queue are completed. If set to true, the atomic integrity of these queue items are preserved.
- 5 **devices commit-queue wait-until-empty** This action waits until the commit queue is empty. Default is to wait `infinity`. A `timeout` can be specified to wait for a number of seconds. The result is `empty` if the queue is empty or `timeout` if there are still items in the queue to become processed.
- 6 **devices commit-queue queue-item [ id ] lock** This action puts a lock on an existing queue item. A locked queue item will not start executing until it has been unlocked.
- 7 **devices commit-queue queue-item [ id ] unlock** This action unlocks a locked queue item. Unlocking a queue item which is not locked is silently ignored.
- 8 **devices commit-queue queue-item [ id ] delete** This action deletes a queue item from the queue. If other queue items are waiting for this (deleted) item, they will all automatically start to run. The devices of the deleted queue item will, after the action has executed, be out of sync if they haven't start executing. Any error-option set for the queue item will also be disregarded.  
The `force` option will brutally kill an ongoing commit. This could leave the device in a bad state. It is not recommended in any normal use case.
- 9 **devices commit-queue queue-item [ id ] prune device [ ... ]** This action prunes the specified devices from the queue item. Devices which are currently being committed to will not be pruned, unless the `force` option is used. Atomic queue items will not be affected, unless all devices in it are pruned.

The `force` option will brutally kill an ongoing commit. This could leave the device in a bad state. It is not recommended in any normal use case.

- 10 **devices commit-queue queue-item [ id ] set-atomic-behaviour atomic [ true,false ]** This action sets the atomic behaviour of this queue item. If this is set to `false`, the devices contained in this queue item can start executing if the same devices in other non-atomic queue items ahead of it in the queue are completed. If set to `true`, the atomic integrity of the queue item is preserved.
- 11 **devices commit-queue queue-item [ id ] wait-until-completed** This action waits until the queue item is completed. Default is to wait `infinity`. A `timeout` can be specified to wait for a number of seconds. The result is `completed` if the queue item is completed or `timeout` if the timer expired before the queue item was completed.
- 12 **devices commit-queue queue-item [ id ] retry** This action retries devices with transient errors instead of waiting for the automatic retry attempt. The `device` option will let you specify the devices to retry.

A typical use scenario is where one or more devices are not operational. In [Example 23, “Viewing queue items”](#), there are two queue items, waiting for device `ce0` to come alive. `ce0` is listed as a transient error, and this is blocking the entire queue. Actually, whenever a queue item is blocked because another item ahead of it cannot connect to a specific managed device, an alarm is generated:

```
ncs# show alarms alarm-list alarm ce0 commit-through-queue-blocked
alarms alarm-list alarm ce0 commit-through-queue-blocked /devices/device[name='ce0'] 94945301
is-cleared false
last-status-change 2015-02-09T16:48:17.915+00:00
last-perceived-severity warning
last-alarm-text "Commit queue item 9494530158 is blocked because item 9494446997 can
status-change 2015-02-09T16:48:17.915+00:00
received-time 2015-02-09T16:48:17.915+00:00
perceived-severity warning
alarm-text "Commit queue item 9494530158 is blocked because item 9494446997 cannot
```

- 1 Block other affecting device `ce0` from entering the commit-queue:

```
ncs(config)# devices commit-queue add-lock device [ ce0 ] block-others
commit-queue-id 9577950918
ncs# show devices commit-queue | notab
devices commit-queue queue-item 9494446997
age 1444
status executing
kilo-bytes-size 1
devices [ ce0 ce1 ce2 ]
transient-errors [ ce0 ]
is-atomic true
devices commit-queue queue-item 9494530158
age 1361
status blocked
kilo-bytes-size 1
devices [ ce0 ]
waiting-for [ ce0 ]
is-atomic true
devices commit-queue queue-item 9577950918
age 55
status locked
kilo-bytes-size 1
devices [ ce0 ]
waiting-for [ ce0 ]
is-atomic true
```

Now queue item 9577950918 is blocking other items using `ce0` from entering the queue.

- 2 Prune the usage of device `ce0` from all queue items in the commit-queue:

```

ncs(config)# devices commit-queue set-atomic-behaviour atomic false
ncs(config)# devices commit-queue prune device [ ce0 ]
num-affected-queue-items 2
num-deleted-queue-items 1
ncs(config)# show devices commit-queue | notab
devices commit-queue queue-item 9577950918
  age          102
  status       locked
  kilo-bytes-size 1
  devices      [ ce0 ]
  is-atomic    true

```

The lock will be in the queue until it has been deleted or unlocked. Queue items affecting other devices are still allowed entering the queue.

- 3 Fix the problem with device ce0, remove the lock item and sync from the device:

```

ncs(config)# devices commit-queue queue-item 9577950918 delete
ncs(config)# devices device ce0 sync-from
result true

```

## Commit Queue in a Cluster Environment

In an LSA cluster each remote NSO has its own commit queue. When committing through the commit queue on the upper node NSO will automatically create queue items on the lower nodes where the devices in the transaction resides. The progress of the lower node queue items are monitored through a queue item on the upper node. The remote NSO is treated itself as a device in the queue item and the remote queue items and devices are opaque to user of the upper node.

### Example 24. Commit queue in an LSA cluster

```

ncs(config)# show configuration
vpn l3vpn volvo
  as-number 65101
  endpoint branch-office1
    ce-device ce1
    ce-interface GigabitEthernet0/11
    ip-network 10.7.7.0/24
    bandwidth 6000000
  !
  endpoint main-office
    ce-device ce0
    ce-interface GigabitEthernet0/11
    ip-network 10.10.1.0/24
    bandwidth 12000000
  !
!

ncs(config-if)# commit commit-queue async
commit-queue-id 9494530158

ncs# show devices commit-queue | notab
devices commit-queue queue-item 9494446997
  age          60
  status       executing
  kilo-bytes-size 1
  devices      [ lsa-nso2 lsa-nso3 ]
  is-atomic    true

ncs# show devices commit-queue | notab
devices commit-queue queue-item 9494446997

```



```

age                66
status             executing
kilo-bytes-size    1
devices            [ lsa-nso2 ]
completed          [ lsa-nso3 ]
is-atomic          true

ncs# show devices commit-queue
% No entries found.

```

**Warning**

Generally it is not recommended to interfere with the queue items of the lower nodes that have been created by an upper NSO. This can cause the upper queue item to not synchronize with the lower ones correctly.

## Configuring Commit Queue in a Cluster Environment

To be able to track the commit queue on the lower cluster nodes, NSO uses the built-in stream `ncs-events` that generates northbound notifications for internal events. This stream is required if running the commit queue in a clustered scenario. It is enabled in `ncs.conf`:

### Example 25. Enabling the `ncs-events` stream

```

<stream>
  <name>ncs-events</name>
  <description>NCS event according to tailf-ncs-devices.yang</description>
  <replay-support>true</replay-support>
  <builtin-replay-store>
    <enabled>true</enabled>
    <dir>./state</dir>
    <max-size>S10M</max-size>
    <max-files>50</max-files>
  </builtin-replay-store>
</stream>

```

In addition the commit queue needs to be enabled in the cluster configuration.

```

ncs(config)# cluster commit-queue enabled
ncs(config)# commit

```

For more detailed information on how to set up clustering, see NSO Layered Service Architecture.

## Error Recovery with Commit Queue

The goal of the commit queue is to increase the transactional throughput of NSO while keeping an eventual consistency view of the database. This means no matter if changes committed through the commit queue originate as pure device changes or as the effect of service manipulations the effects on the network should eventually be the same as if performed without a commit queue no matter if they succeed or not. This should be applicable to a single NSO node as well as NSO nodes in an LSA cluster.

Depending on the selected `error-option` NSO will store the reverse of the original transaction to be able to undo the transaction changes and get back to the previous state. This data is stored in the `/ncs:devices/commit-queue/completed` tree from where it can be viewed and invoked with the `rollback` action. When invoked the data will be removed.

### Example 26. Viewing completed queue items

```

ncs# show devices commit-queue completed | notab

```

```

devices commit-queue completed queue-item 9494446997
  when      2015-02-09T16:48:17.915+00:00
  succeeded false
  devices   [ ce0 ce1 ce2 ]
  failed ce0
    reason "Failed to connect to device ce0: closed"
devices commit-queue completed queue-item 9494530158
  when      2015-02-09T16:48:17.915+00:00
  succeeded false
  devices   [ ce0 ]
  failed ce0
    reason "Deleted by user"

```

The error option can be configured under `/ncs:devices/global-settings/commit-queue/error-option`. Possible values are: *continue-on-error*, *rollback-on-error* and *stop-on-error*. The *continue-on-error* value means that the commit queue will continue on errors. No rollback data will be created. The *rollback-on-error* value means that the commit queue item will roll back on errors. The commit queue will place a lock on the failed queue item, thus blocking other queue items with overlapping devices to be executed. The **rollback** action will then automatically be invoked when the queue item has finished its execution. The lock will be removed as part of the rollback. The *stop-on-error* means that the commit queue will place a lock on the failed queue item, thus blocking other queue items with overlapping devices to be executed. The lock must then either manually be released when the error is fixed or the **rollback** action under `/devices/commit-queue/completed` be invoked. The **rollback** action is as:

#### Example 27. Execute rollback action

```
ncs(config)# devices commit-queue completed queue-item 9494446997 rollback
```

The error option can also be given as a commit parameter.



#### Note

To guarantee service integrity NSO checks for overlapping service or device modifications against the items in the commit queue and returns an error if such exists. If a service instance does a shared set on the same data as a service instance in the queue actually changed, the reference count will be increased but no actual change is pushed to the device(s). This will give a false positive that the change is actually deployed in the network. The *rollback-on-error* and *stop-on-error* error options will automatically create a queue lock on the involved services and devices to prevent such a case.

In a clustered environment, different parts of the resulting configuration change set will end up on different lower nodes. This means on some nodes the queue item could succeed and on others it could not.


The error option in a cluster environment will originate on the upper node. The reverse of the original transaction will be committed on this node and propagated through the cluster down to the lower nodes. The net effect of this is the state of the network will be the same as before the original change.




#### Note

As the error option in a cluster environment will originate on the upper node, any configuration on the lower nodes will be meaningless.

When NSO is recovering from a failed commit, the rollback data of the failed queue items in the cluster, is applied and committed through the commit queue. In the rollback the no-networking flag will be set on the commits towards the failed lower nodes or devices to get CDB consistent with the network. Towards the successful nodes or devices the commit is done as before. This is what the **rollback** action in `/ncs:devices/commit-queue/completed/queue-item` does.

**Example 28. Error recovery in a single node deployment****Figure 28.**


- 1 TR1; service *s1* creates *ce0:a* and *ce1:b*. The nodes *a* and *b* are created in CDB. In the changes of the queue item, CQ1, *a* and *b* are created.
- 2 TR2; service *s2* creates *ce1:c* and *ce2:d*. The nodes *c* and *d* are created in CDB. In the changes of the queue item, CQ2, *c* and *d* are created.
- 3 The queue item from TR1, CQ1, starts to execute. The node *a* cannot be created on the device. The node *b* was created on the device but that change is reverted as *a* failed to be created.

**Figure 29.**

- 4 The reverse of TR1, rollback of CQ1, TR3, is committed.
- 5 TR3; service *s1* is applied with the old parameters. Thus the effect of TR1 is reverted. Nothing needs to be pushed towards the network, so no queue item is created.
- 6 TR2; as the queue item from TR2, CQ2, is not the same service instance and has no overlapping data on the *ce1* device, this queue item executes as normal.


### Example 31. Error recovery in an LSA cluster

Figure 31.



- 1 NSO1:TR1; service *s1* dispatches the service to NSO2 and NSO3 through the queue item NSO1:CQ1. In the changes of NSO1:CQ1, NSO2:*s1* and NSO3:*s1* are created.
- 2 NSO1:TR2; service *s2* dispatches the service to NSO2 through the queue item NSO1:CQ2. In the changes of NSO1:CQ2, NSO2:*s2* is created.
- 3 The queue item from NSO2:TR1, NSO2:CQ1, starts to execute. The node *a* cannot be created on the device. The node *b* was created on the device but that change is reverted as *a* failed to be created.
- 4 The queue item from NSO3:TR1, NSO3:CQ1, starts to execute. The changes in the queue item is committed successfully to the network.

Figure 32.



- 5 The reverse of TR1, rollback of CQ1, TR3, is committed on all nodes part of TR1 that failed.
- 6 NSO2:TR3; service *s1* is applied with the old parameters. Thus the effect of NSO2:TR1 is reverted. Nothing needs to be pushed towards the network, so no queue item is created.
- 7 NSO1:TR3; service *s1* is applied with the old parameters. Thus the effect of NSO1:TR1 is reverted. A queue item is created to push the transaction changes to the lower nodes that didn't fail.
- 8 NSO3:TR3; service *s1* is applied with the old parameters. Thus the effect of NSO3:TR1 is reverted. Since the changes in the queue item NSO3:CQ1 was successfully committed to the network a new queue item NSO3:CQ3 is created to revert those changes.

If for some reason the rollback transaction would fail there are, depending on the failure, different techniques to reconcile the services involved:

- Make sure the commit queue is blocked to not interfere with the error recovery procedure. Do a sync-from on the non-completed device(s) and then re-deploy the failed service(s) with the `reconcile` option to reconcile original data, i.e., take control of that data. This option acknowledges other services controlling the same data. The reference count will indicate how many services control the data. Release any queue lock that was created.
- Make sure the commit queue is blocked to not interfere with the error recovery procedure. Use `un-deploy` with the `no-networking` option on the service and then do sync-from on the non-completed device(s). Make sure the error is fixed and then re-deploy the failed service(s) with the `reconcile` option. Release any queue lock that was created.

## Commit Queue Tuning

As the goal of the commit queue is to increase the transactional throughput of NSO it means that we need to calculate the configuration change towards the device(s) outside of the transaction lock. To calculate

a configuration change NSO needs a pre-commit running and a running view of the database. The key enabler to support this in the commit queue is to allow different views of the database to live beyond the commit. In NSO this is implemented by keeping a snapshot database of the configuration tree for devices and store configuration changes towards this snapshot database on a per device basis. The snapshot database is updated when a device in the queue has been processed. This snapshot database is stored on disk for persistence (the `S.cdb` file in the `ncs-cdb` directory).

The snapshot database could be populated in two ways. This is controlled by the `/ncs-config/cdb/snapshot/pre-populate` setting in the `ncs.conf` file. The parameter controls if the snapshot database should be pre-populated during upgrade or not. Switching this on or off implies different trade-offs.

If set to `false`, NSO is optimized for the default transaction behaviour. The snapshot database is populated in a lazy manner (when a device is committed through the commit queue for the first time after an upgrade). The drawback is that this commit will suffer performance wise, which is especially true for devices with large configurations. Subsequent commits on the same device will not have the same penalty.

If `true`, NSO is optimized for systems using the commit queue extensively. This will lead to better performance when committing using the commit queue with no additional penalty for the first time commits. The drawbacks are that the time to do upgrades will increase and also an almost twofold increase of NSO memory consumption.

## NETCONF Call Home

The NSO device manager has built-in support for the NETCONF Call Home client protocol operations over SSH as defined in [RFC 8071](#).

With NETCONF SSH Call Home, the NETCONF client listens for TCP connection requests from NETCONF servers. The SSH client protocol is started when the connection is accepted. The SSH client validates the server's presented host key with credentials stored in NSO. If no matching host key is found the TCP connection is closed immediately. Otherwise the SSH connection is established, and NSO is enabled to communicate with the device. The SSH connection is kept open until the device itself terminates the connection, a NSO user disconnects the device, or the idle connection timeout is triggered (configurable in the `ncs.conf` file).

NSO will generate an asynchronous notification event whenever there is a connection request. An application can subscribe to these events and, for example, add an unknown device to the device tree with the information provided, or invoke actions on the device if it is known.

If an SSH connection is established, any outstanding configuration in the commit queue for the device will be pushed. Any notification stream for the device will also be reconnected.

NETCONF Call Home is enabled and configured under `/ncs-config/netconf-call-home` in the `ncs.conf` file. By default NETCONF Call Home is disabled.

A device can be connected through the NETCONF Call Home client only if `/devices/device/state/admin-state` is set to `call-home`. This state prevents any southbound communication to the device unless the connection has already been established through the NETCONF Call Home client protocol.

## Notifications

The NSO device manager has built-in support for device notifications. Notifications are a means for the managed devices to send structured data asynchronously to the manager. NSO has native support for

NETCONF event notifications (see RFC 5277) but could also receive notifications from other protocols implemented by the Network Element Drivers.

Notifications can be utilized in various different use case scenarios - It can be used to populate alarms in the Alarm manager, collect certain types of errors over time, build a network wide audit log, react on configuration changes etc.

The basic mode of operation is the manager subscribes to one or more *named* notification channels which are announced by the managed device. The manager keeps an open SSH channel towards the managed device, and then, the managed device may asynchronously send structured XML data on the ssh channel.

The notification support in NSO is usable as is without any further programming. However, NSO cannot understand any semantics contained inside the received XML messages, thus for example a notification with a content of "Clear Alarm 456" cannot be processed by NSO without any additional programming.

When you add programs to interpret and act upon notifications, make sure that resulting operations are idempotent. This means that they should be able to be called any number of times while guaranteeing that side effects only occur once. The reason for this is that, for example, replaying notifications can sometimes mean that your program will handle the same notifications multiple times.

In the `tailf-ncs.yang` data model you find a YANG data model which can be used to:

- Setup subscriptions. A subscription is configuration data from the point of view of NSO, thus if NSO is restarted, all configured subscriptions are automatically resumed.
- Inspect which named streams a managed device publishes.
- View all received notifications.

## An Example Session

In this section we will use the `examples.ncs/web-server-farm/basic` example.

Let's dive into an example session with the NSO CLI. In the NSO example collection, the webserver publish two NETCONF notification structures, indicating what they intend to send to any interested listeners. They all have the YANG module:

### Example 34. notif.yang

```
module notif {
  namespace "http://router.com/notif";
  prefix notif;

  import ietf-inet-types {
    prefix inet;
  }

  notification startUp {
    leaf node-id {
      type string;
    }
  }

  notification linkUp {
    leaf ifName {
      type string;
      mandatory true;
    }
    leaf extraId {
      type string;
    }
  }
}
```

```

    }
    list linkProperty {
      max-elements 64;
      leaf newlyAdded {
        type empty;
      }
      leaf flags {
        type uint32;
        default 0;
      }
      list extensions {
        max-elements 64;
        leaf name {
          type uint32;
          mandatory true;
        }
        leaf value {
          type uint32;
          mandatory true;
        }
      }
    }
  }

  list address {
    key ip;
    leaf ip {
      type inet:ipv4-address;
    }
    leaf mask {
      type inet:ipv4-address;
    }
  }

  leaf-list iface-flags {
    type enumeration {
      enum UP;
      enum DOWN;
      enum BROADCAST;
      enum RUNNING;
      enum MULTICAST;
      enum LOOPBACK;
    }
  }
}

notification linkDown {
  leaf ifName {
    type string;
    mandatory true;
  }
}
}

```

Follow the instructions in the README file if you want to run the example: build the example, start netsim, start ncs.

```

admin@ncs# show devices device pe2 notifications stream | notab
notifications stream NETCONF
description "default NETCONF event stream"
replay-support false
notifications stream tailf-audit

```



```

description      "Tailf Commit Audit events"
replay-support   true
notifications stream interface
description      "Example notifications"
replay-support    true
replay-log-creation-time 2014-10-14T11:21:12+00:00
replay-log-aged-time   2014-10-14T11:53:19.649207+00:00

```

The above shows how we can inspect - as status data - which named streams the managed device publishes. Each stream also has some associated data. The data model for that looks like:

### Example 35. tailf-ncs.yang notification streams

```

module tailf-ncs {
  namespace "http://tail-f.com/ns/ncs";
  ...
  container devices {
    list device {
      ....
      container notifications {
        ....

        list stream {
          description "A list of the notification streams
                     provided by the device. NCS reads this list in
                     real time";

          config false;
          key name;
          leaf name {
            description "The name of the the stream";
            type string;
          }
          leaf description {
            description "A textual description of the stream";
            type string;
          }
          leaf replay-support {
            description "An indication of whether or not event replay
                       is available on this stream.";
            type boolean;
          }
          leaf replay-log-creation-time {
            description "The timestamp of the creation of the log
                       used to support the replay function on
                       this stream.
                       Note that this might be earlier than
                       the earliest available
                       notification in the log. This object
                       is updated if the log resets
                       for some reason.";

            type yang:date-and-time;
          }
          leaf replay-log-aged-time {
            description "The timestamp of the last notification
                       aged out of the log";
            type yang:date-and-time;
          }
        }
      }
    }
  }
}

```

Let's setup a subscription for the stream called *interface*. The subscriptions are NSO configuration data, thus to create a subscription we need to enter configuration mode:

**Example 36. Configuring a Subscription**

```
admin@ncs(config)# devices device www0..2 notifications \
    subscription mysub stream interface
admin@ncs(config-subscription-mysub)# commit
```

The above, created subscriptions for the *interface* stream on all web servers, i.e managed devices, www0, www1 and www2. Each subscription must have an associated stream to it, this is however not the key for an NSO notification, the key is a free form text string. This is since we can have multiple subscriptions to the same stream. More on this later when we describe the filter that can be associated to a subscription. Once the notifications start to arrive, they are read by NSO and stored in stable storage as CDB operational data. they are stored under each managed device - and we can view them as:

**Example 37. Viewing the Received Notifications**

```
admin@ncs# show devices device notifications | notab
devices device www0
notifications subscription mysub
  local-user admin
  status running
notifications stream NETCONF
  description "default NETCONF event stream"
  replay-support false
notifications stream tailf-audit
  description "Tailf Commit Audit events"
  replay-support true
notifications stream interface
  description "Example notifications"
  replay-support true
  replay-log-creation-time 2014-10-14T11:21:12+00:00
  replay-log-aged-time 2014-10-14T11:56:45.755964+00:00
notifications notification-name startUp
  uri http://router.com/notif
notifications notification-name linkUp
  uri http://router.com/notif
notifications notification-name linkDown
  uri http://router.com/notif
notifications received-notifications notification 2014-10-14T11:54:43.692371+00:00 0
  user admin
  subscription mysub
  stream interface
  received-time 2014-10-14T11:54:43.695191+00:00
  data linkUp ifName eth2
  data linkUp linkProperty
    newlyAdded
    flags 42
    extensions
      name 1
      value 3
    extensions
      name 2
      value 4668
  data linkUp address 192.168.128.55
  mask 255.255.255.0
```

Each received notification has some associated meta data, such as the time the event was received by NSO, which subscription and which stream is associated to the the notification and also which user created the subscription.

It is fairly instructive to inspect the XML that goes on the wire when we create a subscription and then also receive the first notification. We can do:

```

ncs(config)# devices global-settings trace pretty trace-dir ./logs
ncs(config)# commit

ncs(config)# devices disconnect

ncs(config)# devices device pe2 notifications \
    subscription foo stream interface
ncs(config-subscription-foo)# top
ncs(config)# exit

ncs# file show ./logs/netconf-pe2.trace
<<<<in 14-Oct-2014::13:59:52.295 device=pe2 session-id=14
<notification xmlns="urn:ietf:params:xml:ns:netconf:notification:1.0">
  <eventTime>2014-10-14T11:58:51.816077+00:00</eventTime>
  <linkUp xmlns="http://router.com/notif">
    <ifName>eth2</ifName>
    <linkProperty>
      <newlyAdded/>
      <flags>42</flags>
      <extensions>
        <name>1</name>
        <value>3</value>
      </extensions>
      <extensions>
        <name>2</name>
        <value>4668</value>
      </extensions>
    </linkProperty>
    <address>
      <ip>192.168.128.55</ip>
      <mask>255.255.255.0</mask>
    </address>
  </linkUp>
</notification>
.....

```

Thus, once the subscription has been configured, NSO continuously receives, and stored in CDB oper persistent storage, the notifications sent from the managed device. The notifications are stored in a circular buffer, to set the size of the buffer, we can do:

```

ncs(config)# devices device www0 notifications \
    received-notifications max-size 100
admin@ncs(config-device-www0)# commit

```

The default value is 200. Once the size of the circular buffer is exceeded, the oldest notification is removed.

## Subscription Status

A running subscription can be in either of three states. The YANG model has:

```

module tailf-ncs {
  namespace "http://tail-f.com/ns/ncs";
  ...
  container devices {
    list device {
      ....
      container notifications {
        ....
        list subscription {
          ....
          leaf status {
            description "Is this subscription currently running";

```

```

config false;
type enumeration {
  enum running {
    description "The subscription is established and we should
                be receiving notifications";
  }
  enum connecting {
    description "Attempting to establish the subscription";
  }
  enum failed {
    description
    "The subscription has failed, unless the failure is
    in the connection establishing, i.e connect() failed
    there will be no automatic re-connect";
  }
}
}

```

If a subscription is in the *failed* state, an optional *failure-reason* field indicates the reason for the failure. If a subscription fails due to, not being able to connect to the managed device or if the managed device closed its end of the SSH socket, NSO will attempt to automatically reconnect. The re-connect attempt interval is configurable.

```
ncs# show devices device notifications subscription
```

		LOCAL		FAILURE	ERROR
NAME	NAME	USER	STATUS	REASON	INFO
www0	foo	admin	running	-	-
	mysub	admin	running	-	-
www1	mysub	admin	running	-	-
www2	mysub	admin	running	-	-

## SNMP Notifications

SNMP Notifications (v1, v2c, v3) can be received by NSO and acted upon. The SNMP receiver is a stand-alone process and by default all notifications are ignored. IP addresses must be opted in and a handler must be defined to take actions on certain notifications. This can be used to for example listen to configuration change notifications and trigger a log action or a resync for example

This actions are programmed in Java, see the developing guide how to do this.

## Inactive configuration

NSO is able to configure inactive parameters on the devices that support inactive configuration. Currently these devices include Juniper devices and devices that announce 'http://tail-f.com/ns/netconf/inactive/1.0' capability. NSO itself implements 'http://tail-f.com/ns/netconf/inactive/1.0' capability which is formally defined in tailf-netconf-inactive YANG module.

To recap, a node that is marked as inactive exists in the datastore, but is not used by the server. The nodes announced as inactive by the device will also be inactive in the device's configuration in NSO, and activating/deactivating a node in NSO will push the corresponding change to the device. This also means that in order for NSO to be able to manage inactive configuration both /ncs-config/enable-inactive and /ncs-config/netconf-north-bound/capabilities/inactive need to be enabled in ncs.conf.

If the inactive feature is disabled in ncs.conf, NSO will still be able to manage devices that have inactive configuration in their datastore, but the inactive attribute will be ignored, so the data will appear as active in NSO and it would not be possible for NSO to activate/deactivate such nodes in the device.



## CHAPTER

# 4

## SSH Key Management

---

- [General, page 101](#)
- [NSO as SSH Server, page 101](#)
- [NSO as SSH Client, page 102](#)

### General

The SSH protocol uses public key technology for two distinct purposes:

Server authentication	This use is a mandatory part of the protocol. It allows an SSH client to authenticate the server, i.e. verify that it is really talking to the intended server and not some man-in-the-middle intruder. This requires that the client has a priori knowledge of the server's public keys, and the server proves its possession of one of the corresponding private keys by using it to sign some data. These keys are normally called "host keys", and the authentication procedure is typically referred to as "host key verification" or "host key checking".
Client authentication	This use is one of several possible client authentication methods, i.e. it is an alternative to the commonly used password authentication. The server is configured with one or more public keys which are authorized for authentication of a user. The client proves possession of one of the corresponding private keys by using it to sign some data - i.e. the exact reverse of the server authentication provided by host keys. The method is called "publickey" authentication in SSH terminology.

These two usages are fundamentally independent, i.e. host key verification is done regardless of whether the client authentication is via publickey, password, or some other method. However host key verification is of particular importance when client authentication is done via password, since failure to detect a man-in-the-middle attack in this case will result in the cleartext password being divulged to the attacker.

### NSO as SSH Server

NSO can act as SSH server for northbound connections to the CLI or the NETCONF agent, and for connections from other nodes in an NSO cluster - cluster connections use NETCONF, and the server side setup used is the same as for northbound connections to the NETCONF agent. It is possible to use either the NSO built-in SSH server, or an external server such as OpenSSH, for all of these cases. When using an external SSH server, host keys for server authentication and authorized keys for client/user authentication

need to be set up per the documentation for that server, and there is no NSO-specific key management in this case.

When the NSO built-in SSH server is used, the setup is very similar to the one OpenSSH uses:

## Host Keys

The private host key(s) must be placed in the directory specified by `/ncs-config/aaa/ssh-server-key-dir` in `ncs.conf`, and named either `ssh_host_dsa_key` (for a DSA key) or `ssh_host_rsa_key` (for a RSA key). The key(s) must be in PEM format (e.g. as generated by the OpenSSH **ssh-keygen** command), and must not be encrypted - protection can be achieved by file system permissions (not enforced by NSO). The corresponding public key(s) is/are typically stored in the same directory with a `.pub` extension to the file name, but they are not used by NSO. The NSO installation creates a DSA private/public key pair in the directory specified by the default `ncs.conf`.

## Publickey Authentication

The public keys that are authorized for authentication of a given user must be placed in the user's SSH directory. Please refer to the section called “Public Key Login” in *NSO 5.7 Administration Guide* for the details of how NSO searches for the keys to use.

## NSO as SSH Client

NSO can act as SSH client for connections to managed devices that use SSH (this is always the case for devices accessed via NETCONF, typically also for devices accessed via CLI), and for connections to other nodes in an NSO cluster. In all cases a built-in SSH client is used. The `$NCS_DIR/examples.ncs/getting-started/using-ncs/8-ssh-keys` example in the NSO example collection has a detailed walk-through of the NSO functionality that is described in this section.

## Host Key Verification

### Verification level

The level of host key verification can be set globally via `/ssh/host-key-verification`. The possible values are:

<code>reject-unknown</code>	The host key provided by the device or cluster node must be known by NSO for the connection to succeed.
<code>reject-mismatch</code>	The host key provided by the device or cluster node may be unknown, but it must not be different from the "known" key for the same key algorithm, for the connection to succeed.
<code>none</code>	No host key verification is done - the connection will never fail due to the host key provided by the device or cluster node.

The default is `reject-unknown`, and it is not recommended to use a different value, although it can be useful or needed in certain circumstances. E.g. `none` may be useful in a development scenario, and temporary use of `reject-mismatch` may be motivated until host keys have been configured for a set of existing managed devices.

### Example 38. Allowing SSH Connections With Unknown Host Keys

```
admin@ncs(config)# ssh host-key-verification reject-mismatch
admin@ncs(config)# commit
Commit complete.
```

## Connection to a Managed Device

The public host keys for a device that is accessed via SSH are stored in the `/devices/device/ssh/host-key` list. There can be several keys in this list, one each for the `ssh-ed25519` (ED25519 key), `ssh-dss` (DSA key) and `ssh-rsa` (RSA key) key algorithms. In case a device has entries in its `live-status-protocol` list that use SSH, the host keys for those can be stored in the `/devices/device/live-status-protocol/ssh/host-key` list, in the same way as the device keys - however if `/devices/device/live-status-protocol/ssh` does not exist, the keys from `/devices/device/ssh/host-key` are used for that protocol. The keys can be configured e.g. via input directly in the CLI, but in most cases it will be preferable to use the actions described below to retrieve keys from the devices. These actions will also retrieve any `live-status-protocol` keys for a device.

The level of host key verification can also be set per device, via `/devices/device/ssh/host-key-verification`. The default is to use the global value (or default) for `/ssh/host-key-verification`, but any explicitly set value will override the global value. The possible values are the same as for `/ssh/host-key-verification`.

There are several actions that can be used to retrieve the host keys from a device and store them in the NSO configuration:

<code>/devices/fetch-ssh-host-keys</code>	Retrieve the host keys for all devices. Successfully retrieved keys are committed to the configuration.
<code>/devices/device-group/fetch-ssh-host-keys</code>	Retrieve the host keys for all devices in a device group. Successfully retrieved keys are committed to the configuration.
<code>/devices/device/ssh/fetch-host-keys</code>	Retrieve the host keys for one or more devices. In the CLI, range expressions can be used for the device name, e.g. using <code>'*'</code> will retrieve keys for all devices etc. The action will commit the retrieved keys if possible, i.e. if the device entry is already committed, otherwise (i.e. if the action is invoked from "configure mode" when the device entry has been created but not committed), the keys will be written to the current transaction, but not committed.

The fingerprints of the retrieved keys will be reported as part of the result from these actions, but it is also possible to ask for the fingerprints of already retrieved keys by invoking the `/devices/device/ssh/host-key/show-fingerprint` action (`/devices/device/live-status-protocol/ssh/host-key/show-fingerprint` for live-status-protocols that use SSH).

### Example 39. Retrieving SSH Host Keys for All Configured Devices

```
admin@ncs# devices fetch-ssh-host-keys
fetch-result {
  device c0
  result unchanged
  fingerprint {
    algorithm ssh-dss
    value 03:64:fc:b7:87:bd:34:5e:3b:6e:d8:71:4d:3f:46:76
  }
}
fetch-result {
  device h0
  result unchanged
  fingerprint {
    algorithm ssh-dss
    value 03:64:fc:b7:87:bd:34:5e:3b:6e:d8:71:4d:3f:46:76
  }
}
```

```
    }
}
```

## Connection to an NSO Cluster Node

This is very similar to the case of a connection to a managed device, it differs mainly in locations - and in the fact that SSH is always used for connection to a cluster node. The public host keys for a cluster node are stored in the `/cluster/remote-node/ssh/host-key` list, in the same way as the host keys for a device. The keys can be configured e.g. via input directly in the CLI, but in most cases it will be preferable to use the action described below to retrieve keys from the cluster node.

The level of host key verification can also be set per cluster node, via `/cluster/remote-node/ssh/host-key-verification`. The default is to use the global value (or default) for `/ssh/host-key-verification`, but any explicitly set value will override the global value. The possible values are the same as for `/ssh/host-key-verification`.

The `/cluster/remote-node/ssh/fetch-host-keys` action can be used to retrieve the host keys for one or more cluster nodes. In the CLI, range expressions can be used for the node name, e.g. using `*` will retrieve keys for all nodes etc. The action will commit the retrieved keys if possible, but if it is invoked from "configure mode" when the node entry has been created but not committed, the keys will be written to the current transaction, but not committed.

The fingerprints of the retrieved keys will be reported as part of the result from this action, but it is also possible to ask for the fingerprints of already retrieved keys by invoking the `/cluster/remote-node/ssh/host-key/show-fingerprint` action.

### Example 40. Retrieving SSH Host Keys for All Cluster Nodes

```
admin@ncs# cluster remote-node * ssh fetch-host-keys
cluster remote-node ncs1 ssh fetch-host-keys
  result updated
  fingerprint {
    algorithm ssh-dss
    value 03:64:fc:b7:87:bd:34:5e:3b:6e:d8:71:4d:3f:46:76
  }
cluster remote-node ncs2 ssh fetch-host-keys
  result updated
  fingerprint {
    algorithm ssh-dss
    value 03:64:fc:b7:87:bd:34:5e:3b:6e:d8:71:4d:3f:46:76
  }
cluster remote-node ncs3 ssh fetch-host-keys
  result updated
  fingerprint {
    algorithm ssh-dss
    value 03:64:fc:b7:87:bd:34:5e:3b:6e:d8:71:4d:3f:46:76
  }
```

## Publickey Authentication

### Private Key Selection

The private key used for publickey authentication can be taken either from the SSH directory for the local user, or from a list of private keys in the NSO configuration. The user's SSH directory is determined according to the same logic as for the server-side public keys that are authorized for authentication of a given user, see the section called "Public Key Login" in *NSO 5.7 Administration Guide*, but of course different files in this directory are used, see below. Alternatively the key can be configured in the `/ssh/private-key` list, using an arbitrary name for the list key. In both cases the key must be in PEM format



(e.g. as generated by the OpenSSH `ssh-keygen` command), and it may be encrypted or not. Encrypted keys configured in `/ssh/private-key` must have the passphrase for the key configured via `/ssh/private-key/passphrase`.

## Connection to a Managed Device

The specific private key to use is configured via the authgroup indirection and the umap selection mechanisms as for password authentication, just a different alternative. Setting `/devices/authgroups/group/umap/public-key` (or `default-map` instead of `umap` for users that are not in `umap`) without any additional parameters will select the default of using a file called `id_dsa` in the local user's SSH directory, which must have an unencrypted key. A different file name can be set via `/devices/authgroups/group/umap/public-key/private-key/file/name`. For an encrypted key, the passphrase can be set via `/devices/authgroups/group/umap/public-key/private-key/file/passphrase`, or `/devices/authgroups/group/umap/public-key/private-key/file/use-password` can be set to indicate that the password used (if any) by the local user when authenticating to NSO should also be used as passphrase for the key. To instead select a private key from the `/ssh/private-key` list, the name of the key is set via `/devices/authgroups/group/umap/public-key/private-key/name`.

### Example 41. Configuring a Private Key File for Publickey Authentication to Devices

```
admin@ncs(config)# devices authgroups group default umap admin
admin@ncs(config-umap-admin)# public-key private-key file name /home/admin/.ssh/id-dsa
admin@ncs(config-umap-admin)# public-key private-key file passphrase
(<AES encrypted string>): *****
admin@ncs(config-umap-admin)# commit
Commit complete.
```

## Connection to an NSO Cluster Node

This is again very similar to the case of a connection to a managed device, since the same authgroup/umap scheme is used. Setting `/cluster/authgroup/umap/public-key` (or `default-map` instead of `umap` for users that are not in `umap`) without any additional parameters will select the default of using a file called `id_dsa` in the local user's SSH directory, which must have an unencrypted key. A different file name can be set via `/cluster/authgroup/umap/public-key/private-key/file/name`. For an encrypted key, the passphrase can be set via `/cluster/authgroup/umap/public-key/private-key/file/passphrase`, or `/cluster/authgroup/umap/public-key/private-key/file/use-password` can be set to indicate that the password used (if any) by the local user when authenticating to NSO should also be used as passphrase for the key. To instead select a private key from the `/ssh/private-key` list, the name of the key is set via `/cluster/authgroup/umap/public-key/private-key/name`.

### Example 42. Configuring a Private Key File for Publickey Authentication in Cluster

```
admin@ncs(config)# cluster authgroup default umap admin
admin@ncs(config-umap-admin)# public-key private-key file name /home/admin/.ssh/id-dsa
admin@ncs(config-umap-admin)# public-key private-key file passphrase
(<AES encrypted string>): *****
admin@ncs(config-umap-admin)# commit
Commit complete.
```





## Managing Network Services

---

- [Overview, page 107](#)
- [A Service Example, page 108](#)
- [Running the example, page 110](#)
- [Service-Life Cycle Management, page 112](#)
- [Advanced Services Orchestration, page 118](#)

### Overview

Up until this point, this user guide has described how to use NSO to configure devices. NSO can also manage the life-cycle for services like VPNs, BGP peers, ACLs. It is important to understand what is meant by service in this context.

- 1 NSO abstracts the device specific details. The user only needs to enter attributes relevant to the service.
- 2 The service instance has configuration data itself that can be represented and manipulated.
- 3 A service instance configuration change is applied to all affected devices.

These are the features NSO uses to support service configuration.

- 1 *Service Modeling*: network engineers can model the service attributes and the mapping to device configurations. For example, this means that a network engineer can specify at data-model for VPNs with router interfaces, VLAN id, VRF and route distinguisher.
- 2 *Service life-cycle*: while less sophisticated configuration management systems can only create an initial service instance in the network they do not support changing or deleting a service instance. With NSO you can at any point in time modify service elements like the VLAN id of a VPN and NSO can generate the corresponding changes to the network devices.
- 3 The NSO *service instance* has configuration data that can be represented and manipulated. The service model run-time updates all NSO northbound interfaces so a network engineer can view and manipulate the service instance over CLI, WebUI, REST etc.
- 4 NSO maintains *references between service instances and device configuration*. This means that a VPN instance knows exactly which device configurations it created/modified. Every configuration stored in the CDB is mapped to the service instance that created it.

## A Service Example

An example is the best method to illustrate how services are created and used in NSO. As described in the sections about devices and NEDs it was said that NEDs come in packages. The same is true for services, either if you do design the services yourself or use ready-made service applications it ends up in a package that is loaded into NSO.




**Tip**

You can find a video presentation of this demo on [YouTube](#).

The example `examples.ncs/service-provider/mpls-vpn` will be used to explain NSO Service Management features. This example illustrates Layer3 VPNs in a service provider MPLS network. The example network consists of Cisco ASR 9k and Juniper core routers (P and PE) and Cisco IOS based CE routers. The Layer3 VPN service configures the CE/PE routers for all endpoints in the VPN with BGP as the CE/PE routing protocol. Layer2 connectivity between CE and PE routers are expected to be done through a Layer2 ethernet access network, which is out of scope for this example. The Layer3 VPN service includes VPN connectivity as well as bandwidth and QOS parameters.

**Figure 43. A L3 VPN Example**



The service configuration only has references to CE devices for the end-points in the VPN. The service mapping logic reads from a simple topology model that is configuration data in NSO, outside the actual service model, and derives what other network devices to configure. The topology information has two parts. The first part lists connections in the network and is used by the service mapping logic to find out which PE router to configure for an endpoint. The snippets below show the configuration output in the Cisco style NSO CLI.

```

topology connection c0
  endpoint-1 device ce0 interface GigabitEthernet0/8 ip-address 192.168.1.1/30
  endpoint-2 device pe0 interface GigabitEthernet0/0/0/3 ip-address 192.168.1.2/30
  link-vlan 88
!
topology connection c1
  endpoint-1 device ce1 interface GigabitEthernet0/1 ip-address 192.168.1.5/30

```

```

endpoint-2 device pe1 interface GigabitEthernet0/0/0/3 ip-address 192.168.1.6/30
link-vlan 77
!

```

The second part lists devices for each role in the network and is in this example only used to dynamically render a network map in the Web UI.

```

topology role ce
device [ ce0 ce1 ce2 ce3 ce4 ce5 ]
!
topology role pe
device [ pe0 pe1 pe2 pe3 ]
!

```

QOS configuration in service provider networks is complex, and often require a lot of different variations. It is also often desirable to be able to deliver different levels of QOS. This example shows how a QOS policy configuration can be stored in NSO and be referenced from VPN service instances. Three different levels of QOS policies are defined; GOLD, SILVER and BRONZE with different queuing parameters.

```

qos qos-policy GOLD
class BUSINESS-CRITICAL
bandwidth-percentage 20
!
class MISSION-CRITICAL
bandwidth-percentage 20
!
class REALTIME
bandwidth-percentage 20
priority
!
!
qos qos-policy SILVER
class BUSINESS-CRITICAL
bandwidth-percentage 25
!
class MISSION-CRITICAL
bandwidth-percentage 25
!
class REALTIME
bandwidth-percentage 10
!

```

Three different traffic classes are also defined with a DSCP value that will be used inside the MPLS core network as well as default rules that will match traffic to a class.

```

qos qos-class BUSINESS-CRITICAL
dscp-value af21
match-traffic ssh
source-ip any
destination-ip any
port-start 22
port-end 22
protocol tcp
!
!
qos qos-class MISSION-CRITICAL
dscp-value af31
match-traffic call-signaling
source-ip any
destination-ip any
port-start 5060
port-end 5061

```

```

    protocol      tcp
  !
!

```

## Running the example

Make sure you start clean, i.e. no old configuration data is present. If you have been running this or some other example before, make sure to stop any NSO or simulated network nodes (ncs-netsim) that you may have running. Output like 'connection refused (stop)' means no previous NSO was running and 'DEVICE ce0 connection refused (stop)...' no simulated network was running, which is good.

```

$ make stop clean all start
$ ncs_cli -u admin -C

```

This will setup the environment and start the simulated network.

Before creating a new L3VPN service we must sync the configuration from all network devices and then enter config mode. (A hint for this complete section is to have the README file from the example and cut and paste the CLI commands).

```

ncs# devices sync-from
sync-result {
    device ce0
    result true
}
...
ncs# config
Entering configuration mode terminal

ncs(config)# vpn l3vpn volvo
ncs(config-l3vpn-volvo)# as-number 65101
ncs(config-l3vpn-volvo)# endpoint main-office
ncs(config-endpoint-main-office)# ce-device ce0
ncs(config-endpoint-main-office)# ce-interface GigabitEthernet0/11
ncs(config-endpoint-main-office)# ip-network 10.10.1.0/24
ncs(config-endpoint-main-office)# bandwidth 12000000
ncs(config-endpoint-main-office)# !
ncs(config-endpoint-main-office)# endpoint branch-office1
ncs(config-endpoint-branch-office1)# ce-device ce1
ncs(config-endpoint-branch-office1)# ce-interface GigabitEthernet0/11
ncs(config-endpoint-branch-office1)# ip-network 10.7.7.0/24
ncs(config-endpoint-branch-office1)# bandwidth 6000000
ncs(config-endpoint-branch-office1)# !
ncs(config-endpoint-branch-office1)# endpoint branch-office2
ncs(config-endpoint-branch-office2)# ce-device ce4
ncs(config-endpoint-branch-office2)# ce-interface GigabitEthernet0/18
ncs(config-endpoint-branch-office2)# ip-network 10.8.8.0/24
ncs(config-endpoint-branch-office2)# bandwidth 300000
ncs(config-endpoint-branch-office2)# !
ncs(config-endpoint-branch-office2)# top
ncs(config)# show configuration
vpn l3vpn volvo
  as-number 65101
  endpoint branch-office1
    ce-device ce1
    ce-interface GigabitEthernet0/11
    ip-network 10.7.7.0/24
    bandwidth 6000000
  !
  endpoint branch-office2

```

```

ce-device      ce4
ce-interface GigabitEthernet0/18
ip-network     10.8.8.0/24
bandwidth     300000
!
endpoint main-office
ce-device      ce0
ce-interface GigabitEthernet0/11
ip-network     10.10.1.0/24
bandwidth     12000000
!
!
ncs(config)# commit dry-run outformat native
native {
    device {
        name ce0
        data interface GigabitEthernet0/11
            description volvo local network
            ip address 10.10.1.1 255.255.255.0
        exit
    }
    ...
}
(config)# commit

```

Add another VPN (prompts ommitted):

```

top
!
vpn l3vpn ford
as-number 65200
endpoint main-office
ce-device      ce2
ce-interface GigabitEthernet0/5
ip-network     192.168.1.0/24
bandwidth     10000000
!
endpoint branch-office1
ce-device      ce3
ce-interface GigabitEthernet0/5
ip-network     192.168.2.0/24
bandwidth     5500000
!
endpoint branch-office2
ce-device      ce5
ce-interface GigabitEthernet0/5
ip-network     192.168.7.0/24
bandwidth     1500000
!

```

The above sequence showed how NSO can be used to manipulate service abstractions on top of devices. Services can be defined for various purpose such as VPNs, Access Control Lists, firewall rules etc. Support for services is added to NSO via a corresponding service package.

A service package in NSO comprises two parts:

- 1 Service model: the attributes of the service, input parameters given when creating the service. In this example name, as-number, and end-points.
- 2 Mapping: what is the corresponding configuration of the devices when the service is applied. The result of the mapping can be inspected by the **commit dry-run outformat native** command.

We later in this guide show how to define this, for now assume that the job is done.

# Service-Life Cycle Management

## Service Changes

When NSO applies services to the network, NSO stores the service configuration along with resulting device configuration changes. This is used as a base for the FASTMAP algorithm which automatically can derive device configuration changes from a service change. So going back to the example L3 VPN above any part of `volvo` VPN instance can be modified. A simple change like changing the `as-number` on the service results in many changes in the network. NSO does this automatically.

```
ncs(config)# vpn l3vpn volvo as-number 65102
ncs(config-l3vpn-volvo)# commit dry-run outformat native
native {
    device {
        name ce0
        data no router bgp 65101
        router bgp 65102
        neighbor 192.168.1.2 remote-as 100
        neighbor 192.168.1.2 activate
        network 10.10.1.0
    }
    !
    ...
ncs(config-l3vpn-volvo)# commit
```

Let us look at a more challenging modification. A common use-case is of course to add a new CE device and add that as an end-point to an existing VPN. Below follows the sequence to add two new CE devices and add them to the VPN's. (In the CLI snippets below we omit the prompt to enhance readability). First we add them to the topology.

```
top
!
topology connection c7
endpoint-1 device ce7 interface GigabitEthernet0/1 ip-address 192.168.1.25/30
endpoint-2 device pe3 interface GigabitEthernet0/0/0/2 ip-address 192.168.1.26/30
link-vlan 103
!
topology connection c8
endpoint-1 device ce8 interface GigabitEthernet0/1 ip-address 192.168.1.29/30
endpoint-2 device pe3 interface GigabitEthernet0/0/0/2 ip-address 192.168.1.30/30
link-vlan 104
!
ncs(config)#commit
```

Note well that the above just updates NSO local information on topological links. It has no effect on the network. The mapping for the L3 VPN services does a look-up in the topology connections to find the corresponding pe router.

Then we add them to the VPN's

```
top
!
vpn l3vpn ford
endpoint new-branch-office
ce-device ce7
ce-interface GigabitEthernet0/5
ip-network 192.168.9.0/24
bandwidth 4500000
!
vpn l3vpn volvo
endpoint new-branch-office
```



```
ce-device      ce8
ce-interface   GigabitEthernet0/5
ip-network     10.8.9.0/24
bandwidth     4500000
!
```

Before we send anything to the network, let's see look at the device configuration using dry-run. As you can see, both new CE devices are connected to the same PE router, but for different VPN customers.

```
nsc(config)#commit dry-run outformat native
```

And commit the configuration to the network

```
(config)#commit
```

## Service Impacting out-of-band changes

Next we will show how NSO can be used to check if the service configuration in the network is up to date. In a new terminal window we connect directly to the device ce0 that is a Cisco device emulated by the tool ncs-netsim.

```
$ ncs-netsim cli-c ce0
```

We will now reconfigure an edge interface that we previously configured using NSO.

```
enable
ce0# configure
Enter configuration commands, one per line. End with CNTL/Z.
ce0(config)# no policy-map volvo
ce0(config)# exit
ce0# exit
```

Going back to the terminal with NSO, check the status of the network configuration:

```
nsc# devices check-sync
sync-result {
  device ce0
  result out-of-sync
  info got: c5c75ee593246f41eaa9c496ce1051ea expected: c5288cc0b45662b4af88288d29be8667
...

nsc# vpn l3vpn * check-sync
vpn l3vpn ford check-sync
  in-sync true
vpn l3vpn volvo check-sync
  in-sync true

nsc# vpn l3vpn * deep-check-sync
vpn l3vpn ford deep-check-sync
  in-sync true
vpn l3vpn volvo deep-check-sync
  in-sync false
```

The CLI sequence above performs 3 different comparisons:

- Real device configuration versus device configuration copy in NSO CDB
- Expected device configuration from service perspective and device configuration copy in CDB.
- Expected device configuration from service perspective and real device configuration.

Notice that the service 'volvo' is out of sync from the service configuration. Use the check-sync outformat cli to see what the problem is:

```
nsc# vpn l3vpn volvo deep-check-sync outformat cli
```

```
cli devices {
    devices {
        device ce0 {
            config {
+               ios:policy-map volvo {
+                   class class-default {
+                       shape {
+                           average {
+                               bit-rate 12000000;
+                           }
+                       }
+                   }
+               }
+           }
+       }
+   }
}
```

Assume that a network engineer considers the real device configuration to be authoritative:

```
ncs# devices device ce0 sync-from
result true
```

And then restore the service:

```
ncs# vpn l3vpn volvo re-deploy dry-run { outformat native }
native {
    device {
        name ce0
        data policy-map volvo
            class class-default
            shape average 12000000
            !
            !
    }
}
ncs# vpn l3vpn volvo re-deploy
```

## Service Deletion

In the same way as NSO can calculate any service configuration change it can also automatically delete the device configurations that resulted from creating services:

```
ncs(config)# no vpn l3vpn ford
ncs(config)# commit dry-run
cli devices {
    device ce7
    config {
-       ios:policy-map ford {
-           class class-default {
-               shape {
-                   average {
-                       bit-rate 4500000;
-                   }
-               }
-           }
-       }
-   }
}
```

It is important to understand the two diffs shown above. The first diff as an output to show configuration shows the diff at service level. The second diff shows the output generated by NSO to clean up the device configurations.

Finally, we commit the changes to delete the service.

```
(config)# commit
```

## Viewing service configurations

Service instances live in the NSO data-store as well as a copy of the device configurations. NSO will maintain relationships between these two.

Show the configuration for a service

```
ncs(config)# show full-configuration vpn l3vpn
vpn l3vpn volvo
  as-number 65102
  endpoint branch-office1
    ce-device    ce1
    ce-interface GigabitEthernet0/11
    ip-network   10.7.7.0/24
    bandwidth    6000000
  !
  ...
```

You can ask NSO to list all devices that are touched by a service and vice versa:

```
ncs# show vpn l3vpn device-list
NAME    DEVICE LIST
-----
volvo   [ ce0 ce1 ce4 ce8 pe0 pe2 pe3 ]
```

```
ncs# show devices device service-list
NAME    SERVICE LIST
-----
ce0     [ "/l3vpn:vpn/l3vpn{volvo}" ]
ce1     [ "/l3vpn:vpn/l3vpn{volvo}" ]
ce2     [ ]
ce3     [ ]
ce4     [ "/l3vpn:vpn/l3vpn{volvo}" ]
ce5     [ ]
ce6     [ ]
ce7     [ ]
ce8     [ "/l3vpn:vpn/l3vpn{volvo}" ]
p0      [ ]
p1      [ ]
p2      [ ]
p3      [ ]
pe0     [ "/l3vpn:vpn/l3vpn{volvo}" ]
pe1     [ ]
pe2     [ "/l3vpn:vpn/l3vpn{volvo}" ]
pe3     [ "/l3vpn:vpn/l3vpn{volvo}" ]
```

Note that operational mode in the CLI was used above. Every service instance has an operational attribute that is maintained by the transaction manager and shows which device configuration it created. Furthermore every device configuration has backwards pointers to the corresponding service instances:

```
ncs(config)# show full-configuration devices device ce3 \
              config | display service-meta-data
devices device ce3
  config
  ...
  /* Refcount: 1 */
  /* Backpointer: [ /l3vpn:vpn/l3vpn:l3vpn[l3vpn:name='ford'] ] */
  ios:interface GigabitEthernet0/2.100
```

```

/* Refcount: 1 */
description Link to PE / pe1 - GigabitEthernet0/0/0/5
/* Refcount: 1 */
encapsulation dot1Q 100
/* Refcount: 1 */
ip address 192.168.1.13 255.255.255.252
/* Refcount: 1 */
service-policy output ford
exit

ncs(config)# show full-configuration devices device ce3 config \
              | display curly-braces | display service-meta-data
...
ios:interface {
  GigabitEthernet 0/1;
  GigabitEthernet 0/10;
  GigabitEthernet 0/11;
  GigabitEthernet 0/12;
  GigabitEthernet 0/13;
  GigabitEthernet 0/14;
  GigabitEthernet 0/15;
  GigabitEthernet 0/16;
  GigabitEthernet 0/17;
  GigabitEthernet 0/18;
  GigabitEthernet 0/19;
  GigabitEthernet 0/2;
  /* Refcount: 1 */
  /* Backpointer: [ /l3vpn:vpn/l3vpn:l3vpn[l3vpn:name='ford'] ] */
  GigabitEthernet 0/2.100 {
    /* Refcount: 1 */
    description "Link to PE / pe1 - GigabitEthernet0/0/0/5";
    encapsulation {
      dot1Q {
        /* Refcount: 1 */
        vlan-id 100;
      }
    }
    ip {
      address {
        primary {
          /* Refcount: 1 */
          address 192.168.1.13;
          /* Refcount: 1 */
          mask 255.255.255.252;
        }
      }
    }
    service-policy {
      /* Refcount: 1 */
      output ford;
    }
  }
}

ncs(config)# show full-configuration devices device ce3 config \
              | display service-meta-data | context-match Backpointer
devices device ce3
/* Refcount: 1 */
/* Backpointer: [ /l3vpn:vpn/l3vpn:l3vpn[l3vpn:name='ford'] ] */
ios:interface GigabitEthernet0/2.100
devices device ce3
/* Refcount: 2 */
/* Backpointer: [ /l3vpn:vpn/l3vpn:l3vpn[l3vpn:name='ford'] ] */

```

```
ios:interface GigabitEthernet0/5
```

The reference counter above makes sure that NSO will not delete shared resources until the last service instance is deleted. The context-match search is helpful, it displays the path to all matching configuration items.

## Using Commit queues

As described in detail in the Device Manager [the section called “Commit Queue”](#) section the commit queue can be used to increase the transaction throughput. When the commit queue are for service activation the services will have states reflecting outstanding commit queue items.



### Note

When committing a service using the commit queue in *async* mode the northbound system can not rely on the service being fully activated in the network when the activation requests returns.

We will now commit a vpn service using the commit queue and one device is down.

```
$ ncs-netsim stop ce0
DEVICE ce0 STOPPED
```

```
ncs(config)# show configuration
vpn l3vpn volvo
  as-number 65101
  endpoint branch-office1
    ce-device    ce1
    ce-interface GigabitEthernet0/11
    ip-network   10.7.7.0/24
    bandwidth    6000000
  !
  endpoint main-office
    ce-device    ce0
    ce-interface GigabitEthernet0/11
    ip-network   10.10.1.0/24
    bandwidth    12000000
  !
!
```

```
ncs# commit commit-queue async
commit-queue-id 10777927137
Commit complete.
```

```
ncs(config)# *** ALARM connection-failure: Failed to connect to device ce0: connection refused
```

This service is not provisioned fully in the network, since **ce0** was down. It will stay in the queue either until the device starts responding or that an action is taken to remove the service or remove the item. The commit queue can be inspected. As shown below we see that we are waiting for **ce0**. Inspecting the queue item shows the outstanding configuration.

```
ncs# show devices commit-queue | notab
devices commit-queue queue-item 10777927137
  age          1934
  status       executing
  kilo-bytes-size 2
  devices      [ ce0 ce1 pe0 ]
  transient-errors [ ce0 ]
  is-atomic     true
```

```
ncs# show vpn l3vpn volvo commit-queue | notab
commit-queue queue-item 1498812003922
```

```
status executing
```

The commit queue will constantly try to push the configuration towards the devices. The number of retry attempts and at what interval they occur can be configured.

```
ncs# show full-configuration devices global-settings commit-queue | details
devices global-settings commit-queue enabled-by-default false
devices global-settings commit-queue atomic true
devices global-settings commit-queue retry-timeout 30
devices global-settings commit-queue retry-attempts unlimited
```

If we start **ce0** and inspect the queue we will see that the queue will finally be empty, and that the commit-queue status for the service is empty.

```
ncs# show devices commit-queue | notab
devices commit-queue queue-item 10777927137
  age          3357
  status       executing
  kilo-bytes-size 2
  devices      [ ce0 ce1 pe0 ]
  transient-errors [ ce0 ]
  is-atomic     true
```

```
ncs# show devices commit-queue | notab
devices commit-queue queue-item 10777927137
  age          3359
  status       executing
  kilo-bytes-size 2
  devices      [ ce0 ce1 pe0 ]
  is-atomic     true
```

```
ncs# show devices commit-queue
% No entries found.
```

```
ncs# show vpn l3vpn volvo commit-queue
% No entries found.
```

```
ncs# show devices commit-queue completed | notab
devices commit-queue completed queue-item 10777927137
  when          2015-02-09T16:48:17.915+00:00
  succeeded      true
  devices      [ ce0 ce1 pe0 ]
  completed     [ ce0 ce1 pe0 ]
  completed-services [ /l3vpn:vpn/l3vpn:l3vpn[l3vpn:name='volvo'] ]
```

## Un-deploying Services

In some scenarios it makes sense to remove the service configuration from the network but keep the representation of the service in NSO. This is called to **un-deploy** a service.

```
ncs# vpn l3vpn volvo check-sync
in-sync false
ncs# vpn l3vpn volvo re-deploy
ncs# vpn l3vpn volvo check-sync
in-sync true
```

## Advanced Services Orchestration

Some services need to be set up in stages where each stage can consist of setting up some device configuration and then wait for this configuration to take effect before performing next stage. In this

scenario each stage must be performed in a separate transaction which is committed separately. Most often an external notification or other event must be detected and trigger the next stage in the service activation.

NSO supports the implementation of such staged services with the use of a Reactive FASTMAP pattern, and the services are often referred to as RFM services.

From the user perspective it is not important how a certain service is implemented. And the implementation should not have an impact on how the user creates or modifies a service. However the knowledge about this can be necessary to explain the behavior of a certain service.

In short the life-cycle of a RFM service is not only controlled by the direct create/set/delete operations. Instead there are one or many implicit `reactive-re-deploy` requests on the service that are triggered from external event detection. If the user examines a RFM service, e.g. using `get-modification`, the device impact will grow over time after the initial create.

## RFM service plans

Reactive Fastmap (RFM) services autonomously will do `reactive-re-deploy` until all "stages" of the service are completed. This implies that an RFM service normally is not completed when the initial create is committed. For the operator to understand that a RFM service has run to completion there must typically be some service specific operational data that can indicate this.

*Plans* are introduced to standardize the operational data that can show the progress of RFM service. This gives the user a standardized view of all RFM services and can directly answer the question whether a service instance has run to completion or not.

A *plan* consists of one or many *component* entries. Each *component* consists of two or many *state* entries where the state can be in status *not-reached*, *reached* or *failed*. A *plan* must have a component named "self" and can have other components with arbitrary names that have meaning for the implementing RFM service. A *plan component* must have a first *state* named "init" and a last *state* named "ready". In between "init" and "ready" a *plan component* can have additional *state* entries with arbitrary naming.

The purpose of the "self" *component* is to describe the main progress of the RFM service as a whole. Most importantly the "self" *component* last *state* named "ready" must have status "reached" if and only if the RFM service as a whole has completed. Other arbitrary components as well as states are added to the plan if they have meaning for the specific RFM service i.e more specific progress reporting.

A *plan* also defines an empty leaf *failed* which is set if and only if any *state* in any *component* has a status set to "failed". As such this is an aggregation to make it easy to verify if a RFM service is progressing without problems or not.

The following is an illustration of using the plan to report progress of an RFM service:

```
nsc# show vpn l3vpn volvo plan
```

NAME	TYPE	STATE	STATUS	WHEN
-----				
self	self	init	reached	2016-04-08T09:22:40
		ready	not-reached	-
endpoint-branch-office	l3vpn	init	reached	2016-04-08T09:22:40
		qos-configured	reached	2016-04-08T09:22:40
endpoint-head-office	l3vpn	ready	reached	2016-04-08T09:22:40
		init	reached	2016-04-08T09:22:40
		pe-created	not-reached	-
		ce-vpe-topo-added	not-reached	-
		vpe-p0-topo-added	not-reached	-
		qos-configured	not-reached	-
		ready	not-reached	-

## Service progress monitoring

*Plans* were introduced to standardize the operational data that show progress of reactive fastmap (RFM) services. This gives the user a standardized view of all RFM services and can answer the question whether a service instance has run to completion or not. To keep track of the progress of *plans service progress monitoring* (SPM) is introduced. The idea with *SPM* is that time limits are put on the progress of plan states. To do so, a *policy* and a *trigger* is needed.

A *policy* defines what plan components and states needs to be in what *status* for the *policy* to be true. A *policy* also defines how long time it can be false without considered jeopardized and how long time it can be false without considered violated. Further it may define an action, that is called in case of a policy being jeopardized, violated or successful.

A *trigger* is used to associate a policy with a service and a component.

The following is an illustration of using a SPM to track progress of an RFM service, in this case the policy specifies that the self components ready state must be reached for the policy to be true:

```
ncs# show vpn l3vpn volvo service-progress-monitoring
```

NAME	POLICY	START TIME	JEOPARDY TIME	JEOPARDY RESULT	VIOLATION TIME	VI RE
self	service-ready	2016-04-08T09:22:40	2016-04-08T09:22:40	-	2016-04-08T09:22:40	-





## CHAPTER 6

# The Alarm Manager


---

- [Alarm Manager Introduction, page 121](#)
- [Overview of the alarm concepts, page 123](#)
- [The Alarm Model, page 125](#)
- [Alarm handling, page 128](#)

## Alarm Manager Introduction

NSO embeds a generic alarm manager. It is used for managing NSO native alarms and can easily be extended with application specific alarms. Alarm sources can be notifications from devices, undesired states on services detected or anything provided via the Java API.

Figure 44. The Alarm Manager



The Alarm Manager has three main components:

Alarm List	a list of alarms in NSO. Each list entry represents an alarm state for a specific device, object within the device and an alarm type
Alarm Model	for each alarm type, you can configure the mapping to for example X.733 alarm standard parameters that are sent as notifications northbound
Operator Actions	actions to set operator states on alarms such as acknowledgement, and also actions to administratively manage the alarm list such as deleting alarms

The alarm manager is accessible over all northbound interfaces. A read-only view including an SNMP alarm table and alarm notifications is available in an SNMP Alarm MIB. This MIB is suitable for integration to SNMP based alarm systems.

In order to populate the alarm list there is a dedicated Java API. This API lets a developer add alarms, change states on alarms etc. A common usage pattern is to use the SNMP notification receiver to map a subset of the device traps into alarms.

## Overview of the alarm concepts


First of all it is important to clearly define what an alarm means. “An alarm denotes an undesirable state in a resource for which an operator action is required.” Alarms are often confused with general logging and event mechanisms, thereby overflowing the operator with alarms. In NSO, the alarm manager shows undesired resource states that an operator should investigate. NSO contains other mechanisms for logging in general. Therefore, NSO does not naively populate the alarm list with traps received in the SNMP notification receiver.

Before looking into how NSO handles alarms it is important to define the fundamental concepts. We make a clear distinction between alarms and events in general. Alarms should be taken seriously and be investigated. Alarms have states, they go active with a specific severity, they change severity and they are cleared by the resource. The same alarm may become active again. A common mistake is to confuse the operator view with the resource view. The model described so far is the resource view. The resource itself may consider the alarm cleared. The alarm manager does not automatically delete cleared alarms. An alarm that has existed in the network may still need investigation. There are dedicated actions an operator can use to manage the alarm list, for example delete alarms based on criterias such as cleared and date. These actions can be performed over all north-bound interfaces.

Rather than viewing alarms as a list of alarm notifications NSO defines alarms as states on objects. The NSO alarm list uses four keys for alarms: the alarming *object* within a *device* and the *alarm type* and an optional *specific problem*. *Alarm types* are normally unique identifiers for a specific alarm state and are defined statically. An alarm type corresponds to the well-known X.733 alarm standard tuple event type, and probable cause. Specific problem is an optional key that is string based and can further redefine an alarm type at run-time. This is needed for alarms that are not known before a system is deployed. Imagine a system with general digital inputs. A MIB might specify traps called input-high, input-low. When defining the SNMP notification reception, an integrator might define an alarm type called "External-Alarm". Input-high might imply a major alarm and input-low might imply clear. At installation some detectors report "fire-alarm" and some "door-open" alarms. This is configured at the device and sent as free text in the SNMP var-binds. This is then managed by using the specific problem field of the NSO alarm manager to separate this different alarm types.

The data model for the alarm-manager is outlined in [Figure 45, “Alarm Model”](#)

Figure 45. Alarm Model



This means that we have a list with key: (managed device, managed object, alarm type, specific problem). In the example above we might have the following different alarms:

- Device : House1; Managed Object : Detector1; Alarm-Type : External Alarm; Specific Problem = Smoke;

- Device : House1; Managed Object : Detector2; Alarm-Type : External Alarm; Specific Problem = Door Open;

Each alarm entry shows the last status change for the alarm and also a child list with all status changes sorted in chronological order.

is-cleared	was the last state change <i>clear</i> ?
last-status-change	time stamp for last status change
last-perceived-severity	last severity (not equal to clear)
last-alarm-text	the last alarm text (not equal to clear)
status-change, event-time	the time reported by the device
status-change, received-time	the time the state change was received by NSO
status-change, perceived-severity	the new perceived severity
status-change, alarm-text	descriptive text associated with the new alarm status

It is fundamental to define alarm types (specific problem) and managed objects with a fine-grained mechanism that still is extensible. For objects we allow YANG instance-identifiers to refer to a YANG instance identifier, an SNMP OID, or a string. Strings can be used when the underlying object is not modelled. We use YANG identities to define alarm types. This has the benefit that alarm types can be defined in a named hierarchy and thereby provide an extensible mechanism. In order to support "dynamic alarm types" so that alarms can be separated by information only available at run-time the string based field specific problem can also be used.

So far we have described the model based on the resource view. It is common practice to let operators manipulate the alarms corresponding to the operators investigation. We clearly separate the resource and the operator view, for example, there is no such thing as an operator "clearing an alarm". Rather the alarm entries can have a corresponding alarm handling state. Operators may want to acknowledge an alarm, set the alarm state to closed or similar.

We also support some alarm list administrative actions:

<i>Synchronize alarms</i>	try to read the alarm states in the underlying resources and update the alarm list accordingly (this action needs to be implemented by user code for specific applications)
<i>Purge alarms</i>	delete entries in the alarm list based on several different filter criteria
<i>Filter alarms</i>	with a XPATH as filter input, this action returns all alarms fulfilling the filter
<i>Compress alarms</i>	since every entry may contain a large amount of state change entries this action compresses the history to the latest state change

Alarms can be forwarded over NSO northbound interfaces. In many telecom environments alarms need to be mapped to X.733 parameters. We provide an *alarm model* where every alarm type is mapped to the corresponding X.733 parameters such as event type and probable cause. In this way, it is easy to integrate the NSO alarms into whatever X.733 enumerated values the upper fault management system is requiring.

## The Alarm Model

The central part of the YANG Alarm model, `tailf-ncs-alarms.yang` has the following structure.

### Example 46. `tailf-ncs-alarms.yang`

```
module tailf-ncs-alarms {
    namespace "http://tail-f.com/ns/ncs-alarms";
    prefix "al";
```

```

...
typedef managed-object-t {
    type union {
        type instance-identifier {
            require-instance false;
        }
        type yang:object-identifier;
        type string;
    }
}

...
typedef event-type {
    type enumeration {
        enum other {value 1;}
        enum communicationsAlarm {value 2;}
        enum qualityOfServiceAlarm {value 3;}
        enum processingErrorAlarm {value 4;}
        enum equipmentAlarm {value 5;}
        ...
    }
    description
    "...";
    reference
    "ITU Recommendation X.736, 'Information Technology - Open
    Systems Interconnection - System Management: Security
    Alarm Reporting Function', 1992";
}

typedef severity-t {
    type enumeration {
        enum cleared {value 1;}
        enum indeterminate {value 2;}
        enum critical {value 3;}
        enum major {value 4;}
        enum minor {value 5;}
        enum warning {value 6;}
    }
    description
    "...";
}

...
identity alarm-type {
    description
    "Base identity for alarm types."
    ...
}

identity ncs-dev-manager-alarm {
    base alarm-type;
}

identity ncs-service-manager-alarm {
    base alarm-type;
}

identity connection-failure {
    base ncs-dev-manager-alarm;
    description
    "NCS failed to connect to a device";
}
....

```

```

container alarm-model {
  list alarm-type {
    key "type";
    leaf type {
      type alarm-type-t;
    }

    uses alarm-model-parameters;
  }
}

...

container alarm-list {
  config false;
  leaf number-of-alarms {
    type yang:gauge32;
  }

  leaf last-changed {
    type yang:date-and-time;
  }

  list alarm {
    key "device type managed-object specific-problem";
    uses common-alarm-parameters;
    leaf is-cleared {
      type boolean;
      mandatory true;
    }

    leaf last-status-change {
      type yang:date-and-time;
      mandatory true;
    }

    leaf last-perceived-severity {
      type severity-t;
    }

    leaf last-alarm-text {
      type alarm-text-t;
    }

    list status-change {
      key event-time;
      min-elements 1;
      uses alarm-state-change-parameters;
    }

    leaf last-alarm-handling-change {
      type yang:date-and-time;
    }

    list alarm-handling {
      key time;
      leaf time {
        tailf:info "Time stamp for operator action";
        type yang:date-and-time;
      }
      leaf state {

```

```

        tailf:info "The operators view of the alarm state";
        type alarm-handling-state-t;
        mandatory true;
        description
            "The operators view of the alarm state.";
    }
    ...
}
...
notification alarm-notification {
    ...
    rpc synchronize-alarms {
        ...
    }
    rpc compress-alarms {
        ...
    }
    rpc purge-alarms {

```

The first part of the YANG listing above shows the definition for `managed-object` type in order for alarms to refer to YANG, SNMP and other resources. We also see basic definitions from the X.733 standard for severity levels.

Note well the definition of `alarm-type` using YANG identities. In this way we can create a structured alarm type hierarchy all rooted at `alarm-type`. In order for you to add your specific alarm types, define your own alarm types YANG file and add identities using `alarm-type` as base.

The `alarm-model` container contains the mapping from alarm types to X.733 parameters used for north-bound interfaces.

The `alarm-list` container is the actual alarm list where we maintain a list mapping (device, managed-object, alarm-type, specific-problem) to the corresponding alarm state changes [(time, severity, text)].

Finally, we see the northbound alarm notification and alarm administrative actions.

## Alarm handling

The NSO alarm manager has support for the operator to acknowledge alarms. We call this alarm handling. Each alarm has an associated list of alarm handling entries as:

```

container alarms {
    ....
    container alarm-list {
        config false;
        ....
        list alarm {
            key "device type managed-object specific-problem";

            .....

            list alarm-handling {
                key time;
                leaf time {
                    type yang:date-and-time;
                    description
                        "Time-stamp for operator action on alarm.";
                }
                leaf state {
                    mandatory true;
                    type alarm-handling-state-t;
                    description
                        "The operators view of the alarm state";

```



```

    }
    leaf user {
        description "Which user has acknowledged this alarm";
        mandatory true;
        type string;
    }
    leaf description {
        description "Additional optional textual information regarding
            this new alarm-handling entry";
        type string;
    }
}

tailf:action handle-alarm {
    tailf:info "Set the operator state of this alarm";
    description
        "An action to allow the operator to add an entry to the
        alarm-handling list. This is a means for the operator to indicate
        the level of human intervention on an alarm.";
    input {
        leaf state {
            type alarm-handling-state-t;
            mandatory true;
        }
    }
}
}

```

The following typedef defines the different states an alarm can be set into.

#### Example 47. Alarm state

```

typedef alarm-handling-state-t {
    type enumeration {
        enum none {
            value 1;
        }
        enum ack {
            value 2;
        }
        enum investigation {
            value 3;
        }
        enum observation {
            value 4;
        }
        enum closed {
            value 5;
        }
    }
    description
        "Operator actions on alarms";
}

```

It is of course also possible to manipulate the alarm handling list from either Java code or Javascript code running in the web browser using the `js_maapi` library.

Below follows a simple scenario to illustrate the alarm concepts. The example can be found in `examples.ncs/service-provider/simple-mpls-vpn`

```

$ make stop clean all start
$ ncs-netsim stop pe0

```

```

$ ncs-netsim stop pe1
$ ncs_cli -u admin -C
admin connected from 127.0.0.1 using console on host
admin@ncs# devices connect
...
connect-result {
    device pe0
    result false
    info Failed to connect to device pe0: connection refused
}
connect-result {
    device pe1
    result false
    info Failed to connect to device pe1: connection refused
}
...
admin@ncs# show alarms alarm-list
alarms alarm-list number-of-alarms 2
alarms alarm-list last-changed 2015-02-18T08:02:49.162436+00:00
alarms alarm-list alarm pe0 connection-failure /devices/device[name='pe0'] ""
    is-cleared                false
    last-status-change         2015-02-18T08:02:49.162734+00:00
    last-perceived-severity    major
    last-alarm-text             "Failed to connect to device pe0: connection refused"
    status-change 2015-02-18T08:02:49.162734+00:00
    received-time              2015-02-18T08:02:49.162734+00:00
    perceived-severity         major
    alarm-text                  "Failed to connect to device pe0: connection refused"
alarms alarm-list alarm pe1 connection-failure /devices/device[name='pe1'] ""
    is-cleared                false
    last-status-change         2015-02-18T08:02:49.162436+00:00
    last-perceived-severity    major
    last-alarm-text             "Failed to connect to device pe1: connection refused"
    status-change 2015-02-18T08:02:49.162436+00:00
    received-time              2015-02-18T08:02:49.162436+00:00
    perceived-severity         major
    alarm-text                  "Failed to connect to device pe1: connection refused"

```

In the above scenario we stop two of the devices and then ask NSO to connect to all devices. This results in two alarms for pe0 and pe1. Note that the key for the alarm is the devicename, the alarm-type and the full path to the object (in this case the device and not an object within the device) and finally an empty string for specific problem.

In the next command sequence we start the device and request NSO to connect. This will clear the alarms.

```

admin@ncs# exit
$ ncs-netsim start pe0
DEVICE pe0 OK STARTED
$ ncs-netsim start pe1
DEVICE pe1 OK STARTED
$ ncs_cli -u admin -C
$ admin@ncs# devices connect
...
connect-result {
    device pe0
    result true
    info (admin) Connected to pe0 - 127.0.0.1:10028
}
connect-result {
    device pe1
    result true
    info (admin) Connected to pe1 - 127.0.0.1:10029
}

```

```

}
...
admin@ncs# show alarms alarm-list
alarms alarm-list number-of-alarms 2
alarms alarm-list last-changed 2015-02-18T08:05:04.942637+00:00
alarms alarm-list alarm pe0 connection-failure /devices/device[name='pe0'] ""
  is-cleared          true
  last-status-change   2015-02-18T08:05:04.942637+00:00
  last-perceived-severity major
  last-alarm-text       "Failed to connect to device pe0: connection refused"
  status-change 2015-02-18T08:02:49.162734+00:00
    received-time      2015-02-18T08:02:49.162734+00:00
    perceived-severity major
    alarm-text          "Failed to connect to device pe0: connection refused"
  status-change 2015-02-18T08:05:04.942637+00:00
    received-time      2015-02-18T08:05:04.942637+00:00
    perceived-severity cleared
    alarm-text          "Connected as admin"
alarms alarm-list alarm pe1 connection-failure /devices/device[name='pe1'] ""
  is-cleared          true
  last-status-change   2015-02-18T08:05:04.84115+00:00
  last-perceived-severity major
  last-alarm-text       "Failed to connect to device pe1: connection refused"
  status-change 2015-02-18T08:02:49.162436+00:00
    received-time      2015-02-18T08:02:49.162436+00:00
    perceived-severity major
    alarm-text          "Failed to connect to device pe1: connection refused"
  status-change 2015-02-18T08:05:04.84115+00:00
    received-time      2015-02-18T08:05:04.84115+00:00
    perceived-severity cleared
    alarm-text          "Connected as admin"

```

Note that there are two status-change entries for the alarm and that the alarm is cleared. In the following scenario we will state that the alarm is closed and finally purge (delete) all alarms that are cleared and closed. (Again note the distinction between operator states and the states from the underlying resources.)

```

admin@ncs# alarms alarm-list alarm pe0 connection-failure /devices/device[name='pe0']
      "" handle-alarm state closed description Fixed

admin@ncs# show alarms alarm-list alarm alarm-handling

DEVICE  TYPE                      STATE  USER  DESCRIPTION
-----
pe0     connection-failure  closed  admin  Fixed

admin@ncs# alarms purge-alarms alarm-handling-state-filter { state closed }
Value for 'alarm-status' [any,cleared,not-cleared]: cleared
purged-alarms 1

```

Assume you need to configure the northbound parameters. This is done using the alarm-model. A logical mapping of the connection problem above is to map it to X.733 probable cause `connectionEstablishmentError (22)`. This is done in the NSO CLI in the following way:

```

admin@ncs# config
Entering configuration mode terminal
admin@ncs(config)# alarms alarm-model alarm-type connection-failure probable-cause 22
admin@ncs(config-alarm-type-connection-failure/*)# commit
Commit complete.
admin@ncs(config-alarm-type-connection-failure/*)# show full-configuration
alarms alarm-model alarm-type connection-failure *
  event-type      communicationsAlarm
  has-clear        true

```

```
kind-of-alarm root-cause  
probable-cause 22
```



## Plug-and-play scripting

---

- [Introduction, page 133](#)
- [Script storage, page 133](#)
- [Script interface, page 134](#)
- [Loading of scripts, page 134](#)
- [Command scripts, page 135](#)
- [Policy scripts, page 139](#)
- [Post-commit scripts, page 142](#)

### Introduction

This chapter defines a scripting mechanism to be used together with the CLI (scripting is not available for any other northbound interfaces). The chapter is intended for users that are familiar with UNIX shell scripting and/or programming. With the scripting mechanism it is possible for an end-user to add new functionality to NSO in a plug-and-play like manner. No special tools are needed. There are three categories of scripts:

command scripts	used to add new commands to the CLI.
policy scripts	invoked at validation time and may control the outcome of a transaction. Policy scripts have the mandate to cause a transaction to abort.
post-commit scripts	invoked when a transaction has been committed. Post-commit scripts can for example be used for logging, sending external events etc.

The terms "script" and "scripting" used throughout this description refer to how functionality can be added without a requirement for integration using the NSO programming APIs. NSO will only run the scripts as UNIX executables. Thus they may be written as shell scripts, or using some other scripting language that is supported by the OS, e.g., Python, or even be compiled code. The scripts are run with the same user id as NSO. The examples in this section are written using shell scripts as a least common denominator, but they could have been written in whatever is suitable, e.g., Python or C.

### Script storage

Scripts are stored in a directory tree with a predefined structure where there is a sub-directory for each script category:

```
scripts/
```

```
command/
policy/
post-commit/
```

For all script categories it suffices to just add a valid script in the correct sub-directory in order to enable the script. See the details for each script category for how a valid script of that category is defined. Scripts with a name beginning with a dot character (".") are ignored.

The directory path to the location of the scripts is configured with the `/ncs-config/scripts/dir` configuration parameter. It is possible to have several scripts directories. The sample `ncs.conf` file that comes with the NSO release specifies two script directories: `./scripts` and `${NCS_DIR}/scripts`.

## Script interface

All scripts are required to provide a formal description of their interface. When the scripts are loaded, NSO will invoke the scripts with (one of)

```
--command
--policy
--post-commit
```

as argument depending of the script category.

The script must respond by writing its formal interface description on `stdout` and exit normally. Such a description consists of one or more sections. Which sections that are required depends on the category of the script.

The sections do however have a common syntax. Each section begins with the keyword "begin" followed by the type of section. After that one or more lines of settings follows. Each such setting begins with a name, followed by a colon character (":") and after that the value is stated. The section ends with the keyword "end". Empty lines and spaces may be used to improve the readability.

For examples see each corresponding section below.

## Loading of scripts

Scripts are automatically loaded at startup and may also be manually reloaded with the CLI command **script reload**. The command takes an optional *verbosity* parameter which may have one of the following values:

```
diff    Shows info about those scripts that have been changed since the latest (re)load. This is the
         default.
all     Shows info about all scripts regardless of whether they have been changed or not.
errors  Shows info about those scripts that are erroneous, regardless of whether they have been
         changed or not. Typical errors are invalid file permissions and syntax errors in the interface
         description.
```

Yet another parameter may be useful when debugging reload of scripts:

```
debug   Shows additional debug info about the scripts.
```

An example session reloading scripts:

```
admin@ncs# script reload all
$NCS_DIR/examples.ncs/getting-started/using-ncs/7-scripting/scripts:
ok
command:
```

```

        add_user.sh: unchanged
        echo.sh: unchanged
    policy:
        check_dir.sh: unchanged
    post-commit:
        show_diff.sh: unchanged
    /opt/ncs/scripts: ok
    command:
        device_brief.sh: unchanged
        device_brief_c.sh: unchanged
        device_list.sh: unchanged
        device_list_c.sh: unchanged
        device_save.sh: unchanged

```

## Command scripts

Command scripts are used to add new commands to the CLI. The scripts are executed in the context of a transaction. When the script is run in `oper` mode, this is a read-only transaction, when it is run in `config` mode, it is a read-write transaction. In that context the script may make use of the environment variables `NCS_MAAPI_USID` and `NCS_MAAPI_THANDLE` in order to attach to the active transaction. This makes it simple to make use of the **ncs-maapi** command (see the `ncs-maapi(1)` in *NSO 5.7 Manual Pages* manual page) for various purposes.

Each command script must be able to handle the argument `--command` and, when invoked, write a `command` section to `stdout`. If the CLI command is intended to take parameters, one `param` section per CLI parameter must also be emitted.

The command is not paginated by default in the CLI and will only do so if it is piped to `more`.

```
joe@io> example_command_script | more
```

## Command section

The following settings can be used to define a command:

<code>modes</code>	Defines in which CLI mode(s) that the command should be available. The value can be <code>oper</code> , <code>config</code> or both (separated with space).
<code>styles</code>	Defines in which CLI styles that the command should be available. The value can be one or more of <code>c</code> , <code>i</code> and <code>j</code> (separated with space). <code>c</code> means Cisco style, <code>i</code> , means Cisco IOS and <code>j</code> for J-style.
<code>cmdpath</code>	Is the full CLI command path. For example the command path <code>my script echo</code> implies that the command will be called <code>my script echo</code> in the CLI.
<code>help</code>	Command help text.

An example of a command section is:

```

begin command
  modes: oper
  styles: c i j
  cmdpath: my script echo
  help: Display a line of text
end

```

## Param section

In this section various aspects of a parameter is specified. This may both affect the parameter syntax for the end-user in the CLI as well as what the command script will get as arguments. The following settings can be used to customize each CLI parameter:

name	Optional name of the parameter. If provided, the CLI will prompt for this name before the value. By default the name is not forwarded to the script. See <code>flag</code> and <code>prefix</code> .
type	The type of the parameter. By default each parameter has a value, but by setting the type to <code>void</code> the CLI will not prompt for a value. In order to be useful the <code>void</code> type must be combined with <code>name</code> and either <code>flag</code> or <code>prefix</code> .
presence	Controls whether the parameter must be present in the CLI input or not. Can be set to <code>optional</code> or <code>mandatory</code> .
words	Controls the number of words that the parameter value may consist of. By default the value must consist of just one word (possibly quoted if it contains spaces). If set to <code>any</code> , the parameter may consist of any number of words. This setting is only valid for the last parameter.
flag	Extra word added before the parameter value. For example if set to <code>-f</code> and the user enters <code>logfile</code> , the script will get <code>-f logfile</code> as arguments.
prefix	Extra string prepended to the parameter value (as a single word). For example if set to <code>--file=</code> and the user enters <code>logfile</code> , the script will get <code>--file=logfile</code> as argument.
help	Parameter help text.

If the command takes a parameter to redirect the output to a file, a `param` section might look like this:

```
begin param
  name: file
  presence: optional
  flag: -f
  help: Redirect output to file
end
```

## Full command example

A command denying changes the configured `trace-dir` for a set of devices it can use the `check_dir.sh` script.

```
#!/bin/bash

set -e

while [ $# -gt 0 ]; do
  case "$1" in
    --command)
      # Configuration of the command
      #
      # modes    - CLI mode (oper config)
      # styles   - CLI style (c i j)
      # cmdpath  - Full CLI command path
      # help     - Command help text
      #
      # Configuration of each parameter
      #
      # name      - (optional) name of the parameter
      # more      - (optional) true or false
      # presence  - optional or mandatory
      # type      - void - A parameter without a value
      # words     - any - Multi word param. Only valid for the last param
      # flag      - Extra word added before the parameter value
      # prefix    - Extra string prepended to the parameter value
      # help      - Command help text
      cat << EOF

begin command
```



```

modes: config
styles: c i j
cmdpath: user-wizard
help: Add a new user
end
EOF

        exit
        ;;
    *)
        break
        ;;
esac
shift
done

## Ask for user name
while true; do
    echo -n "Enter user name: "
    read user

    if [ ! -n "${user}" ]; then
        echo "You failed to supply a user name."
    elif ncs-maapi --exists "/aaa:aaa/authentication/users/user${user}"; then
        echo "The user already exists."
    else
        break
    fi
done

## Ask for password
while true; do
    echo -n "Enter password: "
    read -s pass1
    echo

    if [ "${pass1:0:1}" == "$" ]; then
        echo -n "The password must not start with $. Please choose a "
        echo "different password."
    else
        echo -n "Confirm password: "
        read -s pass2
        echo

        if [ "${pass1}" != "${pass2}" ]; then
            echo "Passwords do not match."
        else
            break
        fi
    fi
done

groups=`ncs-maapi --keys "/nacm/groups/group"`
while true; do
    echo "Choose a group for the user."
    echo -n "Available groups are: "
    for i in ${groups}; do echo -n "${i} "; done
    echo
    echo -n "Enter group for user: "
    read group

    if [ ! -n "${group}" ]; then
        echo "You must enter a valid group."
    fi
done

```

```

else
    for i in ${groups}; do
        if [ "${i}" == "${group}" ]; then
            # valid group found
            break 2;
        fi
    done
    echo "You entered an invalid group."
fi
echo
done

echo "Creating user"

ncs-maapi --create "/aaa:aaa/authentication/users/user${user}"
ncs-maapi --set "/aaa:aaa/authentication/users/user${user}/password" \
    "${pass1}"

echo "Setting home directory to: /homes/${user}"
ncs-maapi --set "/aaa:aaa/authentication/users/user${user}/homedir" \
    "/homes/${user}"

echo "Setting ssh key directory to: /homes/${user}/ssh_keydir"
ncs-maapi --set "/aaa:aaa/authentication/users/user${user}/ssh_keydir" \
    "/homes/${user}/ssh_keydir"

ncs-maapi --set "/aaa:aaa/authentication/users/user${user}/uid" "1000"
ncs-maapi --set "/aaa:aaa/authentication/users/user${user}/gid" "100"

echo "Adding user to the ${group} group."
gusers=`ncs-maapi --get "/nacm/groups/group${group}/user-name"`

for i in ${gusers}; do
    if [ "${i}" == "${user}" ]; then
        echo "User already in group"
        exit 0
    fi
done

ncs-maapi --set "/nacm/groups/group${group}/user-name" "${gusers} ${user}"

```

Calling `$NCS_DIR/examples.ncs/getting-started/using-ncs/7-scripting/scripts/command/echo.sh` with the argument `--command` produces a command section and a couple of param sections:

```

$ ./echo.sh --command
begin command
  modes: oper
  styles: c i j
  cmdpath: my script echo
  help: Display a line of text
end

begin param
  name: nolf
  type: void
  presence: optional
  flag: -n
  help: Do not output the trailing newline
end

begin param

```

```

name: file
presence: optional
flag: -f
help: Redirect output to file
end

begin param
  presence: mandatory
  words: any
  help: String to be displayed
end

```

In the complete example `$NCS_DIR/examples.ncs/getting-started/using-ncs/7-scripting` there is a README file and a simple command script `scripts/command/echo.sh`.

## Policy scripts

Policy scripts are invoked at validation time, before a change is committed. A policy script can reject the data, accept it, or accept it with a warning. If a warning is produced, it will be displayed for interactive users (e.g. through the CLI or Web UI). The user may choose to abort or continue to commit the transaction.

Policy scripts are typically assigned to individual leafs or containers. In some cases it may be feasible to use a single policy script, e.g. on the top level node of the configuration. In such a case, this script is responsible for the validation of all values and their relationships throughout the configuration.

All policy scripts are invoked on every configuration change. The policy scripts can be configured to depend on certain subtrees of the configuration, which can save time but it is very important that all dependencies are stated and also updated when the validation logic of the policy script is updated. Otherwise an update may be accepted even though a dependency should have denied it.

There can be multiple dependency declarations for a policy script. Each declaration consists of a dependency element specifying a configuration subtree that the validation code is dependent upon. If any element in any of the subtrees is modified, the policy script is invoked. A subtree is specified as an absolute path.

If there are no declared dependencies, the root of the configuration tree (`/`) is used, which means that the validation code is executed when any configuration element is modified. If dependencies are declared on a leaf element, an implicit dependency on the leaf itself is added.

Each policy script must handle the argument `--policy` and, when invoked, write a `policy` section to `stdout`. The script must also perform the actual validation when invoked with the argument `--keypath`.

## Policy section

The following settings can be used to configure a policy script:

<code>keypath</code>	Mandatory. Keypath is a path to a node in the configuration data tree. The policy script will be associated with this node. The path must be absolute. A keypath can for example be <code>/devices/device/c0</code> . The script will be invoked if the configuration node, referred to by the keypath, is changed or if any node in the subtree under the node (if the node is a container or list) is changed.
<code>dependency</code>	Declaration of a dependency. The dependency must be an absolute keypath. Multiple dependency settings can be declared. Default is <code>/</code> .

priority	An optional integer parameter specifying the order policy scripts will be evaluated, in order of increasing priority, where lower value is higher priority. The default priority is 0.
call	This optional setting can only be used if the associated node, declared as <code>keypath</code> , is a list. If set to <code>once</code> , the policy script is only called once even though there exists many list entries in the data store. This is useful if we have a huge amount of instances or if values assigned to each instance have to be validated in comparison with its siblings. Default is <code>each</code> .

A policy that will be run for every change on or under `/devices/device`.

```
begin policy
  keypath: /devices/device
  dependency: /devices/global-settings
  priority: 4
  call: each
end
```

## Validation

When NSO has come to the conclusion that the policy script should be invoked to perform its validation logic, the script is invoked with the option `--keypath`. If the registered node is a leaf, its value will be given with the `--value` option. For example `--keypath /devices/device/c0` or if the node is a leaf `--keypath /devices/device/c0/address --value 127.0.0.1`.

Once the script has performed its validation logic it must exit with a proper status. The following exit statuses are valid:

- 0 Validation ok. Vote for commit.
- 1 When the outcome of the validation is dubious it is possible for the script to issue a warning message. The message is extracted from the script output on stdout. An interactive user has the possibility to choose to abort or continue to commit the transaction. Non-interactive users automatically vote for commit.
- 2 When the validation fails it is possible for the script to issue an error message. The message is extracted from the script output on stdout. The transaction will be aborted.

## Full policy example

A policy denying changes the configured `trace-dir` for a set of devices it can use the `check_dir.sh` script.

```
#!/bin/sh

usage_and_exit() {
  cat << EOF
Usage: $0 -h
      $0 --policy
      $0 --keypath <keypath> [--value <value>]

  -h                display this help and exit
  --policy          display policy configuration and exit
  --keypath <keypath> path to node
  --value <value>    value of leaf
}
```

Return codes:

- 0 - ok
- 1 - warning message is printed on stdout

```

    2 - error message    is printed on stdout
EOF
    exit 1
}

while [ $# -gt 0 ]; do
    case "$1" in
        -h)
            usage_and_exit
            ;;
        --policy)
            cat << EOF
begin policy
    keypath: /devices/global-settings/trace-dir
    dependency: /devices/global-settings
    priority: 2
    call: each
end
EOF
            exit 0
            ;;
        --keypath)
            if [ $# -lt 2 ]; then
                echo "<ERROR> --keypath <keypath> - path omitted"
                usage_and_exit
            else
                keypath=$2
                shift
            fi
            ;;
        --value)
            if [ $# -lt 2 ]; then
                echo "<ERROR> --value <value> - leaf value omitted"
                usage_and_exit
            else
                value=$2
                shift
            fi
            ;;
        *)
            usage_and_exit
            ;;
    esac
    shift
done

if [ -z "${keypath}" ]; then
    echo "<ERROR> --keypath <keypath> is mandatory"
    usage_and_exit
fi

if [ -z "${value}" ]; then
    echo "<ERROR> --value <value> is mandatory"
    usage_and_exit
fi

orig="./logs"
dir=${value}
# dir=`ncs-maapi --get /devices/global-settings/trace-dir`
if [ "${dir}" != "${orig}" ]; then
    echo "/devices/global-settings/trace-dir: must retain it original value (${orig})"
    exit 2

```

```
fi
```

Trying to change that parameter would result in an aborted transaction

```
admin@ncs(config)# devices global-settings trace-dir ./testing
admin@ncs(config)# commit
Aborted: /devices/global-settings/trace-dir: must retain it original
value (./logs)
```

In the complete example \$NCS\_DIR/examples.ncs/getting-started/using-ncs/7-scripting/ there is a README file and a simple policy script scripts/policy/check\_dir.sh.

## Post-commit scripts

Post-commit scripts are run when a transaction has been committed, but before any locks have been released. The transaction hangs until the script has returned. The script cannot change the outcome of the transaction. Post-commit scripts can for example be used for logging, sending external events etc. The scripts run as the same user id as NSO.

The script is invoked with `--post-commit` at script (re)load. In future releases it is possible that the `post-commit` section will be used for control of post-commit scripts behavior.

At post-commit, the script is invoked without parameters. In that context the script may make use of the environment variables `NCS_MAAPI_USID` and `NCS_MAAPI_THANDLE` in order to attach to the active (read-only) transaction.

This makes it simple to make use of the `ncs-maapi` command. Especially the command `ncs-maapi --keypath-diff` / may turn out to be useful, as it provides a listing of all updates within the transaction on a format that is easy to parse.

## Post-commit section

All post-commit scripts must be able to handle the argument `--post-commit` and, when invoked, write an empty `post-commit` section to stdout:

```
begin post-commit
end
```

## Full post-commit example

Assume the administrator of a system would want to have a mail each time a change is performed on the system, a script such as `mail_admin.sh`:

```
#!/bin/bash

set -e

if [ $# -gt 0 ]; then
    case "$1" in
        --post-commit)
            cat &lt;&lt; EOF
begin post-commit
end
EOF
            exit 0
            ;;
        *)
            echo
            echo "Usage: $0 [--post-commit]"
    esac
fi
```

```

        echo
        echo "    --post-commit Mandatory for post-commit scripts"
        exit 1
    ;;
esac
else
    file="mail_admin.log"
    NCS_DIFF=$(ncs-maapi --keypath-diff /)
    mail -s "NCS Mailer" admin@example.com <<<EOF
AutoGenerated mail from NCS

$NCS_DIFF
EOF
fi

```

If the admin then loads this script

```

admin@ncs# script reload debug
$NCS_DIR/examples.ncs/getting-started/using-ncs/1-simulated-cisco-ios/scripts:
ok
    post-commit:
        mail_admin.sh: new
--- Output from
$NCS_DIR/examples.ncs/getting-started/using-ncs/1-simulated-cisco-ios/scripts/post-commit/mai
--post-commit ---
1: begin post-commit
2: end
3:
---
admin@ncs# config
Entering configuration mode terminal
admin@ncs(config)# devices global-settings trace-dir ./again
admin@ncs(config)# commit
Commit complete.

```

This configuration change will produce an email to admin@example.com with subject NCS Mailer and body

```

AutoGenerated mail from NCS
value set : /devices/global-settings/trace-dir

```

In the complete example \$NCS\_DIR/examples.ncs/getting-started/using-ncs/7-scripting/ there is a README file and a simple post-commit script scripts/post-commit/show\_diff.sh.







## CHAPTER 8

# Compliance reporting

---

- [Introduction, page 145](#)
- [Creating compliance report definitions, page 145](#)
- [Running compliance reports, page 148](#)

## Introduction

When the network configuration is broken there is a need to gather information and verify the network.

NSO has numerous functions to show different aspects of such a network configuration verification. However, to simplify this task, the compliance reporting can assemble information using a selection of these NSO functions and present the resulting information in one report. The aim for this report is to answer two fundamental questions:

- Who has done what?
- Is the network correctly configured?

What defines a correctly configured network? Where is the authoritative configuration kept? Naturally, NSO, with the configurations stored in CDB, is the authority. Checking the live devices against the NSO stored device configuration is a fundamental part of compliance reporting. Compliance reporting can also be based on one or a number of stored device templates which the live devices are compared against. The compliance reports can also be a combination of both approaches.

Compliance reporting can be configured to check the current situation or checking historic events, or both. To assemble historic events, rollback files and audit logs are used. Therefore this functionality must have been enabled in NSO prior to report execution or else no history view can be presented.

The reports can be formatted either as text, html or docbook xml format. The intention of the docbook format is that the user can take the report and by further post-processing create reports formatted by own choice, for instance PDF using Apache FOP.

## Creating compliance report definitions

It is possible to create several named compliance report definitions. Each named report defines the devices, services and/or templates that should be part of the network configuration verification.

Let us walk through a simple compliance report definition. This example is based on the `examples.ncs/service-provider/mps-vpn` example. For the details of the included services and devices in this example see the README file.

First of all the reports has a name which is key in the *report* list. Furthermore the report has a *device-check* and a *service-check* container for specifying devices and services to check. The *compare-template* list allows for specifying templates to compare device configurations against. A report definition can specify all containers at the same time:

```
$ ncs_cli -u admin -C
admin connected from 127.0.0.1 using console on ncs
ncs# config
Entering configuration mode terminal
ncs(config)# compliance reports report gold-check
Possible completions:
  compare-template  Diff devices against templates
  device-check      Report on devices
  run               Run this compliance report
  service-check     Report on services out of sync
<cr>
```

We will first use the *device-check* container to specify which devices to check. Devices can be defined in one of 4 different ways:

- *all-devices* - Check all defined devices
- *device-group* - Specified list of device groups
- *device* - Specified list of devices
- *select-devices* - Specified by an XPath expression

Furthermore, for a *device-check* the behavior or the verification can be specified. The default behavior for device verification is the following:

- To request a check-sync action to verify that the device is currently in sync. This behavior is controlled by the leaf *current-out-of-sync* (default true).
- To scan history (i.e. logs) for failed check-sync events and report these. This behavior is controlled by the leaf *historic-out-of-sync* (default true).
- To scan commit log (i.e. rollback files) for changes on the devices and report these. This behavior is controlled by the leaf *historic-changes* (default true).

```
ncs(config)# compliance reports report gold-check
ncs(config-report-gold-check)# device-check
Possible completions:
  all-devices          Report on all devices
  current-out-of-sync  Should current check-sync action be performed?
  device               Report on specific devices
  device-group         Report on specific device groups
  historic-changes     Include commit log events from within the report
                      interval
  historic-out-of-sync Include detected devices out of sync events from
                      within the report interval
  select-devices       Report on devices selected by an XPath expression
<cr>
```

We will choose the default behaviour and check all devices:

```
ncs(config-report-gold-check)# device-check all-devices
```

In our example we also use the *service-check* container to specify which services to check. Services can be defined in one of 3 ways:

- *all-services* - Check all defined services
- *service* - Specified list of services
- *select-services* - Specified by an XPath expression

Also for the *service-check* the verification behavior can be specified. The default behavior for service verification is the following:

- To request a check-sync action to verify that the service is currently in sync. This behavior is controlled by the leaf *current-out-of-sync* (default true).
- To scan history (i.e. logs) for failed check-sync events and report these. This behavior is controlled by the leaf *historic-out-of-sync* (default true).
- To scan commit log (i.e. rollback files) for changes on the services and report these. This behavior is controlled by the leaf *historic-changes* (default true).

```

ncs(config-report-gold-check)# service-check
Possible completions:
  all-services          Report on all services
  current-out-of-sync   Should current check-sync action be performed?
  historic-changes      Include commit log events from within the report
                        interval
  historic-out-of-sync  Include detected services out of sync events from
                        within the report interval
  select-services       Report on services selected by an XPath expression
  service              Report on specific services
<cr>

```

In our report we choose the default behavior and to check the l3vpn service:

```

ncs(config-report-gold-check)# service-check select-services /l3vpn:vpn/l3vpn:l3vpn
ncs(config-report-gold-check)# commit
Commit complete.
ncs(config-report-gold-check)# show full-configuration
compliance reports report gold-check
device-check all-devices
service-check select-services /l3vpn:vpn/l3vpn:l3vpn
!

```

Our next example will illustrate how to add a device template in the compliance report. This template will be used to compare some part of the device configuration against. First we define the device template:

```

ncs(config-report-gold-check)# top
ncs(config)# devices template gold-conf config
ncs(config-config)# ios:snmp-server community ${COMMUNITY}
ncs(config-community-${COMMUNITY})# commit
Commit complete.
ncs(config-community-${COMMUNITY})# show full-configuration
devices template gold-conf
config
  ios:snmp-server community ${COMMUNITY}
!
!
!

```

We will also need a device group which will be used later in the report definition. For the sake of simplicity, in this example we will just choose some of the ce devices:

```

ncs(config-community-${COMMUNITY})# top
ncs(config)# devices device-group mygrp device-name
(list): [ce0 ce1 ce2 ce3]
ncs(config-device-group-mygrp)# commit
Commit complete.

```

Now we add the template to the already defined report gold-check. An entry in the *compare-template* list contain the combination of a template and a device-group which imply that the template will be applied to all devices in the device group and the difference (if any) will be reported as an compliance violation.

Note, that no data will be changed on the device. Since the device template can contain variables, each *compare-template* also has a *variable* list.

In our example report we use the *gold-conf* template and the *mygrp* group:

```
ncs(config-device-group-mygrp)# top
ncs(config)# compliance reports report gold-check
ncs(config-report-gold-check)# compare-template gold-conf mygrp
```

Since the *gold-conf* template has a variables we will set the values for this variable in the report:

```
ncs(config-compare-template-gold-conf/mygrp)# variable COMMUNITY
ncs(config-variable-COMMUNITY)# value 'public'
ncs(config-variable-COMMUNITY)# show configuration
compliance reports report gold-check
  compare-template gold-conf mygrp
    variable COMMUNITY
      value 'public'
  !
!
ncs(config-variable-COMMUNITY)# commit
Commit complete.
```

## Running compliance reports

Compliance reporting is a read-only operation. When running a compliance report the result is stored in a file located in a sub directory *compliance-reports* under the NSO state directory. NSO has operational data for managing this report storage which makes it possible to list existing reports. Here is an example of such report listing:

```
ncs(config-variable-COMMUNITY)# top
ncs(config)# exit
ncs# show compliance report-results
compliance report-results report 1
  name          gold-check
  title         "GOLD NW 1"
  time          2015-02-04T18:48:57+00:00
  who           admin
  compliance-status violations
  location       http://.../report_1_admin_1_2015-2-4T18:48:57:0.xml
compliance report-results report 2
  name          gold-check
  title         "GOLD NW 2"
  time          2015-02-04T18:51:48+00:00
  who           admin
  compliance-status violations
  location       http://.../report_2_admin_1_2015-2-4T18:51:48:0.text
compliance report-results report 3
  name          gold-check
  title         "GOLD NW 3"
  time          2015-02-04T19:11:43+00:00
  who           admin
  compliance-status violations
  location       http://.../report_3_admin_1_2015-2-4T19:11:43:0.text
```

There is also a *remove* action to remove report results (and the corresponding file):

```
ncs# compliance report-results report 2.3 remove
ncs# show compliance report-results
compliance report-results report 1
  name          gold-check
```

```

title          "GOLD NW 1"
time           2015-02-04T18:48:57+00:00
who            admin
compliance-status violations
location       http://.../report_1_admin_1_2015-2-4T18:48:57:0.xml

```

When running the report there are a number of parameters that can be specified with the specific *run* action.

The parameters that are possible to specify for a report *run* action are:

- *title* - The title in the resulting report
- *from* - The date and time from which the report should start the information gathering. If not set, the oldest available information is implied.
- *to* - The date and time to where the information gathering should stop. If not set, the current date and time is implied. If set, no new check-syncs of devices and/or services will be attempted.
- *outformat* - One of xml, html or text. If xml is specified the report will be formatted using the docbook schema.

We will request a report run with a title and formatted as text:

```

nscs# compliance reports report gold-check run
Possible completions:
  from      Audit log and check-sync events from this time
  outformat  The format of this report output file, and therefore also the
             file suffix
  title      Report name + title in report header
  to         Audit log and check-sync events from this time
  |          Output modifiers
<cr>

```

In the above command the report was run without a *from* or a *to* argument. This implies that historical information gathering will be based on all available information. This includes information gathered from rollback files and audit logs.

When a *from* argument is supplied to a compliance report run action, this implies that only historical information younger than the *from* date and time is checked.

```

nscs# compliance reports report gold-check run \
> title "First check" from 2015-02-04T00:00:00

```

When a *to* argument is supplied this implies that historic information will be gathered for all logged information up to the date and time of the *to* argument.

```

nscs# compliance reports report gold-check run \
> title "Second check" to 2015-02-05T00:00:00

```

The *from* and a *to* arguments can be combined to specify a fixed historic time interval.

```

nscs# compliance reports report gold-check run \
> title "Third check" from 2015-02-04T00:00:00 to 2015-02-05T00:00:00

```

When a compliance report is run the action will respond with a flag indicating if any discrepancies were found. Also it reports how many devices and services have been verified in total by the report.

```

nscs# compliance reports report gold-check run \
> title "Fourth check" outformat text
id 7
compliance-status violations
info Checking 17 devices and 2 services
location http://.../report_7_admin_1_2015-2-4T20:42:45:0.text

```

Below is an example of a compliance report result (in text format):

#### Example 48. Compliance report result

```
$ cat ./state/compliance-reports/report_7_admin_1_2015-2-4T20\:42\:45\:0.text
reportcookie : g2gCbQAAAAtGaWZ0aCBjaGVja20AAAAKZ29sZC1jaGVjaw==
```

Compliance report : Fourth check

```
Publication date : 2015-2-4 20:42:45
Produced by user : admin
```

Chapter : Summary

```
Compliance result titled "Fifth check" defined by report "gold-check"
Resulting in violations
Checking 17 devices and 2 services
Produced 2015-2-4 20:42:45
From : Oldest available information
To : 2015-2-4 20:42:45
```

Devices out of sync

```
p0
    check-sync unsupported for device

p1
    check-sync unsupported for device

p2
    check-sync unsupported for device

p3
    check-sync unsupported for device

pe0
    check-sync unsupported for device

pe1
    check-sync unsupported for device

pe3
    check-sync unsupported for device
```

Services out of sync

```
/vpn/l3vpn{ford}

Historical out of sync events
4-Feb-2015::17:24:09.060Host1 confd[62635]:
audit user: admin/25 NCS service-out-of-sync
Service '/vpn/l3vpn{ford}' Info ''

4-Feb-2015::18:49:02.223Host1 confd[62635]:
```

```
audit user: admin/29 NCS service-out-of-sync
Service '/vpn/l3vpn{ford}' Info ''
```

```
/vpn/l3vpn{volvo}
```

```
Historical out of sync events
4-Feb-2015::17:24:10.472Host1 confd[62635]:
audit user: admin/25 NCS service-out-of-sync
Service '/vpn/l3vpn{volvo}' Info ''
```

```
4-Feb-2015::18:49:03.623Host1 confd[62635]:
audit user: admin/29 NCS service-out-of-sync
Service '/vpn/l3vpn{volvo}' Info ''
```

Template discrepancies

gold-conf

```
Discrepancies in device
ce0
ce1
ce2
ce3
```

Chapter : Details

Commit list

SeqNo	ID	User	Client	Timestamp	Label	Comment
0	10031	admin	cli	2015-02-04 20:31:42		
1	10030	admin	cli	2015-02-04 20:03:41		
2	10029	admin	cli	2015-02-04 19:54:40		
3	10028	admin	cli	2015-02-04 19:45:20		
4	10027	admin	cli	2015-02-04 18:38:05		

Service commit changes

No service data commits saved for the time interval

Device commit changes

No device data commits saved for the time interval

Service differences

No service data diffs found

Template discrepancies details

gold-conf

```
Device ce0

  config {
    ios:snmp-server {
+     community public {
+     }
    }
  }

Device ce1

  config {
    ios:snmp-server {
+     community public {
+     }
    }
  }

Device ce2

  config {
    ios:snmp-server {
+     community public {
+     }
    }
  }

Device ce3

  config {
    ios:snmp-server {
+     community public {
+     }
    }
  }
```





## CHAPTER 9

# NSO Packages

- [Overview, page 153](#)
- [Listing Packages, page 153](#)

## Overview

NSO Packages contain data models and code for a specific function. It might be a NED for a specific device, a service application like MPLS VPN, a WebUI customization package etc. Packages can be added, removed and upgraded in run-time.

## Listing Packages

The currently loaded packages can be viewed with the following command:

### Example 49. Show Currently Loaded Packages

```
admin@ncs# show packages
packages package cisco-ios
package-version 3.0
description      "NED package for Cisco IOS"
ncs-min-version [ 3.0.2 ]
directory        ./state/packages-in-use/1/cisco-ios
component upgrade-ned-id
  upgrade java-class-name com.tailf.packages.ned.ios.UpgradeNedId
component cisco-ios
  ned cli ned-id cisco-ios
  ned cli java-class-name com.tailf.packages.ned.ios.IOSNedCli
  ned device vendor Cisco
NAME            VALUE
-----
show-tag interface

build-info date "2015-01-29 23:40:12"
build-info file ncs-3.4_HEAD-cisco-ios-3.0.tar.gz
build-info arch linux.x86_64
build-info java "compiled Java class data, version 50.0 (Java 1.6)"
build-info package name cisco-ios
build-info package version 3.0
build-info package ref 3.0
build-info package sha1 a8f1329
build-info ncs version 3.4_HEAD
build-info ncs sha1 81a1e4c
```

```
build-info dev-support version 0.99
build-info dev-support branch e4d3fa7
build-info dev-support sha1 e4d3fa7
oper-status up
```

Thus the above command shows that NSO currently has only one package loaded, the NED package for Cisco IOS. The output includes the name and version of the package, the minimum required NSO version, the Java components included, package build details, and finally the operational status of the package. The operational status is of particular importance - if it is anything other than up, it indicates that there was a problem with the loading or the initialization of the package. In this case an item `error-info` may also be present, giving additional information about the problem. To show only the operational status for all loaded packages, this command can be used:

```
admin@nbs# show packages package * oper-status
packages package cisco-ios
oper-status up
```



## CHAPTER 10

# Life-cycle Operations - how to manipulate existing services and devices

- [Commit flags and device & service actions](#) , page 155
- [Commit Flags](#), page 155
- [Device Actions](#), page 159
- [Service Actions](#), page 163

## Commit flags and device & service actions

Devices and services are the most important entities in NSO. Once created they may be manipulated in several different ways. The three main categories of operations that affect the state of services and devices are

Commit flags	Commit flags modifies the transaction semantics
Device actions	Explicit actions that modifies the devices
Service actions	Explicit actions that modifies the services

The purpose of this chapter is more of a quick reference guide, an enumeration of commonly used commands. The context in which these commands should be used is found in other parts of the documentation.

## Commit Flags

Commit flags may be present when issuing a **commit** command:

```
commit <flag>
```

Some of these flags may be configured to apply globally for all commits, under `/devices/global-settings`, or per device profile, under `/devices/profiles`.

Some of the more important flags are:

<i>and-quit</i>	Exit to (CLI operational mode) after commit.
<i>check</i>	Validate the pending configuration changes. Equivalent to <b>validate</b> command (See <a href="#">Chapter 2, The NSO CLI</a> ).
<i>comment / label</i>	Add a commit comment/label visible in compliance reports, rollback files etc.

*dry-run*

Validate and display the configuration changes but do not perform the actual commit. *Neither* CDB *nor* the devices are affected. Instead the effects that would have taken place is shown in the returned output. The output format can be set with the *outformat* option. Possible output formats are: *xml*, *cli* and *native*.

The *xml* format displays all changes in the whole data model. The changes will be displayed in NETCONF XML edit-config format, i.e., the edit-config that would be applied locally (at NCS) to get a config that is equal to that of the managed device.

The *cli* format displays all changes in the whole data model. The changes will be displayed in CLI curly bracket format.

The *native* format displays only changes under `/devices/device/config`. The changes will be displayed in native device format.

The *native* format can be used with the *reverse* option to display the device commands for getting back to the current running state in the network if the commit is successfully executed. Beware that if any changes are done later on the same data the reverse device commands returned are invalid.

*no-networking*

Validate the configuration changes, update the CDB but *do not* update the actual devices.

This is equivalent to first setting the admin-state to southbound locked, then issuing a standard commit. In both cases the configuration changes are prevented from being sent to the actual devices.

**Warning**


---

If the commit implies changes, it will make the device out-of-sync.

---

*no-out-of-sync-check*

The **sync-to** command can then be used to push the change to the network. Commit even if the device is out-of-sync. This can be used in scenarios where you know that the change you are doing is not in conflict with what is on the device and do not want to perform the action **sync-from** first. Verify result by using the action **compare-config**

**Warning**


---

The device's sync state is assumed to be unknown after such commit and the stored last-transaction-id value is cleared.

---

*no-overwrite*

NSO will check that the data that should be modified has not changed on the device compared to NSO's view of the data. This is a fine-granular sync check; NSO verifies that NSO and the device is in sync regarding the data that will be modified. If they are not in sync, the transaction is aborted.

This parameter is particularly useful in brown field scenarios where the device always is out of sync due to being directly modified by operators or other management systems.

**Warning**

The device's sync state is assumed to be unknown after such commit and the stored last-transaction-id value is cleared.

*no-revision-drop*

Fail if one or more devices have obsolete device models.

When NSO connects to a managed device the version of the device data model is discovered. Different devices in the network might have different versions. When NSO is requested to send configuration to devices, NSO defaults to drop any configuration that only exists in later models than the device supports. This flag forces NSO to never silently drop any data set operations towards a device.

*no-deploy*

Commit without invoking the service create method, i.e. write the service instance data without activating the service(s). The service(s) can later be re-deployed to write the changes of the service(s) to the network.

*reconcile*

Reconcile the service data. All data which existed before the service was created will now be owned by the service. When the service is removed that data will also be removed. In technical terms the reference count will be decreased by one for everything which existed prior to the service.

If manually configured data exists below in the configuration tree that data is kept unless the option *discard-non-service-config* is used.

*use-lsa*

Force handling of the LSA nodes as such. This flag tells NSO to propagate applicable commit flags and actions to the LSA nodes without applying them on the upper NSO node itself. The commit flags affected are *dry-run*, *no-networking*, *no-out-of-sync-check*, *no-overwrite* and *no-revision-drop*.

*no-lsa*

Do not handle any of the LSA nodes as such. These nodes will be handled as any other device.

*commit-queue*

Commit through the commit queue ([the section called “Commit Queue”](#)). While the configuration change is committed to CDB immediately it is not committed to the actual device but rather queued for eventual commit in order to increase transaction throughput.

This enables use of the commit queue feature for individual **commit** commands without enabling it by default.

Possible operation modes are: *async*, *sync* and *bypass*.

If the *async* mode is set the operation returns successfully if the transaction data has been successfully placed in the queue.

The *sync* mode will cause the operation to not return until the transaction data has been sent to all devices, or a timeout occurs. If the timeout occurs the transaction data stays in the queue and the operation returns successfully. The timeout value can be specified with the *timeout* or *infinity* option. By default the timeout value is determined by what is configured in `/devices/global-settings/commit-queue/sync`.

The *bypass* mode means that if `/devices/global-settings/commit-queue/enabled-by-default` *true* the data in this transaction will bypass the commit queue. The data will be written directly to the devices. The operation will still fail if the commit queue contains

one or more entries affecting the same device(s) as the transaction to be committed.

In addition the *commit-queue* flag has a number of other useful options that affects the resulting queue item.

The *tag* option sets a user defined opaque tag that is present in all notifications and events sent referencing the queue item.

The *block-others* option will cause the resulting queue item to block subsequent queue items which use any of the devices in this queue item, from being queued.

The *lock* option will place a lock on the resulting queue item. The queue item will not be processed until it has been unlocked, see the actions *unlock* and *lock* in `/devices/commit-queue/queue-item`. No following queue items, using the same devices, will be allowed to execute as long as the lock is in place.

The *atomic* option sets the atomic behaviour of the resulting queue item. If this is set to *false*, the devices contained in the resulting queue item can start executing if the same devices in other non-atomic queue items ahead of it in the queue are completed. If set to *true*, the atomic integrity of the queue item is preserved.

Depending on the selected *error-option* NSO will store the reverse of the original transaction to be able to undo the transaction changes and get back to the previous state. This data is stored in the `/devices/commit-queue/completed` tree from where it can be viewed and invoked with the **rollback** action. When invoked the data will be removed. Possible values are: *continue-on-error*, *rollback-on-error* and *stop-on-error*. The *continue-on-error* value means that the commit queue will continue on errors. No rollback data will be created. The *rollback-on-error* value means that the commit queue item will roll back on errors. The commit queue will place a lock on the failed queue item, thus blocking other queue items with overlapping devices to be executed. The **rollback** action will then automatically be invoked when the queue item has finished its execution. The lock will be removed as part of the rollback. The *stop-on-error* means that the commit queue will place a lock on the failed queue item, thus blocking other queue items with overlapping devices to be executed. The lock must then either manually be released when the error is fixed or the **rollback** action under `/devices/commit-queue/completed` be invoked.



#### Note

Read about error recovery in [the section called “Commit Queue”](#) for a more detailed explanation.

*wait-device*

Take device locks before entering transaction critical section. The device locks here should be understood to be internal locks in NSO, so the device itself is not locked. If the device locks are held by someone else, wait for them to become available. The timeout applied in this case is the same as used to wait for the transaction lock.

Normally the device locks are taken automatically inside the transaction critical section, because in a typical service transaction we do not know the affected devices before the service code is executed. When taking the device locks inside transaction critical section, it is not possible to wait for lock, so in case the lock is not available the transaction is aborted.

This parameter allows to specify the devices expected to be affected by the transaction so they can be pre-locked before entering the transaction critical section. This allows to wait for device locks. This is useful in cases when other actions holding the device lock may be on-going at the same time and the desired behaviour is to wait for these actions to complete rather than abort the transaction. Examples of such actions are: **sync-from**, **partial-sync-from**, **check-sync**, **sync-to**, **compare-config**.

Similarly, when used with a commit through commit queue, this parameter allows to wait for queue items with *block-others* flag. For example, a queue item with *block-others* flag is created by actions such as **sync-from** and **partial-sync-from**.

If the transaction involves other devices than specified by this parameter, then the lock still needs to be taken on these additional devices, which is done inside transaction critical section and may fail if the device lock for the additional devices is already held by someone else.

Currently this parameter only takes effect in a single-node scenario and *not* in an LSA cluster.

*trace-id*

Use the provided trace id as part of the log messages emitted while processing. If no trace id is given, NSO is going to generate and assign a trace id to the processing.

All commands in NSO can also have pipe commands. A useful pipe command for commit is **details**:

```
ncs% commit | details
```

This will give feedback on the steps performed in the commit.

When working with templates there is a pipe command **debug** which can be used to troubleshoot templates. To enable debugging on all templates use:

```
ncs% commit | debug template
```

When configuring using many templates the debug output can be overwhelming. For this reason there is an option to only get debug information for one template, in this example a template named l3vpn:

```
ncs% commit | debug template l3vpn
```

## Device Actions

Actions for devices can be performed globally on the `/devices` path, and for individual devices on `/devices/device/name`. Many actions are also available on device-groups as well as device ranges.

### add-capability

This action adds a capability to the list of capabilities. If `uri` is specified, then it is parsed as YANG capability string and `module`, `revision`, `feature` and `deviation` parameters are derived from the string. If `module` is specified, then the namespace is looked up in the list of loaded namespaces and capability string constructed automatically. If the `module` is specified and the

<b>apply-template</b>	<p>attempt to look it up failed, then the action does nothing. If <code>module</code> is specified or can be derived from capability string, then the <code>module</code> is also added/replaced in the list of modules. This action is only intended to be used for pre-provisioning: it is not possible to override capabilities and modules provided by the NED implementation using this action.</p> <p>Take a named template and apply its configuration here.</p> <p>If the <code>accept-empty-capabilities</code> parameter is included, the template is applied to devices even if the capability of the device is unknown.</p>
<b>check-sync</b>	<p>This action will behave differently depending on if it is invoked with a transaction or not. When invoked with a transaction (such as via the CLI) it will apply the template to it and leave it to the user to commit or revert the resulting changes. If invoked without a transaction (for example when invoked via RESTCONF), the action will automatically create one and commit the resulting changes. An error will be returned and the transaction aborted if the template failed to apply on any of the devices.</p> <p>Check if the NSO copy of the device configuration is in sync with the actual device configuration, using device-specific mechanisms. This operation is usually cheap as it only compares a signature of the configuration from the device rather than comparing the entire configuration.</p> <p>Depending on the device the signature is implemented as a transaction-id, timestamp, hash-sum or not at all. The capability must be supported by the corresponding NED. The output might say unsupported, and then the only way to perform this would be to do a full <b>compare-config</b> command.</p>
<b>check-yang-modules</b>	<div data-bbox="678 1171 716 1213"></div> <div data-bbox="641 1232 716 1257"><b>Warning</b></div> <p>As some NEDs implements the signature as an hash-sum of the entire configuration, this operation might for some devices be just as expensive as performing a full <b>compare-config</b> command.</p>
<b>clear-trace</b> <b>compare-config</b>	<p>Check if the device YANG modules loaded by NSO have revisions that are compatible with the ones reported by the device.</p> <p>This can indicate for example that the device has a YANG module of later revision than the corresponding NED.</p> <p>Clear all trace files for all active traces for all managed devices.</p> <p>Retrieve the config from the device and compare to the NSO locally stored copy.</p>
<b>connect</b>	<p>Set up a session to the unlocked device. This is not used in real operational scenarios. NSO automatically establishes connections on demand. However it is useful for test purposes when installing new NEDs, adding devices etc.</p> <p>When a device is southbound locked, all southbound communication is turned off. The <code>override-southbound-locked</code> flag overrides the southbound lock for connection attempts. Thus, this is</p>



**copy-capabilities**

a way to update the capabilities including revision information for a managed device although the device is southbound locked.

This action copies the list of capabilities and the list of modules from another device or profile. When used on a device, this action is only intended to be used for pre-provisioning: it is not possible to override capabilities and modules provided by the NED implementation using this action.

**Note**

This action overwrites existing list of capabilities.

**delete-config**

Delete the device configuration in NSO without executing the corresponding delete on the managed device.

**disconnect**

Close all sessions to the device.

**fetch-ssh-host-keys**

Retrieve the SSH host keys from all devices, or all devices in the given device group, and store them in each device's `ssh/host-key` list. Successfully retrieved new or updated keys are always committed by the action.

**find-capabilities**

This action populates the list of capabilities based on the configured `ned-id` for the device, if possible. NSO will look up the package corresponding to the `ned-id` and add all the modules from these packages to the list of device capabilities and list of modules. It is the responsibility of the caller to verify that the automatically populated list of capabilities matches actual device's capabilities. The list of capabilities can then be fine-tuned using **add-capability** and **capability/remove** actions. Currently this approach will only work for CLI and generic devices. This action is only intended to be used for pre-provisioning: it is not possible to override capabilities and modules provided by the NED implementation using this action.

**Note**

This action overwrites existing list of capabilities.

**instantiate-from-other-device**

Instantiate the configuration for the device as a copy of the configuration of some other already working device.

**load-native-config**

Load configuration data in native format into the transaction. This action is only applicable for devices with NETCONF, CLI and generic NEDs.

The action can load the configuration data either from a file in the local filesystem or as a string through the northbound client. If loading XML the data must be a valid XML document, either with a single namespace or wrapped in a config node with the `http://tailf.com/ns/config/1.0` namespace.

The `verbose` option can be used to show additional parse information reported by the NED. By default the behaviour is to merge the configuration that is applied. This can be changed by setting the `mode` option to `replace`. This will replace the entire device configuration.

This action will behave differently depending on if it is invoked with a transaction or not. When invoked with a transaction (such as via the CLI) it will load the configuration into it and leave it to the

<b>migrate</b>	<p>user to commit or revert the resulting changes. If invoked without a transaction (for example when invoked via RESTCONF), the action will automatically create one and commit the resulting changes.</p> <p>Change the NED identity and migrate all data. As a side-effect reads and commits the actual device configuration.</p> <p>The action reports what paths have been modified and the services affected by those changes. If the <code>verbose</code> option is used, all service instances are reported instead of just the service points. If the <code>dry-run</code> option is used, the action simply reports what it would do.</p>
<b>partial-sync-from</b>	<p>If the <code>no-networking</code> option is used, no southbound traffic is generated towards the devices. Only the device configuration in CDB is used for the migration. If used, NSO can not know if the device is in sync. To determine this, the <b>compare-config</b> or the <b>sync-from</b> action must be used.</p> <p>Synchronize parts of the devices' configuration by pulling from the network.</p>
<b>ping</b>	ICMP ping the device.
<b>scp-from</b>	<p>Secure copy file from the device.</p> <p>The <code>port</code> option specifies the port to connect to on the device. If this leaf is not configured, NSO will use the port for the management interface of the device.</p>
<b>scp-to</b>	<p>The <code>preserve</code> option preserves modification times, access times, and modes from the original file. This is not always supported by the device.</p> <p>Secure copy file to the device.</p> <p>The <code>port</code> option specifies the port to connect to on the device. If this leaf is not configured, NSO will use the port for the management interface of the device.</p>
<b>sync-from</b>	<p>The <code>preserve</code> option preserves modification times, access times, and modes from the original file. This is not always supported by the device.</p> <p>Synchronize the NSO copy of the device configuration by reading the actual device configuration. The change will be immediately committed to NSO.</p> <p>If the <code>dry-run</code> option is used, the action simply reports (in different formats) what it would do. The <code>verbose</code> option can be used to show additional parse information reported by the NED.</p>
<b>sync-to</b>	<p>Synchronize the device configuration by pushing the NSO copy to the device.</p>

**Note**

If you have any services that has created configuration on the device the corresponding service might be out-of-sync. Use the commands **check-sync** and **re-deploy** to reconcile this.

NSO pushes a minimal diff to the device. The diff is calculated by reading the configuration from the device and comparing with the configuration in NSO.

If the `dry-run` option is used, the action simply reports (in different formats) what it would do.

Some of the operations above can't be performed while the device is being committed to (or waiting in the commit queue). This is to avoid getting inconsistent data when reading the configuration. The `wait-for-lock` option in these specifies a timeout to wait for a device lock to be placed in the commit queue. The lock will be automatically released once the action has been executed. If the `no-wait-for-lock` option is specified, the action will fail immediately for the device if the lock is taken for the device or if the device is placed in the commit queue. The `wait-for-lock` and the `no-wait-for-lock` options are device settings as well, they can be set as a device profile, device and global setting. The `no-wait-for-lock` option is set in the global settings by default. If neither `wait-for-lock` and the `no-wait-for-lock` options are provided together with the action, the device setting is used.

## Service Actions

Service actions are performed on the service instance.

### **check-sync**

Check if the service has been undermined, i.e., if the service was to be re-deployed, would it do anything. This action will invoke the FASTMAP code to create the change set that is compared to the existing data in CDB locally. If `outformat` is boolean, `true` is returned if the service is in sync, i.e., a re-deploy would do nothing. If `outformat` is `cli`, `xml` or `native`, the changes that the service would do to the network if re-deployed are returned.

If configuration changes has been made out-of-band then **deep-check-sync** is needed to detect a out-of-sync condition.

The `deep` option is used to recursively **check-sync** stacked services. The `shallow` option only **check-sync** the topmost service.

### **deep-check-sync**

Check if the service has been undermined on the device itself. The action **check-sync** compares the output of the service code to what is stored in CDB locally. This action retrieves the configuration from the devices touched by the service and compares the forward diff set of the service to the retrieved data. This is thus a fairly heavy weight operation. As opposed to the **check-sync** action that invokes the FASTMAP code, this action re-applies the forward diff-set. This is the same output you see when inspecting the **get-modifications** operational field in the service instance.

If the device is in sync with CDB, the output of this action is identical to the output of the cheaper **check-sync** action.

### **get-modifications**

Returns the data the service modified, either in CLI curly bracket format, or NETCONF XML edit-config format. The modifications are shown as if the service instance was the only instance that modifies the data. This data is only available if the parameter `/services/global-settings/collect-forward-diff` is set to `true`.

If the parameter `reverse` is given the modifications needed to reverse the effect of the service is shown. The modifications are shown as if this service instance was the last service instance. This will be applied if the service is deleted. This data is always available.

**re-deploy**

The **deep** option is used to recursively **get-modifications** for stacked services. The **shallow** option only **get-modifications** for the topmost service.

Run the service code again, possibly writing the changes of the service to the network once again. There are several reasons for performing this operation such as:

- a **device sync-from** action has been performed in order to incorporate an out-of-band change.
- data referenced by the service has changed such as topology information, QoS policy definitions etc.

The **deep** option is used to recursively **re-deploy** stacked services. The **shallow** option only **re-deploy** the topmost service.

If the **dry-run** option is used, the action simply reports (in different formats) what it would do.

Use the option **reconcile** if the service should reconcile original data, i.e., take control of that data. This option acknowledges other services controlling the same data. All data which existed before the service was created will now be owned by the service. When the service is removed that data will also be removed. In technical terms the reference count will be decreased by one for everything which existed prior to the service. If manually configured data exists below in the configuration tree that data is kept unless the option **discard-non-service-config** is used.

**Note**

The action is idempotent. If no configuration diff exists then nothing needs to be done.

**Note**

The NSO general principle of minimum change applies.

**reactive-re-deploy**

This is a tailored **re-deploy** intended to be used in the reactive FASTMAP scenario. It differs from the ordinary **re-deploy** in that this action does not take any commit parameters.

This action will **re-deploy** the services as an shallow depth **re-deploy**. It will be performed with the same user as the original commit. Also, the commit parameters will be identical to the latest commit involving this service.

By default this action is asynchronous and returns nothing. Use the **sync** leaf to get synchronous behaviour and block until the service **re-deploy** transaction is committed. The **sync** leaf also means that the action will possibly return a commit result, such as commit queue id if any, or an error if the transaction failed.

**touch**

This action marks the service as changed.

Executing the action **touch** followed by a commit is the same as executing the action **re-deploy shallow**.

By using the action **touch** several re-deploys can be performed in the same transaction.

**un-deploy**

Undo the effects of the service instance but keep the service itself. The service can later be re-deployed. This is a means to deactivate a service, but keeping it in the system.





## CHAPTER 11

# The Web User Interface

---

- [Overview, page 167](#)
- [Using the Web UI, page 167](#)
- [Transactions and Commit, page 167](#)

## Overview

The NSO Web UI consists of a suit of web based applications. Each application has it's own distinct concern, for instance handle configuration, transaction handling, manage devices, manage services or monitor the system. The different applications can be accessed from the application hub, which is shown directly after authentication.

The Web UI is a mix of custom built applications and auto-rendering from the underlying device and service models. The latter gives the benefit that a Web UI is immediately updated when new devices or services are added to the system. So, say you add support for a new device vendor. Without any programming is the NSO Web UI capable of configuring those devices.

All modern web browsers are supported and no plug-ins are required. The interface is a pure JavaScript Client.

## Using the Web UI

The Web UI is available on port 8080 on the NSO server. The port can be changed in the `ncs.conf` file. A NSO user must exist.

More help how to use the Web UI is present in the Web UI applications. The help is located in the user menu, which can be found to the right in the application header.

## Transactions and Commit

Take special notice to the Commit Manager application, whenever a transaction has started, the active changes can be inspected and evaluated before they are committed and pushed to the network. The data is saved to NSO datastore and pushed to the network when a user presses "Commit".

Any network-wide change can be picked up as a rollback-file. That rollback can then be applied to undo whatever happened to the network.







## CHAPTER 12

# The Network Simulator

- [Overview, page 169](#)
- [Using Netsim, page 169](#)
- [Using ConfD Tools with Netsim, page 171](#)
- [Learn more, page 171](#)

## Overview

The **ncs-netsim** program is a useful tool to simulate a network of devices to be managed by NSO. It makes it easy to test NSO packages towards simulated devices. All you need is the NSO NED packages for the devices that you need to simulate. The devices are simulated with the Tail-f ConfD product.

All the NSO examples use **ncs-netsim** to simulate the devices. A good way to learn how to use **ncs-netsim** is to study these.

## Using Netsim

The **ncs-netsim** tool takes any number of NED packages as input. The user can specify the number of device instances per package (device type) and a string that is used as prefix for the name of the devices. The command takes the following parameters:

```
admin$ ncs-netsim --help
Usage ncs-netsim [--dir <NetsimDir>]
    create-network <NcsPackage> <NumDevices> <Prefix> |
    create-device <NcsPackage> <DeviceName> |
    add-to-network <NcsPackage> <NumDevices> <Prefix> |
    add-device <NcsPackage> <DeviceName> |
    delete-network
    [-a | --async] start [devname]
    [-a | --async ] stop [devname]
    [-a | --async ] reset [devname]
    [-a | --async ] restart [devname]
    list
    is-alive [devname]
    status [devname]
    whichdir
    ncs-xml-init [devname]
    ncs-xml-init-remote <RemoteNodeName> [devname] |
    [--force-generic]
    packages
    netconf-console devname [XPathFilter] |
```

```
[-w | --window] [cli | cli-c | cli-i] devname
```

Assume you have prepared a NSO package for a device called `router`. (See the `examples.ncs/getting-started/developing-with-ncs/0-router-network` example). Also assume the package is in `./packages/router`. At this point you can create the simulated network by:

```
$ ncs-netsim create-network ./packages/router 3 device --dir ./netsim
```

This creates three devices; `device0`, `device1`, and `device2`. The simulated network is stored in the `./netsim` directory. The output structure is:

```
./netsim/device/
  device0/<ConfD files>, <log files>
  device1/
  ....
```

There is one separate directory for every ConfD simulating the devices.

The network can be started with

```
$ ncs-netsim start
```

You can add more devices to the network in a similar way as it was created. E.g. if you created a network with some Juniper devices and want to add some Cisco IOS devices. Point to the NED you want to use (See `{NCS_DIR}/packages/neds/`) and run the command. Remember to start the new devices after they have been added to the network.

```
$ ncs-netsim add-to-network ${NCS_DIR}/packages/neds/cisco-ios 2 c-device --dir ./netsim
```

To extract the device data from the simulated network to a file in XML format.

```
$ ncs-netsim ncs-xml-init > devices.xml
```

This data is usually used to load the simulated network into NSO. Putting the xml file in the `./ncs-cdb` folder will load it when NSO starts. If NSO is already started it can be reloaded while running.

```
$ ncs_load -l -m devices.xml
```

The generated device data creates devices of the same type as the device being simulated. This is true for `netconf`, `cli` and `snmp` devices. When simulating generic devices the simulated device will run as a `netconf` device.

Under very special circumstances one can choose to force running the simulation as a generic device with the option `--force-generic`

The simulated network device info can be shown with:

```
$ ncs-netsim list
...
name=device0 netconf=12022 snmp=11022 ipc=5010 cli=10022 dir=examples.ncs/getting-started/developing-with-ncs/0-router-network/netsim/device/device0
...
```

Here you can see the device name, the working directory and port number for different services to be accessed on the simulated device (NETCONF SSH, SNMP, IPC and direct access to the CLI).

You can reach the CLI of individual devices with:

```
$ ncs-netsim cli-c device0
```

The simulated devices actually provides three different styles of CLI:

- cli : J-Style
- cli-c : Cisco XR Style
- cli-i : Cisco IOS Style

Individual devices can be started and stopped with:

```
$ ncs-netsim start device0
$ ncs-netsim stop device0
```

You can check the status of the simulated network. Either a short version just to see if the device is running or a more verbose with all information.

```
$ ncs-netsim is-alive device0
$ ncs-netsim status device0
```

View which packages are used in the simulated network.

```
$ ncs-netsim packages
```

It is also possible to reset the network back to state of initialization.

```
$ ncs-netsim reset
```

When you are done, remove the network.

```
$ ncs-netsim delete-network
```

## Using ConfD Tools with Netsim

The netsim tool includes a standard ConfD distribution and the ConfD C API library (libconfd) that the ConfD tools use. The library is built with default settings where the values for MAXDEPTH and MAXKEYLEN are 20 and 9, respectively. These values define the size of confd\_hkeypath\_t struct and this size is related to the size of data models in terms of depth and key lengths. Default values should be big enough even for very large and complex data models. But in some rare cases, one or both of these values might not be large enough for a given data model.

One might observe a limitation when the data models that are used by simulated devices exceed these limits. Then it would not be possible to use the ConfD tools that are provided with the netsim. To overcome this limitation, it is advised to use the corresponding NSO tools to perform desired tasks on devices.

NSO and ConfD tools and Python APIs are basically the same except for naming, the default IPC port and the MAXDEPTH and MAXKEYLEN values, where for NSO tools, the values are set to 60 and 18, respectively. Thus, the advised solution is to use the NSO tools and NSO Python API with netsim.

e.g. Instead of using below cmd

```
$ CONFD_IPC_PORT=5010 ${NCS_DIR}/netsim/confd/bin/confd_load -m -l *.xml
```

One may use:

```
$ NCS_IPC_PORT=5010 ncs_load -m -l *.xml
```

## Learn more

The README file in `examples.ncs/getting-started/developing-with-ncs/0-router-network` gives a good introduction on how to use **ncs-netsim**.

