

Johar “Star” Interface Interpreter

Requirements Specification of the Star GUI

1 The Main Panel

See Figure 1. The Main Panel is displayed when the application is started, and remains visible throughout the lifetime of the application.

1. At the top is the *Menu Bar*. This shows one menu for each command group in the application.
2. Each menu is labelled in the Menu Bar by the name of the command group.
3. The menu items in each menu are the commands that are in that command group.
4. A menu item is clickable (not greyed out) if the corresponding command is *active*.
5. A command is *active* at a given point if either it has no `ActiveIfMethod`, or it has an `ActiveIfMethod` and that method returns `true`.
6. On the left is the *Text Display Area*. This shows all text messages sent by the application engine using `displayText` that are not displayed through some other means.
7. On the right is the *Table Area*. This is a tabbed pane.
8. In the Table Area, there is one tab corresponding to every revealed Table currently in the application.
9. The application decides which Tables to conceal and reveal.
10. If, during the processing of a command, the application engine sets the top table, then immediately after the command has finished processing, the topmost table in the Table Area is the last table to have been set as the top table.
11. If, during the processing of a command, the application engine does not set the top table, then immediately after the command has finished processing, the topmost table in the Table Area remains unchanged from the time that the command was issued.
12. Notwithstanding the table set as the topmost table by the app engine, the user can (between issuing one command and issuing the next command) click on a table tab in order to move that table to the top.
13. At the bottom is the *Status Bar*. This shows low-prominence messages sent by the application engine using `displayText`.

2 The Command Dialog Box

See Figure 2.

1. At the top is the `Label` attribute of the command.
2. Under that is one section for every *queryable parameter* (see below) in the current stage.




Figure 1: The main panel.

3. Many commands have only one stage. However, if there is more than one stage, only the queryable parameters in the current stage will appear in the parameter section.
4. There is one section of the box for each queryable parameter in the current stage.
5. At the bottom are two to four buttons: Cancel, Previous, Next, and OK. Cancel and OK always appear; Previous and Next do not always appear.
6. The *Cancel button* always appears and is always enabled.
7. The Cancel button is on the left-hand side of the dialog box.
8. The *Previous button*:
 - (a) Appears if there is more than one *queryable stage* (see below).
 - (b) Is enabled if the current stage is not the first queryable stage.
9. The *Next button*:
 - (a) Appears if there is more than one queryable stage.
 - (b) Is enabled if the current stage is not the last queryable stage.
10. The *OK button*:
 - (a) Always appears.
 - (b) Is enabled if there are no *incomplete stages* (see below).
11. The OK button is on the right-hand side of the dialog box.
12. A parameter is *inactive* if both (a) it has a `ParentParameter`, and (b) the current value of the `ParentParameter` is not the `ParentValue` for this parameter.




Figure 2: The command dialog box.




Figure 3: The parameter section of the command dialog box.

13. A *queryable parameter* is any parameter that is not a `tableEntry` parameter with a browsable `SourceTable`.
14. A *queryable stage* is a stage that contains some queryable parameter.
15. An *incomplete stage* is a stage that contains some parameter such that: (a) the parameter is not inactive, (b) there is no `DefaultValue` or `DefaultValueMethod` for the parameter, and (c) the current number of repetitions is less than the `MinNumberOfReps` for the parameter.

3 Parameter Section of the Command Dialog Box

Every queryable parameter in the current stage is represented by a section of the command dialog box. See Figure 3.

1. On the left is the `Label` attribute of the parameter, at the top of the left-hand side, followed by a colon.
2. On the right is one subsection for each repetition of the parameter, and sometimes a small *Add Another* button.
3. Initially (before any user interaction), the number of repetition sections will be equal to $\text{maximum}(1, m)$, where m is the value of `MinNumberOfReps` for the parameter.
4. The *Add Another* button:
 - (a) Has the `ToolTip` “Add another”.
 - (b) Is a small button with a plus sign (“+”) in it.
 - (c) Appears only if `MinNumberOfReps` is not equal to `MaxNumberOfReps` for this parameter.
 - (d) Is enabled only if the current number of repetitions of the parameter is less than `MaxNumberOfReps` for this parameter.
 - (e) Is on the left-hand side of the right-hand half of the parameter section.




Figure 4: The repetition section of the parameter section.

5. The entire section corresponding to the parameter is greyed out if the parameter is inactive.

4 Repetition Section of the Parameter Section

Every repetition of a queryable parameter in the current stage is represented by a section of the command dialog box. See Figure 4.

1. On the left is a widget which the user can use to select the value of the repetition. This widget will be different for different types of parameters. For instance, for a `boolean` parameter, it may be a widget consisting of two radio buttons labelled “Yes” and “No”, whereas for a `string` parameter it may be a text area.
2. On the right of the section is zero to three small buttons with icons in them.
3. The `Move Up` button:
 - (a) Is a small button with an up-arrow in it.
 - (b) Has the ToolTip “Move up”.
 - (c) Appears only if `MaxNumberOfReps` is not equal to 1 for this parameter, and `RepsModel` for this parameter is `sequence`.
 - (d) Is enabled only if this is not the first repetition (the topmost repetition).
4. The `Move Down` button:
 - (a) Is a small button with an down-arrow in it.
 - (b) Has the ToolTip “Move down”.
 - (c) Appears only if `MaxNumberOfReps` is not equal to 1 for this parameter, and `RepsModel` for this parameter is `sequence`.
 - (d) Is enabled only if this is not the last repetition (the bottommost repetition).
5. The `Delete` button:
 - (a) Is a small button with an X (“x”) in it.
 - (b) Has the ToolTip “Delete”.

- (c) Appears only if `MinNumberOfReps` is not equal to `MaxNumberOfReps` for this parameter.
- (d) Is enabled only if the current number of repetitions of the parameter is more than $\text{maximum}(1, m)$, where m is the value of `MinNumberOfReps` for this parameter.