

# Table of Contents

Raster Commands .....	1
Envelope .....	1
Info .....	2
Get Projection .....	2
Get Size .....	3
World File .....	3


## Raster Commands

### Envelope

Get the Envelope of a Raster as a Vector Layer.

Short Name	Long Name	Description
-o	--output-workspace	The output workspace
-r	--output-layer	The output layer
-i	--input-raster	The input raster
-l	--input-raster-name	The input raster name
-p	--input-projection	The input projection
	--help	Print the help message
	--web-help	Open help in a browser

```
geoc raster envelope -i src/test/resources/earth.tif -o target/earth_envelope.shp
```



# Info

Get information about a Raster.

Short Name	Long Name	Description
-i	--input-raster	The input raster
-l	--input-raster-name	The input raster name
-p	--input-projection	The input projection
	--help	Print the help message
	--web-help	Open help in a browser

```
geoc raster info -i src/test/resources/earth.tif
```

```
Format: GeoTIFF
Size: 800, 400
Projection ID: EPSG:4326
Projection WKT: GEOGCS["WGS 84",
  DATUM["World Geodetic System 1984",
    SPHEROID["WGS 84", 6378137.0, 298.257223563, AUTHORITY["EPSG","7030"]],
    AUTHORITY["EPSG","6326"]],
  PRIMEM["Greenwich", 0.0, AUTHORITY["EPSG","8901"]],
  UNIT["degree", 0.017453292519943295],
  AXIS["Geodetic longitude", EAST],
  AXIS["Geodetic latitude", NORTH],
  AUTHORITY["EPSG","4326"]]
Extent: -179.9999999999997, -89.99999999998205, 179.99999999996405, 90.0
Pixel Size: 0.4499999999995505, 0.449999999999551
Block Size: 800, 8
Bands:
  RED_BAND
    Min Value: 56.0 Max Value: 255.0
  GREEN_BAND
    Min Value: 84.0 Max Value: 255.0
  BLUE_BAND
    Min Value: 91.0 Max Value: 255.0
```

## Get Projection

Get the Raster Projection.

Short Name	Long Name	Description
-t	--type	The output type (epsg, id, srs, wkt)

Short Name	Long Name	Description
-i	--input-raster	The input raster
-l	--input-raster-name	The input raster name
-p	--input-projection	The input projection
	--help	Print the help message
	--web-help	Open help in a browser

```
geoc raster projection -i src/test/resources/earth.tif
```

```
EPSG:4326
```

## Get Size

Get the Raster size (width,height).

Short Name	Long Name	Description
-i	--input-raster	The input raster
-l	--input-raster-name	The input raster name
-p	--input-projection	The input projection
	--help	Print the help message
	--web-help	Open help in a browser

```
geoc raster size -i src/test/resources/earth.tif
```

```
800,400
```

## World File

Create a Raster world file

Short Name	Long Name	Description
-b	--bounds	The bounds
-s	--size	The size
-f	--file	The world file
	--help	Print the help message
	--web-help	Open help in a browser

```
geoc raster worldfile -b 10,11,20,21 -s 800,751
```

```
0.0125
```

```
0.0
```

```
0.0
```

```
-0.013315579227696404
```

```
10.00625
```

```
20.993342210386153
```