



Apache Data Collector

Cloud Insights

Tony Lavoie, Dave Grace

February 27, 2020

This PDF was generated from https://docs.netapp.com/us-en/cloudinsights/task_config_telegraf_apache.html on April 23, 2020. Always check docs.netapp.com for the latest.

Table of Contents

- Apache Data Collector 1
 - Installation..... 1
 - Setup 2
 - Objects and Counters..... 4
 - Troubleshooting 5

Apache Data Collector

This data collector allows collection of data from Apache servers in your environment.

Pre-requisites

- You must have your Apache HTTP Server set up and properly running
- You must have sudo or administrator permissions on your agent host/VM
- Typically, the Apache *mod_status* module is configured to expose a page at the '/server-status?auto' location of the Apache server. The *ExtendedStatus* option must be enabled in order to collect all available fields. For information about how to configure your server, see the Apache module documentation: https://httpd.apache.org/docs/2.4/mod/mod_status.html#enable

Installation

1. From **Admin > Data Collectors**, click **+Data Collector**. Under **Services**, choose Apache.

Select the Operating System or Platform on which the Telegraf agent is installed.

2. If you haven't already installed an Agent for collection, or you wish to install an Agent for a different Operating System or Platform, click *Show Instructions* to expand the [Agent installation](#) instructions.
3. Select the Agent Access Key for use with this data collector. You can add a new Agent Access Key by clicking the **+ Agent Access Key** button. Best practice: Use a different Agent Access Key only when you want to group data collectors, for example, by OS/Platform.
4. Follow the configuration steps to configure the data collector. The instructions vary depending on the type of Operating System or Platform you are using to collect data.



Apache Configuration

Gathers Apache metrics.

What Operating System or Platform Are You Using?

[Need Help?](#)

Ubuntu & Debian

Select existing Agent Access Key or create a new one

Default (405fb5ec-d4cb-4404-977b-71fa931e1ad3)

+ Agent Access Key

*Please ensure that you have a Telegraf Agent in you environment before configuring [Show Instructions](#)

Follow Configuration Steps

[Need Help?](#)

- 1 Ensure that the Apache HTTP Server system you're going to gather metrics on has the 'mod_status' module enabled and exposed. For details refer to the following [document](#).
- 2 Copy the contents below into a new .conf file under the /etc/telegraf/telegraf.d/ directory. For example, copy the contents to the /etc/telegraf/telegraf.d/cloudinsights-apache.conf file.

```
[[inputs.apache]]
  ## An array of URLs to gather from, must be directed at the machine
  ## readable version of the mod_status page including the auto query string.
  ## USER-ACTION: Provide address of apache server, port for apache server, confirm path for
  ## server-status.
  ## Please provide actual machine IP address and replace from url to localhost address if -
```

- 3 Replace <INSERT_APACHE_ADDRESS> with the applicable Apache server address. Please specify a real machine address, and refrain from using a loopback address.
- 4 Replace <INSERT_APACHE_PORT> with the applicable Apache server port.
- 5 Modify the '/server-status' path in accordance to the Apache server configuration.
- 6 Restart the Telegraf service.

```
systemctl restart telegraf
```

Setup

Telegraf's plugin for Apache's HTTP Server relies on the 'mod_status' module to be enabled. When this is enabled, Apache's HTTP Server will expose an HTML endpoint that can be viewed on your browser or scraped for extraction of status of all Apache's HTTP Server configuration.

Compatibility:

Configuration was developed against Apache's HTTP Server version 2.4.38.

Enabling mod_status:

Enabling and exposing the 'mod_status' modules involves two steps:

- Enabling module
- Exposing stats from module

Enabling module:

The loading of modules is controlled by the config file under '/usr/local/apache/conf/httpd.conf'. Edit the config file and uncomment the following lines:

```
LoadModule status_module modules/mod_status.so
```

```
Include conf/extra/httpd-info.conf
```

Exposing stats from module:

The exposing of 'mod_status' is controlled by the config file under '/usr/local/apache2/conf/extra/httpd-info.conf'. Make sure you have the following in that configuration file (at least, other directives will be there):

```
# Allow server status reports generated by mod_status,
# with the URL of http://servername/server-status
<Location /server-status>
    SetHandler server-status
</Location>

#
# ExtendedStatus controls whether Apache will generate "full" status
# information (ExtendedStatus On) or just basic information (ExtendedStatus
# Off) when the "server-status" handler is called. The default is Off.
#
ExtendedStatus On
```

For detailed instructions on the 'mod_status' module, see the [Apache documentation](#)

Objects and Counters

The following objects and their counters are collected:

Object:	Identifiers:	Attributes:	Datapoints:
Apache	Namespace Server	Node IP Node Name Port Parent Server Config Generation Parent Server MPM Generation Server Uptime Is Stopping	Busy Workers Bytes per Request Bytes per Second CPU Children System CPU Children User CPU Load CPU System CPU User Asynchronous Connections Closing Asynchronous Connections Keep Alive Asynchronous Connections Writing Connections Total Duration per Request Idle Workers Load Average (last 1m) Load Average (last 15m) Load Average (last 5m) Processes Requests per Second Total Accesses Total Duration Total KBytes Scoreboard Closing Scoreboard DNS Lookups Scoreboard Finishing Scoreboard Idle Cleanup Scoreboard Keep Alive Scoreboard Logging Scoreboard Open Scoreboard Reading Scoreboard Sending Scoreboard Starting Scoreboard Waiting

Troubleshooting

Additional information may be found from the [Support](#) page.

Copyright Information

Copyright © 2019–2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.