

S3K: System Calls Documentation

Henrik Karlsson

March 12, 2025

Contents

1	Introduction to System Calls	1
2	List of System Calls	1
3	System Call Description	2
3.1	s3k_get_pid	2
3.2	s3k_get_time	2
3.3	s3k_get_timeout	2
3.4	s3k_reg_read	2
3.5	s3k_reg_write	3
3.6	s3k_sync	3
3.7	s3k_sleep	3
3.8	s3k_cap_read	4
3.9	s3k_cap_move	4
3.10	s3k_cap_delete	4
3.11	s3k_cap_revoke	5
3.12	s3k_cap_derive	5

1 Introduction to System Calls

2 List of System Calls

3 System Call Description

3.1 s3k_get_pid

Syntax

```
s3k_pid_t s3k_get_pid(void)
```

Description

Fetches the process ID of the caller.

Returns

The process ID of the caller.

3.2 s3k_get_time

Syntax

```
uint64_t s3k_get_time(void)
```

Description

Fetches the current value of the real-time clock.

Returns

The current value of the real-time clock.

Notes

The frequency of the RTC is hardware dependant.

3.3 s3k_get_timeout

Syntax

```
uint64_t s3k_get_timeout(void)
```

Description

Fetches the preemption time, which indicates how long the current process can run before being preempted.

Returns

The current value of the preemption time.

Notes

The frequency of the RTC is hardware dependant.

3.4 s3k_reg_read

Syntax

```
uint64_t s3k_reg_read(s3k_reg_t reg)
```

Description

Reads the value of the specified register **reg**. This system call is primarily used to read S3K's virtual registers but can also read standard RISC-V registers.

Parameters

reg The register to read. Should be one of S3K's virtual registers or a standard RISC-V register.

Returns

The value of the specified register **reg**. Returns 0 if **reg** is invalid.

Notes

Returns 0 if the specified register is invalid. Ensure that the register being read is valid.

3.5 s3k_reg_write

Syntax

```
uint64_t s3k_reg_write(s3k_reg_t reg, uint64_t val)
```

Description

Writes the value `val` to the specified register `reg`. This system call is primarily used to write to S3K's virtual registers but can also write to standard RISC-V registers.

Parameters

`reg` The register to write to. Should be one of S3K's virtual registers or a standard RISC-V register.

`val` The value to write to the register.

Returns

The value of the specified register `reg` before the write operation. Returns 0 if `reg` is invalid.

Notes

Returns 0 if the specified register is invalid. Ensure that the register being written to is valid.

3.6 s3k_sync

Syntax

```
void s3k_sync(void)
```

Description

Synchronizes the process's context with capabilities. This ensures that any changes to capabilities are reflected in the process's execution context.

Returns

This function does not return a value.

Notes

This function should be called after modifying capabilities such as time slices or PMP to ensure that the changes take effect immediately.

3.7 s3k_sleep

Syntax

```
void s3k_sleep(uint64_t time)
```

Description

Sets the process to sleep until the real-time clock (RTC) reaches the specified `time`. If `time` is 0, the process sleeps until the next timer preemption, as determined by `s3k_get_timeout()`.

Parameters

`time` The time at which the process should wake up. If 0, the process sleeps until the next timer preemption.

Returns

This function does not return a value.

Notes

Ensure that the `time` value is valid and represents a future point in time. If `time` is in the past, the process will wake up immediately.

3.8 s3k_cap_read

Syntax

```
s3k_err_t s3k_cap_read(s3k_cidx_t idx, s3k_cap_t *cap)
```

Description

Reads the description of the capability at index `idx` in the caller's capability table. This function is used to retrieve information about a specific capability.

Parameters

`idx` The index in the caller's capability table.

`cap` A pointer to a buffer where the capability description will be stored.

Returns

`ERR_SUCCESS` If the capability is successfully read.

`ERR_INVALID_INDEX` If `idx` is out of range.

`ERR_EMPTY` If there is no capability at `idx`.

Notes

Ensure that the `cap` buffer is properly allocated and can hold the capability description. This function is useful for inspecting capabilities before performing operations that depend on them.

3.9 s3k_cap_move

Syntax

```
s3k_err_t s3k_cap_move(s3k_cidx_t src, s3k_cidx_t dst)
```

Description

Moves a capability from index `src` to `dst` in the caller's capability table. This function is used to reorganize capabilities within the table.

Parameters

`src` The index in the caller's capability table from which the capability will be moved.

`dst` The index in the caller's capability table to which the capability will be moved.

Returns

`ERR_SUCCESS` If the capability is successfully moved.

`ERR_INVALID_INDEX` If `src` or `dst` is out of range.

`ERR_SRC_EMPTY` If there is no capability at `src`.

`ERR_DST_OCCUPIED` If there is already a capability at `dst`.

Notes

Ensure that the destination index `dst` is not occupied before moving the capability. This function is useful for reorganizing capabilities within the table.

3.10 s3k_cap_delete

Syntax

```
s3k_err_t s3k_cap_delete(s3k_cidx_t idx)
```

Description

Deletes a capability at index `idx` in the caller's capability table. This func-

tion is used to remove a capability from the table, freeing up the index for future use.

Parameters

idx The index in the caller's capability table from which the capability will be deleted.

Returns

ERR_SUCCESS If the capability is successfully deleted.

ERR_INVALID_INDEX If **idx** is out of range.

ERR_EMPTY If there is no capability at **idx**.

Notes

Ensure that the index **idx** is valid and that there is a capability present at that index before attempting to delete it. This function is useful for managing the capability table by removing unused or unwanted capabilities.

3.11 s3k_cap_revoke

Syntax

```
s3k_err_t s3k_cap_revoke(s3k_cidx_t idx)
```

Description

Revokes the children of the capability at index **idx** in the caller's capability table. This function is used to reclaim resources that have been granted to child capabilities.

Parameters

idx The index in the caller's capability table from which the capability's children will be revoked.

Returns

ERR_SUCCESS If the children are successfully revoked.

ERR_INVALID_INDEX If **idx** is out of range.

ERR_EMPTY If there is no capability at **idx**.

Notes

Ensure that the index **idx** is valid and that there is a capability present at that index before attempting to revoke its children. This function is useful for managing the capability table by reclaiming resources from child capabilities.

3.12 s3k_cap_derive

Syntax

```
s3k_err_t s3k_cap_derive(s3k_cidx_t src, s3k_cidx_t dst,  
s3k_cap_t newcap)
```

Description

Derives a new capability **newcap** from the capability at index **src** in the caller's capability table. The new capability is placed at index **dst** in the caller's capability table.

Parameters

src The index in the caller's capability table from which the new capability will be derived.

dst The index in the caller's capability table where the new capability will be placed.

newcap The new capability to be derived and placed at **dst**.

Returns

ERR_SUCCESS If the new capability is successfully derived and placed.

ERR_INVALID_INDEX If **src** or **dst** is out of range.

ERR_SRC_EMPTY If there is no capability at **src**.

ERR_DST_OCCUPIED If there is already a capability at **dst**.

ERR_INVALID_DERIVATION If **newcap** cannot be derived from the capability at index **src**.

Notes

Ensure that the indices **src** and **dst** are valid and that there is a capability present at **src** before attempting to derive a new capability. This function is useful for creating new capabilities based on existing ones.