

QUICK SETUP

OPENLISP & OPENLISP-CP

PURPOSE

Introduction step by step of installation and configuration of the xTR using:

- OpenLISP data plane
- OpenLISP control plane

OpenLISP data-plane (1)

- Add of the data-plane function of xTR (en/decapsulation packet) in kernel (now support FreeBSD 8.2, 9.2 and 10.0)
- Requirements:
 - FreeBSD 8.2, 9.2 or 10.0
 - Libconfig
 - Kernel source code
 - OpenLISP-0.2.0.2

OpenLISP data-plane (2)

- Step 1: Install FreeBSD
 - The iso file and documents can be retrieved from <http://www.freebsd.org/>
 - Step 2: Install *Libconfig* using the *ports collection*
 - ***#cd /usr/ports/devel/libconfig/***
 - ***#make clean install***

Note: if libconfig does not exist in ports collection, you need to update the *ports collection* by following theses commands (take over 10 minutes, depend on the bandwidth)

 - ***#portsnap fetch***
 - ***#portsnap extract***
 - ***#portsnap fetch***
 - ***#portsnap update***
- *Note**: lines start with ***#*** and ***italic, bold*** mean command

OpenLISP data-plane (3)

- Step 3: Install the Kernel source code if it does not exist (/usr/src/ is empty), using the package management of system.

Note:

- For FreeBSD < 9, the easiest way to install the full source tree is to run **#sysinstall** as root, and then choosing **Configure -> Distributions -> Src -> All**
- For FreeBSD >= 9.0, you can install by downloading the tar file that matches the version you installed from <http://www.freebsd.org/> and extract to /usr/src.

- Step 4: Install OpenLISP

1. Source code and documents (version 0.2.0.2) can be retrieved from <https://github.com/lip6-lisp/data-plane>
2. From the source code directory, run the shell script to patch the kernel source code
#sh install-lisp.sh

OpenLISP data-plane (4)

- Bellow is an example of kernel compilation. The full document to compile the kernel can be retrieved from: http://www.freebsd.org/doc/en_US.ISO8859-1/books/handbook/makeworld.html
 - Make a new configuration file for a new kernel
 - **#cd /usr/src/sys/*amd64*/conf**
 - Note:*** Change *amd64* to your server architecture
 - **#cp GENERIC OPENLISP_KERNEL**
 - **#echo "options LISP" >> OPENLISP_KERNEL**
 - Rebuild a new kernel with a new configuration file
 - **#cd /usr/src**
 - **#make buildkernel KERNCONF=OPENLISP_KERNEL**
 - Or
 - #make buildkernel KERNCONF=OPENLISP_KERNEL -j n**
(to speed up, with n <= number of cores or CPUs)
 - **#make installkernel KERNCONF=OPENLISP_KERNEL**
- Note: it could take more than 30 minutes, depend on the system

OpenLISP data-plane (5)

4. Installation of the OpenLISP tools

- OpenLISP map: to manage OpenLISP mapping database
 - *#cd /usr/src/sbin/map/*
 - *#make depend*
 - *#make*
 - *#make install*
- OpenLISP mapstat: for statistical of OpenLISP
 - *#cd /usr/src/usr.bin/mapstat/*
 - *#make depend*
 - *#make*
 - *#make install*

OpenLISP data-plane (6)

- OpenLISP man: man page of OpenLISP
 - *#cd /usr/src/share/man/man4/*
 - *#make*
 - *#make install*

Note: reboot the system to load new kernel

- Some commands to start with OpenLISP
 - *#man lispintro*
 - *#man 4 map*
 - *#man mapstat*
 - *#mapstat -Xn*
 - *#mapstat -s -p lisp*

OpenLISP control-plane ⁽¹⁾

- functionality: do the control-plane function of xTR/MS/MR/DDT_NODE (now support both FreeBSD and Linux)
- requirements:
 - Expat library
 - OpenLISP-CP 3.1

OpenLISP control-plane (2)

- Step 1: installation of the expat library using ***ports collection*** (on FreeBSD) or ***packaging tool*** (on Linux)
 - FreeBSD
 - ***#cd /usr/ports/textproc/expat2***
 - ***#make clean install***
 - Make sure that ***expat.h*** and ***expat_external.h*** exist in ***/usr/local/include/***, if not you need to copy by hand.
 - ***#cd /usr/ports/textproc/expat2/work/expat-2.0.1/lib***
 - ***#cp expat.h expat_external.h /usr/local/include/***
 - Linux (example)
 - ***#apt-get install libexpat1-dev***

OpenLISP control-plane (2)

- Step 2: installation of the OpenLISP-CP
 - Verify that the **gcc compiler** is installed on the machine. If use other compiler, set **new compiler** in the Makefile
 - `CC = gcc` → `CC = new compiler`
 - Get the sources code and documents from <https://github.com/lip6-lisp/control-plane>
 - Unpack the tarball source code.
 - From the source code directory, run
 - **#make**
 - **#make install**
 - To start the program for the first time, use
 - `#service opencp start`
 - Or
 - `/etc/rc.d/opencp start`
 - Or
 - `#!/opencp -f [<path_to_opencp.conf>]`
- to allow the program to start automatically after reboot, add the following line to the `/etc/rc.conf`:
 - `opencp_enable="YES"`

OpenLISP control-plane (3)

- Step 3: configuration of the OpenLISP-CP
 - Main configuration file (opencp.conf): default put in /etc/rc.d
 - The configuration relies on a main configuration file named "opencp.conf" that points to specific xml files:

Functions: xTR, ms(Map-Server), mr/ddt (DDT Map-Resolver or DDT-only node)

functions = ms mr ddt

#Set debug level

debug_level = 2

#Support LISP-TE

lisp_te = No

#Choose source IP for map-response packet, default is auto select

source_ipv4 = auto

source_ipv6 = auto

#Set size of open control-plane queue size, default is 1000

queue_size = default

#Parameter to setup worker pool

min_thread = default

max_thread = default

linger_thread = default

specific xml files

xtr_configure = /etc/rc.d/opencp_xtr.xml

ms_configure = /etc/rc.d/opencp_ms.xml

mr_configure = /etc/rc.d/opencp_mr.xml

OpenLISP control-plane (3)

- Step 3: configuration of the OpenLISP-CP
 - xTR configuration file (default /etc/opencp_xtr.xml)
 - The <mapserver> section defines the list of MSs the xTR registers to. Each MS needs a key to authenticate.
 - The <mapresolve> section defines the list of MRs the xTR can send map-requests.
 - One or more <eid> sections. Each section gives the information for one EID IP prefix to register.

OpenLISP control-plane (4)

- Step 3: configuration of the OpenLISP-CP
 - Map server configuration file (default /etc/opencp_ms.xml)
 - The <geid> section defines the IP prefixes the map-server allows ETR to register to. The IP ranges must not be overlapped.
 - One or more <site> sections. Each section includes the informations for one site:
 - *site name,*
 - *key for map-register messages (NB: the key is case sensitive and must not include spaces),*
 - *EID IP prefixes the site can register.*

OpenLISP control-plane (5)

- Step 3: configuration of the OpenLISP-CP
 - DDT node and MR configuration file (default /etc/opencp_mr.xml)
 - The <geid> section defines the IP prefix(es) the node is delegated. The IP ranges must not be overlapped. NB: if the node is a DDT root, then it is here configured as being delegated for 0.0.0.0/0 (IPv4) and 0::/0 (IPv6).
 - One or more <eid> sections. Each section contains the information for one delegated prefix. Special <eid> sections with prefix equal 0.0.0.0/0 or 0::/0 is for DDT root nodes.

OpenLISP control-plane (6)

- Step 3: configuration of the OpenLISP-CP
 - RTR/PxTR configuration file (default /etc/opencp_rtr.xml)
 - The <mapresolve> section defines the list of MRs the RTR can send map-requests.
 - One or more <eid> sections.