

Feed Registry API Reference

This guide outlines the functions which can be used with Chainlink's Feed Registry. You can learn more about the feed registry [here](#).

Functions

Name**Description****[decimals](#)**The number of decimals in the response**[description](#)**The description of the aggregator that the proxy points to**[getRoundData](#)**Get data from a specific round**[latestRoundData](#)**Get data from the latest round**[version](#)**The version representing the type of aggregator the proxy points to**[getFeed](#)**Returns the primary aggregator address of a base / quote pair**[getPhaseFeed](#)**Returns the aggregator address of a base / quote pair at a specified phase**[isFeedEnabled](#)**Returns true if an aggregator is enabled as primary on the registry**[getPhase](#)**Returns the raw starting and ending aggregator round ids of a base / quote pair**[getRoundFeed](#)**Returns the underlying aggregator address of a base / quote pair at a specified round**[getPhaseRange](#)**Returns the starting and ending round ids of a base / quote pair at a specified phase**[getPreviousRoundId](#)**Returns the previous round id of a base / quote pair given a specified round**[getNextRoundId](#)**Returns the next round id of a base / quote pair given a specified round**[getCurrentPhaseId](#)**Returns the current phase id of a base / quote pair.

[decimals](#)

Get the number of decimals present in the response value.

```
function decimals(address base, address quote) external view returns (uint8)
```

[Parameters](#)

- base: The base asset address.
- quote: The quote asset address.

[Return values](#)

- RETURN: The number of decimals.

[description](#)

Get the description of the underlying aggregator that the proxy points to.

```
function description(address base, address quote) external view returns (string memory)
```

[Parameters](#)

- base: The base asset address.
- quote: The quote asset address.

[Return values](#)

- RETURN: The description of the underlying aggregator.

[getRoundData](#)

Get data about a specific round, using the roundId.

```
function getRoundData(address base, address quote, uint80 roundId) external view returns (uint80 roundId, int256 answer, uint256 startedAt, uint256 updatedAt, uint80 answeredInRound)
```

[Parameters](#)

- base: The base asset address.
- quote: The quote asset address.
- roundId: The round ID.

[Return values](#)

- roundId: The round ID.
- answer: The price.
- startedAt: Timestamp of when the round started.
- updatedAt: Timestamp of when the round was updated.
- answeredInRound: Deprecated - Previously used when answers could take multiple rounds to be computed

[latestRoundData](#)

Get the price from the latest round.

```
function latestRoundData(address base, address quote) external view returns (uint80 roundId, int256 answer, uint256 startedAt, uint256 updatedAt, uint80 answeredInRound)
```

[Return values](#)

- roundId: The round ID.
- answer: The price.
- startedAt: Timestamp of when the round started.
- updatedAt: Timestamp of when the round was updated.
- answeredInRound: Deprecated - Previously used when answers could take multiple rounds to be computed

[version](#)

The version representing the type of aggregator the proxy points to.

```
function version(address base, address quote) external view returns (uint256)
```

[Parameters](#)

- base: The base asset address.
- quote: The quote asset address.

[Return values](#)

- RETURN: The version number.

[getFeed](#)

Returns the primary aggregator address of a base / quote pair. Note that onchain contracts cannot read from aggregators directly, only through Feed Registry or Proxy contracts.

```
functiongetFeed(addressbase,addressquote)externalviewreturns(AggregatorV2V3Interface aggregator);
```

[Parameters](#)

- base: The base asset address.
- quote: The quote asset address.

[Return values](#)

- aggregator: The primary aggregator address.

[getPhaseFeed](#)

Returns the underlying aggregator address of a base / quote pair at a specified phase. Note that onchain contracts cannot read from aggregators directly, only through Feed Registry or Proxy contracts. Phase ids start at 1. You can get the current Phase by calling `getCurrentPhaseId()`.

```
functiongetPhaseFeed(addressbase,addressquote,uint16phaseId)externalviewreturns(AggregatorV2V3Interface aggregator);
```

[Parameters](#)

- base: The base asset address.
- quote: The quote asset address.
- phaseId: The phase id.

[Return values](#)

- aggregator: The primary aggregator address at the specified phase.

[isFeedEnabled](#)

Returns true if an aggregator is enabled as primary on the feed registry. This is useful to check if you should index events from an aggregator contract, because you want to only index events of primary aggregators.

```
functionisFeedEnabled(addressaggregator)externalviewreturns(bool);
```

[Parameters](#)

- aggregator: The aggregator address

[Return values](#)

- RETURN:true if the supplied aggregator is a primary aggregator for any base / quote pair.

[getPhase](#)

Returns the starting and ending aggregator round ids of a base / quote pair.

```
functiongetPhase(addressbase,addressquote,uint16phaseId)externalviewreturns(Phasememoryphase);
```

 Phases hold the following information:

```
structPhase{uint16phaseId;uint80startingAggregatorRoundId;uint80endingAggregatorRoundId;}
```

[Parameters](#)

- base: The base asset address.
- quote: The quote asset address.
- phaseId: The phase id.

[Return values](#)

- RETURN:Phase details of a base / quote pair.

[getRoundFeed](#)

Returns the underlying aggregator address of a base / quote pair at a specified round. Note that onchain contracts cannot read from aggregators directly, only through Feed Registry or Proxy contracts.

```
functiongetRoundFeed(addressbase,addressquote,uint80roundId)externalviewreturns(AggregatorV2V3Interface aggregator);
```

[Parameters](#)

- base: The base asset address.
- quote: The quote asset address.
- roundId: The round id.

[Return values](#)

- aggregator: The underlying aggregator address of a base / quote pair at the specified round.

[getPhaseRange](#)

Returns the starting and ending round ids of a base / quote pair at a specified phase.

Please note that this `roundId` is calculated from the phase id and the underlying aggregator's round id. To get the raw aggregator round ids of a phase for indexing purposes, please use `getPhase()`.

```
functiongetPhaseRange(addressbase,addressquote,uint16phaseId)externalviewreturns(uint80startingRoundId,uint80endingRoundId);
```

[Parameters](#)

- base: The base asset address.
- quote: The quote asset address.
- phaseId: The phase id.

[Return values](#)

- startingRoundId: The starting round id
- endingRoundId: The ending round id

[getPreviousRoundId](#)

Returns the previous round id of a base / quote pair given a specified round. Note that rounds are non-monotonic across phases.

```
functiongetPreviousRoundId(addressbase,addressquote,uint80roundId)externalviewreturns(uint80previousRoundId);
```

[Parameters](#)

- base: The base asset address.
- quote: The quote asset address.
- roundId: The round id.

[Return values](#)

- previousRoundId: The previous round id of a base / quote pair.

[getNextRoundId](#)

Returns the next round id of a base / quote pair given a specified round. Note that rounds are non-monotonic across phases.

```
functiongetNextRoundId(addressbase,addressquote,uint80roundId)externalviewreturns(uint80nextRoundId);
```

[Parameters](#)

- base: The base asset address.
- quote: The quote asset address.
- roundId: The round id.

[Return values](#)

- nextRoundId: The next round id of a base / quote pair.

[getCurrentPhaseId](#)

Returns the current phase id of a base / quote pair.

```
functiongetCurrentPhaseId(addressbase,addressquote)externalviewreturns(uint16currentPhaseId);
```

[Parameters](#)

- base: The base asset address.
- quote: The quote asset address.

[Return values](#)

- phaseId: The current phase id of a base / quote pair.