



Chapter 7: DHCP



Switched Networks

Cisco | Networking Academy®
Mind Wide Open™



7.1 Dynamic Host Configuration Protocol v4



Cisco | Networking Academy®
Mind Wide Open™



DHCPv4 Operation

Introducing DHCPv4


DHCPv4 uses three different address allocation methods:

- **Manual Allocation** – The administrator assigns a pre-allocated IPv4 address to the client, and DHCPv4 communicates only the IPv4 address to the device.
- **Automatic Allocation** – DHCPv4 automatically assigns a static IPv4 address permanently to a device, selecting it from a pool of available addresses.
- **Dynamic Allocation** – DHCPv4 dynamically assigns, or leases, an IPv4 address from a pool of addresses for a limited period of time chosen by the server, or until the client no longer needs the address. This method is the most commonly used.



DHCPv4 Operation

DHCPv4 Operation





DHCPv4 Operation


DHCPv4 Message Format

DHCPv4 Message Format			
8	16	24	32
OP Code (1)	Hardware type (1)	Hardware address length (1)	Hops (1)
Transaction Identifier			
Seconds - 2 bytes		Flags - 2 bytes	
Client IP Address (CIADDR) - 4 bytes			
Your IP Address (YIADDR) - 4 bytes			
Server IP Address (SIADDR) - 4 bytes			
Gateway IP Address (GIADDR) - 4 bytes			
Client Hardware Address (CHADDR) - 16 bytes			
Server name (SNAME) - 64 bytes			
Boot Filename - 128 bytes			
DHCP Options - variable			



DHCPv4 Operation

Format DHCPv4 Discover and Offer Messages





DHCPv4 Operation

Configuring a DHCPv4 Server

A Cisco router running the Cisco IOS software can be configured to act as a DHCPv4 server. To set up DHCP:

1. Exclude addresses from the pool.
2. Set up the DHCP pool name.
3. Define the range of addresses and subnet mask. Use the **default-router** command for the default gateway. Optional parameters that can be included in the *pool* – *dns server*, *domain-name*.

```
R1(config)# ip dhcp excluded-address 192.168.10.1 192.168.10.9
R1(config)# ip dhcp excluded-address 192.168.10.254
R1(config)# ip dhcp pool LAN-POOL-1
R1(dhcp-config)# network 192.168.10.0 255.255.255.0
R1(dhcp-config)# default-router 192.168.10.1
R1(dhcp-config)# dns-server 192.168.11.5
R1(dhcp-config)# domain-name example.com
R1(dhcp-config)# end
R1#
```


To disable DHCP, use the **no service dhcp** command.



DHCPv4 Operation

Verifying a DHCPv4 Server

- Commands to verify DHCP:
 - `show running-config | section dhcp`
 - `show ip dhcp binding`
 - `show ip dhcp server statistics`
- On the PC, issue the `ipconfig /all` command.



```

C:\WINDOWS\system32\cmd.exe

WINS Proxy Enabled .....: No

Ethernet Adapter Local Area Connection

Connection-specific DNS Suffix.: example.com
Description .....: SiS 900 PCI Fast Ethernet Adapter
Physical Address.....: 00-E0-18-5B-DD-35
Dhcp Enabled .....: Yes
Autoconfiguration Enabled.....: Yes
IP Address .....: 192.168.10.10
Subnet Mask.....: 255.255.255.0
Default Gateway.....: 192.168.10.1
DHCP Server .....: 192.168.10.1
Lease Obtained.....: Monday, May 27, 2013 1:06:22PM

Lease Expires .....: Tuesday, May 28, 2013 1:06:22PM

DNS Servers . . . . .: 192.168.11.5

C:\Documents and settings\SpanPC>
  
```




DHCPv4 Operation

DHCPv4 Relay

Using an IP helper address enables a router to forward DHCPv4 broadcasts to the DHCPv4 server. Acting as a relay.

```
R1(config)# interface g0/0
R1(config-if)# ip helper-address 192.168.11.6
R1(config-if)# end
R1# show ip interface g0/0
GigabitEthernet0/0 is up, line protocol is up
  Internet address is 192.168.10.1/24
  Broadcast address is 255.255.255.255
  Address determined by setup command
  MTU is 1500 bytes
  Helper address is 192.168.11.6
<Output omitted>
```



Configuring a DHCPv4 Client

Configuring a Router as a DHCPv4 Client



```

SOHO(config)# interface g0/1
SOHO(config-if)# ip address dhcp
SOHO(config-if)# no shutdown
SOHO(config-if)#
*Jan 31 17:31:11.507: %DHCP-6-ADDRESS_ASSIGN: Interface
GigabitEthernet0/1 assigned DHCP address 209.165.201.12, mask
255.255.255.224, hostname SOHO
SOHO(config-if)# end
SOHO# show ip interface g0/1
GigabitEthernet0/1 is up, line protocol is up
  Internet address is 209.165.201.12/27
  Broadcast address is 255.255.255.255
  Address determined by DHCP
  <Output omitted>
  
```



Troubleshoot DHCPv4

Verifying the Router DHCPv4 Configuration

Verifying DHCPv4 Relay and DHCPv4 Services

```
R1# show running-config | section interface GigabitEthernet0/0
interface GigabitEthernet0/0
  ip address 192.168.10.1 255.255.255.0
  ip helper-address 192.168.11.6
  duplex auto
  speed auto
R1#

R1# show running-config | include no service dhcp
R1#
```

Cisco | Networking Academy[®]

Mind Wide Open[™]