

# ***Network License Administrator's Guide***

The following instructions are for administrators at sites with a network license for IBM® SPSS® Modeler 15. This license allows you to install IBM SPSS Modeler on any number of computers. However, only the number of users for which you purchased the license can run the application concurrently.

## ***Before You Start***

You will need your authorization code. This may be on a separate sheet of paper or is available from <http://www.ibm.com/software/getspss>. The authorization code enables you to get a license for the network license manager. The **network license manager** controls your network license and allows end users to run IBM® SPSS® Modeler. If you cannot find your authorization code, contact your sales representative.

To ensure that you set up the network license correctly, follow these steps:

- ▶ **Install the network license manager.** The network license manager is the utility that will serve up the network licenses to end users. You can install the license manager on any computer on your network. This is typically a server to which desktop computers can connect. For more information, see the topic “Installing the Network License Manager” on p. 2.
- ▶ **License your product.** This action will give the license manager the required information for serving up the licenses. For more information, see the topic “Licensing Your Product” on p. 5.
- ▶ **Test the network license manager.** You should test license manager to make sure it is serving up licenses. For more information, see the topic “Testing the License Manager” on p. 9.
- ▶ **Install IBM SPSS Modeler on the local desktop computers.** You or your end users will complete the full installation on the desktop computers. During an installation, an end user can specify the computer on which the license manager is running. When an end user tries to launch IBM SPSS Modeler, the product communicates with this license manager to get a license. If a license is available, IBM SPSS Modeler launches. For more information, see the topic “Installing the Product on the Local Desktop Computers” on p. 9.

No administration steps are required for the installation, but if any problems arise, see “Administering the Network License” on p. 12.

## ***Terminal Services***

You can install and publish the IBM® SPSS® Modeler application on your Terminal Services Server the same way that you install and publish other Windows applications.

## ***Mixed Licensing***

IBM® SPSS® Modeler has limited support for a mixed licensing environment (a combination of local and network licenses). In a typical environment, all licenses are handled locally or through the network license manager. For example, if the main product is licensed through the network license manager, options are also licensed through the network license manager.

The only option for mixed licensing is to license the main product through the network license manager and to license the options on the end user's computer with *licenseactivator*. To set up this type of mixed licensing, install IBM SPSS Modeler with a network license. Then use *licenseactivator* on the end user's computer to license the options. For more information about *licenseactivator*, see "Using licenseactivator to Install a License Automatically" on p. 6.

IBM SPSS Modeler does not support the opposite scenario to license the main product locally and to license the options through the network license manager.

## ***Installing the Network License Manager***

Before end users install IBM® SPSS® Modeler on their desktop computers, you must install the network license manager. This utility is a continuously executing service or daemon that you will typically install on one computer on your network. (You also have the option of installing on multiple computers, in which case you would set up redundant license managers. For more information, see the topic "Setting Up Redundant License Servers" on p. 14.) You do not install the network license manager on the desktop computers.

Whenever an end user starts a network-licensed IBM SPSS application, the application will request a license from the license manager. This utility will deliver licenses up to a fixed number of simultaneous end users, determined by the license that you have purchased. After this number has been met, any further requests for licenses will be refused. If you find that end users are often being refused licenses, you can contact your sales representative to purchase a license that will allow more simultaneous users.

*Note:* The license manager will record the number of active end-user sessions and information about each session in a log file, which you can use to troubleshoot connection problems. For more information, see the topic "Obtaining Log Information" on p. 13.

### ***Multiple Operating Systems***

The platform on which the network license manager is running does not have to match the platform on which the client is running.

### ***Administering the License Manager***

You administer the license manager using the license manager tools, which are available only for Windows. Therefore, you need at least one Windows machine on which to install the license manager tools.

### **System Requirements**

The computer on which you install the network license manager must meet the following requirements:

- 550 Mhz or higher processor
- 128 MB of RAM or more

**Important!** If a firewall is running on the license server, you must open port 5093 for UDP. Otherwise, client computers will not be able to retrieve a license from the license manager. Furthermore, if you are using redundant license servers, you must open port 5099 for UDP to enable the license servers to communicate with each other.

### **Upgrading the License Manager**

If you have a previous version of the license manager installed, you must perform the following steps:

- ▶ Go to the directory in which you installed the old license manager.
- ▶ Copy the *lservrc* file. On Windows, look in the *winnt* subdirectory.
- ▶ Save the *lservrc* file to a safe location.
- ▶ If any users have checked out commuter licenses, make sure those users check the licenses back in. See the topic “Configuring Commuter Licenses” on p. 16 for information about obtaining a list of checked out licenses.
- ▶ Shutdown the license manager. For more information, see the topic “Starting and Stopping the License Manager” on p. 18.
- ▶ Uninstall the old license manager. For more information, see the topic “Uninstalling the License Manager” on p. 19.
- ▶ Install the new license manager. For information about installing on Windows, see the topic “Installing the License Manager on Windows” on p. 4. For information about installing on UNIX/Linux, see the topic “Installing the License Manager on UNIX/Linux” on p. 4.
- ▶ Copy the saved *lservrc* file to the directory in which you installed the new license manager or the *winnt* subdirectory of the installation directory on Windows. If you accepted the default location on Windows, check the *C:\Program Files\Common Files\SafeNet Sentinel\Sentinel RMS License Manager\* folder.

### **Installing the Concurrent Licensing Tools (All Platforms)**

Before you can install the license manager and the license manager tools, you must run the concurrent licensing tools installer. This installer will copy the installer files for the license manager and/or the license manager tools to your computer. During installation, you will be able to choose which installer files you want to copy.

The concurrent licensing tools installer requires Java 1.5 or higher.

- ▶ Insert the DVD into the DVD drive of the network computer on which you want to run the license manager and/or license manager tools. Look for the installer for your operating system and launch it from the DVD.

*or*

- ▶ If you downloaded an eImage file, use an archive utility such as WinZip to extract all the files in the appropriate eImage. Launch the installer file for your operating system.

*Note:* There may be multiple eImages for the concurrent license tools: one for the license manager, one for the license manager tools, and one for hardware key drivers. Each eImage installs the concurrent licensing tools and the installer for the named component.

- ▶ Follow the instructions that appear on the screen. Be sure to note the installation directory. If you chose to install the license manager and/or the license manager tools, the installation process for these will be started automatically.

### ***Installing the License Manager on Windows***

*Note:* On Windows Vista or 7, you must launch the installer as administrator. When instructed to launch an installer file, right-click the file and choose Run As Administrator.

*Note:* Ensure that the machine on which you are installing has Java installed.

- ▶ If you haven't installed the concurrent licensing tools, install them and be sure to select Sentinel License Manager if prompted. For more information, see the topic "Installing the Concurrent Licensing Tools (All Platforms)" on p. 3.
- ▶ When you install the concurrent licensing tools from the DVD, the installer for the license manager should start automatically. If it didn't or you cancelled the installation, browse to the *licensemanager* directory in the concurrent licensing tools installation directory.
- ▶ Launch *setup.exe*. On Windows Vista or 7, be sure to launch the installer as administrator.
- ▶ Follow the instructions that appear on the screen.

### ***Installing the License Manager on UNIX/Linux***

- ▶ If you haven't installed the concurrent licensing tools, install them and be sure to select Sentinel License Manager if prompted. For more information, see the topic "Installing the Concurrent Licensing Tools (All Platforms)" on p. 3.
- ▶ Browse to the *licensemanager* directory in the concurrent licensing tools installation directory.
- ▶ Untar the license manager file.
- ▶ Install the license manager tools on a Windows machine. For more information, see the topic "Installing the License Manager Tools" on p. 5.
- ▶ Refer to "Starting and Stopping the License Manager" on p. 18 for information about starting the license manager.

## Installing the License Manager Tools

The Windows-only license manager tools are used to administer the license manager. Depending on your operating system, you may need to manually install these tools.

- **Windows.** You can install the license manager tools on the same machine on which you installed the license manager. You also have the option of installing on another Windows machine if you want to administer the license manager remotely.
  - **Other Operating Systems.** If you installed the license manager on a non-Windows machine, you must install the license manager tools on a Windows machine.
- ▶ If you haven't installed the concurrent licensing tools, install them and be sure to select Tools when prompted. For more information, see the topic "Installing the Concurrent Licensing Tools (All Platforms)" on p. 3.
  - ▶ Browse to the *tools* directory in the concurrent licensing tools installation directory.
  - ▶ Launch *setup.exe*.

## Licensing Your Product

After the main part of the installation is complete on Windows, click Finish to launch the License Authorization Wizard. The License Authorization Wizard allows you to obtain a license for IBM® SPSS® Modeler. On other operating systems, you must install the license from the command prompt after installing the license manager.

If you do not get a license now, you can enable IBM SPSS Modeler to be used for a temporary usage period by a limited number of users. All options are enabled. After the temporary usage period has completed—and which begins when the product is first used—IBM SPSS Modeler will no longer run. Therefore, it is recommended that you obtain a license as soon as possible. You must either obtain a license or enable for temporary usage to use IBM SPSS Modeler.

*Note:* Licenses are tied to the network computer's hardware with a **lock code**. If you replace the network computer or its hardware, you will have a new lock code and will need to contact your sales representative to obtain a new authorization code.

*Warning:* The license is sensitive to time changes. If you must change the system time and then cannot run the product, contact IBM Corp. Technical Support by visiting <http://www.ibm.com/support>.

## Using the License Authorization Wizard (Windows Only)

*Note:* If you are running Windows Vista, you may be prompted for administrator credentials. Without the correct credentials, you will not be able to run the License Authorization Wizard.

The License Authorization Wizard is available only on Windows. If you need to license the license manager on a different operating system, you must license from the command prompt. For more information, see the topic "Installing a License from the Command Prompt" on p. 6.

- ▶ If you don't launch the License Authorization Wizard during installation or cancel the License Authorization Wizard before obtaining a license, you can launch it by running *law.exe*, which can be found in the license manager installation directory. On Windows Vista or 7, you must run as administrator. Right-click *law.exe* and choose Run As Administrator.
- ▶ When prompted, choose License my product now.
- ▶ When prompted, enter one or more authorization codes. If you received physical installation media, your authorization code may be delivered on a separate sheet of paper along with your software or on the inside cover of the DVD case. You should have received the authorization code(s) from your administrator.

The License Authorization Wizard sends your authorization code over the Internet to IBM Corp. and automatically retrieves your license. If your computer is behind a proxy, click Configure proxy settings and enter the appropriate settings.

If the authorization process fails, you will be prompted to send an e-mail message. Choose whether you want to send the e-mail message through your desktop e-mail program or through a Web-based e-mail application.

- If you choose the desktop option, a new message with the appropriate information will be created automatically.
- If you choose the Web-based option, you must first create a new message in your Web-based e-mail program. Then copy the message text from the License Authorization Wizard and paste it into your e-mail application.

Send the e-mail message and respond to the prompt in the License Authorization Wizard. The e-mail message will be processed almost instantaneously. You can click Enter License Code(s) to enter any license code(s) that you receive. If you already closed the License Authorization Wizard, restart it and select License my product now. On the Enter Codes panel, add the license code that you received and click Next to complete the process.

## ***Installing a License from the Command Prompt***

You have two options for installing from the command prompt. You can use *licenseactivator* to get a license from the Internet automatically, or you can use *echoid* to get a license manually.

### ***Using licenseactivator to Install a License Automatically***

The computer on which you are installing the license must be connected to the Internet. If it isn't, install the license manually. For more information, see the topic "Installing a License Manually" on p. 7.

- ▶ Log in as the user who installed the license manager.
- ▶ Open a command prompt and change directories to the license manager installation directory. Note that this is the directory in which you installed the *license manager*, not the directory in which you installed IBM® SPSS® Modeler. If you accepted the default location on Windows, check the *C:\Program Files\Common Files\SafeNet Sentinel\Sentinel RMS License Manager\* folder.

- **Windows Only.** Change directories to the *winnt* subdirectory.
- You typically have an authorization code. In the simplest case, you enter the following at the command prompt. See below for more details about the command prompt usage.

```
licenseactivator <auth-code>
```

where <auth-code> is your authorization code.

You should see a message that the license was added successfully. If it wasn't, note the error code and try installing the license manually. For more information, see the topic "Installing a License Manually" on p. 7.

When you use *licenseactivator*, it licenses the product and writes a log file to its directory. The name of the log file is *licenseactivator\_<month>\_<day>\_<year>.log*. If any errors occur, you can check the log file for more information. This information is also useful if you contact IBM Corp. for support.

### **Using *licenseactivator* with Authorization Codes**

*licenseactivator* is typically used with one or more authorization codes that you received when you purchased the product. Enter all of the text on one line.

```
licenseactivator authcode1[:authcode2:...:authcodeN] [PROXYHOST=proxy-hostname]
[PROXYPORT=proxy-port-number] [PROXYUSER=proxy-userid] [PROXYPASS=proxy-password]
```

- Multiple authorization codes are separated by colons (:).
- The proxy settings are optional, but you may need them if your computer is behind a proxy. Which proxy settings are needed depend on the operating system.

**Windows.** On Windows, the proxy settings work only when the Local Area Network (LAN) settings in the Internet Settings control panel reference a specific proxy server (host) address and port. You do not enter the proxy host and port on the command line. But you do need to enter values for PROXYUSER and PROXYPASS.

**Other Operating Systems.** On other operating systems, you may need to enter all of the proxy settings on the command line, depending on your specific proxy configuration.

### **Using *licenseactivator* with License Codes**

In less common scenarios, IBM Corp. may have sent you a *license*.

```
licenseactivator licensecode[:licensecode2:...:licensecodeN]
```

- Multiple license codes are separated by colons (:).
- When using license codes, *licenseactivator* does not connect to the Internet, so you do not need to specify proxy information.

### **Installing a License Manually**

- Log in as the user who installed the license manager.

- ▶ Open a command prompt and change directories to the license manager installation directory. Note that this is the directory in which you installed the *license manager*, not the directory in which you installed IBM® SPSS® Modeler. If you accepted the default location on Windows, check the *C:\Program Files\Common Files\SafeNet Sentinel\Sentinel RMS License Manager\* folder.
- ▶ **Windows Only.** Change directories to the *winnt* subdirectory.
- ▶ Get the lock code for the server machine. At the command prompt, type *echoid* (other operating systems).
- ▶ Send the lock code and your authorization code to IBM Corp. by calling your local office or sending an e-mail message to *spsscs@us.ibm.com*. IBM Corp. will then provide a license code or a file containing a license code.
- ▶ Use *licenseactivator* to enter the license code or codes.

## ***Enabling for Temporary Usage***

If you did not install the license, you can enable IBM® SPSS® Modeler for temporary usage.

- ▶ If you have physical installation media, make sure that the DVD is in the DVD drive. If you downloaded an eImage, open and/or extract the contents of the eImage.
  - ▶ Start the WlmAdmin application. For more information, see the topic “Starting the WlmAdmin Application” on p. 12.
  - ▶ In the left pane of the WlmAdmin application, click the + sign next to Subnet Servers. If the license manager server is not listed, specify the computer by choosing Defined Server List from the Edit menu.
  - ▶ Right-click the name of the network computer on which the license manager is running and choose: Add Feature > From a File > To Server and its File
- Note:* If you select To Server rather than To Server and its File, the temporary usage information is stored in memory. You will lose this information when the network computer is rebooted.
- ▶ In the Open dialog box, type *D:\Sentinel\LicenseManager\lservrc.temp*, where *D* is your installation disk drive. If you are not using *D* for the disk drive, enter the appropriate drive location.
  - ▶ When the application displays your license, click OK. For information about viewing the license's details, see “Viewing Details about a License” on p. 13.

## ***Adding a License***

You may want to add a license at a later time. The process for adding a license is the same as installing the original license.



## Viewing Your License

You can view your network license (including the number of users) in the WlmAdmin application. For information about the WlmAdmin application and specifics about viewing the license, see “Administering the Network License” on p. 12.

## Testing the License Manager

To make sure the license manager is serving up licenses correctly, you should test it.

- ▶ Install another license manager on a Windows machine that is *not* running the license manager you want to test. For more information, see the topic “Installing the License Manager on Windows” on p. 4 .
- ▶ Start the WlmAdmin application. For more information, see the topic “Starting the WlmAdmin Application” on p. 12.
- ▶ Add the remote license manager server that you want to test. For more information, see the topic “Adding a Server” on p. 13.
- ▶ View the licenses on the remote server. For more information, see the topic “Viewing Details about a License” on p. 13.

If you are able to view the license, the license manager is ready for local desktop computers to connect to it. You can proceed with installing the product on local desktop computers. If you are not able to view the license, review the previous steps to ensure the license manager was installed correctly.

## Installing the Product on the Local Desktop Computers

*Note:* We do not officially support connecting to the network license manager through VPN.

You have two options for installing the full product locally on an end user's computer. You can manually install on each computer, or you can use an application like Systems Management Server (SMS) to push the installation to the computers running Windows.

### ***To Manually Install on a Local Desktop***

- ▶ **Make the installation media available.** Download the eImage for the product and extract the files to a shared network drive. If you have physical installation media, make as many copies of the DVD as you need or place it on a shared network drive.
- ▶ **Copy the installation instructions and prepare licensing information.** Make as many copies of the product installation instructions as you need. The installation instructions are available from the download site or, if you received physical installation media, in the *Documentation\<language>\Installation* directory on the DVD. Look for the instructions that correspond to your license type. You can distribute the full or abbreviated versions of the instructions. After installation, the end user must enter the IP address or the name of the network

computer on which the network license manager is running. Fill out this information in the space provided at the beginning of the instructions before copying them.

- **Distribute the installation materials to end users.** Distribute the installation DVD ( or network location), the installation instructions, and the licensing information to end users who can manually install on each computer as needed.

### ***To Push to the Local Desktops Running Windows***

Because IBM® SPSS® Modeler installations are compatible with Microsoft Windows Installer (MSI), you can push an installation to the end-user desktop computers.

## ***Pushing an Installation to Windows Computers***

Pushing an installation is a method for remotely distributing software to any number of end users without any user intervention. You can push the full installation of IBM® SPSS® Modeler to the end-user desktop computers running Windows. The technology that you are using for pushing the installation must support the MSI 3.0 engine or higher.

### ***Uninstalling a Previous Version***

If you are going to push to the same directory in which a previous version of IBM® SPSS® Modeler was installed, you need to uninstall the old version. You must manually uninstall any IBM® SPSS® Modeler versions prior to 11.0 since push installations were not available for those versions.

### ***Properties for Push Installations***

Following are the properties that you can use for push installations. All properties are case sensitive. Values must be quoted if they contain spaces.

Table 1-1  
*Properties for Push Installations*

Property	Description	Valid value(s)
INSTALLDIR	The directory where IBM® SPSS® Modeler should be installed on the end user's desktop computer. This property is optional. If it is excluded, the default is used.	A valid path such as C:\Program Files\IBM\SPSS\ModelerServer\15.
LICENSETYPE	The license type. The value is case sensitive.	Network
LSHOST	The IP addresses or the names of the network computer or computers on which the network license manager is running.	One or more valid IP addresses or network computer names. Multiple addresses or names are separated by colons (for example, <i>server1:server2:server3</i> ).

Property	Description	Valid value(s)
DISABLE_COMMUTE	Disables the commuter license functionality on the end user's desktop computer. If this property is specified, no shortcuts for the commuter license will be installed on the desktop computer. For more information about commuter licenses, see "Configuring Commuter Licenses" on p. 16.	1, which indicates that commuter licenses are disabled.
COMMUTE_MAX_LIFE	The maximum number of days for which an end user can check out a commuter license. For more information, see the topic "Configuring Commuter Licenses" on p. 16.	A number between 1 and 30.
COMPANYNAME	The name of your company.	Any string.

### MSI Files

The *.msi* file is located under the *modeler\<architecture>* directory on the DVD, where *<architecture>* is *32bit* or *64bit*. If you downloaded the software, you must extract the contents of the eImage to access the MSI file.

### Command Line Example

Following is a command line that you could use to push a product installation. Enter all of the text on one line.

```
MsiExec.exe /i "ClemClient.msi" /qn /L*v logfile.txt
INSTALLDIR="C:\Program Files\IBM\SPSS\ModelerServer\15" LICENSETYPE="Network" LSHOST="mylicserver"
```

### Using SMS to Push the Installation

The basic steps for using Systems Management Servers (SMS) to push IBM® SPSS® Modeler are:

- ▶ Copy the appropriate subdirectory under the *modeler\<architecture>* directory on the DVD to a directory on a network computer. If you downloaded the software, you must first extract the contents of the eImage.
- ▶ Edit the *.pdf* file located in the copied directory. Using a text editor, modify the value of *CommandLine* by adding the appropriate properties. For a list of the available properties, refer to "Properties for Push Installations" on p. 10. Make sure to specify the correct MSI file in the command line.
- ▶ Create a package from the *.pdf* file and distribute the package to the end-user desktop machines.

### ***Using Group Policy or Related Technology to Push the Installation***

- ▶ Copy the appropriate subdirectory under the *modeler\<architecture>* directory on the DVD to a directory on a network computer. If you downloaded the software, you must first extract the contents of the eImage.
- ▶ Using an application like ORCA, edit the Properties table in the appropriate *.msi* file under the copied folder. ORCA is part of the Windows 2003 Server SDK, which you can find at <http://www.microsoft.com/downloads> by searching for the SDK. For a list of the properties that you can add to the Properties table, refer to “Properties for Push Installations” on p. 10. Make sure to use the correct MSI file.
- ▶ Create a package using the edited *.msi* file and distribute the package to the end-user desktop computers.

### ***Pushing an Uninstallation***

*Note:* When you push the uninstall command, the end user loses customizations. If specific users require customizations, you can exclude those users from the distribution and ask them to install the product manually.

If you push an installation of a later version of IBM® SPSS® Modeler, you may want to uninstall first. You can do this silently by pushing the following command. Enter all of the text on one line.

```
MsiExec.exe /X{product_code} /qn /L*v logfile.txt  
ALLUSERS=1 REMOVE="ALL"
```

The product code for a specific version is in the *setup.ini* file within each version's installed folders.

## ***Administering the Network License***

The license manager maintains your network license. To administer the license manager itself and to view information about the network licenses that it is maintaining, you can use the WlmAdmin application, which is the main user interface for the license manager tools. The license manager tools are installed automatically with the network license manager on Windows.

*Note:* If you need additional administration information, refer to the SafeNet documentation, which is installed with the concurrent licensing tools. This documentation is in the *licensemanager/documentation* directory in the concurrent licensing tools installation directory.

### ***Starting the WlmAdmin Application***

#### ***From a Windows Computer where the License Manager is Installed***

- ▶ From the Windows Start menu, choose:  
[All] Programs > Sentinel RMS License Manager > Sentinel RMS Server Administration

## **Adding a Server**

Before you can administer a network license manager, you need to add its server to the WlmAdmin application. You have two options for adding the server.

### ***To Manually Add a Server***

- ▶ From the WlmAdmin application menus, choose:  
Edit > Defined Server List
- ▶ In the Defined Server List dialog, enter the name or IP address of the server on which the license manager is running.
- ▶ Click Add.
- ▶ Click OK.

The server now appears in the Defined Servers lists in the left pane of the WlmAdmin application.

### ***To View a List of Servers on the Subnet***

- ▶ In the left pane of the WlmAdmin application, click the + sign next to Subnet Servers.

A list of network license manager servers on your subnet appears. If you can't find a specific server with this method, manually add it as described above.

## **Obtaining Log Information**

If end users have difficulty checking out licenses, the log files may contain useful information. You can use the `LSERVOPTS` environment variable and the `-f <trace-log-file>` and `-l <usage-log-file>` options to specify that log files should be created. For more information about this environment variable and its options, refer to the SafeNet documentation in the *licensemanager/documentation* directory in the concurrent licensing tools installation directory.

## **Viewing Details about a License**

You can view details about licenses that you added either manually or through the License Authorization Wizard.

- ▶ In the left pane of the WlmAdmin application, click the + sign next to the license manager server to see the license(s).
- ▶ Click the name of the license. The right pane displays details about the license. Codes are used to identify the licenses. The first part of the code indicates the feature. The second part indicates the version.

### ***To See the Names Associated with the Feature Codes***

- ▶ Using a command prompt, change to the directory in which the license manager is installed.

- ▶ Type `lmshowlic <server>` (Windows) or `./lmshowlic <server>` (other operating systems), where `<server>` is the name or IP address of the server on which the license manager is running.

The output lists all the features available on the server, grouped by product and version.

## ***Setting Up Redundant License Servers***

You can set up multiple, redundant license servers that support the same users. Redundant servers can help prevent any interruption that may occur when a server crashes. Another redundant server can take over the management of the license when the first server crashes.

You will need a special authorization code to enable the redundancy feature. The authorization code shipped with the software will not enable redundancy. Be advised that by installing the code that ships with the software, you will forfeit your ability to use the redundancy feature. If you wish to enable redundancy, complete the preparation steps described below. Then contact Customer Service at [spsscs@us.ibm.com](mailto:spsscs@us.ibm.com) or call (800) 521-1337 between 8:30 A.M. and 5:00 P.M. U.S. Central Time. For customers outside of North America, please contact your local office.

There must be an odd number of servers (at least three of them), and a majority must be running at the same time. For example, if there are three redundant license servers, two of them must be running.

### ***To Prepare Each Redundant License Server***

- ▶ Install the license manager. For more information, see the topic “Installing the Network License Manager” on p. 2 .
- ▶ Using a command prompt, change to the directory in which you installed the license manager.
- ▶ Get the lock code for each server machine. At the command prompt, type `echoid` (Windows) or `./echoid` (other operating systems).
- ▶ Write down the lock code. You will need this when you contact Customer Support or your local office.
- ▶ Repeat these steps for each redundant license server.

### ***To Set Up the Redundant License Server Pool***

- ▶ If a license manager is running on any of the redundant license servers, stop the license manager on each computer.
- ▶ From the WlmAdmin application menus, choose:  
Edit > Redundant License File  
  
This action opens the WrlfTool application.
- ▶ From the WrlfTool application menus, choose:  
File > New
- ▶ For each redundant license server, click Add to specify the hostname and IP address of each server.

- ▶ Change the order of the servers to indicate the order in which the redundant license servers are used. The first one in the list is the primary server.
- ▶ Click Add License to add the license(s) that you received from Customer Service or your local office. If you received multiple licenses, be sure to add every one.
- ▶ Click OK.
- ▶ Click Done when you are finished.

#### ***To Save the Redundant License File***

- ▶ From the WrlfTool application menus, choose:  
File > Save As
- ▶ Save the redundant license file (*lservrlf*) to an easily accessible location. You will need to copy the file in the next steps.

#### ***To Configure the Redundant License Servers***

- ▶ Copy the redundant license file (*lservrlf*) to the *winnt* subfolder of the license manager installation directory on Windows. If you accepted the default location, check the *C:\Program Files\Common Files\SafeNet Sentinel\Sentinel RMS License Manager\* folder. There must be at least three redundant license servers.
- ▶ Start the license manager on each redundant license server.

#### ***To Configure End-User Computers***

When the end user installs the product, the user specifies all redundant servers, with the server names or IP addresses separated by a colon (for example, *server1:server2:server3*). The setup program then adds the necessary configuration information to the end user's computer. If the product is already installed on the desktop computers, you can perform the following manual steps to add the configuration information. You can also push an uninstall followed by a new install that defines all the servers. Refer to "Pushing an Installation to Windows Computers" on p. 10 for information about pushing installations.

- ▶ Using a text editor, open *spssprod.inf*, which is located in the product installation directory on the desktop computer.
- ▶ Comment out the line for DAEMONHOST. For example:  
  
`#DAEMONHOST=server1`
- ▶ Save *spssprod.inf*.
- ▶ Create an LSHOST environment variable. Set this variable to include all redundant servers, with the server names or IP addresses separated by a colon (for example, *server1:server2:server3*).

## **Configuring Commuter Licenses**

Commuter licenses allow your end users to check out licenses from the license manager, so that they can use the license when not connected to the network. Commuter licenses are enabled by default. Instructions for actually checking out the commuter license appear in the end user installation instructions.

You can restrict the percentage of licenses that are enabled for commuting on the license manager server. It's a good idea to restrict commuter licenses to prevent all the licenses (tokens) from being used up by commuters. After the specified percentage of licenses have been used by commuters, no more will be available until the commuter licenses expire or are checked back in. You can also configure the maximum duration for which an end user can check out a license. The default maximum duration is 3 days.

### ***To Set the Percentage of Available Commuter Licenses***

- ▶ Edit the value of the `LSERVOPTS` environment variable to include `-com <percentage>`, where `<percentage>` is a numeric value between 0 and 100 indicating the percentage of licenses that are available for commuting. Specifying 0 disables commuter licenses.
- ▶ Restart the computer on which the license manager is running.

### ***To Set the Maximum Duration for Commuter Licenses***

The maximum length of time a user can check out a commuter license is specified by the `CommuterMaxLife` setting in the `spssprod.inf` file on the *desktop*. computer. This file is located in the product installation directory on the desktop computer. Open `spssprod.inf` and look for `CommuterMaxLife`. Set the value of this option to the maximum number of days for which an end user can check out a commuter license. This should be a number between 1 and 30. You can also set this value when you push the installation. For more information, see the topic "Pushing an Installation to Windows Computers" on p. 10.

*Note:* This functionality works off the date, not the time. For example, if you set the `CommuterMaxLife` option to one day, then check a license out at 9 a.m., this license does not get checked back in until midnight on the following day. So although `CommuterMaxLife` is set to one day, the license is actually held for 39 hours.

### ***To Obtain a List of Checked Out Licenses from the Command Line***

You can find out which users have checked out licenses.

- ▶ Using a command prompt, change to the directory in which the license manager is installed.
- ▶ Type `lsmon <server>` (Windows) or `./lsmon <server>` (other operating systems), where `<server>` is the name or IP address of the server on which the license manager is running. You can omit the license server name if you want to view checked out licenses for only the localhost server.



***To Obtain a List of Checked Out Licenses from the WlmAdmin Application***

You can also view checked out licenses in the WlmAdmin application:

- ▶ In the left pane of the WlmAdmin application, click the + sign next to the license manager server.
- ▶ Click the + sign next to Clients. Clients using the network license are listed. If no clients are listed, no users are using the network license.
- ▶ Select a particular Client to view whether the client has a checked out license. Review the Detailed Information area in the right pane after selection.

***Configuring License Reservations***

You can create a reservation file, which specifies how many licenses are reserved for specific users or groups of users. Users are identified by network IDs or computer names (*not* IP addresses). For example, you can set up a reservation file that reserves the license for a group of power users. Licenses will always be available for these users. You can also use the reservations to prevent certain users from accessing the license.

***To Create a New Reservation File***

- ▶ From the WlmAdmin application menus, choose:  
Edit > Reservation File

This action opens the Wlsgmr application.

- ▶ From the Wlsgmr application menus, choose:  
File > New

***To Add Licenses and Users to the Reservation File***

- ▶ From the Wlsgmr application menus, choose:  
Feature > Add
- ▶ Click Next on the first screen of the wizard.
- ▶ Specify the feature code associated with the license that you want to reserve. Refer to “Viewing Details about a License” on p. 13 for information about getting the feature codes associated with licenses. Also define a specific version, which is entered as it appears in the WlmAdmin application (for example, 160). The version is not optional. Ignore the Capacity controls, because capacity licenses are not supported.
- ▶ Click Next.
- ▶ Specify a name for a group of users. The name is arbitrary, but you should make it descriptive (for example, Sales).
- ▶ Specify the number of licenses that are reserved for the group. Group members can still access all licenses, but the number of licenses you specify will no longer be available for users who are not included in the group. That is, if you have 10 licenses and you reserve five, members of the group have 10 licenses available to them, while other users have only five.

- ▶ On the Members window, click Add to specify a user or computer name associated with the group (do not use IP addresses). If the user or machine is included in the group, that user or machine can use the reserved license. If the user or machine is excluded from the group, that user or machine cannot access the license at all. Specify as many users or machines as needed. Note that groups must be mutually exclusive. Therefore, different groups for the same license cannot contain common users or computers.
- ▶ Click Finish when all users have been added to the group.
- ▶ Add other groups or licenses as needed. You can also modify or delete licenses and groups by right-clicking one and choosing Properties.

### ***To Save the Reservation File***

- ▶ When finished defining the reservation file, from the menus choose:  
File > Save As
- ▶ Save the file to an easily accessible location. You will need to copy the file in the next step.
- ▶ To enable the license server to automatically find the *lsreserv* file at start up, copy the file to the *winnt* subfolder of the license manager installation directory on Windows. If you accepted the default location, check the *C:\Program Files\Common Files\SafeNet Sentinel\Sentinel RMS License Manager\* folder.
- ▶ If you want the same reservations to apply for all redundant servers, copy the reservation file (*lsreserv*) to each server.
- ▶ Restart each license manager when finished.

## ***Starting and Stopping the License Manager***

The method for starting the license manager depends on your operating system.

### ***Windows***

On Windows machines, the license manager is a System Service. The service is automatically started by default. However, if you need to start it manually:

- ▶ In the Windows Control Panel, double-click Administrative Tools.
- ▶ Double-click Services.
- ▶ Locate Sentinel RMS License Manager in the Services list.
- ▶ Right-click the service and choose Start or Stop.

### ***Other Operating Systems***

On other operating systems, the license manager is a daemon service. Complete the following steps to start it manually. You can also configure the license manager to start automatically (instructions follow).

- ▶ Using the command prompt, browse to the directory in which you installed the license manager.
- ▶ **Starting.** As root, type `./lserv &` at the command prompt and press Enter.
- ▶ **Stopping.** As root, type `./lsrdown <hostname>` at the command prompt, where `<hostname>` is the network name of the computer on which the license manager is running. Then press Enter.

## ***Configuring the License Manager to Start Automatically***

### ***Windows***

- ▶ In the Windows Control Panel, double-click Administrative Tools.
- ▶ Double-click Services.
- ▶ Locate Sentinel RMS License Manager in the Services list.
- ▶ Right-click the service and choose Properties.
- ▶ Set the Startup type to Automatic.
- ▶ Click OK.

### ***Other Operating Systems***

- ▶ Add `./lserv &` to one of the operating system startup files.

## ***Uninstalling the License Manager***

### ***Windows***

- ▶ From the Windows Start menu, choose:  
Settings > Control Panel
- ▶ Double-click Add/Remove Programs.
- ▶ Select Sentinel RMS License Manager and then click Remove.
- ▶ Click Yes when prompted to remove the license manager.

### ***Other Operating Systems***

- ▶ Using the command prompt, browse to the directory to which you installed the license manager.
- ▶ As root, stop the license manager by typing `./lsrdown <hostname>` at the command prompt, where `<hostname>` is the network name of the computer on which the license manager is running. Then press Enter.

- ▶ Remove the directory where the license manager is installed.

## ***Uninstalling the Concurrent Licensing Tools***

### ***Windows***

- ▶ From the Windows Start menu, choose:  
Settings > Control Panel
- ▶ Double-click Add/Remove Programs.
- ▶ Select IBM SPSS Concurrent Licensing Tools and then click Remove.
- ▶ Click Yes when prompted to remove the concurrent licensing tools.

### ***Other Operating Systems***

- ▶ Remove the directory where the concurrent licensing tools are installed.

## ***Troubleshooting Desktop Computers***

If the end users' desktop computers are having trouble finding the license manager:

- ▶ Run `lswhere` to verify that the desktop computer can find the network computer on which the license manager is running. For more information, see the topic "Running `lswhere`" on p. 20.
- ▶ Make sure the license manager service is running on the network computer.
- ▶ Check the appropriate `spssprod.inf` file. This file is located in the product installation directory on the desktop computer. Open `spssprod.inf` and make sure `DAEMONHOST` is set to the correct name or IP address of the computer on which the license manager is running. If you are using redundant servers, this should be blank.
- ▶ If you are using redundant servers, make sure the `LSHOST` environment variable defines all of them. Each name is separated by a colon (:) character. For example, if the license manager computers are `SERVER1`, `SERVER2`, and `SERVER3`, `LSHOST` is set to `SERVER1:SERVER2:SERVER3`.

### ***Running lswhere***

You can run `lswhere` from an end user's desktop computer to check which computer is running the network license manager.

- ▶ Using a command prompt, change the current directory to the IBM® SPSS® Modeler installation directory.
- ▶ Type `lswhere`.

### ***Defining Environment Variables on End Users' Computers***

The following instructions are for defining environment variables on end users' computers.

***To Define an Environment Variable on Windows XP or Vista***

- ▶ In the Windows Control Panel, double-click System.
- ▶ Click the Advanced tab (Windows XP) or Advanced System Settings (Vista).
- ▶ Click Environment Variables.
- ▶ In the System Variables area of the tab, click New.
- ▶ In the Variable Name text box, type LSHOST.
- ▶ In the Variable Value text box, type the name or IP address of the computer on which the license manager is running—for example, myserver or 204.171.64.2.
- ▶ Click OK.

***Service and Support***

To contact IBM Corp. Technical Support, visit <http://www.ibm.com/support> and submit a case. You will need to register with IBM Corp. Technical Support if you haven't done so previously.

IBM Corp. provides public training seminars for IBM Corp. products on a regular basis. You can also arrange to have training presented onsite. For information on training seminars, visit <http://www.ibm.com/training/spss>.