



Nginx Data Collector

Cloud Insights

Tony Lavoie, Dave Grace
February 28, 2020

This PDF was generated from https://docs.netapp.com/us-en/cloudinsights/task_config_telegraf_nginx.html on May 19, 2020. Always check docs.netapp.com for the latest.



Table of Contents

- Nginx Data Collector 1
 - Installation..... 1
 - Setup 2
 - Objects and Counters..... 2
 - Troubleshooting 3

Nginx Data Collector


Cloud Insights uses this data collector to gather metrics from Nginx.

Installation

1. From **Admin > Data Collectors**, click **+Data Collector**. Under **Services**, choose Nginx.


Select the Operating System or Platform on which the Telegraf agent is installed.

2. If you haven't already installed an Agent for collection, or you wish to install an Agent for a different Operating System or Platform, click *Show Instructions* to expand the [Agent installation](#) instructions.
3. Select the Agent Access Key for use with this data collector. You can add a new Agent Access Key by clicking the **+ Agent Access Key** button. Best practice: Use a different Agent Access Key only when you want to group data collectors, for example, by OS/Platform.
4. Follow the configuration steps to configure the data collector. The instructions vary depending on the type of Operating System or Platform you are using to collect data.



Nginx Configuration
Gathers Nginx metrics.

What Operating System or Platform Are You Using?[Need Help?](#)

 Ubuntu & Debian

Select existing Agent Access Key or create a new one

Default (405fb5ec-d4cb-4404-977b-71fa931e1ad3)

+ Agent Access Key

*Please ensure that you have a Telegraf Agent in you environment before configuring [Show Instructions](#)

Follow Configuration Steps

[Need Help?](#)

- 1 If you already have a URL enabled to provide Nginx metrics, go directly to the plugin configuration.
- 2 Nginx metrics are available through a status page when the HTTP stub status module is enabled. Refer to the below link for verifying/enabling `http_stub_status_module`.

```
http://nginx.org/en/docs/http/nginx_http_stub_status_module.html
```



- 3 After verifying the module is enabled, modify the Nginx configuration to set up a locally-accessible URL for the status page:

```
server {  
    listen    <PORT NUMBER>;  
    Please specify actual machine IP address, and refrain from using a loopback address (i.e.  
    localhost or 127.0.0.1)  
    server_name <IP ADDRESS>;  
    location /nginx_status {  
        stub_status on;  
    }  
}
```



- 4 Reload the configuration:

```
nginx -s reload
```



- 5 Copy the contents below into a new `.conf` file under the `/etc/telegraf/telegraf.d/` directory. For example, copy the contents to the `/etc/telegraf/telegraf.d/cloudinsights-nginx.conf` file.

```
[[inputs.nginx]]  
  ## USER-ACTION: Provide Nginx status url  
  ## Please specify actual machine IP address where nginx_status is enabled, and refrain from  
  using a loopback address (i.e. localhost or 127.0.0.1).  
  ## When configuring with multiple Nginx servers, enter them in the format ["url1", "url2",  
  "url3"]
```



- 6 Replace `<INSERT_NGINX_ADDRESS>` with the applicable Nginx address. Please specify a real machine address, and refrain from using a loopback address.
- 7 Replace `<INSERT_NGINX_PORT>` with the applicable Nginx port.
- 8 Restart the Telegraf service.

```
systemctl restart telegraf
```



Setup

Nginx metric collection requires that Nginx [http_stub_status_module](#) be enabled.

Additional information may be found in the [Nginx documentation](#).

Objects and Counters

The following objects and their counters are collected:

Object:	Identifiers:	Attributes:	Datapoints:
Nginx	Namespace Server	Node IP Node Name Port	Accepts Active Handled Reading Requests Waiting Writing

Troubleshooting

Additional information may be found from the [Support](#) page.

Copyright Information

Copyright © 2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.