



Max-Planck-Institut
für Meteorologie

Max-Planck-Institut für Meteorologie
Bundesstr. 53
D-20146 Hamburg



Deutscher Wetterdienst
Wetter und Klima aus einer Hand

Deutscher Wetterdienst
Frankfurter Str. 135
D-63067 Offenbach

ICON User's Guide

G. Zängl, D. Reinert, F. Prill,
M. Giorgetta, L. Kornblueh, and L. Linardakis

assembled and edited by

T. Schad, I. Kraut, D. Rieger, C. Walter, S. Gruber, K. Deetz, H. Vogel, and B. Vogel



Karlsruhe Institute of Technology

Karlsruhe Institute of Technology
Institute for Meteorology and Climate Research (IMK-TRO)
Hermann-von-Helmholtz-Platz 1
D-76344 Eggenstein-Leopoldshafen

June 4, 2014

Preface

This user guide was assembled and edited based on available documents on the ICON web-page by the persons mentioned at the front page. The content of the user guide follows the requirements of DWD.

Important hints:

In chapter 4 a list of the namelist parameters is given. New and inexperienced users should only modify the namelist parameters that are given in bold letters.

When results produced with ICON are published the following papers have to be cited in the list of references:

[Zängl \(2012\)](#)

Information for authors:

Please read the README for further instructions and templates.

Contents

1	Guide for New Users	1
1.1	Needed Software	1
1.2	The Source Code	1
1.2.1	Directory structure	2
1.3	Configuration and Compilation	4
1.3.1	Description of the Configuration Files	4
1.3.2	Configuring and Compiling the Code	5
1.4	Running the Model (Idealized Cases)	6
1.4.1	Jablonowski-Williamson test	6
1.4.2	Mountain Rossby wave	7
1.5	Running the Model (Real Case)	7
1.5.1	Input Data	8
1.5.2	Creating a Runscript	10
1.5.3	Restart	10
1.5.4	Make Runscript Environment	12
1.6	Pre-built Grids and ExtPar Data	13
1.6.1	Grid file nomenclature	13
1.7	Grid Generation	14
1.7.1	ICON atmosphere grids	14
1.7.2	Creating atmosphere grids	15
1.7.3	Atmosphere grid generation parameters	15
1.7.4	Information contained in grid files	16
1.7.5	Viewing/plotting grids	17
2	Output	19
2.1	Extra output	22
3	Visualization	24
3.1	icon_plot.ncl	24
3.1.1	Requirements	24
3.1.2	Customization	24
3.1.3	Basic command line option	25
3.1.4	Plot Types	25
3.1.5	Regional plots	28
3.1.6	Masking	29
3.1.7	Data on other grids	29
3.1.8	All options	29
3.2	ncview/GrADS	29
3.3	Other Possibilities	30
4	ICON Namelists Overview	32
4.1	Namelist Annotation	32

4.2	ICON Namelists	33
4.2.1	Scripts, Namelist files and Programs	33
4.2.2	Namelist parameters	34
4.3	Namelist parameters for grid generation	34
4.3.1	Namelist parameters defining the atmosphere grid	34
4.4	Namelist parameters defining the atmospheric model	39
4.4.1	coupling_nml	39
4.4.2	diffusion_nml	39
4.4.3	dynamics_nml	41
4.4.4	echam_conv_nml	42
4.4.5	echam_phy_nml	44
4.4.6	gribout_nml	45
4.4.7	grid_nml	47
4.4.8	gridref_nml	49
4.4.9	gw_hines_nml (Scope: lgw_hines = .TRUE. in echam_phy_nml)	51
4.4.10	ha_dyn_nml	52
4.4.11	initicon_nml	53
4.4.12	interpol_nml	56
4.4.13	io_nml	58
4.4.14	les_nml (parameters for LES turbulence scheme; valid for inwp_turb=5)	61
4.4.15	limarea_nml (Scope: l_limited_area=1 in grid_nml)	62
4.4.16	lnd_nml	63
4.4.17	ls_forcing_nml (parameters for large-scale forcing; valid for torus geometry)	65
4.4.18	master_model_nml (repeated for each model)	66
4.4.19	master_nml	67
4.4.20	meteogram_output_nml	67
4.4.21	nh_pzlev_nml	67
4.4.22	nonhydrostatic_nml (relevant if run_nml:iequations=3)	68
4.4.23	nwp_phy_nml	73
4.4.24	output_nml (relevant if run_nml/output='nml')	76
4.4.25	parallel_nml	86
4.4.26	radiation_nml	88
4.4.27	run_nml	90
4.4.28	sleve_nml (relevant if nonhydrostatic_nml:ivctype=2)	93
4.4.29	time_nml	94
4.4.30	transport_nml (used if run_nml/ltransport=.TRUE.)	96
4.4.31	turbdiff_nml	98
4.4.32	vdifff_nml	100
4.5	Ocean-specific namelist parameters	100
4.5.1	ocean_physics_nml	100
4.5.2	sea_ice_nml (relevant if run_nml/forcing=2 (ECHAM))	101
4.6	Namelist parameters for testcases (NAMELIST_ICON)	102
4.6.1	ha_testcase_nml (Scope: ltestcase=.TRUE. and iequations=[0,1,2] in run_nml)	102
4.6.2	nh_testcase_nml (Scope: ltestcase=.TRUE. and iequations=3 in run_nml)	104
4.7	External data	113
4.7.1	extpar_nml (Scope: itopo=1 in run_nml)	113

Contentsiv

4.8 External packages

114

4.8.1 art_nml

114

4.9 Information on vertical level distribution

114

References

116

1 Guide for New Users

This tutorial is meant for people with some knowledge and/or experience in modelling and Linux, but which have no experience with the ICON model. In the following we will describe in short how to compile and run ICON on your machine.

1.1 Needed Software

For some components ICON uses external libraries. Therefore you will need some additional software which should be installed on your machine. The following software needed to be installed on your machine:

- NetCDF: NetCDF is a set of software libraries and self-describing, machine-independent data formats that support the creation, access, and sharing of array-oriented scientific data.
(Source: <http://www.unidata.ucar.edu/software/netcdf/>)
- GRIB: GRIB (GRIdded Binary) is a format defined by the WMO (World Meteorological Organization). The use of GRIB in ICON is optional. The ECMWF GRIB API is an application program interface accessible from C, FORTRAN and Python programs developed for encoding and decoding WMO FM-92 GRIB edition 1 and edition 2 messages. A useful set of command line tools is also provided to give quick access to GRIB messages.
(Source: <https://software.ecmwf.int/wiki/display/GRIB/Home>)
- MPI: MPI is a library specification for message-passing, proposed as a standard by a broadly based committee of vendors, implementors, and users.
(Source: <http://www.mcs.anl.gov/research/projects/mpi/>)
- OpenMP: Jointly defined by a group of major computer hardware and software vendors, the OpenMP API is a portable, scalable model that gives shared-memory parallel programmers a simple and flexible interface for developing parallel applications on platforms ranging from embedded systems and accelerator devices to multicore systems and shared-memory systems.
(Source: <http://openmp.org/wp/>)

1.2 The Source Code

You can obtain the source code on the website of DKRZ:

<https://www.dkrz.de/>

You can use the following commands to untar the ICON source code:

```
tar xfvz icon.tar.gz
```

This will create a folder `icon-1.0` inside your current directory. Within the ICON User Guide, this folder will further on be called `$ICONDIR`.

1.2.1 Directory structure

Within `$ICONDIR`, you will find a set of subdirectories. The important subdirectories are described in the following.

build

Within the `$ICONDIR/build` directory, a subdirectory with the name of your computer architecture is created at compilation. Within this subdirectory, a `bin` subdirectory containing the binary `control_model` and several further subdirectories containing the compiled module files are created at compilation.

config

Inside the `$ICONDIR/config` directory, different machine dependent configuration are stored within the configuration files. You can find a description of how to use and set up such configuration files in chapter 1.3.

data

Within the `$ICONDIR/data` directory, you will find divers input datasets. For example, there are the datasets `"rrtmg_lw.nc"` and `"ECHAM6_CldOptProps.nc"`, which are necessary for the radiation scheme (see sec. 1.5.1).

doc

Within the `$ICONDIR/doc` directory, several documentations for ICON are stored. There are according subdirectories for scientific (`$ICONDIR/doc/science`), technical (`$ICONDIR/doc/technical`) and programming style guides (`$ICONDIR/doc/style`).

externals

Within the `$ICONDIR/externals` directory, external libraries for ICON are stored. Currently, it is the `mtime` library which is used to convert different date time formats.

include

Within the `$ICONDIR/include` directory, interfaces to libraries needed by ICON are stored. Currently, the interface to the CDI library is stored inside this directory.

run

Within the `$ICONDIR/run` directory, namelist descriptor files as well as the full namelist documentation are stored. The namelist descriptor files can be used to generate runscripts. Further information can be found in [1.5](#).

src

Within the `$ICONDIR/src` directory, the source code of ICON including the main program and ICON modules can be found. The modules are ordered in several subdirectories which are described in the following.

The main program `control_model.f90` can be found inside the subdirectory `$ICONDIR/src/drivers`. Additionally, this directory contains the modules for a hydrostatic and a nonhydrostatic setup.

The configuration of an ICON run is performed within the modules inside `$ICONDIR/src/configure_model` and `$ICONDIR/src/namelists`. Modules regarding the configuration of idealized test cases can be found inside `$ICONDIR/src/testcases`.

The dynamics of ICON are inside `$ICONDIR/src/atm_dyn_iconam` and the physical parameterizations inside `$ICONDIR/src/atm_phy_nwp`. Parameterizations for the interactions with the surface can be found inside `$ICONDIR/src/lnd_phy_nwp`.

Shared infrastructure modules for 3-D and 4-D variables can be found within `$ICONDIR/src/shared`. The according routines for 2-D fields (e.g. external parameters) are stored within `$ICONDIR/src/shr_horizontal`.

Modules handling the parallelization can be found in `$ICONDIR/src/parallel_infrastructure`.

Input and output modules are stored in `$ICONDIR/src/io`.

The modules for the grid generator, as described in chapter [1.7](#) can be found inside `$ICONDIR/src/grid_generator`.

vertical_coord_table

Inside the `$ICONDIR/vertical_coord_tables` directory, information files describing the relation between model layer, pressure and height are stored.

1.3 Configuration and Compilation

To ease up the compilation a configure-file is provided which should take over the main work. This Autoconf configuration is used to analyze the computer architecture (hardware and software) and set user specified preferences, e.g. the compiler. This preferences are read from `config/mh-<OS>`, where `<OS>` is the identified operating system. Operating systems are listed in the configure-files in `$ICONDIR/config/` with the according files `mh-<OS>`. If your machine is not listed you can add a config-file with your own `<OS>` based on the given `mh-<OS>` files. If different compilers are available, the `mh-<OS>` file may contain a case construct to distinguish them. If your `<OS>` is not recognized but is one of the listed `<OS>` you can invoke the configure file with the according option `--host=$HOST`. Examples for the DWD CRAY system are given in the boxes.

1.3.1 Description of the Configuration Files

To add a specific compiler or change your compiler flags, you have to enter the `$ICONDIR/config/mh-<OS>` according to your operating system `<OS>`. For the DWD CRAY, the compiler flags in `mh-linux` look like the following:

```
cray)
    config_compiler=cray
        CC          = cc
    FC              = ftn
    F77             = "$FC"
    FFLAGS          = -v -D__LOOP_EXCHANGE -D__MIXED_PRECISION -Df2cFortran
-e Z -em -hflex_mp=conservative -hfp1 -hadd_paren -r am -Ktrap=divz,ovf
    CFLAGS          = -I${GRIB_API}/include -v -Df2cFortran
-DHAVE_CF_INTERFACE -DHAVE_LIBNETCDF -DHAVE_LIBGRIB
-DHAVE_LIBGRIB_API -O3 -D__SVN_VERSION="${SVNVERSION}"
    F77FLAGS        = "$FFLAGS"
    FCLIBS          = "-v"
    GEN_FLAGS       =
    FDEBUG          = -g -R abc
    OMPFLAG         = -mp
    DEFOPT          = -D
    DEFCOPT         = -D
    MODOPT          = -I
    MODDIR          =
;;
```

The `cray)` in this example gives the name of this specific configuration. It can be addressed by a flag at configuration. For this example, the according command to choose this setting would be `./configure --with-fortran=cray` (see section 1.3.2). Like this, you can create your own configuration by adding a new compiler.

`CC`, `FC` and `F77` are the compiler directives for C-Compiler, FORTRAN2003-Compiler and FORTRAN77-Compiler. The according compiler flags are set via `CFLAGS`, `FFLAGS` and `F77FLAGS`. The variable to set an OpenMP flag is called `OMPFLAG`. Libraries are set via `FCLIBS`.

1.3.2 Configuring and Compiling the Code

To configure the source code go to \$ICONDIR and give:

```
./configure
./build_command
```

If you want to use another compiler than the default compiler you give:

```
./configure --with-fortran=<compiler>
./build_command
```

where <compiler> is {gcc,nag,intel,pgi,cray}.

```
CRAY EXAMPLE: Configure + Make
./configure --with-fortran=cray}
./build_command
```

Note, that CRAY compiler environment (cce) versions 8.2.x do not work with ICON. The CRAY configuration is expanded to the following:

```
CRAY EXAMPLE: Configuration
ftn -I../module -v -D__LOOP_EXCHANGE -D__MIXED_PRECISION -Df2cFortran -e
Z -em -hflex_mp=conservative -hfp1 -hadd_paren -r am -Ktrap=divz,ovf
-D__ICON__ <object files> -L/usr/local/pkg/grib_api/1.11.0/CRAY/lib
-L../lib -lsupport -lgrib_api_f90 -lgrib_api -lmtime $(LAPACK_LIB)
$(NETCDF_LIB) $(HDF5_LIB) $(SZIP_LIB) $(ZLIB_LIB) $(MPI_LIB)
$(METIS_LIB) $(PROFILE_LIB) $(SCT_LIB)
```

ICON is parallelized using MPI and OpenMP. You can control the parallelization to be used by giving:

```
./configure --with-mpi/--without-mpi --with-openmp/--without-openmp
./build_command
```

By default the options are set to `--with-mpi --without-openmp`. After a successful build, you will find the ICON executable named `control_model` inside `$ICONDIR/build/<OS>/bin/`.

```
CRAY EXAMPLE: OpenMP
The CRAY Fortran compiler command includes automatically OpenMP.
Therefore, although using --without-openmp, OpenMP is used.
```

If you wish to re-configure ICON it is advisable first to clean the old setup by giving:

```
make distclean
```

Some more details on configure options can be found in the help of the configure command:

```
./configure --help
```

1.4 Running the Model (Idealized Cases)

To shed light on the functionality and the quality of the dynamical core, setups for two test cases are presented in the following. Additionally, results of these test cases are shown. These tests are classified in short deterministic test cases (typically a simulation period of about 10-30 days) and tests in a climate mode (typically a multi-year period). This section concentrates on the first class, which starts from prescribed initial conditions (ideally provided in analytic form). The simulation results are either compared to analytic solutions (if available) or high-resolution reference solutions. For testcase details the reader is referred to [Zängl et al. \(2013\)](#). Here only some special setups are described.

1.4.1 Jablonowski-Williamson test

The Jablonowski-Williamson Test ([Jablonowski and Williamson, 2006](#)) is a standard test for dynamical cores in global models and can be run for dry dynamics only - as it is intended for- but full physics can be also tested.

Setup

For full physics, two additional namelist parameters are introduced in the `testcase_nml` to control the initial moisture in the atmosphere:

- Here `rh_at_1000hpa` to be set between 0 and 1. The default is set to 0.7 which gives a quite smooth start. If you really want to see early onsets of convection and microphysics you have to tune this parameter.
- `qv_max` is usually set to $20.e - 3 kg/kg$ and refers to the maximum value in the tropics.

Input Data

GRID

Results

The **Jablonowski-Williamson steady-state test** is based on a zonally symmetric, strongly baroclinic atmosphere. Initially, it is in a hydrostatic and geostrophic balance and therefore

should remain stationary if no perturbation is imposed. Grid irregularities can disturb this stationary conditions and hence the test identifies the presence and magnitude of grid imprinting of a numerical model. For the **Jablonowski-Williamson baroclinic wave test**, a weak (and unbalanced) perturbation disturbs the initial wind. This test highlights the diffusivity (or effective resolution) of a dynamical core and the presence of phase speed errors in the advection of poorly resolved structures.

1.4.2 Mountain Rossby wave

In order to test the model dynamics in dry stage but with real or any complex topography one can choose the mountain rossby wave test and select different types of topography.

Setup

By setting this, you might want to have the turbulence scheme switched on while the rest of physics is switched OFF. Simulating dry physics means to set the tracer fields to zero. The transport is not necessary but should be switched off via the transport namelist, so the resulting namelist setting for this case is:

- `testcase_nml`
 - `nh_test_name = 'mrw_nh'`

As an extreme case the user can examine the flow over very steep mountains, by using a flow of an isothermal atmosphere with $U = 20 \text{ m s}^{-1}$ over a circular Gaussian mountain

$$h(x, y) = h_m \exp\left(-\frac{x^2 + y^2}{a^2}\right) \quad (1.1)$$

with $a = 2000 \text{ m}$ and $h_m = 4000 \text{ m}$ and 7000 m , respectively. This configuration produces slope angles of 59° and 71° . However, [Zängl et al. \(2013\)](#) recommend to avoid slope angles close to or even above 70° in scientific applications.

Input Data

GRID

Results

1.5 Running the Model (Real Case)

The ICON code, as checkout from the SVN repository, does not include runscripts. Instead the run directory (`$ICONDIR/run/`) includes several descriptor files for building grids, defining experiments and post-processings. There exist three different types of descriptor files with prefixes `grid`, `exp`, `post`:

- `grid.<name>`: to configure the grid generator, see chapter [1.7](#) for more details. It is recommended to use pre-built grids. For details, see section [1.6](#).

- `exp.<name>`: to define the namelist, which determinate the experiments.
- `post.<name>`: to define post-processing.

1.5.1 Input Data

Generally ICON requires the following input data: Grid files, external parameters, initialization (DWD analysis or IFS), input fields for radiation.

Grid Files

In order to run ICON, it is necessary to have the horizontal grid information as an input parameter. This information is stored within so-called grid files. For a ICON run, one global grid file is necessary. Additionally, if you want to nest, grid files of the nested domains are necessary, too. To improve the performance of ICON, a (optional) reduced radiation grid for each domain may be used.

The naming of the ICON-Grid is as follows: The initial icosahedron grid is refined by `<n>`-secting the edges, and further refinement is obtained by iteratively bisecting the created edges. The grid produced at the `<k>`refining iteration is named "R`<n>`B`<k>`". For further details, see the ICON Technical Documentation.

It is recommended to use pre-built grids. Further information can be found in chapter 1.6. For building own grids, the reader is referred to chapter 1.7. The names of the grid files have to be specified within the `grid_nml`:

```
&grid_nml
dynamics_grid_filename = "<INSERTFILENAME>"
radiation_grid_filename = "<INSERTFILENAME>"
```

External Parameters

ICON requires geographical localized datasets like the topographic height of the earth surface, the plant cover, the distribution of land and sea and, dependent on the schemes used, a variety of other so called external parameters. The EXTPAR software system (EXTPAR - External Parameter for Numerical Weather Prediction and Climate Application) is able to generate external parameters for the different models GME, COSMO, HRM and ICON. The software can run on a UNIX or Linux systems where the raw data is stored. It allows operators (experienced users) running the scripts to create new external parameters controlled by user specifications like the model domain. For a more detailed overview of EXTPAR, the reader is referred to the User and Implementation Guide of EXTPAR.

The name of the EXTPAR file which has to be read by ICON can be specified as follows:

```
&extpar_nml
extpar_filename = "<INSERTFILENAME>"
```

If not specified explicitly, ICON uses the following file name:

"<path>extpar_<gridfile>".

<path> and <gridfile> are then replaced at runtime by ICON.

Initialization

For the initialization of ICON, input data from either DWD or IFS is needed.

In case of DWD (init_mode=1) a first guess and an analysis is required:

```
&initicon_nml
dwdfg_filename = "<INSERTFILENAME>"
dwdana_filename = "<INSERTFILENAME>"
```

If not specified explicitly, ICON uses the following file names:

"<path>dwdFG_R<n>B<k>_DOM<idom>.nc" and

"<path>dwdana_R<n>B<k>_DOM<idom>.nc".

<path>, <n>, <k> and <idom> are then replaced at runtime by ICON according to the chosen gridfile (see 1.5.1). The variable <idom> is an index for the domain on which the calculations are performed. <idom>=0000 is reserved for a reduced radiation grid, <idom>=0001 for the global domain, higher numbers are used for nested domains. NETCDF as well as GRIB2 input can be used.

In case of IFS (init_mode=2) an analysis is required. It has to be in NetCDF:

```
&initicon_nml
ifs2icon_filename = "<INSERTFILENAME>"
```

If not specified explicitly, ICON uses the following file name:

"<path>ifs2icon_R<n>B<k>_DOM<idom>.nc".

<path>, <n>, <k> and <idom> are then replaced at runtime by ICON according to the chosen gridfile (see 1.5.1). The variable <idom> is an index for the domain on which the calculations are performed. <idom>=0000 is reserved for a reduced radiation grid, <idom>=0001 for the global domain, higher numbers are used for nested domains.

Radiation

ICON requires input fields for the RRTM radiation scheme. The file names are specified as follows:

```
&nwp_phy_nml
lrtm_filename = "<INSERTFILENAME>"
cldopt_filename = "<INSERTFILENAME>"
```

If not specified explicitly, ICON uses the following file names:

"rrtmg_lw.nc" and

"ECHAM6_CldOptProps.nc".

The files can be found within \$ICONDIR/data.

1.5.2 Creating a Runscript

To create a runscript, new users are advised to use the namelist descriptor file `exp.nh_oper` which contains recently recommended namelist settings. It might be necessary to account for the file names and paths of the input data. Additionally, machine dependent settings need to be added to this script to obtain a runscript. For some architectures, this step can be performed by using the make runscript environment as shown in 1.5.4. In the following, example settings for DWD CRAY are listed.

```
CRAY EXAMPLE: Environment variables
#!/bin/ksh
#=====
#PBS -q xc_normal
#PBS -l select=:ncpus=:mpiprocs=:ompthreads=:mem=?gb
#PBS -l place=scatter
#PBS -j oe
#PBS -N <<Jobname>>

export MPICH_RMA_OVER_DMAPP=1
```

```
CRAY EXAMPLE: Namelists
<<Place your namelists e.g. from exp.nh_oper here>>
```

```
CRAY EXAMPLE: Submitting a job
aprun                                \
  -n <<INSERT: MPI Tasks>>          \
  -N <<INSERT: MPI Tasks/Node>>      \
  <<INSERT: Hyperthreading e.g. 2 -> 20 physical -> 40 "virtual" cores>> \
  -d <<INSERT: Threads/MPI Task>>   \
  -m <<INSERT: Amount of memory to use>> control_model
```

1.5.3 Restart

A restart of the model requires a restart file that has to be created by a previous model run. In the following the procedures and the corresponding namelist settings are explained.

Creating the initial restart file:

The first job in a series of model runs creates the first restart file. To do so we have to use the following namelist switches.

```
&master_nml
lrestart = .FALSE.
```

In addition we have to prescribe at which time interval the job should produce a restart file:


```
&io_nml
dt_checkpoint = "<Insert time in seconds>"
```

The ICON run then creates restart files for each domain 1, ..., `n_dom`, and for each restart output time step.

The filenames are generic and look like:

```
"<gridfile>_restart_<modeltype>_<timestamp>.nc",
```

An example would be:

```
"iconR2B06_DOM01_restart_atm_20110101T001200Z.nc"      (NetCDF format)
```

This filename can be customized using the namelist parameter:

```
&mo_run_nml
restart_filename = "<INSERTFILENAME>"
```

This file contains:

- data
- namelists
- several attributes

Note: - ICON reads the namelists only once and assumes that these are identical for all domains. - Since we do not know about the total number of domains at startup, we have to ask the current restart file for the attribute "`n_dom`".

For each domain 1, ..., `n_dom`, a symbolic link is generated with the generic name:

```
"restart_<modeltype>_DOMxx.nc"
```

Note: - The domain-dependent suffix "`...DOMxx`" is also required for non-nested setups.

Running the model in the restart mode:

ICON has to be informed that you want to carry out a restart run:

```
&master_nml
lrestart = .TRUE.
```

The generic link "`restart_<modeltype>_DOMxx.nc`" is used by the restart run to point to the last written restart file of the previous model run.

Chain of restart runs

If a chain of restart runs is foreseen it is recommended to use the namelist parameter `dt_restart`.

```
&time_nml  
dt_restart = "<Insert time in seconds>"
```

In this case only one restart file is produced by each model run and after writing the restart file the job stops.

Note:- `dt_restart` and `dt_checkpoint` have to be selected carefully.

Asynchronous in- and output:

It is highly recommended that the asynchronous in- and output option of ICON is applied. In short this option reserves a number of processors for in- and output only. While reading and writing the remaining processors continuously carry out calculations. Otherwise they would have to wait until in- or output is finished. The corresponding namelist parameter is:

```
&parallel_nml  
num_restart_procs = n
```

`n` is the number of processors used for in- and output.

Note: `n=1` is the most efficient selection.

1.5.4 Make Runscript Environment

A full listing of descriptor files you will find in `$ICON/run/`.

After configuration and compiling (chapter 1.3) these descriptor files can be transformed into runscripts, which should include the necessary system dependent parameters and the execution section `exec.icon` (`$ICONDIR/run/exec.iconrun`), which starts the actual integration. This transformation is done in `$ICONDIR` by:

```
./make_runscripts
```

This transforms every existing descriptor file in `$ICONDIR/run/<type>.<name>` into a ready-to-use run script `$ICONDIR/run/<type>.<name>.run`

For illustration there exists also

```
./make_my_runscripts
```

which transforms a single descriptor file into a run script. This file is an exemplary file and you can see how to define run parameters.

An exemplary descriptor file for a operational run is `exp.nh_oper`.

Note: if you change, or create a descriptor you will need to (re)create the run script in order for the changes to take effect.

To run a script `<type>.<name>.run`, either for creating grids or making an experiment or doing post-processing, go to the `./run` folder

```
cd run
```

and use the job submission command, which depends on your machine:

```
[<submit>] <type>.<name>.run
```

[<submit>] is something like: `{llsubmit,qsub}`

Note: Before (!) running an experiment, the ICON grids must be available to the model. For this purpose, either pre-built grids and ExtPar Data can be used (see Sec. 1.6) or create own grids (1.7). For a new user, it is suggested to use pre-built grids first.

1.6 Pre-built Grids and ExtPar Data

A list of grid files has been pre-built for the ICON model together with the corresponding reduced radiation grids and the external parameters.

1. The **primary storage** location for ICON grids is

```
blizzard:/pool/data/ICON/grids/public
```

2. Every 24h the contents of the primary storage directory are mirrored to DWD's HPC.
3. Every 24h the contents of the primary storage directory are mirrored to a public web site: <http://icon-downloads.zmaw.de>.

Each grid file consists of a NetCDF file and a GPG signature file

(http://de.wikipedia.org/wiki/GNU_Privacy_Guard).

The signature file makes sure that a grid file is complete and verifies the authorship.

1.6.1 Grid file nomenclature

The grids are identified by

- a **centre** number

- a **subcentre** number
- a **numberOfGridUsed** which is simply an integer number, increased by one with every new ‘official’ grid.

The grid files and the external parameter files are named accordingly, e.g.,

```
icon_grid_0001_RxxByy_G.nc
icon_extpar_0001_RxxByy_G.nc
```

where the name components are as follows:

```
icon _ grid _ 0001 _ R 02 B 06 _ R .nc
                        (radiation/reduced)
icon _ extpar _ 0002 _ 03 07 _ G .nc
                        (global)
...      ...      ...
```

The **numberOfGridUsed** parameter is part of the file name (0001, ...) and makes this file name unique.

In general, a lookup table is required to find the actual file name to which a set of these parameters corresponds. This ‘table file’ is located under

http://icon-downloads.zmaw.de/dwd_grids.xml

(the table file itself is under version control: https://svn.zmaw.de/svn/icon_grid_table).

1.7 Grid Generation

1.7.1 ICON atmosphere grids

The ICON horizontal spherical grid is based on the projection of the icosahedron on the sphere. This is a 2-dimensional grid, representing the earth’s surface. For defining the vertical discretization see the Experiments section. The ICON grids need to be created, stored as NetCDF files, and consequently used by the ICON model. Alternatively, already stored grids maybe used.

The initial icosahedron grid is refined by $\langle n \rangle$ -secting the edges, and further refinement is obtained by iteratively bisecting the created edges. The grid produced at the $\langle k \rangle$ refining iteration is named “R $\langle n \rangle$ B $\langle k \rangle$ ”, and the corresponding NetCDF-file is “iconR $\langle n \rangle$ B $\langle k \rangle$ -grid.nc”. The grid files, after their creation, are located in the ./grids folder.

Examples of grids are in Grids. More information can be found in [\\$ICONDIR/doc/technical/icon_grid.pdf](#)

1.7.2 Creating atmosphere grids

The descriptor file for creating the atmosphere grids is `./run/grid.create_atmo_grids`. It generates 5 levels of icon grids using spring dynamics and symmetry optimizations. In addition it creates an hierarchy of three nested grids for the `exp.nat_jww_nwp_mpiomp` experiment (source: `$ICONDIR/run/exp.nat_jww_nwp_mpiomp`).

For creating the run script `$ICONDIR/run/grid.create_atmo_grids.run`, give

```
./make_runscripts
```

To submit it, go to `$ICONDIR/run` and give

```
[<submit>] grid.create_atmo_grids.run
```

See chapter 1.5 how to generate run scripts for more information on creating and running scripts.

After running the `grid.create_atmo_grids.run`, the NetCDF-grid-files will be located in the `$ICONDIR/grids` folder.

Note that the grid generator is only OpenMP parallelized and not MPI parallelized.

1.7.3 Atmosphere grid generation parameters

In the beginning of the descriptor file `$ICONDIR/run/grid.create_atmo_grids` the basic atmosphere grid generation parameters are defined:

```
#-----
# if make_patches="true", the hierarchy of nested patches
#   iconR2B03_DOM00.nc, iconR2B04_DOM01.nc, iconR2B05_DOM02.nc
#   will be created
make_patches="true"

# define number of levels (bisections) to create
no_of_levels=5

#define optimization
use_spring_optimization="true"
use_symmetry_optimization="true"
start_optimize=2
end_optimize=$no_of_levels

# define refinement method
refinement_method=1      # 1=edge bisection, 2=dual centers
#-----
```

The script variable `no_of_levels` defines the number of bisecting iterations (after the initial bisection), and determines the horizontal resolution. It is set to `no_of_level=5`, giving in the highest resolution the triangular grid R2B05 of 81920 triangles, with a mean distance of 70 km between triangle circumcenters, where scalars are defined. You may increase the resolution by increasing the `no_of_levels`.

1.7.4 Information contained in grid files

The ICON grids are treated as a general unstructured grid, so the grid NetCDF-files contain the full information of the location and the connectivity of all the grid entities (cells, edges and vertices). The grid nesting hierarchy information is also included.

Some basic variables that may be useful for plotting are:

```
double clon(cell)           : longitude of cell centers [radian]
double clat(cell)           : latitude  of cell centers [radian]
double clon_vertices(cell, nv) : longitudes of the vertices of the cell [radian]
double clat_vertices(cell, nv) : latitudess of the vertices of the cell [radian]
double elon(edge)           : longitude of edge midpoint [radian]
double elat(edge)           : latitude  of edge midpoint [radian]
double elon_vertices(edge, no) : longitudes of the vertices of the edges [radian]
double elat_vertices(edge, no) : latitudes  of the vertices of the edges [radian]
double vlon(vertex)          : longitude of vertices [radian]
double vlat(vertex)          : latitude  of vertices [radian]
...
double cell_area(cell)        : area of grid cell [m2]
double cell_elevation(cell)   : elevation at the cell centers [m]
int    cell_sea_land_mask(cell): sea (-2 inner, -1 boundary)
                                land (2 inner, 1 boundary) mask for the cell
...
double edge_length(edge)      : lengths of edges of triangular cells [m]
double dual_edge_length(edge) : lengths of dual edges (distances between
                                triangular cell circumcenters) [m]
...
```

For a full listing of variables contained in a grid file, for instance in `iconR2B04-grid.nc`, use:

```
ncdump -h iconR2B04-grid.nc
```

or

```
cdo sinfov iconR2B04-grid.nc
```

More details on the grid fields can be found [here](#).

1.7.5 Viewing/plotting grids

In order to plot an icon grid you should ensure that `ncl-6.0` and `cdo-1.5.4` is available on your machine. Then go to the `$ICONDIR/grids/` folder and give:

```
alias iplot="ncl $ICONDIR/scripts/postprocessing/tools/icon_plot.ncl
'altLibDir="$ICONDIR/scripts/postprocessing/tools/"' iplot 'iFile="<grid file name>"'
'mapType="ortho"' 'varName="cell_sea_land_mask"' 'oType="png"' 'showGrid=True'
'lStrg="Cell sea land mask"' 'bStrg=""'
```

The above example will plot cell sea land mask. More details on plotting can be found at the Visualization chapter.

The `$ICONDIR/run/post.plot_icon_grids` script can be used to plot nested grids. Go to `$ICONDIR/run/` folder and give:

```
./post.plot_icon_grids
```

A PDF-file with a plot of the `iconR2B04.DOM01` and `iconR2B05.DOM02` grids will appear on your screen. (Note that this process is time consuming.)

Discussion

Document last edited by *S Gruber* on *08-01-2014* Document last edited by *B Vogel* on *27-05-2014*.

2 Output

In general the user has to specify six individual quantities to generate output of the model. These are:

1. The time interval between two model outputs.
2. The name of the output file.
3. The name of the variable.
4. The procedure (eg. single variable, or a variable group).
5. The type of the vertical output grid (e.g. pressure levels or model levels).
6. The type of the horizontal output grid (e.g. ICON grid or geographical coordinates).

ICON offers the possibility to write groups of variables. In the following we will present two examples to demonstrate the options the user has to prescribe these quantities. A detailed description of all namelist parameters available to organize the output is described in `output_nml` in the namelist section.

Variable groups

First we explain the meaning of variable groups. Using the "`group:`" keyword for the namelist parameters `ml_varlist`, `hl_varlist`, `pl_varlist`, sets of common variables can be added to the output:

<code>group:all</code>	output of all variables (caution: do not combine with <u>mixed</u> vertical interp
<code>group:atmo_ml_vars</code>	basic atmospheric variables on model levels
<code>group:atmo_pl_vars</code>	same set as <code>atmo_ml_vars</code> , but except pres
<code>group:atmo_zl_vars</code>	same set as <code>atmo_ml_vars</code> , but expect height
<code>group:nh_prog_vars</code>	additional prognostic variables of the nonhydrostatic model
<code>group:atmo_derived_vars</code>	derived atmospheric variables
<code>group:rad_vars</code>	
<code>group:precip_vars</code>	
<code>group:cloud_diag</code>	
<code>group:pbl_vars</code>	
<code>group:phys_tendencies</code>	
<code>group:land_vars</code>	
<code>group:multisnow_vars</code>	tile-averaged variables

There exists a special syntax which allows to remove variables from the output list, e. g. if these undesired variables were contained in a previously selected group.

Typing "-i`varname`" (for example "-temp") removes the variable from the union set of group variables and other selected variables. Note that typos are not detected but that the corresponding variable is simply not removed!

Example 1

We will begin with an individual variable which is written in NETCDF format on pressure levels and is interpolated to a horizontally regular lat-long grid:

```
NAMELIST EXAMPLE
&output_nml
  filetype                = 4    ! output format: 2=GRIB2, 4=NETCDFv2
  dom                     = 1    ! write output for domain 1
  output_bounds           = 0., 1.E7, 3600. ! start, end, interval in s.
  steps_per_file          = 50   ! max. num. of time steps within one file
  mode                    = 1    ! 1: forecast mode (relative t-axis)
  include_last            = .TRUE. ! include the last time step
  output_filename         = '<INSERTFILENAME>' ! file name base
  pl_varlist              = 'geopot' ! name of pressure level field
  remap                   = 1    ! output is transferred to lat long grid
  reg_lon_def              = 0.,0.5,359.5 !start, incr., end, in deg.
  reg_lat_def             = 90.,-0.5, -90. !start, incr., end, in deg.
```

Example 2

The flexibility of the options ICON offers is demonstrated in another example. Now we apply another possibility to define the runtime of ICON, write several variables, at the same time, in one data set, on pressure levels, and on the original horizontal grid of ICON. In addition the example below shows the options when several model domains run at the same time and we want to produce output for all model domains.

```
NAMELIST EXAMPLE
&output_nml
  dom                     = -1 ! write all domains
  steps_per_file          = 5   ! max. num. of time steps within
  output_start            = "1978-01-01T00:00:00Z" ! ISO-format date+time
  output_end              = "1979-01-02T00:00:00Z" ! ISO-format date+time
  output_interval         = "PT01H"                ! ISO-format interval
  file_interval           = "PT01D"                ! ISO-format interval
  include_last            = .FALSE.
  output_filename         = '<INSERTFILENAME>'      ! file name base
  ml_varlist='u', 'group:precip_vars' ! Individ. variable and variable group
  output_grid             = .TRUE. ! Output on the ICON horizontal grid
```

Data format

ICON offers the possibility to produce output either in NETCDF or GRIB2 format. This can be chosen by the namelist parameter `filetype` of the namelist `&output_nml`. New users are suggested to set `filetype=4` in order to use NETCDF output.

In GRIB2, a variable is uniquely defined by the following set of metadata:

- *Discipline* (see GRIB2 code table 4.2)
- *ParameterCategory* (see GRIB2 code table 4.2)
- *ParameterNumber* (see GRIB2 code table 4.2)
- *typeOfFirstFixedSurface* and *typeOfSecondFixedSurface* (see GRIB2 code table 4.5)
- *stepType* (instant, accum, avg, max, min, diff, rms, sd, cov, ...)

A documentation of the official WMO GRIB2 code tables can be found on the website of WMO [here](#).

In the following, *typeOfFirstFixedSurface* and *typeOfSecondFixedSurface* will be abbreviated by *Lev-Typ 1/2*. The available output fields are listed in tabular form.

Asynchronous in- and output:

It is highly recommended that the asynchronous in- and output option of ICON is applied. In short this option reserves a number of processors for in- and output only. While reading and writing the remaining processors continuously carry out calculations. Otherwise they would have to wait until in- or output is finished. The corresponding namelist parameter is:

```
&parallel_nml
num_io_procs = n
```

`n` is the number of processors used for in- and output.

Time stamp format

The namelist parameters `output_start`, `output_end`, `output_interval` allow the specification of time stamps according to ISO 8601. The general format for time stamps is `YYYY-MM-DDThh:mm:ss` where `Y`: year, `M`: month, `D`: day for dates, and `hh`: hour, `mm`: minute, `ss`: second for time strings. The general format for durations is `PnYnMnDnHnMnS`. See, for example, http://en.wikipedia.org/wiki/ISO_8601 for details and further specifications.

NOTE: as the `mtime` library underlaying the output driver currently has some restrictions concerning the specification of durations:

1. Any number `n` in `PnYnMnDnHnMnS` must have two digits. For instance use `"PT06H"` instead of `"PT6H"`
2. In a duration string `PnyearYnmonMndayDTnhrHnminMnsecS` the numbers `nxyz` must not pass the carry over number to the next larger time unit: `0j=nmonj=12`, `0j=nhrj=23`,

0_i=nmin_i=59, 0_i=nsec_i=59.999. For instance use "P01D" instead of "PT24H", or "PT01M" instead of "PT60S".

Soon the formatting problem will be resolved and the valid number ranges will be enlarged. (2013-12-16).

2.1 Extra output

1. In the namelist `run_ctl` set the number of fields with `inextra_2d` or `inextra_3d`. The logical variable for output `lwrite_extra` then will be set automatically. Note, the number of extra fields is limited by 9 each for 2D and 3D.
2. USE these variables in the module needed.
3. Implement the storage of wished fields by using the nonhydrostatic diagnostic type with `p_diag%extra_2d/3d`.

Example for the use of `p_diag%extra_2d`:

```
USE mo_global_variables, ONLY: inextra_2d
...
DO jc = i_startidx, i_endidx
  p_diag\%extra_2d(jc,jb,1)= yxz(jc,jb)
ENDDO
```

Discussion

Document last edited by *I. Kraut* on *29.11.2013* Document last edited by *S Gruber* on *08-01-2014* Document last edited by *B Vogel* on *27-05-2014* .

3 Visualization

Visualizing data on a non-regular grids is a task on its own, because the number of tools for solving such problem is very limited. NCL is one of them and we chose it as the main tool for ICON. On its website, you can find [several examples](#) of how to write simple plot scripts for ICON data sets. The coordinate information is essential for writing your own plot scripts. ICON output files currently have three different types of them: cells, edges and vertices, e.g. tracers like temperature and salinity and surface elevation are defined on each cell center while the normal velocity is defined on edges.

3.1 icon_plot.ncl

For getting around the different coordinates and in order not to rewrite things there is a general plot scripts: `icon_plot.ncl`. It supports contour and vector plots, a combination of both via overlaying and vertical sections. Both atmosphere and ocean vertical coordinate systems can be handled by it: While ocean uses a plain depth axes, atmosphere model uses hybrid sigma pressure levels (hydrostatic) and free 3D height variable (non-hydrostatic).

The script `icon_plot.ncl` is a single NCL program, which provides multiple plot types for data on ICON's grid. It is located in the ICON-repository under `source:/trunk/icon-dev/scripts/postprocessing/tools/icon_plot.ncl`. Most of the functionality is implemented in a library: `icon_plot_lib.ncl` located in `source:/trunk/icon-dev/scripts/postprocessing/tools/icon_plot_lib.ncl`. Both files are installed into the `/pool/data/ICON/tools` which is the default lookup location for the library. For different location like an icon checkout, use `altLibDir`, e.g. `altLibDir='/home/user/src/icon-dev/tools'`.

3.1.1 Requirements

- [NCL 5.2.1](#) is the minimum version of NCAR's plotting language
- [CDO](#)

3.1.2 Customization

`icon_plot.ncl` optionally reads a configuration file named `$HOME/.icon_plot.rc` where default options can be set. Actually it is handled like an ordinary ncl file. This can be used to customize the `altLibDir` setting, e.g.:

```
altLibDir="/home/ram/src/git/icon/scripts/postprocessing/tools"
oType="png"
```

3.1.3 Basic command line option

Required are options for

1. **Input/output files:** Use the variable `iFile` for defining the input and `oFile` for the output file. It's extension depends on the output type, which can be set with `oType`. If `oFile` is left out, the output file will inherit its name from the input file.
2. **Variable selection:** Depending on the plot mode you like to use, `varName` for scalar variables or `vecVars` for vector-variables must be used.

Optional (default:0) parameter are

1. **Level selection:** Levels can only be selected by their index. That's why, the corresponding variable is called `levIndex`. Please note that it starts with 0, like any other NCL indices.
2. **Time selection:** Like `levIndex`, the variable `timeStep` can be used to select a certain time step, again starting from 0.

There are many more parameters (see 3.1.8) for mapping, transections, selecting regions and masking, but these are the most fundamental ones.

3.1.4 Plot Types

For flexibility the selection of a specific plot mode is implemented by combining certain options.

Contour plots

Contour plot are the default plot mode. If only the required parameters are set, e.g. `iFile` and `varName`, a simple contour plot is created with


```
ncl icon_plot.ncl 'varName="T"' 'iFile="iFILENAME"'
```

This is a basic temperature plot. Captions are set to basic information like variable name, time and level information and input filename.

Vector plots


Use `vecVars` instead of `varName`. To adjust the length of the reference vector, use the variable `vecRefLength`.

```
ncl icon_plot.ncl 'vecVars="U V"' 'iFile="iFILENAME"' vecRefLength=0.01
```



Prgr icon_plot.ncl: Wed Nov 30 14:28:49 CET 2011,ram

Figure 3.1: Example of contour plot




Prgr icon_plot.ncl: Wed Nov 30 14:39:10 CET 2011,ram

Figure 3.2: Example of vector plot

Overlay of scalar and vector variables

Contour and vector plots can be combined into a single plot by overlaying both. Following this approach, such an overlay plot will be created, if `varName` and `vecVars` are given:

```
ncl icon_plot.ncl 'varName="T"' 'iFile="iFILENAME"' 'vecVars="U V"'
```



Pgr icon_plot.ncl: Wed Nov 30 14:51:24 CET 2011,ram

Figure 3.3: Example of overlay plot


Vertical sections

Data for sections have to be interpolated first. This is done internally and you do not have to care about it. Section plots are created, if a start and end point of a section is given. For this purpose, the variables `secLC` (section-left-corner) and `secRC` (section-right-corner) have to be used. These variables have to be (lon,lat) arrays like `secLC=(/20.,30./)`.

Example call:

```
ncl icon_plot.ncl 'varName="T"' 'iFile="iFILENAME"' \
  'secLC=(/0,80/)' 'secRC=(/0,-80/)'
```

`secPoints` is an option to set the accuracy of the plot. The representing of the location of the section is suppressed by setting `showSecMap=False`. Its default value is `True`.



Prgr icon_plot.ncl: Wed Nov 30 15:05:50 CET 2011,ram

Figure 3.4: Example of vertical sections plot

Display the ICON grid

Set the parameter `showGrid` to `True` and for scalar variables, the ICON grid is represented instead of the contour plot. For large grids, this can take a long time.

3.1.5 Regional plots

Use the variables `mapLLC` (map-Lower-Left-Corner) and `mapURC` (map-Upper-Right-Corner) to select special regions of the earth. Here is a list of useful examples:

Table 3.1: Examples of useful regional plots

Trop. Atlantic	'mapLLC=(/-60, -25/)'	'mapURC=(/ 25,25/)'
North Polar	'mapLLC=(/-200, 20/)'	'mapURC=(/160,90/)'
North Atlantic	'mapLLC=(/-100,-15/)'	'mapURC=(/ 35,65/)'
Labrador/Panama	'mapLLC=(/-200, -5/)'	'mapURC=(/ 35,85/)'
North Atlantic/Eurasia	'mapLLC=(/ -80, -5/)'	'mapURC=(/ 75,85/)'
Asia	'mapLLC=(/ 20,-15/)'	'mapURC=(/160,85/)'

3.1.6 Masking

Masking can be done in two different ways:

1. Manually mask the data with CDO before running the plot scripts, i.e. use the `ifthen` operator or perform a division with the mask variable:

```
cdo div iconInput.nc -selname,mask_variable iconInput.nc maskedOutput.nc
```

2. Let the plot script perform the masking using the NCL's `mask` function. For this purpose, the commandline variables `maskName` and `maskFile` have to be used. If the mask variable is part of the regular input file, `maskFile` can be left out.

Both methods have their pros and cons. Whereas the second methods works fine for all types of horizontal representation, the first produces better results for vertical cross sections.

3.1.7 Data on other grids

Although `icon_plot.ncl` is implemented for ICON, it can be used for data an regular grids, too. In this case, internal interpolation is not performed.

3.1.8 All options

`icon_plot.ncl` has built-in documentation of all options. Use

```
ncl icon_plot.ncl help=True
```

3.2 ncview/GrADS

[Ncview](#) and [GrADS](#) can be used after converting icon data sets to a regular grid. This can easily be done with `cdo`:

```
cdo -P 8 -r remapnn,r180x90 icon.nc regular_icon.nc
```

This uses nearest neighbor interpolation and hereby keeps the model values. When using a higher regular resolution the triangular icon grid keeps visible.

3.3 Other Possibilities

- GMT is useful, when the grid should be visualized.
- ParaView is an alternative to display data on an unstructured grid. As a caveat, the model output has first to be converted into the vtk format.

Discussion

Document last edited by *I. Kraut* on *29.11.2013*.

Note: -

4 ICON Namelists Overview

4.1 Namelist Annotation

Every ICON run generates annotated lists of namelist parameters during the setup. These lists are written to text files `nml.atmo.log`, `nml.cpl.log`, `nml.ocean.log` and have the following form:

```
NAMELIST IO_NML
  OUT_EXPNAME      'case4'                [...] (truncated)
                  >> DEFAULT: 'IIIEEEETTTT' [...] (truncated)

  OUT_FILETYPE     2
  LKEEP_IN_SYNC    F
  DT_DATA          43200.000000000000
                  >> DEFAULT: 21600.000000000000
  DT_DIAG          1728000.0000000000
                  >> DEFAULT: 86400.000000000000
```

and so on.

The **DEFAULT** annotation denotes all those parameters that have been modified by the user; in this case the default value of the namelist parameter is stated together with the modified value. All other namelist parameters are listed only with their default values.

4.2 ICON Namelists

4.2.1 Scripts, Namelist files and Programs

Run scripts starting the programs for the grid generation and the models are stored in run/. These scripts write namelist files containing the specified Fortran namelists. Programs are stored in < icon home>/build/<architecture>/bin/.

Table 4.1: Namelist files

Namelist file	Purpose	Made by script	Used by program
NAMELIST_GRAPH	Generate graphs	create_global_grids.run	grid_command
NAMELIST_GRID	Generate grids	create_global_grids.run	grid_command
NAMELIST_GRIDREF	Gen. nested domains	create_global_grids.run	grid_command
NAMELIST_ICON	Run ICON models	exp_iiname _i .run	control_model

4.2.2 Namelist parameters

The following subsections tabulate all available Fortran namelist parameters by name, type, default value, unit, description, and scope:

- *Type* refers to the type of the Fortran variable, in which the value is stored: I=INTEGER, L=LOGICAL, R=REAL, C=character string
- *Default* is the preset value, if defined, that is assigned to this parameter within the programs.
- *Unit* shows the unit of the control parameter, where applicable.
- *Description* explains in a few words the purpose of the parameter.
- *Scope* explains under which conditions the namelist parameter has any effect, if its scope is restricted to specific settings of other namelist parameters.

Information on the file, where the namelist is defined and used, is given at the end of each table.

4.3 Namelist parameters for grid generation

4.3.1 Namelist parameters defining the atmosphere grid

graph_ini (NAMELIST_GRAPH)

Parameter	Type	Default	Unit	Description	Scope
nroot	I	2		root subdivision of initial edges	
grid_levels	I	4		number of edge bisections following the root subdivision	
lplane	L	.FALSE.		switch for generating a double periodic planar grid. The root level consists of 8 triangles.	

Defined and used in: src/grid_generator/mo_io_graph.f90

grid_ini (NAMELIST_GRID)

Parameter	Type	Default	Unit	Description	Scope
nroot	I	2		root subdivision of initial edges	
grid_levels	I	4		number of edge bisections following the root subdivision	
lplane	L	.FALSE.		switch for generating planar grid. The root level consists of 8 triangles.	

Defined and used in: `src/grid_generator/mo_grid_levels.f90`

grid_options (NAMELIST_GRID)

Parameter	Type	Default	Unit	Description	Scope
x_rot_angle	R	0.0	deg	Rotation of the icosahedron about the x-axis (connecting the origin and [0°E, 0°N])	
y_rot_angle	R	0.0	deg	Rotation of the icosahedron about the y-axis (connecting the origin and [90°E, 0°N]), done after the rotation about the x-axis.	
z_rot_angle	R	0.0	deg	rotation of the icosahedron about the z-axis (connecting the origin and [0°E, 90°N]), done after the rotation about the y-axis.	
itype_optimize	I	4		Grid optimization type 0: no optimization 1: Heikes Randall 2: equal area 3: c-grid small circle 4: spring dynamics	
l_c_grid	L	.FALSE.		C-grid constraint on last level	

Parameter	Type	Default	Unit	Description	Scope
maxlev_optim	I	100		Maximum grid level where the optimization is applied	i_type_optimize = 1 or 4
beta_spring	R	0.90		tuning factor for target grid length	i_type_optimize = 4

Defined and used in: `src/grid_generator/mo_grid_levels.f90`

plane_options (NAMELIST_GRID)

Parameter	Type	Default	Unit	Description	Scope
tria_arc_km	R	10.0	km	length of triangle edge on plane	lplane=.TRUE.

The number of grid points is generated by root level section and further bisections. The double periodic root level consists of 8 triangles. The spatial coordinates are $-1 < x \leq 1$, and $-\sqrt{3}/2 < y \leq \sqrt{3}/2$. Currently the planar option can only be used as an *f*-plane.

Defined and used in: `src/grid_generator/mo_grid_levels.f90`

gridref_ini (NAMELIST_GRIDREF)

Parameter	Type	Default	Unit	Description	Scope
grid_root	I	2		root subdivision of initial edges	
start_leve	I	4		number of edge bisections following the root subdivision	
n_dom	I	2		number of logical model domains, including the global one	
n_phys_dom	I	n_dom		number of physical model domains, may be larger than n_dom (in this case, domain merging is applied)	

Parameter	Type	Default	Unit	Description	Scope
parent_id	I(n_phys_dom-1)	i		ID of parent domain (first entry refers to first nested domain; needs to be specified only in case of more than one nested domain per grid level)	
logical_id	I(n_phys_dom-1)	i+1		logical grid ID of domain (first entry refers to first nested domain; needs to be specified only in case of domain merging, i.e. n_dom < n_phys_dom)	
l_plot	L	.FALSE.		produces GMT plots showing the locations of the nested domains	
l_circ	L	.FALSE.		Create circular (.T.) or rectangular (.F.) refined domains	
l_rotate	L	.FALSE.		Rotates center point into the equator in case of l_circ = .FALSE.	lcirc=.FALSE.
write_hierarchy	I	1		0: Output only computational grids 1: Output in addition parent grid of global model domain (required for computing physics on a reduced grid) 2: Output all grids back to level 0 (required for hierarchical search algorithms)	
bdy_indexing_depth	I	12		Number of cell rows along the lateral boundary of a model domain for which the refin_ctrl fields contain the distance from the lateral boundary; needs to be enlarged when lateral boundary nudging is required for one-way nesting	lcirc=.TRUE.
radius	R(n_dom-1)	30.	deg	radius of nested domain (first entry refers to first nested domain; needs to be specified for each nested domain separately)	lcirc=.FALSE.
hwidth_lon	R(n_dom-1)	20.	deg	zonal half-width of refined domain (first entry refers to first nested domain; needs to be specified for each nested domain separately)	

Parameter	Type	Default	Unit	Description	Scope
hwidth_lat	R(n_dom-1)	20.	deg	meridional half-width of refined domain (first entry refers to first nested domain; needs to be specified for each nested domain separately)	lcirc=.FALSE.
center_lon	R(n_dom-1)	30.	deg	center longitude of refined domain (first entry refers to first nested domain; needs to be specified for each nested domain separately)	
center_lat	R(n_dom-1)	90.	deg	center latitude of refined domain (first entry refers to first nested domain; needs to be specified for each nested domain separately)	

Defined and used in: `src/grid_generator/mo_gridrefinement.f90`

gridref_metadata (NAMELIST_GRIDREF)

Parameter	Type	Default	Unit	Description	Scope
number_of_grid_used	I(n_dom+1)	0		sets the number of grid used in the netcdf header; the number of entries must be n_dom+1 since the first number refers to the radiation grid	
centre	I	0		centre running the grid generator 78: EDZW (DWD) 252: MPIM	
subcentre	I	0		subcentre to be assigned by centre, usually 0	
outname_style	I	1		Output name style 1: Standard: <i>iconRBBXX_DOMXX.nc</i> 2: DWD: <i>icon_grid_XXXX_RBBXX_X.nc</i>	

Defined and used in: `src/grid_generator/mo_gridrefinement.f90`

4.4 Namelist parameters defining the atmospheric model

Namelist parameters for the ICON models are organized in several thematic Fortran namelists controlling the experiment, and the properties of dynamics, transport, physics etc.

4.4.1 coupling_nml

Parameter	Type	Default	Unit	Description	Scope
name	C	blank		short name of the coupling field	
dt_coupling	I	0	s	coupling time step / coupling interval	
dt_model	I	0	s	model time step	
lag	I	0		offset to coupling event in number of model time steps	
l_time_average	L	.FALSE.		.TRUE.: time averaging between two coupling events	
l_time_accumulation	L	.FALSE.		.TRUE.: accumulation of coupling fields in time between two coupling events	
l_diagnostic	L	.FALSE.		.TRUE.: simple diagnostics (min, max, avg) for coupling fields is switched on	
l_activated	L	.FALSE.		.TRUE.: activate the coupling of the respective coupling field	

Defined and used in: `src/namelists/mo_coupling_nml.f90`

4.4.2 diffusion_nml

Parameter	Type	Default	Unit	Description	Scope
lhdiff_temp	L	.TRUE.		Diffusion on the temperature field	
lhdiff_vn	L	.TRUE.		Diffusion on the horizontal wind field	

Parameter	Type	Default	Unit	Description	Scope
lhdiff_w	L	.TRUE.		Diffusion on the vertical wind field	
hdiff_order	I	4 (hydro) 5 (NH)		Order of ∇ operator for diffusion: -1: no diffusion 2: ∇^2 diffusion (not available for NH model on triangles!)	
				3: Smagorinsky ∇^2 diffusion (includes frictional heating for the hexagonal model if <code>lhdiff_temp=.TRUE.</code>)	
				4: ∇^4 diffusion	
				5: Smagorinsky ∇^2 diffusion combined with ∇^4 background diffusion as specified via <code>hdiff_efdt_ratio</code>	
itype_vn_diffu	I	1		24 or 42: ∇^2 diffusion from model top to a certain level (cf. <code>k2_pres_max</code> and <code>k2_klev_max</code> below); ∇^4 for the lower levels.	24 and 42 currently allowed only in the hydrostatic atm model (dynam-ics_nml:iequations = 1 or 2). iequations=3, hdiff_order=3 or 5
itype_t_diffu	I	2		Reconstruction method used for Smagorinsky diffusion: 1: u/v reconstruction at vertices only 2: u/v reconstruction at cells and vertices Discretization of temperature diffusion: 1: $K_h \nabla^2 T$ 2: $\nabla \cdot (K_h \nabla T)$	iequations=3, hdiff_order=3 or 5
k2_pres_max	R	-99.	Pa	Pressure level above which ∇^2 diffusion is applied.	hdiff_order = 24 or 42, and dynam-ics_nml:iequations = 1 or 2.

Parameter	Type	Default	Unit	Description	Scope
k2_klev_max	I	0		Index of the vertical level till which (from the model top) ∇^2 diffusion is applied. If a positive value is specified for k2_pres_max, k2_klev_max is reset accordingly during the initialization of a model run.	hdiff_order = 24 or 42, and dynamics.nml:iequations = 1 or 2.
hdiff_efdt_ratio	R	1.0 (hydro) 36.0 (NH)		ratio of e-folding time to time step (or 2* time step when using a 3 time level time stepping scheme) (for triangular NH model, values above 30 are recommended when using hdiff_order=5)	iequations=3
hdiff_w_efdt_ratio	R	15.0		ratio of e-folding time to time step for diffusion on vertical wind speed	iequations=3 .AND. hdiff_order=4
hdiff_min_efdt_ratio	R	1.0		minimum value of hdiff_efdt_ratio near model top	
hdiff_tv_ratio	R	1.0		Ratio of diffusion coefficients for temperature and normal wind: $T : v_n$	n_dom>1
hdiff_multfac	R	1.0		Multiplication factor of normalized diffusion coefficient for nested domains	
hdiff_smag_fac	R	0.15 (hydro) 0.015 (NH)		Scaling factor for Smagorinsky diffusion	iequations=3

Defined and used in: `src/namelist/mo_diffusion_nml.f90`

4.4.3 dynamics_nml

This namelist is relevant if `run_nml:dynamics=.TRUE.`

Parameter	Type	Default	Unit	Description	Scope
iequations	I	3		Equations and prognostic variables. Use positive indices for the atmosphere and negative indices for the ocean. 0: shallow water model 1: hydrostatic atmosphere, T 2: hydrostatic atm., θ -dp 3: non-hydrostatic atmosphere -1: hydrostatic ocean	
idiv_method	I	1		Method for divergence computation: 1: Standard Gaussian integral. Hydrostatic atm. model: for unaveraged normal components Non-hydrostatic atm. model: for averaged normal components 2: bilinear averaging of divergence	
divavg_cntrwgt	R	0.5		Weight of central cell for divergence averaging	
lcoriolis	L	.TRUE.		Coriolis force	
sw_ref_height	R	0.9* 2.94e4/g	m	Reference height of shallow water model used for linearization in the semi-implicit time stepping scheme	idiv_method = 2

Defined and used in: `src/namelist/mo_dynamics_nml.f90`

4.4.4 echam_conv_nml

Parameter	Type	Default	Unit	Description	Scope
iconv	I	1		Choice of cumulus convection scheme. 1: Nordeng scheme 2: Tiedtke scheme 3: hybrid scheme	iforcing = 2 .AND. lconv = .TRUE.

Parameter	Type	Default	Unit	Description	Scope
ncvsmicro	I	0		Choice of convective microphysics scheme.	iforcing = 2 .AND. lconv = .TRUE.
lmfpen	L	.TRUE.		Switch on penetrative convection.	iforcing = 2 .AND. lconv = .TRUE.
lmfmid	L	.TRUE.		Switch on midlevel convection.	iforcing = 2 .AND. lconv = .TRUE.
lmfdd	L	.TRUE.		Switch on cumulus downdraft.	iforcing = 2 .AND. lconv = .TRUE.
lmfldudv	L	.TRUE.		Switch on cumulus friction.	iforcing = 2 .AND. lconv = .TRUE.
cmftau	R	10800.		Characteristic convective adjustment time scale.	iforcing = 2 .AND. lconv = .TRUE.
cmfctop	R	0.3		Fractional convective mass flux (valid range [0,1]) across the top of cloud	iforcing = 2 .AND. lconv = .TRUE.
cprcon	R	1.0e-4		Coefficient for determining conversion from cloud water to rain.	iforcing = 2 .AND. lconv = .TRUE.
cminbuoy	R	0.025		Minimum excess buoyancy.	iforcing = 2 .AND. lconv = .TRUE.
entrpen	R	1.0e-4		Entrainment rate for penetrative convection.	iforcing = 2 .AND. lconv = .TRUE.
dllev	R	3.e4	Pa	Critical thickness necessary for the onset of convective precipitation.	iforcing = 2 .AND. lconv = .TRUE.

Defined and used in: `src/namelist/mo_echam_conv_nml.f90`

4.4.5 echam_phy_nml

Parameter	Type	Default	Unit	Description	Scope
lrad	L	.TRUE.		Switch on radiation.	iforcing = 2
lvdiff	L	.TRUE.		Switch on turbulent mixing (i.e. vertical diffusion).	iforcing = 2
lconv	L	.TRUE.		Switch on cumulus convection.	iforcing = 2
lcond	L	.TRUE.		Switch on large scale condensation.	iforcing = 2
icover	I	1		1 = diagnostic Sunquist cloud cover scheme, 2 = prognostic Tompkins cloud cover scheme.	iforcing = 2 Note: icover = .TRUE. runs, but has not been evaluated (yet) in ICON.
lgw_hines	L	.TRUE.		.TRUE. for atmospheric gravity wave drag by the Hines scheme	iforcing = 2
lssodrag	L	.TRUE.		.TRUE. for subgrid scale orographic drag	iforcing = 2
llandsurf	L	.FALSE.		.TRUE. for surface exchanges	Not implemented yet
lice	L	.FALSE.		.TRUE. for sea-ice temperature calculation	iforcing = 2
lmeltpond	L	.FALSE.		.TRUE. for calculation of meltponds	Not implemented yet
lhld	L	.FALSE.		.TRUE. for hydrologic discharge model	iforcing = 2
lmlo	L	.FALSE.		.TRUE. for mixed layer ocean	Not implemented yet
ljsbach	L	.FALSE.		.TRUE. for calculating the JSBACH land surface	iforcing = 2
lamip	L	.FALSE.		.TRUE. for AMIP simulations	Not implemented yet
dt_rad	R	3600.	s	time interval of full radiation computation	Not implemented yet run_nml/iforcing = iecham

Defined and used in: `src/namelist/mo_echam_phy_nml.f90`

4.4.6 gribout_nml

Parameter	Type	Default	Unit	Description	Scope
preset	C	"none"		Setting this different to "none" enables a couple of defaults for the other <code>gribout_nml</code> namelist parameters. If, additionally, the user tries to set any of these other parameters to a conflicting value, an error message is thrown. Possible values are "none", "deterministic", "ensemble".	filetype=2
backgroundProcess	I	0		Background process - GRIB2 code table <code>backgroundProcess.table</code>	filetype=2
generatingCenter	I	-1		Output generating center. If this key is not set, center information is taken from the grid file DWD: 78 MPIMET: 98 ECMWF: 98	filetype=2
generatingSubcenter	I	-1		Output generating Subcenter. If this key is not set, subcenter information is taken from the grid file DWD: 255 MPIMET: 232 ECMWF: 0	filetype=2
generatingProcessIdentifier	I(n_dom)	1		generating Process Identifier - GRIB2 code table generatingProcessIdentifier.table	filetype=2
numberOfForecastsInEnsemble	I	-1		Local definiton for ensemble products, (only set if value changed from default)	filetype=2

Parameter	Type	Default	Unit	Description	Scope
perturbationNumber	I	-1		Local definition for ensemble products, (only set if value changed from default)	filetype=2
productionStatusOfProcessedData	I	1		Production status of data - GRIB2 code table 1.3	filetype=2
significanceOfReferenceTime	I	1		Significance of reference time - GRIB2 code table 1.2	filetype=2
typeOfEnsembleForecast	I	-1		Local definition for ensemble products (only set if value changed from default)	filetype=2
typeOfGeneratingProcess	I	-1		Type of generating process - GRIB2 code table 4.3	filetype=2
typeOfProcessedData	I	-1		Type of data - GRIB2 code table 1.4	filetype=2
localDefinitionNumber	I	-1		local Definition Number - GRIB2 code table	filetype=2
localNumberOfExperiment	I	1		grib2LocalSectionNumber.78.table local Number of Experiment	filetype=2
localTypeOfEnsembleForecast	I	-1		Local definition for ensemble products (only set if value changed from default)	filetype=2
Ispecialdate_invar	L	.FALSE.		Special reference date for invariant and climatological fields .TRUE.: set special reference date 0001-01-01, 00:00 .FALSE.: no special reference date	filetype = 2
ldate_grib_act	L	.TRUE.		GRIB creation date .TRUE.: add creation date .FALSE.: add dummy date	filetype=2
lgribout_24bit	L	.FALSE.		If TRUE, write thermodynamic fields ρ , θ_v , T , p with 24bit precision instead of 16bit	filetype=2

Defined and used in: `src/namelist/mo_gribout_nml.f90`

4.4.7 grid_nml

Parameter	Type	Default	Unit	Description	Scope
<code>cell_type</code>	I	3		Cell type: not used	
<code>lplane</code>	L	.FALSE.		planar option	
<code>is_plane_torus</code>	L	.FALSE.		f-plane approximation on triangular grid	
<code>corio_lat</code>	R	0.0	deg	Center of the f-plane is located at this geographical latitude	<code>lplane=.TRUE.</code> and <code>is_plane_torus=.TRUE.</code>
<code>grid_angular_velocity</code>	R	Earth's	rad/s	The angular velocity in rad per sec.	
limited_area	L	.FALSE.		The geometry and the timestep will be multiplied by this factor.	
<code>grid_rescale_factor</code>	R	1.0		The angular velocity will be divided by this factor.	
lfeedback	L(n_dom)	.TRUE.		Specifies if feedback to parent grid is performed. Setting <code>lfeedback(1)=.false.</code> turns off feedback for all nested domains; to turn off feedback for selected nested domains, set <code>lfeedback(1)=.true.</code> and set “.false.” for the desired model domains	<code>n_dom > 1</code>
<code>iffeedback_type</code>	I	2		1: incremental feedback 2: relaxation-based feedback Note: vertical nesting requires option 2 to run numerically stable over longer time periods	<code>n_dom > 1</code>
<code>start_time</code>	R(n_dom)	0.	s	Time when a nested domain starts to be active (namelist entry is ignored for the global domain)	<code>n_dom > 1</code>

Parameter	Type	Default	Unit	Description	Scope
<code>end_time</code>	R(n_dom)	1.E30	s	Time when a nested domain terminates (namelist entry is ignored for the global domain)	n_dom > 1
<code>patch_weight</code>	R(n_dom)	0.		If <code>patch_weight</code> is set to a value > 0 for any of the first level child patches, processor splitting will be performed, i.e. every of the first level child patches gets a subset of the total number of processors corresponding to its <code>patch_weight</code> . A value of 0. corresponds to exactly 1 processor for this patch, regardless of the total number of processors. For the root patch and higher level childs, <code>patch_weight</code> is not used. However, <code>patch_weight</code> must be set to 0 for these patches to avoid confusion. If set to <code>.true.</code> radiation is calculated on a reduced grid (= one grid level higher)	n_dom > 1
<code>hredgrid_phys</code>	L	<code>.FALSE.</code>		Array of the grid filenames to be used by the dycore. May contain the keyword <code><path></code> which will be substituted by <code>model_base_dir.</code>	
<code>dynamics_grid_filename</code>	C			Array of the indexes of the parent grid filenames, as described by the <code>dynamics_grid_filename</code> array. Indexes start at 1, an index of 0 indicates no parent.	
<code>dynamics_parent_grid_id</code>	I(n_dom)	$i - 1$		Array of the grid filenames to be used for the radiation model. Filled only if the radiation grid is different from the dycore grid. May contain the keyword <code><path></code> which will be substituted by <code>model_base_dir.</code>	
<code>radiation_grid_filename</code>	C				<code>hredgrid_phys=.TRUE.</code>

Parameter	Type	Default	Unit	Description	Scope
dynamics_radiation_grid_link	I(n_dom)	1 for i=1		Array of the indexes linking the dycore grids, as described by the dynamics_grid_filename array, and the radiation_grid_filename array. It provides the link index of the radiation_grid_filename, for each entry of the dynamics_grid_filename array. Indexes start at 1, an index of 0 indicates that the radiation grid is the same as the dycore grid. Only needs to be filled when the radiation_grid_filename is defined.	
create_vgrid	L	.FALSE.		.TRUE.: Write vertical grid files containing (vct_a, vct_b, z_ifc, and z_ifv).	
vertical_grid_filename	C(n_dom)			Array of filenames. These files contain the vertical grid definition (vct_a, vct_b, z_ifc). If empty, the vertical grid is created within ICON during the setup phase.	
use_duplicated_connectivity	L	.TRUE.		if .TRUE., the zero connectivity is replaced by the last non-zero value	
use_dummy_cell_closure	L	.FALSE.		if .TRUE. then create a dummy cell and connect it to cells and edges with no neighbor	

Defined and used in: `src/namelist/mo_grid_nml.f90`

4.4.8 gridref_nml

Parameter	Type	Default	Unit	Description	Scope
grf_intmethod_c	I	2		Interpolation method for grid refinement (cell-based dynamical variables): 1: parent-to-child copying	n_dom>1

Parameter	Type	Default	Unit	Description	Scope
grf_intmethod_ct	I	2		2: gradient-based interpolation Interpolation method for grid refinement (cell-based tracer variables): 1: parent-to-child copying 2: gradient-based interpolation	n_dom > 1
grf_intmethod_e	I	6		Interpolation method for grid refinement (edge-based variables): 1: inverse-distance weighting (IDW) 2: RBF interpolation 3: combination gradient-based / IDW 4: combination gradient-based / RBF 5/6: same as 3/4, respectively, but direct interpolation of mass fluxes along nest interface edges	n_dom > 1
grf_velfbk	I	1		Method of velocity feedback: 1: average of child edges 1 and 2	n_dom > 1
grf_scalfbk	I	2		2: 2nd-order method using RBF interpolation Feedback method for dynamical scalar variables (T, p_{sfc}): 1: area-weighted averaging 2: bilinear interpolation	n_dom > 1
grf_tracfbk	I	2		Feedback method for tracer variables: 1: area-weighted averaging 2: bilinear interpolation	n_dom > 1
grf_idw_exp_e12	R	1.2		exponent of generalized IDW function for child edges 1/2	n_dom > 1
grf_idw_exp_e34	R	1.7		exponent of generalized IDW function for child edges 3/4	n_dom > 1
rbf_vec_kern_grf_e	I	1		RBF kernel for grid refinement (edges): 1: Gaussian 2: $1/(1 + r^2)$	n_dom > 1

Parameter	Type	Default	Unit	Description	Scope
rbf_scale_grf_e	R(n_dom)	0.5		3: inverse multiquadric	n_dom > 1
denom_diffu_t	R	135		RRBF scale factor for grid refinement (edges)	n_dom > 1
denom_diffu_v	R	200		Denominator for lateral boundary diffusion of temperature	n_dom > 1
l_mass_consvcorr	L	.FALSE.		Denominator for lateral boundary diffusion of velocity	n_dom > 1
l_density_nudging	L	.FALSE.		.TRUE.: Apply mass conservation correction in feedback routine	n_dom > 1 .AND. lfeedback = .TRUE.
fbk_relax_timescale	R	10800		.TRUE.: Apply density nudging near lateral nest boundary if grf.intmethod_e ≤ 4	n_dom > 1 .AND. lfeedback = .TRUE. .AND. iffeedback_type = 2
				Relaxation time scale for feedback	

Defined and used in: src/namelist/mo_gridref_nml.f90

4.4.9 gw_hines_nml (Scope: lgw_hines = .TRUE. in echam_phy_nml)

Parameter	Type	Default	Unit	Description	Scope
lheatcal	L	.FALSE.		.TRUE.: compute drag, heating rate and diffusion coefficient from the dissipation of gravity waves	
emiss_lev	I	10		.FALSE.: compute drag only	
				Index of model level, counted from the surface, from which the gravity wave spectra are emitted	
rmscon	R	1.0	m/s	Root mean square gravity wave wind at the emission level	

Parameter	Type	Default	Unit	Description	Scope
kstar	R	5.0e-5	1/m	Typical gravity wave horizontal wavenumber	
m_min	R	0.0	1/m	Minimum bound in vertical wavenumber	
lrmscon_lat	L	.FALSE.		.TRUE.: use latitude dependent rms wind - --latitude-- >= lat_rmscon: use rmscon - --latitude-- <= lat_rmscon_eq: use rmscon_eq - lat_rmscon_eq < --latitude-- < lat_rmscon: use linear interpolation between rmscon_eq and rmscon .FALSE.: use globally constant rms wind rmscon	
lat_rmscon_eq	R	5.0	deg N	rmscon_eq is used equatorward of this latitude	lrmscon_lat = .TRUE.
lat_rmscon	R	10.0	deg N	rmscon is used poleward of this latitude	lrmscon_lat = .TRUE.
rmscon_eq	R	1.2	m/s	is used equatorward of latitude lat_rmscon_eq	lrmscon_lat = .TRUE.

Defined and used in: `src/namelist/mo_gw_hines_nml.f90`

4.4.10 ha_dyn_nml

This namelist is relevant if `run_nml:ldynamics=.TRUE.` and `dynamics_nml:iequations=IHS_ATM_TEMP` or `IHS_ATM_THETA`.

Parameter	Type	Default	Unit	Description	Scope
itime_scheme	I	14		Time integration scheme: 11: pure advection (no dynamics) 12: 2 time level semi implicit (not yet implemented) 13: 3 time level explicit 14: 3 time level with semi implicit correction 15: standard 4th-order Runge-Kutta method (4-stage)	

Parameter	Type	Default	Unit	Description	Scope
ileapfrog_startup	I	1		16: SSPRK(5,4) scheme (5-stage) How to integrate the first time step when the leapfrog scheme is chosen. 1 = Euler forward; 2 = a series of sub-steps.	itime_scheme= 13 or 14
asselin_coeff	R	0.1		Asselin filter coefficient	itime_scheme= 13 or 14
si_2tls	R	0.6		weight of time step n+1. Valid range: [0,1]	itime_scheme=12
si_expl_scheme	I	2		scheme for the explicit part used in the 2 time level semi-implicit time stepping scheme. 1 = Euler forward; 2 = Adams-Bashforth 2nd order	itime_scheme=12
si_cmin	R	30.0	m/s	semi implicit correction is done for eigenmodes with speeds larger than si_cmin	itime_scheme=14 and lsi_3d=.FALSE.
si_coeff	R	1.0		weight of the semi implicit correction	itime_scheme=14
si_offctr	R	0.7			itime_scheme=14
si_rtol	R	1.0e-3		relative tolerance for GMRES solver	itime_scheme=14
lsi_3d	L	.FALSE.		3D GMRES solver or decomposition into 2D problems	lshallow_water=.FALSE. and itime_scheme=14
ldry_dycore	L	.TRUE.		Assume dry atmosphere	iequations∈{1,2}
lref_temp	L	.FALSE.		Set a background temperature profile as base state when computing the pressure gradient force	iequations∈{1,2}

4.4.11 initicon_nml

Parameter	Type	Default	Unit	Description	Scope
init_mode	I	2		1: start from DWD analysis 2: start from IFS analysis 3: combined mode: IFS atm + GME soil 4: start from COSMO-DE forecast	
dt_iau	R	10800	s	Time interval during which an incremental analysis update (IAU) is performed	init_mode=5

Parameter	Type	Default	Unit	Description	Scope
<code>rho_incr_filter_wgt</code>	R	0	s	Vertical filtering weight on density increments	init_mode=5
<code>type_iau_wgt</code>	I	1		Weighting function for performing IAU 1: Top-Hat 2: SIN2	init_mode=5
<code>nlevsoil_in</code>	I	4		number of soil levels of input data	init_mode=2
<code>zpbl1</code>	R	500.0	m	bottom height (AGL) of layer used for gradient computation	
<code>zpbl2</code>	R	1000.0	m	top height (AGL) of layer used for gradient computation	
<code>l_sst_in</code>	L	.TRUE.		Logical switch. If true, the surface temperature of the water sea points is initialized with the SST provided in the ifs2icon file. If false, it is initialized with the skin temperature. If the SST is not provided in the ifs2icon file, l_sst_in is reset to false.	init_mode=2
<code>lread_ana</code>	L	.TRUE.		If .FALSE., ICON is started from first guess only. Analysis field is not required, and skipped if provided.	init_mode=1,3
<code>l_coarse2fine.mode</code>	L(n_dom)	.FALSE.		If true, apply corrections for coarse-to-fine mesh interpolation to wind and temperature	
<code>ifs2icon_filename</code>	C			Filename of IFS2ICON input file, default " <code><path>ifs2icon_R<nroot>B<jlev>.DOM<idom>.nc</code> ". May contain the keywords <code><path></code> which will be substituted by <code>model_base_dir</code> , as well as <code>nroot</code> , <code>jlev</code> , and <code>idom</code> defining the current patch.	init_mode=2

Parameter	Type	Default	Unit	Description	Scope
dwdlfg_filename	C			Filename of DWD first-guess input file, default " <code><path>dwdFG_R<nroot>B<jlev>_DOM<idom>.nc</code> ". May contain the keywords <code><path></code> which will be substituted by <code>model_base_dir</code> , as well as <code>nroot</code> , <code>jlev</code> , and <code>idom</code> defining the current patch.	init_mode=1,3
dwdana_filename	C			Filename of DWD analysis input file, default " <code><path>dwdana_R<nroot>B<jlev>_DOM<idom>.nc</code> ". May contain the keywords <code><path></code> which will be substituted by <code>model_base_dir</code> , as well as <code>nroot</code> , <code>jlev</code> , and <code>idom</code> defining the current patch.	init_mode=1
filetype	I	-1 (undef.)		One of CDF's FILETYPE_XXX constants. Possible values: 2 (=FILETYPE_GRB2), 4 (=FILETYPE_NC2). If this parameter has not been set, we try to determine the file type by its extension <code>"*.grb"</code> or <code>".nc"</code> .	
ana_varlist	C			List of mandatory analysis fields that must be present in the analysis file. If these fields are not found, the model aborts. For all other analysis fields, the FG-fields will serve as fallback position.	init_mode=1
ana_varnames_map_file	C			Dictionary file which maps internal variable names onto GRIB2 shortnames or NetCDF variable names. This is a text file with two columns separated by whitespace, where left column: ICON variable name, right column: GRIB2 short name.	

Defined and used in: `src/namelist/mo_initicon_nml.f90`

4.4.12 interpola_nml

Parameter	Type	Default	Unit	Description	Scope
l_intra_c2l	L	.TRUE.		If .TRUE. directly interpolate scalar variables from cell centers to lon-lat points, otherwise do gradient interpolation and reconstruction.	
l_mono_c2l	L	.TRUE.		Monotonicity can be enforced by demanding that the interpolated value is not higher or lower than the stencil point values.	
llsq_high_consv	L	.TRUE.		conservative (T) or non-conservative (F) least-squares reconstruction for high order transport	
llsq_high_ord	I	3		polynomial order for high order reconstruction 1: linear 2: quadratic 30: cubic (no 3 rd order cross deriv.) 3: cubic	ihadv_tracer=4
llsq_lin_consv	L	.FALSE.		conservative (T) or non-conservative (F) least-squares reconstruction for 2nd order (linear) transport	
nudge_efold_width	R	2.0		e-folding width (in units of cell rows) for lateral boundary nudging coefficient	
nudge_max_coeff	R	0.02		Maximum relaxation coefficient for lateral boundary nudging	
nudge_zone_width	I	8		Total width (in units of cell rows) for lateral boundary nudging zone. If 0 the patch boundary_depth_index is used.	
rbf_dim_c2l	I	10		stencil size for direct lon-lat interpolation: 4 = nearest neighbor, 13 = vertex stencil, 10 = edge stencil.	

Parameter	Type	Default	Unit	Description	Scope
rbf_scale_mode_ll	I	2		Specifies, how the RBF shape parameter is determined for lon-lat interpolation. 1 : lookup table based on grid level 2 : determine automatically. So far, this routine only estimates the smallest value for the shape parameter for which the Cholesky is likely to succeed in floating point arithmetic.	
rbf_vec_kern_c	I	1		Kernel type for reconstruction at cell centres: 1: Gaussian 3: inverse multiquadric	
rbf_vec_kern_e	I	3		Kernel type for reconstruction at edges: 1: Gaussian 3: inverse multiquadric	
rbf_vec_kern_ll	I	1		Kernel type for reconstruction at lon-lat-points: 1: Gaussian 3: inverse multiquadric	
rbf_vec_kern_v	I	1		Kernel type for reconstruction at vertices: 1: Gaussian 3: inverse multiquadric	
rbf_vec_scale_c	R(n_dom)	resolution-dependent		Scale factor for RBF reconstruction at cell centres	
rbf_vec_scale_e	R(n_dom)	resolution-dependent		Scale factor for RBF reconstruction at edges	
rbf_vec_scale_v	R(n_dom)	resolution-dependent		Scale factor for RBF reconstruction at vertices	

Defined and used in: `src/namelist/mo_interp_nml.f90`

4.4.13 io_nml

Parameter	Type	Default	Unit	Description	Scope
lkeep_in_sync	L	.FALSE.		Sync output stream with file on disk after each timestep	
dt_diag	R	86400.	s	diagnostic integral output interval	
dt_checkpoint	R	2592000	s	Time interval for writing restart files. Note that if the value of dt_checkpoint resulting from model default or user's specification is longer than time_nml:dt_restart, it will be reset (by the model) to dt_restart so that at least one restart file is generated during the restart cycle.	output /= "none" (run_nml)
inextra_2d	I	0		Number of extra 2D Fields for diagnostic/debugging output.	dynamics_nml:iequations = 3 (to be done for 1, 2)
inextra_3d	I	0		Number of extra 3D Fields for diagnostic/debugging output.	dynamics_nml:iequations = 3 (to be done for 1, 2)
lflux_avg	L	.TRUE.		if .FALSE. the output fluxes are accumulated from the beginning of the run if .TRUE. the output fluxes are average values from the beginning of the run, except of TOT_PREC that would be accumulated	iequations=3 iforcing=3
itype_pres_msl	I	1		Specifies method for computation of mean sea level pressure (and geopotential at pressure levels below the surface). 1: GME-type extrapolation, 2: stepwise analytical integration, 3: current IFS method, 4: IFS method with consistency correction	

Parameter	Type	Default	Unit	Description	Scope
itype_rh	I	1		Specifies method for computation of relative humidity 1: WMO-type: water only ($e_s=e_{s_water}$), 2: IFS-type: mixed phase (water and ice), 3: IFS-type with clipping ($rh \leq 100$)	
output_nml_dict	C	,		File containing the mapping of variable names to the internal ICON names. May contain the keyword <code><path></code> which will be substituted by <code>model_base_dir</code> . The format of this file: One mapping per line, first the name as given in the <code>ml_varlist</code> , <code>hl_varlist</code> , <code>pl_varlist</code> or <code>il_varlist</code> of the <code>output_nml</code> namelists, then the internal ICON name, separated by an arbitrary number of blanks. The line may also start and end with an arbitrary number of blanks. Empty lines or lines starting with <code>#</code> are treated as comments. Names not covered by the mapping are used as they are.	output_nml_namelists

Parameter	Type	Default	Unit	Description	Scope
netcdf_dict	C	, ,		File containing the mapping from internal names to names written to NetCDF. May contain the keyword <code><path></code> which will be substituted by <code>model_base_dir</code> . The format of this file: One mapping per line, first the name written to NetCDF, then the internal name, separated by an arbitrary number of blanks (<i>inverse to the definition of</i> <code>output_nml_dict</code>). The line may also start and end with an arbitrary number of blanks. Empty lines or lines starting with <code>#</code> are treated as comments. Names not covered by the mapping are output as they are. Note that the specification of output variables, e.g. in <code>ml_varlist</code> , is independent from this renaming, see the namelist parameter <code>output_nml_dict</code> for this.	output_nml namelists, NetCDF output
laxis_reference	L	.TRUE.		FALSE: encode vertical axis as ZAXIS_HYBRID for 3D atmospheric fields TRUE: encode vertical axis as ZAXIS_REFERENCE for 3D atmospheric fields	GRIB2-output (ZAXIS_HYBRID will be removed after some testing phase)
restart_file_type	I	4		Type of restart file. One of CDF's FILETYPE_XXX. So far, only 4 (=FILETYPE_NC2) is allowed	
use_set_event_to_simstep	L			Currently inactive	

Defined and used in: `src/namelists/mo_io_nml.f90`

4.4.14 les_nml (parameters for LES turbulence scheme; valid for inwp_turb=5)

Parameter	Type	Default	Unit	Description	Scope
sst	R	300	K	sea surface temperature for idealized LES simulations	nh_test_name=CBL, RICO
shflux	R	-999	Km/s	Kinematic sensible heat flux at surface	isrfc_type=5,4
lhflux	R	-999	m/s	Kinematic latent heat flux at surface	isrfc_type = 2
isrfc_type	I	1		surface type 1 = TERRA land physics 2 = fixed surface fluxes 3 = fixed buoyancy fluxes 4 = RICO test case 5 = fixed SST	isrfc_type = 2
ufrc	R	-999	m/s	friction velocity for idealized LES simulations	
is_dry_cbl	L	.FALSE.		switch for dry convective boundary layer simulations	
smag_constant	R	0.23		Smagorinsky constant	
turb_prandtl	R	0.333333		turbulent Prandtl number	
bflux	R	-999	m ² /s ³	buoyancy flux for idealized LES simulations (Stevens 2007)	isrfc_type=3
tran_coeff	R	-999	m/s	transfer coefficient near surface for idealized LES simulation (Stevens 2007)	isrfc_type=3
vert_scheme_type	I	2		type of time integration scheme in vertical diffusion 1 = explicit 2 = fully implicit	
sampl_freq_sec	R	60	s	sampling frequency in seconds for statistical (1D and 0D) output	
avg_interval_sec	R	900	s	(time) averaging interval in seconds for 1D statistical output	

Parameter	Type	Default	Unit	Description	Scope
expname	C	ICOLES		expxname to name the statistical output file	
ldiag_les_out	L	.FALSE.		Control for the statistical output in LES mode	

Defined and used in: `src/namelist/mo_les_nml.f90`

4.4.15 limarea_nml (Scope: `limited_area=1` in `grid_nml`)

Parameter	Type	Default	Unit	Description	Scope
itype_latbc	I	0		Type of lateral boundary nudging. Nudge from 0: the initial data, 1: IFS data analysis/forecast (if <code>initicon_nml:init_mode=4</code> , we take COSMO-DE data), 2: ICON output data (with the identical 3d grid)	
dtime_latbc	R	10800.0	s	Time difference between two consecutive boundary data.	$\text{itype_latbc} \geq 1$
nlev_latbc	I	0	s	Number of vertical levels in boundary data.	$\text{itype_latbc} \geq 1$
latbc_filename	C			Filename of boundary data input file, default: " <code>prepiconR<nroot>B<jlev>_y<m><d><h>.nc</code> ". <code><y></code> , <code><m></code> , <code><d></code> , and <code><h></code> will be automatically replaced during the run-time. In case the time span between two consecutive boundary data is less than 1 hour, one can use <code><min></code> and <code><sec></code> . These files must be located in the <code>latbc_path</code> directory.	$\text{itype_latbc} \geq 1$
latbc_path	C			Absolute path to boundary data.	$\text{itype_latbc} \geq 1$

Defined and used in: `src/namelist/mo_limarea_nml.f90`

4.4.16 `lnd_nml`

Parameter	Type	Default	Unit	Description	Scope
<code>nlev_snow</code>	I	2		number of snow layers	<code>lmulti_snow=.true.</code>
<code>ntiles</code>	I	1		number of tiles	<code>ntiles>1</code>
<code>lsnowtile</code>	L	<code>.FALSE.</code>		<code>.TRUE.:</code> consider snow-covered and snow-free tiles separately	<code>ntiles>1</code>
<code>frlnd_thrhd</code>	R	0.05		fraction threshold for creating a land grid point	<code>ntiles>1</code>
<code>frlake_thrhd</code>	R	0.05		fraction threshold for creating a lake grid point	<code>ntiles>1</code>
<code>frsea_thrhd</code>	R	0.05		fraction threshold for creating a sea grid point	<code>ntiles>1</code>
<code>frlndtile_thrhd</code>	R	0.05		fraction threshold for retaining the respective tile for a grid point	<code>ntiles>1</code>
<code>lmelt</code>	L	<code>.TRUE.</code>		<code>.TRUE.</code> soil model with melting process	
<code>lmelt_var</code>	L	<code>.TRUE.</code>		<code>.TRUE.</code> freezing temperature dependent on water content	
<code>lana_rho_snow</code>	L	<code>.TRUE.</code>		<code>.TRUE.</code> take rho_snow-values from analysis file	<code>init_mode=1</code>
<code>lmulti_snow</code>	L	<code>.TRUE.</code>		<code>.TRUE.</code> for use of multi-layer snow model	<code>lmulti_snow=.TRUE.</code>
<code>max_toplaydepth</code>	R	0.25	m	maximum depth of uppermost snow layer	
<code>idiag_snowfrac</code>	I	1		Type of snow-fraction diagnosis: 1 = based on SWE only 2-4 = more advanced experimental methods	

Parameter	Type	Default	Unit	Description	Scope
itype_lndtbl	I	1		Table values used for associating surface parameters to land-cover classes: 1 = defaults from extpar (GLC2000 and GLOBCOVER2009) 2 = Tuned version based on IFS values for globcover classes (GLOBCOVER2009 only) 3 = even more tuned version (EXPERIMENTAL!!, GLOBCOVER2009 only)	
itype_root	I	2		root density distribution: 1 = constant 2 = exponential	
itype_evsl	I	2		type of bare soil evaporation parameterization 2 = Dickinson (1984) 3 = Noilhan and Platon (1989)	
itype_heatcond	I	1		type of soil heat conductivity 1 = constant soil heat conductivity 2 = moisture dependent soil heat conductivity	
itype_interception	I	1		type of plant interception 1 = effectively switched off (security minimum of 1E – 6 m for surface area index) 2 = Rain and snow interception (under development)	
itype_hydbound	I	1		type of hydraulic lower boundary condition 1 = none 3 = ground water as lower boundary of soil column	
lstomata	L	.TRUE.		If .TRUE., use map of minimum stomatal resistance If .FALSE., use constant value of 150 s/m.	

Parameter	Type	Default	Unit	Description	Scope
<code>l2tls</code>	L	.TRUE.		If .TRUE., forecast with 2-Time-Level integration scheme	
<code>lseai</code>	L	.TRUE.		.TRUE. for use of sea-ice model	
<code>llake</code>	L	.TRUE.		.TRUE. for use of lake model	
<code>sstice_mode</code>	I	1		1: SST and sea ice fraction are read from the analysis and kept constant. The sea ice fraction can be modified by the seaice model. 2: SST and sea ice fraction are updated daily, based on climatological monthly means 3: SST and sea ice fraction are updated daily, based on actual monthly means 4: SST and sea ice fraction are updated daily, based on actual daily means, not yet implemented	iequations=3 iforcing=3
<code>sst_td_filename</code>	C			Filename of SST input files for time dependent SST. Default is " <path>SST_<year>_jmonth_i_<gridfile>". May contain the keyword <path> which will be substituted by model_base_dir	sstice_mode=2,3
<code>ci_td_filename</code>	C			Filename of sea ice fraction input files for time dependent sea ice fraction. Default is " <path>CI_<year>_<month>_<gridfile>". May contain the keyword <path> which will be substituted by model_base_dir	sstice_mode=2,3

Defined and used in: `src/namelist/mo_lnd_nwp_nml.f90`

4.4.17 ls_forcing_nml (parameters for large-scale forcing; valid for torus geometry)

Parameter	Type	Default	Unit	Description	Scope
is_subsidence_moment	L	.FALSE.		switch for enabling LS vertical advection due to subsidence for momentum equations	is_plane_torus=.TRUE.
is_subsidence_heat	L	.FALSE.		switch for enabling LS vertical advection due to subsidence for thermal equations	is_plane_torus=.TRUE.
is_advection	L	.FALSE.		switch for enabling LS horizontal advection (currently only for thermal equations)	is_plane_torus=.TRUE.
is_geowind	L	.FALSE.		switch for enabling geostrophic wind	is_plane_torus=.TRUE.
is_rad_forcing	L	.FALSE.		switch for enabling radiative forcing	inwp_rad=.FALSE.
is_theta	L	.FALSE.		switch to indicate that the prescribed radiative forcing is for potential temperature	is_plane_torus=.TRUE. is_rad_forcing=.TRUE.

Defined and used in: `src/namelist/mo_ls_forcing_nml.f90`

4.4.18 master_model_nml (repeated for each model)

Parameter	Type	Default	Unit	Description	Scope
model_name	C			Character string for naming this component.	
model_namelist_filename	C			File name containing the model namelists.	
model_type	I	-1		Identifies which component to run. 1=atmosphere 2=ocean 3=radiation 99=dummy_model	
model_min_rank	I	0		Start MPI rank for this model.	
model_max_rank	I	-1		End MPI rank for this model.	
model_inc_rank	I	1		Stride of MPI ranks.	

4.4.19 master_nml

Parameter	Type	Default	Unit	Description	Scope
lrestart	L	.FALSE.		If .TRUE.: Current experiment is started from a restart.	
model_base_dir	C	''		General path which may be used in file names of other name lists: If a file name contains the keyword "<path>", then this model_base_dir will be substituted.	

4.4.20 meteogram_output_nml

Parameter	Type	Default	Unit	Description	Scope
lmeteogram_enabled	L(n_dom)	.FALSE.		Flag. True, if meteogram of output variables is desired.	
zprefix	C(n_dom)	"METEOGRAM."		string with file name prefix for output file	
ldistributed	L(n_dom)	.TRUE.		Flag. Separate files for each PE.	
n0_mtgrm	I(n_dom)	1		initial time step for meteogram output	
ninc_mtgrm	I(n_dom)	1		output interval (in time steps)	
stationlist_tot		53.633, 9.983, 'Hamburg'		list of meteogram stations (triples with lat, lon, name string)	

Defined and used in: `src/namelists/mo_mtgrm_nml.f90`

4.4.21 nh_pzlev_nml

Parameter	Type	Default	Unit	Description	Scope
nzlev	I	10		number of height levels	iequations=3
nplev	I	10		number of pressure levels	iequations=3
nilev	I	3		number of isentropes	iequations=3
zlevels	R(100)	10000, 9000, ..., 1000, 0	m	array of height levels level ordering from TOA to bottom	iequations=3
plevels	R(100)	10000, 20000, 30000, ..., 100000	Pa	array of pressure levels level ordering from TOA to bottom	iequations=3
ilevels	R(100)	340, 320, 300	K	array of isentropic levels level ordering from TOA to bottom	iequations=3

Defined and used in: `src/namelist/mo_nh_pzlev_nml.f90`

4.4.22 nonhydrostatic_nml (relevant if `run_nml:iequations=3`)

Parameter	Type	Default	Unit	Description	Scope
itime_scheme	I	4		Options for predictor-corrector time-stepping scheme:	

Parameter	Type	Default	Unit	Description	Scope
rayleigh_type	I	2		4: Contravariant vertical velocity is computed in the predictor step only, velocity tendencies are computed in the corrector step only (most efficient option) 5: Contravariant vertical velocity is computed in both substeps (beneficial for numerical stability in very-high resolution setups with extremely steep slopes, otherwise no significant impact) 6: As 5, but velocity tendencies are also computed in both substeps (no apparent benefit, but more expensive) Type of Rayleigh damping 1: CLASSICAL (requires velocity reference state!)	iequations=3
rayleigh_coeff	R(n_dom)	0.05 for i=1		2: Klemp (2008) type Rayleigh damping coefficient $1/\tau_0$ (Klemp, Dudhia, Hassiotis: MWR136, pp.3987-4004); higher values are recommended for R2B6 or finer resolution	
damp_height	R(n_dom)	45000 for i=1	m	Height at which Rayleigh damping of vertical wind starts (needs to be adjusted to model top height; the damping layer should have a depth of at least 20 km when the model top is above the stratopause)	
htop_moist_proc	R	22500.0	m	Height above which moist physics and advection of cloud and precipitation variables are turned off	
hbot_qvsubstep	R	22500.0	m	Height above which QV is advected with substepping scheme (must be at least as large as htop_moist_proc)	ihadv_tracer=22, 32, 42 or 52

Parameter	Type	Default	Unit	Description	Scope
vwind_offctr	R	0.15		Off-centering in vertical wind solver. Higher values may be needed for R2B5 or coarser grids when the model top is above 50 km.	
rhotheta_offctr	R	-0.1		Off-centering of density and potential temperature at interface level (may be set to 0.0 for R2B6 or finer grids)	
veladv_offctr	R	0.25		Off-centering of velocity advection in corrector step	
ivctype	I	2		Type of vertical coordinate: 1: Gal-Chen hybrid	
iadv_rcf	I	5		2: SLEVE (uses sleve_nml) reduced calling frequency (rcf) for transport/diffusion/physics 1: no rcf (every dynamics-step) n>1: transport every n-th step Setting odd values (besides 1) requires l_nest_rcf = .TRUE.	
lhdiff_rcf	L	.TRUE.		.TRUE.: Compute diffusion only at advection time steps (in this case, divergence damping is applied in the dynamical core)	
lextra_diffu	L	.TRUE.		.TRUE.: Apply additional momentum diffusion at grid points close to the stability limit for vertical advection (becomes effective extremely rarely in practice; this is mostly an emergency fix for pathologic cases with very large orographic gravity waves)	
divdamp_fac	R	0.0025		Scaling factor for divergence damping	lhdiff_rcf = .TRUE.

Parameter	Type	Default	Unit	Description	Scope
divdamp_order	I	4		Order of divergence damping: 2 = second-order divergence damping 4 = fourth-order divergence damping 24 = combined second-order and fourth-order divergence damping and enhanced vertical wind off-centering during the initial spinup phase (does not allow checkpointing/restarting earlier than 2.5 hours of integration)	lhdif_rcf = .TRUE.
divdamp_type	I	3		Type of divergence damping: 2 = divergence damping acting on 2D divergence 3 = divergence damping acting on 3D divergence 32 = combination of 3D div. damping in the troposphere with transition to 2D div. damping in the stratosphere (recommended for data assimilation cycle only!)	lhdif_rcf = .TRUE.
l_nest_rcf	L	.TRUE.		Synchronize interpolation/feedback calls with advection (transport) time steps. l_nest_rcf is automatically reset to .FALSE. if iadv_rcf=1	
nest_substeps	I	2		Number of dynamics substeps for the child patches. DO NOT CHANGE!!! The code will not work correctly with other values	
l_masscorr_nest	L	.FALSE.		.TRUE.: Apply mass conservation correction also in nested domain	
iadv_rhotheta	I	2		Advection method for rho and rhotheta: 1: simple second-order upwind-biased scheme 2: 2nd order Miura horizontal 3: 3rd order Miura horizontal (not recommended)	

Parameter	Type	Default	Unit	Description	Scope
igradp_method	I	3		Discretization of horizontal pressure gradient: 1: conventional discretization with metric correction term 2: Taylor-expansion-based reconstruction of pressure (advantageous at very high resolution) 3: Similar discretization as option 2, but uses hydrostatic approximation for downward extrapolation over steep slopes 4: Cubic/quadratic polynomial interpolation for pressure reconstruction 5: Same as 4, but hydrostatic approximation for downward extrapolation over steep slopes .TRUE.: Compute Smagorinsky temperature diffusion truly horizontally over steep slopes Slope threshold above which truly horizontal temperature diffusion is activated	hdiff_order=3/5 .AND. lhdiff_temp = .true. hdiff_order=3/5 .AND. lhdiff_temp=.true. .AND. lzdifft=.true. hdiff_order=3/5 .AND. lhdiff_temp=.true. .AND. lzdifft=.true.
lzdifft	L	.TRUE.			
thslp_zdifft	R	0.025			
thhgtd_zdifft	R	200	m	Threshold of height difference between neighboring grid points above which truly horizontal temperature diffusion is activated (alternative criterion to thslp_zdifft)	
exner_expol	R	1./3.		Temporal extrapolation (fraction of dt) of Exner function for computation of horizontal pressure gradient. This damps horizontally propagating sound waves. For R2B5 or coarser grids, values between 1/2 and 2/3 are recommended.	
l_open_ubc	L	.FALSE.		.TRUE.: Use open upper boundary condition (rather than w=0) to allow vertical motions related to diabatic heating to extend beyond the model top	

Defined and used in: `src/namelist/mo_nonhydrostatic_nml.f90`

4.4.23 `nwp_phy_nml`

The switches for the physics schemes and the time steps can be set for each model domain individually. If only one value is specified, it is copied to all child domains, implying that the same set of parameterizations and time steps is used in all domains. If the number of values given in the namelist is larger than 1 but less than the number of model domains, then the settings from the highest domain ID are used for the remaining model domains. If the time steps are not an integer multiple of the advective time step (`dtime*iadv_rcf`), then the time step of the respective physics parameterization is automatically rounded to the next higher integer multiple of the advective time step.

Parameter	Type	Default	Unit	Description	Scope
inwp_gscp	I (max_ dom)	1		cloud microphysics and precipitation 0: none 1: hydc1 (COSMO-EU microphysics, 2-cat ice: cloud ice, snow) 2: hydc1-gr (COSMO-DE microphysics, 3-cat ice: cloud ice, snow, graupel) 3: as 1, but with improved ice nucleation scheme by C. Koehler 4: Two-moment microphysics by A. Seifert 9: Kessler scheme	run_nml:iforcing = inwp
qi0	R	0.0	kg/kg	cloud ice threshold for autoconversion	inwp_gscp=1
qc0	R	0.0	kg/kg	cloud water threshold for autoconversion	inwp_gscp=1
mu_rain	R	0.0		shape parameter in gamma distribution for rain	inwp_gscp>0
mu_snow	R	0.0		shape parameter in gamma distribution for snow	inwp_gscp>0
inwp_convection	I (max_ dom)	1		convection 0: none 1: Tiedtke/Bechtold convection	run_nml:iforcing = inwp

Parameter	Type	Default	Unit	Description	Scope
inwp_cldcover	I (max_dom)	1		cloud cover scheme for radiation 0: no clouds (only QV) 1: diagnostic cloud cover (by Martin Koehler) 2: prognostic total water variance (not yet started) 3: clouds from COSMO SGS cloud scheme 4: clouds as in turbulence (turbdiff) 5: grid scale clouds	run_nml:iforcing = inwp
inwp_radiation	I (max_dom)	1		radiation 0: none 1: RRTM radiation	run_nml:iforcing = inwp
inwp_satad	I	1		2: Ritter-Geleyn radiation saturation adjustment 0: none	run_nml:iforcing = inwp
inwp_turb	I (max_dom)	1		1: saturation adjustment at constant density vertical diffusion and transfer 0: none 1: COSMO diffusion and transfer 2: GME turbulence scheme 3: EDMF-DUALM (work in progress) 5: Classical Smagorinsky diffusion subgrid scale orographic drag 0: none 1: Lott and Miller scheme (COSMO) non-orographic gravity wave drag 0: none 1: Orr-Ern-Bechtold-scheme (IFS) surface scheme 0: none 1: TERRA	run_nml:iforcing = inwp
inwp_sso	I (max_dom)	1			run_nml:iforcing = inwp
inwp_gwd	I (max_dom)	1			run_nml:iforcing = inwp
inwp_surface	I (max_dom)	1			run_nml:iforcing = inwp

Parameter	Type	Default	Unit	Description	Scope
ustart_raylfric	R	160.0	m/s	wind speed at which extra Rayleigh friction starts	inwp_gwd > 0
efdt_min_raylfric	R	10800.	s	minimum e-folding time of Rayleigh friction (effective for $u > \text{ustart_raylfric} + 90$ m/s)	inwp_gwd > 0
latm_above_top	L (max_dom)	.FALSE.		.TRUE.: take into account atmosphere above model top for radiation computation	inwp_radiation > 0
itype_z0	I	2		Type of roughness length data used for turbulence scheme: 1 = land-cover-related roughness including contribution from sub-scale orography 2 = land-cover-related roughness only	inwp_turb > 0
dt_conv	R (max_dom)	600.	s	time interval of convection call	run_nml:iforcing = inwp
dt_rad	R (max_dom)	1800.	s	currently each subdomain has the same value time interval of radiation call	run_nml:iforcing = inwp
dt_sso	R (max_dom)	1200.	s	currently each subdomain has the same value time interval of sso call	run_nml:iforcing = inwp
dt_gwd	R (max_dom)	1200.	s	currently each subdomain has the same value time interval of gwd call	run_nml:iforcing = inwp
lrtm_filename	C(:)	"lrrtmg- lw.nc"		currently each subdomain has the same value NetCDF file containing longwave absorption coefficients and other data for RRTMG_LW k-distribution model.	run_nml:iforcing = inwp
cldopt_filename	C(:)	"ECHAM 6_CldOpt Props.nc"		NetCDF file with RRTM Cloud Optical Properties for ECHAM6.	

Defined and used in: `src/namelist/mo_nwp_phy_nml.f90`

4.4.24 output_nml (relevant if run_nml/output=='nml')

Please note: There may be several instances of output_nml in the namelist file, every one defining a list of variables with separate attributes for output.

Parameter	Type	Default	Unit	Description	Scope
dom	I(:)	-1		Array of domains for which this name-list is used. If not specified (or specified as -1 as the first array member), this name-list will be used for all domains. Attention: Depending on the setting of the parameter l_output_phys_patch these are either logical or physical domain numbers! Defines the length of a file in terms of an ISO-8601 duration string. An example for this time stamp format is given below. This namelist parameter can be set instead of steps_per_file .	
file_interval	C	‘;’		Output filename format. Includes keywords path, output_filename, physdom, etc. (see below). Default is <output_filename>_DOM<physdom>_<levtype>_<jfile>	
filename_format	C	see description.		One of CDI's FILETYPE_XXX constants. Possible values: 2=FILETYPE_GRB2, 4=FILETYPE_NC2, 5=FILETYPE_NC4	
filetype	I	4		height levels	
h_levels	R(:)	None	m	Not yet implemented. The height levels are currently taken from the array <i>zlevels</i> in namelist nh_pzlev_nml.	

Parameter	Type	Default	Unit	Description	Scope
p_levels	R(:)	None	hPa	pressure levels Not yet implemented. The pressure levels are currently taken from the array <i>plevels</i> in namelist <i>nh_pzlev_nml</i> .	
i_levels	R(:)	None	K	isentropic levels Not yet implemented. The isentropic levels are currently taken from array <i>ilevels</i> in namelist <i>nh_pzlev_nml</i> .	
ml_varlist	C(:)	None		Name of model level fields to be output.	
hl_varlist	C(:)	None		Name of height level fields to be output.	
pl_varlist	C(:)	None		Name of pressure level fields to be output.	
il_varlist	C(:)	None		Name of isentropic level fields to be output.	
include_last	L	.TRUE.		Flag whether to include the last time step	
mode	I	2		1 = forecast mode, 2 = climate mode In climate mode the time axis of the output file is set to TAXIS_ABSOLUTE. In forecast mode it is set to TAXIS_RELATIVE. Till now the forecast mode only works if the output is at multiples of 1 hour	
taxis_tunit	I	2		Time unit of the TAXIS_RELATIVE time axis. 1 = TUNIT_SECOND 2 = TUNIT_MINUTE 3 = TUNIT_HOUR	mode=1
output_bounds	R(3)	None		For a complete list of possible values see <i>cdi.inc</i> Post-processing times: start, end, increment. We choose the advection time step matching or following the requested output time, therefore we require output_bounds(3) < dtime*iadv_rcf . See namelist parameters output_start , output_end , output_interval for an alternative specification of output events.	

Parameter	Type	Default	Unit	Description	Scope
output_time_unit	I	1		Units of output bounds specification. 1 = second 2 = minute 3 = hour 4 = day 5 = month 6 = year	
output_filename	C	None		Output filename prefix (which may include path). Domain number, level type, file number and extension will be added, according to the format given in namelist parameter "filename_format".	
output_grid	L	.FALSE.		Flag whether grid information is added to output.	
output_start	C	‘ ‘		ISO8601 time stamp for begin of output. An example for this time stamp format is given below. See namelist parameter output_bounds for an alternative specification of output events.	
output_end	C	‘ ‘		ISO8601 time stamp for end of output. An example for this time stamp format is given below. See namelist parameter output_bounds for an alternative specification of output events.	
output_interval	C	‘ ‘		ISO8601 time stamp for repeating output intervals. We choose the advection time step matching or following the requested output time, therefore we require output_bounds(3) < dtime*iadv_rcf . An example for this time stamp format is given below. See namelist parameter output_bounds for an alternative specification of output events.	

Parameter	Type	Default	Unit	Description	Scope
pe_placement_il	I(:)	-1		Advanced output option: Explicit assignment of output MPI ranks to the isentropic level output file. At most <code>stream_partitions_il</code> different ranks can be specified. See namelist parameter <code>pe_placement_m1</code> for further details.	
pe_placement_hl	I(:)	-1		Advanced output option: Explicit assignment of output MPI ranks to the height level output file. At most <code>stream_partitions_hl</code> different ranks can be specified. See namelist parameter <code>pe_placement_m1</code> for further details.	
pe_placement_m1	I(:)	-1		Advanced output option: Explicit assignment of output MPI ranks to the model level output file. At most <code>stream_partitions_m1</code> different ranks can be specified, out of the following list: 0 ... (<code>num_io_procs</code> - 1). If this namelist parameters is not provided, then the output ranks are chosen in a Round-Robin fashion among those ranks that are not occupied by explicitly placed output files.	
pe_placement_pl	I(:)	-1		Advanced output option: Explicit assignment of output MPI ranks to the pressure level output file. At most <code>stream_partitions_pl</code> different ranks can be specified. See namelist parameter <code>pe_placement_m1</code> for further details.	

Parameter	Type	Default	Unit	Description	Scope
ready_file	C	'default'		A <i>ready_file</i> is a technique for handling dependencies between the NWP processes. The completion of the write process is signalled by creating a small file with name <i>ready_file</i> . Different <i>output_nml</i> 's may be joined together to form a single ready file event. The setting of <i>ready_file</i> = "default" does not create a ready file. The ready file name may contain string tokens <path>, <datetime>, <ddhhmmss> which are substituted as described for the namelist parameter <i>filename_format</i> .	
reg_def.mode	I	0		Specify if the "delta" value prescribes an interval size or the total *number* of intervals: 0: switch automatically between increment and no. of grid points, 1: <i>reg_lon/lat_def</i> (2) specifies increment, 2: <i>reg_lon/lat_def</i> (2) specifies no. of grid points. interpolate horizontally 0: none	remap=1
remap	I	0		0: none	
north_pole	R(2)	0,90		1: to regular lat-lon grid	
reg_lat_def	R(3)	None		definition of north pole for rotated lon-lat grids. start, increment, end latitude in degrees. Alternatively, the user may set the number of grid points instead of an increment. Details for the setting of regular grids is given below together with an example.	remap=1

Parameter	Type	Default	Unit	Description	Scope
reg_lon_def	R(3)	None		The regular grid points are specified by three values: start, increment, end given in degrees. Alternatively, the user may set the number of grid points instead of an increment. Details for the setting of regular grids is given below together with an example.	remap=1
steps_per_file	I	-1		Max number of output steps in one output file. If this number is reached, a new output file will be opened.	
steps_per_file_inclfirst	L	see descr.		Defines if first step is counted wrt. steps_per_file files count. The default is .FALSE. for GRIB2 output, and .TRUE. otherwise.	
stream_partitions_hl	I	1		Splits height level output of this namelist into several concurrent alternating files. See namelist parameter stream_partitions_ml for details.	
stream_partitions_il	I	1		Splits isentropic level output of this namelist into several concurrent alternating files. See namelist parameter stream_partitions_ml for details.	
stream_partitions_ml	I	1		Splits model level output of this namelist into several concurrent alternating files. The output is split into N files, where the start date of part i gets an offset of $(i - 1) * \text{output_interval}$. The output interval is then replaced by $N * \text{output_interval}$, the include_last flag is set to .FALSE. , the steps_per_file_inclfirst flag is set to .FALSE. , and the steps_per_file counter is set to 1.	

Parameter	Type	Default	Unit	Description	Scope
stream_partitions_pl	I	1		Splits pressure level output of this namelist into several concurrent alternating files. See namelist parameter <code>stream_partitions_m1</code> for details.	

Defined and used in: `src/io/shared/mo_name_list_output_init.f90`

Interpolation onto regular grids: Horizontal interpolation onto regular grids is possible through the namelist setting `remap=1`, where the mesh is defined by the parameters

- `reg_lon_def`: mesh latitudes in degrees,
- `reg_lat_def`: mesh longitudes in degrees,
- `north_pole`: definition of north pole for rotated lon-lat grids.

The regular grid points in `reg_lon_def`, `reg_lat_def` are each specified by three values, given in degrees: *start, increment, end*. The mesh then contains all grid points $start + k * increment \leq end$, where k is an integer. Instead of defining an increment it is also possible to prescribe the number of grid points.

- Setting the namelist parameter `reg_def_mode=0`: Switch automatically from increment specification to no. of grid points, when the `reg_lon/lat_def(2)` value is larger than 5.0.
- 1: `reg_lon/lat_def(2)` specifies increment
- 2: `reg_lon/lat_def(2)` specifies no. of grid points

For longitude values the last grid point is omitted if the end point matches the start point, e.g. for 0 and 360 degrees.

Examples

local grid with 0.5 degree increment:

```
reg_lon_def = -30., 0.5, 30.
reg_lat_def = 90., -0.5, -90.
```


global grid with 720x361 grid points:

```
reg_lon_def = 0.,720,360.
reg_lat_def = -90.,360,90.
```

Time stamp format: The namelist parameters `output_start`, `output_end`, `output_interval` allow the specification of time stamps according to ISO 8601. The general format for time stamps is `YYYY-MM-DDThh:mm:ss` where `Y`: year, `M`: month, `D`: day for dates, and `hh`: hour, `mm`: minute, `ss`: second for time strings. The general format for durations is `PnYnMnDnHnMnS`. See, for example, http://en.wikipedia.org/wiki/ISO_8601 for details and further specifications.

NOTE: as the `mtime` library underlying the output driver currently has some restrictions concerning the specification of durations:

1. Any number `n` in `PnYnMnDnHnMnS` must have two digits. For instance use `"PT06H"` instead of `"PT6H"`
2. In a duration string `PnyearYnmonMndayDtnhrHnminMnsecS` the numbers `nxyz` must not pass the carry over number to the next larger time unit: `0j=nmonj=12, 0j=nhrj=23, 0j=nminj=59, 0j=nsecj=59.999`. For instance use `"P01D"` instead of `"PT24H"`, or `"PT01M"` instead of `"PT60S"`.

Soon the formatting problem will be resolved and the valid number ranges will be enlarged. (2013-12-16).

Examples

```
date and time representation (output_start, output_end)      2013-10-27T13:41:00Z
duration (output_interval)                                   P00DT06H00M00S
```

Variable Groups: Using the `"group:"` keyword for the namelist parameters `ml_varlist`, `hl_varlist`, `pl_varlist`, sets of common variables can be added to the output:

```
group:all
group:atmo_ml_vars      output of all variables (caution: do not combine with mixed vertical interpolation)
group:atmo_pl_vars      basic atmospheric variables on model levels
group:atmo_zl_vars      same set as atmo_ml_vars, but except pres
group:nh_prog_vars      same set as atmo_ml_vars, but expect height
group:atmo_derived_vars additional prognostic variables of the nonhydrostatic model
                        derived atmospheric variables
```

```

group:rad_vars
group:precip_vars
group:cloud_diag
group:pbl_vars
group:phys_tendencies
group:land_vars
group:snow_vars
group:multisnow_vars
group:additional_precip_vars
group:dwd_fg_atm_vars
group:dwd_fg_sfc_vars

```

snow variables
multi-layer snow variables

DWD first guess fields (atmosphere)
DWD first guess fields (surface/soil)

Note:

There exists a special syntax which allows to remove variables from the output list, e. g. if these undesired variables were contained in a previously selected group.

Typing "-|varname|" (for example "-temp") removes the variable from the union set of group variables and other selected variables. Note that typos are not detected but that the corresponding variable is simply not removed!

Keyword substitution in output filename (filename_format):

path	substituted by model_base_dir
output_filename	substituted by output_filename
physdom	substituted by physical patch ID
levtype	substituted by level type "ML", "PL", "HL", "IL"
levtype_l	like levtype, but in lower case
jfile	substituted by output file counter
datetime	substituted by ISO-8601 date-time stamp in format YYYY-MM-DDThh:mm:ss.sssZ
datetime2	substituted by ISO-8601 date-time stamp in format YYYYMMDDThhmmssZ
datetime3	substituted by ISO-8601 date-time stamp in format YYYYMMDDThhmmss.sssZ
ddhhmmss	substituted by <i>relative</i> day-hour-minute-second string

substituted by *relative* hour-minute-second string
If namelist is split into concurrent files: number of stream partitions.
If namelist is split into concurrent files: stream partition index of this file.
If namelist is split into concurrent files: substituted by the file counter
(like in `jfile`), which an "unsplit" namelist would have produced

hhmmss
npartitions
ifile_partition
total_index

4.4.25 parallel_nml

Parameter	Type	Default	Unit	Description	Scope
nproma	I	1		chunk length	
n_ghost_rows	I	1		number of halo cell rows	
division_method	I	1		method of domain decomposition 0: read in from file 1: use built-in geometric subdivision 2: use METIS	
division_file_name	C			Name of division file	division_method = 0
ldiv_phys_dom	L	.TRUE.		.TRUE.: split into physical domains before computing domain decomposition (in case of merged domains) (This reduces load imbalance; turning off this option is not recommended except for very small processor numbers)	division_method = 1
p_test_run	L	.FALSE.		.TRUE. means verification run for MPI parallelization (PE 0 processes full domain)	
l_test_openmp	L	.FALSE.		if .TRUE. is combined with p_test_run=.TRUE. and OpenMP parallelization, the test PE gets only 1 thread in order to verify the OpenMP parallelization	p_test_run = .TRUE.
l_log_checks	L	.FALSE.		if .TRUE. messages are generated during each synchronization step (use for debugging only)	
l_fast_sum	L	.FALSE.		if .TRUE., use fast (not processor-configuration-invariant) global summation	
use_dycore_barrier	L	.FALSE.		if .TRUE., set an MPI barrier at the beginning of the nonhydrostatic solver (do not use for production runs!)	

Parameter	Type	Default	Unit	Description	Scope
itype_exch_barrier	I	0		1: set an MPI barrier at the beginning of each MPI exchange call 2: set an MPI barrier after each MPI WAIT call 3: 1+2 (do not use for production runs!)	
iorder_sendrecv	I	1		Sequence of send/receive calls: 1 = irecv/send 2 = isend/recv 3 = isend/irecv	
itype_comm	I	1		1: use local memory for exchange buffers 3: asynchronous halo communication for dynamical core (currently deactivated)	
num_io_procs	I	0		Number of I/O processors (running exclusively for doing I/O)	
num_restart_procs	I	0		Number of restart processors (running exclusively for doing restart)	
pio_type	I	1		Type of parallel I/O. Only used if number of I/O processors greater than number of domains. Experimental!	
use_icon_comm	L	.FALSE.		Enable the use of MPI bulk communication through the icon_comm_lib	
icon_comm_debug	L	.FALSE.		Enable debug mode for the icon_comm_lib	
max_send_recv_buffer_size	I	131072		Size of the send/receive buffers for the icon_comm_lib.	
use_dp_mpi2io	L	.FALSE.		Enable this flag if output fields shall be gathered by the output processes in DOUBLE PRECISION.	
restart_chunk_size	I	1		(<i>Advanced namelist parameter:</i>) Number of levels to be buffered by the asynchronous restart process. The (asynchronous) restart is capable of writing and communicating more than one 2D slice at once.	

Defined and used in: `src/namelist/mo_parallel_nml.f90`

4.4.26 radiation_nml

Parameter	Type	Default	Unit	Description	Scope
ldiur	L	.TRUE.		switch for solar irradiation: .TRUE.: diurnal cycle, .FALSE.: zonally averaged irradiation	
nmonth	I	0		0: Earth circles on orbit 1-12: Earth orbit position fixed for specified month	
lyr_perp	L	.FALSE.		.FALSE.: transient Earth orbit following VSOP87 .TRUE.: Earth orbit of year yr_perp of the VSOP87 orbit is pertuated	
yr_perp	L	-99999		year used for lyr_perp = .TRUE. Insolation scheme	
isolrad	I	0		0: Use original SRTM insolation. 1: Use insolation from external file containing the spectrally resolved insolation (monthly means) 2: Use preindustrial insolation as in CMIP5 (average from 1844–1856) 3: Use insolation for AMIP-type CMIP5 simulation (average from 1979–1988)	

Parameter	Type	Default	Unit	Description	Scope
izenith	I	4		Choice of zenith angle formula for the radiative transfer computation. 0: Sun in zenith everywhere 1: Zenith angle depends only on latitude 2: Zenith angle depends only on latitude. Local time of day fixed at 07:14:15 for radiative transfer computation ($\sin(\text{time of day}) = 1/\pi$) 3: Zenith angle changing with latitude and time of day 4: Zenith angle and irradiance changing with season, latitude, and time of day (iforcing=inwp only)	
albedo_type	I	1		Type of surface albedo 1: based on soil type specific tabulated values (dry soil) 2: MODIS albedo	iforcing=inwp
irad_h2o	I	1		Switches for the concentration of radiative agents	Note: until further notice, please use
irad_co2		2		0: 0.	irad_h2o = 1
irad_ch4		3		1: prognostic variable	irad_co2 = 2
irad_n2o		3		2: global constant	and 0 for all the other agents for
irad_o3		0		3: externally specified	run_nml/forcing = 2 (ECHAM).
irad_o2		2		irad_o3 = 2: ozone climatology from MPI	
irad_cfc11		2		irad_o3 = 4: ozone clim for Aqua Planet Exp	
irad_cfc12		2		irad_o3 = 6: ozone climatology with T5 geographical distribution and Fourier series for seasonal cycle for run_nml/forcing = 3 (NWP)	
				irad_o3 = 7: GEMS ozone climatology (from IFS) for run_nml/forcing = 3 (NWP)	

Parameter	Type	Default	Unit	Description	Scope
vmr_co2	R	348.0e-6		Volume mixing ratio of the radiative agents	
vmr_ch4		1650.0e-9			
vmr_n2o		306.0e-9			
vmr_o2		0.20946			
vmr_cfc11		214.5e-12			
vmr_cfc12		371.1e-12			
irad_aero	I	2		Aerosols 1: prognostic variable 2: global constant 3: externally specified 5: Tanre aerosol climatology for run_nml/forcing = 3 (NWP) 6: Tegen aerosol climatology for run_nml/forcing = 3 (NWP) .AND. itopo = 1 writes actual aerosol optical properties to output	
lrad_aero_diag	L	.FALSE.		Select dynamic greenhouse gases scenario (read from file)	run_nml/forcing=2 (ECHAM)
ighg	I	0		0 : select default gas volume mixing ratios - 1990 values (CMIP5) 1 : transient CMIP5 scenario from file	

Defined and used in: `src/namelist/mo_radiation_nml.f90`

4.4.27 run_nml

Parameter	Type	Default	Unit	Description	Scope
nsteps	I	0		number of time steps of this run.	
dtime	R	600.0	s	time step	

Parameter	Type	Default	Unit	Description	Scope
ltestcase	L	.TRUE.		Idealized testcase runs	
ldynamics	L	.TRUE.		Compute adiabatic dynamic tendencies	
iforcing	I	0		Forcing of dynamics and transport by parameterized processes. Use positive indices for the atmosphere and negative indices for the ocean. 0: no forcing 1: Held-Suarez forcing 2: ECHAM forcing 3: NWP forcing 4: local diabatic forcing without physics 5: local diabatic forcing with physics -1: MPIOM forcing (to be done)	
ltransport	L	.FALSE.		Compute large-scale tracer transport	
ntracer	I	0		Number of advected tracers handled by the large-scale transport scheme	
lvert_nest	L	.FALSE.		If set to .true. vertical nesting is switched on (i.e. variable number of vertical levels)	
num_lev	I(max_dom)	31		Number of full levels (atm.) for each domain	lvert_nest=.TRUE.
nshift	I(max_dom)	0		vertical half level of parent domain which coincides with upper boundary of the current domain required for vertical refinement, which is not yet implemented	lvert_nest=.TRUE.
ltimer	L	.TRUE.		TRUE: Timer for monitoring the runtime of specific routines is on (FALSE = off)	
timers_level	I	1		TRUE: Timer for monitoring runtime of communication routines (FALSE = off)	
activate_sync_timers	L	F			

Parameter	Type	Default	Unit	Description	Scope
msg_level	I	10		controls how much printout is written during runtime. For values less than 5, only the time step is written.	
msg_timestamp	L	.FALSE.		If .TRUE., precede output messages by time stamp.	
test_mode	I	0		Setting a value larger than 0 activates a dummy mode in which time stepping is changed into just doing iterations, and MPI communication is replaced by copying some value from the send buffer into the receive buffer (does not work with nesting and reduced radiation grid because the send buffer may then be empty on some PEs)	
debug_check_level	I	0		Setting a value larger than 0 activates debug checks.	iequations = 3
output	C(:)	"nml", "totint"		Main switch for enabling/disabling components of the model output. One or more choices can be set (as an array of string constants). Possible choices are: <ul style="list-style-type: none"> • "none": switch off all output; • "nml": new output mode (cf. <code>output_nml</code>); • "totint": computation of total integrals. If the <code>output</code> namelist parameter is not set explicitly, the default setting "nml", "totint" is assumed.	

Parameter	Type	Default	Unit	Description	Scope
restart_filename	C			File name for restart/checkpoint files (containing keyword substitution patterns <gridfile>, <idom>, <rstime>, <mtype>). default: ”<gridfile>_restart_<mtype>_<rstime>.nc”.	
profiling_output	I	1		controls how profiling printout is written: TIMER_MODE_AGGREGATED=1, TIMER_MODE_DETAILED=2, TIMER_MODE_WRITE_FILES=3.	

Defined and used in: src/namelists/mo_run_nml.f90

4.4.28 sleve_nml (relevant if nonhydrostatic_nml:ivctype=2)

Parameter	Type	Default	Unit	Description	Scope
min_lay_thckn	R	50	m	Layer thickness of lowermost layer; specifying zero or a negative value leads to constant layer thicknesses determined by top_height and nlev	
top_height	R	23500.0	m	Height of model top	
stretch_fac	R	1.0		Stretching factor to vary distribution of model levels; values <1 increase the layer thickness near the model top	
decay_scale_1	R	4000	m	Decay scale of large-scale topography component	
decay_scale_2	R	2500	m	Decay scale of small-scale topography component	
decay_exp	R	1.2		Exponent of decay function	
flat_height	R	16000	m	Height above which the coordinate surfaces are flat	

Parameter	Type	Default	Unit	Description	Scope
lread_smt	L	.FALSE.		read smoothed topography from file (TRUE) or compute internally (FALSE)	

Defined and used in: `src/namelist/mo_sleve_nml.f90`

4.4.29 time_nml

Parameter	Type	Default	Unit	Description	Scope
calendar	I	1		Calendar type: 0=Julian/Gregorian 1=proleptic Gregorian 2=30day/month, 360day/year	
dt_restart	R	86400.*30.	s	Length of restart cycle in seconds. This namelist parameter specifies how long the model runs until it saves its state to a file and stops. Later, the model run can be resumed, s. t. a simulation over a long period of time can be split into a chain of restarted model runs. Note that the frequency of writing restart files is controlled by <code>io_nml:dt_checkpoint</code> . Only if the value of <code>dt_checkpoint</code> resulting from model default or user's specification is longer than <code>dt_restart</code> , it will be reset (by the model) to <code>dt_restart</code> so that at least one restart file is generated during the restart cycle. If <code>dt_restart</code> is larger than but not a multiple of <code>dt_checkpoint</code> , restart file will <i>not</i> be generated at the end of the restart cycle.	

Parameter	Type	Default	Unit	Description	Scope
ini_datetime_string	C	'2008-09-01T00:00:00Z'		Initial date and time of the simulation	
end_datetime_string	C	'2008-09-01T01:40:00Z'		End date and time of the simulation	
is_relative_time	L	.FALSE.		.TRUE., if time loop shall start with step 0 regardless whether we are in a standard run or in a restarted run (which means re-initialized run).	

Length of the run If "nsteps" in run_nml is positive, then nsteps*dtime is used to compute the end date and time of the run. Else the initial date and time, the end date and time, dt_restart, as well as the time step are used to compute "nsteps".

4.4.30 transport_nml (used if run_nml/ltransport=.TRUE.)

Parameter	Type	Default	Unit	Description	Scope
lvadv_tracer	L	.TRUE.		TRUE : compute vertical tracer advection FALSE: do not compute vertical tracer advection	
ihadv_tracer	I(ntracer)	2		Tracer specific method to compute horizontal advection: 0: no horiz. transport (note that the specific tracer quantity q is kept constant and not tracer mass ρq) 1: upwind (1st order) 2: Miura (2nd order, linear reconstr.) 3: Miura3 (quadr. or cubic reconstr.) 4: FFSL (quadr. or cubic reconstr.) 5: hybrid Miura3/FFSL (quadr. or cubic reconstr.) 20: miura (2nd order, lin. reconstr.) with subcycling 22: combination of miura and miura with subcycling 32: combination of miura3 and miura with subcycling 42: combination of FFSL and miura with subcycling	lsq_high_ord $\in [2,3]$ lsq_high_ord $\in [2,3]$ lsq_high_ord $\in [2,3]$

Parameter	Type	Default	Unit	Description	Scope
<code>ivadv_tracer</code>	I(ntracer)	3		52: combination of hybrid FFSL/Miura3 with subcycling Subcycling means that the integration from time step n to $n+1$ is splitted into substeps to meet the stability requirements. For NWP runs, substepping is generally applied above $z = 22$ km (see <code>nonhydrostatic_nml/hbot_qvsubstep</code>). Tracer specific method to compute vertical advection: 0: no vert. transport (note that tracer mass ρq instead of the specific tracer quantity q is kept constant. This differs from the behaviour in horizontal direction!) 1: upwind (1st order) 3: ppm_cfl (3 rd order, handles $CFL > 1$) 30: ppm (3rd order, $CFL \leq 1$) Type of TKE advection 0: no TKE advection 1: vertical advection only 2: vertical and horizontal advection Time splitting method TRUE: second order Strang splitting FALSE: first order Godunov splitting list of tracer names Type of limiter for horizontal transport: 0: no limiter 3: monotonous flux limiter 4: positive definite flux limiter Type of limiter for vertical transport: 0: no limiter	<code>lvadv_tracer=TRUE</code>
<code>iadv_tke</code>	I	0			<code>inwp_turb=1</code>
<code>lstrang</code>	L	.FALSE.			
<code>ctracer_list</code> itype_hlimit	C I(ntracer)	" 3 4			<code>run_nml/ltestcase=.TRUE.</code> <code>ihadv_tracer ≠ 'iup3[4]'</code>
itype_vlimit	I(ntracer)	1			

Parameter	Type	Default	Unit	Description	Scope
niter_fct	I	1		1: semi-monotone slope limiter 2: monotonous slope limiter 4: positive definite flux limiter number of iterations of monotone flux correction procedure (experimental!) factor of allowed over-/undershooting in monotonous limiter	itype_hlimit = 3
beta_fct	R	1.005		order of backward trajectory calculation:	itype_hlimit = 3
iord_backtraj	I	1		1: first order 2: second order (iterative; currently 1 iteration hardcoded; experimental!)	ihadv_tracer='miura'
igrad_c_miura	I	1		Method for gradient reconstruction at cell center for 2nd order miura scheme 1: Least-squares (linear, non-consv) 2: Green-Gauss	ihadv_tracer=2
ivcfl_max	I	5		determines stability range of vertical PPM-scheme in terms of the maximum allowable CFL-number	ivadv_tracer=3
llsq_svd	L	.TRUE.		use QR decomposition (FALSE) or SV decomposition (TRUE) for least squares design matrix A	
lclip_tracer	L	.FALSE.		Clipping of negative values	

Defined and used in: `src/namelists/mo_advection_nml.f90`

4.4.31 turbdiff_nml

Parameter	Type	Default	Unit	Description	Scope
itype_tran	I	2		type of surface-atmosphere transfer	inwp_turb = 1
imode_tran	I	0		mode of surface-atmosphere transfer	inwp_turb = 1

Parameter	Type	Default	Unit	Description	Scope
icldm_tran	I	2		mode of cloud representation in transfer parametr	inwp_turb = 1
imode_turb	I	1		mode of turbulent diffusion parametrization	inwp_turb = 1
icldm_turb	I	2		mode of cloud representation in turbulence parametr	inwp_turb = 1
itype_sher	I	1		type of shear production for TKE	inwp_turb = 1
ltkesso	L	.FALSE.		calculation SSO-wake turbulence production for TKE	inwp_turb = 1
ltkcon	L	.FALSE.		consider convective buoyancy production for TKE	inwp_turb = 1
lexpcor	L	.FALSE.		explicit corrections of the implicit calculated turbul. diff.	inwp_turb = 1
ltmpcor	L	.FALSE.		consideration of thermal TKE-sources in the enthalpy budget	inwp_turb = 1
lprfcor	L	.FALSE.		using the profile values of the lowest main level instead of the mean value of the lowest layer for surface flux calculations	inwp_turb = 1
lnonloc	L	.FALSE.		nonlocal calculation of vertical gradients used for turbul. diff.	inwp_turb = 1
lcpfluc	L	.FALSE.		consideration of fluctuations of the heat capacity of air	inwp_turb = 1
limpltkediff	L	.TRUE.		use semi-implicit TKE diffusion	inwp_turb = 1
itype_wcd	I	2		type of water cloud diagnosis	inwp_turb = 1
itype_synd	I	2		type of diagnostics of synoptical near surface variables	inwp_turb = 1
lconst_z0	L	.FALSE.		TRUE: horizontally homogeneous roughness length z0	inwp_turb = 1
const_z0	R	0.001	m	value for horizontally homogeneous roughness length z0	inwp_turb = 1 lconst_z0=.TRUE.

Parameter	Type	Default	Unit	Description	Scope
tkhmin	R	0.75	m ² /s	Scaling factor for minimum vertical diffusion coefficient (proportional to $1/\sqrt{Ri}$) for heat and moisture	inwp_turb = 1
tkmmin	R	0.75	m ² /s	Scaling factor for minimum vertical diffusion coefficient (proportional to $1/\sqrt{Ri}$) for momentum	inwp_turb = 1

Defined and used in: src/namelist/mo_turbdiff_nml.f90

4.4.32 vdiff_nml

Parameter	Type	Default	Unit	Description	Scope
lsfc_mon_flux	L	.TRUE.		Switch on surface momentum flux.	lvdiff = .TRUE.
lsfc_heat_flux	L	.TRUE.		Switch on surface sensible and latent heat flux.	lvdiff = .TRUE.

Defined and used in: src/namelist/mo_vdiff_nml.f90

4.5 Ocean-specific namelist parameters

4.5.1 ocean_physics_nml

Parameter	Type	Default	Unit	Description	Scope
i_sea_ice	I	1		0: No sea ice, 1: Include sea ice	
richardson_factor_tracer	I	0.5e-5	m/s	.FALSE.: compute drag only	
richardson_factor_veloc	I	0.5e-5	m/s		
l_constant_mixing	L	.FALSE.			

4.5.2 sea_ice_nml (relevant if run_nml/forcing=2 (ECHAM))

Parameter	Type	Default	Unit	Description	Scope
i_ice_therm	I	2		Switch for thermodynamic model: 1: Zero-layer model 2: Two layer Winton (2000) model 3: Zero-layer model with analytical forcing (for diagnostics) 4: Zero-layer model for atmosphere-only runs (for diagnostics)	In an ocean run i_sea_ice must be $i_i=1$. In an atmospheric run the ice surface type must be defined.
i_ice_dyn	I	0		Switch for sea-ice dynamics: 0: No dynamics 1: FEM dynamics (from AWT)	
i_ice_albedo	I	1		Switch for albedo model. Only one is implemented so far.	
i_Qio_type	I	2		Switch for ice-ocean heat-flux calculation method: 1: Proportional to ocean cell thickness (like MPI-OM) 2: Proportional to speed difference between ice and ocean	Defaults to 1 when i_ice_dyn=0 and 2 otherwise.
kice	I	1		Number of ice classes (must be one for now)	
hnull	R	0.5	m	Hibler's h_0 parameter for new-ice growth.	
hmin	R	0.05	m	Minimum sea-ice thickness allowed.	
ramp_wind	R	10	days	Number of days it takes the wind to reach correct strength. Only used at the start of an OMIP/NCEP simulation (not after restart).	

4.6 Namelist parameters for testcases (NAMELIST_ICON)

The ICON model code includes several experiments, so-called test cases, for the shallow water model as well as the 3-dimensional atmosphere. Depending on the specified experiment, initial conditions and boundary conditions are computed internally.

4.6.1 ha_testcase_nml (Scope: ltestcase=.TRUE. and iequations=[0,1,2] in run_nml)

Parameter	Type	Default	Unit	Description	Scope
ctest_name	C	'JWw'		Name of test case: 'SW_GW': gravity wave 'USBR': unsteady solid body rotation 'Will_2': Williamson test 2 'Will_3': Williamson test 3 'Will_5': Williamson test 5 'Will_6': Williamson test 6 'GW': gravity wave (nlev=20 only!) 'LDF': local diabatic forcing test without physics 'LDF-Moist': local diabatic forcing test with physics initialised with zonal wind field 'HS': Held-Suarez test 'JWs': Jablonowski-Will. steady state 'JWw': Jablonowski-Will. wave test 'JWw-Moist': Jablonowski-Will. wave test including moisture 'APE': aqua planet experiment 'MRW': mountain induced Rossby wave 'MRW2': modified mountain induced Rossby wave 'PA': pure advection	lshallow_water=.TRUE. lshallow_water=.TRUE. lshallow_water=.TRUE. lshallow_water=.TRUE. lshallow_water=.TRUE. lshallow_water=.TRUE. lshallow_water=.FALSE. lshallow_water=.FALSE. and iforcing=4 lshallow_water=.FALSE., and iforcing=5 lshallow_water=.FALSE. lshallow_water=.FALSE. lshallow_water=.FALSE. lshallow_water=.FALSE. lshallow_water=.FALSE. lshallow_water=.FALSE. lshallow_water=.FALSE. lshallow_water=.FALSE. lshallow_water=.FALSE.

Parameter	Type	Default	Unit	Description	Scope
rotate_axis_deg	R	0.0	deg	'SV': stationary vortex 'DF1': deformational flow test 1 'DF2': deformational flow test 2 'DF3': deformational flow test 3 'DF4': deformational flow test 4 'RH': Rossby-Haurwitz wave test Earth's rotation axis pitch angle	lshallow_water=.FALSE., ntracer = 2 lshallow_water=.FALSE. ctest_name= 'Will_2', 'Will_3', 'JWs', 'JWw', 'PA', 'DF1234' ctest_name= 'GW' ctest_name= 'GW' ctest_name= 'GW' ctest_name= 'GW' ctest_name= 'JWw'
gw_brunt_vais	R	0.01	1/s	Brunt Vaisala frequency	ctest_name= 'MRW(2)'
gw_u0	R	0.0	m/s	zonal wind parameter	ctest_name= 'MRW(2)'
gw_lon_deg	R	180.0	deg	longitude of initial perturbation	ctest_name= 'MRW(2)'
gw_lat_deg	R	0.0	deg	latitude of initial perturbation	ctest_name= 'MRW(2)'
jw_uptb	R	1.0	m/s	amplitude of the wave perturbation	ctest_name= 'MRW(2)'
			(?)		ctest_name= 'RH'
mountctr_lon_deg	R	90.0	deg	longitude of mountain peak	ctest_name= 'RH'
mountctr_lat_deg	R	30.0	deg	latitude of mountain peak	ctest_name= 'HS'
mountctr_height	R	2000.0	m	mountain height	
mountctr_half_width	R	1500000.0	m	mountain half width	
mount_u0	R	20.0	m/s	wind speed for MRW cases	
rh_wavenum	I	4		wave number	
rh_init_shift_deg	R	0.0	deg	pattern shift	
ihs_init_type	I	1		Choice of initial condition for the Held-Suarez test. 1: the zonal state defined in the JW's test case; other integers: isothermal state (T=300 K, ps=1000 hPa, u=v=0.)	
lhs_vn_ptb	L	.TRUE.		Add random noise to the initial wind field in the Held-Suarez test.	
hs_vn_ptb_scale	R	1.	m/s	Magnitude of the random noise added to the initial wind field in the Held-Suarez test.	

Parameter	Type	Default	Unit	Description	Scope
lrh_linear_pres	L	.FALSE.		Initialize the relative humidity using a linear function of pressure.	cctest_name= 'JWw-Moist','APE', 'LDF-Moist'
rh.at_1000hpa	R	0.75		relative humidity 0, 1	cctest_name= 'JWw-Moist','APE', 'LDF-Moist'
limit_tracer_fv	L	.TRUE.		at 1000 hPa	cctest_name='PA'
ape_sst_case	C	'sst1'		Finite volume initialization for tracer fields SST distribution selection 'sst1': Control experiment 'sst2': Peaked experiment 'sst3': Flat experiment 'sst4': Control-5N experiment 'sst_qobs': Qobs SST distribution exp 'sst_ice': Control SST distribution with -1.8 C above 64 N/S.	cctest_name='APE'
ildf_init_type	I	0		Choice of initial condition for the Local diabatic forcing test. 1: the zonal state defined in the JW's test case; other: isothermal state (T=300 K, ps=1000 hPa, u=v=0.)	cctest_name= 'LDF'
ldf-symm	L	.TRUE.		Shape of local diabatic forcing: .TRUE.: local diabatic forcing symmetric about the equator (at 0 N) .FALSE.: local diabatic forcing asym. about the equator (at 30 N)	cctest_name= 'LDF','LDF-Moist'

Defined and used in: src/testcases/mo_ha_testcases.f90

4.6.2 nh_testcase_nml (Scope: ltestcase=.TRUE. and iequations=3 in run_nml)

Parameter	Type	Default	Unit	Description	Scope
nh_test_name	C	'jabw'		<p>testcase selection</p> <p>'zero': no orography</p> <p>'bell': bell shaped mountain at 0E,0N</p> <p>'schaer': hilly mountain at 0E,0N</p> <p>'jabw': Initializes the full Jablonowski Williamson test case.</p> <p>'jabw_s': Initializes the Jablonowski Williamson steady state test case.</p> <p>'jabw_m': Initializes the Jablonowski Williamson test case with a mountain instead of the wind perturbation (specify mount_height).</p> <p>'mrw_nh': Initializes the full Mountain-induced Rossby wave test case.</p> <p>'mrw2_nh': Initializes the modified mountain-induced Rossby wave test case.</p> <p>'mwbr_const': Initializes the mountain wave with two layers test case. The lower layer is isothermal and the upper layer has constant brunt vaisala frequency. The interface has constant pressure.</p> <p>'PA': Initializes the pure advection test case.</p> <p>'HS_nh': Initializes the Held-Suarez test case. At the moment with an isothermal atmosphere at rest ($T=300K$, $ps=1000hPa$, $u=v=0$, $topography=0.0$).</p> <p>'HS_jw': Initializes the Held-Suarez test case with Jablonowski Williamson initial conditions and zero topography.</p> <p>'APE_nh': Initializes the APE experiments. With the jabw test case, including moisture.</p>	

Parameter	Type	Default	Unit	Description	Scope
				<p>'wk82': Initializes the Weisman Klemm test case</p> <p>'g_lim_area': Initializes a series of general limited area test cases: itype_atmos_ana determines the atmospheric profile, itype_anaprop_uv determines the wind profile and itype_topo_ana determines the topography</p> <p>'dcmip_pa_12': Initializes Hadley-like meridional circulation pure advection test case.</p> <p>'dcmip_rest_200': atmosphere at rest test (Schaer-type mountain)</p> <p>'dcmip_mw_2x': nonhydrostatic mountain waves triggered by Schaer-type mountain</p> <p>'dcmip_gw_31': nonhydrostatic gravity waves triggered by a localized perturbation (nonlinear)</p> <p>'dcmip_gw_32': nonhydrostatic gravity waves triggered by a localized perturbation (linear)</p> <p>'dcmip_tc_51': tropical cyclone test case with 'simple physics' parameterizations (not yet implemented)</p> <p>'dcmip_tc_52': tropical cyclone test case with full physics in Aqua-planet mode</p> <p>'CBL': convective boundary layer simulations for LES package on torus (doubly periodic) grid</p>	<p>l_limited_area = .TRUE.</p>
					lcoriolis = .FALSE.
					lcoriolis = .FALSE.
					l_limited_area = .TRUE. and lcoriolis = .FALSE. lcoriolis = .TRUE.
					lcoriolis = .TRUE.
					is_plane_torus = .TRUE. nh_test_name='jabw'
jw_up	R	1.0	m/s	amplitude of the u-perturbation in jabw test case	nh_test_name= 'mrw(2)_nh' and 'mwbr_const'
u0_mrw	R	20.0	m/s	wind speed for mrw(2) and mwbr_const cases	

Parameter	Type	Default	Unit	Description	Scope
mount_height_mrw	R	2000.0	m	maximum mount height in mrw(2) and mwbr_const	nh_test_name= 'mrw(2)_nh' and 'mwbr_const'
mount_half_width	R	1500000.0	m	half width of mountain in mrw(2), mwbr_const and bell	nh_test_name= 'mrw(2)_nh', 'mwbr_const' and 'bell'
mount_lonctr_mrw_deg	R	90.	deg	lon of mountain center in mrw(2) and mwbr_const	nh_test_name= 'mrw(2)_nh' and 'mwbr_const'
mount_latctr_mrw_deg	R	30.	deg	lat of mountain center in mrw(2) and mwbr_const	nh_test_name= 'mrw(2)_nh' and 'mwbr_const'
temp_i_mwbr_const	R	288.0	K	temp at isothermal lower layer for mwbr_const case	nh_test_name= 'mwbr_const'
p_int_mwbr_const	R	70000.	Pa	pres at the interface of the two layers for mwbr_const case	nh_test_name= 'mwbr_const'
bruntvais_u_mwbr_const	R	0.025	1/s	constant brunt vaissala frequency at upper layer for mwbr_const case	nh_test_name= 'mwbr_const'
mount_height	R	100.0	m	peak height of mountain	nh_test_name = 'bell'
layer_thickness	R	-999.0	m	thickness of vertical layers	If layer_thickness < 0, the vertical level distribution is read in from externally given HYB_PARAMS_XX. layer_thickness > 0
n_flat_level	I	2		level number for which the layer is still flat and not terrain-following	
nh_u0	R	0.0	m/s	initial constant zonal wind speed	nh_test_name = 'bell'
nh_t0	R	300.0	K	initial temperature at lowest level	nh_test_name = 'bell'
nh_brunt_vais	R	0.01	1/s	initial Brunt-Vaisala frequency	nh_test_name = 'bell'
torus_domain_length	R	100000.0	m	length of slice domain	nh_test_name = 'bell', lplane=.TRUE.

Parameter	Type	Default	Unit	Description	Scope
rotate_axis_deg	R	0.0	deg	Earth's rotation axis pitch angle	nh_test_name= 'PA'
lhs_nh_vn_ptb	L	.TRUE.		Add random noise to the initial wind field in the Held-Suarez test.	nh_test_name= 'HS_nh'
lhs_fric_heat	L	.FALSE.		add frictional heating from Rayleigh friction in the Held-Suarez test.	nh_test_name= 'HS_nh'
hs_nh_vn_ptb_scale	R	1.	m/s	Magnitude of the random noise added to the initial wind field in the Held-Suarez test.	nh_test_name= 'HS_nh'
rh_at_1000hpa	R	0.7	1	relative humidity at 1000 hPa	nh_test_name= 'jabw', nh_test_name= 'mrw'
qv_max	R	20.e-3	kg/kg	specific humidity in the tropics	nh_test_name= 'jabw', nh_test_name= 'mrw'
ape_sst_case	C	'sst1'		SST distribution selection 'sst1': Control experiment 'sst2': Peaked experiment 'sst3': Flat experiment 'sst4': Control-5N experiment 'sst_qobs': Qobs SST distribution exp.	nh_test_name= 'mrw'
limit_tracer_fv	L	.TRUE.		Finite volume initialization for tracer fields	nh_test_name= 'APE_nh'
lcoupled_rho	L	.FALSE.		Integrate density equation 'offline'	pure advection tests, only
qv_max_wk	R	0.014	Kg/kg	maximum specific humidity near the surface, range 0.012 - 0.016 used to vary the buoyancy	pure advection tests, only nh_test_name= 'wk82'
u_infty_wk	R	20.	m/s	zonal wind at infinity height range 0. - 45.	nh_test_name= 'wk82'
bub_amp	R	2.	K	used to vary the wind shear maximum amplitude of the thermal perturbation	nh_test_name= 'wk82'
bubctr_lat	R	0.	deg	latitude of the center of the thermal perturbation	nh_test_name= 'wk82'

Parameter	Type	Default	Unit	Description	Scope
bubctr_lon	R	90.	deg	longitude of the center of the thermal perturbation	nh_test_name='wk82'
bubctr_z	R	1400.	m	height of the center of the thermal perturbation	nh_test_name='wk82'
bub_hor_width	R	10000.	m	horizontal radius of the thermal perturbation	nh_test_name='wk82'
bub_ver_width	R	1400.	m	vertical radius of the thermal perturbation	nh_test_name='wk82'
itype_atmo_ana	I	1		kind of atmospheric profile: 1 piecewise N constant layers 2 piecewise polytropic layers	nh_test_name='g_lim_area'
itype_anaprof_uv	I	1		kind of wind profile: 1 piecewise linear wind layers 2 constant zonal wind 3 constant meridional wind	nh_test_name='g_lim_area'
itype_topo_ana	I	1		kind of orography: 1 schaer test case mountain 2 gaussian_2d mountain 3 gaussian_3d mountain any other no orography	nh_test_name='g_lim_area'
nlayers_nconst	I	1		Number of the desired layers with a constant Brunt-Vaisala-frequency	nh_test_name='g_lim_area' and itype_atmo_ana=1
p_base_nconst	R	100000.	Pa	pressure at the base of the first N constant layer	nh_test_name='g_lim_area' and itype_atmo_ana=1
theta0_base_nconst	R	288.	K	potential temperature at the base of the first N constant layer	nh_test_name='g_lim_area' and itype_atmo_ana=1
h_nconst	R(nlayers_nconst)	0., 1500., 12000.	m	height of the base of each of the N constant layers	nh_test_name='g_lim_area' and itype_atmo_ana=1

Parameter	Type	Default	Unit	Description	Scope
N_nconst	R(nlayers _nconst)	0.01	1/s	Brunt-Vaisala-frequency at each of the N constant layers	nh_test_name= 'g_lim_area' and itype_atmo_ana=1
rh_nconst	R(nlayers _nconst)	0.5	%	relative humidity at the base of each N constant layers	nh_test_name= 'g_lim_area' and itype_atmo_ana=1
rhgr_nconst	R(nlayers _nconst)	0.	%	relative humidity gradient at each of the N constant layers	nh_test_name= 'g_lim_area' and itype_atmo_ana=1
nlayers_poly	I	2		Number of the desired layers with constant gradient temperature	nh_test_name= 'g_lim_area' and itype_atmo_ana=2
p_base_poly	R	100000.	Pa	pressure at the base of the first polytropic layer	nh_test_name= 'g_lim_area' and itype_atmo_ana=2
h_poly	R(nlayers _poly)	0., 12000.	m	height of the base of each of the polytropic layers	nh_test_name= 'g_lim_area' and itype_atmo_ana=2
t_poly	R(nlayers _poly)	288., 213.	K	temperature at the base of each of the polytropic layers	nh_test_name= 'g_lim_area' and itype_atmo_ana=2
rh_poly	R(nlayers _poly)	0.8, 0.2	%	relative humidity at the base of each of the polytropic layers	nh_test_name= 'g_lim_area' and itype_atmo_ana=2
rhgr_poly	R(nlayers _poly)	5.e-5, 0.	%	relative humidity gradient at each of the polytropic layers	nh_test_name= 'g_lim_area' and itype_atmo_ana=2
nlayers_linwind	I	2		Number of the desired layers with constant U gradient	nh_test_name= 'g_lim_area' and itype_anaprof_uv=1

Parameter	Type	Default	Unit	Description	Scope
h_linwind	R(nlayers _linwind)	0., 2500.	m	height of the base of each of the linear wind layers	nh_test_name= 'g_lim_area' and itype_anaprof_uv=1
u_linwind	R(nlayers _linwind)	5, 10.	m/s	zonal wind at the base of each of the linear wind layers	nh_test_name= 'g_lim_area' and itype_anaprof_uv=1
ugr_linwind	R(nlayers _linwind)	0., 0.	1/s	zonal wind gradient at each of the linear wind layers	nh_test_name= 'g_lim_area' and itype_anaprof_uv=1
velconst	R	20.	m/s	constant zonal/meridional wind (itype_anaprof_uv=2,3)	nh_test_name= 'g_lim_area' and itype_anaprof_uv=2,3
mount_lonc_deg	R	90.	deg	longitud of the center of the mountain	nh_test_name= 'g_lim_area'
mount_latc_deg	R	0.	deg	latitud of the center of the mountain	nh_test_name= 'g_lim_area'
schaer_h0	R	250.	m	h0 parameter for the schauer mountain	nh_test_name= 'g_lim_area' and itype_topo_ana=1
schaer_a	R	5000.	m	-a- parameter for the schauer mountain, also half width in the north and south side of the finite ridge to round the sharp edges	nh_test_name= 'g_lim_area' and itype_topo_ana=1,2
schaer_lambda	R	4000.	m	lambda parameter for the schauer mountain	nh_test_name= 'g_lim_area' and itype_topo_ana=1
lshear_dc mip	L	FALSE		run dc mip_mw_2x with/without vertical wind shear FALSE: dc mip_mw_21: non-sheared TRUE : dc mip_mw_22: sheared	nh_test_name= 'dc mip_mw_2x'

Parameter	Type	Default	Unit	Description	Scope
halfwidth_2d	R	10000.	m	half length of the finite ridge in the north-south direction	nh_test_name= 'g_lim_area' and itype_topo_ana=1,2
m_height	R	1000.	m	height of the mountain	nh_test_name= 'g_lim_area' and itype_topo_ana=2,3
m_width_x	R	5000.	m	half width of the gaussian mountain in the east-west direction	nh_test_name= 'g_lim_area' and itype_topo_ana=2,3
m_width_y	R	5000.	m	half width in the north-south direction in the rounding of the finite ridge (gaussian_2d)	nh_test_name= 'g_lim_area' and itype_topo_ana=2,3
gw_u0	R	0.	m/s	half width of the gaussian mountain in the north-south direction	nh_test_name= 'g_lim_area' and itype_topo_ana=2,3
gw_clat	R	90.	deg	maximum amplitude of the zonal wind	nh_test_name= 'dcnip_gw_3X'
gw_delta_temp	R	0.01	K	Lat of perturbation center	nh_test_name= 'dcnip_gw_3X'
u_cbl(2)	R	0:0	m/s and 1/s	maximum temperature perturbation	nh_test_name= 'dcnip_gw_32'
v_cbl(2)	R	0:0	m/s and 1/s	to prescribe initial zonal velocity profile for convective boundary layer simulations where u_cbl(1) sets the constant and u_cbl(2) sets the vertical gradient	nh_test_name=CBL
th_cbl(2)	R	290:0.006	K and K/m	to prescribe initial meridional velocity profile for convective boundary layer simulations where v_cbl(1) sets the constant and v_cbl(2) sets the vertical gradient	nh_test_name=CBL
				to prescribe initial potential temperature profile for convective boundary layer simulations where th_cbl(1) sets the constant and th_cbl(2) sets the gradient	nh_test_name=CBL

Defined and used in: `src/testcases/mo_nh_testcases.f90`

4.7 External data

4.7.1 `extpar_nml` (Scope: `itopo=1` in `run_nml`)

Parameter	Type	Default	Unit	Description	Scope
itopo	I	0		0: analytical topography/ext. data 1: topography/ext. data read from file	
n_iter_smooth_topo	I(n_dom)	0		iterations of topography smoother	
fac_smooth_topo	R	0.015625		pre-factor of topography smoother	
heightdiff_threshold	R(n_dom)	3000.	m	height difference between neighboring grid points above which additional local nabla2 diffusion is applied	<code>itopo = 1</code> <code>n_iter_smooth_topo > 0</code>
l_emiss	L			read and use external surface emissivity map	
extpar_filename	C	.TRUE.		Filename of external parameter input file, default: " <code><path>extpar_<gridfile></code> ". May contain the keyword <code><path></code> which will be substituted by <code>model_base_dir</code> .	<code>itopo = 1</code>
extpar_varnames_map_file	C	,		Filename of external parameter dictionary, This is a text file with two columns separated by whitespace, where left column: NetCDF name, right column: GRIB2 short name. It is required, if external parameter are read from a file in GRIB2 format.	

Defined and used in: `src/namelist/mo_extpar_nml.f90`

4.8 External packages

4.8.1 art_nml

Parameter	Type	Default	Unit	Description	Scope
lart	L	.FALSE.		main switch for ART-package	
lemi_volc	L	.FALSE.		Emission of volcanic ash	
lconv_tracer	L	.FALSE.		Convection of tracers	
lwash_tracer	L	.FALSE.		Washout of tracers	
lrad_volc	L	.FALSE.		Radiative impact of volcanic ash	
lcld_tracer	L	.FALSE.		Impact on clouds	

Defined and used in: `src/namelists/mo_art_nml.f90`

4.9 Information on vertical level distribution

If no vertical level coordinate is chosen (ivctype / =2), the hydrostatic and nonhydrostatic models need hybrid vertical level information to generate the terrain following coordinates. The hybrid level specification is stored in `<icon home>/hyb_params/HYB_PARAMS_<nlev>`. The **hydrostatic** model assumes to get **pressure based** coordinates, the **nonhydrostatic** model expects **height based** coordinates. For further information see `<icon home>/hyb_params/README`.

Discussion

Document last edited by *addyourname* on *insertdate* Document last edited by *S Gruber* on *08-01-2014*.

References

- Jablonowski, C. and D. L. Williamson, 2006.** A baroclinic instability test case for atmospheric model dynamical cores. *Quart. J. Roy. Meteor. Soc.*, 132, 2943–2975.
- Zängl, G., 2012.** Extending the Numerical Stability Limit of Terrain-Following Coordinate Models over Steep Slopes. *Monthly Weather Review* 140(11), 3722–3733.
- Zängl, G., D. Reinert, M.-P. Rípodas, and M. Baldauf, 2013.** The ICON (ICOsa-hedral Nonhydrostatic) modelling framework of DWD and MPI-M: Description of the nonhydrostatic dynamical core. *INSERT*, in press.