

Computer Networks Lab Assignment 6

Lab 6: NAT Configuration


Objective:

- To configure Network Address Translation (NAT) on a router using Cisco Packet Tracer
- To demonstrate the setup and configuration of NAT to allow internal network devices to communicate with external networks.

Steps taken to set up the network


Step 1:

Drag and drop required Network devices (2 Router-PT's and 1 Switch-PT) and End devices (2 PC-PT's and a Server-PT) as shown below.



Step 2:

Open each Router and navigate to physical tab, and add PT-ROUTER-NM-1CGE, PT-ROUTER-NM-1S, PT-ROUTER-NM-1FFE Modules to the Router1 and add the same modules as Router1 except for PT-ROUTER-NM-1FFE, add PT-ROUTER-NM-1CGE module.



Step 3:

Make connections using cables between all the devices as shown in the picture.

Use Copper Straight through cable to connect different devices and use a Serial DCE cable to connect ISP Router and Router 1.

Step 4:

Now, Configure IP address of the routers and end devices according to the configuration table below;

Device Name	Interface	IP Address	Subnet Mask
Router1	FastEthernet0/0	192.168.10.1	255.255.255.0
Router1	Serial0/0/0	200.0.0.1	255.255.255.252
ISP Router	Serial0/0/0	200.0.0.2	255.255.255.252

PC Configuration Table:

Device Name	IP Address	Subnet Mask	Gateway
PC0	192.168.10.2	255.255.255.0	192.168.10.1
PC1	192.168.10.3	255.255.255.0	192.168.10.1

PC-0

Physical

Config

Desktop

Programming

Attributes

IP Configuration

Interface

FastEthernet0

IP Configuration

DHCP

Static

IPv4 Address

192.168.10.2

Subnet Mask

255.255.255.0

Default Gateway

192.168.10.1

DNS Server

0.0.0.0

IPv6 Configuration

PC-1

Physical

Config

Desktop

Programming

Attributes

IP Configuration

Interface

FastEthernet0

IP Configuration

DHCP

Static

IPv4 Address

192.168.10.3

Subnet Mask

255.255.255.0

Default Gateway

192.168.10.1

DNS Server

0.0.0.0

IPv6 Configuration

```

Router>
Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa 0/0
      ^
% Invalid input detected at '^' marker.

Router(config)#int fa 0/0
Router(config-if)#ip address 192.168.10.1 255.255.255.0
Router(config-if)#no shut
Router(config-if)#exit
Router(config)#int se 2/0
Router(config-if)#ip address 200.0.0.1 255.255.255.252
Router(config-if)#no shut
Router(config-if)#exit
Router(config)#

```

Router1

```

Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int gi 8/0
Router(config-if)#ip address 8.8.8.1 255.255.255.0
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet8/0, changed state to up


%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet8/0, changed state to up

Router(config-if)#exit
Router(config)#

```

ISP Router

And configure the Ip address of the server as ;



The screenshot shows a window titled "Server0" with tabs for Physical, Config, Services, Desktop, Programming, and Attributes. The "Config" tab is active, displaying the "IP Configuration" section. The "Static" radio button is selected, and the following fields are filled:

Field	Value
IPv4 Address	8.8.8.8
Subnet Mask	255.255.255.0
Default Gateway	200.0.0.2
DNS Server	0.0.0.0

The "IPv6 Configuration" section is visible at the bottom but not fully configured.

Step 5:

We shall enable ospf routing protocol between both routers.

In Router 1;

```
Router>enable
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa 0/0
Router(config-if)#ip address 192.168.10.1 255.255.255.0
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#int se 2/0
      ^
% Invalid input detected at '^' marker.


Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int se 2/0
Router(config-if)#ip address 200.0.0.
Router(config-if)#ip address 200.0.0.
Router(config-if)#ip address 200.0.0.
Router(config-if)#ip address 200.0.0.
Router(config-if)#ip address 200.0.0.1 255.255.255.252
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up


Router(config-if)#exit
Router(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

Router(config)#router ospf 30
Router(config-router)#router-id 1.1.1.1
Router(config-router)#network 192.168.10.0 0.0.0.255 area 0
Router(config-router)#network 192.168.10.0 0.0.0.255 area 0
Router(config-router)#network 200.0.0.0 0.0.0.3 area 0
Router(config-router)#
Router(config-router)#
Router(config-router)#exit
Router(config)#
Router(config)#do wr
Building configuration...
[OK]
Router(config)#
```

In ISP router;



Step 6: Ping Server (8.8.8.8) from PC-1




```
C:\>tracert 8.8.8.8

Tracing route to 8.8.8.8 over a maximum of 30 hops:

  1  0 ms    0 ms    0 ms    192.168.10.1
  2  0 ms    1 ms    0 ms    200.0.0.2
  3  1 ms    0 ms    1 ms    8.8.8.8

Trace complete.
```

Step 7: Check for Address Translation



Step 8:


Configure Static NAT and configure interfaces as NAT inside and outside.

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 8.8.8.8

Pinging 8.8.8.8 with 32 bytes of data:

Reply from 8.8.8.8: bytes=32 time=1ms TTL=126
Reply from 8.8.8.8: bytes=32 time=1ms TTL=126
Reply from 8.8.8.8: bytes=32 time=1ms TTL=126
Reply from 8.8.8.8: bytes=32 time=31ms TTL=126

Ping statistics for 8.8.8.8:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 31ms, Average = 8ms
```



```

Router(config)#do sh ip nat translations
Pro  Inside global      Inside local      Outside local      Outside global
---  200.0.0.1             192.168.10.2      ---               ---

```

Now, let us ping again and verify the NAT;

In Router1;

```

Router(config)#do sh ip nat translations
Pro  Inside global      Inside local      Outside local      Outside global
icmp 200.0.0.1:10      192.168.10.2:10  8.8.8.8:10        8.8.8.8:10
icmp 200.0.0.1:11      192.168.10.2:11  8.8.8.8:11        8.8.8.8:11
icmp 200.0.0.1:12      192.168.10.2:12  8.8.8.8:12        8.8.8.8:12
icmp 200.0.0.1:13      192.168.10.2:13  8.8.8.8:13        8.8.8.8:13
icmp 200.0.0.1:1       192.168.10.2:1   8.8.8.8:1         8.8.8.8:1
icmp 200.0.0.1:2       192.168.10.2:2   8.8.8.8:2         8.8.8.8:2
icmp 200.0.0.1:3       192.168.10.2:3   8.8.8.8:3         8.8.8.8:3
icmp 200.0.0.1:4       192.168.10.2:4   8.8.8.8:4         8.8.8.8:4
icmp 200.0.0.1:8       192.168.10.2:8   8.8.8.8:8         8.8.8.8:8
icmp 200.0.0.1:9       192.168.10.2:9   8.8.8.8:9         8.8.8.8:9
---  200.0.0.1           192.168.10.2      ---               ---

```