

# Gentoo Linux AMD64 Handbook

[Sven Vermeulen](#) *Author*

[Grant Goodyear](#) *Author*

[Roy Marples](#) *Author*

[Daniel Robbins](#) *Author*

[Chris Houser](#) *Author*

[Jerry Alexandratos](#) *Author*

[Seemant Kulleen](#) *Gentoo x86 Developer*

[Tavis Ormandy](#) *Gentoo Alpha Developer*

[Jason Huebel](#) *Gentoo AMD64 Developer*

[Guy Martin](#) *Gentoo HPPA developer*

[Pieter Van den Abeele](#) *Gentoo PPC developer*

[Joe Kallar](#) *Gentoo SPARC developer*

[John P. Davis](#) *Editor*

[Pierre-Henri Jondot](#) *Editor*

[Eric Stockbridge](#) *Editor*

[Rajiv Manglani](#) *Editor*

[Jungmin Seo](#) *Editor*

[Stoyan Zhekov](#) *Editor*

[Jared Hudson](#) *Editor*

[Colin Morey](#) *Editor*

[Jorge Paulo](#) *Editor*

[Carl Anderson](#) *Editor*

[Jon Portnoy](#) *Editor*

[Zack Gilburd](#) *Editor*

[Jack Morgan](#) *Editor*

[Benny Chuang](#) *Editor*

[Erwin](#) *Editor*

[Joshua Kinard](#) *Editor*

[Tobias Scherbaum](#) *Editor*

[Xavier Neys](#) *Editor*

[Joshua Saddler](#) *Editor*

[Gerald J. Normandin Jr.](#) *Reviewer*

[Donnie Berkholz](#) *Reviewer*

[Ken Nowack](#) *Reviewer*

[Lars Weiler](#) *Contributor*

*Page updated March 16, 2013*

Content:

- [Installing Gentoo](#)

In this part you learn how to install Gentoo on your system.

1. [About the Gentoo Linux Installation](#)  
This chapter introduces you to the installation approach documented in this handbook.
2. [Choosing the Right Installation Medium](#)  
You can install Gentoo in many ways. This chapter explains how to install Gentoo using the minimal Installation CD.
3. [Configuring your Network](#)  
To be able to download the latest source code, you will need to setup networking.
4. [Preparing the Disks](#)  
To be able to install Gentoo, you must create the necessary partitions. This chapter describes how to partition a disk for future usage.
5. [Installing the Gentoo Installation Files](#)  
Gentoo installs work through a stage3 archive. In this chapter we describe how you extract the stage3 archive and configure Portage.
6. [Installing the Gentoo Base System](#)  
After installing and configuring a stage3, the eventual result is that you have a Gentoo base system at your disposal. This chapter describes how to progress to that state.
7. [Configuring the Kernel](#)  
The Linux kernel is the core of every distribution. This chapter explains how to configure your kernel.
8. [Configuring your System](#)  
You need to edit some important configuration files. In this chapter you receive an overview of these files and an explanation on how to proceed.
9. [Installing Necessary System Tools](#)  
In this chapter we help you choose and install some important tools.
10. [Configuring the Bootloader](#)  
In this chapter we'll describe the GRUB bootloader and step you through the process of configuring GRUB to your needs.
11. [Finalizing your Gentoo Installation](#)  
You're almost done. We'll just create one (or more) users for your system.
12. [Where to go from here?](#)  
Now you have your Gentoo system, but what's next?

- [Working with Gentoo](#)

Learn how to work with Gentoo: installing software, altering variables, changing Portage behaviour etc.

1. [A Portage Introduction](#)  
This chapter explains the "simple" steps a user definitely needs to know to maintain the software on his system.

2. [USE flags](#)  
USE flags are a very important aspect of Gentoo. In this chapter, you learn to work with USE flags and understand how USE flags interact with your system.
3. [Portage Features](#)  
Discover the features Portage has, such as support for distributed compiling, ccache and more.
4. [Initscripts](#)  
Gentoo uses a special initscript format which, amongst other features, allows dependency-driven decisions and virtual initscripts. This chapter explains all these aspects and explains how to deal with these scripts.
5. [Environment Variables](#)  
With Gentoo you can easily manage the environment variables for your system. This chapter explains how you do that, and also describes frequently used variables.
- [Working with Portage](#)  
"Working with Portage" provides an in-depth coverage of Portage, Gentoo's Software Management Tool.
  1. [Files and Directories](#)  
Once you want to know Portage in-depth you need to know where it stores its files and data.
  2. [Configuring through Variables](#)  
Portage is completely configurable through various variables you can set in the configuration file or as environment variable.
  3. [Mixing Software Branches](#)  
Gentoo provides software separated in several branches, depending on stability and architectural support. "Mixing Software Branches" inform you how these branches can be configured and how you can override this separation individually.
  4. [Additional Portage Tools](#)  
Portage comes with a few extra tools that might make your Gentoo experience even better. Read on to discover how to use dispatch-conf and other tools.
  5. [Diverting from the Official Tree](#)  
"Diverting from the Official Tree" gives you some tips and tricks on how to use your own Portage tree, how to synchronise only the categories you want, inject packages and more.
  6. [Advanced Portage Features](#)  
As times goes by, Portage evolves and matures further and further. Additional features are continuously being put in - many of these are only of use by more advanced users. This chapter will go into more detail of these specific features.
- [Gentoo Network Configuration](#)  
A comprehensive guide to Networking in Gentoo.
  1. [Getting Started](#)  
A guide to quickly get your network interface up and running in most common environments.
  2. [Advanced Configuration](#)  
Here we learn about how the configuration works - you need to know this before we learn about modular networking.
  3. [Modular Networking](#)  
Gentoo provides you flexible networking - here you are told about choosing different DHCP clients, setting up bonding, bridging, VLANs and more.
  4. [Wireless Networking](#)  
Wireless configuration can be tricky. Hopefully we'll get you working!
  5. [Adding Functionality](#)  
If you're feeling adventurous, you can add your own functions to networking.
  6. [Network Management](#)  
For laptop users or people who move their computer around different networks.

## A. Installing Gentoo

### 1. About the Gentoo Linux Installation

#### 1.a. Introduction

##### Welcome!

First of all, *welcome* to Gentoo. You are about to enter the world of choices and performance. Gentoo is all about choices. When installing Gentoo, this is made clear to you several times -- you can choose how much you want to compile yourself, how to install Gentoo, what system logger you want, etc.

Gentoo is a fast, modern metadistribution with a clean and flexible design. Gentoo is built around free software and doesn't hide from its users what is beneath the hood. Portage, the package maintenance system which Gentoo uses, is written in Python, meaning you can easily view and modify the source code. Gentoo's packaging system uses source code (although support for precompiled packages is included too) and configuring Gentoo happens through regular textfiles. In other words, openness everywhere.

It is very important that you understand that *choices* are what makes Gentoo run. We try not to force you onto anything you don't like. If you feel like we do, please [bugreport](#) it.

##### How is the Installation Structured?

The Gentoo Installation can be seen as a 10-step procedure, corresponding to chapters 2 - 11. Every step results in a certain state:

- After step 1, you are in a working environment ready to install Gentoo
- After step 2, your internet connection is ready to install Gentoo
- After step 3, your hard disks are initialized to house your Gentoo installation
- After step 4, your installation environment is prepared and you are ready to chroot into the new environment
- After step 5, core packages, which are the same on all Gentoo installations, are installed
- After step 6, you have compiled your Linux kernel
- After step 7, you have written most of your Gentoo system configuration files

- After step 8, necessary system tools (which you can choose from a nice list) are installed
- After step 9, your choice of bootloader has been installed and configured and you are logged in into your new Gentoo installation
- After step 10, your Gentoo Linux environment is ready to be explored

When you are given a certain choice, we try our best to explain what the pros and cons are. We will continue then with a default choice, identified by "Default: " in the title. The other possibilities are marked by "Alternative: ". Do *not* think that the default is what we recommend. It is however what we believe most users will use.

Sometimes you can pursue an optional step. Such steps are marked as "Optional: " and are therefore not needed to install Gentoo. However, some optional steps are dependent on a previous decision you made. We will inform you when this happens, both when you make the decision, and right before the optional step is described.

What are my Options?

You can install Gentoo in many different ways. You can download and install from one of our Installation CDs, from a distribution already installed, from a non-Gentoo bootable CD (such as Knoppix), from a netbooted environment, from a rescue floppy, etc.

This document covers the installation using a *Gentoo Installation CD* or, in certain cases, netbooting. This installation assumes that you want to install the latest available version of each package.

**Note:** For help on the other installation approaches, including using non-Gentoo CDs, please read our [Alternative Installation Guide](#).

If you want to perform a networkless installation, you should read the [Gentoo 2008.0 Handbooks](#) which contain the installation instructions for a networkless environment.

Also note that, if you plan on using GRP (the Gentoo Reference Platform, a collection of prebuilt packages meant for immediate use after a Gentoo installation), you *must* follow the instructions in the [Gentoo 2008.0 Handbooks](#).

We also provide a [Gentoo Installation Tips & Tricks](#) document that might be useful to read as well. If you are an experienced Gentoo user and just need a brief installation checklist, feel free to use our Quick Installation Guide available from our [Documentation Resources](#) if your architecture has such a document available.

You also have several possibilities: you can compile your entire system from scratch or use a prebuilt environment to have your Gentoo environment up and running in no time. And of course you have intermediate solutions in which you don't compile everything but start from a semi-ready system.

Troubles?

If you find a problem in the installation (or in the installation documentation), please visit our [bugtracking system](#) and check if the bug is known. If not, please create a bugreport for it so we can take care of it. Do not be afraid of the developers who are assigned to (your) bugs -- they generally don't eat people.

Note though that, although the document you are now reading is architecture-specific, it will contain references to other architectures as well. This is due to the fact that large parts of the Gentoo Handbook use source code that is common for all architectures (to avoid duplication of efforts and starvation of development resources). We will try to keep this to a minimum to avoid confusion.

If you are uncertain if the problem is a user-problem (some error you made despite having read the documentation carefully) or a software-problem (some error we made despite having tested the installation/documentation carefully) you are free to join #gentoo on irc.freenode.net. Of course, you are welcome otherwise too as our chat channel covers the broad Gentoo spectrum :)

Speaking of which, if you have a question regarding Gentoo, check out our [Frequently Asked Questions](#), available from the [Gentoo Documentation](#). You can also view the [FAQs](#) on our [forums](#).

2. Choosing the Right Installation Medium

2.a. Hardware Requirements

Introduction

Before we start, we first list what hardware requirements you need to successfully install Gentoo on your box.

Hardware Requirements

	Minimal CD	LiveCD
CPU	Any AMD64 CPU or <a href="#">EM64T CPU</a> (Core 2 Duo & Quad processors are EM64T)	
Memory	256 MB	512 MB
Diskspace	2.5 GB (excluding swap space)	
Swap space	At least 256 MB	

You should check the [Gentoo AMD64 Project Page](#) before proceeding.

2.b. The Gentoo Installation CDs

Introduction

The *Gentoo Installation CDs* are bootable CDs which contain a self-sustained Gentoo environment. They allow you to boot Linux from the CD. During the boot process your hardware is detected and the appropriate drivers are loaded. They are maintained by Gentoo developers.

All Installation CDs allow you to boot, set up networking, initialize your partitions and start installing Gentoo from the Internet.

Gentoo Minimal Installation CD

The Minimal Installation CD is called `install-amd64-minimal-<release>.iso` and takes up around 200 MB of disk space. You can use this Installation CD to install Gentoo, but *only* with a working Internet connection.

## Gentoo Linux LiveDVDs

Every 6 months (give or take), a special DVD is crafted by the Gentoo Ten project which can be used to install Gentoo with too. The instructions further down this chapter target the Minimal Installation CDs so might be a bit different. However, the LiveDVD (or any other bootable Linux environment) supports getting a root prompt by just invoking `sudo su -` or `sudo -i` on a terminal.

## The Stage3 Tarball

A stage3 tarball is an archive containing a minimal Gentoo environment, suitable to continue the Gentoo installation using the instructions in this manual. Previously, the Gentoo Handbook described the installation using one of three stage tarballs. While Gentoo still offers stage1 and stage2 tarballs, the official installation method uses the stage3 tarball. If you are interested in performing a Gentoo installation using a stage1 or stage2 tarball, please read the Gentoo FAQ on [How do I Install Gentoo Using a Stage1 or Stage2 Tarball?](#)

Stage3 tarballs can be downloaded from `releases/amd64/autobuilds/current-stage3/` on any of the [Official Gentoo Mirrors](#) and are not provided on the LiveCD.

## 2.c. Download, Burn and Boot a Gentoo Installation CD

### Downloading and Burning the Installation CDs

You have chosen to use a Gentoo Installation CD. We'll first start by downloading and burning the chosen Installation CD. We previously discussed the several available Installation CDs, but where can you find them?

You can download any of the Installation CDs from one of our [mirrors](#). The Installation CDs are located in the `releases/amd64/autobuilds/current-iso/` directory.

Inside that directory you'll find ISO files. Those are full CD images which you can write on a CD-R.

In case you wonder if your downloaded file is corrupted or not, you can check its SHA-2 checksum and compare it with the SHA-2 checksum we provide (such as `install-amd64-minimal-<release>.iso.DIGESTS`). You can check the SHA-2 checksum with the `sha512sum` tool under Linux/Unix or [File Checksum Tool](#) for Windows.

Another way to check the validity of the downloaded file is to use GnuPG to verify the cryptographic signature that we provide (the file ending with `.asc`).

Download the signature file and obtain the public keys whose key ids can be found on the [release engineering project site](#).

#### Code Listing 3.1: Obtaining the public key

```
(... Substitute the key ids with those mentioned on the release engineering site ...)
$ gpg --keyserver subkeys.pgp.net --recv-keys 96D8BF6D 2D182910 17072058
```

Now verify the signature:

#### Code Listing 3.2: Verify the files

```
(Verify the cryptographic signature)
$ gpg --verify <downloaded iso.DIGESTS.asc>
(Verify the checksum)
$ sha1sum -c <downloaded iso.DIGESTS.asc>
```

To burn the downloaded ISO(s), you have to select raw-burning. How you do this is highly program-dependent. We will discuss `cdrecord` and `k3b` here; more information can be found in our [Gentoo FAQ](#).

- With `cdrecord`, you simply type `cdrecord dev=/dev/hdc <downloaded iso file>` (replace `/dev/hdc` with your CD-RW drive's device path).
- With `K3B`, select **Tools > Burn CD Image**. Then you can locate your ISO file within the 'Image to Burn' area. Finally click **Start**.

## Booting the Installation CD

Once you have burnt your installation CD, it is time to boot it. Remove all CDs from your CD drives, reboot your system and enter the BIOS. This is usually done by hitting DEL, F1 or ESC, depending on your BIOS. Inside the BIOS, change the boot order so that the CD-ROM is tried before the hard disk. This is often found under "CMOS Setup". If you don't do this, your system will just reboot from the hard disk, ignoring the CD-ROM.

Now place the installation CD in the CD-ROM drive and reboot. You should see a boot prompt. At this screen, you can hit Enter to begin the boot process with the default boot options, or boot the Installation CD with custom boot options by specifying a kernel followed by boot options and then hitting Enter.

When the boot prompt is shown, you get the option of displaying the available kernels (**F1**) and boot options (**F2**). If you make no selection within 15 seconds (either displaying information or using a kernel) then the LiveCD will fall back to booting from disk. This allows installations to reboot and try out their installed environment without the need to remove the CD from the tray (something well appreciated for remote installations).

Now we mentioned specifying a kernel. On our Installation CDs, we provide several kernels. The default one is `gentoo`. Other kernels are for specific hardware needs and the `-nofb` variants which disable framebuffer.

Below you'll find a short overview on the available kernels:

Kernel	Description
<code>gentoo</code>	Default kernel with support for K8 CPUs (including NUMA support) and EM64T CPUs
<code>gentoo-nofb</code>	Same as <code>gentoo</code> but without framebuffer support
<code>memtest86</code>	Test your local RAM for errors

You can also provide kernel options. They represent optional settings you can (de)activate at will.

### Hardware options:

#### `acpi=on`

This loads support for ACPI and also causes the `acpid` daemon to be started by the CD on boot. This is only needed if your system requires ACPI to function properly. This is not required for Hyperthreading support.

#### `acpi=off`

Completely disables ACPI. This is useful on some older systems and is also a requirement for using APM. This will disable any Hyperthreading support of your processor.

#### **console=X**

This sets up serial console access for the CD. The first option is the device, usually ttyS0 on x86, followed by any connection options, which are comma separated. The default options are 9600,8,n,1.

#### **dmraid=X**

This allows for passing options to the device-mapper RAID subsystem. Options should be encapsulated in quotes.

#### **doapm**

This loads APM driver support. This requires you to also use acpi=off.

#### **dopcmcia**

This loads support for PCMCIA and Cardbus hardware and also causes the pcmcia cardmgr to be started by the CD on boot. This is only required when booting from PCMCIA/Cardbus devices.

#### **doscsi**

This loads support for most SCSI controllers. This is also a requirement for booting most USB devices, as they use the SCSI subsystem of the kernel.

#### **sda=stroke**

This allows you to partition the whole hard disk even when your BIOS is unable to handle large disks. This option is only used on machines with an older BIOS. Replace sda with the device that requires this option.

#### **ide=nodma**

This forces the disabling of DMA in the kernel and is required by some IDE chipsets and also by some CDROM drives. If your system is having trouble reading from your IDE CDROM, try this option. This also disables the default hdparm settings from being executed.

#### **noapic**

This disables the Advanced Programmable Interrupt Controller that is present on newer motherboards. It has been known to cause some problems on older hardware.

#### **nodetect**

This disables all of the autodetection done by the CD, including device autodetection and DHCP probing. This is useful for doing debugging of a failing CD or driver.

#### **nodhcp**

This disables DHCP probing on detected network cards. This is useful on networks with only static addresses.

#### **nodmraid**

Disables support for device-mapper RAID, such as that used for on-board IDE/SATA RAID controllers.

#### **nofirewire**

This disables the loading of Firewire modules. This should only be necessary if your Firewire hardware is causing a problem with booting the CD.

#### **nogpm**

This disables gpm console mouse support.

#### **nohotplug**

This disables the loading of the hotplug and coldplug init scripts at boot. This is useful for doing debugging of a failing CD or driver.

#### **nokeymap**

This disables the keymap selection used to select non-US keyboard layouts.

#### **noapic**

This disables the local APIC on Uniprocessor kernels.

#### **nosata**

This disables the loading of Serial ATA modules. This is used if your system is having problems with the SATA subsystem.

#### **nosmp**

This disables SMP, or Symmetric Multiprocessing, on SMP-enabled kernels. This is useful for debugging SMP-related issues with certain drivers and motherboards.

#### **nosound**

This disables sound support and volume setting. This is useful for systems where sound support causes problems.

#### **nousb**

This disables the autoloading of USB modules. This is useful for debugging USB issues.

#### **slowusb**

This adds some extra pauses into the boot process for slow USB CDROMs, like in the IBM BladeCenter.

### **Volume/Device Management:**

#### **dolvm**

This enables support for Linux's Logical Volume Management.

### **Other options:**

#### **debug**

Enables debugging code. This might get messy, as it displays a lot of data to the screen.

#### **docache**

This caches the entire runtime portion of the CD into RAM, which allows you to umount /mnt/cdrom and mount another CDROM. This option requires that you have at least twice as much available RAM as the size of the CD.

#### **doload=X**

This causes the initial ramdisk to load any module listed, as well as dependencies. Replace X with the module name. Multiple modules can be specified by a comma-separated list.

#### **dosshd**

Starts sshd on boot, which is useful for unattended installs.

#### **passwd=foo**

Sets whatever follows the equals as the root password, which is required for dosshd since we scramble the root password.

#### **noload=X**

This causes the initial ramdisk to skip the loading of a specific module that may be causing a problem. Syntax matches that of doload.

#### **nonfs**

Disables the starting of portmap/nfsmount on boot.

#### **nox**

This causes an X-enabled LiveCD to not automatically start X, but rather, to drop to the command line instead.

#### **scandelay**

This causes the CD to pause for 10 seconds during certain portions the boot process to allow for devices that are slow to initialize to be ready for use.

#### **scandelay=X**

This allows you to specify a given delay, in seconds, to be added to certain portions of the boot process to allow for devices that are slow to initialize to be ready for use. Replace X with the number of seconds to pause.

**Note:** The CD will check for "no\*" options before "do\*" options, so that you can override any option in the exact order you specify.

Now boot your CD, select a kernel (if you are not happy with the default [gentoo](#) kernel) and boot options. As an example, we show you how to boot the [gentoo](#) kernel, with [dopcmcia](#) as kernel parameters:

#### Code Listing 3.3: Booting an Installation CD

```
boot: gentoo dopcmcia
```

You will then be greeted with a boot screen and progress bar. If you are installing Gentoo on a system with a non-US keyboard, make sure you immediately press Alt-F1 to switch to verbose mode and follow the prompt. If no selection is made in 10 seconds the default (US keyboard) will be accepted and the boot process will continue. Once the boot process completes, you will be automatically logged in to the "Live" Gentoo Linux as "root", the super user. You should have a root ("#") prompt on the current console and can also switch to other consoles by pressing Alt-F2, Alt-F3 and Alt-F4. Get back to the one you started on by pressing Alt-F1.

Now continue with [Extra Hardware Configuration](#).

### Extra Hardware Configuration

When the Installation CD boots, it tries to detect all your hardware devices and loads the appropriate kernel modules to support your hardware. In the vast majority of cases, it does a very good job. However, in some cases it may not auto-load the kernel modules you need. If the PCI auto-detection missed some of your system's hardware, you will have to load the appropriate kernel modules manually.

In the next example we try to load the [8139too](#) module (support for certain kinds of network interfaces):

#### Code Listing 3.4: Loading kernel modules

```
# modprobe 8139too
```

### Optional: User Accounts

If you plan on giving other people access to your installation environment or you want to chat using [irssi](#) without root privileges (for security reasons), you need to create the necessary user accounts and change the root password.

To change the root password, use the [passwd](#) utility:

#### Code Listing 3.5: Changing the root password

```
# passwd
New password: (Enter your new password)
Re-enter password: (Re-enter your password)
```

To create a user account, we first enter their credentials, followed by its password. We use [useradd](#) and [passwd](#) for these tasks. In the next example, we create a user called "john".

#### Code Listing 3.6: Creating a user account

```
# useradd -m -G users john
# passwd john
New password: (Enter john's password)
Re-enter password: (Re-enter john's password)
```

You can change your user id from root to the newly created user by using [su](#):

#### Code Listing 3.7: Changing user id

```
# su - john
```

### Optional: Viewing Documentation while Installing

If you want to view the Gentoo Handbook during the installation, make sure you have created a user account (see [Optional: User Accounts](#)). Then press **Alt-F2** to go to a new terminal.

You can view the handbook using [links](#), once you have completed the *Configuring your Network* chapter (otherwise you won't be able to go on the Internet to view the document):

#### Code Listing 3.8: Viewing the Online Documentation

```
# links http://www.gentoo.org/doc/en/handbook/handbook-amd64.xml
```

You can go back to your original terminal by pressing **Alt-F1**.

### Optional: Starting the SSH Daemon

If you want to allow other users to access your computer during the Gentoo installation (perhaps because those users are going to help you install Gentoo, or even do it for you), you need to create a user account for them and perhaps even provide them with your root password (*only* do that *if* you **fully trust** that user).

To fire up the SSH daemon, execute the following command:

#### Code Listing 3.9: Starting the SSH daemon

```
# /etc/init.d/sshd start
```

**Note:** If you (or other users) log on to the system, they will get a message that the host key for this system needs to be confirmed (through what is called a fingerprint). This is to be expected as it is the first time people log on to the system. However, later when your system is set up and you log on to the newly created system, your SSH client will warn you that the host key has been changed. This is because you now log on to - for SSH - a different server (namely your freshly installed Gentoo system rather than the live environment you are on right now). When you hit that warning, follow the instructions given on the screen then to replace the host key on the client system.



To be able to use `sshd`, you first need to set up your networking. Continue with the chapter on [Configuring your Network](#).

### 3. Configuring your Network

#### 3.a. Automatic Network Detection

##### Maybe it just works?

If your system is plugged into an Ethernet network with a DHCP server, it is very likely that your networking configuration has already been set up automatically for you. If so, you should be able to take advantage of the many included network-aware commands on the Installation CD such as [ssh](#), [scp](#), [ping](#), [irssi](#), [wget](#) and [links](#), among others.

If networking has been configured for you, the `ifconfig` command should list some network interfaces besides `lo`, such as `eth0`:

##### Code Listing 1.1: `ifconfig` for a working network configuration

```
# ifconfig
(...)
eth0      Link encap:Ethernet  HWaddr 00:50:BA:8F:61:7A
          inet addr:192.168.0.2  Bcast:192.168.0.255  Mask:255.255.255.0
          inet6 addr: fe80::50:ba8f:617a/10 Scope:Link
          UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
          RX packets:1498792 errors:0 dropped:0 overruns:0 frame:0
          TX packets:1284980 errors:0 dropped:0 overruns:0 carrier:0
          collisions:1984 txqueuelen:100
          RX bytes:485691215 (463.1 Mb)  TX bytes:123951388 (118.2 Mb)
          Interrupt:11 Base address:0xe800
```

##### Optional: Configure any Proxies

If you access the Internet through a proxy, you might need to set up proxy information during the installation. It is very easy to define a proxy: you just need to define a variable which contains the proxy server information.

In most cases, you can just define the variables using the server hostname. As an example, we assume the proxy is called [proxy.gentoo.org](#) and the port is `8080`.

##### Code Listing 1.2: Defining proxy servers

```
(If the proxy filters HTTP traffic)
# export http_proxy="http://proxy.gentoo.org:8080"
(If the proxy filters FTP traffic)
# export ftp_proxy="ftp://proxy.gentoo.org:8080"
(If the proxy filters RSYNC traffic)
# export RSYNC_PROXY="proxy.gentoo.org:8080"
```

If your proxy requires a username and password, you should use the following syntax for the variable:

##### Code Listing 1.3: Adding username/password to the proxy variable

```
http://username:password@proxy.gentoo.org:8080
```

#### Testing the Network

You may want to try pinging your ISP's DNS server (found in `/etc/resolv.conf`) and a Web site of your choice, just to make sure that your packets are reaching the net, DNS name resolution is working correctly, etc.

##### Code Listing 1.4: Further network testing

```
# ping -c 3 www.gentoo.org
```

If you are now able to use your network, you can skip the rest of this section and continue with [Preparing the Disks](#). If not, read on.

#### 3.b. Automatic Network Configuration

If the network doesn't work immediately, some installation media allow you to use [net-setup](#) (for regular or wireless networks), [pppoe-setup](#) (for ADSL-users) or [pptp](#) (for PPTP-users - available on x86, amd64, alpha, ppc and ppc64).

If your installation medium does not contain any of these tools or your network doesn't function yet, continue with [Manual Network Configuration](#).

- Regular Ethernet users should continue with [Default: Using net-setup](#)
- ADSL users should continue with [Alternative: Using PPP](#)
- PPTP users should continue with [Alternative: Using PPTP](#)

##### Default: Using net-setup

The simplest way to set up networking if it didn't get configured automatically is to run the `net-setup` script:

##### Code Listing 2.1: Running the net-setup script

```
# net-setup eth0
```

`net-setup` will ask you some questions about your network environment. When all is done, you should have a working network connection. Test your network connection as stated before. If the tests are positive, congratulations! You are now ready to install Gentoo. Skip the rest of this section and continue with [Preparing the Disks](#).

If your network still doesn't work, continue with [Manual Network Configuration](#).

### Alternative: Using PPP

Assuming you need PPPoE to connect to the internet, the Installation CD (any version) has made things easy for you by including [ppp](#). Use the provided [pppoe-setup](#) script to configure your connection. You will be prompted for the ethernet device that is connected to your adsl modem, your username and password, the IPs of your DNS servers and if you need a basic firewall or not.

#### Code Listing 2.2: Using ppp

```
# pppoe-setup
# pppoe-start
```

If something goes wrong, double-check that you correctly typed your username and password by looking at `/etc/ppp/pap-secrets` or `/etc/ppp/chap-secrets` and make sure you are using the right ethernet device. If your ethernet device doesn't exist, you will have to load the appropriate network modules. In that case you should continue with [Manual Network Configuration](#) as we explain how to load the appropriate network modules there.

If everything worked, continue with [Preparing the Disks](#).

### Alternative: Using PPTP

If you need PPTP support, you can use [pptpclient](#) which is provided by our Installation CDs. But first you need to make sure that your configuration is correct. Edit `/etc/ppp/pap-secrets` or `/etc/ppp/chap-secrets` so it contains the correct username/password combination:

#### Code Listing 2.3: Editing /etc/ppp/chap-secrets

```
# nano -w /etc/ppp/chap-secrets
```

Then adjust `/etc/ppp/options.pptp` if necessary:

#### Code Listing 2.4: Editing /etc/ppp/options.pptp

```
# nano -w /etc/ppp/options.pptp
```

When all that is done, just run [pptp](#) (along with the options you couldn't set in `options.pptp`) to connect the server:

#### Code Listing 2.5: Connection to a dial-in server

```
# pptp <server ip>
```

Now continue with [Preparing the Disks](#).

## 3.c. Manual Network Configuration

### Loading the Appropriate Network Modules

When the Installation CD boots, it tries to detect all your hardware devices and loads the appropriate kernel modules (drivers) to support your hardware. In the vast majority of cases, it does a very good job. However, in some cases, it may not auto-load the kernel modules you need.

If [net-setup](#) or [pppoe-setup](#) failed, then it is possible that your network card wasn't found immediately. This means you may have to load the appropriate kernel modules manually.

To find out what kernel modules we provide for networking, use `ls`:

#### Code Listing 3.1: Searching for provided modules

```
# ls /lib/modules/`uname -r`/kernel/drivers/net
```

If you find a driver for your network card, use [modprobe](#) to load the kernel module:

#### Code Listing 3.2: Using modprobe to load a kernel module

```
(As an example, we load the pcnet32 module)
# modprobe pcnet32
```

To check if your network card is now detected, use [ifconfig](#). A detected network card would result in something like this:

#### Code Listing 3.3: Testing availability of your network card, successful

```
# ifconfig eth0
eth0      Link encap:Ethernet  HWaddr FE:FD:00:00:00:00
          BROADCAST NOARP MULTICAST  MTU:1500  Metric:1
          RX packets:0 errors:0 dropped:0 overruns:0 frame:0
          TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:0
          RX bytes:0 (0.0 b)  TX bytes:0 (0.0 b)
```

If however you receive the following error, the network card is not detected:

#### Code Listing 3.4: Testing availability of your network card, failed

```
# ifconfig eth0
eth0: error fetching interface information: Device not found
```

If you have multiple network cards in your system they are named `eth0`, `eth1`, etc. Make sure that the network card you want to use works well and remember to use the correct naming throughout this document. We will assume that the network card `eth0` is used.

Assuming that you now have a detected network card, you can retry [net-setup](#) or [pppoe-setup](#) again (which should work now), but for the hardcore people amongst you we explain how to configure your network manually.

Select one of the following sections based on your network setup:



- [Using DHCP](#) for automatic IP retrieval
- [Preparing for Wireless Access](#) if you have a wireless card
- [Understanding Network Terminology](#) explains what you need to know about networking
- [Using ifconfig and route](#) explains how to set up your networking manually

## Using DHCP

DHCP (Dynamic Host Configuration Protocol) makes it possible to automatically receive networking information (IP address, netmask, broadcast address, gateway, nameservers etc.). This only works if you have a DHCP server in your network (or if your provider provides a DHCP service). To have a network interface receive this information automatically, use `dhcpcd`:

### Code Listing 3.5: Using dhcpcd

```
# dhcpcd eth0
Some network admins require that you use the
hostname and domainname provided by the DHCP server.
In that case, use
# dhcpcd -HD eth0
```

If this works (try pinging some internet server, like [Google](#)), then you are all set and ready to continue. Skip the rest of this section and continue with [Preparing the Disks](#).

## Preparing for Wireless Access

**Note:** Support for the `iwconfig` command is only available on x86, amd64 and ppc Installation CDs. You can still get the extensions working otherwise by following the instructions of the [linux-wlan-ng project](#).

If you are using a wireless (802.11) card, you may need to configure your wireless settings before going any further. To see the current wireless settings on your card, you can use `iwconfig`. Running `iwconfig` might show something like:

### Code Listing 3.6: Showing the current wireless settings

```
# iwconfig eth0
eth0      IEEE 802.11-DS  ESSID:"GentooNode"
          Mode:Managed  Frequency:2.442GHz  Access Point: 00:09:5B:11:CC:F2
          Bit Rate:11Mb/s   Tx-Power=20 dBm   Sensitivity=0/65535
          Retry limit:16   RTS thr:off   Fragment thr:off
          Power Management:off
          Link Quality:25/10  Signal level:-51 dBm  Noise level:-102 dBm
          Rx invalid nwid:5901 Rx invalid crypt:0 Rx invalid frag:0 Tx
          excessive retries:237 Invalid misc:350282 Missed beacon:84
```

**Note:** Some wireless cards may have a device name of `wlan0` or `ra0` instead of `eth0`. Run `iwconfig` without any command-line parameters to determine the correct device name.

For most users, there are only two settings that might be important to change, the ESSID (aka wireless network name) or the WEP key. If the ESSID and Access Point address listed are already that of your access point and you are not using WEP, then your wireless is working. If you need to change your ESSID, or add a WEP key, you can issue the following commands:

**Note:** If your wireless network is set up with WPA or WPA2, you will need to use `wpa_supplicant`. For more information on configuring wireless networking in Gentoo Linux, please read the [Wireless Networking](#) chapter in the Gentoo Handbook.

### Code Listing 3.7: Changing ESSID and/or adding WEP key

```
(This sets the network name to "GentooNode")
# iwconfig eth0 essid GentooNode

(This sets a hex WEP key)
# iwconfig eth0 key 1234123412341234abcd

(This sets an ASCII key - prefix it with "s:")
# iwconfig eth0 key s:some-password
```

You can then confirm your wireless settings again by using `iwconfig`. Once you have wireless working, you can continue configuring the IP level networking options as described in the next section ([Understanding Network Terminology](#)) or use the `net-setup` tool as described previously.

## Understanding Network Terminology

**Note:** If you know your IP address, broadcast address, netmask and nameservers, then you can skip this subsection and continue with [Using ifconfig and route](#).

If all of the above fails, you will have to configure your network manually. This is not difficult at all. However, you need to be familiar with some network terminology, as you will need it to be able to configure your network to your satisfaction. After reading this, you will know what a *gateway* is, what a *netmask* serves for, how a *broadcast* address is formed and why you need *nameservers*.

In a network, hosts are identified by their *IP address* (Internet Protocol address). Such an address is a combination of four numbers between 0 and 255. Well, at least that is how we perceive it. In reality, such an IP address consists of 32 bits (ones and zeros). Let's view an example:

### Code Listing 3.8: Example of an IP address

```
IP Address (numbers): 192.168.0.2
IP Address (bits):   11000000 10101000 00000000 00000010
                    -----
                    192      168      0      2
```

Such an IP address is unique to a host as far as all accessible networks are concerned (i.e. every host that you are able to reach must have a unique IP address). In order to distinguish between hosts inside and outside a network, the IP address is divided in two parts: the *network* part and the *host* part.

The separation is written down with the *netmask*, a collection of ones followed by a collection of zeros. The part of the IP that can be mapped on the ones is the network-part, the other one is the host-part. As usual, the netmask can be written down as an IP-address.

Code Listing 3.9: Example of network/host separation

IP-address:	192	168	0	2
	11000000	10101000	00000000	00000010
Netmask:	11111111	11111111	11111111	00000000
	255	255	255	0
	+-----+-----+			
	Network			Host

In other words, 192.168.0.14 is still part of our example network, but 192.168.1.2 is not.

The *broadcast* address is an IP-address with the same network-part as your network, but with only ones as host-part. Every host on your network listens to this IP address. It is truly meant for broadcasting packets.

Code Listing 3.10: Broadcast address

IP-address:	192	168	0	2
	11000000	10101000	00000000	00000010
Broadcast:	11000000	10101000	00000000	11111111
	192	168	0	255
	+-----+-----+			
	Network			Host

To be able to surf on the internet, you must know which host shares the Internet connection. This host is called the *gateway*. Since it is a regular host, it has a regular IP address (for instance 192.168.0.1).

We previously stated that every host has its own IP address. To be able to reach this host by a name (instead of an IP address) you need a service that translates a name (such as *dev.gentoo.org*) to an IP address (such as *64.5.62.82*). Such a service is called a name service. To use such a service, you must define the necessary *name servers* in */etc/resolv.conf*.

In some cases, your gateway also serves as nameserver. Otherwise you will have to enter the nameservers provided by your ISP.

To summarise, you will need the following information before continuing:

Network Item	Example
Your IP address	192.168.0.2
Netmask	255.255.255.0
Broadcast	192.168.0.255
Gateway	192.168.0.1
Nameserver(s)	195.130.130.5, 195.130.130.133

Using ifconfig and route

Setting up your network consists of three steps. First we assign ourselves an IP address using *ifconfig*. Then we set up routing to the gateway using *route*. Then we finish up by placing the nameserver IPs in */etc/resolv.conf*.

To assign an IP address, you will need your IP address, broadcast address and netmask. Then execute the following command, substituting *\${IP\_ADDR}* with your IP address, *\${BROADCAST}* with your broadcast address and *\${NETMASK}* with your netmask:

Code Listing 3.11: Using ifconfig

```
# ifconfig eth0 ${IP_ADDR} broadcast ${BROADCAST} netmask ${NETMASK} up
```

Now set up routing using *route*. Substitute *\${GATEWAY}* with your gateway IP address:

Code Listing 3.12: Using route

```
# route add default gw ${GATEWAY}
```

Now open */etc/resolv.conf* with your favorite editor (in our example, we use *nano*):

Code Listing 3.13: Creating /etc/resolv.conf

```
# nano -w /etc/resolv.conf
```

Now fill in your nameserver(s) using the following as a template. Make sure you substitute *\${NAMESERVER1}* and *\${NAMESERVER2}* with the appropriate nameserver addresses:

Code Listing 3.14: /etc/resolv.conf template

```
nameserver ${NAMESERVER1}
nameserver ${NAMESERVER2}
```

That's it. Now test your network by pinging some Internet server (like [Google](#)). If this works, congratulations then. You are now ready to install Gentoo. Continue with [Preparing the Disks](#).

4. Preparing the Disks

4.a. Introduction to Block Devices

Block Devices

We'll take a good look at disk-oriented aspects of Gentoo Linux and Linux in general, including Linux filesystems, partitions and block devices. Then, once you're familiar with the ins and outs of disks and filesystems, you'll be guided through the process of setting up partitions and filesystems for your Gentoo Linux installation.

To begin, we'll introduce *block devices*. The most famous block device is probably the one that represents the first drive in a Linux system, namely `/dev/sda`. SCSI and Serial ATA drives are both labeled `/dev/sd*`; even IDE drives are labeled `/dev/sd*` with the new libata framework in the kernel. If you're using the old device framework, then your first IDE drive is `/dev/hda`.

The block devices above represent an abstract interface to the disk. User programs can use these block devices to interact with your disk without worrying about whether your drives are IDE, SCSI or something else. The program can simply address the storage on the disk as a bunch of contiguous, randomly-accessible 512-byte blocks.

Partitions

Although it is theoretically possible to use a full disk to house your Linux system, this is almost never done in practice. Instead, full disk block devices are split up in smaller, more manageable block devices. On AMD64 systems, these are called *partitions*.

Partitions are divided in three types: *primary*, *extended* and *logical*.

A *primary* partition is a partition which has its information stored in the MBR (master boot record). As an MBR is very small (512 bytes) only four primary partitions can be defined (for instance, `/dev/sda1` to `/dev/sda4`).

An *extended* partition is a special primary partition (meaning the extended partition must be one of the four possible primary partitions) which contains more partitions. Such a partition didn't exist originally, but as four partitions were too few, it was brought to life to extend the formatting scheme without losing backward compatibility.

A *logical* partition is a partition inside the extended partition. Their definitions aren't placed inside the MBR, but are declared inside the extended partition.

Advanced Storage

The AMD64 Installation CDs provide support for LVM2. LVM2 increases the flexibility offered by your partitioning setup. During the installation instructions, we will focus on "regular" partitions, but it is still good to know LVM2 is supported as well.

4.b. Designing a Partitioning Scheme

Default Partitioning Scheme

If you are not interested in drawing up a partitioning scheme for your system, you can use the partitioning scheme we use throughout this book:

Partition	Filesystem	Size	Description
<code>/dev/sda1</code>	<code>ext2</code>	32M	Boot partition
<code>/dev/sda2</code>	<code>(swap)</code>	512M	Swap partition
<code>/dev/sda3</code>	<code>ext4</code>	Rest of the disk	Root partition

If you are interested in knowing how big a partition should be, or even how many partitions you need, read on. Otherwise continue now with partitioning your disk by reading [Using fdisk to Partition your Disk](#) or [Using parted to Partition your Disk](#) (both are partitioning tools, `fdisk` is well known and stable, `parted` is a bit more recent but supports partitions larger than 2TB).

How Many and How Big?

The number of partitions is highly dependent on your environment. For instance, if you have lots of users, you will most likely want to have your `/home` separate as it increases security and makes backups easier. If you are installing Gentoo to perform as a mailserver, your `/var` should be separate as all mails are stored inside `/var`. A good choice of filesystem will then maximise your performance. Gameservers will have a separate `/opt` as most gaming servers are installed there. The reason is similar for `/home`: security and backups. You will definitely want to keep `/usr` big: not only will it contain the majority of applications, the Portage tree alone takes around 500 Mbyte excluding the various sources that are stored in it.

As you can see, it very much depends on what you want to achieve. Separate partitions or volumes have the following advantages:

- You can choose the best performing filesystem for each partition or volume
- Your entire system cannot run out of free space if one defunct tool is continuously writing files to a partition or volume
- If necessary, file system checks are reduced in time, as multiple checks can be done in parallel (although this advantage is more with multiple disks than it is with multiple partitions)
- Security can be enhanced by mounting some partitions or volumes read-only, nosuid (setuid bits are ignored), noexec (executable bits are ignored) etc.

However, multiple partitions have disadvantages as well. If not configured properly, you will have a system with lots of free space on one partition and none on another. Another nuisance is that separate partitions - especially for important mountpoints like `/usr` or `/var` - often require the administrator to boot with an `initramfs` to mount the partition before other boot scripts start. This isn't always the case though, so your results may vary.

There is also a 15-partition limit for SCSI and SATA unless you use GPT labels.

As an example partitioning, we show you one for a 20GB disk, used as a demonstration laptop (containing webserver, mailserver, gnome, ...):

Code Listing 2.1: Filesystem usage example

```
$ df -h
Filesystem      Type      Size  Used Avail Use% Mounted on
/dev/sda5       ext4      509M  132M  351M   28% /
/dev/sda2       ext4      5.0G   3.0G   1.8G   63% /home
/dev/sda7       ext4      7.9G   6.2G   1.3G   83% /usr
/dev/sda8       ext4     1011M  483M  477M   51% /opt
/dev/sda9       ext4      2.0G   607M   1.3G   32% /var
/dev/sda1       ext2       51M    17M   31M   36% /boot
/dev/sda6       swap      516M    12M  504M    2% <not mounted>
(Unpartitioned space for future usage: 2 GB)
```

`/usr` is rather full (83% used) here, but once all software is installed, `/usr` doesn't tend to grow that much. Although allocating a few gigabytes of disk space for `/var` may seem excessive, remember that Portage uses this partition by default for compiling packages. If you want to keep `/var` at a more reasonable size, such as 1GB, you will need to alter your `PORTAGE_TMPDIR` variable in `/etc/portage/make.conf` to point to the partition with enough free space for compiling extremely large packages such as OpenOffice.

4.c. Using fdisk to Partition your Disk

**Important:** If your environment will deal with partitions larger than 2 TB, please use the [Using parted to Partition your Disk](#) instructions instead. `fdisk` is not able to deal with larger partitions.

The following parts explain how to create the example partition layout using `fdisk`. The example partition layout was mentioned earlier:

Partition	Description
<code>/dev/sda1</code>	Boot partition
<code>/dev/sda2</code>	Swap partition
<code>/dev/sda3</code>	Root partition

Change your partition layout according to your own preference.

Viewing the Current Partition Layout

`fdisk` is a popular and powerful tool to split your disk into partitions. Fire up `fdisk` on your disk (in our example, we use `/dev/sda`):

Code Listing 3.1: Starting fdisk

```
# fdisk /dev/sda
```

Once in `fdisk`, you'll be greeted with a prompt that looks like this:

Code Listing 3.2: fdisk prompt

```
Command (m for help):
```

Type `p` to display your disk's current partition configuration:

Code Listing 3.3: An example partition configuration

```
Command (m for help): p

Disk /dev/sda: 240 heads, 63 sectors, 2184 cylinders
Units = cylinders of 15120 * 512 bytes

   Device Boot      Start         End      Blocks   Id  System
/dev/sda1  *           1           14    105808+   83  Linux
/dev/sda2             15           49    264600   82  Linux swap
/dev/sda3             50           70    158760   83  Linux
/dev/sda4             71          2184   15981840   5  Extended
/dev/sda5             71           209    1050808+   83  Linux
/dev/sda6            210           348    1050808+   83  Linux
/dev/sda7            349           626    2101648+   83  Linux
/dev/sda8            627           904    2101648+   83  Linux
/dev/sda9            905          2184    9676768+   83  Linux

Command (m for help):
```

This particular disk is configured to house seven Linux filesystems (each with a corresponding partition listed as "Linux") as well as a swap partition (listed as "Linux swap").

Removing all Partitions

We will first remove all existing partitions from the disk. Type `d` to delete a partition. For instance, to delete an existing `/dev/sda1`:

Code Listing 3.4: Deleting a partition

```
Command (m for help): d
Partition number (1-4): 1
```

The partition has been scheduled for deletion. It will no longer show up if you type `p`, but it will not be erased until your changes have been saved. If you made a mistake and want to abort without saving your changes, type `q` immediately and hit enter and your partition will not be deleted.

Now, assuming that you do indeed want to wipe out all the partitions on your system, repeatedly type `p` to print out a partition listing and then type `d` and the number of the partition to delete it. Eventually, you'll end up with a partition table with nothing in it:

Code Listing 3.5: An empty partition table

```
Disk /dev/sda: 30.0 GB, 30005821440 bytes
240 heads, 63 sectors/track, 3876 cylinders
Units = cylinders of 15120 * 512 = 7741440 bytes

Device Boot      Start         End      Blocks   Id  System

Command (m for help):
```

Now that the in-memory partition table is empty, we're ready to create the partitions. We will use a default partitioning scheme as discussed previously. Of course, don't follow these instructions to the letter if you don't want the same partitioning scheme!

Creating the Boot Partition

We first create a small boot partition. Type `n` to create a new partition, then `p` to select a primary partition, followed by `1` to select the first primary partition. When prompted for the first cylinder, hit enter. When prompted for the last cylinder, type `+32M` to create a partition 32 Mbyte in size and set its bootable flag:

Code Listing 3.6: Creating the boot partition

```
Command (m for help): n
Command action
```

```
e    extended
p    primary partition (1-4)
p
Partition number (1-4): 1
First cylinder (1-3876, default 1): (Hit Enter)
Using default value 1
Last cylinder or +size or +sizeM or +sizeK (1-3876, default 3876): +32M
```

Now, when you type `p`, you should see the following partition printout:

**Code Listing 3.7: Created boot partition**

```
Command (m for help): p

Disk /dev/sda: 30.0 GB, 30005821440 bytes
240 heads, 63 sectors/track, 3876 cylinders
Units = cylinders of 15120 * 512 = 7741440 bytes

   Device Boot      Start         End      Blocks   Id  System
/dev/sda1            1           14     105808+    83  Linux
```

We need to make this partition bootable. Type `a` to toggle the bootable flag on a partition and select `1`. If you press `p` again, you will notice that an `*` is placed in the "Boot" column.

**Creating the Swap Partition**

Let's now create the swap partition. To do this, type `n` to create a new partition, then `p` to tell `fdisk` that you want a primary partition. Then type `2` to create the second primary partition, `/dev/sda2` in our case. When prompted for the first cylinder, hit enter. When prompted for the last cylinder, type `+512M` to create a partition 512MB in size. After you've done this, type `t` to set the partition type, `2` to select the partition you just created and then type in `82` to set the partition type to "Linux Swap". After completing these steps, typing `p` should display a partition table that looks similar to this:

**Code Listing 3.8: Partition listing after creating a swap partition**

```
Command (m for help): p

Disk /dev/sda: 30.0 GB, 30005821440 bytes
240 heads, 63 sectors/track, 3876 cylinders
Units = cylinders of 15120 * 512 = 7741440 bytes

   Device Boot      Start         End      Blocks   Id  System
/dev/sda1    *            1           14     105808+    83  Linux
/dev/sda2                15           81      506520    82  Linux swap
```

**Creating the Root Partition**

Finally, let's create the root partition. To do this, type `n` to create a new partition, then `p` to tell `fdisk` that you want a primary partition. Then type `3` to create the third primary partition, `/dev/sda3` in our case. When prompted for the first cylinder, hit enter. When prompted for the last cylinder, hit enter to create a partition that takes up the rest of the remaining space on your disk. After completing these steps, typing `p` should display a partition table that looks similar to this:

**Code Listing 3.9: Partition listing after creating the root partition**

```
Command (m for help): p

Disk /dev/sda: 30.0 GB, 30005821440 bytes
240 heads, 63 sectors/track, 3876 cylinders
Units = cylinders of 15120 * 512 = 7741440 bytes

   Device Boot      Start         End      Blocks   Id  System
/dev/sda1    *            1           14     105808+    83  Linux
/dev/sda2                15           81      506520    82  Linux swap
/dev/sda3                 82        3876    28690200    83  Linux
```

**Saving the Partition Layout**

To save the partition layout and exit `fdisk`, type `w`.

**Code Listing 3.10: Save and exit fdisk**

```
Command (m for help): w
```

Now that your partitions are created, you can continue with [Creating Filesystems](#).

**4.d. Using parted to Partition your Disk**

In this chapter, we guide you through the creation of the example partition layout mentioned earlier in the instructions. Unlike the previous chapter, we describe the method using the `parted` application instead. Both `parted` and `fdisk` offer the same functions, so if you partitioned your system using `fdisk` already, you can skip this section and continue with [Creating Filesystems](#).

The example partition layout we use is shown in the next table:

Partition	Description
/dev/sda1	Boot partition
/dev/sda2	Swap partition
/dev/sda3	Root partition

Change your partition layout according to your own preference.

**Viewing the Current Partition Layout**

The `parted` application is a somewhat more modern variant of `fdisk`. It offers a simpler interface for partitioning your disks and supports very large partitions (more than 2 TB). Fire up `parted` on your disk (in our example, we use `/dev/sda`):

#### Code Listing 4.1: Starting parted

```
# parted /dev/sda
GNU Parted 2.3
Using /dev/vda
Welcome to GNU Parted! Type 'help' to view a list of commands.
```

To find out about all options supported by `parted`, type `help` and press return. For now, we just continue by asking `parted` to show the partitions currently in use on the selected disk. The `print` command can be used for that.

#### Code Listing 4.2: An example partition configuration shown by parted

```
(parted) print
Model: SCSI Block Device
Disk /dev/sda: 21.5GB
Sector size (logical/physical): 512B/512B
Partition Table: msdos

Number  Start   End     Size    Type    File system  Flags
 1      512B   2148MB  2148MB  primary ext4
 2     2148MB 3222MB  1074MB  primary linux-swaps(v1)
 3     3222MB 21.5GB  18.3GB  primary lvm
```

### Optional: Setting the GPT Label

Most disks on x86/amd64 are prepared using an *msdos* label. However, if you plan on creating huge partitions (2 TB and more), you must use a *gpt* label (the *GUID Partition Type*) for your disk. Using `parted`, this can be accomplished with `mklabel gpt`:

**Warning:** Changing the partition type will remove all partitions from your disk. All data on the disk will be lost.

#### Code Listing 4.3: Setting the GPT label

```
(parted) mklabel gpt
```

### Removing all Partitions

If this isn't done yet (for instance through the `mklabel` operation earlier, or because the disk is a freshly formatted one), we will first remove all existing partitions from the disk. Type `rm <number>` where `<number>` is the partition you want to remove.

#### Code Listing 4.4: Removing a partition from the disk

```
(parted) rm 2
```

Do the same for all other partitions that you don't need. However, make sure you do not make any mistakes here - `parted` executes the changes immediate (unlike `fdisk` which stages them, allowing a user to "undo" his changes before saving or exiting `fdisk`).

### Creating the Partitions

Now let's create the partitions we mentioned earlier. Creating partitions with `parted` isn't very difficult - all we need to do is inform `parted` about the following settings:

- The *partition type* to use. This usually is *primary* in case you are not going to have more than 4 partitions (with the *msdos* partition label). Otherwise, you will need to make your fourth partition an *extended* one which hosts the rest of the disk, and create *logical* partitions inside it. If you use a *gpt*-labeled partition, then there is no limit on the number of primary partitions.
- The *file system type* to use. The `parted` application supports most common file systems and knows which kind of partition ID it needs to use for these partitions. This does *not* mean that `parted` will create a file system on the partition (you can with the `mkpartfs` command, but we'll use the regular `mkfs.*` commands later for this purpose). The partition ID is often used by auto-detection tools to know what to do with a particular partition.
- The start location of a partition (which can be expressed in MB or GB)
- The end location of the partition (which can be expressed in MB or GB)

One advantage of `parted` is that you can easily just use the partition sizes to automatically find the correct start and end location as you will see in the next example.

#### Code Listing 4.5: Creating the partitions

```
# Create a 32 mbyte /boot partition
(parted) mkpart primary ext2 0 32mb
Warning: The resulting partition is not properly aligned for best performance.
Ignore/Cancel? i

# Create a 512 mbyte swap partition
(parted) mkpart primary linux-swaps 32mb 542mb

# Create a partition that spans the remaining disk.
# -1s (minus one s) means the end of the disk
(parted) mkpart primary ext4 542mb -1s
Warning: You requested a partition from 542MB to 21.5GB.
The closest location we can manage is 542MB to 21.5GB.
Is this still acceptable to you?
Yes/No? y
```

You can now `print` the partition layout again to validate if everything is as expected. When you are satisfied, use the `quit` command to exit `parted`.

### 4.e. Creating Filesystems



Introduction

Now that your partitions are created, it is time to place a filesystem on them. If you don't care about what filesystem to choose and are happy with what we use as default in this handbook, continue with [Applying a Filesystem to a Partition](#). Otherwise read on to learn about the available filesystems...

Filesystems

Several filesystems are available. Some of them are found stable on the amd64 architecture, others aren't. The following filesystems are found to be stable: ext2, ext3, ext4 and XFS. JFS and ReiserFS may work but need more testing. If you're really adventurous you can try the other filesystems.

**ext2** is the tried and true Linux filesystem but doesn't have metadata journaling, which means that routine ext2 filesystem checks at startup time can be quite time-consuming. There is now quite a selection of newer-generation journaled filesystems that can be checked for consistency very quickly and are thus generally preferred over their non-journaled counterparts. Journaled filesystems prevent long delays when you boot your system and your filesystem happens to be in an inconsistent state. If you intend to install Gentoo on a very small disk (less than 4GB), then you'll need to tell ext2 to reserve enough inodes when you create the filesystem. The `mke2fs` application uses the "bytes-per-inode" setting to calculate how many inodes a file system should have. By running `mke2fs -T small /dev/<device>` the number of inodes will generally quadruple for a given file system as its "bytes-per-inode" reduces from one every 16kB to one every 4kB. You can tune this even further by using `mke2fs -i <ratio> /dev/<device>`.

**ext3** is the journaled version of the ext2 filesystem, providing metadata journaling for fast recovery in addition to other enhanced journaling modes like full data and ordered data journaling. It uses an HTree index that enables high performance in almost all situations. In short, ext3 is a very good and reliable filesystem. If you intend to install Gentoo on a very small disk (less than 4GB), then you'll need to tell ext3 to reserve enough inodes when you create the filesystem. The `mke2fs` application uses the "bytes-per-inode" setting to calculate how many inodes a file system should have. By running `mke2fs -j -T small /dev/<device>` the number of inodes will generally quadruple for a given file system as its "bytes-per-inode" reduces from one every 16kB to one every 4kB. You can tune this even further by using `mke2fs -j -i <ratio> /dev/<device>`.

**ext4** is a filesystem created as a fork of ext3 bringing new features, performance improvements and removal of size limits with moderate changes to the on-disk format. It can span volumes up to 1 EB and with maximum file size of 16 TB. Instead of the classic ext2/3 bitmap block allocation ext4 uses [extents](#), which improve large file performance and reduce fragmentation. Ext4 also provides more sophisticated block allocation algorithms (delayed allocation and multiblock allocation) giving the filesystem driver more ways to optimise the layout of data on the disk. The ext4 filesystem is a compromise between production-grade code stability and the desire to introduce extensions to an almost decade old filesystem. Ext4 is the recommended all-purpose all-platform filesystem.

**JFS** is IBM's high-performance journaling filesystem. JFS is a light, fast and reliable B+tree-based filesystem with good performance in various conditions.

**ReiserFS** is a B+tree-based journaled filesystem that has good overall performance, especially when dealing with many tiny files at the cost of more CPU cycles. ReiserFS appears to be less maintained than other filesystems.

**XFS** is a filesystem with metadata journaling which comes with a robust feature-set and is optimized for scalability. XFS seems to be less forgiving to various hardware problems.

Applying a Filesystem to a Partition

To create a filesystem on a partition or volume, there are tools available for each possible filesystem:

Filesystem	Creation Command
ext2	<code>mkfs.ext2</code>
ext3	<code>mkfs.ext3</code>
ext4	<code>mkfs.ext4</code>
reiserfs	<code>mkreiserfs</code>
xfs	<code>mkfs.xfs</code>
jfs	<code>mkfs.jfs</code>

For instance, to have the boot partition (`/dev/sda1` in our example) in ext2 and the root partition (`/dev/sda3` in our example) in ext4 (as in our example), you would use:

Code Listing 5.1: Applying a filesystem on a partition

```
# mkfs.ext2 /dev/sda1
# mkfs.ext4 /dev/sda3
```

Now create the filesystems on your newly created partitions (or logical volumes).

Activating the Swap Partition

`mkswap` is the command that is used to initialize swap partitions:

Code Listing 5.2: Creating a Swap signature

```
# mkswap /dev/sda2
```

To activate the swap partition, use `swapon`:

Code Listing 5.3: Activating the swap partition

```
# swapon /dev/sda2
```

Create and activate the swap with the commands mentioned above.

4.f. Mounting

Now that your partitions are initialized and are housing a filesystem, it is time to mount those partitions. Use the `mount` command. Don't forget to create the necessary mount directories for every partition you created. As an example we mount the root and boot partition:

Code Listing 6.1: Mounting partitions

```
# mount /dev/sda3 /mnt/gentoo
# mkdir /mnt/gentoo/boot
# mount /dev/sda1 /mnt/gentoo/boot
```

**Note:** If you want your `/tmp` to reside on a separate partition, be sure to change its permissions after mounting: `chmod 1777 /mnt/gentoo/tmp`. This also holds for `/var/tmp`.

We will also have to mount the `proc` filesystem (a virtual interface with the kernel) on `/proc`. But first we will need to place our files on the partitions.

Continue with [Installing the Gentoo Installation Files](#).

## 5. Installing the Gentoo Installation Files

### 5.a. Installing a Stage Tarball

#### Setting the Date/Time Right

Before you continue you need to check your date/time and update it. A misconfigured clock may lead to strange results in the future!

To verify the current date/time, run `date`:

##### Code Listing 1.1: Verifying the date/time

```
# date
Fri Mar 29 16:21:18 UTC 2005
```

If the date/time displayed is wrong, update it using the `date MMDDhhmmYYYY` syntax (Month, Day, hour, minute and Year). At this stage, you should use UTC time. You will be able to define your timezone later on. For instance, to set the date to March 29th, 16:21 in the year 2005:

##### Code Listing 2.4: Setting the UTC date/time

```
# date 032916212005
```

#### Making your Choice

The next step you need to perform is to install the `stage3` tarball onto your system. The command `uname -m` can be used to help you decide which stage file to download as it provides information on the architecture of your system.

### 5.b. Using a Stage from the Internet

#### Downloading the Stage Tarball

Go to the Gentoo mountpoint at which you mounted your filesystems (most likely `/mnt/gentoo`):

##### Code Listing 2.1: Going to the Gentoo mountpoint

```
# cd /mnt/gentoo
```

Depending on your installation medium, you have a couple of tools available to download a stage. If you have `links` available, then you can immediately surf to [the Gentoo mirrorlist](#) and choose a mirror close to you: type `links http://www.gentoo.org/main/en/mirrors.xml` and press enter.

If you don't have `links` available you should have `lynx` at your disposal. If you need to go through a proxy, export the `http_proxy` and `ftp_proxy` variables:

##### Code Listing 2.2: Setting proxy information for lynx

```
# export http_proxy="http://proxy.server.com:port"
# export ftp_proxy="http://proxy.server.com:port"
```

We will now assume that you have `links` at your disposal.

Select a mirror closeby. Usually HTTP mirrors suffice, but other protocols are available as well. Move to the `releases/amd64/autobuilds/` directory. There you should see all available stage files for your architecture (they might be stored within subdirectories named after the individual subarchitectures). Select one and press `D` to download. When you're finished, press `Q` to quit the browser.

##### Code Listing 2.3: Surfing to the mirror listing with links

```
# links http://www.gentoo.org/main/en/mirrors.xml

(If you need proxy support with links:)
# links -http-proxy proxy.server.com:8080 http://www.gentoo.org/main/en/mirrors.xml
```

Make sure you download a **stage3** tarball - installations using a stage1 or stage2 tarball are not supported anymore (and in most cases, you will not find stage1 or stage2 tarballs on our regular download mirrors anyway).

If you want to check the integrity of the downloaded stage tarball, use `openssl` and compare the output with the checksums provided on the mirror. The digests files provide several checksums, each taken with a different algorithm. The recommended ones are SHA512 and Whirlpool.

##### Code Listing 2.4: Calculating the integrity checksum of a stage tarball

```
## Calculating the SHA512 checksum
# openssl dgst -r -sha512 stage3-amd64-<release>.tar.bz2
or
# sha512sum stage3-amd64-<release>.tar.bz2

## Calculating the Whirlpool checksum
# openssl dgst -r -whirlpool stage3-amd64-<release>.tar.bz2
```

Then compare the output of these commands with the value registered in the `.DIGESTS` files that can be found on the mirrors as well. The values need to match, otherwise the downloaded file might be corrupt (or the digests file is).

#### Unpacking the Stage Tarball

Now unpack your downloaded stage onto your system. We use `tar` to proceed as it is the easiest method:

```
# tar xvjpf stage3-*.tar.bz2
```

Make sure that you use the same options (`xvjpf`). The `x` stands for *Extract*, the `v` for *Verbose* to see what happens during the extraction process (optional), the `j` for *Decompress with bzip2*, the `p` for *Preserve permissions* and the `f` to denote that we want to extract a file, not standard input.

Now that the stage is installed, continue with [Configuring the Compile Options](#).

## 5.c. Configuring the Compile Options

### Introduction

To optimize Gentoo, you can set a couple of variables which impact Portage behaviour. All those variables can be set as environment variables (using `export`) but that isn't permanent. To keep your settings, Portage provides you with `/etc/portage/make.conf`, a configuration file for Portage. It is this file we will edit now.

**Note:** A commented listing of all possible variables can be found in `/mnt/gentoo/usr/share/portage/config/make.conf.example`. For a successful Gentoo installation you'll only need to set the variables which are mentioned beneath.

Fire up your favorite editor (in this guide we use `nano`) so we can alter the optimization variables we will discuss hereafter.

#### Code Listing 3.1: Opening `/etc/portage/make.conf`

```
# nano -w /mnt/gentoo/etc/portage/make.conf
```

As you probably noticed, the `make.conf.example` file is structured in a generic way: commented lines start with `"#"`, other lines define variables using the `VARIABLE="content"` syntax. The `make.conf` file uses the same syntax. Several of those variables are discussed next.

### CFLAGS and CXXFLAGS

The `CFLAGS` and `CXXFLAGS` variables define the optimization flags for the `gcc` C and C++ compiler respectively. Although we define those generally here, you will only have maximum performance if you optimize these flags for each program separately. The reason for this is because every program is different.

In `make.conf` you should define the optimization flags you think will make your system the most responsive *generally*. Don't place experimental settings in this variable; too much optimization can make programs behave bad (crash, or even worse, malfunction).

We will not explain all possible optimization options. If you want to know them all, read the [GNU Online Manual\(s\)](#) or the `gcc` info page (`info gcc` -- only works on a working Linux system). The `make.conf.example` file itself also contains lots of examples and information; don't forget to read it too.

A first setting is the `-march=` or `-mtune=` flag, which specifies the name of the target architecture. Possible options are described in the `make.conf.example` file (as comments). A commonly used value is `native` as that tells the compiler to select the target architecture of the current system (the one you are installing on).

A second one is the `-O` flag (that is a capital O, not a zero), which specifies the `gcc` optimization class flag. Possible classes are `s` (for size-optimized), `0` (zero - for no optimizations), `1`, `2` or even `3` for more speed-optimization flags (every class has the same flags as the one before, plus some extras). `-O2` is the recommended default. `-O3` is known to cause problems when used system-wide, so we recommend that you stick to `-O2`.

Another popular optimization flag is `-pipe` (use pipes rather than temporary files for communication between the various stages of compilation). It has no impact on the generated code, but uses more memory. On systems with low memory, gcc might get killed. In that case, do not use this flag.

Using `-fomit-frame-pointer` (which doesn't keep the frame pointer in a register for functions that don't need one) might have serious repercussions on the debugging of applications.

When you define the `CFLAGS` and `CXXFLAGS`, you should combine several optimization flags. The default values contained in the stage3 archive you unpacked should be good enough. The following example is just an example:

#### Code Listing 3.2: Defining the `CFLAGS` and `CXXFLAGS` variable

```
CFLAGS="-march=k8 -O2 -pipe"    # Intel EM64T users should use -march=core2
# Use the same settings for both variables
CXXFLAGS="${CFLAGS}"
```

**Note:** You may also want to view the [Compilation Optimization Guide](#) for more information on how the various compilation options can affect your system.

### MAKEOPTS

With `MAKEOPTS` you define how many parallel compilations should occur when you install a package. A good choice is the number of CPUs (or CPU cores) in your system plus one, but this guideline isn't always perfect.

#### Code Listing 3.3: `MAKEOPTS` for a regular, 1-CPU system

```
MAKEOPTS="-j2"
```

### Ready, Set, Go!

Update your `/mnt/gentoo/etc/portage/make.conf` to your own preference and save (`nano` users would hit `Ctrl-X`). You are now ready to continue with [Installing the Gentoo Base System](#).

## 6. Installing the Gentoo Base System

### 6.a. Chrooting

#### Optional: Selecting Mirrors

In order to download source code quickly it is recommended to select a fast mirror. Portage will look in your `make.conf` file for the `GENTOO_MIRRORS` variable and use the mirrors listed therein. You can surf to our [mirror list](#) and search for a mirror (or mirrors) close to you (as those are most frequently the fastest ones),

but we provide a nice tool called [mirrorselect](#) which provides you with a nice interface to select the mirrors you want. Just navigate to the mirrors of choice and press spacebar to select one or more mirrors.

#### Code Listing 1.1: Using mirrorselect for the GENTOO\_MIRRORS variable

```
# mirrorselect -i -o >> /mnt/gentoo/etc/portage/make.conf
```

A second important setting is the SYNC setting in `make.conf`. This variable contains the rsync server you want to use when updating your Portage tree (the collection of ebuilds, scripts containing all the information Portage needs to download and install software). Although you can manually enter a SYNC server for yourself, [mirrorselect](#) can ease that operation for you:

#### Code Listing 1.2: Selecting an rsync mirror using mirrorselect

```
# mirrorselect -i -r -o >> /mnt/gentoo/etc/portage/make.conf
```

After running [mirrorselect](#) it is advisable to double-check the settings in `/mnt/gentoo/etc/portage/make.conf` !

**Note:** If you want to manually set a SYNC server in `make.conf`, you should check out the [community mirrors list](#) for the mirrors closest to you. We recommend choosing a *rotation*, such as [rsync.us.gentoo.org](#), rather than choosing a single mirror. This helps spread out the load and provides a failsafe in case a specific mirror is offline.

## Copy DNS Info

One thing still remains to be done before we enter the new environment and that is copying over the DNS information in `/etc/resolv.conf`. You need to do this to ensure that networking still works even after entering the new environment. `/etc/resolv.conf` contains the nameservers for your network.

#### Code Listing 1.3: Copy over DNS information

```
(The "-L" option is needed to make sure we don't copy a symbolic link)
# cp -L /etc/resolv.conf /mnt/gentoo/etc/
```

## Mounting the necessary Filesystems

In a few moments, we will change the Linux root towards the new location. To make sure that the new environment works properly, we need to make certain file systems available there as well.

Mount the `/proc` filesystem on `/mnt/gentoo/proc` to allow the installation to use the kernel-provided information within the chrooted environment, and then mount-bind the `/dev` and `/sys` filesystems.

#### Code Listing 1.4: Mounting /proc and /dev

```
# mount -t proc none /mnt/gentoo/proc
# mount --rbind /sys /mnt/gentoo/sys
# mount --rbind /dev /mnt/gentoo/dev
```

## Entering the new Environment

Now that all partitions are initialized and the base environment installed, it is time to enter our new installation environment by *chrooting* into it. This means that we change from the current installation environment (Installation CD or other installation medium) to your installation system (namely the initialized partitions).

This chrooting is done in three steps. First we will change the root from `/` (on the installation medium) to `/mnt/gentoo` (on your partitions) using [chroot](#). Then we will reload some settings, as provided by `/etc/profile`, in memory using [source](#). The last step is to redefine the primary prompt to help us remember that we are inside a chroot environment.

#### Code Listing 1.5: Chrooting into the new environment

```
# chroot /mnt/gentoo /bin/bash
# source /etc/profile
# export PS1="(chroot) $PS1"
```

Congratulations! You are now inside your own Gentoo Linux environment. Of course it is far from finished, which is why the installation still has some sections left :-)

If you at any time would need another terminal or console to access the chroot environment, all you need to do is to execute the above steps again.

## 6.b. Configuring Portage

### Unpacking a Portage Snapshot

You now have to install a Portage snapshot, a collection of files that inform Portage what software titles you can install, which profiles are available, etc. The contents of this snapshot will be extracted to `/usr/portage`.

We recommend the use of [emerge-webrsync](#). This will fetch the latest portage snapshot (which Gentoo releases on a daily basis) from one of our mirrors and install it onto your system.

#### Code Listing 2.1: Running emerge-webrsync to install a Portage snapshot

```
# mkdir /usr/portage
# emerge-webrsync
```

### Optional: Updating the Portage tree

You can now update your Portage tree to the latest version. `emerge --sync` will use the rsync protocol to update the Portage tree (which you fetched earlier on through [emerge-webrsync](#)) to the latest state.

#### Code Listing 2.2: Updating the Portage tree

```
# emerge --sync
(If you're using a slow terminal like some framebuffer or a serial
```

```
console, you can add the --quiet option to speed up this process:)
# emerge --sync --quiet
```

If you are behind a firewall that blocks rsync traffic, you safely ignore this step as you already have a quite up-to-date Portage tree.

If you are warned that a new Portage version is available and that you should update Portage, you should do it now using `emerge --oneshot portage`. You might also be notified that "news items need reading". More on that next.

## Reading News Items

When a Portage tree is synchronized to your system, Portage might warn you with the following:

### Code Listing 2.3: Portage informing that news items are available

```
* IMPORTANT: 2 news items need reading for repository 'gentoo'.
* Use eselect news to read news items.
```

Portage news items were created to provide a communication medium to push critical messages to users via the rsync tree. To manage them you will need to use `eselect news`. With the `read` subcommand, you can read all news items. With `list` you can get an overview of the available news items, and with `purge` you can remove them once you have read them and have no further need for the item(s) anymore.

### Code Listing 2.4: Handling Portage news

```
# eselect news list
# eselect news read
```

More information about the newsreader is available through its manual page: `man news.eselect`.

## Choosing the Right Profile

First, a small definition is in place.

A profile is a building block for any Gentoo system. Not only does it specify default values for `USE`, `CFLAGS` and other important variables, it also locks the system to a certain range of package versions. This is all maintained by the Gentoo developers.

Previously, such a profile was untouched by the users. However, there may be certain situations in which you may decide a profile change is necessary.

You can see what profile you are currently using with the following command:

### Code Listing 2.5: Verifying system profile

```
# eselect profile list
Available profile symlink targets:
[1]  default/linux/amd64/13.0 *
[2]  default/linux/amd64/13.0/desktop
[3]  default/linux/amd64/13.0/server
```

As you can see, there are also `desktop` and `server` subprofiles available for some architectures. Running `eselect profile list` will show all available profiles.

After viewing the available profiles for your architecture, you can use a different one if you wish:

### Code Listing 2.6: Changing profiles

```
# eselect profile set 2
```

If you want to have a pure 64-bit environment, with no 32-bit applications or libraries, you should use a non-multilib profile:

### Code Listing 2.7: Switching to a non-multilib profile

```
# eselect profile list
Available profile symlink targets:
[1]  default/linux/amd64/13.0 *
[2]  default/linux/amd64/13.0/desktop
[3]  default/linux/amd64/13.0/no-multilib
[4]  default/linux/amd64/13.0/server
(Choose the no-multilib profile)
# eselect profile set 3
(Verify the change)
# eselect profile list
Available profile symlink targets:
[1]  default/linux/amd64/13.0
[2]  default/linux/amd64/13.0/desktop
[3]  default/linux/amd64/13.0/no-multilib *
[4]  default/linux/amd64/13.0/server
```

**Note:** The `developer` subprofile is specifically for Gentoo Linux development tasks. It is *not* meant to help set up general development environments.

## Configuring the USE variable

`USE` is one of the most powerful variables Gentoo provides to its users. Several programs can be compiled with or without optional support for certain items. For instance, some programs can be compiled with `gtk-support`, or with `qt-support`. Others can be compiled with or without `SSL` support. Some programs can even be compiled with `framebuffer` support (`svglib`) instead of `X11` support (`X-server`).

Most distributions compile their packages with support for as much as possible, increasing the size of the programs and startup time, not to mention an enormous amount of dependencies. With Gentoo you can define what options a package should be compiled with. This is where `USE` comes into play.

In the `USE` variable you define keywords which are mapped onto compile-options. For instance, `ssl` will compile `ssl-support` in the programs that support it. `-X` will remove `X-server` support (note the minus sign in front). `gnome gtk -kde -qt4` will compile your programs with `gnome` (and `gtk`) support, and not with `kde` (and `qt`) support, making your system fully tweaked for GNOME.

The default [USE](#) settings are placed in the `make.defaults` files of your profile. You will find `make.defaults` files in the directory which `/etc/portage/make.profile` points to and all parent directories as well. The default [USE](#) setting is the sum of all [USE](#) settings in all `make.defaults` files. What you place in `/etc/portage/make.conf` is calculated against these defaults settings. If you add something to the [USE](#) setting, it is added to the default list. If you remove something from the [USE](#) setting (by placing a minus sign in front of it) it is removed from the default list (if it was in the default list at all). *Never* alter anything inside the `/etc/portage/make.profile` directory; it gets overwritten when you update Portage!

A full description on [USE](#) can be found in the second part of the Gentoo Handbook, [USE flags](#). A full description on the available USE flags can be found on your system in `/usr/portage/profiles/use.desc`.

#### Code Listing 2.8: Viewing available USE flags

```
# less /usr/portage/profiles/use.desc
(You can scroll using your arrow keys, exit by pressing 'q')
```

As an example we show a [USE](#) setting for a KDE-based system with DVD, ALSA and CD Recording support:

#### Code Listing 2.9: Opening `/etc/portage/make.conf`

```
# nano -w /etc/portage/make.conf
```

#### Code Listing 2.10: USE setting

```
USE="-gtk -gnome qt4 kde dvd alsa cdr"
```

## 6.c. Timezone

Finally select your timezone so that your system knows where it is physically located. Look for your timezone in `/usr/share/zoneinfo`, then copy it to `/etc/localtime`. Please avoid the `/usr/share/zoneinfo/Etc/GMT*` timezones as their names do not indicate the expected zones. For instance, `GMT-8` is in fact `GMT+8`.

#### Code Listing 3.1: Setting the timezone information

```
# ls /usr/share/zoneinfo
(Suppose you want to use Europe/Brussels)
# cp /usr/share/zoneinfo/Europe/Brussels /etc/localtime
(Next set the timezone)
# echo "Europe/Brussels" > /etc/timezone
```

## 7. Configuring the Kernel

### 7.a. Installing the Sources

#### Choosing a Kernel

The core around which all distributions are built is the Linux kernel. It is the layer between the user programs and your system hardware. Gentoo provides its users several possible kernel sources. A full listing with description is available at the [Gentoo Kernel Guide](#).

For AMD64-based systems we have [gentoo-sources](#) (kernel source patched for extra features).

Choose your kernel source and install it using [emerge](#).

#### Code Listing 1.1: Installing a kernel source

```
# emerge gentoo-sources
```

When you take a look in `/usr/src` you should see a symlink called `linux` pointing to your kernel source. In this case, the installed kernel source points to [gentoo-sources-3.4.9](#). Your version may be different, so keep this in mind.

#### Code Listing 1.2: Viewing the kernel source symlink

```
# ls -l /usr/src/linux
lrwxrwxrwx 1 root root 12 Oct 13 11:04 /usr/src/linux -> linux-3.4.9
```

Now it is time to configure and compile your kernel source. You can use [genkernel](#) for this, which will build a generic kernel as used by the Installation CD. We explain the "manual" configuration first though, as it is the best way to optimize your environment.

If you want to manually configure your kernel, continue now with [Default: Manual Configuration](#). If you want to use [genkernel](#) you should read [Alternative: Using genkernel](#) instead.

### 7.b. Default: Manual Configuration

#### Introduction

Manually configuring a kernel is often seen as the most difficult procedure a Linux user ever has to perform. Nothing is less true -- after configuring a couple of kernels you don't even remember that it was difficult ;)

However, one thing *is* true: you must know your system when you start configuring a kernel manually. Most information can be gathered by emerging `pciutils` (`emerge pciutils`) which contains `lspci`. You will now be able to use `lspci` within the `chrooted` environment. You may safely ignore any `pci-lib` warnings (like `pci-lib: cannot open /sys/bus/pci/devices`) that `lspci` throws out. Alternatively, you can run `lspci` from a *non-chrooted* environment. The results are the same. You can also run `lsmod` to see what kernel modules the Installation CD uses (it might provide you with a nice hint on what to enable).

Now go to your kernel source directory and execute `make menuconfig`. This will fire up an ncurses-based configuration menu.

#### Code Listing 2.1: Invoking `menuconfig`

```
# cd /usr/src/linux
# make menuconfig
```



You will be greeted with several configuration sections. We'll first list some options you must activate (otherwise Gentoo will not function, or not function properly without additional tweaks).

## Activating Required Options

Make sure that every driver that is vital to the booting of your system (such as SCSI controller, ...) is compiled *in* the kernel and not as a module, otherwise your system will not be able to boot completely.

We shall then select the exact processor type. The x86\_64 kernel maintainer strongly recommends users enable MCE features so that they are able to be notified of any hardware problems. On x86\_64, these errors are not printed to `dmesg` like on other architectures, but to `/dev/mcelog`. This requires the `app-admin/mcelog` package. Make sure you select IA32 Emulation if you want to be able to run 32-bit programs. Gentoo will install a multilib system (mixed 32-bit/64-bit computing) by default, so this option is required.

**Note:** If you plan to use a non-multilib profile (for a pure 64-bit system), then you don't have to select IA32 Emulation support. However, you'll also need to follow the [instructions](#) for switching to a [non-multilib profile](#), as well as choosing the correct [bootloader](#).

### Code Listing 2.2: Selecting processor type and features

```
Processor type and features --->
[ ] Machine Check / overheating reporting
[ ] Intel MCE Features
[ ] AMD MCE Features
Processor family (AMD-Opteron/Athlon64) --->
( ) Opteron/Athlon64/Hammer/K8
( ) Intel P4 / older Netburst based Xeon
( ) Core 2/newer Xeon
( ) Intel Atom
( ) Generic-x86-64
Executable file formats / Emulations --->
[*] IA32 Emulation
```

Next select *Maintain a devtmpfs file system to mount at /dev* so that critical device files are already available early in the boot process.

### Code Listing 2.3: Enabling devtmpfs support

```
Device Drivers --->
Generic Driver Options --->
[*] Maintain a devtmpfs filesystem to mount at /dev
[ ] Automount devtmpfs at /dev, after the kernel mounted the rootfs
```

Now go to [File Systems](#) and select support for the filesystems you use. *Don't* compile them as modules, otherwise your Gentoo system will not be able to mount your partitions. Also select [Virtual memory](#) and [/proc file system](#).

### Code Listing 2.4: Selecting necessary file systems

```
File systems --->
(Select one or more of the following options as needed by your system)
<*> Second extended fs support
<*> Ext3 journalling file system support
<*> The Extended 4 (ext4) filesystem
<*> Reiserfs support
<*> JFS filesystem support
<*> XFS filesystem support
...
Pseudo Filesystems --->
[*] /proc file system support
[*] Virtual memory file system support (former shm fs)

(Enable GPT partition label support if you used that previously)
-*- Enable the block layer --->
...
Partition Types --->
[*] Advanced partition selection
...
[*] EFI GUID Partition support
```

If you are using PPPoE to connect to the Internet or you are using a dial-up modem, you will need the following options in the kernel:

### Code Listing 2.5: Selecting PPPoE necessary drivers

```
Device Drivers --->
Network device support --->
<*> PPP (point-to-point protocol) support
<*> PPP support for async serial ports
<*> PPP support for sync tty ports
```

The two compression options won't harm but are not definitely needed, neither does the [PPP over Ethernet](#) option, that might only be used by `ppp` when configured to do kernel mode PPPoE.

If you require it, don't forget to include support in the kernel for your ethernet card.

If you have a multi-CPU Opteron or a multi-core (e.g. AMD64 X2) system, you should activate "Symmetric multi-processing support":

### Code Listing 2.6: Activating SMP support

```
Processor type and features --->
[*] Symmetric multi-processing support
```

**Note:** In multi-core systems, each core counts as one processor.

If you use USB Input Devices (like Keyboard or Mouse) don't forget to enable those as well:

```
Device Drivers --->
[*] HID Devices ---->
<*>  USB Human Interface Device (full HID) support
```

## Compiling and Installing

Now that your kernel is configured, it is time to compile and install it. Exit the configuration and start the compilation process:

### Code Listing 2.8: Compiling the kernel

```
# make && make modules_install
```

When the kernel has finished compiling, copy the kernel image to `/boot`. Use whatever name you feel is appropriate for your kernel choice and remember it as you will need it later on when you configure your bootloader. Remember to replace `kernel-3.4.9-gentoo` with the name and version of your kernel.

### Code Listing 2.9: Installing the kernel

```
# cp arch/x86_64/boot/bzImage /boot/kernel-3.4.9-gentoo
```

## (Optional) Building an Initramfs

If you use a specific partition layout where important file system locations (like `/usr` or `/var`) are on separate partitions, then you will need to setup an initramfs so that this partition can be mounted before it is needed.

Without an initramfs, you risk that the system will not boot up properly as the tools that are responsible for mounting the file systems need information that resides on those file systems. An initramfs will pull in the necessary files into an archive which is used right after the kernel boots, but before the control is handed over to the `init` tool. Scripts on the initramfs will then make sure that the partitions are properly mounted before the system continues booting.

To install an initramfs, install `genkernel` first, then have it generate an initramfs for you.

### Code Listing 2.10: Building an initramfs

```
# emerge genkernel
# genkernel --install initramfs
```

If you need specific support in the initramfs, such as lvm or raid, add in the appropriate options to `genkernel`. See `genkernel --help` for more information, or the next example which enables support for LVM and software raid (mdadm):

### Code Listing 2.11: Building an initramfs with support for LVM and software raid

```
# genkernel --lvm --mdadm --install initramfs
```

The initramfs will be stored in `/boot`. You can find the file by simply listing the files starting with `initramfs`:

### Code Listing 2.12: Checking the initramfs file name

```
# ls /boot/initramfs*
```

Now continue with [Kernel Modules](#).

## 7.c. Alternative: Using genkernel

If you are reading this section, you have chosen to use our `genkernel` script to configure your kernel for you.

Now that your kernel source tree is installed, it's now time to compile your kernel by using our `genkernel` script to automatically build a kernel for you. `genkernel` works by configuring a kernel nearly identically to the way our Installation CD kernel is configured. This means that when you use `genkernel` to build your kernel, your system will generally detect all your hardware at boot-time, just like our Installation CD does. Because `genkernel` doesn't require any manual kernel configuration, it is an ideal solution for those users who may not be comfortable compiling their own kernels.

Now, let's see how to use `genkernel`. First, emerge the `genkernel` ebuild:

### Code Listing 3.1: Emerging genkernel

```
# emerge genkernel
```

Now, compile your kernel sources by running `genkernel all`. Be aware though, as `genkernel` compiles a kernel that supports almost all hardware, this compilation will take quite a while to finish!

Note that, if your boot partition doesn't use `ext2` or `ext3` as filesystem you might need to manually configure your kernel using `genkernel --menuconfig all` and add support for your filesystem *in* the kernel (i.e. *not* as a module). Users of LVM2 will probably want to add `--lvm2` as an argument as well.

### Code Listing 3.2: Running genkernel

```
# genkernel all
```

Once `genkernel` completes, a kernel, full set of modules and *initial ram disk* (initramfs) will be created. We will use the kernel and `initrd` when configuring a boot loader later in this document. Write down the names of the kernel and `initrd` as you will need it when writing the bootloader configuration file. The `initrd` will be started immediately after booting to perform hardware autodetection (just like on the Installation CD) before your "real" system starts up.

### Code Listing 3.3: Checking the created kernel image name and initrd

```
# ls /boot/kernel* /boot/initramfs*
```

## 7.d. Kernel Modules

### Configuring the Modules

You should list the modules you want automatically loaded in `/etc/conf.d/modules`. You can add extra options to the modules too if you want.

To view all available modules, run the following `find` command. Don't forget to substitute "`<kernel version>`" with the version of the kernel you just compiled:

Code Listing 4.1: Viewing all available modules

```
# find /lib/modules/<kernel version>/ -type f -iname '*.o' -or -iname '*.ko' | less
```

For instance, to automatically load the `3c59x.ko` module (which is the driver for a specific 3Com network card family), edit the `/etc/conf.d/modules` file and enter the module name in it.

Code Listing 4.2: Editing `/etc/conf.d/modules`

```
# nano -w /etc/conf.d/modules
modules_2_6="3c59x"
```

Continue the installation with [Configuring your System](#).

8. Configuring your System

8.a. Filesystem Information

What is `fstab`?

Under Linux, all partitions used by the system must be listed in `/etc/fstab`. This file contains the mount points of those partitions (where they are seen in the file system structure), how they should be mounted and with what special options (automatically or not, whether users can mount them or not, etc.)

Creating `/etc/fstab`

`/etc/fstab` uses a special syntax. Every line consists of six fields, separated by whitespace (space(s), tabs or a mixture). Each field has its own meaning:

- The first field shows the **partition** described (the path to the device file)
- The second field shows the **mount point** at which the partition should be mounted
- The third field shows the **filesystem** used by the partition
- The fourth field shows the **mount options** used by `mount` when it wants to mount the partition. As every filesystem has its own mount options, you are encouraged to read the mount man page (`man mount`) for a full listing. Multiple mount options are comma-separated.
- The fifth field is used by `dump` to determine if the partition needs to be **dumped** or not. You can generally leave this as `0` (zero).
- The sixth field is used by `fsck` to determine the order in which filesystems should be **checked** if the system wasn't shut down properly. The root filesystem should have `1` while the rest should have `2` (or `0` if a filesystem check isn't necessary).

**Important:** The default `/etc/fstab` file provided by Gentoo is *not a valid fstab file*. You **have to create** your own `/etc/fstab`.

Code Listing 1.1: Opening `/etc/fstab`

```
# nano -w /etc/fstab
```

Let us take a look at how we write down the options for the `/boot` partition. This is just an example, if you didn't or couldn't create a `/boot`, don't copy it.

In our default AMD64 partitioning example, `/boot` is usually the `/dev/sda1` partition, with `ext2` as filesystem. It needs to be checked during boot, so we would write down:

Code Listing 1.2: An example `/boot` line for `/etc/fstab`

```
/dev/sda1 /boot ext2 defaults 0 2
```

Some users don't want their `/boot` partition to be mounted automatically to improve their system's security. Those people should substitute `defaults` with `noauto`. This does mean that you need to manually mount this partition every time you want to use it.

Add the rules that match your partitioning scheme and append rules for your CD-ROM drive(s), and of course, if you have other partitions or drives, for those too.

Now use the *example* below to create your `/etc/fstab`:

Code Listing 1.3: A full `/etc/fstab` example

```
/dev/sda1 /boot ext2 defaults,noatime 0 2
/dev/sda2 none swap sw 0 0
/dev/sda3 / ext4 noatime 0 1

/dev/cdrom /mnt/cdrom auto noauto,user 0 0
```

`auto` makes `mount` guess for the filesystem (recommended for removable media as they can be created with one of many filesystems) and `user` makes it possible for non-root users to mount the CD.

To improve performance, most users would want to add the `noatime` mount option, which results in a faster system since access times aren't registered (you don't need those generally anyway).

Double-check your `/etc/fstab`, save and quit to continue.

8.b. Networking Information

Host name, Domainname, etc

One of the choices the user has to make is name his/her PC. This seems to be quite easy, but *lots* of users are having difficulties finding the appropriate name for their Linux-pc. To speed things up, know that any name you choose can be changed afterwards. For all we care, you can just call your system `tux` and domain `homenetwork`.

```
# nano -w /etc/conf.d/hostname
```

```
(Set the hostname variable to your host name)
hostname="tux"
```

Second, *if* you need a domainname, set it in `/etc/conf.d/net`. You only need a domain if your ISP or network administrator says so, or if you have a DNS server but not a DHCP server. You don't need to worry about DNS or domainnames if your networking is setup for DHCP.

#### Code Listing 2.2: Setting the domainname

```
# nano -w /etc/conf.d/net
```

```
(Set the dns_domain variable to your domain name)
dns_domain_lo="homenetwork"
```

**Note:** If you choose not to set a domainname, you can get rid of the "This is hostname.(none)" messages at your login screen by editing `/etc/issue`. Just delete the string `.\n` from that file.

If you have a NIS domain (if you don't know what that is, then you don't have one), you need to define that one too:

#### Code Listing 2.3: Setting the NIS domainname

```
# nano -w /etc/conf.d/net
```

```
(Set the nis_domain variable to your NIS domain name)
nis_domain_lo="my-nisdomain"
```

**Note:** For more information on configuring DNS and NIS, please read the examples provided in `/usr/share/doc/openrc-*/net.example.bz2` which can be read using [bzless](#). Also, you may want to emerge [openresolv](#) to help manage your DNS/NIS setup.

## Configuring your Network

Before you get that "Hey, we've had that already"-feeling, you should remember that the networking you set up in the beginning of the Gentoo installation was just for the installation. Right now you are going to configure networking for your Gentoo system permanently.

**Note:** More detailed information about networking, including advanced topics like bonding, bridging, 802.1Q VLANs or wireless networking is covered in the [Gentoo Network Configuration](#) section.

All networking information is gathered in `/etc/conf.d/net`. It uses a straightforward yet not intuitive syntax if you don't know how to set up networking manually. But don't fear, we'll explain everything. A fully commented example that covers many different configurations is available in `/usr/share/doc/openrc-*/net.example.bz2`.

DHCP is used by default. For DHCP to work, you will need to install a DHCP client. This is described later in [Installing Necessary System Tools](#). Do not forget to install a DHCP client.

If you need to configure your network connection either because you need specific DHCP options or because you do not use DHCP at all, open `/etc/conf.d/net` with your favorite editor ([nano](#) is used in this example):

#### Code Listing 2.4: Opening /etc/conf.d/net for editing

```
# nano -w /etc/conf.d/net
```

You will see the following file:

#### Code Listing 2.5: Default /etc/conf.d/net

```
# This blank configuration will automatically use DHCP for any net.*
# scripts in /etc/init.d. To create a more complete configuration,
# please review /usr/share/doc/openrc-*/net.example.bz2 and save
# your configuration in /etc/conf.d/net (this file :!)).
```

To enter your own IP address, netmask and gateway, you need to set both `config_eth0` and `routes_eth0`:

#### Code Listing 2.6: Manually setting IP information for eth0

```
config_eth0="192.168.0.2 netmask 255.255.255.0 brd 192.168.0.255"
routes_eth0="default via 192.168.0.1"
```

To use DHCP, define `config_eth0`:

#### Code Listing 2.7: Automatically obtaining an IP address for eth0

```
config_eth0="dhcp"
```

Please read `/usr/share/doc/openrc-*/net.example.bz2` for a list of all available options. Be sure to also read your DHCP client manpage if you need to set specific DHCP options.

If you have several network interfaces repeat the above steps for `config_eth1`, `config_eth2`, etc.

Now save the configuration and exit to continue.

## Automatically Start Networking at Boot

To have your network interfaces activated at boot, you need to add them to the default runlevel.

#### Code Listing 2.8: Adding net.eth0 to the default runlevel

```
# cd /etc/init.d
# ln -s net.lo net.eth0
# rc-update add net.eth0 default
```

If you have several network interfaces, you need to create the appropriate `net.eth1`, `net.eth2` etc. just like you did with `net.eth0`.

## Writing Down Network Information

You now need to inform Linux about your network. This is defined in `/etc/hosts` and helps in resolving host names to IP addresses for hosts that aren't resolved by your nameserver. You need to define your system. You may also want to define other systems on your network if you don't want to set up your own internal DNS system.

### Code Listing 2.9: Opening `/etc/hosts`

```
# nano -w /etc/hosts
```

### Code Listing 2.10: Filling in the networking information

```
(This defines the current system)
127.0.0.1    tux.homenetwork tux localhost

(Define extra systems on your network,
they need to have a static IP to be defined this way.)
192.168.0.5  jenny.homenetwork jenny
192.168.0.6  benny.homenetwork benny
```

Save and exit the editor to continue.

If you don't have PCMCIA, you can now continue with [System Information](#). PCMCIA-users should read the following topic on PCMCIA.

## Optional: Get PCMCIA Working

PCMCIA users should first install the `pcmciautils` package.

### Code Listing 2.11: Installing `pcmciautils`

```
# emerge pcmciautils
```

## 8.c. System Information

### Root Password

First we set the root password by typing:

### Code Listing 3.1: Setting the root password

```
# passwd
```

## System Information

Gentoo uses `/etc/rc.conf` to configure the services, startup, and shutdown of your system. Open up `/etc/rc.conf` and enjoy all the comments in the file.

### Code Listing 3.2: Configuring services

```
# nano -w /etc/rc.conf
```

When you're finished configuring these two files, save them and exit.

Gentoo uses `/etc/conf.d/keymaps` to handle keyboard configuration. Edit it to configure your keyboard.

### Code Listing 3.3: Opening `/etc/conf.d/keymaps`

```
# nano -w /etc/conf.d/keymaps
```

Take special care with the `keymap` variable. If you select the wrong `keymap`, you will get weird results when typing on your keyboard.

When you're finished configuring `/etc/conf.d/keymaps`, save and exit.

Gentoo uses `/etc/conf.d/hwclock` to set clock options. Edit it according to your needs.

### Code Listing 3.4: Opening `/etc/conf.d/hwclock`

```
# nano -w /etc/conf.d/hwclock
```

If your hardware clock is not using UTC, you need to add `clock="local"` to the file. Otherwise you will notice some clock skew.

When you're finished configuring `/etc/conf.d/hwclock`, save and exit.

## Configure locales

You will probably only use one or maybe two locales on your system. You have to specify locales you will need in `/etc/locale.gen`.

### Code Listing 3.5: Opening `/etc/locale.gen`

```
# nano -w /etc/locale.gen
```

The following locales are an example to get both English (United States) and German (Germany) with the accompanying character formats (like UTF-8).

### Code Listing 3.6: Specify your locales

```
en_US ISO-8859-1
en_US.UTF-8 UTF-8
de_DE ISO-8859-1
de_DE@euro ISO-8859-15
```

**Note:** You can select your desired locales in the list given by running `locale -a`.

**Warning:** We strongly suggest that you should use at least one UTF-8 locale because some applications may require it.

The next step is to run `locale-gen`. It will generate all the locales you have specified in the `/etc/locale.gen` file.

#### Code Listing 3.7: Running locale-gen

```
# locale-gen
```

Once done, you now have the possibility to set the system-wide locale settings in the `/etc/env.d/02locale` file:

#### Code Listing 3.8: Setting the default system locale in /etc/env.d/02locale

```
LANG="de_DE.UTF-8"
LC_COLLATE="C"
```

And reload your environment:

#### Code Listing 3.9: Reload shell environment

```
# env-update && source /etc/profile
```

We made a full [Localization Guide](#) to help you through this process. You can also read our detailed [UTF-8 Guide](#) for very specific informations to enable UTF-8 on your system.

Please continue with [Installing Necessary System Tools](#).

## 9. Installing Necessary System Tools

### 9.a. System Logger

Some tools are missing from the *stage3* archive because several packages provide the same functionality. It is now up to you to choose which ones you want to install.

The first tool you need to decide on has to provide logging facilities for your system. Unix and Linux have an excellent history of logging capabilities -- if you want you can log everything that happens on your system in logfiles. This happens through the *system logger*.

Gentoo offers several system loggers to choose from. There are `sysklogd`, which is the traditional set of system logging daemons, `syslog-ng`, an advanced system logger, and `metalog` which is a highly-configurable system logger. Others might be available through Portage as well - our number of available packages increases on a daily basis.

If you plan on using `sysklogd` or `syslog-ng` you might want to install `logrotate` afterwards as those system loggers don't provide any rotation mechanism for the log files.

To install the system logger of your choice, `emerge` it and have it added to the default runlevel using `rc-update`. The following example installs `syslog-ng`. Of course substitute with your system logger:

#### Code Listing 1.1: Installing a system logger

```
# emerge syslog-ng
# rc-update add syslog-ng default
```

### 9.b. Optional: Cron Daemon

Next is the cron daemon. Although it is optional and not required for your system, it is wise to install one. But what is a cron daemon? A cron daemon executes scheduled commands. It is very handy if you need to execute some command regularly (for instance daily, weekly or monthly).

Gentoo offers three possible cron daemons: `dcron`, `fcron` and `vixie-cron`. Installing one of them is similar to installing a system logger. However, `dcron` and `fcron` require an extra configuration command, namely `crontab /etc/crontab`. If you don't know what to choose, use `vixie-cron`.

We only provide `vixie-cron` for networkless installations. If you want another cron daemon you can wait and install it later on.

#### Code Listing 2.1: Installing a cron daemon

```
# emerge vixie-cron
# rc-update add vixie-cron default
(Only if you have chosen dcron or fcron) # crontab /etc/crontab
```

### 9.c. Optional: File Indexing

If you want to index your system's files so you are able to quickly locate them using the `locate` tool, you need to install `sys-apps/mlocate`.

#### Code Listing 3.1: Installing mlocate

```
# emerge mlocate
```

### 9.d. Optional: Remote Access

If you need to access your system remotely after installation, don't forget to add `sshd` to the default runlevel:

#### Code Listing 4.1: Adding sshd to the default runlevel



```
# rc-update add sshd default
```

If you need serial console access (which is possible in case of remote servers), you'll need to uncomment the serial console section in `/etc/inittab`.

Code Listing 4.2: Editing `/etc/inittab`

```
# nano -w /etc/inittab
```

The following excerpt shows the uncommented section:

Code Listing 4.3: Uncommenting serial consoles in `inittab`

```
# SERIAL CONSOLES
s0:12345:respawn:/sbin/agetty 9600 ttyS0 vt100
s1:12345:respawn:/sbin/agetty 9600 ttyS1 vt100
```

9.e. File System Tools

Depending on what file systems you are using, you need to install the necessary file system utilities (for checking the filesystem integrity, creating additional file systems etc.). Please note that tools for managing ext2, ext3 or ext4 filesystems ([e2fsprogs](#)) are already installed as a part of the system.

The following table lists the tools you need to install if you use a certain file system:

File System	Tool	Install Command
XFS	xfsprops	<code>emerge xfsprops</code>
ReiserFS	reiserfsprogs	<code>emerge reiserfsprogs</code>
JFS	jfsutils	<code>emerge jfsutils</code>

9.f. Networking Tools

If you don't require any additional networking-related tools (such as `ppp` or a `dhcp` client) continue with [Configuring the Bootloader](#).

Optional: Installing a DHCP Client

If you require Gentoo to automatically obtain an IP address for your network interface(s), you need to install `dhcpcd` (or any other DHCP client -- see [Modular Networking](#) for a list of available DHCP clients). If you don't do this now, you might not be able to connect to the internet after the installation.

Code Listing 6.1: Installing `dhcpcd`

```
# emerge dhcpcd
```

Optional: Installing a PPPoE Client

If you need `ppp` to connect to the net, you need to install it.

Code Listing 6.2: Installing `ppp`

```
# emerge ppp
```

Now continue with [Configuring the Bootloader](#).

10. Configuring the Bootloader

10.a. Making your Choice

Introduction

Now that your kernel is configured and compiled and the necessary system configuration files are filled in correctly, it is time to install a program that will fire up your kernel when you start the system. Such a program is called a *bootloader*.

For AMD64, Gentoo Linux provides [GRUB](#) and [LILO](#).

But before we install the bootloader, we inform you how to configure framebuffer (assuming you want it of course). With framebuffer you can run the Linux command line with (limited) graphical features (such as using the nice bootsplash image Gentoo provides).

Optional: Framebuffer

If you have configured your kernel with framebuffer support (or you used `genkernel` default kernel configuration), you can activate it by adding a `video` statement to your bootloader configuration file.

First of all, you need to know your framebuffer device. You should have used `uvesafb` as the *VESA driver*.

The `video` statement controls framebuffer display options. It needs to be given the framebuffer driver followed by the control statements you wish to enable. All variables are listed in `/usr/src/linux/Documentation/fb/uvesafb.txt`. The most-used options are:

Control	Description
<code>ywrap</code>	Assume that the graphical card can wrap around its memory (i.e. continue at the beginning when it has approached the end)
<code>mtrr:n</code>	Setup MTRR registers. <code>n</code> can be: 0 - disabled 1 - uncachable 2 - write-back 3 - write-combining 4 - write-through
<code>mode</code>	Set up the resolution, color depth and refresh rate. For instance, <code>1024x768-32@85</code> for a resolution of 1024x768, 32 bit color depth and a refresh rate of 85 Hz.

The result could be something like `video=uvesafb:mtrr:3,ywrap,1024x768-32@85`. Write this setting down; you will need it shortly.

Now continue by installing [GRUB](#) or [LILO](#).

## 10.b. Default: Using GRUB

### Understanding GRUB's terminology

The most critical part of understanding GRUB is getting comfortable with how GRUB refers to hard drives and partitions. Your Linux partition `/dev/sda1` will most likely be called `(hd0,0)` under GRUB. Notice the parentheses around the `hd0,0` - they are required.

Hard drives count from zero rather than "a" and partitions start at zero rather than one. Be aware too that with the `hd` devices, only hard drives are counted, not `atapi-ide` devices such as `cdrom` players and burners. Also, the same construct is used with SCSI drives. (Normally they get higher numbers than IDE drives except when the BIOS is configured to boot from SCSI devices.) When you ask the BIOS to boot from a different hard disk (for instance your primary slave), *that* harddisk is seen as `hd0`.

Assuming you have a hard drive on `/dev/sda` and two more on `/dev/sdb` and `/dev/sdc`, `/dev/sdb7` gets translated to `(hd1,6)`. It might sound tricky and tricky it is indeed, but as we will see, GRUB offers a tab completion mechanism that comes handy for those of you having a lot of hard drives and partitions and who are a little lost in the GRUB numbering scheme.

Having gotten the feel for that, it is time to install GRUB.

### Installing GRUB

To install GRUB, let's first emerge it:

**Important:** If you are using a non-multilib [profile](#), you should **not** emerge `grub`, but instead you should emerge `grub-static`. If you plan to use a non-multilib profile *and* you have **disabled** IA-32 emulation in your kernel, then you should use [lilo](#).

#### Code Listing 2.1: Installing GRUB

```
# emerge grub
```

Although GRUB is now installed, we still need to write up a configuration file for it and place GRUB in our MBR so that GRUB automatically boots your newly created kernel. Create `/boot/grub/grub.conf` with [nano](#) (or, if applicable, another editor):

#### Code Listing 2.2: Creating /boot/grub/grub.conf

```
# nano -w /boot/grub/grub.conf
```

Now we are going to write up a `grub.conf`. Make sure you use *your* kernel image filename and, if appropriate, *your* `initrd` image filename.

**Note:** Grub assigns device designations from the BIOS. If you change your BIOS settings, your device letters and numbers may change, too. For example, if you change your device boot order, you may need to change your grub configuration.

**Note:** If your root filesystem is JFS, you *must* add "ro" to the [kernel](#) line since JFS needs to replay its log before it allows read-write mounting.

#### Code Listing 2.3: Example grub.conf

```
# Which listing to boot as default. 0 is the first, 1 the second etc.
default 0
# How many seconds to wait before the default listing is booted.
timeout 30
# Nice, fat splash-image to spice things up :)
# Comment out if you don't have a graphics card installed
splashimage=(hd0,0)/boot/grub/splash.xpm.gz

title Gentoo Linux 3.4.9
# Partition where the kernel image (or operating system) is located
root (hd0,0)
kernel /boot/kernel-3.4.9-gentoo root=/dev/sda3

title Gentoo Linux 3.4.9 (rescue)
# Partition where the kernel image (or operating system) is located
root (hd0,0)
kernel /boot/kernel-3.4.9-gentoo root=/dev/sda3 init=/bin/bb

# The next four lines are only if you dualboot with a Windows system.
# In this case, Windows is hosted on /dev/sda6.
title Windows XP
rootnoverify (hd0,5)
makeactive
chainloader +1
```

If, while building the Linux kernel, you opted to include an `initramfs` to boot from, then you will need to change the configuration by referring to this `initramfs` file and telling the `initramfs` where your real root device is at:

#### Code Listing 2.4: GRUB snippet for initramfs-enabled kernel builds

```
title Gentoo Linux 3.4.9
root (hd0,0)
kernel /boot/3.4.9 real\_root=/dev/sda3
initrd /boot/initramfs-genkernel-amd64-3.4.9-gentoo
```

If you used a different partitioning scheme and/or kernel image, adjust accordingly. However, make sure that anything that follows a GRUB-device (such as `(hd0,0)`) is relative to the mountpoint, not the root. In other words, `(hd0,0)/grub/splash.xpm.gz` is in reality `/boot/grub/splash.xpm.gz` since `(hd0,0)` is / `boot`.

Besides, if you chose to use a different partitioning scheme and did not put `/boot` in a separate partition, the `/boot` prefix used in the above code samples is really *required*. If you followed our suggested partitioning plan, the `/boot` prefix is not required, but a `boot` symlink makes it work. In short, the above examples should work whether you defined a separate `/boot` partition or not.

If you need to pass any additional options to the kernel, simply add them to the end of the kernel command. We're already passing one option (`root=/dev/sda3` or `real_root=/dev/sda3`), but you can pass others as well, such as the `video` statement for framebuffer as we discussed previously.

If your bootloader configuration file contains the `real_root` parameter, use the `real_rootflags` parameter to set root filesystem mount options.

If you're using a 2.6.7 or higher kernel and you jumpered your harddrive because the BIOS can't handle large harddrives you'll need to append `sda=stroke`. Replace `sda` with the device that requires this option.

`genkernel` users should know that their kernels use the same boot options as is used for the Installation CD. For instance, if you have SCSI devices, you should add `doscsi` as kernel option.

Now save the `grub.conf` file and exit. You still need to install GRUB in the MBR (Master Boot Record) so that GRUB is automatically executed when you boot your system.

The GRUB developers recommend the use of `grub-install`. However, if for some reason `grub-install` fails to work correctly you still have the option to manually install GRUB.

Continue with [Default: Setting up GRUB using grub-install](#) or [Alternative: Setting up GRUB using manual instructions](#).

### Default: Setting up GRUB using grub-install

To install GRUB you will need to issue the `grub-install` command. However, `grub-install` won't work off-the-shelf since we are inside a chrooted environment. We need to create `/etc/mtab` which lists all mounted filesystems. Fortunately, there is an easy way to accomplish this - just copy over `/proc/mounts` to `/etc/mtab`, excluding the `rootfs` line if you haven't created a separate boot partition. The following command will work in both cases:

#### Code Listing 2.5: Creating /etc/mtab

```
# grep -v rootfs /proc/mounts > /etc/mtab
```

Now we can install GRUB using `grub-install`:

#### Code Listing 2.6: Running grub-install

```
# grub-install --no-floppy /dev/sda
```

If you have more questions regarding GRUB, please consult the [GRUB FAQ](#), the [GRUB Wiki](#), or read `info grub` in your terminal.

Continue with [Rebooting the System](#).

### Alternative: Setting up GRUB using manual instructions

To start configuring GRUB, you type in `grub`. You'll be presented with the `grub>` grub command-line prompt. Now, you need to type in the right commands to install the GRUB boot record onto your hard drive.

#### Code Listing 2.7: Starting the GRUB shell

```
# grub --no-floppy
```

**Note:** If your system does not have any floppy drives, add the `--no-floppy` option to the above command to prevent grub from probing the (non-existing) floppy drives.

In the example configuration we want to install GRUB so that it reads its information from the boot partition `/dev/sda1`, and installs the GRUB boot record on the hard drive's MBR (master boot record) so that the first thing we see when we turn on the computer is the GRUB prompt. Of course, if you haven't followed the example configuration during the installation, change the commands accordingly.

The tab completion mechanism of GRUB can be used from within GRUB. For instance, if you type in "`root` (" followed by a TAB, you will be presented with a list of devices (such as `hd0`). If you type in "`root` (`hd0`," followed by a TAB, you will receive a list of available partitions to choose from (such as `hd0,0`).

By using the tab completion, setting up GRUB should be not that hard. Now go on, configure GRUB, shall we? :-)

#### Code Listing 2.8: Installing GRUB in the MBR

```
grub> root (hd0,0)    (Specify where your /boot partition resides)
grub> setup (hd0)     (Install GRUB in the MBR)
grub> quit           (Exit the GRUB shell)
```

**Note:** If you want to install GRUB in a certain partition instead of the MBR, you have to alter the `setup` command so it points to the right partition. For instance, if you want GRUB installed in `/dev/sda3`, then the command becomes `setup (hd0,2)`. Few users however want to do this.

If you have more questions regarding GRUB, please consult the [GRUB FAQ](#), the [GRUB Wiki](#), or read `info grub` in your terminal.

Continue with [Rebooting the System](#).

## 10.c. Alternative: Using LILO

### Installing LILO

LILO, the LinuxLoader, is the tried and true workhorse of Linux bootloaders. However, it lacks some features that GRUB has (which is also the reason why GRUB is currently gaining popularity). The reason why LILO is still used is that, on some systems, GRUB doesn't work and LILO does. Of course, it is also used because some people know LILO and want to stick with it. Either way, Gentoo supports both, and apparently you have chosen to use LILO.

Installing LILO is a breeze; just use `emerge`.

#### Code Listing 3.1: Installing LILO

```
# emerge lilo
```

### Configuring LILO

To configure LILO, you must create `/etc/lilo.conf`. Fire up your favorite editor (in this handbook we use `nano` for consistency) and create the file.

```
# nano -w /etc/lilo.conf
```

Some sections ago we have asked you to remember the kernel-image name you have created. In the next example `lilo.conf` we use the example partitioning scheme.

Make sure you use *your* kernel image filename and, if appropriate, *your* initrd image filename.

**Note:** If your root filesystem is JFS, you *must* add a `append="ro"` line after each boot item since JFS needs to replay its log before it allows read-write mounting.

#### Code Listing 3.3: Example `/etc/lilo.conf`

```
boot=/dev/sda          # Install LILO in the MBR
prompt                # Give the user the chance to select another section
timeout=50            # Wait 5 (five) seconds before booting the default section
default=gentoo        # When the timeout has passed, boot the "gentoo" section

image=/boot/kernel-3.4.9-gentoo
label=gentoo          # Name we give to this section
read-only             # Start with a read-only root. Do not alter!
root=/dev/sda3        # Location of the root filesystem

image=/boot/kernel-3.4.9-gentoo
label=gentoo.rescue   # Name we give to this section
read-only             # Start with a read-only root. Do not alter!
root=/dev/sda3        # Location of the root filesystem
append="init=/bin/bb" # Launch the Gentoo static rescue shell

# The next two lines are only if you dualboot with a Windows system.
# In this case, Windows is hosted on /dev/sda6.
other=/dev/sda6
label=windows
```

**Note:** If you use a different partitioning scheme and/or kernel image, adjust accordingly.

If, while building the Linux kernel, you opted to include an initramfs to boot from, then you will need to change the configuration by referring to this initramfs file and telling the initramfs where your real root device is at:

#### Code Listing 3.4: LILO snippet for initramfs-enabled kernel builds

```
image=/boot/kernel-3.4.9-gentoo
label=gentoo
read-only
append="real_root=/dev/sda3"
initrd=/boot/initramfs-genkernel-amd64-3.4.9-gentoo
```

If you need to pass any additional options to the kernel, add an `append` statement to the section. As an example, we add the `video` statement to enable framebuffer:

#### Code Listing 3.5: Using `append` to add kernel options

```
image=/boot/kernel-3.4.9-gentoo
label=gentoo
read-only
root=/dev/sda3
append="video=uvesafb:mtrr,ywrap,1024x768-32@85"
```

If you're using a 2.6.7 or higher kernel and you jumped over your harddrive because the BIOS can't handle large harddrives you'll need to append `sda=stroke`. Replace `sda` with the device that requires this option.

`genkernel` users should know that their kernels use the same boot options as is used for the Installation CD. For instance, if you have SCSI devices, you should add `doscsi` as kernel option.

Now save the file and exit. To finish up, you have to run `/sbin/lilo` so LILO can apply the `/etc/lilo.conf` to your system (i.e. install itself on the disk). Keep in mind that you'll also have to run `/sbin/lilo` every time you install a new kernel or make any changes to the menu.

#### Code Listing 3.6: Finishing the LILO installation

```
# /sbin/lilo
```

If you have more questions regarding LILO, please consult its [wikipedia page](#).

You can now continue with [Rebooting the System](#).

## 10.d. Rebooting the System

Exit the chrooted environment and unmount all mounted partitions. Then type in that one magical command you have been waiting for: `reboot`.

#### Code Listing 4.1: Unmounting all partitions and rebooting

```
# exit
cdimage ~# cd
cdimage ~# umount -l /mnt/gentoo/dev{/shm,/pts,}
cdimage ~# umount -l /mnt/gentoo{/boot,/proc,}
cdimage ~# reboot
```

Of course, don't forget to remove the bootable CD, otherwise the CD will be booted again instead of your new Gentoo system.

Once rebooted in your Gentoo installation, finish up with [Finalizing your Gentoo Installation](#).

11. Finalizing your Gentoo Installation

11.a. User Administration

Adding a User for Daily Use

Working as root on a Unix/Linux system is *dangerous* and should be avoided as much as possible. Therefore it is *strongly* recommended to add a user for day-to-day use.

The groups the user is member of define what activities the user can perform. The following table lists a number of important groups you might wish to use:

Group	Description
audio	be able to access the audio devices
cdrom	be able to directly access optical devices
floppy	be able to directly access floppy devices
games	be able to play games
portage	be able to use <code>emerge --pretend</code> as a normal user
usb	be able to access USB devices
video	be able to access video capturing hardware and doing hardware acceleration
wheel	be able to use <code>su</code>

For instance, to create a user called `john` who is member of the `wheel`, `users` and `audio` groups, log in as root first (only root can create users) and run `useradd`:

Code Listing 1.1: Adding a user for day-to-day use

```
Login: root
Password: (Your root password)

# useradd -m -G users,wheel,audio -s /bin/bash john
# passwd john
Password: (Enter the password for john)
Re-enter password: (Re-enter the password to verify)
```

If a user ever needs to perform some task as root, they can use `su -` to temporarily receive root privileges. Another way is to use the `sudo` package which is, if correctly configured, very secure.

11.b. Disk Cleanup

Removing tarballs

Now that you've finished installing Gentoo and rebooted, if everything has gone well, you can remove the downloaded stage3 tarball from your hard disk. Remember that they were downloaded to your `/` directory.

Code Listing 2.1: Removing the stage3 tarball

```
# rm /stage3-*.tar.bz2*
```

12. Where to go from here?

12.a. Documentation

Congratulations! You now have a working Gentoo system. But where to go from here? What are your options now? What to explore first? Gentoo provides its users with lots of possibilities, and therefore lots of documented (and less documented) features.

You should definitely take a look at the next part of the Gentoo Handbook entitled [Working with Gentoo](#) which explains how to keep your software up to date, how to install more software, what USE flags are, how the Gentoo init system works, etc.

If you are interested in optimizing your system for desktop use, or you want to learn how to configure your system to be a full working desktop system, consult our extensive [Gentoo Desktop Documentation Resources](#). Besides, you might want to use our [localization guide](#) to make your system feel more at home.

We also have a [Gentoo Security Handbook](#) which is worth reading.

For a full listing of all our available documentation check out our [Documentation Resources](#) page.

Finally, we also have an official [Gentoo Wiki](#) where additional, community-provided documentation can be found.

12.b. Gentoo Online

You are of course always welcome on our [Gentoo Forums](#) or on one of our many [Gentoo IRC channels](#).

We also have several [mailing lists](#) open to all our users. Information on how to join is contained in that page.

We'll shut up now and let you enjoy your installation. :)

B. Working with Gentoo

1. A Portage Introduction

1.a. Welcome to Portage

Portage is probably Gentoo's most notable innovation in software management. With its high flexibility and enormous amount of features it is frequently seen as the best software management tool available for Linux.

Portage is completely written in [Python](#) and [Bash](#) and therefore fully visible to the users as both are scripting languages.

Most users will work with Portage through the [emerge](#) tool. This chapter is not meant to duplicate the information available from the emerge man page. For a complete rundown of emerge's options, please consult the man page:

#### Code Listing 1.1: Reading the emerge man page

```
$ man emerge
```

## 1.b. The Portage Tree

### Ebuilds

When we talk about packages, we often mean software titles that are available to the Gentoo users through the Portage tree. The Portage tree is a collection of *ebuilds*, files that contain all information Portage needs to maintain software (install, search, query, ...). These ebuilds reside in `/usr/portage` by default.

Whenever you ask Portage to perform some action regarding software titles, it will use the ebuilds on your system as a base. It is therefore important that you regularly update the ebuilds on your system so Portage knows about new software, security updates, etc.

### Updating the Portage Tree

The Portage tree is usually updated with [rsync](#), a fast incremental file transfer utility. Updating is fairly simple as the [emerge](#) command provides a front-end for rsync:

#### Code Listing 2.1: Updating the Portage tree

```
# emerge --sync
```

If you are unable to rsync due to firewall restrictions you can still update your Portage tree by using our daily generated Portage tree snapshots. The [emerge-websync](#) tool automatically fetches and installs the latest snapshot on your system:

#### Code Listing 2.2: Running emerge-websync

```
# emerge-websync
```

An additional advantage of using [emerge-websync](#) is that it allows the administrator to only pull in portage tree snapshots that are signed by the Gentoo release engineering GPG key. More information on this can be found in the [Portage Features](#) section on [Fetching Validated Portage Tree Snapshots](#).

## 1.c. Maintaining Software

### Searching for Software

To search through the Portage tree after software titles, you can use [emerge](#) built-in search capabilities. By default, [emerge --search](#) returns the names of packages whose title matches (either fully or partially) the given search term.

For instance, to search for all packages who have "pdf" in their name:

#### Code Listing 3.1: Searching for pdf-named packages

```
$ emerge --search pdf
```

If you want to search through the descriptions as well you can use the [--searchdesc](#) (or [-S](#)) switch:

#### Code Listing 3.2: Searching for pdf-related packages

```
$ emerge --searchdesc pdf
```

When you take a look at the output, you'll notice that it gives you a lot of information. The fields are clearly labelled so we won't go further into their meanings:

#### Code Listing 3.3: Example 'emerge --search' output

```
* net-print/cups-pdf
  Latest version available: 1.5.2
  Latest version installed: [ Not Installed ]
  Size of downloaded files: 15 kB
  Homepage:      http://cip.physik.uni-wuerzburg.de/~vrbehr/cups-pdf/
  Description:   Provides a virtual printer for CUPS to produce PDF files.
  License:      GPL-2
```

### Installing Software

Once you've found a software title to your liking, you can easily install it with [emerge](#): just add the package name. For instance, to install [gnumeric](#):

#### Code Listing 3.4: Installing gnumeric

```
# emerge gnumeric
```

Since many applications depend on each other, any attempt to install a certain software package might result in the installation of several dependencies as well. Don't worry, Portage handles dependencies well. If you want to find out what Portage *would* install when you ask it to install a certain package, add the [--pretend](#) switch. For instance:

#### Code Listing 3.5: Pretend to install gnumeric

```
# emerge --pretend gnumeric
```



When you ask Portage to install a package, it will download the necessary source code from the internet (if necessary) and store it by default in `/usr/portage/distfiles`. After this it will unpack, compile and install the package. If you want Portage to only download the sources without installing them, add the `--fetchonly` option to the `emerge` command:

#### Code Listing 3.6: Download the sourcecode for gnumeric

```
# emerge --fetchonly gnumeric
```

## Finding Installed Package Documentation

Many packages come with their own documentation. Sometimes, the `doc` USE flag determines whether the package documentation should be installed or not. You can check the existence of a `doc` USE flag with the `emerge -vp <package name>` command.

#### Code Listing 3.7: Checking the existence of a doc USE flag

```
(alsa-lib is just an example, of course.)
# emerge -vp alsa-lib
[ebuild N ] media-libs/alsa-lib-1.0.14_rc1 -debug +doc 698 kB
```

The best way of enabling the `doc` USE flag is doing it on a per-package basis via `/etc/portage/package.use`, so that you get documentation only for packages that you are interested in. Enabling this flag globally is known to cause problems with circular dependencies. For more information, please read the [USE Flags](#) chapter.

Once the package installed, its documentation is generally found in a subdirectory named after the package under the `/usr/share/doc` directory. You can also list all installed files with the `equery` tool which is part of the [app-portage/gentoolkit package](#).

#### Code Listing 3.8: Locating package documentation

```
# ls -l /usr/share/doc/alsa-lib-1.0.14_rc1
total 28
-rw-r--r-- 1 root root 669 May 17 21:54 ChangeLog.gz
-rw-r--r-- 1 root root 9373 May 17 21:54 COPYING.gz
drwxr-xr-x 2 root root 8560 May 17 21:54 html
-rw-r--r-- 1 root root 196 May 17 21:54 TODO.gz

(Alternatively, use equery to locate interesting files:)
# equery files alsa-lib| less
media-libs/alsa-lib-1.0.14_rc1
* Contents of media-libs/alsa-lib-1.0.14_rc1:
/usr
/usr/bin
/usr/bin/alsalisp
(Output truncated)
```

## Removing Software

When you want to remove a software package from your system, use `emerge --unmerge`. This will tell Portage to remove all files installed by that package from your system *except* the configuration files of that application if you have altered those after the installation. Leaving the configuration files allows you to continue working with the package if you ever decide to install it again.

However, a **big warning** applies: Portage will *not* check if the package you want to remove is required by another package. It will however warn you when you want to remove an important package that breaks your system if you unmerge it.

#### Code Listing 3.9: Removing gnumeric from the system

```
# emerge --unmerge gnumeric
```

When you remove a package from your system, the dependencies of that package that were installed automatically when you installed the software are left. To have Portage locate all dependencies that can now be removed, use `emerge's --depclean` functionality. We will talk about this later on.

## Updating your System

To keep your system in perfect shape (and not to mention install the latest security updates) you need to update your system regularly. Since Portage only checks the ebuids in your Portage tree you first have to update your Portage tree. When your Portage tree is updated, you can update your system with `emerge --update world`. In the next example, we'll also use the `--ask` switch which will tell Portage to display the list of packages it wants to upgrade and ask you if you want to continue:

#### Code Listing 3.10: Updating your system

```
# emerge --update --ask world
```

Portage will then search for newer version of the applications you have installed. However, it will only verify the versions for the applications you have *explicitly* installed (the applications listed in `/var/lib/portage/world`) - it does not thoroughly check their dependencies. If you want to update the dependencies of those packages as well, add the `--deep` argument:

#### Code Listing 3.11: Updating your system with dependencies

```
# emerge --update --deep world
```

Still, this doesn't mean *all packages*: some packages on your system are needed during the compile and build process of packages, but once that package is installed, these dependencies are no longer required. Portage calls those *build dependencies*. To include those in an update cycle, add `--with-bdeps=y`:

#### Code Listing 3.12: Updating your entire system

```
# emerge --update --deep --with-bdeps=y world
```

Since security updates also happen in packages you have not explicitly installed on your system (but that are pulled in as dependencies of other programs), it is recommended to run this command once in a while.

If you have altered any of your [USE flags](#) lately you might want to add `--newuse` as well. Portage will then verify if the change requires the installation of new packages or recompilation of existing ones:

#### Code Listing 3.13: Performing a full update

```
# emerge --update --deep --with-bdeps=y --newuse world
```

## Metapackages

Some packages in the Portage tree don't have any real content but are used to install a collection of packages. For instance, the `kde-meta` package will install a complete KDE environment on your system by pulling in various KDE-related packages as dependencies.

If you ever want to remove such a package from your system, running `emerge --unmerge` on the package won't have much effect as the dependencies remain on the system.

Portage has the functionality to remove orphaned dependencies as well, but since the availability of software is dynamically dependent you first need to update your entire system fully, including the new changes you applied when changing USE flags. After this you can run `emerge --depclean` to remove the orphaned dependencies. When this is done, you need to rebuild the applications that were dynamically linked to the now-removed software titles but don't require them anymore.

All this is handled with the following three commands:

#### Code Listing 3.14: Removing orphaned dependencies

```
# emerge --update --deep --newuse world
# emerge --depclean
# revdep-rebuild
```

`revdep-rebuild` is provided by the `gentoolkit` package; don't forget to emerge it first:

#### Code Listing 3.15: Installing the gentoolkit package

```
# emerge gentoolkit
```

## 1.d. Licenses

Beginning with Portage version 2.1.7, you can accept or reject software installation based on its license. All packages in the tree contain a `LICENSE` entry in their ebuilds. Running `emerge --search packagename` will tell you the package's license.

By default, Portage permits all licenses, except End User License Agreements (EULAs) that require reading and signing an acceptance agreement.

The variable that controls permitted licenses is `ACCEPT_LICENSE`, which can be set in `/etc/portage/make.conf`:

#### Code Listing 4.1: Default ACCEPT\_LICENSE in /etc/portage/make.conf

```
ACCEPT_LICENSE="* -@EULA"
```

With this configuration, packages that require interaction during installation to approve their EULA *will not* be installed. Packages without an EULA *will* be installed.

You can set `ACCEPT_LICENSE` globally in `/etc/portage/make.conf`, or you can specify it on a per-package basis in `/etc/portage/package.license`.

For example, if you want to allow the `truecrypt-2.7` license for `app-crypt/truecrypt`, add the following to `/etc/portage/package.license`:

#### Code Listing 4.2: Specifying a truecrypt license in package.license

```
app-crypt/truecrypt truecrypt-2.7
```

This permits installation of truecrypt versions that have the `truecrypt-2.7` license, but not versions with the `truecrypt-2.8` license.

**Important:** Licenses are stored in `/usr/portage/licenses`, and license groups are kept in `/usr/portage/profiles/license_groups`. The first entry of each line in CAPITAL letters is the name of the license group, and every entry after that is an individual license.

License groups defined in `ACCEPT_LICENSE` are prefixed with an `@` sign. Here's an example of a system that globally permits the GPL-compatible license group, as well as a few other groups and individual licenses:

#### Code Listing 4.3: ACCEPT\_LICENSE in /etc/portage/make.conf

```
ACCEPT_LICENSE="@GPL-COMPATIBLE @OSI-APPROVED @EULA atheros-hal BitstreamVera"
```

If you want only free software and documentation on your system, you might use the following setup:

#### Code Listing 4.4: Use only free licenses

```
ACCEPT_LICENSE="- * @FREE"
```

In this case, "free" is mostly defined by the [FSF](#) and [OSI](#). Any package whose license does not meet these requirements will not be installed on your system.

## 1.e. When Portage is Complaining...

### About SLOTS, Virtuals, Branches, Architectures and Profiles

As we stated before, Portage is extremely powerful and supports many features that other software management tools lack. To understand this, we explain a few aspects of Portage without going into too much detail.

With Portage different versions of a single package can coexist on a system. While other distributions tend to name their package to those versions (like `freetype` and `freetype2`) Portage uses a technology called *SLOTS*. An ebuild declares a certain SLOT for its version. Ebuilds with different SLOTS can coexist on the same system. For instance, the `freetype` package has ebuilds with `SLOT="1"` and `SLOT="2"`.

There are also packages that provide the same functionality but are implemented differently. For instance, [metalogd](#), [sysklogd](#) and [syslog-ng](#) are all system loggers. Applications that rely on the availability of "a system logger" cannot depend on, for instance, [metalogd](#), as the other system loggers are as good a choice as any. Portage allows for *virtuals*: each system logger is listed as an "exclusive" dependency of the logging service in the [logger](#) virtual package of the [virtual](#) category, so that applications can depend on the [virtual/logger](#) package. When installed, the package will pull in the first logging package mentioned in the package, unless a logging package was already installed (in which case the virtual is satisfied).

Software in the Portage tree can reside in different branches. By default your system only accepts packages that Gentoo deems stable. Most new software titles, when committed, are added to the testing branch, meaning more testing needs to be done before it is marked as stable. Although you will see the ebuilds for those software in the Portage tree, Portage will not update them before they are placed in the stable branch.

Some software is only available for a few architectures. Or the software doesn't work on the other architectures, or it needs more testing, or the developer that committed the software to the Portage tree is unable to verify if the package works on different architectures.

Each Gentoo installation adheres to a certain [profile](#) which contains, amongst other information, the list of packages that are required for a system to function normally.

## Blocked Packages

### Code Listing 5.1: Portage warning about blocked packages (with --pretend)

```
[blocks B      ] mail-mta/ssmtp (is blocking mail-mta/postfix-2.2.2-r1)
```

### Code Listing 5.2: Portage warning about blocked packages (without --pretend)

```
!!! Error: the mail-mta/postfix package conflicts with another package.
!!!       both can't be installed on the same system together.
!!!       Please use 'emerge --pretend' to determine blockers.
```

Ebuilds contain specific fields that inform Portage about its dependencies. There are two possible dependencies: build dependencies, declared in [DEPEND](#) and run-time dependencies, declared in [RDEPEND](#). When one of these dependencies explicitly marks a package or virtual as being *not* compatible, it triggers a blockage.

While recent versions of Portage are smart enough to work around minor blockages without user intervention, occasionally you will need to fix it yourself, as explained below.

To fix a blockage, you can choose to not install the package or unmerge the conflicting package first. In the given example, you can opt not to install [postfix](#) or to remove [ssmtp](#) first.

You may also see blocking packages with specific atoms, such as `<media-video/mplayer-1.0_rc1-r2`. In this case, updating to a more recent version of the blocking package would remove the block.

It is also possible that two packages that are yet to be installed are blocking each other. In this rare case, you should find out why you need to install both. In most cases you can do with one of the packages alone. If not, please file a bug on [Gentoo's bugtracking system](#).

## Masked Packages

### Code Listing 5.3: Portage warning about masked packages

```
!!! all ebuilds that could satisfy "bootsplash" have been masked.
```

### Code Listing 5.4: Portage warning about masked packages - reason

```
!!! possible candidates are:
- gnome-base/gnome-2.8.0_pre1 (masked by: ~x86 keyword)
- lm-sensors/lm-sensors-2.8.7 (masked by: -sparc keyword)
- sys-libs/glibc-2.3.4.20040808 (masked by: -* keyword)
- dev-util/cvsd-1.0.2 (masked by: missing keyword)
- games-fps/unreal-tournament-451 (masked by: package.mask)
- sys-libs/glibc-2.3.2-r11 (masked by: profile)
- net-im/skype-2.1.0.81 (masked by: skype-eula license(s))
```

When you want to install a package that isn't available for your system, you will receive this masking error. You should try installing a different application that is available for your system or wait until the package is put available. There is always a reason why a package is masked:

- **~arch keyword** means that the application is not tested sufficiently to be put in the stable branch. Wait a few days or weeks and try again.
- **-arch keyword** or **-\* keyword** means that the application does not work on your architecture. If you believe the package does work file a bug at our [bugzilla](#) website.
- **missing keyword** means that the application has not been tested on your architecture yet. Ask the architecture porting team to test the package or test it for them and report your findings on our [bugzilla](#) website.
- **package.mask** means that the package has been found corrupt, unstable or worse and has been deliberately marked as do-not-use.
- **profile** means that the package has been found not suitable for your profile. The application might break your system if you installed it or is just not compatible with the profile you use.
- **license** means that the package's license is not compatible with your [ACCEPT\\_LICENSE](#) setting. You must explicitly permit its license or license group by setting it in `/etc/portage/make.conf` or in `/etc/portage/package.license`. Refer to [Licenses](#) to learn how licenses work.

## Necessary USE Flag Changes

### Code Listing 5.5: Portage warning about USE flag change requirement

```
The following USE changes are necessary to proceed:
#required by app-text/happypackage-2.0, required by happypackage (argument)
>=app-text/feelings-1.0.0 test
```

The error message might also be displayed as follows, if `--autounmask` isn't set:

### Code Listing 5.6: Portage error about USE flag change requirement

```

emerge: there are no ebuilds built with USE flags to satisfy "app-text/feelings[test]".
!!! One of the following packages is required to complete your request:
- app-text/feelings-1.0.0 (Change USE: +test)
(dependency required by "app-text/happypackage-2.0" [ebuild])
(dependency required by "happypackage" [argument])

```

Such warning or error occurs when you want to install a package which not only depends on another package, but also requires that that package is built with a particular USE flag (or set of USE flags). In the given example, the package `app-text/feelings` needs to be built with `USE="test"`, but this USE flag is not set on the system.

To resolve this, either add the requested USE flag to your global USE flags in `/etc/portage/make.conf`, or set it for the specific package in `/etc/portage/package.use`.

## Missing Dependencies

### Code Listing 5.7: Portage warning about missing dependency

```

emerge: there are no ebuilds to satisfy ">=sys-devel/gcc-3.4.2-r4".

!!! Problem with ebuild sys-devel/gcc-3.4.2-r2
!!! Possibly a DEPEND/*DEPEND problem.

```

The application you are trying to install depends on another package that is not available for your system. Please check [bugzilla](#) if the issue is known and if not, please report it. Unless you are mixing branches this should not occur and is therefore a bug.

## Ambiguous Ebuild Name

### Code Listing 5.8: Portage warning about ambiguous ebuild names

```

[ Results for search key : listen ]
[ Applications found : 2 ]

* dev-tinyos/listen [ Masked ]
  Latest version available: 1.1.15
  Latest version installed: [ Not Installed ]
  Size of files: 10,032 kB
  Homepage:      http://www.tinyos.net/
  Description:   Raw listen for TinyOS
  License:      BSD

* media-sound/listen [ Masked ]
  Latest version available: 0.6.3
  Latest version installed: [ Not Installed ]
  Size of files: 859 kB
  Homepage:      http://www.listen-project.org
  Description:   A Music player and management for GNOME
  License:      GPL-2

!!! The short ebuild name "listen" is ambiguous. Please specify
!!! one of the above fully-qualified ebuild names instead.

```

The application you want to install has a name that corresponds with more than one package. You need to supply the category name as well. Portage will inform you of possible matches to choose from.

## Circular Dependencies

### Code Listing 5.9: Portage warning about circular dependencies

```

!!! Error: circular dependencies:

ebuild / net-print/cups-1.1.15-r2 depends on ebuild / app-text/ghostscript-7.05.3-r1
ebuild / app-text/ghostscript-7.05.3-r1 depends on ebuild / net-print/cups-1.1.15-r2

```

Two (or more) packages you want to install depend on each other and can therefore not be installed. This is most likely a bug in the Portage tree. Please resync after a while and try again. You can also check [bugzilla](#) if the issue is known and if not, report it.

## Fetch failed

### Code Listing 5.10: Portage warning about fetch failed

```

!!! Fetch failed for sys-libs/ncurses-5.4-r5, continuing...
(...)
!!! Some fetch errors were encountered. Please see above for details.

```

Portage was unable to download the sources for the given application and will try to continue installing the other applications (if applicable). This failure can be due to a mirror that has not synchronised correctly or because the ebuild points to an incorrect location. The server where the sources reside can also be down for some reason.

Retry after one hour to see if the issue still persists.

## System Profile Protection

### Code Listing 5.11: Portage warning about profile-protected package

```

!!! Trying to unmerge package(s) in system profile. 'sys-apps/portage'
!!! This could be damaging to your system.

```

You have asked to remove a package that is part of your system's core packages. It is listed in your profile as required and should therefore not be removed from the system.

## Digest Verification Failures

Sometimes, when you attempt to emerge a package, it will fail with the message:

### Code Listing 5.12: Digest verification failure

```
>>> checking ebuild checksums
!!! Digest verification failed:
```

This is a sign that something is wrong with the Portage tree -- often, it is because a developer may have made a mistake when committing a package to the tree.

When the digest verification fails, do *not* try to re-digest the package yourself. Running `ebuild foo manifest` will not fix the problem; it will almost certainly make it worse!

Instead, wait an hour or two for the tree to settle down. It's likely that the error was noticed right away, but it can take a little time for the fix to trickle down the Portage tree. While you're waiting, check [Bugzilla](#) and see if anyone has reported the problem yet. If not, go ahead and file a bug for the broken package.

Once you see that the bug has been fixed, you may want to re-sync to pick up the fixed digest.

**Important:** This does *not* mean that you can re-sync your tree multiple times! As stated in the rsync policy (when you run `emerge --sync`), users who sync too often will be banned! In fact, it's better to just wait until your next scheduled sync, so that you don't overload the rsync servers.

## 2. USE flags

### 2.a. What are USE flags?

#### The ideas behind USE flags

When you are installing Gentoo (or any other distribution, or even operating system for that matter) you make choices depending on the environment you are working with. A setup for a server differs from a setup for a workstation. A gaming workstation differs from a 3D rendering workstation.

This is not only true for choosing what packages you want to install, but also what features a certain package should support. If you don't need OpenGL, why would you bother installing OpenGL and build OpenGL support in most of your packages? If you don't want to use KDE, why would you bother compiling packages with KDE support if those packages work flawlessly without?

To help users in deciding what to install/activate and what not, we wanted the user to specify his/her environment in an easy way. This forces the user into deciding what they really want and eases the process for Portage, our package management system, to make useful decisions.

#### Definition of a USE flag

Enter the USE flags. Such a flag is a keyword that embodies support and dependency-information for a certain concept. If you define a certain USE flag, Portage will know that you want support for the chosen keyword. Of course this also alters the dependency information for a package.

Let us take a look at a specific example: the `kde` keyword. If you do not have this keyword in your `USE` variable, all packages that have *optional* KDE support will be compiled *without* KDE support. All packages that have an *optional* KDE dependency will be installed *without* installing the KDE libraries (as dependency). If you have defined the `kde` keyword, then those packages *will* be compiled with KDE support, and the KDE libraries will be installed as dependency.

By correctly defining the keywords you will receive a system tailored specifically to your needs.

#### What USE flags exist?

There are two types of USE flags: *global* and *local* USE flags.

- A *global* USE flag is used by several packages, system-wide. This is what most people see as USE flags.
- A *local* USE flag is used by a single package to make package-specific decisions.

A list of available global USE flags can be found [online](#) or locally in `/usr/portage/profiles/use.desc`.

A list of available local USE flags can be found locally in `/usr/portage/profiles/use.local.desc`.

### 2.b. Using USE flags

#### Declare permanent USE flags

In the hope you are convinced of the importance of USE flags we will now inform you how to declare USE flags.

As previously mentioned, all USE flags are declared inside the `USE` variable. To make it easy for users to search and pick USE flags, we already provide a *default* USE setting. This setting is a collection of USE flags we think are commonly used by the Gentoo users. This default setting is declared in the `make.defaults` files part of your profile.

The profile your system listens to is pointed to by the `/etc/portage/make.profile` symlink. Each profile works on top of another, larger profile, the end result is therefore the sum of all profiles. The top profile is the base profile (`/usr/portage/profiles/base`).

Let us take a look at this default setting for the 13.0 profile:

### Code Listing 2.1: Cumulative make.defaults USE variable for the 13.0 profile

```
(This example is the sum of the settings in base, default/linux,
 default/linux/x86 and default/linux/x86/13.0/)
USE="a52 aac acpi alsa branding cairo cdr dbus dts dvd dvdr emboss encode exif
fam firefox flac gif gpm gtk hal jpeg lcms ldap libnotify mad mikmod mng mp3
mp4 mpeg ogg opengl pango pdf png ppds qt3support qt4 sdl spell
startup-notification svg tiff truetype vorbis unicode usb X xcb x264 xml xv
xvid"
```

As you can see, this variable already contains quite a lot of keywords. Do **not** alter any `make.defaults` file to tailor the `USE` variable to your needs: changes in this file will be undone when you update Portage!

To change this default setting, you need to add or remove keywords to the `USE` variable. This is done globally by defining the `USE` variable in `/etc/portage/make.conf`. In this variable you add the extra `USE` flags you require, or remove the `USE` flags you don't want. This latter is done by prefixing the keyword with the minus-sign ("-").

For instance, to remove support for KDE and QT but add support for ldap, the following `USE` can be defined in `/etc/portage/make.conf`:

#### Code Listing 2.2: An example `USE` setting in `/etc/portage/make.conf`

```
USE="-kde -qt4 ldap"
```

### Declaring `USE` flags for individual packages

Sometimes you want to declare a certain `USE` flag for one (or a couple) of applications but not system-wide. To accomplish this, you will need to create the `/etc/portage` directory (if it doesn't exist yet) and edit `/etc/portage/package.use`. This is usually a single file, but can also be a directory; see [man portage](#) for more information. The following examples assume `package.use` is a single file.

For instance, if you don't want `berkdb` support globally but you do want it for `mysql`, you would add:

#### Code Listing 2.3: `/etc/portage/package.use` example

```
dev-db/mysql berkdb
```

You can of course also explicitly *disable* `USE` flags for a certain application. For instance, if you don't want `java` support in PHP:

#### Code Listing 2.4: `/etc/portage/package.use` 2nd example

```
dev-php/php -java
```

### Declare temporary `USE` flags

Sometimes you want to set a certain `USE` setting only once. Instead of editing `/etc/portage/make.conf` twice (to do and undo the `USE` changes) you can just declare the `USE` variable as environment variable. Remember that, when you re-emerge or update this application (either explicitly or as part of a system update) your changes will be lost!

As an example we will temporarily remove `java` from the `USE` setting during the installation of `seamonkey`.

#### Code Listing 2.5: Using `USE` as environment variable

```
# USE="-java" emerge seamonkey
```

### Precedence

Of course there is a certain precedence on what setting has priority over the `USE` setting. You don't want to declare `USE="-java"` only to see that `java` is still used due to a setting that has a higher priority. The precedence for the `USE` setting is, ordered by priority (first has lowest priority):

1. Default `USE` setting declared in the `make.defaults` files part of your profile
2. User-defined `USE` setting in `/etc/portage/make.conf`
3. User-defined `USE` setting in `/etc/portage/package.use`
4. User-defined `USE` setting as environment variable

To view the final `USE` setting as seen by Portage, run `emerge --info`. This will list all relevant variables (including the `USE` variable) with the content used by Portage.

#### Code Listing 2.6: Running `emerge --info`

```
# emerge --info
```

### Adapting your Entire System to New `USE` Flags

If you have altered your `USE` flags and you wish to update your entire system to use the new `USE` flags, use `emerge's --newuse` option:

#### Code Listing 2.7: Rebuilding your entire system

```
# emerge --update --deep --newuse world
```

Next, run Portage's `depclean` to remove the conditional dependencies that were emerged on your "old" system but that have been obsoleted by the new `USE` flags.

**Warning:** Running `emerge --depclean` is a dangerous operation and should be handled with care. Double-check the provided list of "obsoleted" packages to make sure it doesn't remove packages you need. In the following example we add the `-p` switch to have `depclean` only list the packages without removing them.

#### Code Listing 2.8: Removing obsoleted packages

```
# emerge -p --depclean
```

When `depclean` has finished, run `revdep-rebuild` to rebuild the applications that are dynamically linked against shared objects provided by possibly removed packages. `revdep-rebuild` is part of the `gentoolkit` package; don't forget to emerge it first.

#### Code Listing 2.9: Running `revdep-rebuild`

```
# revdep-rebuild
```

When all this is accomplished, your system is using the new `USE` flag settings.



### Viewing available USE flags

### Code Listing 3.1: Viewing the used USE flags

`emerge` isn't the only tool for this job. In fact, we have a tool dedicated to package information called `equery` which resides in the `gentoolkit` package. First, install `gentoolkit`:

### Code Listing 3.2: Installing gentoolkit

```
# emerge gentoolkit
```

### Code Listing 3.3: Using equery to view used USE flags

### 3.a. Portage Features

Portage has several additional features that makes your Gentoo experience even better. Many of these features rely on certain software tools that improve performance, reliability, security, ...

To enable or disable certain Portage features you need to edit `/etc/portage/make.conf`'s `FEATURES` variable which contains the various feature keywords, separated by white space. In several cases you will also need to install the additional tool on which the feature relies.

Not all features that Portage supports are listed here. For a full overview, please consult the `make.conf` man page:

### Code Listing 1.1: Consulting the make.conf man page

\$ man make.conf

To find out what FEATURES are default set, run `emerge --info` and search for the FEATURES variable or grep it out:

### Code Listing 1.2: Finding out the FEATURES that are already set

```
$ emerge --info | grep FEATURES
```

### 3.b. Distributed Compiling

## Using distcc

`distcc` is a program to distribute compilations across several, not necessarily identical, machines on a network. The `distcc` client sends all necessary information to the available `distcc` servers (running `distccd`) so they can compile pieces of source code for the client. The net result is a faster compilation time.

You can find more information about [distcc](#) (and how to have it work with Gentoo) in our [Gentoo Distcc Documentation](#).

## Installing distcc

Distcc ships with a graphical monitor to monitor tasks that your computer is sending away for compilation. If you use Gnome then put 'gnome' in your USE variable. However, if you don't use Gnome and would still like to have the monitor then you should put 'gtk' in your USE variable.

### Code Listing 2.1: Installing distcc

```
# emerge distcc
```

## Activating Portage Support

Add `distcc` to the `FEATURES` variable inside `/etc/portage/make.conf`. Next, edit the `MAKEOPTS` variable to your liking. A known guideline is to fill in `"-jX"` with `X` the number of CPUs that run `distcc` (including the current host) plus one, but you might have better results with other numbers.

Now run `distcc-config` and enter the list of available distcc servers. For a simple example we assume that the available DistCC servers are 192.168.1.102 (the current host), 192.168.1.103 and 192.168.1.104 (two "remote" hosts):

#### Code Listing 2.2: Configuring distcc to use three available distcc servers

```
# distcc-config --set-hosts "192.168.1.102 192.168.1.103 192.168.1.104"
```

Don't forget to run the `distccd` daemon as well:

#### Code Listing 2.3: Starting the distccd daemons

```
# rc-update add distccd default
# /etc/init.d/distccd start
```

## 3.c. Caching Compilation

### About ccache

`ccache` is a fast compiler cache. When you compile a program, it will cache intermediate results so that, whenever you recompile the same program, the compilation time is greatly reduced. The first time you run `ccache`, it will be much slower than a normal compilation. Subsequent recompiles should be faster. `ccache` is only helpful if you will be recompiling the same application many times; thus it's mostly only useful for software developers.

If you are interested in the ins and outs of `ccache`, please visit the [ccache homepage](#).

**Warning:** `ccache` is known to cause numerous compilation failures. Sometimes `ccache` will retain stale code objects or corrupted files, which can lead to packages that cannot be emerged. If this happens (if you receive errors like "File not recognized: File truncated"), try recompiling the application with `ccache` disabled (`FEATURES="-ccache"` in `/etc/portage/make.conf`) *before* reporting a bug. Unless you are doing development work, *do not enable ccache*.

### Installing ccache

To install `ccache`, run `emerge ccache`:

#### Code Listing 3.1: Installing ccache

```
# emerge ccache
```

### Activating Portage Support

Open `/etc/portage/make.conf` and add `ccache` to the `FEATURES` variable. Next, add a new variable called `CCACHE_SIZE` and set it to "2G":

#### Code Listing 3.2: Editing CCACHE\_SIZE in /etc/portage/make.conf

```
CCACHE_SIZE="2G"
```

To check if `ccache` functions, ask `ccache` to provide you with its statistics. Because Portage uses a different `ccache` home directory, you need to set the `CCACHE_DIR` variable as well:

#### Code Listing 3.3: Viewing ccache statistics

```
# CCACHE_DIR="/var/tmp/ccache" ccache -s
```

The `/var/tmp/ccache` location is Portage' default `ccache` home directory; if you want to alter this setting you can set the `CCACHE_DIR` variable in `/etc/portage/make.conf`.

However, if you would run `ccache`, it would use the default location of `${HOME}/.ccache`, which is why you needed to set the `CCACHE_DIR` variable when asking for the (Portage) `ccache` statistics.

### Using ccache for non-Portage C Compiling

If you would like to use `ccache` for non-Portage compilations, add `/usr/lib/ccache/bin` to the beginning of your `PATH` variable (before `/usr/bin`). This can be accomplished by editing `.bash_profile` in your user's home directory. Using `.bash_profile` is one way to define `PATH` variables.

#### Code Listing 3.4: Editing .bash\_profile

```
PATH="/usr/lib/ccache/bin:/opt/bin:${PATH}"
```

## 3.d. Binary Package Support

### Creating Prebuilt Packages

Portage supports the installation of prebuilt packages. Even though Gentoo does not provide prebuilt packages by itself (except for the GRP snapshots) Portage can be made fully aware of prebuilt packages.

To create a prebuilt package you can use `quickpkg` if the package is already installed on your system, or `emerge` with the `--buildpkg` or `--buildpkgonly` options.

If you want Portage to create prebuilt packages of every single package you install, add `buildpkg` to the `FEATURES` variable.

More extended support for creating prebuilt package sets can be obtained with `catalyst`. For more information on `catalyst` please read the [Catalyst Frequently Asked Questions](#).

### Installing Prebuilt Packages

Although Gentoo doesn't provide one, you can create a central repository where you store prebuilt packages. If you want to use this repository, you need to make Portage aware of it by having the `PORTAGE_BINHOST` variable point to it. For instance, if the prebuilt packages are on `ftp://buildhost/gentoo`:

#### Code Listing 4.1: Setting PORTAGE\_BINHOST in /etc/portage/make.conf

```
PORTAGE_BINHOST="ftp://buildhost/gentoo"
```

When you want to install a prebuilt package, add the `--getbinpkg` option to the emerge command alongside of the `--usepkg` option. The former tells emerge to download the prebuilt package from the previously defined server while the latter asks emerge to try to install the prebuilt package first before fetching the sources and compiling it.

For instance, to install `gnumeric` with prebuilt packages:

#### Code Listing 4.2: Installing the gnumeric prebuilt package

```
# emerge --usepkg --getbinpkg gnumeric
```

More information about emerge's prebuilt package options can be found in the emerge man page:

#### Code Listing 4.3: Reading the emerge man page

```
$ man emerge
```

## 3.e. Fetching Files

### Parallel fetch

When you are emerging a series of packages, Portage can fetch the source files for the next package in the list even while it is compiling another package, thus shortening compile times. To make use of this capability, add "parallel-fetch" to your FEATURES. Note that this is on by default, so you shouldn't need to specifically enable it.

### Userfetch

When Portage is run as root, FEATURES="userfetch" will allow Portage to drop root privileges while fetching package sources. This is a small security improvement.

## 3.f. Pulling Validated Portage Tree Snapshots

As an administrator, you can opt to only update your local Portage tree with a cryptographically validated Portage tree snapshot as released by the Gentoo infrastructure. This ensures that no rogue rsync mirror is adding unwanted code or packages in the tree you are downloading.

To configure Portage, first create a truststore in which you download and accept the keys of the Gentoo Infrastructure responsible for signing the Portage tree snapshots. Of course, if you want to, you can validate this GPG key as per the [proper guidelines](#) (like checking the key fingerprint). You can find the list of GPG keys used by the release engineering team on their [project page](#).

#### Code Listing 6.1: Creating a truststore for Portage

```
# mkdir -p /etc/portage/gpg
# chmod 0700 /etc/portage/gpg
(... Substitute the keys with those mentioned on the release engineering site ...)
# gpg --homedir /etc/portage/gpg --keyserver subkeys.pgp.net --recv-keys 0x239C75C4 0x96D8BF6D
# gpg --homedir /etc/portage/gpg --edit-key 0x239C75C4 trust
# gpg --homedir /etc/portage/gpg --edit-key 0x96D8BF6D trust
```

Next, edit /etc/portage/make.conf and enable support for validating the signed Portage tree snapshots (using FEATURES="webrsync-gpg") and disabling updating the Portage tree using the regular `emerge --sync` method.

#### Code Listing 6.2: Updating Portage for signed tree validation

```
FEATURES="webrsync-gpg"
PORTAGE_GPG_DIR="/etc/portage/gpg"
SYNC=""
```

That's it. Next time you run `emerge-webrsync`, only the snapshots with a valid signature will be expanded on your file system.

## 4. Initscripts

### 4.a. Runlevels

#### Booting your System

When you boot your system, you will notice lots of text floating by. If you pay close attention, you will notice this text is the same every time you reboot your system. The sequence of all these actions is called the *boot sequence* and is (more or less) statically defined.

First, your boot loader will load the kernel image you have defined in the boot loader configuration into memory after which it tells the CPU to run the kernel. When the kernel is loaded and run, it initializes all kernel-specific structures and tasks and starts the `init` process.

This process then makes sure that all filesystems (defined in /etc/fstab) are mounted and ready to be used. Then it executes several scripts located in /etc/init.d, which will start the services you need in order to have a successfully booted system.

Finally, when all scripts are executed, `init` activates the terminals (in most cases just the virtual consoles which are hidden beneath `Alt-F1`, `Alt-F2`, etc.) attaching a special process called `agetty` to it. This process will then make sure you are able to log on through these terminals by running `login`.

#### Init Scripts

Now `init` doesn't just execute the scripts in /etc/init.d randomly. Even more, it doesn't run all scripts in /etc/init.d, only the scripts it is told to execute. It decides which scripts to execute by looking into /etc/runlevels.

First, `init` runs all scripts from /etc/init.d that have symbolic links inside /etc/runlevels/boot. Usually, it will start the scripts in alphabetical order, but some scripts have dependency information in them, telling the system that another script must be run before they can be started.

When all `/etc/runlevels/boot` referenced scripts are executed, `init` continues with running the scripts that have a symbolic link to them in `/etc/runlevels/default`. Again, it will use the alphabetical order to decide what script to run first, unless a script has dependency information in it, in which case the order is changed to provide a valid start-up sequence.

## How Init Works

Of course `init` doesn't decide all that by itself. It needs a configuration file that specifies what actions need to be taken. This configuration file is `/etc/inittab`.

If you remember the boot sequence we have just described, you will remember that `init`'s first action is to mount all filesystems. This is defined in the following line from `/etc/inittab`:

### Code Listing 1.1: The system initialisation line in `/etc/inittab`

```
si::sysinit:/sbin/rc sysinit
```

This line tells `init` that it must run `/sbin/rc sysinit` to initialize the system. The `/sbin/rc` script takes care of the initialisation, so you might say that `init` doesn't do much -- it delegates the task of initialising the system to another process.

Second, `init` executed all scripts that had symbolic links in `/etc/runlevels/boot`. This is defined in the following line:

### Code Listing 1.2: The system initialisation, continued

```
rc::bootwait:/sbin/rc boot
```

Again the `rc` script performs the necessary tasks. Note that the option given to `rc` (*boot*) is the same as the subdirectory of `/etc/runlevels` that is used.

Now `init` checks its configuration file to see what *runlevel* it should run. To decide this, it reads the following line from `/etc/inittab`:

### Code Listing 1.3: The `initdefault` line

```
id:3:initdefault:
```

In this case (which the majority of Gentoo users will use), the *runlevel* id is 3. Using this information, `init` checks what it must run to start *runlevel* 3:

### Code Listing 1.4: The runlevel definitions

```
10:0:wait:/sbin/rc shutdown
11:S1:wait:/sbin/rc single
12:2:wait:/sbin/rc nonetwork
13:3:wait:/sbin/rc default
14:4:wait:/sbin/rc default
15:5:wait:/sbin/rc default
16:6:wait:/sbin/rc reboot
```

The line that defines level 3, again, uses the `rc` script to start the services (now with argument *default*). Again note that the argument of `rc` is the same as the subdirectory from `/etc/runlevels`.

When `rc` has finished, `init` decides what virtual consoles it should activate and what commands need to be run at each console:

### Code Listing 1.5: The virtual consoles definition

```
c1:12345:respawn:/sbin/agetty 38400 tty1 linux
c2:12345:respawn:/sbin/agetty 38400 tty2 linux
c3:12345:respawn:/sbin/agetty 38400 tty3 linux
c4:12345:respawn:/sbin/agetty 38400 tty4 linux
c5:12345:respawn:/sbin/agetty 38400 tty5 linux
c6:12345:respawn:/sbin/agetty 38400 tty6 linux
```

## What is a runlevel?

You have seen that `init` uses a numbering scheme to decide what *runlevel* it should activate. A *runlevel* is a state in which your system is running and contains a collection of scripts (runlevel scripts or *initscripts*) that must be executed when you enter or leave a runlevel.

In Gentoo, there are seven runlevels defined: three internal runlevels, and four user-defined runlevels. The internal runlevels are called *sysinit*, *shutdown* and *reboot* and do exactly what their names imply: initialize the system, powering off the system and rebooting the system.

The user-defined runlevels are those with an accompanying `/etc/runlevels` subdirectory: *boot*, *default*, *nonetwork* and *single*. The *boot* runlevel starts all system-necessary services which all other runlevels use. The remaining three runlevels differ in what services they start: *default* is used for day-to-day operations, *nonetwork* is used in case no network connectivity is required, and *single* is used when you need to fix the system.

## Working with the Init Scripts

The scripts that the `rc` process starts are called *init scripts*. Each script in `/etc/init.d` can be executed with the arguments *start*, *stop*, *restart*, *pause*, *zap*, *status*, *ined*, *iuse*, *needsme*, *usesme* or *broken*.

To start, stop or restart a service (and all depending services), `start`, `stop` and `restart` should be used:

### Code Listing 1.6: Starting Postfix

```
# /etc/init.d/postfix start
```

**Note:** Only the services that *need* the given service are stopped or restarted. The other depending services (those that *use* the service but don't need it) are left untouched.

If you want to stop a service, but not the services that depend on it, you can use the `pause` argument:

### Code Listing 1.7: Stopping Postfix but keep the depending services running

```
# /etc/init.d/postfix pause
```

If you want to see what status a service has (started, stopped, paused, ...) you can use the `status` argument:

```
# /etc/init.d/postfix status
```

If the status information tells you that the service is running, but you know that it is not, then you can reset the status information to "stopped" with the `zap` argument:

```
Code Listing 1.9: Resetting status information for postfix
```

```
# /etc/init.d/postfix zap
```

To also ask what dependencies the service has, you can use `iuse` or `ineed`. With `ineed` you can see the services that are really necessary for the correct functioning of the service. `iuse` on the other hand shows the services that can be used by the service, but are not necessary for the correct functioning.

```
Code Listing 1.10: Requesting a list of all necessary services on which Postfix depends
```

```
# /etc/init.d/postfix ineed
```

Similarly, you can ask what services require the service (`needsme`) or can use it (`usesme`):

```
Code Listing 1.11: Requesting a list of all services that require Postfix
```

```
# /etc/init.d/postfix needsme
```

Finally, you can ask what dependencies the service requires that are missing:

```
Code Listing 1.12: Requesting a list of missing dependencies for Postfix
```

```
# /etc/init.d/postfix broken
```

## 4.b. Working with rc-update

### What is rc-update?

Gentoo's init system uses a dependency-tree to decide what service needs to be started first. As this is a tedious task that we wouldn't want our users to have to do manually, we have created tools that ease the administration of the runlevels and init scripts.

With `rc-update` you can add and remove init scripts to a runlevel. The `rc-update` tool will then automatically ask the `depscan.sh` script to rebuild the dependency tree.

### Adding and Removing Services

You have already added init scripts to the "default" runlevel during the installation of Gentoo. At that time you might not have had a clue what the "default" is for, but now you should. The `rc-update` script requires a second argument that defines the action: `add`, `del` or `show`.

To add or remove an init script, just give `rc-update` the `add` or `del` argument, followed by the init script and the runlevel. For instance:

```
Code Listing 2.1: Removing Postfix from the default runlevel
```

```
# rc-update del postfix default
```

The `rc-update -v show` command will show all the available init scripts and list at which runlevels they will execute:

```
Code Listing 2.2: Receiving init script information
```

```
# rc-update -v show
```

You can also run `rc-update show` (without `-v`) to just view enabled init scripts and their runlevels.

## 4.c. Configuring Services

### Why the Need for Extra Configuration?

Init scripts can be quite complex. It is therefore not really desirable to have the users edit the init script directly, as it would make it more error-prone. It is however important to be able to configure such a service. For instance, you might want to give more options to the service itself.

A second reason to have this configuration outside the init script is to be able to update the init scripts without the fear that your configuration changes will be undone.

### The /etc/conf.d Directory

Gentoo provides an easy way to configure such a service: every init script that can be configured has a file in `/etc/conf.d`. For instance, the `apache2` init script (called `/etc/init.d/apache2`) has a configuration file called `/etc/conf.d/apache2`, which can contain the options you want to give to the Apache 2 server when it is started:

```
Code Listing 3.1: Variable defined in /etc/conf.d/apache2
```

```
APACHE2_OPTS="-D PHP5"
```

Such a configuration file contains variables and variables alone (just like `/etc/portage/make.conf`), making it very easy to configure services. It also allows us to provide more information about the variables (as comments).

## 4.d. Writing Init Scripts

### Do I Have To?

No, writing an init script is usually not necessary as Gentoo provides ready-to-use init scripts for all provided services. However, you might have installed a service without using Portage, in which case you will most likely have to create an init script.

Do not use the init script provided by the service if it isn't explicitly written for Gentoo: Gentoo's init scripts are not compatible with the init scripts used by other distributions!

## Layout

The basic layout of an init script is shown below.

**Code Listing 4.1: Basic layout of an init script**

```
#!/sbin/runscript

depend() {
    (Dependency information)
}

start() {
    (Commands necessary to start the service)
}

stop() {
    (Commands necessary to stop the service)
}
```

Any init script *requires* the `start()` function to be defined. All other sections are optional.

## Dependencies

There are two dependency-alike settings you can define that influence the start-up or sequencing of init scripts: `use` and `need`. Next to these two, there are also two order-influencing methods called `before` and `after`. These last two are no dependencies per se - they do not make the original init script fail if the selected one isn't scheduled to start (or fails to start).

- The `use` settings informs the init system that this script *uses* functionality offered by the selected script, but does not directly depend on it. A good example would be `use logger` or `use dns`. If those services are available, they will be put in good use, but if you do not have a logger or DNS server the services will still work. If the services exist, then they are started before the script that `use`'s them.
- The `need` setting is a hard dependency. It means that the script that is `need`'ing another script will not start before the other script is launched successfully. Also, if that other script is restarted, then this one will be restarted as well.
- When using `before`, then the given script is launched before the selected one *if* the selected one is part of the init level. So an init script `xdm` that defines `before alsasound` will start before the `alsasound` script, but only if `alsasound` is scheduled to start as well in the same init level. If `alsasound` is not scheduled to start too, then this particular setting has no effect and `xdm` will be started when the init system deems it most appropriate.
- Similarly, `after` informs the init system that the given script should be launched after the selected one *if* the selected one is part of the init level. If not, then the setting has no effect and the script will be launched by the init system when it deems it most appropriate.

It should be clear from the above that `need` is the only "true" dependency setting as it affects if the script will be started or not. All the others are merely pointers towards the init system to clarify in which order scripts can be (or should be) launched.

Now, if you look at many of Gentoo's available init scripts, you will notice that some have dependencies on things that are no init scripts. These "things" we call *virtuals*.

A *virtual* dependency is a dependency that a service provides, but that is not provided solely by that service. Your init script can depend on a system logger, but there are many system loggers available (`metalogd`, `syslog-ng`, `sysklogd`, ...). As you cannot `need` every single one of them (no sensible system has all these system loggers installed and running) we made sure that all these services `provide` a virtual dependency.

Let us take a look at the dependency information for the postfix service.

**Code Listing 4.2: Dependency information for Postfix**

```
depend() {
    need net
    use logger dns
    provide mta
}
```

As you can see, the postfix service:

- requires the (virtual) `net` dependency (which is provided by, for instance, `/etc/init.d/net.eth0`)
- uses the (virtual) `logger` dependency (which is provided by, for instance, `/etc/init.d/syslog-ng`)
- uses the (virtual) `dns` dependency (which is provided by, for instance, `/etc/init.d/named`)
- provides the (virtual) `mta` dependency (which is common for all mail servers)

## Controlling the Order

As we described in the previous section, you can tell the init system what order it should use for starting (or stopping) scripts. This ordering is handled both through the dependency settings `use` and `need`, but also through the order settings `before` and `after`. As we have described these earlier already, let's take a look at the Portmap service as an example of such init script.

**Code Listing 4.3: The depend() function in the Portmap service**

```
depend() {
    need net
    before inetd
    before xinetd
}
```

You can also use the `***` glob to catch all services in the same runlevel, although this isn't advisable.

**Code Listing 4.4: Running an init script as first script in the runlevel**



```
depend() {
    before *
```

If your service must write to local disks, it should need `localmount`. If it places anything in `/var/run` such as a pidfile, then it should start after `bootmisc`:

#### Code Listing 4.5: Example `depend()` function

```
depend() {
    need localmount
    after bootmisc
}
```

## Standard Functions

Next to the `depend()` functionality, you also need to define the `start()` function. This one contains all the commands necessary to initialize your service. It is advisable to use the `ebegin` and `end` functions to inform the user about what is happening:

#### Code Listing 4.6: Example `start()` function

```
start() {
    if [ "${RC_CMD}" = "restart" ];
    then
        # Do something in case a restart requires more than stop, start
    fi

    ebegin "Starting my_service"
    start-stop-daemon --start --exec /path/to/my_service \
        --pidfile /path/to/my_pidfile
    end $?
}
```

Both `--exec` and `--pidfile` should be used in start and stop functions. If the service does not create a pidfile, then use `--make-pidfile` if possible, though you should test this to be sure. Otherwise, don't use pidfiles. You can also add `--quiet` to the `start-stop-daemon` options, but this is not recommended unless the service is extremely verbose. Using `--quiet` may hinder debugging if the service fails to start.

Another notable setting used in the above example is to check the contents of the `RC_CMD` variable. Unlike the previous init script system, the newer `openrc` system does not support script-specific restart functionality. Instead, the script needs to check the contents of the `RC_CMD` variable to see if a function (be it `start()` or `stop()`) is called as part of a restart or not.

**Note:** Make sure that `--exec` actually calls a service and not just a shell script that launches services and exits -- that's what the init script is supposed to do.

If you need more examples of the `start()` function, please read the source code of the available init scripts in your `/etc/init.d` directory.

Another function you can define is `stop()`. You are not obliged to define this function though! Our init system is intelligent enough to fill in this function by itself if you use `start-stop-daemon`.

Here is an example of a `stop()` function:

#### Code Listing 4.7: Example `stop()` function

```
stop() {
    ebegin "Stopping my_service"
    start-stop-daemon --stop --exec /path/to/my_service \
        --pidfile /path/to/my_pidfile
    end $?
}
```

If your service runs some other script (for example, bash, python, or perl), and this script later changes names (for example, `foo.py` to `foo`), then you will need to add `--name` to `start-stop-daemon`. You must specify the name that your script will be changed to. In this example, a service starts `foo.py`, which changes names to `foo`:

#### Code Listing 4.8: A service that starts the `foo` script

```
start() {
    ebegin "Starting my_script"
    start-stop-daemon --start --exec /path/to/my_script \
        --pidfile /path/to/my_pidfile --name foo
    end $?
}
```

`start-stop-daemon` has an excellent man page available if you need more information:

#### Code Listing 4.9: Getting the man page for `start-stop-daemon`

```
$ man start-stop-daemon
```

Gentoo's init script syntax is based on the POSIX Shell so you are free to use sh-compatible constructs inside your init script. Keep other constructs, like bash-specific ones, out of the init scripts to ensure that the scripts remain functional regardless of the change Gentoo might do on its init system.

## Adding Custom Options

If you want your init script to support more options than the ones we have already encountered, you should add the option to the `extra_commands` variable, and create a function with the same name as the option. For instance, to support an option called `restartdelay`:

#### Code Listing 4.10: Supporting the `restartdelay` option

```
extra_commands="restartdelay"

restartdelay() {
```

```
stop
sleep 3    # Wait 3 seconds before starting again
start
}
```

**Important:** The function `restart()` cannot be overridden in `openrc!`

## Service Configuration Variables

You don't have to do anything to support a configuration file in `/etc/conf.d`: if your init script is executed, the following files are automatically sourced (i.e. the variables are available to use):

- `/etc/conf.d/<your init script>`
- `/etc/conf.d/basic`
- `/etc/rc.conf`

Also, if your init script provides a virtual dependency (such as `net`), the file associated with that dependency (such as `/etc/conf.d/net`) will be sourced too.

## 4.e. Changing the Runlevel Behaviour

### Who might benefit from this?

Many laptop users know the situation: at home you need to start `net.eth0` while you don't want to start `net.eth0` while you're on the road (as there is no network available). With Gentoo you can alter the runlevel behaviour to your own will.

For instance you can create a second "default" runlevel which you can boot that has other init scripts assigned to it. You can then select at boottime what default runlevel you want to use.

### Using softlevel

First of all, create the runlevel directory for your second "default" runlevel. As an example we create the `offline` runlevel:

#### Code Listing 5.1: Creating a runlevel directory

```
# mkdir /etc/runlevels/offline
```

Add the necessary init scripts to the newly created runlevels. For instance, if you want to have an exact copy of your current `default` runlevel but without `net.eth0`:

#### Code Listing 5.2: Adding the necessary init scripts

```
(Copy all services from default runlevel to offline runlevel)
# cd /etc/runlevels/default
# for service in *; do rc-update add $service offline; done
(Remove unwanted service from offline runlevel)
# rc-update del net.eth0 offline
(Display active services for offline runlevel)
# rc-update show offline
(Partial sample Output)
      acpid | offline
domainname | offline
      local | offline
      net.eth0 |
```

Even though `net.eth0` has been removed from the offline runlevel, `udev` might want to attempt to start any devices it detects and launch the appropriate services, a functionality that is called *hotplugging*. By default, Gentoo does not enable hotplugging.

If you do want to enable hotplugging, but only for a selected set of scripts, use the `rc_hotplug` variable in `/etc/rc.conf`:

#### Code Listing 5.3: Disabling device initiated services in /etc/rc.conf

```
# Allow net.wlan as well as any other service, except those matching net.*
# to be hotplugged
rc_hotplug="net.wlan !net.*"
```

**Note:** For more information on device initiated services, please see the comments inside `/etc/rc.conf`.

Now edit your bootloader configuration and add a new entry for the `offline` runlevel. For instance, in `/boot/grub/grub.conf`:

#### Code Listing 5.4: Adding an entry for the offline runlevel

```
title Gentoo Linux Offline Usage
  root (hd0,0)
  kernel (hd0,0)/kernel-2.4.25 root=/dev/hda3 softlevel=offline
```

Voilà, you're all set now. If you boot your system and select the newly added entry at boot, the `offline` runlevel will be used instead of the `default` one.

### Using bootlevel

Using `bootlevel` is completely analogous to `softlevel`. The only difference here is that you define a second "boot" runlevel instead of a second "default" runlevel.

## 5. Environment Variables

### 5.a. Environment Variables?

#### What they are

An environment variable is a named object that contains information used by one or more applications. Many users (and especially those new to Linux) find this a bit weird or unmanageable. However, this is a mistake: by using environment variables one can easily change a configuration setting for one or more applications.

Important Examples

The following table lists a number of variables used by a Linux system and describes their use. Example values are presented after the table.

Variable	Description
PATH	This variable contains a colon-separated list of directories in which your system looks for executable files. If you enter a name of an executable (such as <code>ls</code> , <code>rc-update</code> or <code>emerge</code> ) but this executable is not located in a listed directory, your system will not execute it (unless you enter the full path as command, such as <code>/bin/ls</code> ).
ROOTPATH	This variable has the same function as <code>PATH</code> , but this one only lists the directories that should be checked when the root-user enters a command.
LDPATH	This variable contains a colon-separated list of directories in which the dynamical linker searches through to find a library.
MANPATH	This variable contains a colon-separated list of directories in which the <code>man</code> command searches for the man pages.
INFODIR	This variable contains a colon-separated list of directories in which the <code>info</code> command searches for the info pages.
PAGER	This variable contains the path to the program used to list the contents of files through (such as <code>less</code> or <code>more</code> ).
EDITOR	This variable contains the path to the program used to change the contents of files with (such as <code>nano</code> or <code>vi</code> ).
KDEDIRS	This variable contains a colon-separated list of directories which contain KDE-specific material.
CONFIG_PROTECT	This variable contains a space-delimited list of directories which should be protected by Portage during updates.
CONFIG_PROTECT_MASK	This variable contains a space-delimited list of directories which should not be protected by Portage during updates.

Below you will find an example definition of all these variables:

```
Code Listing 2.2: Example definitions

PATH="/bin:/usr/bin:/usr/local/bin:/opt/bin:/usr/games/bin"
ROOTPATH="/sbin:/bin:/usr/sbin:/usr/bin:/usr/local/sbin:/usr/local/bin"
LDPATH="/lib:/usr/lib:/usr/local/lib:/usr/lib/gcc-lib/i686-pc-linux-gnu/3.2.3"
MANPATH="/usr/share/man:/usr/local/share/man"
INFODIR="/usr/share/info:/usr/local/share/info"
PAGER="/usr/bin/less"
EDITOR="/usr/bin/vim"
KDEDIRS="/usr"
CONFIG_PROTECT="/usr/X11R6/lib/X11/xkb /opt/tomcat/conf \
                /usr/kde/3.1/share/config /usr/share/texmf/tex/generic/config/ \
                /usr/share/texmf/tex/latex/config/ /usr/share/config"
CONFIG_PROTECT_MASK="/etc/gconf"
```

5.b. Defining Variables Globally

The /etc/env.d Directory

To centralise the definitions of these variables, Gentoo introduced the `/etc/env.d` directory. Inside this directory you will find a number of files, such as `00basic`, `05gcc`, etc. which contain the variables needed by the application mentioned in their name.

For instance, when you installed `gcc`, a file called `05gcc` was created by the ebuild which contains the definitions of the following variables:

```
Code Listing 2.1: /etc/env.d/05gcc

PATH="/usr/i686-pc-linux-gnu/gcc-bin/3.2"
ROOTPATH="/usr/i686-pc-linux-gnu/gcc-bin/3.2"
MANPATH="/usr/share/gcc-data/i686-pc-linux-gnu/3.2/man"
INFOPATH="/usr/share/gcc-data/i686-pc-linux-gnu/3.2/info"
CC="gcc"
CXX="g++"
LDPATH="/usr/lib/gcc-lib/i686-pc-linux-gnu/3.2.3"
```

Other distributions tell you to change or add such environment variable definitions in `/etc/profile` or other locations. Gentoo on the other hand makes it easy for you (and for Portage) to maintain and manage the environment variables without having to pay attention to the numerous files that can contain environment variables.

For instance, when `gcc` is updated, the `/etc/env.d/05gcc` file is updated too without requesting any user-interaction.

This not only benefits Portage, but also you, as user. Occasionally you might be asked to set a certain environment variable system-wide. As an example we take the `http_proxy` variable. Instead of messing about with `/etc/profile`, you can now just create a file (`/etc/env.d/99local`) and enter your definition(s) in it:

```
Code Listing 2.4: /etc/env.d/99local

http_proxy="proxy.server.com:8080"
```

By using the same file for all your variables, you have a quick overview on the variables you have defined yourself.

The env-update Script

Several files in `/etc/env.d` define the `PATH` variable. This is not a mistake: when you run `env-update`, it will append the several definitions before it updates the environment variables, thereby making it easy for packages (or users) to add their own environment variable settings without interfering with the already existing values.

The `env-update` script will append the values in the alphabetical order of the `/etc/env.d` files. The file names must begin with two decimal digits.

```
Code Listing 2.3: Update order used by env-update

      00basic      99kde-env      99local
+-----+-----+-----+
PATH="/bin:/usr/bin:/usr/kde/3.2/bin:/usr/local/bin"
```

The concatenation of variables does not always happen, only with the following variables: `ADA_INCLUDE_PATH`, `ADA_OBJECTS_PATH`, `CLASSPATH`, `KDEDIRS`, `PATH`, `LDPATH`, `MANPATH`, `INFODIR`, `INFOPATH`, `ROOTPATH`, `CONFIG_PROTECT`, `CONFIG_PROTECT_MASK`, `PRELINK_PATH`, `PRELINK_PATH_MASK`, `PKG_CONFIG_PATH` and `PYTHONPATH`. For all other variables the latest defined value (in alphabetical order of the files in `/etc/env.d`) is used.

You can add more variables into this list of concatenate-variables by adding the variable name to either `COLON_SEPARATED` or `SPACE_SEPARATED` variables (also inside an `env.d` file).

When you run `env-update`, the script will create all environment variables and place them in `/etc/profile.env` (which is used by `/etc/profile`). It will also extract the information from the `LDPATH` variable and use that to create `/etc/ld.so.conf`. After this, it will run `ldconfig` to recreate the `/etc/ld.so.cache` file used by the dynamical linker.

If you want to notice the effect of `env-update` immediately after you run it, execute the following command to update your environment. Users who have installed Gentoo themselves will probably remember this from the installation instructions:

#### Code Listing 2.4: Updating the environment

```
# env-update && source /etc/profile
```

**Note:** The above command only updates the variables in your current terminal, *new* consoles, and their children. Thus, if you are working in X11, you will need to either type `source /etc/profile` in every new terminal you open or restart X so that all new terminals source the new variables. If you use a login manager, become root and type `/etc/init.d/xdm restart`. If not, you will need to logout and log back in for X to spawn children with the new variable values.

**Important:** You cannot use shell variables when defining other variables. This means things like `FOO="$BAR"` (where `$BAR` is another variable) are forbidden.

## 5.c. Defining Variables Locally

### User Specific

You do not always want to define an environment variable globally. For instance, you might want to add `/home/my_user/bin` and the current working directory (the directory you are in) to the `PATH` variable but don't want all other users on your system to have that in their `PATH` too. If you want to define an environment variable locally, you should use `~/.bashrc` or `~/.bash_profile`:

#### Code Listing 3.1: Extending PATH for local usage in ~/.bashrc

(A colon followed by no directory is treated as the current working directory)

```
PATH="${PATH}:/home/my_user/bin:"
```

When you relogin, your `PATH` variable will be updated.

### Session Specific

Sometimes even stricter definitions are requested. You might want to be able to use binaries from a temporary directory you created without using the path to the binaries themselves or editing `~/.bashrc` for the short time you need it.

In this case, you can just define the `PATH` variable in your current session by using the `export` command. As long as you don't log out, the `PATH` variable will be using the temporary settings.

#### Code Listing 3.2: Defining a session-specific environment variable

```
# export PATH="${PATH}:/home/my_user/tmp/usr/bin"
```

## C. Working with Portage

### 1. Files and Directories

#### 1.a. Portage Files

##### Configuration Directives

Portage comes with a default configuration stored in `/etc/make.globals`. When you take a look at it, you'll notice that all Portage configuration is handled through variables. What variables Portage listens to and what they mean are described later.

Since many configuration directives differ between architectures, Portage also has default configuration files which are part of your profile. Your profile is pointed to by the `/etc/portage/make.profile` symlink; Portage' configurations are set in the `make.defaults` files of your profile and all parent profiles. We'll explain more about profiles and the `/etc/portage/make.profile` directory later on.

If you're planning on changing a configuration variable, *don't* alter `/etc/make.globals` or `make.defaults`. Instead use `/etc/portage/make.conf` which has precedence over the previous files. You'll also find a `/usr/share/portage/config/make.conf.example`. As the name implies, this is merely an example file - Portage does not read in this file.

You can also define a Portage configuration variable as an environment variable, but we don't recommend this.

##### Profile-Specific Information

We've already encountered the `/etc/portage/make.profile` directory. Well, this isn't exactly a directory but a symbolic link to a profile, by default one inside `/usr/portage/profiles` although you can create your own profiles elsewhere and point to them. The profile this symlink points to is the profile to which your system adheres.

A profile contains architecture-specific information for Portage, such as a list of packages that belong to the system corresponding with that profile, a list of packages that don't work (or are masked-out) for that profile, etc.

##### User-Specific Configuration

When you need to override Portage's behaviour regarding the installation of software, you will end up editing files within `/etc/portage`. You are *highly recommended* to use files within `/etc/portage` and *highly discouraged* to override the behaviour through environment variables!

Within `/etc/portage` you can create the following files:

- `package.mask` which lists the packages you never want Portage to install
- `package.unmask` which lists the packages you want to be able to install even though the Gentoo developers highly discourage you from emerging them
- `package.accept_keywords` which lists the packages you want to be able to install even though the package hasn't been found suitable for your system or architecture (yet)
- `package.use` which lists the USE flags you want to use for certain packages without having the entire system use those USE flags

These don't have to be files; they can also be directories that contain one file per package. More information about the `/etc/portage` directory and a full list of possible files you can create can be found in the Portage man page:

#### Code Listing 1.1: Reading the Portage man page

```
$ man portage
```

### Changing Portage File & Directory Locations

The previously mentioned configuration files cannot be stored elsewhere - Portage will always look for those configuration files at those exact locations. However, Portage uses many other locations for various purposes: build directory, source code storage, Portage tree location, ...

All these purposes have well-known default locations but can be altered to your own taste through `/etc/portage/make.conf`. The rest of this chapter explains what special-purpose locations Portage uses and how to alter their placement on your filesystem.

This document isn't meant to be used as a reference though. If you need 100% coverage, please consult the Portage and `make.conf` man pages:

#### Code Listing 1.2: Reading the Portage and make.conf man pages

```
$ man portage
$ man make.conf
```

## 1.b. Storing Files

### The Portage Tree

The Portage tree default location is `/usr/portage`. This is defined by the `PORTDIR` variable. When you store the Portage tree elsewhere (by altering this variable), don't forget to change the `/etc/portage/make.profile` symbolic link accordingly.

If you alter the `PORTDIR` variable, you might want to alter the following variables as well since they will not notice the `PORTDIR` change. This is due to how Portage handles variables: `PKGDIR`, `DISTDIR`, `RPMDIR`.

### Prebuilt Binaries

Even though Portage doesn't use prebuilt binaries by default, it has extensive support for them. When you ask Portage to work with prebuilt packages, it will look for them in `/usr/portage/packages`. This location is defined by the `PKGDIR` variable.

### Source Code

Application source code is stored in `/usr/portage/distfiles` by default. This location is defined by the `DISTDIR` variable.

### Portage Database

Portage stores the state of your system (what packages are installed, what files belong to which package, ...) in `/var/db/pkg`. Do *not* alter these files manually! It might break Portage's knowledge of your system.

### Portage Cache

The Portage cache (with modification times, virtuals, dependency tree information, ...) is stored in `/var/cache/edb`. This location really is a cache: you can clean it if you are not running any portage-related application at that moment.

## 1.c. Building Software

### Temporary Portage Files

Portage's temporary files are stored in `/var/tmp` by default. This is defined by the `PORTAGE_TMPDIR` variable.

If you alter the `PORTAGE_TMPDIR` variable, you might want to alter the following variables as well since they will not notice the `PORTAGE_TMPDIR` change. This is due to how Portage handles variables: `BUILD_PREFIX`.

### Building Directory

Portage creates specific build directories for each package it emerges inside `/var/tmp/portage`. This location is defined by the `BUILD_PREFIX` variable.

### Live Filesystem Location

By default Portage installs all files on the current filesystem (`/`), but you can change this by setting the `ROOT` environment variable. This is useful when you want to create new build images.

## 1.d. Logging Features

### Ebuild Logging

Portage can create per-rebuild logfiles, but only when the `PORT_LOGDIR` variable is set to a location that is writable by Portage (the portage user). By default this variable is unset. If you don't set `PORT_LOGDIR`, then you won't receive any build logs with the current logging system, though you may receive some logs from the new [elog](#). If you do have `PORT_LOGDIR` defined and you use `elog`, you will receive build logs and any logs saved by `elog`, as explained below.

Portage offers fine-grained control over logging through the use of [elog](#):

- **PORTAGE\_ELOG\_CLASSES**: This is where you set what kinds of messages to be logged. You can use any space-separated combination of [info](#), [warn](#), [error](#), [log](#), and [qa](#).
  - [info](#): Logs "einfo" messages printed by an ebuild
  - [warn](#): Logs "ewarn" messages printed by an ebuild
  - [error](#): Logs "error" messages printed by an ebuild
  - [log](#): Logs the "elog" messages found in some ebuilds
  - [qa](#): Logs the "QA Notice" messages printed by an ebuild
- **PORTAGE\_ELOG\_SYSTEM**: This selects the module(s) to process the log messages. If left empty, logging is disabled. You can use any space-separated combination of [save](#), [custom](#), [syslog](#), [mail](#), [save\\_summary](#), and [mail\\_summary](#). You must select at least one module in order to use elog.
  - [save](#): This saves one log per package in `$PORT_LOGDIR/elog`, or `/var/log/portage/elog` if `$PORT_LOGDIR` is not defined.
  - [custom](#): Passes all messages to a user-defined command in `$PORTAGE_ELOG_COMMAND`; this will be discussed later.
  - [syslog](#): Sends all messages to the installed system logger.
  - [mail](#): Passes all messages to a user-defined mailserver in `$PORTAGE_ELOG_MAILURI`; this will be discussed later. The mail features of elog require `>=portage-2.1.1`.
  - [save\\_summary](#): Similar to [save](#), but it merges all messages in `$PORT_LOGDIR/elog/summary.log`, or `/var/log/portage/elog/summary.log` if `$PORT_LOGDIR` is not defined.
  - [mail\\_summary](#): Similar to [mail](#), but it sends all messages in a single mail when emerge exits.
- **PORTAGE\_ELOG\_COMMAND**: This is only used when the [custom](#) module is enabled. Here is where you specify a command to process log messages. Note that you can make use of two variables: `${PACKAGE}` is the package name and version, while `${LOGFILE}` is the absolute path to the logfile. Here's one possible usage:
  - `PORTAGE_ELOG_COMMAND="/path/to/logger -p '${PACKAGE}' -f '${LOGFILE}'"`
- **PORTAGE\_ELOG\_MAILURI**: This contains settings for the [mail](#) module such as address, user, password, mailserver, and port number. The default setting is "root@localhost localhost".
- Here's an example for an smtp server that requires username and password-based authentication on a particular port (the default is port 25):
  - `PORTAGE_ELOG_MAILURI="user@some.domain username:password@smtp.some.domain:995"`
- **PORTAGE\_ELOG\_MAILFROM**: Allows you to set the "from" address of log mails; defaults to "portage" if unset.
- **PORTAGE\_ELOG\_MAILSUBJECT**: Allows you to create a subject line for log mails. Note that you can make use of two variables: `${PACKAGE}` will display the package name and version, while `${HOST}` is the fully qualified domain name of the host Portage is running on.
- Here's one possible use:
  - `PORTAGE_ELOG_MAILSUBJECT="package ${PACKAGE} was merged on ${HOST} with some messages"`

**Important:** If you used [enotice](#) with Portage-2.0.\*, you must completely remove enotice, as it is incompatible with elog.

## 2. Configuring through Variables

### 2.a. Portage Configuration

As noted previously, Portage is configurable through many variables which you should define in `/etc/portage/make.conf`. Please refer to the `make.conf` man page for more and complete information:

#### Code Listing 1.1: Reading the make.conf man page

```
$ man make.conf
```

### 2.b. Build-specific Options

#### Configure and Compiler Options

When Portage builds applications, it passes the contents of the following variables to the compiler and configure script:

- **CFLAGS** & **CXXFLAGS** define the desired compiler flags for C and C++ compiling.
- **CHOST** defines the build host information for the application's configure script
- **MAKEOPTS** is passed to the [make](#) command and is usually set to define the amount of parallelism used during the compilation. More information about the make options can be found in the [make](#) man page.

The **USE** variable is also used during configure and compilations but has been explained in great detail in previous chapters.

#### Merge Options

When Portage has merged a newer version of a certain software title, it will remove the obsoleted files of the older version from your system. Portage gives the user a 5 second delay before unmerging the older version. These 5 seconds are defined by the **CLEAN\_DELAY** variable.

You can tell [emerge](#) to use certain options every time it is run by setting **EMERGE\_DEFAULT\_OPTS**. Some useful options would be `--ask`, `--verbose`, `--tree`, and so on.

### 6.c. Configuration File Protection

#### Portage's Protected Locations

Portage overwrites files provided by newer versions of a software title if the files aren't stored in a *protected* location. These protected locations are defined by the **CONFIG\_PROTECT** variable and are generally configuration file locations. The directory listing is space-delimited.



A file that would be written in such a protected location is renamed and the user is warned about the presence of a newer version of the (presumable) configuration file.

You can find out about the current CONFIG\_PROTECT setting from the `emerge --info` output:

#### Code Listing 3.1: Getting the CONFIG\_PROTECT setting

```
$ emerge --info | grep 'CONFIG_PROTECT='
```

More information about Portage's Configuration File Protection is available in the CONFIGURATION FILES section of the `emerge` manpage:

#### Code Listing 3.2: More information about Configuration File Protection

```
$ man emerge
```

## Excluding Directories

To 'unprotect' certain subdirectories of protected locations you can use the CONFIG\_PROTECT\_MASK variable.

## 2.d. Download Options

### Server Locations

When the requested information or data is not available on your system, Portage will retrieve it from the Internet. The server locations for the various information and data channels are defined by the following variables:

- GENTOO\_MIRRORS defines a list of server locations which contain source code (distfiles)
- PORTAGE\_BINHOST defines a particular server location containing prebuilt packages for your system

A third setting involves the location of the rsync server which you use when you update your Portage tree:

- SYNC defines a particular server which Portage uses to fetch the Portage tree from

The GENTOO\_MIRRORS and SYNC variables can be set automatically through the `mirrorselect` application. You need to `emerge mirrorselect` first before you can use it. For more information, see mirrorselect's online help:

#### Code Listing 4.1: More information about mirrorselect

```
# mirrorselect --help
```

If your environment requires you to use a proxy server, you can use the `http_proxy`, `ftp_proxy` and `RSYNC_PROXY` variables to declare a proxy server.

## Fetch Commands

When Portage needs to fetch source code, it uses `wget` by default. You can change this through the FETCHCOMMAND variable.

Portage is able to resume partially downloaded source code. It uses `wget` by default, but this can be altered through the RESUMECOMMAND variable.

Make sure that your FETCHCOMMAND and RESUMECOMMAND stores the source code in the correct location. Inside the variables you should use `\${URI}` and `\${DISTDIR}` to point to the source code location and distfiles location respectively.

You can also define protocol-specific handlers with `FETCHCOMMAND_HTTP`, `FETCHCOMMAND_FTP`, `RESUMECOMMAND_HTTP`, `RESUMECOMMAND_FTP`, and so on.

## Rsync Settings

You cannot alter the rsync command used by Portage to update the Portage tree, but you can set some variables related to the rsync command:

- PORTAGE\_RSYNC\_OPTS sets a number of default variables used during sync, each space-separated. These shouldn't be changed unless you know *exactly* what you're doing. Note that certain absolutely required options will always be used even if PORTAGE\_RSYNC\_OPTS is empty.
- PORTAGE\_RSYNC\_EXTRA\_OPTS can be used to set additional options when syncing. Each option should be space separated.
  - `--timeout=<number>`: This defines the number of seconds an rsync connection can idle before rsync sees the connection as timed-out. This variable defaults to 180 but dialup users or individuals with slow computers might want to set this to 300 or higher.
  - `--exclude-from=/etc/portage/rsync_excludes`: This points to a file listing the packages and/or categories rsync should ignore during the update process. In this case, it points to `/etc/portage/rsync_excludes`. Please read [Using a Portage Tree Subset](#) for the syntax of this file.
  - `--quiet`: Reduces output to the screen
  - `--verbose`: Prints a complete filelist
  - `--progress`: Displays a progress meter for each file
- PORTAGE\_RSYNC\_RETRIES defines how many times rsync should try connecting to the mirror pointed to by the SYNC variable before bailing out. This variable defaults to 3.

For more information on these options and others, please read `man rsync`.

## 2.e. Gentoo Configuration

### Branch Selection

You can change your default branch with the ACCEPT\_KEYWORDS variable. It defaults to your architecture's stable branch. More information on Gentoo's branches can be found in the next chapter.

## Portage Features

You can activate certain Portage features through the FEATURES variable. The Portage Features have been discussed in previous chapters, such as [Portage Features](#).

## 2.f. Portage Behaviour

### Resource Management

With the PORTAGE\_NICENESS variable you can augment or reduce the nice value Portage runs with. The PORTAGE\_NICENESS value is *added* to the current nice value.

For more information about nice values, see the nice man page:

#### Code Listing 6.1: More information about nice

```
$ man nice
```

### Output Behaviour

The NOCOLOR, which defaults to "false", defines if Portage should disable the use of coloured output.

## 3. Mixing Software Branches

### 2.a. Using One Branch

#### The Stable Branch

The ACCEPT\_KEYWORDS variable defines what software branch you use on your system. It defaults to the stable software branch for your architecture, for instance **x86**.

We recommend that you only use the stable branch. However, if you don't care about stability this much and you want to help out Gentoo by submitting bugreports to <http://bugs.gentoo.org>, read on.

#### The Testing Branch

If you want to use more recent software, you can consider using the testing branch instead. To have Portage use the testing branch, add a `~` in front of your architecture.

The testing branch is exactly what it says - *Testing*. If a package is in testing, it means that the developers feel that it is functional but has not been thoroughly tested. You could very well be the first to discover a bug in the package in which case you could file a [bugreport](#) to let the developers know about it.

Beware though, you might notice stability issues, imperfect package handling (for instance wrong/missing dependencies), too frequent updates (resulting in lots of building) or broken packages. If you do not know how Gentoo works and how to solve problems, we recommend that you stick with the stable and tested branch.

For example, to select the testing branch for the x86 architecture, edit `/etc/portage/make.conf` and set:

#### Code Listing 1.1: Setting the ACCEPT\_KEYWORDS variable

```
ACCEPT_KEYWORDS="~x86"
```

If you update your system now, you will find out that *lots* of packages will be updated. Mind you though: when you have updated your system to use the testing branch there is usually no easy way back to the stable, official branch (except for using backups of course).

### 3.b. Mixing Stable with Testing

#### The package.accept\_keywords location

You can ask Portage to allow the testing branch for particular packages but use the stable branch for the rest of the system. To achieve this, add the package category and name you want to use the testing branch of in `/etc/portage/package.accept_keywords`. You can also create a directory (with the same name) and list the package in the files under that directory. For instance, to use the testing branch for **gnumeric**:

#### Code Listing 2.1: /etc/portage/package.accept\_keywords setting for gnumeric

```
app-office/gnumeric
```

### Test Particular Versions

If you want to use a specific software version from the testing branch but you don't want Portage to use the testing branch for subsequent versions, you can add in the version in the `package.accept_keywords` location. In this case you *must* use the `=` operator. You can also enter a version range using the `<=`, `<`, `>` or `>=` operators.

In any case, if you add version information, you *must* use an operator. If you leave out version information, you *cannot* use an operator.

In the following example we ask Portage to accept gnumeric-1.2.13:

#### Code Listing 2.2: Enabling a particular gnumeric test version

```
=app-office/gnumeric-1.2.13
```

## 10.c. Using Masked Packages

### The package.unmask location

**Important:** The Gentoo developers do **not** support the use of this location. Please exercise due caution when doing so. Support requests related to `package.unmask` and/or `package.mask` will not be answered. You have been warned.

When a package has been masked by the Gentoo developers and you still want to use it despite the reason mentioned in the `package.mask` file (situated in `/usr/portage/profiles` by default), add the desired version (usually this will be the exact same line from `profiles`) in the `/etc/portage/package.unmask` file (or in a file in that directory if it is a directory).

For instance, if `=net-mail/hotwayd-0.8` is masked, you can unmask it by adding the exact same line in the `package.unmask` location:

#### Code Listing 3.1: `/etc/portage/package.unmask`

```
=net-mail/hotwayd-0.8
```

**Note:** If an entry in `/usr/portage/profiles/package.mask` contains a range of package versions, you will need to unmask only the version(s) you actually want. Please read the [previous section](#) to learn how to specify versions in `package.unmask`.

### The `package.mask` location

When you don't want Portage to take a certain package or a specific version of a package into account you can mask it yourself by adding an appropriate line to the `/etc/portage/package.mask` location (either in that file or in a file in this directory).

For instance, if you don't want Portage to install newer kernel sources than `gentoo-sources-2.6.8.1`, you add the following line at the `package.mask` location:

#### Code Listing 3.2: `/etc/portage/package.mask` example

```
>sys-kernel/gentoo-sources-2.6.8.1
```

## 4. Additional Portage Tools

### 4.a. `dispatch-conf`

`dispatch-conf` is a tool that aids in merging the `._cfg0000_<name>` files. `._cfg0000_<name>` files are generated by Portage when it wants to overwrite a file in a directory protected by the `CONFIG_PROTECT` variable.

With `dispatch-conf`, you are able to merge updates to your configuration files while keeping track of all changes. `dispatch-conf` stores the differences between the configuration files as patches or by using the RCS revision system. This means that if you make a mistake when updating a config file, you can revert to the previous version of your config file at any time.

When using `dispatch-conf`, you can ask to keep the configuration file as-is, use the new configuration file, edit the current one or merge the changes interactively. `dispatch-conf` also has some nice additional features:

- Automatically merge configuration file updates that only contain updates to comments
- Automatically merge configuration files which only differ in the amount of whitespace

Make certain you edit `/etc/dispatch-conf.conf` first and create the directory referenced by the `archive-dir` variable.

#### Code Listing 1.1: Running `dispatch-conf`

```
# dispatch-conf
```

When running `dispatch-conf`, you'll be taken through each changed config file, one at a time. Press `u` to update (replace) the current config file with the new one and continue to the next file. Press `z` to zap (delete) the new config file and continue to the next file. Once all config files have been taken care of, `dispatch-conf` will exit. You can also press `q` to exit any time.

For more information, check out the `dispatch-conf` man page. It tells you how to interactively merge current and new config files, edit new config files, examine differences between files, and more.

#### Code Listing 1.2: Reading the `dispatch-conf` man page

```
$ man dispatch-conf
```

### 4.b. `etc-update`

You can also use `etc-update` to merge config files. It's not as simple to use as `dispatch-conf`, nor as featureful, but it does provide an interactive merging setup and can also auto-merge trivial changes.

However, unlike `dispatch-conf`, `etc-update` does *not* preserve the old versions of your config files. Once you update the file, the old version is gone forever! So be very careful, as using `etc-update` is *significantly* less safe than using `dispatch-conf`.

#### Code Listing 2.1: Running `etc-update`

```
# etc-update
```

After merging the straightforward changes, you will be prompted with a list of protected files that have an update waiting. At the bottom you are greeted by the possible options:

#### Code Listing 2.2: `etc-update` options

```
Please select a file to edit by entering the corresponding number.
    (-1 to exit) (-3 to auto merge all remaining files)
    (-5 to auto-merge AND not use 'mv -i'):
```

If you enter `-1`, `etc-update` will exit and discontinue any further changes. If you enter `-3` or `-5`, *all* listed configuration files will be overwritten with the newer versions. It is therefore very important to first select the configuration files that should not be automatically updated. This is simply a matter of entering the number listed to the left of that configuration file.

As an example, we select the configuration file `/etc/pear.conf`:

#### Code Listing 2.3: Updating a specific configuration file

```
Beginning of differences between /etc/pear.conf and /etc/._cfg0000_pear.conf
[...]
```

End of differences between `/etc/pear.conf` and `/etc/._cfg0000_pear.conf`

- 1) Replace original with update
- 2) Delete update, keeping original as is
- 3) Interactively merge original with update
- 4) Show differences again

You can now see the differences between the two files. If you believe that the updated configuration file can be used without problems, enter [1](#). If you believe that the updated configuration file isn't necessary, or doesn't provide any new or useful information, enter [2](#). If you want to interactively update your current configuration file, enter [3](#).

There is no point in further elaborating the interactive merging here. For completeness sake, we will list the possible commands you can use while you are interactively merging the two files. You are greeted with two lines (the original one, and the proposed new one) and a prompt at which you can enter one of the following commands:

#### Code Listing 2.4: Commands available for the interactive merging

```
ed:    Edit then use both versions, each decorated with a header.
eb:    Edit then use both versions.
el:    Edit then use the left version.
er:    Edit then use the right version.
e:     Edit a new version.
l:     Use the left version.
r:     Use the right version.
s:     Silently include common lines.
v:     Verbosely include common lines.
q:     Quit.
```

When you have finished updating the important configuration files, you can now automatically update all the other configuration files. `etc-update` will exit if it doesn't find any more updateable configuration files.

### 4.c. quickpkg

With `quickpkg` you can create archives of the packages that are already merged on your system. These archives can be used as prebuilt packages. Running `quickpkg` is straightforward: just add the names of the packages you want to archive.

For instance, to archive `curl`, `orage`, and `procps`:

#### Code Listing 3.1: Example quickpkg usage

```
# quickpkg curl orage procps
```

The prebuilt packages will be stored in `$PKGDIR (/usr/portage/packages/` by default). These packages are placed in `$PKGDIR/<category>`.

## 5. Diverting from the Official Tree

### 5.a. Using a Portage Tree Subset

#### Excluding Packages/Categories

You can selectively update certain categories/packages and ignore the other categories/packages. We achieve this by having `rsync` exclude categories/packages during the `emerge --sync` step.

You need to define the name of the file that contains the exclude patterns in the `PORTAGE_RSYNC_EXTRA_OPTS` variable in your `/etc/portage/make.conf`.

#### Code Listing 1.1: Defining the exclude file in /etc/portage/make.conf

```
PORTAGE_RSYNC_EXTRA_OPTS="--exclude-from=/etc/portage/rsync_excludes"
```

#### Code Listing 1.2: Excluding all games in /etc/portage/rsync\_excludes

```
games-*/*
```

Note however that this may lead to dependency issues since new, allowed packages might depend on new but excluded packages.

### 5.b. Adding Unofficial Ebuilds

#### Defining a Portage Overlay Directory

You can ask Portage to use ebuilds that are not officially available through the Portage tree. Create a new directory (for instance `/usr/local/portage`) in which you store the 3rd-party ebuilds. Use the same directory structure as the official Portage tree!

Then define `PORTDIR_OVERLAY` in `/etc/portage/make.conf` and have it point to the previously defined directory. When you use Portage now, it will take those ebuilds into account as well without removing/overwriting those ebuilds the next time you run `emerge --sync`.

#### Working with Several Overlays

For the powerusers who develop on several overlays, test packages before they hit the Portage tree or just want to use unofficial ebuilds from various sources, the `app-portage/layman` package brings you `layman`, a tool to help you keep the overlay repositories up to date.

First install and configure `layman` as shown in the [Overlays Users' Guide](#), and add your desired repositories with `layman -a <overlay-name>`.

Suppose you have two repositories called `java` (for the in-development java ebuilds) and `entapps` (for the applications developed in-house for your enterprise). You can update those repositories with the following command:

#### Code Listing 2.1: Using layman to update all repositories

```
# layman -S
```

For more information on working with overlays, please read [man layman](#) and the [layman/overlay users' guide](#).

## 5.c. Non-Portage Maintained Software

### Using Portage with Self-Maintained Software

In some cases you want to configure, install and maintain software yourself without having Portage automate the process for you, even though Portage can provide the software titles. Known cases are kernel sources and nvidia drivers. You can configure Portage so it knows that a certain package is manually installed on your system. This process is called *injecting* and supported by Portage through the `/etc/portage/profile/package.provided` file.

For instance, if you want to inform Portage about [gentoo-sources-2.6.11.6](#) which you've installed manually, add the following line to `/etc/portage/profile/package.provided`:

#### Code Listing 3.1: Example line for package.provided

```
sys-kernel/gentoo-sources-2.6.11.6
```

## 6. Advanced Portage Features

### 6.a. Introduction

For most users, the information received thus far is sufficient for all their Linux operations. But Portage is capable of much more; many of its features are for advanced users or only applicable in specific corner cases. Still, that would not be an excuse not to document them.

Of course, with lots of flexibility comes a huge list of potential cases. It will not be possible to document them all here. Instead, we hope to focus on some generic issues which you can then bend to fit your own needs. If you have need for more specific tweaks and tips, you might find them on the [Gentoo Wiki](#) instead.

Most, if not all of these additional features can be easily found by digging through the manual pages that portage provides:

#### Code Listing 1.1: Reading up on portage man pages

```
$ man portage
$ man make.conf
```

Finally, know that these are advanced features which, if not worked with correctly, can make debugging and troubleshooting very difficult. Make sure you mention these if you think you hit a bug and want to open a bugreport.

### 6.b. Per-Package Environment Variables

#### Using /etc/portage/env

By default, package builds will use the environment variables defined in `/etc/portage/make.conf`, such as [CFLAGS](#), [MAKEOPTS](#) and more. In some cases though, you might want to provide different variables for specific packages. To do so, Portage supports the use of `/etc/portage/env` and `/etc/portage/package.env`.

The `/etc/portage/package.env` file contains the list of packages for which you want deviating variables as well as a specific identifier that tells Portage which changes you want. The identifier name you pick yourself, Portage will look for the variables in the `/etc/portage/env/<identifier>` file.

#### Example: Using debugging for specific packages

As an example, we enable debugging for the `media-video/mplayer` package.

First of all, we set the debugging variables in a file called `/etc/portage/env/debug-cflags`. The name is arbitrarily chosen, but of course reflects the reason of the deviation to make it more obvious later why a deviation was put in.

#### Code Listing 2.1: /etc/portage/env/debug-cflags content

```
CFLAGS="-O2 -ggdb -pipe"
FEATURES="${FEATURES} nostrip"
```

Next, we tag the `media-video/mplayer` package to use this content:

#### Code Listing 2.2: /etc/portage/package.env content

```
media-video/mplayer debug-cflags
```

## 6.c. Hooking In the Emerge Process

### Using /etc/portage/bashrc and affiliated files

When Portage works with ebuilds, it uses a bash environment in which it calls the various build functions (like `src_prepare`, `src_configure`, `pkg_postinst`, etc.). But Portage also allows you to set up a bash environment yourself.

The advantage of using your own bash environment is that you can hook in the emerge process during each step it performs. This can be done for every emerge (through `/etc/portage/bashrc`) or by using per-package environments (through `/etc/portage/env` as discussed earlier).

To hook in the process, the bash environment can listen to the variables [EBUILD\\_PHASE](#), [CATEGORY](#) as well as the variables that are always available during ebuild development (such as [P](#), [PF](#), ...). Based on the values of these variables, you can then execute additional steps.

#### Example: Updating File Databases

In this example, we'll use `/etc/portage/bashrc` to call some file database applications to ensure their databases are up to date with the system. The applications used in the example are [aide](#) (an intrusion detection tool) and [updatedb](#) (to use with [locate](#)), but these are meant as examples. Do not consider this as a HOWTO for AIDE ;-)

To use `/etc/portage/bashrc` for this case, we need to "hook" in the `postrm` (after removal of files) and `postinst` (after installation of files) functions, because that is when the files on the file system have been changed.

#### Code Listing 3.1: Example `/etc/portage/bashrc`

```
if [ "${EBUILD_PHASE}" == "postinst" ] || [ "${EBUILD_PHASE}" == "postrm" ];
then
    echo ":: Calling aide --update to update its database";
    aide --update;
    echo ":: Calling updatedb to update its database";
    updatedb;
fi
```

## 6.d. Executing Tasks After `--sync`

### The `/etc/portage/postsync.d` location

Until now we've talked about hooking into the ebuild processes. However, Portage also has another important function: updating the Portage tree. In order to run tasks after updating the Portage tree, put a script inside `/etc/portage/postsync.d` and make sure it is marked as executable.

#### Example: Running `eix-update`

If you didn't use `eix-sync` to update the tree, you can still have its database updated after running `emerge --sync` (or `emerge-webrsync`) by putting a symlink to `/usr/bin/eix` called `eix-update` in `/etc/portage/postsync.d`.

#### Code Listing 4.1: Running `eix-update` after a sync operation

```
# ln -s /usr/bin/eix /etc/portage/postsync.d/eix-update
```

**Note:** If you rather use a different name, you will need to make a script that calls `/usr/bin/eix-update` instead. The `eix` binary looks at how it has been called to find out which function it has to execute. If you put in a symlink to `eix` that isn't called `eix-update`, it will not run correctly.

## 6.e. Overriding Profile Settings

### The `/etc/portage/profile` location

By default, Gentoo uses the settings contained in the profile pointed to by `/etc/portage/make.profile` (a symbolic link to the right profile directory). These profiles define both specific settings as well as inherit settings from other profiles (through their parent file).

By using `/etc/portage/profile`, you can override profile settings such as `packages` (what packages are considered to be part of the system set), forced use flags and more.

#### Example: Adding `nfs-utils` to the System Set

If you use NFS-based file systems for rather critical file systems, you might want to have `net-fs/nfs-utils` "protected" as a system package, causing Portage to heavily warn you if it would be deleted.

To accomplish that, we add the package to `/etc/portage/profile/packages`, prepended with a `*`:

#### Code Listing 5.1: `/etc/portage/profile/packages` content

```
*net-fs/nfs-utils
```

## 6.f. Applying Non-Standard Patches

### Using `epatch_user`

To manage several ebuilds in a similar manner, ebuild developers use *eclasses* (sort-of shell libraries) that define commonly used functions. One of these eclasses is `eutils.eclass` which offers an interesting function called `epatch_user`.

The `epatch_user` function applies source code patches that are found in `/etc/portage/patches/<category>/<package>[-<version>[-<revision>]]`, whatever directory is found first. Sadly, not all ebuilds automatically call this function so just putting your patch in this location might not always work.

Luckily, with the information provided above, you can call this function by hooking into, for instance, the `prepare` phase. The function can be called as many times as you like - it will only apply the patches once.

#### Example: Applying Patches to Firefox

The `www-client/firefox` package is one of the few that already call `epatch_user` from within the ebuild, so you do not need to override anything specific.

If you need to patch firefox (for instance because a developer provided you with a patch and asked you to check if it fixes the bug you reported), put the patch in `/etc/portage/patches/www-client/firefox` (probably best to use the full name, including version so that the patch does not interfere with later versions) and rebuild firefox.

# D. Gentoo Network Configuration

## 1. Getting Started

### 1.a. Getting started

**Note:** This document assumes that you have correctly configured your kernel, its modules for your hardware and you know the interface name of your hardware. We also assume that you are configuring `eth0`, but it could also be `eth1`, `wlan0`, etc.



To get started configuring your network card, you need to tell the Gentoo RC system about it. This is done by creating a symbolic link from `net.lo` to `net.eth0` in `/etc/init.d`.

Code Listing 1.1: Symlinking net.eth0 to net.lo

```
# cd /etc/init.d
# ln -s net.lo net.eth0
```

Gentoo's RC system now knows about that interface. It also needs to know how to configure the new interface. All the network interfaces are configured in `/etc/conf.d/net`. Below is a sample configuration for DHCP and static addresses.

Code Listing 1.2: Examples for /etc/conf.d/net

```
# For DHCP
config_eth0="dhcp"

# For static IP using CIDR notation
config_eth0="192.168.0.7/24"
routes_eth0="default via 192.168.0.1"
dns_servers_eth0="192.168.0.1 8.8.8.8"

# For static IP using netmask notation
config_eth0="192.168.0.7 netmask 255.255.255.0"
routes_eth0="default via 192.168.0.1"
dns_servers_eth0="192.168.0.1 8.8.8.8"
```

**Note:** If you do not specify a configuration for your interface then DHCP is assumed.

**Note:** CIDR stands for Classless InterDomain Routing. Originally, IPv4 addresses were classified as A, B, or C. The early classification system did not envision the massive popularity of the Internet, and is in danger of running out of new unique addresses. CIDR is an addressing scheme that allows one IP address to designate many IP addresses. A CIDR IP address looks like a normal IP address except that it ends with a slash followed by a number; for example, 192.168.0.0/16. CIDR is described in [RFC 1519](#).

Now that we have configured our interface, we can start and stop it using the following commands:

Code Listing 1.3: Starting and stopping network scripts

```
# /etc/init.d/net.eth0 start
# /etc/init.d/net.eth0 stop
```

**Important:** When troubleshooting networking, take a look at `/var/log/rc.log`. Unless you have `rc_logger="NO"` set in `/etc/rc.conf`, you will find information on the boot activity stored in that log file.

Now that you have successfully started and stopped your network interface, you may wish to get it to start when Gentoo boots. Here's how to do this. The last "rc" command instructs Gentoo to start any scripts in the current runlevel that have not yet been started.

Code Listing 1.4: Configuring a network interface to load at boot time

```
# rc-update add net.eth0 default
# rc
```

2. Advanced Configuration

2.a. Advanced Configuration

The `config_eth0` variable is the heart of an interface configuration. It's a high level instruction list for configuring the interface (`eth0` in this case). Each command in the instruction list is performed sequentially. The interface is deemed OK if at least one command works.

Here's a list of built-in instructions.

Command	Description
<code>null</code>	Do nothing
<code>noop</code>	If the interface is up and there is an address then abort configuration successfully
an IPv4 or IPv6 address	Add the address to the interface
<code>dhcp</code> , <code>ads1</code> or <code>apipa</code> (or a custom command from a 3rd party module)	Run the module which provides the command. For example <code>dhcp</code> will run a module that provides DHCP which can be one of either <code>dhcpcd</code> , <code>dhclient</code> or <code>pump</code> .

If a command fails, you can specify a fallback command. The fallback has to match the config structure exactly.

You can chain these commands together. Here are some real world examples.

Code Listing 1.1: Configuration examples

```
# Adding three IPv4 addresses
config_eth0="192.168.0.2/24
192.168.0.3/24
192.168.0.4/24"

# Adding an IPv4 address and two IPv6 addresses
config_eth0="192.168.0.2/24
4321:0:1:2:3:4:567:89ab
4321:0:1:2:3:4:567:89ac"

# Keep our kernel assigned address, unless the interface goes
# down so assign another via DHCP. If DHCP fails then add a
# static address determined by APIPA
config_eth0="noop
dhcp
fallback_eth0=null
apipa"
```

**Note:** When using the `ifconfig` module and adding more than one address, interface aliases are created for each extra address. So with the above two examples you will get interfaces `eth0`, `eth0:1` and `eth0:2`. You cannot do anything special with these interfaces as the kernel and other programs will just treat `eth0:1` and `eth0:2` as `eth0`.

**Important:** The fallback order is important! If we did not specify the `null` option then the `apipa` command would only be run if the `noop` command failed.

**Note:** [APIPA](#) and [DHCP](#) are discussed later.

## 2.b. Network Dependencies

Init scripts in `/etc/init.d` can depend on a specific network interface or just `net`. All network interfaces in Gentoo's init system provide what is called `net`.

If, in `/etc/rc.conf`, `rc_depend_strict="YES"` is set, then all network interfaces that provide `net` must be active before a dependency on "net" is assumed to be met. In other words, if you have a `net.eth0` and `net.eth1` and an init script depends on "net", then both must be enabled.

On the other hand, if `rc_depend_strict="NO"` is set, then the "net" dependency is marked as resolved the moment at least one network interface is brought up.

But what about `net.br0` depending on `net.eth0` and `net.eth1`? `net.eth1` may be a wireless or PPP device that needs configuration before it can be added to the bridge. This cannot be done in `/etc/init.d/net.br0` as that's a symbolic link to `net.lo`.

The answer is defining an `rc_need_` setting in `/etc/conf.d/net`.

### Code Listing 2.1: net.br0 dependency in /etc/conf.d/net

```
rc_need_br0="net.eth0 net.eth1"
```

That alone, however, is not sufficient. Gentoo's networking init scripts use a virtual dependency called `net` to inform the system when networking is available. Clearly, in the above case, networking should only be marked as available when `net.br0` is up, not when the others are. So we need to tell that in `/etc/conf.d/net` as well:

### Code Listing 2.2: Updating virtual dependencies and provisions for networking

```
rc_net_lo_provide="!net"
rc_net_eth0_provide="!net"
rc_net_eth1_provide="!net"
```

For a more detailed discussion about dependency, consult the section [Writing Init Scripts](#) in the Gentoo Handbook. More information about `/etc/rc.conf` is available as comments within that file.

## 2.c. Variable names and values

Variable names are dynamic. They normally follow the structure of `variable_${interface|mac|ssid|apmac}`. For example, the variable `dhcpcd_eth0` holds the value for `dhcpcd` options for `eth0` and `dhcpcd_essid` holds the value for `dhcpcd` options when any interface connects to the ESSID "ssid".

However, there is no hard and fast rule that states interface names must be `ethx`. In fact, many wireless interfaces have names like `wlanx`, `rax` as well as `ethx`. Also, some user defined interfaces such as bridges can be given any name, such as `foo`. To make life more interesting, wireless Access Points can have names with non alpha-numeric characters in them - this is important because you can configure networking parameters per ESSID.

The downside of all this is that Gentoo uses bash variables for networking - and bash cannot use anything outside of English alpha-numerics. To get around this limitation we change every character that is not an English alpha-numeric into a `_` character.

Another downside of bash is the content of variables - some characters need to be escaped. This can be achieved by placing the `\` character in front of the character that needs to be escaped. The following list of characters needs to be escaped in this way: `"`, `'` and `\`.

In this example we use wireless ESSID as they can contain the widest scope of characters. We shall use the ESSID `My "\ NET`:

### Code Listing 3.1: variable name example

```
(This does work, but the domain is invalid)
dns_domain_My____NET="My \"\" NET"

(The above sets the dns domain to My "\ NET when a wireless card
connects to an AP whose ESSID is My "\ NET)
```

## 3. Modular Networking

### 3.a. Network Modules

We now support modular networking scripts, which means we can easily add support for new interface types and configuration modules while keeping compatibility with existing ones.

Modules load by default if the package they need is installed. If you specify a module here that doesn't have its package installed then you get an error stating which package you need to install. Ideally, you only use the modules setting when you have two or more packages installed that supply the same service and you need to prefer one over the other.

**Note:** All settings discussed here are stored in `/etc/conf.d/net` unless otherwise specified.

### Code Listing 1.1: Module preference

```
# Prefer ifconfig over iproute2
modules="ifconfig"

# You can also specify other modules for an interface
# In this case we prefer pump over dhcpcd
modules_eth0="pump"

# You can also specify which modules not to use - for example you may be
# using a supplicant or linux-wlan-ng to control wireless configuration but
```

```
# you still want to configure network settings per ESSID associated with.
modules="!iwconfig"
```

3.b. Interface Handlers

We provide two interface handlers presently: `ifconfig` and `iproute2`. You need one of these to do any kind of network configuration.

`ifconfig` is installed by default (the `net-tools` package is part of the system profile). `iproute2` is a more powerful and flexible package, but it's not included by default.

Code Listing 2.1: To install iproute2

```
# emerge sys-apps/iproute2

# To prefer ifconfig over iproute2 if both are installed as openrc prefers
# to use iproute2 then
modules="ifconfig"
```

As both `ifconfig` and `iproute2` do very similar things we allow their basic configuration to work with each other. For example both the below code snippet work regardless of which module you are using.

Code Listing 2.2: ifconfig and iproute2 examples

```
config_eth0="192.168.0.2/24"
config_eth0="192.168.0.2 netmask 255.255.255.0"

# We can also specify broadcast
config_eth0="192.168.0.2/24 brd 192.168.0.255"
config_eth0="192.168.0.2 netmask 255.255.255.0 broadcast 192.168.0.255"
```

3.c. DHCP

DHCP is a means of obtaining network information (IP address, DNS servers, Gateway, etc) from a DHCP server. This means that if there is a DHCP server running on the network, you just have to tell each client to use DHCP and it sets up the network all by itself. Of course, you will have to configure for other things like wireless, PPP or other things if required before you can use DHCP.

DHCP can be provided by `dhclient`, `dhcpcd`, or `pump`. Each DHCP module has its pros and cons - here's a quick run down.

DHCP Module	Package	Pros	Cons
dhclient	net-misc/dhclient	Made by ISC, the same people who make the BIND DNS software. Very configurable	Configuration is overly complex, software is quite bloated, cannot get NTP servers from DHCP, does not send hostname by default
dhcpcd	net-misc/dhcpcd	Long time Gentoo default, no reliance on outside tools, actively developed by Gentoo	Can be slow at times, does not yet daemonize when lease is infinite
pump	net-misc/pump	Lightweight, no reliance on outside tools	No longer maintained upstream, unreliable, especially over modems, cannot get NIS servers from DHCP

If you have more than one DHCP client installed, you need to specify which one to use - otherwise we default to `dhcpcd` if available.

To send specific options to the DHCP module, use `module_eth0="..."` (change module to the DHCP module you're using - i.e. `dhcpcd_eth0`).

We try and make DHCP relatively agnostic - as such we support the following commands using the `dhcpc_eth0` variable. The default is not to set any of them:

- `release` - releases the IP address for re-use
- `nodns` - don't overwrite `/etc/resolv.conf`
- `nontp` - don't overwrite `/etc/ntp.conf`
- `nonis` - don't overwrite `/etc/yp.conf`

Code Listing 3.1: Sample DHCP configuration in /etc/conf.d/net

```
# Only needed if you have more than one DHCP module installed
modules="dhcpcd"

config_eth0="dhcp"
dhcpcd_eth0="-t 10" # Timeout after 10 seconds
dhcp_eth0="release nodns nontp nonis" # Only get an address
```

**Note:** `dhcpcd` and `pump` send the current hostname to the DHCP server by default so you don't need to specify this anymore.

3.d. ADSL with PPPoE/PPPoA

First we need to install the ADSL software.

Code Listing 4.1: Install the ppp package

```
# emerge net-dialup/ppp
```

Second, create the PPP net script and the net script for the ethernet interface to be used by PPP:

Code Listing 4.2: Creating the PPP and ethernet scripts

```
# ln -s /etc/init.d/net.lo /etc/init.d/net.ppp0
# ln -s /etc/init.d/net.lo /etc/init.d/net.eth0
```

Be sure to set `rc_depend_strict` to "YES" in `/etc/rc.conf`.

Now we need to configure `/etc/conf.d/net`.

```

config_eth0=null (Specify your ethernet interface)
config_ppp0="ppp"
link_ppp0="eth0" (Specify your ethernet interface)
plugins_ppp0="pppoe"
username_ppp0='user'
password_ppp0='password'
pppd_ppp0=""
noauth
defaultroute
usepeerdns
holdoff 3
child-timeout 60
lcp-echo-interval 15
lcp-echo-failure 3
noaccomp noccp nobsdcomp nodeflate nopcomp novj novjccomp"

rc_need_ppp0="net.eth0"

```

You can also set your password in `/etc/ppp/pap-secrets`.

#### Code Listing 4.4: Sample `/etc/ppp/pap-secrets`

```

# The * is important
"username" * "password"

```

If you use PPPoE with a USB modem you'll need to emerge [br2684ctl](#). Please read `/usr/portage/net-dialup/speedtouch-usb/files/README` for information on how to properly configure it.

**Important:** Please carefully read the section on ADSL and PPP in `/usr/share/doc/openrc-0.8.3-r1/net.example.bz2`. It contains many more detailed explanations of all the settings your particular PPP setup will likely need. Of course, change [0.8.3-r1](#) with the version of OpenRC installed on your system.

### 3.e. APIPA (Automatic Private IP Addressing)

APIPA tries to find a free address in the range 169.254.0.0-169.254.255.255 by arping a random address in that range on the interface. If no reply is found then we assign that address to the interface.

This is only useful for LANs where there is no DHCP server and you don't connect directly to the internet and all other computers use APIPA.

For APIPA support, emerge [net-misc/iputils](#) or [net-analyzer/arping](#).

#### Code Listing 5.1: APIPA configuration in `/etc/conf.d/net`

```

# Try DHCP first - if that fails then fallback to APIPA
config_eth0="dhcp"
fallback_eth0="apipa"

# Just use APIPA
config_eth0="apipa"

```

### 3.f. Bonding

For link bonding/trunking emerge [net-misc/ifenslave](#).

Bonding is used to increase network bandwidth. If you have two network cards going to the same network, you can bond them together so your applications see just one interface but they really use both network cards.

#### Code Listing 6.1: bonding configuration in `/etc/conf.d/net`

```

# To bond interfaces together
slaves_bond0="eth0 eth1 eth2"

# You may not want to assign an IP to the bonded interface
config_bond0="null"

# Depend on eth0, eth1 and eth2 as they may require extra configuration
rc_need_bond0="net.eth0 net.eth1 net.eth2"

```

### 3.g. Bridging (802.1d support)

For bridging support emerge [net-misc/bridge-utils](#).

Bridging is used to join networks together. For example, you may have a server that connects to the internet via an ADSL modem and a wireless access card to enable other computers to connect to the internet via the ADSL modem. You could create a bridge to join the two interfaces together.

#### Code Listing 7.1: Bridge configuration in `/etc/conf.d/net`

```

# Configure the bridge - "man brctl" for more details
brctl_br0="setfd 0" "sethello 0" "stp off"

# To add ports to bridge br0
bridge_br0="eth0 eth1"

# You need to configure the ports to null values so dhcp does not get started
config_eth0="null"
config_eth1="null"

# Finally give the bridge an address - you could use DHCP as well
config_br0="192.168.0.1/24"

```

```
# Depend on eth0 and eth1 as they may require extra configuration
rc_need_br0="net.eth0 net.eth1"
```

**Important:** For using some bridge setups, you may need to consult the [variable name](#) documentation.

### 3.h. MAC Address

If you need to, you can change the MAC address of your interfaces through the network configuration file too.

#### Code Listing 8.1: MAC Address change example

```
# To set the MAC address of the interface
mac_eth0="00:11:22:33:44:55"

# To randomize the last 3 bytes only
mac_eth0="random-ending"

# To randomize between the same physical type of connection (e.g. fibre,
# copper, wireless) , all vendors
mac_eth0="random-samekind"

# To randomize between any physical type of connection (e.g. fibre, copper,
# wireless) , all vendors
mac_eth0="random-anykind"

# Full randomization - WARNING: some MAC addresses generated by this may
# NOT act as expected
mac_eth0="random-full"
```

### 3.i. Tunnelling

You don't need to emerge anything for tunnelling as the interface handler can do it for you.

#### Code Listing 9.1: Tunnelling configuration in /etc/conf.d/net

```
# For GRE tunnels
iptunnel_vpn0="mode gre remote 207.170.82.1 key 0xffffffff ttl 255"

# For IPIP tunnels
iptunnel_vpn0="mode ipip remote 207.170.82.2 ttl 255"

# To configure the interface
config_vpn0="192.168.0.2 peer 192.168.1.1"
```

### 3.j. VLAN (802.1q support)

For VLAN support, emerge [net-misc/vconfig](#).

Virtual LAN is a group of network devices that behave as if they were connected to a single network segment - even though they may not be. VLAN members can only see members of the same VLAN even though they may share the same physical network.

#### Code Listing 10.1: VLAN configuration in /etc/conf.d/net

```
# Specify the VLAN numbers for the interface like so
# Please ensure your VLAN IDs are NOT zero-padded
vlans_eth0="1 2"

# You can also configure the VLAN
# see for vconfig man page for more details
vconfig_eth0="set_name_type VLAN_PLUS_VID_NO_PAD"
vconfig_vlan1="set_flag 1" "set_egress_map 2 6"

# Configure the interface as usual
config_vlan1="172.16.3.1 netmask 255.255.254.0"
config_vlan2="172.16.2.1 netmask 255.255.254.0"
```

**Important:** For using some VLAN setups, you may need to consult the [variable name](#) documentation.

## 4. Wireless Networking

### 4.a. Introduction

Wireless networking on Linux is usually pretty straightforward. There are two ways of configuring wifi: graphical clients, or the command line.

The *easiest* way is to use a graphical client once you've installed a [desktop environment](#). Most graphical clients, such as [wicd](#) and [NetworkManager](#), are pretty self-explanatory. They offer a handy point-and-click interface that gets you on a network in just a few seconds.

**Note:** [wicd](#) offers a command line utility *in addition* to the main graphical interface. You can get it by emerging [wicd](#) with the [ncurses](#) USE flag set. This [wicd-ncurses](#) utility is particularly useful for folks who don't use a gtk-based desktop environment, but still want an easy command line tool that doesn't require hand-editing configuration files.

However, if you don't want to use a graphical client, then you can configure wifi on the command line by editing a few configuration files. This takes a bit more time to setup, but it also requires the fewest packages to download and install. Since the graphical clients are mostly self-explanatory (with helpful screenshots at their homepages), we'll focus on the command line alternatives.

You can setup wireless networking on the command line by installing [wireless-tools](#) or [wpa\\_supplicant](#). The important thing to remember is that you configure wireless networks on a global basis and not an interface basis.

`wpa_supplicant` is the best choice. For a list of supported drivers, [read the wpa\\_supplicant site](#).

`wireless-tools` supports nearly all cards and drivers, but it cannot connect to WPA-only Access Points. If your networks only offer WEP encryption or are completely open, you may prefer the simplicity of `wireless-tools`.

**Warning:** The `linux-wlan-ng` driver is not supported by baselayout at this time. This is because `linux-wlan-ng` have its own setup and configuration which is completely different to everyone else's. The `linux-wlan-ng` developers are rumoured to be changing their setup over to `wireless-tools`, so when this happens you may use `linux-wlan-ng` with baselayout.

## 4.b. WPA Supplicant

[WPA Supplicant](#) is a package that allows you to connect to WPA enabled access points.

### Code Listing 2.1: Install wpa\_supplicant

```
# emerge net-wireless/wpa_supplicant
```

**Important:** You have to have `CONFIG_PACKET` enabled in your kernel for `wpa_supplicant` to work. Try running `grep CONFIG_PACKET /usr/src/linux/.config` to see if you have it enabled in your kernel.

**Note:** Depending on your USE flags, `wpa_supplicant` can install a graphical interface written in Qt4, which will integrate nicely with KDE. To get it, run `echo "net-wireless/wpa_supplicant qt4" >> /etc/portage/package.use` as root before emerging `wpa_supplicant`.

Now we have to configure `/etc/conf.d/net` to so that we prefer `wpa_supplicant` over `wireless-tools` (if both are installed, `wireless-tools` is the default)

### Code Listing 2.2: configure /etc/conf.d/net for wpa\_supplicant

```
# Prefer wpa_supplicant over wireless-tools
modules="wpa_supplicant"
```

```
# It's important that we tell wpa_supplicant which driver we should
# be using as it's not very good at guessing yet
wpa_supplicant_eth0="-Dmadwifi"
```

**Note:** If you're using the host-ap driver you will need to put the card in *Managed mode* before it can be used with `wpa_supplicant` correctly. You can use `iwconfig_eth0="mode managed"` to achieve this in `/etc/conf.d/net`.

That was simple, wasn't it? However, we still have to configure `wpa_supplicant` itself which is a bit more tricky depending on how secure the Access Points are that you are trying to connect to. The below example is taken and simplified from `/usr/share/doc/wpa_supplicant-<version>/wpa_supplicant.conf.gz` which ships with `wpa_supplicant`.

### Code Listing 2.3: An example /etc/wpa\_supplicant/wpa\_supplicant.conf

```
# The below line not be changed otherwise we refuse to work
ctrl_interface=/var/run/wpa_supplicant

# Ensure that only root can read the WPA configuration
ctrl_interface_group=0

# Let wpa_supplicant take care of scanning and AP selection
ap_scan=1

# Simple case: WPA-PSK, PSK as an ASCII passphrase, allow all valid ciphers
network={
    ssid="simple"
    psk="very secret passphrase"
    # The higher the priority the sooner we are matched
    priority=5
}

# Same as previous, but request SSID-specific scanning (for APs that reject
# broadcast SSID)
network={
    ssid="second ssid"
    scan_ssid=1
    psk="very secret passphrase"
    priority=2
}

# Only WPA-PSK is used. Any valid cipher combination is accepted
network={
    ssid="example"
    proto=WPA
    key_mgmt=WPA-PSK
    pairwise=CCMP TKIP
    group=CCMP TKIP WEP104 WEP40
    psk=06b4be19da289f475aa46a33cb793029d4ab3db7a23ee92382eb0106c72ac7bb
    priority=2
}

# Plaintext connection (no WPA, no IEEE 802.1X)
network={
    ssid="plaintext-test"
    key_mgmt=NONE
}

# Shared WEP key connection (no WPA, no IEEE 802.1X)
network={
    ssid="static-wep-test"
```



```
key_mgmt=NONE
# Keys in quotes are ASCII keys
wep_key0="abcde"
# Keys specified without quotes are hex keys
wep_key1=0102030405
wep_key2="1234567890123"
wep_tx_keyidx=0
priority=5
}

# Shared WEP key connection (no WPA, no IEEE 802.1X) using Shared Key
# IEEE 802.11 authentication
network={
    ssid="static-wep-test2"
    key_mgmt=NONE
    wep_key0="abcde"
    wep_key1=0102030405
    wep_key2="1234567890123"
    wep_tx_keyidx=0
    priority=5
    auth_alg=SHARED
}

# IBSS/ad-hoc network with WPA-None/TKIP
network={
    ssid="test adhoc"
    mode=1
    proto=WPA
    key_mgmt=WPA-NONE
    pairwise=NONE
    group=TKIP
    psk="secret passphrase"
}
```

4.c. Wireless Tools

Initial setup and Managed Mode

[Wireless Tools](#) provide a generic way to configure basic wireless interfaces up to the WEP security level. While WEP is a weak security method it's also the most prevalent.

Wireless Tools configuration is controlled by a few main variables. The sample configuration file below should describe all you need. One thing to bear in mind is that no configuration means "connect to the strongest unencrypted Access Point" - we will always try and connect you to something.

Code Listing 3.1: Install wireless-tools

```
# emerge net-wireless/wireless-tools
```

**Note:** Although you can store your wireless settings in `/etc/conf.d/wireless` this guide recommends you store them in `/etc/conf.d/net`.

**Important:** You *will* need to consult the [variable name](#) documentation.

Code Listing 3.2: sample iwconfig setup in /etc/conf.d/net

```
# Prefer iwconfig over wpa_supplicant
modules="iwconfig"

# Configure WEP keys for Access Points called ESSID1 and ESSID2
# You may configure up to 4 WEP keys, but only 1 can be active at
# any time so we supply a default index of [1] to set key [1] and then
# again afterwards to change the active key to [1]
# We do this incase you define other ESSID's to use WEP keys other than 1
#
# Prefixing the key with s: means it's an ASCII key, otherwise a HEX key
#
# enc open specified open security (most secure)
# enc restricted specified restricted security (least secure)
key_ESSID1="[1] s:yourkeyhere key [1] enc open"
key_ESSID2="[1] aaaa-bbbb-cccc-dd key [1] enc restricted"

# The below only work when we scan for available Access Points

# Sometimes more than one Access Point is visible so we need to
# define a preferred order to connect in
preferred_aps="'ESSID1' 'ESSID2'"
```

Fine tune Access Point Selection

You can add some extra options to fine-tune your Access Point selection, but these are not normally required.

You can decide whether we only connect to preferred Access Points or not. By default if everything configured has failed and we can connect to an unencrypted Access Point then we will. This can be controlled by the `associate_order` variable. Here's a table of values and how they control this.

Value	Description
any	Default behaviour
preferredonly	We will only connect to visible APs in the preferred list
forcepreferred	We will forceably connect to APs in the preferred order if they are not found in a scan
forcepreferredonly	Do not scan for APs - instead just try to connect to each one in order
forceany	Same as <code>forcepreferred</code> + connect to any other available AP

Finally we have some `blacklist_aps` and `unique_ap` selection. `blacklist_aps` works in a similar way to `preferred_aps`. `unique_ap` is a `yes` or `no` value that says if a second wireless interface can connect to the same Access Point as the first interface.

Code Listing 3.3: blacklist\_aps and unique\_ap example

```
# Sometimes you never want to connect to certain access points
blacklist_aps="'ESSID3' 'ESSID4'"

# If you have more than one wireless card, you can say if you want
# to allow each card to associate with the same Access Point or not
# Values are "yes" and "no"
# Default is "yes"
unique_ap="yes"
```

Ad-Hoc and Master Modes

If you want to set yourself up as an Ad-Hoc node if you fail to connect to any Access Point in managed mode, you can do that too.

Code Listing 3.4: fallback to ad-hoc mode

```
adhoc_essid_eth0="This Adhoc Node"
```

What about connecting to Ad-Hoc networks or running in Master mode to become an Access Point? Here's a configuration just for that! You may need to specify WEP keys as shown above.

Code Listing 3.5: sample ad-hoc/master configuration

```
# Set the mode - can be managed (default), ad-hoc or master
# Not all drivers support all modes
mode_eth0="ad-hoc"

# Set the ESSID of the interface
# In managed mode, this forces the interface to try and connect to the
# specified ESSID and nothing else
essid_eth0="This Adhoc Node"

# We use channel 3 if you don't specify one
channel_eth0="9"
```

**Important:** The below is taken verbatim from the BSD wavelan documentation found at [the NetBSD documentation](#). There are 14 channels possible; We are told that channels 1-11 are legal for North America, channels 1-13 for most of Europe, channels 10-13 for France, and only channel 14 for Japan. If in doubt, please refer to the documentation that came with your card or access point. Make sure that the channel you select is the same channel your access point (or the other card in an ad-hoc network) is on. The default for cards sold in North America and most of Europe is 3; the default for cards sold in France is 11, and the default for cards sold in Japan is 14.

Troubleshooting Wireless Tools

There are some more variables you can use to help get your wireless up and running due to driver or environment problems. Here's a table of other things you can try.

Variable	Default Value	Description
iwconfig_eth0		See the iwconfig man page for details on what to send <code>iwconfig</code>
iwpriv_eth0		See the iwpriv man page for details on what to send <code>iwpriv</code>
sleep_scan_eth0	0	The number of seconds to sleep before attempting to scan. This is needed when the driver/firmware needs more time to active before it can be used.
sleep_associate_eth0	5	The number of seconds to wait for the interface to associate with the Access Point before moving onto the next one
associate_test_eth0	MAC	Some drivers do not reset the MAC address associated with an invalid one when they lose or attempt association. Some drivers do not reset the quality level when they lose or attempt association. Valid settings are <code>MAC</code> , <code>quality</code> and <code>all</code> .
scan_mode_eth0		Some drivers have to scan in ad-hoc mode, so if scanning fails try setting <code>ad-hoc</code> here
iwpriv_scan_pre_eth0		Sends some <code>iwpriv</code> commands to the interface before scanning. See the iwpriv man page for more details.
iwpriv_scan_post_eth0		Sends some <code>iwpriv</code> commands to the interface after scanning. See the iwpriv man page for more details.

4.d. Defining network configuration per ESSID

Sometimes, you need a static IP when you connect to `ESSID1` and you need DHCP when you connect to `ESSID2`. In fact, most module variables can be defined per ESSID. Here's how we do this.

**Note:** These work if you're using WPA Supplicant or Wireless Tools.

**Important:** You *will* need to consult the [variable name](#) documentation.

Code Listing 4.1: override network settings per ESSID

```
config_ESSID1="192.168.0.3/24 brd 192.168.0.255"
routes_ESSID1="default via 192.168.0.1"

config_ESSID2="dhcp"
fallback_ESSID2="192.168.3.4/24"
fallback_route_ESSID2="default via 192.168.3.1"

# We can define nameservers and other things too
# NOTE: DHCP will override these unless it's told not to
dns_servers_ESSID1="192.168.0.1 192.168.0.2"
dns_domain_ESSID1="some.domain"
dns_search_domains_ESSID1="search.this.domain search.that.domain"

# You override by the MAC address of the Access Point
# This handy if you goto different locations that have the same ESSID
```

```
config_001122334455="dhcp"
dhcpcd_001122334455="-t 10"
dns_servers_001122334455="192.168.0.1 192.168.0.2"
```

## 5. Adding Functionality

### 5.a. Standard function hooks

Four functions can be defined in `/etc/conf.d/net` which will be called surrounding the `start/stop` operations. The functions are called with the interface name first so that one function can control multiple adapters.

The return values for the `preup()` and `predown()` functions should be 0 (success) to indicate that configuration or deconfiguration of the interface can continue. If `preup()` returns a non-zero value, then interface configuration will be aborted. If `predown()` returns a non-zero value, then the interface will not be allowed to continue deconfiguration.

The return values for the `postup()` and `postdown()` functions are ignored since there's nothing to do if they indicate failure.

`${IFACE}` is set to the interface being brought up/down. `${IFVAR}` is `${IFACE}` converted to variable name bash allows.

Code Listing 1.1: pre/post up/down function examples in `/etc/conf.d/net`

```
preup() {
    # Test for link on the interface prior to bringing it up. This
    # only works on some network adapters and requires the ethtool
    # package to be installed.
    if ethtool ${IFACE} | grep -q 'Link detected: no'; then
        ewarn "No link on ${IFACE}, aborting configuration"
        return 1
    fi

    # Remember to return 0 on success
    return 0
}

predown() {
    # The default in the script is to test for NFS root and disallow
    # downing interfaces in that case. Note that if you specify a
    # predown() function you will override that logic. Here it is, in
    # case you still want it...
    if is_net_fs /; then
        error "root filesystem is network mounted -- can't stop ${IFACE}"
        return 1
    fi

    # Remember to return 0 on success
    return 0
}

postup() {
    # This function could be used, for example, to register with a
    # dynamic DNS service. Another possibility would be to
    # send/receive mail once the interface is brought up.
    return 0
}

postdown() {
    # This function is mostly here for completeness... I haven't
    # thought of anything nifty to do with it yet ;-)
    return 0
}
```

**Note:** For more information on writing your own functions, please read `/usr/share/doc/openrc-*/net.example.bz2`.

### 5.b. Wireless Tools function hooks

**Note:** This will not work with WPA Supplicant - but the `${ESSID}` and `${ESSIDVAR}` variables are available in the `postup()` function.

Two functions can be defined in `/etc/conf.d/net` which will be called surrounding the `associate` function. The functions are called with the interface name first so that one function can control multiple adapters.

The return values for the `preassociate()` function should be 0 (success) to indicate that configuration or deconfiguration of the interface can continue. If `preassociate()` returns a non-zero value, then interface configuration will be aborted.

The return value for the `postassociate()` function is ignored since there's nothing to do if it indicates failure.

`${ESSID}` is set to the exact ESSID of the AP you're connecting to. `${ESSIDVAR}` is `${ESSID}` converted to a variable name bash allows.

Code Listing 2.1: pre/post association functions in `/etc/conf.d/net`

```
preassociate() {
    # The below adds two configuration variables leap_user_ESSID
    # and leap_pass_ESSID. When they are both configured for the ESSID
    # being connected to then we run the CISCO LEAP script

    local user pass
    eval user="\${leap_user_${ESSIDVAR}}\"
    eval pass="\${leap_pass_${ESSIDVAR}}\"

    if [[ -n ${user} && -n ${pass} ]]; then
        if [[ ! -x /opt/cisco/bin/leapscript ]]; then
```

```

    eend "For LEAP support, please emerge net-misc/cisco-aironet-client-utils"
    return 1
fi
einfo "Waiting for LEAP Authentication on \"${ESSID}/\\\\\\\\/}\""
if /opt/cisco/bin/leapscript ${user} ${pass} | grep -q 'Login incorrect'; then
    ewarn "Login Failed for ${user}"
    return 1
fi
fi
return 0
}

postassociate() {
    # This function is mostly here for completeness... I haven't
    # thought of anything nifty to do with it yet ;-)

    return 0
}

```

**Note:** `${ESSID}` and `${ESSIDVAR}` are unavailable in `predown()` and `postdown()` functions.

**Note:** For more information on writing your own functions, please read `/usr/share/doc/openrc-*/net.example.bz2`.

## 6. Network Management

### 6.a. Network Management

If you and your computer are always on the move, you may not always have an ethernet cable or plugged in or an access point available. Also, you may want networking to automatically work when an ethernet cable is plugged in or an access point is found.

Here you can find some tools that help you manage this.

**Note:** This document only talks about `ifplugd`, but there are alternatives such as `netplug`. `netplug` is a lightweight alternative to `ifplugd`, but it relies on your kernel network drivers working correctly, and many drivers do not.

### 6.b. ifplugd

`ifplugd` is a daemon that starts and stops interfaces when an ethernet cable is inserted or removed. It can also manage detecting association to Access Points or when new ones come in range.

#### Code Listing 2.2: Installing ifplugd

```
# emerge sys-apps/ifplugd
```

Configuration for `ifplugd` is fairly straightforward too. The configuration file is held in `/etc/conf.d/net`. Run `man ifplugd` for details on the available variables. Also, see `/usr/share/doc/openrc-*/net.example.bz2` for more examples.

#### Code Listing 2.2: Sample ifplug configuration

```

(Replace eth0 with the interface to be monitored)
ifplugd_eth0="..."

(To monitor a wireless interface)
ifplugd_eth0="--api-mode=wlan"

```

In addition to managing multiple network connections, you may want to add a tool that makes it easy to work with multiple DNS servers and configurations. This is very handy when you receive your IP address via DHCP. Simply emerge `openresolv`.

#### Code Listing 2.3: Installing openresolv

```
# emerge openresolv
```

See `man resolvconf` to learn more about its features.

The contents of this document, unless otherwise expressly stated, are licensed under the [CC-BY-SA-2.5](#) license. The [Gentoo Name and Logo Usage Guidelines](#) apply.