



9. Deploy Additional User Clusters: NetApp HCI with Anthos

NetApp Solutions

Dorian Henderson, Kevin Hoke
January 18, 2021

This PDF was generated from https://docs.netapp.com/us-en/netapp-solutions/containers/anthos_task_deploy_additional_user_clusters.html on May 19, 2021. Always check docs.netapp.com for the latest.

Table of Contents

9. Deploy Additional User Clusters: NetApp HCI with Anthos 1

9. Deploy Additional User Clusters: NetApp HCI with Anthos

With Anthos, organizations can scale their environments to incorporate multiple user clusters and segregate workloads between teams. A single admin cluster can support up to five user clusters, and each user cluster can support up to twenty-five nodes.

To add additional user clusters to your deployment, complete the following steps:

1. Copy the `config.yaml` file to a new file named `anthos-cluster02-config.yaml`.

```
ubuntu@Anthos-Admin-Workstation:~$ cp config.yaml anthos-cluster02-config.yaml
```

2. Make the following edits to the newly created file:

1. Comment out the sections that refer to the existing admin cluster with (#).
2. When you get to the `usercluster` section, update the following fields:
 1. Update the partition name under the `bigip` section.
 2. Update the `controlplanvip` and `ingressvip` values under the `vip` section.
 3. Update the `clustername` value.

```
usercluster:
  # In-Cluster vCenter configuration
  vcenter:
    # If specified it overwrites the network field in global
    vcenter configuration
    network: ""
    # # The absolute or relative path to the yaml file to use for
    static IP allocation.
    # # Do not include if using DHCP
    # ipblockfilepath: ""
    # # Specify pre-defined nodeports if using "manual" load
    balancer mode
    # manullbspec:
    #   ingresshttpnodeport: 30243
    #   ingresshttpsnodeport: 30879
    #   controlplanenodeport: 30562
    #   addonsnodeport: 0
    # Specify the already-existing partition and credentials to use
    with F5
    bigip:
      # To re-use credentials across clusters we recommend using
      YAML node anchors.
```

```

# See https://yaml.org/spec/1.2/spec.html#id2785586
credentials:
  address: "172.21.224.22"
  username: "admin"
  password: "NetApp!23"
partition: "Anthos-Cluster02-Part"
# # Optionally specify a pool name if using SNAT
# snatpoolname: ""
# The VIPs to use for load balancing
vips:
  # Used to connect to the Kubernetes API
  controlplanevip: "10.63.172.108"
  # Shared by all services for ingress traffic
  ingressvip: "10.63.172.109"
  # # Used for admin cluster addons (needed for multi cluster
features). Must be the same
  # # across clusters
  # addonsvip: ""
# A unique name for this cluster
clustername: "anthos-cluster02"
# User cluster master nodes must have either 1 or 3 replicas
masternode:
  cpus: 4
  memorymb: 8192
  # How many machines of this type to deploy
  replicas: 1
# The number of worker nodes to deploy and their size. Min. 2
replicas
workernode:
  cpus: 4
  memorymb: 8192
  # How many machines of this type to deploy
  replicas: 3
# The Kubernetes service CIDR range for the cluster
serviceiprange: 10.96.0.0/12
# The Kubernetes pod CIDR range for the cluster
podiprange: 192.168.0.0/16

```

3. Run the following command to check the config file again to verify that there are no syntax errors. Because you have removed the admin section, you must reference the `kubeconfig` file for the admin cluster named `kubeconfig` (found in the working directory).

```
ubuntu@Anthos-Admin-Workstation:~$ gkectl check-config --config anthos-
cluster02-config.yaml --kubeconfig kubeconfig
- Validation Category: Config Check
  - [SUCCESS] Config

- Validation Category: Docker Registry
  - [SUCCESS] gcr.io/gke-on-prem-release access

- Validation Category: vCenter
  - [SUCCESS] Credentials
  - [SUCCESS] Datacenter
  - [SUCCESS] Datastore
  - [FAILURE] Data Disk: vCenter data disk already exists
  - [SUCCESS] Resource Pool
  - [SUCCESS] Network

- Validation Category: F5 BIG-IP
  - [SUCCESS] Credentials
  - [SUCCESS] Partition

- Validation Category: Network Configuration
  - [SUCCESS] CIDR, VIP and static IP (availability and overlapping)

- Validation Category: VIPs
  - [SUCCESS] ping (availability)


- Validation Category: Node IPs
  - [SUCCESS] ping (availability)

Some validations FAILED or SKIPPED. Check report above.
```

4. If all the checks succeed as expected, you can deploy this new user cluster in a manner very similar to the first cluster creation, referencing the `kubeconfig` file from the admin cluster.

```
ubuntu@Anthos-Admin-Workstation:~$ gkectl create cluster --config
anthos-cluster02-config.yaml --kubeconfig kubeconfig
```

5. As with the previous deployment, the process runs for several minutes and can be monitored on screen and in vCenter by watching the resource pool as the VMs populate. When complete, you should be able to see the new user cluster (four nodes).



6. You can access and execute commands against the deployed user cluster using the kubectl command line tool and the `kubeconfig` file generated by the process (stored in the working directory).

```
ubuntu@Anthos-Admin-Workstation:~$ kubectl get nodes --kubeconfig
anthos-cluster02-kubeconfig
NAME                                STATUS    ROLES    AGE    VERSION
anthos-cluster02-84744f5bd8-8rqk6  Ready    <none>   9m16s  v1.13.7-
gke.20
anthos-cluster02-84744f5bd8-f1786  Ready    <none>   9m28s  v1.13.7-
gke.20
anthos-cluster02-84744f5bd8-fnsmp  Ready    <none>   9m21s  v1.13.7-
gke.20
```

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.