



Optimizing Memory for Red Hat Virtualization: NetApp HCI with RHV

NetApp Solutions

Kevin Hoke, Dorian Henderson
January 14, 2021

This PDF was generated from https://docs.netapp.com/us-en/netapp-solutions/infra/rhv-optimizing_memory_for_red_hat_virtualization.html on May 19, 2021. Always check docs.netapp.com for the latest.

Table of Contents

Optimizing Memory for Red Hat Virtualization: NetApp HCI with RHV 1

Optimizing Memory for Red Hat Virtualization: NetApp HCI with RHV

One of the primary benefits for deploying a virtual infrastructure is to enable the more efficient use of physical resources in the environment. In a case in which the guest VMs underutilize the memory allotted, you can use memory overcommitment to optimize memory usage. With this feature, the sum of the memory allocated to guest VMs on a host is allowed to exceed the amount of physical memory on that host.

The concept behind memory overcommitment is similar to thin provisioning of storage resources. At any given moment, every VM on the host does not use the total amount of memory allocated to it. When one VM has excess memory, its unused memory is available for other VMs to use. Therefore, an end user can deploy more VMs than the physical infrastructure would normally allow. Memory overcommitment on the hosts in the cluster is handled by Memory Overcommit Manager (MoM). Techniques like memory ballooning and Kernel Same-page Merging (KSM) can improve memory overcommitment depending on the kind of workload.

Memory ballooning is a memory management technique which allows a host to artificially expand its memory by reclaiming unused memory that was previously allocated to various VMs, with a limitation of the guaranteed memory size of every VM. For memory ballooning to work, each VM by default has a balloon device with the necessary drivers. Ballooning essentially is a cooperative operation between the VM driver and the host. Depending on the memory needs of the host, it instructs the guest OS to inflate (provide memory to host) or deflate (regain the memory) the balloon which is controlled by the balloon device.

Kernel Same-page Merging (KSM) allows the host kernel to examine two or more running VMs and compare their image and memory. If any memory regions or pages are identical, KSM reduces multiple identical memory pages to a single page. This page is then marked 'copy on write' and a new page is created for that guest VM if the contents of the page are modified by a guest VM.

Both features can be enabled at a cluster level to apply to all hosts in that cluster. To enable these features, navigate to Compute > Clusters, select the desired cluster and click Edit. Then click the Optimization sub-tab and perform the following steps based on your requirements:

1. Depending on the use-case and workload, enable Memory Optimization to allow overcommitment of memory to either 150% or 200% of the available physical memory.
2. To enable memory ballooning, check the Enable Memory Balloon Optimization checkbox.
3. To enable KSM, check the Enable KSM checkbox.
4. Click Ok to confirm the changes.

Edit Cluster

General

Optimization

Migration Policy

Scheduling Policy

Console

Fencing Policy

MAC Address Pool

Memory Optimization

☐ None - Disable memory overcommit
 ☒ For Server Load - Allow scheduling of 150% of physical memory
 ☐ For Desktop Load - Allow scheduling of 200% of physical memory

Symmetric Multithreading

☐ Symmetric Multithreading disabled

CPU Threads

☐ Count Threads As Cores

Changes made in this section will not take effect until the host is activated for the first time, enters and exits maintenance mode, or the MOM policy is manually synced.

Memory Balloon

☒ Enable Memory Balloon Optimization

KSM control

☒ Enable KSM
 ☒ Share memory pages across all available memory (best KSM effectiveness)
 ☐ Share memory pages inside NUMA nodes (best NUMA performance)

OK

Cancel

Be aware that after these changes have been applied, they do not take effect until you manually sync the MoM policy. To sync the MoM policy, navigate to Compute > Clusters and click the cluster for which you made the optimization changes. Navigate to the Hosts sub-tab, select all the hosts, and then click Sync MoM Policy.

Compute > Clusters > Default

Edit

Remove

Upgrade

General

Logical Networks

Hosts

Virtual Machines

Affinity Groups

Affinity Labels

CPU Profiles

Permissions

Red Hat Documentation

Sync MoM Policy

1 - 2

	Name	Hostname/IP	Status	Load	Display Address Overridden
	rhv-h01.cie.netapp.com	rhv-h01.cie.netapp.com	Up	3 VMs	No
	rhv-h02.cie.netapp.com	rhv-h02.cie.netapp.com	Up	5 VMs	No

KSM and ballooning can free up some memory on the host and facilitate overcommitment, but, if the amount of shareable memory decreases and the use of physical memory increases, it might cause an out-of-memory condition. Therefore, the administrator should be sure to reserve enough memory to avoid out-of-memory conditions if the shareable memory decreases.

In some scenarios, memory ballooning may collide with KSM. In such situations, MoM tries to adjust the

balloon size to minimize collisions. Also, there can be scenarios for which ballooning might cause sub-optimal performance. Therefore, depending on the workload requirements, you can consider enabling either or both the techniques.

Next: [Where to Find Additional Information NetApp HCI with RHV](#)

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.