



Solution Automation

NetApp Solutions

NetApp
August 18, 2021

This PDF was generated from https://docs.netapp.com/us-en/netapp-solutions/automation/automation_introduction.html on August 18, 2021. Always check docs.netapp.com for the latest.

Table of Contents

- Solution Automation 1
 - NetApp Solution Automation 1
 - Setup the Ansible control node (For CLI based deployments). 1
 - NetApp solution automation 3

Solution Automation

NetApp Solution Automation

Introduction

One of the objectives of validating and architecting solutions is to make the solution easily consumable. Therefore, it is paramount that the deployment and configuration of infrastructure and/or applications delivered through our solutions is simplified through automation. NetApp is committed to simplifying solution consumption through automation using RedHat Ansible.

Ansible is an open-source automation engine that helps IT teams automate application deployment, cloud provisioning, configuration management, and many other IT needs. Ansible is agentless and does not require a custom security infrastructure. You can manage the automation of multiple systems from your control system remotely via SSH making it a robust solution for IT teams looking to automate their tedious and repetitive IT needs.

If you are new to NetApp solution automation, you can use the following sections to set up your Ansible controller.

For more information about RedHat Ansible, see the documentation [here](#).

Setup the Ansible control node (For CLI based deployments)

NetApp Solution Automation

Procedure

1. Requirements for the Ansible control node,:
 - a. A RHEL/CentOS machine with the following packages installed:
 - i. Python3
 - ii. Pip3
 - iii. Ansible (version greater than 2.10.0)
 - iv. Git

If you have a fresh RHEL/CentOS machine without the above requirements installed, follow the below steps to setup that machine as the Ansible control node:

1. Enable the Ansible repository for RHEL-8/RHEL-7
 - a. For RHEL-8 (run the below command as root)

```
subscription-manager repos --enable ansible-2.9-for-rhel-8-x86_64-rpms
```

- b. For RHEL-7 (run the below command as root)

```
subscription-manager repos --enable rhel-7-server-ansible-2.9-rpms
```

2. Create a .sh file

```
vi setup.sh
```

3. Paste the below content in the file

```
#!/bin/bash
echo "Installing Python ----->"
sudo yum -y install python3 >/dev/null
echo "Installing Python Pip ----->"
sudo yum -y install python3-pip >/dev/null
echo "Installing Ansible ----->"
python3 -W ignore -m pip --disable-pip-version-check install ansible
>/dev/null
echo "Installing git ----->"
sudo yum -y install git >/dev/null
```

4. Make the file executable

```
chmod +x setup.sh
```

5. Run the script (as root)

```
./setup.sh
```

NetApp Solution Automation

Procedure

1. Requirements for the Ansible control node,:
 - a. A Ubuntu/Debian machine with the following packages installed:
 - i. Python3
 - ii. Pip3
 - iii. Ansible (version greater than 2.10.0)
 - iv. Git

If you have a fresh Ubuntu/Debian machine without the above requirements installed, follow the below steps to setup that machine as the Ansible control node:

1. Create a .sh file

```
vi setup.sh
```

2. Paste the below content in the file

```
#!/bin/bash
echo "Installing Python ----->"
sudo apt-get -y install python3 >/dev/null
echo "Installing Python Pip ----->"
sudo apt-get -y install python3-pip >/dev/null
echo "Installing Ansible ----->"
python3 -W ignore -m pip --disable-pip-version-check install ansible
>/dev/null
echo "Installing git ----->"
sudo apt-get -y install git >/dev/null
```

3. Make the file executable

```
chmod +x setup.sh
```

4. Run the script (as root)

```
./setup.sh
```

NetApp solution automation

Procedure

This section describes the steps required to configure the parameters in AWX/Ansible Tower that prepare the environment for consuming NetApp automated solutions.

1. Configure the inventory.
 - a. Navigate to Resources → Inventories → Add and click Add Inventory.
 - b. Provide name and organization details and click Save.
 - c. In the Inventories page, click the inventory resources you just created.
 - d. If there are any inventory variables, paste them into the variables field.
 - e. Go to the Groups sub-menu and click Add.
 - f. Provide the name of the group, copy in the group variables (if necessary), and click Save.
 - g. Click the group created, go to the Hosts sub-menu and click Add New Host.

- h. Provide the hostname and IP address of the host, paste in the host variables (if necessary), and click Save.
2. Create credential types. For solutions involving ONTAP, Element, VMware, or any other HTTPS-based transport connection, you must configure the credential type to match the username and password entries.
 - a. Navigate to Administration → Credential Types and click Add.
 - b. Provide the name and description.
 - c. Paste the following content into the Input Configuration:

```
fields:
- id: username
type: string
label: Username
- id: password
type: string
label: Password
secret: true
- id: vsadmin_password
type: string
label: vsadmin_password
secret: true
```

- a. Paste the following content into the Injector Configuration:

```
extra_vars:
password: '{{ password }}'
username: '{{ username }}'
vsadmin_password: '{{ vsadmin_password }}'
```

1. Configure credentials.
 - a. Navigate to Resources → Credentials and click Add.
 - b. Enter the name and organization details.
 - c. Select the correct credential type; if you intend to use the standard SSH login, select the type Machine or alternatively select the custom credential type that you created.
 - d. Enter the other corresponding details and click Save.
2. Configure the project.
 - a. Navigate to Resources → Projects and click Add.
 - b. Enter the name and organization details.
 - c. Select Git for the Source Control Credential Type.
 - d. Paste the source control URL (or git clone URL) corresponding to the specific solution.
 - e. Optionally, if the Git URL is access controlled, create and attach the corresponding credential in Source Control Credential.

f. Click Save.

3. Configure the job template.

- a. Navigate to Resources → Templates → Add and click Add Job Template.
- b. Enter the name and description.
- c. Select the Job type; Run configures the system based on a playbook and Check performs a dry run of the playbook without actually configuring the system.
- d. Select the corresponding inventory, project, and credentials for the playbook.
- e. Select the playbook that you would like to run as a part of the job template.
- f. Usually the variables are pasted during runtime. Therefore, to get the prompt to populate the variables during runtime, make sure to tick the checkbox Prompt on Launch corresponding to the Variable field.
- g. Provide any other details as required and click Save.

4. Launch the job template.

- a. Navigate to Resources → Templates.
- b. Click the desired template and then click Launch.
- c. Fill in any variables if prompted on launch and then click Launch again.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.