



# **Preparing the source and target**

## **Cloud Manager**

Ben Cammett  
September 14, 2021

# Table of Contents

- Preparing the source and target. . . . . 1
  - Supported sync relationships . . . . . 1
  - Source and target requirements. . . . . 7

# Preparing the source and target

Prepare to sync data by verifying that your source and target are supported and setup.

## Supported sync relationships

Cloud Sync enables you to sync data from a source to a target (this is called a *sync relationship*). You should understand the supported relationships before you get started.

| Source location      | Supported target locations  |
|----------------------|---|
| Amazon EFS           | <ul style="list-style-type: none"><li>• Amazon EFS</li><li>• Amazon FSx for ONTAP</li><li>• Amazon S3</li><li>• Azure Blob</li><li>• Azure NetApp Files</li><li>• Cloud Volumes ONTAP</li><li>• Cloud Volumes Service</li><li>• Google Cloud Storage</li><li>• IBM Cloud Object Storage</li><li>• NFS server</li><li>• On-premises ONTAP cluster</li><li>• SMB server</li><li>• StorageGRID</li></ul> |
| Amazon FSx for ONTAP | <ul style="list-style-type: none"><li>• Amazon EFS</li><li>• Amazon FSx for ONTAP</li><li>• Amazon S3</li><li>• Azure Blob</li><li>• Azure NetApp Files</li><li>• Cloud Volumes ONTAP</li><li>• Cloud Volumes Service</li><li>• Google Cloud Storage</li><li>• IBM Cloud Object Storage</li><li>• NFS server</li><li>• On-premises ONTAP cluster</li><li>• SMB Server</li><li>• StorageGRID</li></ul> |

| Source location | Supported target locations  |
|-----------------|---|
| Amazon S3       | <ul style="list-style-type: none"> <li>• Amazon EFS</li> <li>• Amazon FSx for ONTAP</li> <li>• Amazon S3</li> <li>• Azure Blob</li> <li>• Azure NetApp Files</li> <li>• Cloud Volumes ONTAP</li> <li>• Cloud Volumes Service</li> <li>• Google Cloud Storage</li> <li>• IBM Cloud Object Storage</li> <li>• NFS server</li> <li>• On-premises ONTAP cluster</li> <li>• SMB Server</li> <li>• StorageGRID</li> </ul> |
| Azure Blob      | <ul style="list-style-type: none"> <li>• Amazon EFS</li> <li>• Amazon FSx for ONTAP</li> <li>• Amazon S3</li> <li>• Azure Blob</li> <li>• Azure NetApp Files</li> <li>• Cloud Volumes ONTAP</li> <li>• Cloud Volumes Service</li> <li>• Google Cloud Storage</li> <li>• IBM Cloud Object Storage</li> <li>• NFS server</li> <li>• On-premises ONTAP cluster</li> <li>• SMB Server</li> <li>• StorageGRID</li> </ul> |

| Source location     | Supported target locations  |
|---------------------|---|
| Azure NetApp Files  | <ul style="list-style-type: none"> <li>• Amazon EFS</li> <li>• Amazon FSx for ONTAP</li> <li>• Amazon S3</li> <li>• Azure Blob</li> <li>• Azure NetApp Files</li> <li>• Cloud Volumes ONTAP</li> <li>• Cloud Volumes Service</li> <li>• Google Cloud Storage</li> <li>• IBM Cloud Object Storage</li> <li>• NFS server</li> <li>• On-premises ONTAP cluster</li> <li>• SMB Server</li> <li>• StorageGRID</li> </ul> |
| Box <sup>1</sup>    | <ul style="list-style-type: none"> <li>• Amazon S3</li> <li>• IBM Cloud Object Storage</li> <li>• StorageGRID</li> </ul>  |
| Cloud Volumes ONTAP | <ul style="list-style-type: none"> <li>• Amazon EFS</li> <li>• Amazon FSx for ONTAP</li> <li>• Amazon S3</li> <li>• Azure Blob</li> <li>• Azure NetApp Files</li> <li>• Cloud Volumes ONTAP</li> <li>• Cloud Volumes Service</li> <li>• Google Cloud Storage</li> <li>• IBM Cloud Object Storage</li> <li>• NFS server</li> <li>• On-premises ONTAP cluster</li> <li>• SMB Server</li> <li>• StorageGRID</li> </ul> |

| Source location       | Supported target locations  |
|-----------------------|---|
| Cloud Volumes Service | <ul style="list-style-type: none"> <li>• Amazon EFS</li> <li>• Amazon FSx for ONTAP</li> <li>• Amazon S3</li> <li>• Azure Blob</li> <li>• Azure NetApp Files</li> <li>• Cloud Volumes ONTAP</li> <li>• Cloud Volumes Service</li> <li>• Google Cloud Storage</li> <li>• IBM Cloud Object Storage</li> <li>• NFS server</li> <li>• On-premises ONTAP cluster</li> <li>• SMB Server</li> <li>• StorageGRID</li> </ul>                             |
| Google Cloud Storage  | <ul style="list-style-type: none"> <li>• Amazon EFS</li> <li>• Amazon FSx for ONTAP</li> <li>• Amazon S3</li> <li>• Azure Blob</li> <li>• Azure NetApp Files</li> <li>• Cloud Volumes ONTAP</li> <li>• Cloud Volumes Service</li> <li>• Google Cloud Storage</li> <li>• IBM Cloud Object Storage</li> <li>• NFS server</li> <li>• On-premises ONTAP cluster</li> <li>• ONTAP S3 Storage</li> <li>• SMB Server</li> <li>• StorageGRID</li> </ul> |

| Source location          | Supported target locations  |
|--------------------------|---|
| IBM Cloud Object Storage | <ul style="list-style-type: none"> <li>• Amazon EFS</li> <li>• Amazon FSx for ONTAP</li> <li>• Amazon S3</li> <li>• Azure Blob</li> <li>• Azure NetApp Files</li> <li>• Cloud Volumes ONTAP</li> <li>• Cloud Volumes Service</li> <li>• Google Cloud Storage</li> <li>• IBM Cloud Object Storage</li> <li>• NFS server</li> <li>• On-premises ONTAP cluster</li> <li>• SMB Server</li> <li>• StorageGRID</li> </ul> |
| NFS server               | <ul style="list-style-type: none"> <li>• Amazon EFS</li> <li>• Amazon FSx for ONTAP</li> <li>• Amazon S3</li> <li>• Azure Blob</li> <li>• Azure NetApp Files</li> <li>• Cloud Volumes ONTAP</li> <li>• Cloud Volumes Service</li> <li>• Google Cloud Storage</li> <li>• IBM Cloud Object Storage</li> <li>• NFS server</li> <li>• On-premises ONTAP cluster</li> <li>• SMB Server</li> <li>• StorageGRID</li> </ul> |

| Source location       | Supported target locations  |
|-----------------------|---|
| On-prem ONTAP cluster | <ul style="list-style-type: none"> <li>• Amazon EFS</li> <li>• Amazon FSx for ONTAP</li> <li>• Amazon S3</li> <li>• Azure Blob</li> <li>• Azure NetApp Files</li> <li>• Cloud Volumes ONTAP</li> <li>• Cloud Volumes Service</li> <li>• Google Cloud Storage</li> <li>• IBM Cloud Object Storage</li> <li>• NFS server</li> <li>• On-premises ONTAP cluster</li> <li>• SMB Server</li> <li>• StorageGRID</li> </ul>                             |
| ONTAP S3 Storage      | <ul style="list-style-type: none"> <li>• Google Cloud Storage</li> <li>• SMB server</li> <li>• StorageGRID</li> <li>• ONTAP S3 Storage</li> </ul>   |
| SFTP <sup>1</sup>     | S3  |
| SMB server            | <ul style="list-style-type: none"> <li>• Amazon EFS</li> <li>• Amazon FSx for ONTAP</li> <li>• Amazon S3</li> <li>• Azure Blob</li> <li>• Azure NetApp Files</li> <li>• Cloud Volumes ONTAP</li> <li>• Cloud Volumes Service</li> <li>• Google Cloud Storage</li> <li>• IBM Cloud Object Storage</li> <li>• NFS server</li> <li>• On-premises ONTAP cluster</li> <li>• ONTAP S3 Storage</li> <li>• SMB Server</li> <li>• StorageGRID</li> </ul> |



| Source location | Supported target locations  |
|-----------------|---|
| StorageGRID     | <ul style="list-style-type: none"> <li>• Amazon EFS</li> <li>• Amazon FSx for ONTAP</li> <li>• Amazon S3</li> <li>• Azure Blob</li> <li>• Azure NetApp Files</li> <li>• Cloud Volumes ONTAP</li> <li>• Cloud Volumes Service</li> <li>• Google Cloud Storage</li> <li>• IBM Cloud Object Storage</li> <li>• NFS server</li> <li>• On-premises ONTAP cluster</li> <li>• ONTAP S3 Storage</li> <li>• SMB Server</li> <li>• StorageGRID</li> </ul> |

#### Notes:

1. Sync relationships with this source are supported by using the Cloud Sync API only.
2. You can choose a specific Azure Blob storage tier when a Blob container is the target:
  - Hot storage
  - Cool storage
3. You can choose a specific S3 storage class when Amazon S3 is the target:
  - Standard (this is the default class)
  - Intelligent-Tiering
  - Standard-Infrequent Access
  - One Zone-Infrequent Access
  - Glacier
  - Glacier Deep Archive
4. You can choose a specific storage class when a Google Cloud Storage bucket is the target:
  - Standard
  - Nearline
  - Coldline
  - Archive

## Source and target requirements

Verify that your source and targets meet the following requirements.

## Networking

- The source and target must have a network connection to the data broker.

For example, if an NFS server is in your data center and the data broker is in AWS, then you need a network connection (VPN or Direct Connect) from your network to the VPC.

- NetApp recommends configuring the source, target, and data broker to use a Network Time Protocol (NTP) service. The time difference between the three components should not exceed 5 minutes.

## Target directory

When you create a sync relationship, Cloud Sync enables you to select an existing target directory and then optionally create a new folder inside that directory. So be sure that your preferred target directory already exists.

## Permissions to read directories

In order to show every directory or folder in a source or target, Cloud Sync needs read permissions on the directory or folder.

### NFS

Permissions must be defined on the source/target with uid/gid on files and directories.

### Object storage

- For AWS and Google Cloud, the data broker must have list object permissions (these permissions are provided by default if you follow the data broker installation steps).
- For Azure, StorageGRID, and IBM, the credentials that you enter when setting up a sync relationship must have list object permissions.

### SMB

The SMB credentials that you enter when setting up a sync relationship must have list folder permissions.



The data broker ignores the following directories by default: .snapshot, ~snapshot, .copy-offload

## Amazon S3 bucket requirements

Make sure that your Amazon S3 bucket meets the following requirements.

### Supported data broker locations for Amazon S3

Sync relationships that include S3 storage require a data broker deployed in AWS or on your premises. In either case, Cloud Sync prompts you to associate the data broker with an AWS account during installation.

- [Learn how to deploy the AWS data broker](#)
- [Learn how to install the data broker on a Linux host](#)

### Supported AWS regions

All regions are supported except for the China and GovCloud (US) regions.

## Permissions required for S3 buckets in other AWS accounts

When setting up a sync relationship, you can specify an S3 bucket that resides in an AWS account that isn't associated with the data broker.

The [permissions included in this JSON file](#) must be applied to that S3 bucket so the data broker can access it. These permissions enable the data broker to copy data to and from the bucket and to list the objects in the bucket.


Note the following about the permissions included in the JSON file:

1. *<BucketName>* is the name of the bucket that resides in the AWS account that isn't associated with the data broker.
2. *<RoleARN>* should be replaced with one of the following:
  - If the data broker was manually installed on a Linux host, *RoleARN* should be the ARN of the AWS user for which you provided AWS credentials when deploying the data broker.
  - If the data broker was deployed in AWS using the CloudFormation template, *RoleARN* should be the ARN of the IAM role created by the template.

You can find the Role ARN by going to the EC2 console, selecting the data broker instance, and clicking the IAM role from the Description tab. You should then see the Summary page in the IAM console that contains the Role ARN.

### Summary

Delete role

**Role ARN** `arn:aws:iam::142999174890:role/tanyaBroker0304-DataBrokerIamRole-1VMHWXMW3AQ05` 

Role description [Edit](#)

## Azure Blob storage requirements

Make sure that your Azure Blob storage meets the following requirements.

### Supported data broker locations for Azure Blob


The data broker can reside in any location when a sync relationship includes Azure Blob storage.

### Supported Azure regions

All regions are supported except for the China, US Gov, and US DoD regions.

### Connection string required for relationships that include Azure Blob and NFS/SMB

When creating a sync relationship between an Azure Blob container and an NFS or SMB server, you need to provide Cloud Sync with the storage account connection string:

 **a63cde60b553020** - Access keys

Storage account

Search (Ctrl+ /)

Overview

Activity log

Access control (IAM)

Tags

Diagnose and solve problems

Storage Explorer (preview)

Settings

**Access keys**

CORS

Configuration

Encryption

Use access keys to authenticate your applications when making requests to this Azure storage account. Store your access keys securely - for example, using Azure Key Vault - and don't share them. We recommend regenerating your access keys regularly. You are provided two access keys so that you can maintain connections using one key while regenerating the other.

When you regenerate your access keys, you must update any Azure resources and applications that access this storage account to use the new keys. This action will not interrupt access to disks from your virtual machines. [Learn more](#)

Storage account name

a63cde60b553020

**key1**

Key

vScjFdvVZqIPyO/

Connection string

DefaultEndpoints

If you want to sync data between two Azure Blob containers, then the connection string must include a [shared access signature](#) (SAS). You also have the option to use a SAS when syncing between a Blob container and an NFS or SMB server.

The SAS must allow access to the Blob service and all resource types (Service, Container, and Object). The SAS must also include the following permissions:

- For the source Blob container: Read and List
- For the target Blob container: Read, Write, List, Add, and Create

Overview

Activity log

Access control (IAM)

Tags

Diagnose and solve problems

Storage Explorer (preview)

Settings

Access keys

CORS

Configuration

Encryption

**Shared access signature**

Firewalls and virtual networks

Advanced Threat Protection (pr...

Properties

Locks

Allowed services ⓘ  
☒ Blob ☐ File ☐ Queue ☐ Table

Allowed resource types ⓘ  
☒ Service ☒ Container ☒ Object

Allowed permissions ⓘ  
☒ Read ☒ Write ☒ Delete ☒ List ☒ Add ☒ Create ☐ Update ☐ Process

Start and expiry date/time ⓘ  
Start  
2018-10-23 10:07:32 AM  
End  
2019-10-23 6:07:32 PM  
(UTC-04:00) --- Current Time Zone ---

Allowed IP addresses ⓘ  
for example, 168.1.5.65 or 168.1.5.65-168.1.5.70

Allowed protocols ⓘ  
☒ HTTPS only ☐ HTTPS and HTTP

Signing key ⓘ  
key1

Generate SAS and connection string

## Azure NetApp Files requirement

Use the Premium or Ultra service level when you sync data to or from Azure NetApp Files. You might experience failures and performance issues if the disk service level is Standard.



Consult a solutions architect if you need help determining the right service level. The volume size and volume tier determines the throughput that you can get.

[Learn more about Azure NetApp Files service levels and throughput.](#)

## Box requirements

Cloud Sync supports [Box](#) as the source in a sync relationship when using the Cloud Sync API.

In order to copy from Box, you'll need to provide the following credentials:

- clientId
- clientSecret
- publicKeyId
- privateKey

- passphrase
- enterpriseld

[Learn more about using the API to create a sync relationship from Box.](#)

## Google Cloud Storage bucket requirements

Make sure that your Google Cloud Storage bucket meets the following requirements.

### Supported data broker locations for Google Cloud Storage

Sync relationships that include Google Cloud Storage require a data broker deployed in GCP or on your premises. Cloud Sync guides you through the data broker installation process when you create a sync relationship.

- [Learn how to deploy the GCP data broker](#)
- [Learn how to install the data broker on a Linux host](#)

### Supported GCP regions

All regions are supported.

### Permissions required for buckets in other Google Cloud projects

When setting up a sync relationship, you can choose from Google Cloud buckets in different projects, if you provide the required permissions to the data broker's service account. [Learn how to set up the service account.](#)

## ONTAP requirements

If the sync relationship includes Cloud Volumes ONTAP or an on-prem ONTAP cluster and you selected NFSv4 or later, then you'll need to enable NFSv4 ACLs on the ONTAP system. This is required to copy the ACLs.

### Permissions for a SnapMirror destination

If the source for a sync relationship is a SnapMirror destination (which is read-only), "read/list" permissions are sufficient to sync data from the source to a target.

## NFS server requirements

- The NFS server can be a NetApp system or a non-NetApp system.
- The file server must allow the data broker host to access the exports.
- NFS versions 3, 4.0, 4.1, and 4.2 are supported.

The desired version must be enabled on the server.

- If you want to sync NFS data from an ONTAP system, ensure that access to the NFS export list for an SVM is enabled (vserver nfs modify -vserver *svm\_name* -showmount enabled).



The default setting for showmount is *enabled* starting with ONTAP 9.2.

## ONTAP S3 Storage requirements

When you set up a sync relationship that includes [ONTAP S3 Storage](#), you'll need to provide the following:

- The IP address of the LIF that's connected to ONTAP S3
- The access key and secret key that ONTAP is configured to use

## SMB server requirements

- The SMB server can be a NetApp system or a non-NetApp system.
- You need to provide Cloud Sync with credentials that have permissions on the SMB server.
  - For a source SMB server, the following permissions are required: list and read.

Members of the Backup Operators group are supported with a source SMB server.

- For a target SMB server, the following permissions are required: list, read, and write.
- The file server must allow the data broker host to access the exports.
- SMB versions 1.0, 2.0, 2.1, 3.0 and 3.11 are supported.
- Grant the "Administrators" group with "Full Control" permissions to the source and target folders.

If you don't grant this permission, then the data broker might not have sufficient permissions to get the ACLs on a file or directory. If this occurs, you'll receive the following error: "getxattr error 95"

## SMB limitation for hidden directories and files

An SMB limitation affects hidden directories and files when syncing data between SMB servers. If any of the directories or files on the source SMB server were hidden through Windows, the hidden attribute isn't copied to the target SMB server.

## SMB sync behavior due to case-insensitivity limitation

The SMB protocol is case-insensitive, which means uppercase and lowercase letters are treated as being the same. This behavior can result in overwritten files and directory copy errors, if a sync relationship includes an SMB server and data already exists on the target.

For example, let's say that there's a file named "a" on the source and a file named "A" on the target. When Cloud Sync copies the file named "a" to the target, file "A" is overwritten by file "a" from the source.

In the case of directories, let's say that there's a directory named "b" on the source and a directory named "B" on the target. When Cloud Sync tries to copy the directory named "b" to the target, Cloud Sync receives an error that says the directory already exists. As a result, Cloud Sync always fails to copy the directory named "b."

The best way to avoid this limitation is to ensure that you sync data to an empty directory.

## Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

## Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.