

# OSAL User's Guide

Generated by Doxygen 1.8.13

## Contents

<b>1</b>	<b>Osai API Documentation</b>	<b>2</b>
<b>2</b>	<b>OSAL Introduction</b>	<b>3</b>
<b>3</b>	<b>Version Numbers</b>	<b>4</b>
<b>4</b>	<b>File System Overview</b>	<b>5</b>
<b>5</b>	<b>File Descriptors In Osai</b>	<b>6</b>
<b>6</b>	<b>Timer Overview</b>	<b>7</b>
<b>7</b>	<b>Deprecated List</b>	<b>7</b>
<b>8</b>	<b>Module Index</b>	<b>7</b>
8.1	Modules . . . . .	7
<b>9</b>	<b>Data Structure Index</b>	<b>8</b>
9.1	Data Structures . . . . .	8
<b>10</b>	<b>File Index</b>	<b>9</b>
10.1	File List . . . . .	9
<b>11</b>	<b>Module Documentation</b>	<b>11</b>
11.1	OSAL Semaphore State Defines . . . . .	11
11.1.1	Detailed Description . . . . .	11
11.1.2	Macro Definition Documentation . . . . .	11
11.2	OSAL Binary Semaphore APIs . . . . .	12
11.2.1	Detailed Description . . . . .	12
11.2.2	Function Documentation . . . . .	12
11.3	OSAL BSP low level access APIs . . . . .	18
11.3.1	Detailed Description . . . . .	18

11.3.2 Function Documentation . . . . .	18
11.4 OSAL Real Time Clock APIs . . . . .	19
11.4.1 Detailed Description . . . . .	19
11.4.2 Function Documentation . . . . .	19
11.5 OSAL Core Operation APIs . . . . .	31
11.5.1 Detailed Description . . . . .	31
11.5.2 Function Documentation . . . . .	31
11.6 OSAL Counting Semaphore APIs . . . . .	35
11.6.1 Detailed Description . . . . .	35
11.6.2 Function Documentation . . . . .	35
11.7 OSAL Directory APIs . . . . .	40
11.7.1 Detailed Description . . . . .	40
11.7.2 Function Documentation . . . . .	40
11.8 OSAL Return Code Defines . . . . .	44
11.8.1 Detailed Description . . . . .	45
11.8.2 Macro Definition Documentation . . . . .	45
11.9 OSAL Error Info APIs . . . . .	54
11.9.1 Detailed Description . . . . .	54
11.9.2 Function Documentation . . . . .	54
11.10 OSAL File Access Option Defines . . . . .	55
11.10.1 Detailed Description . . . . .	55
11.10.2 Macro Definition Documentation . . . . .	55
11.11 OSAL Reference Point For Seek Offset Defines . . . . .	56
11.11.1 Detailed Description . . . . .	56
11.11.2 Macro Definition Documentation . . . . .	56
11.12 OSAL Standard File APIs . . . . .	57
11.12.1 Detailed Description . . . . .	57
11.12.2 Function Documentation . . . . .	57

11.13OSAL File System Level APIs . . . . .	69
11.13.1 Detailed Description . . . . .	69
11.13.2 Function Documentation . . . . .	69
11.14OSAL Heap APIs . . . . .	77
11.14.1 Detailed Description . . . . .	77
11.14.2 Function Documentation . . . . .	77
11.15OSAL Object Type Defines . . . . .	78
11.15.1 Detailed Description . . . . .	78
11.15.2 Macro Definition Documentation . . . . .	78
11.16OSAL Object ID Utility APIs . . . . .	82
11.16.1 Detailed Description . . . . .	82
11.16.2 Function Documentation . . . . .	82
11.17OSAL Dynamic Loader and Symbol APIs . . . . .	89
11.17.1 Detailed Description . . . . .	89
11.17.2 Function Documentation . . . . .	89
11.18OSAL Mutex APIs . . . . .	94
11.18.1 Detailed Description . . . . .	94
11.18.2 Function Documentation . . . . .	94
11.19Network ID APIs . . . . .	99
11.19.1 Detailed Description . . . . .	99
11.19.2 Function Documentation . . . . .	99
11.20OSAL Printf APIs . . . . .	101
11.20.1 Detailed Description . . . . .	101
11.20.2 Function Documentation . . . . .	101
11.21OSAL Message Queue APIs . . . . .	103
11.21.1 Detailed Description . . . . .	103
11.21.2 Function Documentation . . . . .	103
11.22OSAL Select APIs . . . . .	108

11.22.1 Detailed Description . . . . .	108
11.22.2 Function Documentation . . . . .	108
11.23 OSAL Shell APIs . . . . .	111
11.23.1 Detailed Description . . . . .	111
11.23.2 Function Documentation . . . . .	111
11.24 OSAL Socket Address APIs . . . . .	112
11.24.1 Detailed Description . . . . .	112
11.24.2 Function Documentation . . . . .	112
11.25 OSAL Socket Management APIs . . . . .	116
11.25.1 Detailed Description . . . . .	116
11.25.2 Function Documentation . . . . .	116
11.26 OSAL Task APIs . . . . .	124
11.26.1 Detailed Description . . . . .	124
11.26.2 Function Documentation . . . . .	124
11.27 OSAL Time Base APIs . . . . .	131
11.27.1 Detailed Description . . . . .	131
11.27.2 Function Documentation . . . . .	131
11.28 OSAL Timer APIs . . . . .	137
11.28.1 Detailed Description . . . . .	137
11.28.2 Function Documentation . . . . .	137

<b>12 Data Structure Documentation</b>	<b>143</b>
12.1 OS_bin_sem_prop_t Struct Reference	143
12.1.1 Detailed Description	143
12.1.2 Field Documentation	143
12.2 OS_count_sem_prop_t Struct Reference	144
12.2.1 Detailed Description	144
12.2.2 Field Documentation	144
12.3 os_dirent_t Struct Reference	145
12.3.1 Detailed Description	145
12.3.2 Field Documentation	145
12.4 OS_FdSet Struct Reference	145
12.4.1 Detailed Description	146
12.4.2 Field Documentation	146
12.5 OS_file_prop_t Struct Reference	146
12.5.1 Detailed Description	146
12.5.2 Field Documentation	147
12.6 os_fsinfo_t Struct Reference	147
12.6.1 Detailed Description	148
12.6.2 Field Documentation	148
12.7 os_fstat_t Struct Reference	149
12.7.1 Detailed Description	149
12.7.2 Field Documentation	149
12.8 OS_heap_prop_t Struct Reference	150
12.8.1 Detailed Description	150
12.8.2 Field Documentation	150
12.9 OS_module_address_t Struct Reference	151
12.9.1 Detailed Description	151
12.9.2 Field Documentation	151

12.10OS_module_prop_t Struct Reference . . . . .	153
12.10.1 Detailed Description . . . . .	153
12.10.2 Field Documentation . . . . .	153
12.11OS_mut_sem_prop_t Struct Reference . . . . .	154
12.11.1 Detailed Description . . . . .	155
12.11.2 Field Documentation . . . . .	155
12.12OS_queue_prop_t Struct Reference . . . . .	155
12.12.1 Detailed Description . . . . .	156
12.12.2 Field Documentation . . . . .	156
12.13OS_SockAddr_t Struct Reference . . . . .	156
12.13.1 Detailed Description . . . . .	157
12.13.2 Field Documentation . . . . .	157
12.14OS_SockAddrData_t Union Reference . . . . .	157
12.14.1 Detailed Description . . . . .	158
12.14.2 Field Documentation . . . . .	158
12.15OS_socket_prop_t Struct Reference . . . . .	159
12.15.1 Detailed Description . . . . .	159
12.15.2 Field Documentation . . . . .	159
12.16OS_static_symbol_record_t Struct Reference . . . . .	160
12.16.1 Detailed Description . . . . .	160
12.16.2 Field Documentation . . . . .	160
12.17OS_statvfs_t Struct Reference . . . . .	161
12.17.1 Detailed Description . . . . .	161
12.17.2 Field Documentation . . . . .	161
12.18OS_task_prop_t Struct Reference . . . . .	162
12.18.1 Detailed Description . . . . .	162
12.18.2 Field Documentation . . . . .	162
12.19OS_time_t Struct Reference . . . . .	163
12.19.1 Detailed Description . . . . .	163
12.19.2 Field Documentation . . . . .	164
12.20OS_timebase_prop_t Struct Reference . . . . .	164
12.20.1 Detailed Description . . . . .	164
12.20.2 Field Documentation . . . . .	164
12.21OS_timer_prop_t Struct Reference . . . . .	165
12.21.1 Detailed Description . . . . .	166
12.21.2 Field Documentation . . . . .	166

<b>13 File Documentation</b>	<b>167</b>
13.1 build/doc/osconfig-example.h File Reference	167
13.1.1 Macro Definition Documentation	168
13.2 cfe/docs/src/cfs_versions.dox File Reference	176
13.3 cfe/docs/src/osal_fs.dox File Reference	176
13.4 cfe/docs/src/osal_timer.dox File Reference	176
13.5 cfe/docs/src/osalmain.dox File Reference	176
13.6 osal/src/os/inc/common_types.h File Reference	176
13.6.1 Macro Definition Documentation	177
13.6.2 Typedef Documentation	178
13.6.3 Function Documentation	182
13.7 osal/src/os/inc/osapi-binsem.h File Reference	183
13.8 osal/src/os/inc/osapi-bsp.h File Reference	184
13.9 osal/src/os/inc/osapi-clock.h File Reference	184
13.9.1 Enumeration Type Documentation	185
13.10 osal/src/os/inc/osapi-common.h File Reference	186
13.10.1 Typedef Documentation	187
13.10.2 Enumeration Type Documentation	187
13.11 osal/src/os/inc/osapi-constants.h File Reference	188
13.11.1 Macro Definition Documentation	189
13.12 osal/src/os/inc/osapi-countsem.h File Reference	190
13.13 osal/src/os/inc/osapi-dir.h File Reference	190
13.13.1 Macro Definition Documentation	191
13.14 osal/src/os/inc/osapi-error.h File Reference	191
13.14.1 Macro Definition Documentation	193
13.14.2 Typedef Documentation	194
13.15 osal/src/os/inc/osapi-file.h File Reference	194
13.15.1 Macro Definition Documentation	196



13.15.2 Enumeration Type Documentation . . . . .	197
13.16osal/src/os/inc/osapi-filesys.h File Reference . . . . .	198
13.16.1 Macro Definition Documentation . . . . .	199
13.17osal/src/os/inc/osapi-heap.h File Reference . . . . .	199
13.18osal/src/os/inc/osapi-idmap.h File Reference . . . . .	200
13.18.1 Macro Definition Documentation . . . . .	201
13.19osal/src/os/inc/osapi-macros.h File Reference . . . . .	202
13.19.1 Macro Definition Documentation . . . . .	202
13.20osal/src/os/inc/osapi-module.h File Reference . . . . .	204
13.20.1 Macro Definition Documentation . . . . .	204
13.21osal/src/os/inc/osapi-mutex.h File Reference . . . . .	205
13.22osal/src/os/inc/osapi-network.h File Reference . . . . .	206
13.23osal/src/os/inc/osapi-printf.h File Reference . . . . .	206
13.24osal/src/os/inc/osapi-queue.h File Reference . . . . .	207
13.25osal/src/os/inc/osapi-select.h File Reference . . . . .	207
13.25.1 Enumeration Type Documentation . . . . .	208
13.26osal/src/os/inc/osapi-shell.h File Reference . . . . .	208
13.27osal/src/os/inc/osapi-sockets.h File Reference . . . . .	209
13.27.1 Macro Definition Documentation . . . . .	210
13.27.2 Enumeration Type Documentation . . . . .	210
13.28osal/src/os/inc/osapi-task.h File Reference . . . . .	211
13.28.1 Macro Definition Documentation . . . . .	212
13.28.2 Typedef Documentation . . . . .	213
13.28.3 Function Documentation . . . . .	214
13.29osal/src/os/inc/osapi-timebase.h File Reference . . . . .	214
13.29.1 Typedef Documentation . . . . .	215
13.30osal/src/os/inc/osapi-timer.h File Reference . . . . .	215
13.30.1 Typedef Documentation . . . . .	216
13.31osal/src/os/inc/osapi-version.h File Reference . . . . .	216
13.31.1 Detailed Description . . . . .	217
13.31.2 Macro Definition Documentation . . . . .	217
13.32osal/src/os/inc/osapi.h File Reference . . . . .	220

## 1 Osal API Documentation

- General Information and Concepts
  - [OSAL Introduction](#)
- Core
  - [OSAL Return Code Defines](#)
  - [OSAL Object Type Defines](#)
  - [APIs](#)
    - \* [OSAL Core Operation APIs](#)
    - \* [OSAL Object ID Utility APIs](#)
    - \* [OSAL Task APIs](#)
    - \* [OSAL Message Queue APIs](#)
    - \* [OSAL Heap APIs](#)
    - \* [OSAL Error Info APIs](#)
    - \* [OSAL Select APIs](#)
    - \* [OSAL Printf APIs](#)
    - \* [OSAL BSP low level access APIs](#)
    - \* [OSAL Real Time Clock APIs](#)
    - \* [OSAL Shell APIs](#)
  - [Common Reference](#)
  - [Return Code Reference](#)
  - [Id Map Reference](#)
  - [Clock Reference](#)
  - [Task Reference](#)
  - [Message Queue Reference](#)
  - [Heap Reference](#)
  - [Select Reference](#)
  - [Printf Reference](#)
  - [BSP Reference](#)
  - [Shell Reference](#)
- File System
  - [File System Overview](#)
  - [File Descriptors In Osal](#)
  - [OSAL File Access Option Defines](#)
  - [OSAL Reference Point For Seek Offset Defines](#)
  - [APIs](#)
    - \* [OSAL Standard File APIs](#)
    - \* [OSAL Directory APIs](#)
    - \* [OSAL File System Level APIs](#)

- [File System Reference](#)
  - [File Reference](#)
  - [Directory Reference](#)
- Object File Loader
  - APIs
    - \* [OSAL Dynamic Loader and Symbol APIs](#)
  - [File Loader Reference](#)
- Network
  - APIs
    - \* [Network ID APIs](#)
    - \* [OSAL Socket Address APIs](#)
    - \* [OSAL Socket Management APIs](#)
  - [Network Reference](#)
  - [Socket Reference](#)
- Timer
  - [Timer Overview](#)
  - APIs
    - \* [OSAL Time Base APIs](#)
    - \* [OSAL Timer APIs](#)
  - [Timer Reference](#)
  - [Time Base Reference](#)
- Semaphore and Mutex
  - [OSAL Semaphore State Defines](#)
  - APIs
    - \* [OSAL Binary Semaphore APIs](#)
    - \* [OSAL Counting Semaphore APIs](#)
    - \* [OSAL Mutex APIs](#)
  - [Binary Semaphore Reference](#)
  - [Counting Semaphore Reference](#)
  - [Mutex Reference](#)

## 2 OSAL Introduction

The goal of this library is to promote the creation of portable and reusable real time embedded system software. Given the necessary OS abstraction layer implementations, the same embedded software should compile and run on a number of platforms ranging from spacecraft computer systems to desktop PCs.

The OS Application Program Interfaces (APIs) are broken up into core, file system, loader, network, and timer APIs. See the related document sections for full descriptions.

### Note

The majority of these APIs should be called from a task running in the context of an OSAL application and in general should not be called from an ISR. There are a few exceptions, such as the ability to give a binary semaphore from an ISR.

## 3 Version Numbers

### Version Number Semantics

The version number is a sequence of four numbers, generally separated by dots when written. These are, in order, the Major number, the Minor number, the Revision number, and the Mission Revision number. Missions may modify the Mission Revision information as needed to suit their needs.

It is important to note that Major, Minor, and Revision numbers are only updated upon official releases of tagged versions, **NOT** on development builds. We aim to follow the Semantic Versioning v2.0 specification with our versioning.

The MAJOR number shall be incremented on release to indicate when there is a change to an API that may cause existing, correctly-written cFS components to stop working. It may also be incremented for a release that contains changes deemed to be of similar impact, even if there are no actual changes to the API.

The MINOR number shall be incremented on release to indicate the addition of features to the API which do not break the existing code. It may also be incremented for a release that contains changes deemed to be of similar impact, even if there are no actual updates to the API.

The REVISION number shall be incremented on changes that benefit from unique identification such as bug fixes or major documentation updates. The Revision number may also be updated if there are other changes contained within a release that make it desirable for applications to distinguish one release from another. **WARNING:** The revision number is set to the number 99 in development builds. To distinguish between development builds refer to the BUILD\_NUMBER and BUILD\_BASELINE detailed in the section "Identifying Development Builds".

The Major, Minor, and Revision numbers are provided in this header file as part of the API definition; this macro must expand to a simple integer value, so that it can be used in simple if directives by the macro preprocessor.

The Mission Version number shall be set to zero in all officially released packages, and is entirely reserved for the use of the mission. The Mission Version is provided as a simple macro defined in the cfe\_platform\_cfg.h header file.

### Version Number Flexibility

The major number may increment when there is no breaking change to the API, if the changes are significant enough to warrant the same level of attention as a breaking API change.

The minor number may increment when there have been no augmentations to the API, if changes are as significant as additions to the public API.

The revision numbers may increment in implementations where no actual implementation-specific code has changed, if there are other changes within the release with similar significance.

### How and Where Defined

The Major, Minor, and Revision components of the version are provided as simple macros defined in the cfe\_version.h header file as part of the API definition; these macros must expand to simple integer values, so that they can be used in simple if directives by the macro preprocessor.

The Mission Version is provided as a simple macro defined in the cfe\_platform\_cfg.h header file. As delivered in official releases, these macros must expand to simple integer values, so that they can be used in simple macro preprocessor conditions, but delivered code should not prevent a mission from, for example, deciding that the Mission Version is actually a text string.

### Identifying Development Builds

In order to distinguish between development versions, we also provide a BUILD\_NUMBER.

The BUILD\_NUMBER reflects the number of commits since the BUILD\_BASELINE, a baseline git tag, for each particular component. The BUILD\_NUMBER integer increases monotonically for a given development cycle. The BUILD\_BASELINE identifies the current development cycle and is a git tag with format vX.Y.Z. The Codename used in the version string also refers to the current development cycle. When a new baseline tag and codename are created, the BUILD\_NUMBER resets to zero and begins increasing from a new baseline.

### Templates for the version and version string

The following templates are the code to be used in cfe\_version.h for either official releases or development builds. The apps and repositories follow the same pattern by replacing the CFE\_ prefix with the appropriate name; for example, osal uses OS\_, psp uses CFE\_PSP\_IMPL, and so on.

#### Template for Official Releases

```
/*<! Official Release Version Number */
#define CFE_SRC_VERSION \
    CFE_STR(CFE_MAJOR_VERSION) "." \
    CFE_STR(CFE_MINOR_VERSION) "." \
    CFE_STR(CFE_REVISION) "." \
    CFE_STR(CFE_MISSION_REV)

#define CFE_VERSION_STRING \
    "cFE version " CFE_SRC_VERSION
```

#### Template for Development Builds

```
/*! @brief Development Build Version Number.
 * Baseline git tag + Number of commits since baseline. @n
 * See cfs_versions.dox for format differences between development and release versions.
 */
#define CFE_SRC_VERSION \
    CFE_BUILD_BASELINE CFE_STR(CFE_BUILD_NUMBER)

/*! @brief Development Build Version String.
 * Reports the current development build's baseline, number, and name. Also includes a note about the latest official release.
 * See cfs_versions.dox for format differences between development and release versions.
 */
#define CFE_VERSION_STRING \
    " cFE Development Build " \
    CFE_SRC_VERSION " (Codename: CONSTELLATION_NAME)" /* Codename for current development */ \
    ", Last Official Release: cfe vX.Y.Z" /* For full support please use this version */
```

## 4 File System Overview

The File System API is a thin wrapper around a selection of POSIX file APIs. In addition the File System API presents a common directory structure and volume view regardless of the underlying system type. For example, vxWorks uses MS-DOS style volume names and directories where a vxWorks RAM disk might have the volume "RAM:0". With this File System API, volumes are represented as Unix-style paths where each volume is mounted on the root file system:

- RAM:0/file1.dat becomes /mnt/ram/file1.dat
- FL:0/file2.dat becomes /mnt/fl/file2.dat

This abstraction allows the applications to use the same paths regardless of the implementation and it also allows file systems to be simulated on a desktop system for testing. On a desktop Linux system, the file system abstraction can be set up to map virtual devices to a regular directory. This is accomplished through the OS\_mkfs call, OS\_mount call, and a BSP specific volume table that maps the virtual devices to real devices or underlying file systems.

In order to make this file system volume abstraction work, a "Volume Table" needs to be provided in the Board Support Package of the application. The table has the following fields:

- Device Name: This is the name of the virtual device that the Application uses. Common names are "ramdisk1", "flash1", or "volatile1" etc. But the name can be any unique string.
- Physical Device Name: This is an implementation specific field. For vxWorks it is not needed and can be left blank. For a File system based implementation, it is the "mount point" on the root file system where all of the volume will be mounted. A common place for this on Linux could be a user's home directory, "/tmp", or even the current working directory ".". In the example of "/tmp" all of the directories created for the volumes would be under "/tmp" on the Linux file system. For a real disk device in Linux, such as a RAM disk, this field is the device name "/dev/ram0".
- Volume Type: This field defines the type of volume. The types are: FS\_BASED which uses the existing file system, RAM\_DISK which uses a RAM\_DISK device in vxWorks, RTEMS, or Linux, FLASH\_DISK\_FORMAT which uses a flash disk that is to be formatted before use, FLASH\_DISK\_INIT which uses a flash disk with an existing format that is just to be initialized before it's use, EEPROM which is for an EEPROM or PROM based system.
- Volatile Flag: This flag indicates that the volume or disk is a volatile disk (RAM disk ) or a non-volatile disk, that retains its contents when the system is rebooted. This should be set to TRUE or FALSE.
- Free Flag: This is an internal flag that should be set to FALSE or zero.
- Is Mounted Flag: This is an internal flag that should be set to FALSE or zero. Note that a "pre-mounted" FS\_BASED path can be set up by setting this flag to one.
- Volume Name: This is an internal field and should be set to a space character " ".
- Mount Point Field: This is an internal field and should be set to a space character " ".
- Block Size Field: This is used to record the block size of the device and does not need to be set by the user.

## 5 File Descriptors In Osal

The OSAL uses abstracted file descriptors. This means that the file descriptors passed back from the OS\_open and OS\_creat calls will only work with other OSAL OS\_\* calls. The reasoning for this is as follows:

Because the OSAL now keeps track of all file descriptors, OSAL specific information can be associated with a specific file descriptor in an OS independent way. For instance, the path of the file that the file descriptor points to can be easily retrieved. Also, the OSAL task ID of the task that opened the file can also be retrieved easily. Both of these pieces of information are very useful when trying to determine statistics for a task, or the entire system. This information can all be retrieved with a single API, OS\_FDGetInfo.

All of possible file system calls are not implemented. "Special" files requiring OS specific control/operations are by nature not portable. Abstraction in this case is not possible, so the raw OS calls should be used (including open/close/etc).

Mixing with OSAL calls is not supported for such cases. [OS\\_TranslatePath](#) is available to support using open directly by an app and maintain abstraction on the file system.

There are some small drawbacks with the OSAL file descriptors. Because the related information is kept in a table, there is a define called `OS_MAX_NUM_OPEN_FILES` that defines the maximum number of file descriptors available. This is a configuration parameter, and can be changed to fit your needs.

Also, if you open or create a file not using the OSAL calls (`OS_open` or `OS_creat`) then none of the other `OS_*` calls that accept a file descriptor as a parameter will work (the results of doing so are undefined). Therefore, if you open a file with the underlying OS's open call, you must continue to use the OS's calls until you close the file descriptor. Be aware that by doing this your software may no longer be OS agnostic.

## 6 Timer Overview

The timer API is a generic interface to the OS timer facilities. It is implemented using the POSIX timers on Linux and vxWorks and the native timer API on RTEMS. The number of timers supported is controlled by the configuration parameter `OS_MAX_TIMERS`.

## 7 Deprecated List

### Global [OS\\_TaskRegister](#) (void)

Explicit registration call no longer needed

## 8 Module Index

### 8.1 Modules

Here is a list of all modules:

<b>OSAL Semaphore State Defines</b>	<b>11</b>
<b>OSAL Binary Semaphore APIs</b>	<b>12</b>
<b>OSAL BSP low level access APIs</b>	<b>18</b>
<b>OSAL Real Time Clock APIs</b>	<b>19</b>
<b>OSAL Core Operation APIs</b>	<b>31</b>
<b>OSAL Counting Semaphore APIs</b>	<b>35</b>
<b>OSAL Directory APIs</b>	<b>40</b>
<b>OSAL Return Code Defines</b>	<b>44</b>
<b>OSAL Error Info APIs</b>	<b>54</b>

OSAL File Access Option Defines	55
OSAL Reference Point For Seek Offset Defines	56
OSAL Standard File APIs	57
OSAL File System Level APIs	69
OSAL Heap APIs	77
OSAL Object Type Defines	78
OSAL Object ID Utility APIs	82
OSAL Dynamic Loader and Symbol APIs	89
OSAL Mutex APIs	94
Network ID APIs	99
OSAL Printf APIs	101
OSAL Message Queue APIs	103
OSAL Select APIs	108
OSAL Shell APIs	111
OSAL Socket Address APIs	112
OSAL Socket Management APIs	116
OSAL Task APIs	124
OSAL Time Base APIs	131
OSAL Timer APIs	137

## 9 Data Structure Index

### 9.1 Data Structures

Here are the data structures with brief descriptions:

<a href="#">OS_bin_sem_prop_t</a> OSAL binary semaphore properties	143
<a href="#">OS_count_sem_prop_t</a> OSAL counting semaphore properties	144
<a href="#">os_dirent_t</a> Directory entry	145
<a href="#">OS_FdSet</a> An abstract structure capable of holding several OSAL IDs	145



<a href="#">OS_file_prop_t</a>	
OSAL file properties	146
<a href="#">os_fsinfo_t</a>	
OSAL file system info	147
<a href="#">os_fstat_t</a>	
File system status	149
<a href="#">OS_heap_prop_t</a>	
OSAL heap properties	150
<a href="#">OS_module_address_t</a>	
OSAL module address properties	151
<a href="#">OS_module_prop_t</a>	
OSAL module properties	153
<a href="#">OS_mut_sem_prop_t</a>	
OSAL mutex properties	154
<a href="#">OS_queue_prop_t</a>	
OSAL queue properties	155
<a href="#">OS_SockAddr_t</a>	
Encapsulates a generic network address	156
<a href="#">OS_SockAddrData_t</a>	
Storage buffer for generic network address	157
<a href="#">OS_socket_prop_t</a>	
Encapsulates socket properties	159
<a href="#">OS_static_symbol_record_t</a>	
Associates a single symbol name with a memory address	160
<a href="#">OS_statvfs_t</a>	
	161
<a href="#">OS_task_prop_t</a>	
OSAL task properties	162
<a href="#">OS_time_t</a>	
OSAL time interval structure	163
<a href="#">OS_timebase_prop_t</a>	
Time base properties	164
<a href="#">OS_timer_prop_t</a>	
Timer properties	165

## 10 File Index

### 10.1 File List

Here is a list of all files with brief descriptions:

<a href="#">build/doc/osconfig-example.h</a>	167
<a href="#">osal/src/os/inc/common_types.h</a>	176
<a href="#">osal/src/os/inc/osapi-binsem.h</a>	183
<a href="#">osal/src/os/inc/osapi-bsp.h</a>	184
<a href="#">osal/src/os/inc/osapi-clock.h</a>	184
<a href="#">osal/src/os/inc/osapi-common.h</a>	186
<a href="#">osal/src/os/inc/osapi-constants.h</a>	188
<a href="#">osal/src/os/inc/osapi-countsem.h</a>	190
<a href="#">osal/src/os/inc/osapi-dir.h</a>	190
<a href="#">osal/src/os/inc/osapi-error.h</a>	191
<a href="#">osal/src/os/inc/osapi-file.h</a>	194
<a href="#">osal/src/os/inc/osapi-filesys.h</a>	198
<a href="#">osal/src/os/inc/osapi-heap.h</a>	199
<a href="#">osal/src/os/inc/osapi-idmap.h</a>	200
<a href="#">osal/src/os/inc/osapi-macros.h</a>	202
<a href="#">osal/src/os/inc/osapi-module.h</a>	204
<a href="#">osal/src/os/inc/osapi-mutex.h</a>	205
<a href="#">osal/src/os/inc/osapi-network.h</a>	206
<a href="#">osal/src/os/inc/osapi-printf.h</a>	206
<a href="#">osal/src/os/inc/osapi-queue.h</a>	207
<a href="#">osal/src/os/inc/osapi-select.h</a>	207
<a href="#">osal/src/os/inc/osapi-shell.h</a>	208
<a href="#">osal/src/os/inc/osapi-sockets.h</a>	209
<a href="#">osal/src/os/inc/osapi-task.h</a>	211
<a href="#">osal/src/os/inc/osapi-timebase.h</a>	214
<a href="#">osal/src/os/inc/osapi-timer.h</a>	215
<a href="#">osal/src/os/inc/osapi-version.h</a>	
Purpose:	216
<a href="#">osal/src/os/inc/osapi.h</a>	220

## 11 Module Documentation

### 11.1 OSAL Semaphore State Defines

#### Macros

- `#define OS_SEM_FULL 1`  
*Semaphore full state.*
- `#define OS_SEM_EMPTY 0`  
*Semaphore empty state.*

#### 11.1.1 Detailed Description

#### 11.1.2 Macro Definition Documentation

##### 11.1.2.1 OS\_SEM\_EMPTY

```
#define OS_SEM_EMPTY 0
```

Semaphore empty state.

Definition at line 35 of file osapi-binsem.h.

##### 11.1.2.2 OS\_SEM\_FULL

```
#define OS_SEM_FULL 1
```

Semaphore full state.

Definition at line 34 of file osapi-binsem.h.

## 11.2 OSAL Binary Semaphore APIs

### Functions

- `int32 OS_BinSemCreate (osal_id_t *sem_id, const char *sem_name, uint32 sem_initial_value, uint32 options)`  
*Creates a binary semaphore.*
- `int32 OS_BinSemFlush (osal_id_t sem_id)`  
*Unblock all tasks pending on the specified semaphore.*
- `int32 OS_BinSemGive (osal_id_t sem_id)`  
*Increment the semaphore value.*
- `int32 OS_BinSemTake (osal_id_t sem_id)`  
*Decrement the semaphore value.*
- `int32 OS_BinSemTimedWait (osal_id_t sem_id, uint32 msecs)`  
*Decrement the semaphore value with a timeout.*
- `int32 OS_BinSemDelete (osal_id_t sem_id)`  
*Deletes the specified Binary Semaphore.*
- `int32 OS_BinSemGetIdByName (osal_id_t *sem_id, const char *sem_name)`  
*Find an existing semaphore ID by name.*
- `int32 OS_BinSemGetInfo (osal_id_t sem_id, OS_bin_sem_prop_t *bin_prop)`  
*Fill a property object buffer with details regarding the resource.*

### 11.2.1 Detailed Description

### 11.2.2 Function Documentation

#### 11.2.2.1 OS\_BinSemCreate()

```
int32 OS_BinSemCreate (
    osal_id_t * sem_id,
    const char * sem_name,
    uint32 sem_initial_value,
    uint32 options )
```

Creates a binary semaphore.

Creates a binary semaphore with initial value specified by `sem_initial_value` and name specified by `sem_name`. `sem_id` will be returned to the caller

#### Parameters

out	<code>sem_id</code>	will be set to the non-zero ID of the newly-created resource
in	<code>sem_name</code>	the name of the new resource to create
in	<code>sem_initial_value</code>	the initial value of the binary semaphore
in	<code>options</code>	Reserved for future use, should be passed as 0.

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if sen name or sem_id are NULL
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NO_FREE_IDS</a>	if all of the semaphore ids are taken
<a href="#">OS_ERR_NAME_TAKEN</a>	if this is already the name of a binary semaphore
<a href="#">OS_SEM_FAILURE</a>	if the OS call failed

**11.2.2.2 OS\_BinSemDelete()**

```
int32 OS_BinSemDelete (
    osal_id_t sem_id )
```

Deletes the specified Binary Semaphore.

This is the function used to delete a binary semaphore in the operating system. This also frees the respective sem\_id to be used again when another semaphore is created.

**Parameters**

in	<i>sem_id</i>	The object ID to delete
----	---------------	-------------------------

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a valid binary semaphore
<a href="#">OS_SEM_FAILURE</a>	the OS call failed

**11.2.2.3 OS\_BinSemFlush()**

```
int32 OS_BinSemFlush (
    osal_id_t sem_id )
```

Unblock all tasks pending on the specified semaphore.

The function unblocks all tasks pending on the specified semaphore. However, this function does not change the state of the semaphore.

#### Parameters

in	<i>sem_id</i>	The object ID to operate on
----	---------------	-----------------------------

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a binary semaphore
<a href="#">OS_SEM_FAILURE</a>	if an unspecified failure occurs

#### 11.2.2.4 OS\_BinSemGetIdByName()

```
int32 OS_BinSemGetIdByName (
    osal_id_t * sem_id,
    const char * sem_name )
```

Find an existing semaphore ID by name.

This function tries to find a binary sem Id given the name of a bin\_sem The id is returned through sem\_id

#### Parameters

out	<i>sem_id</i>	will be set to the ID of the existing resource
in	<i>sem_name</i>	the name of the existing resource to find

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	is semid or sem_name are NULL pointers
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NAME_NOT_FOUND</a>	if the name was not found in the table

## 11.2.2.5 OS\_BinSemGetInfo()

```
int32 OS_BinSemGetInfo (
    osal_id_t sem_id,
    OS_bin_sem_prop_t * bin_prop )
```

Fill a property object buffer with details regarding the resource.

This function will pass back a pointer to structure that contains all of the relevant info( name and creator) about the specified binary semaphore.

## Parameters

in	<i>sem_id</i>	The object ID to operate on
out	<i>bin_prop</i>	The property object buffer to fill

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a valid semaphore
<a href="#">OS_INVALID_POINTER</a>	if the bin_prop pointer is null

## 11.2.2.6 OS\_BinSemGive()

```
int32 OS_BinSemGive (
    osal_id_t sem_id )
```

Increment the semaphore value.

The function unlocks the semaphore referenced by sem\_id by performing a semaphore unlock operation on that semaphore. If the semaphore value resulting from this operation is positive, then no threads were blocked waiting for the semaphore to become unlocked; the semaphore value is simply incremented for this semaphore.

## Parameters

in	<i>sem_id</i>	The object ID to operate on
----	---------------	-----------------------------

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_SEM_FAILURE</a>	the semaphore was not previously initialized or is not in the array of semaphores defined by the system
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a binary semaphore

**11.2.2.7 OS\_BinSemTake()**

```
int32 OS_BinSemTake (
    osal_id_t sem_id )
```

Decrement the semaphore value.

The locks the semaphore referenced by sem\_id by performing a semaphore lock operation on that semaphore. If the semaphore value is currently zero, then the calling thread shall not return from the call until it either locks the semaphore or the call is interrupted.

**Parameters**

in	<i>sem</i> ↔ _id	The object ID to operate on
----	---------------------	-----------------------------

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	the Id passed in is not a valid binary semaphore
<a href="#">OS_SEM_FAILURE</a>	if the OS call failed

**11.2.2.8 OS\_BinSemTimedWait()**

```
int32 OS_BinSemTimedWait (
    osal_id_t sem_id,
    uint32 msec )
```



Decrement the semaphore value with a timeout.

The function locks the semaphore referenced by `sem_id`. However, if the semaphore cannot be locked without waiting for another process or thread to unlock the semaphore, this wait shall be terminated when the specified timeout, msec, expires.

#### Parameters

in	<i>sem_id</i>	The object ID to operate on
in	<i>msecs</i>	The maximum amount of time to block, in milliseconds

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_SEM_TIMEOUT</a>	if semaphore was not relinquished in time
<a href="#">OS_SEM_FAILURE</a>	the semaphore was not previously initialized or is not in the array of semaphores defined by the system
<a href="#">OS_ERR_INVALID_ID</a>	if the ID passed in is not a valid semaphore ID

## 11.3 OSAL BSP low level access APIs

### Functions

- `uint32 OS_BSP_GetArgC (void)`
- `char *const * OS_BSP_GetArgV (void)`
- `void OS_BSP_SetExitCode (int32 code)`

### 11.3.1 Detailed Description

These are for OSAL internal BSP information access to pass any BSP-specific boot/command line/startup arguments through to the application, and return a status code back to the OS after exit.

Not intended for user application use

### 11.3.2 Function Documentation

#### 11.3.2.1 OS\_BSP\_GetArgC()

```
uint32 OS_BSP_GetArgC (  
    void )
```

#### 11.3.2.2 OS\_BSP\_GetArgV()

```
char* const* OS_BSP_GetArgV (  
    void )
```

#### 11.3.2.3 OS\_BSP\_SetExitCode()

```
void OS_BSP_SetExitCode (  
    int32 code )
```

## 11.4 OSAL Real Time Clock APIs

### Functions

- `int32 OS_GetLocalTime (OS_time_t *time_struct)`  
*Get the local time.*
- `int32 OS_SetLocalTime (const OS_time_t *time_struct)`  
*Set the local time.*
- static `int64 OS_TimeGetTotalSeconds (OS_time_t tm)`  
*Get interval from an OS\_time\_t object normalized to whole number of seconds.*
- static `int64 OS_TimeGetTotalMilliseconds (OS_time_t tm)`  
*Get interval from an OS\_time\_t object normalized to millisecond units.*
- static `int64 OS_TimeGetTotalMicroseconds (OS_time_t tm)`  
*Get interval from an OS\_time\_t object normalized to microsecond units.*
- static `int64 OS_TimeGetTotalNanoseconds (OS_time_t tm)`  
*Get interval from an OS\_time\_t object normalized to nanosecond units.*
- static `int64 OS_TimeGetFractionalPart (OS_time_t tm)`  
*Get subseconds portion (fractional part only) from an OS\_time\_t object.*
- static `uint32 OS_TimeGetSubsecondsPart (OS_time_t tm)`  
*Get 32-bit normalized subseconds (fractional part only) from an OS\_time\_t object.*
- static `uint32 OS_TimeGetMillisecondsPart (OS_time_t tm)`  
*Get milliseconds portion (fractional part only) from an OS\_time\_t object.*
- static `uint32 OS_TimeGetMicrosecondsPart (OS_time_t tm)`  
*Get microseconds portion (fractional part only) from an OS\_time\_t object.*
- static `uint32 OS_TimeGetNanosecondsPart (OS_time_t tm)`  
*Get nanoseconds portion (fractional part only) from an OS\_time\_t object.*
- static `OS_time_t OS_TimeAssembleFromNanoseconds (int64 seconds, uint32 nanoseconds)`  
*Assemble/Convert a number of seconds + nanoseconds into an OS\_time\_t interval.*
- static `OS_time_t OS_TimeAssembleFromMicroseconds (int64 seconds, uint32 microseconds)`  
*Assemble/Convert a number of seconds + microseconds into an OS\_time\_t interval.*
- static `OS_time_t OS_TimeAssembleFromMilliseconds (int64 seconds, uint32 milliseconds)`  
*Assemble/Convert a number of seconds + milliseconds into an OS\_time\_t interval.*
- static `OS_time_t OS_TimeAssembleFromSubseconds (int64 seconds, uint32 subseconds)`  
*Assemble/Convert a number of seconds + subseconds into an OS\_time\_t interval.*
- static `OS_time_t OS_TimeAdd (OS_time_t time1, OS_time_t time2)`  
*Computes the sum of two time intervals.*
- static `OS_time_t OS_TimeSubtract (OS_time_t time1, OS_time_t time2)`  
*Computes the difference between two time intervals.*

#### 11.4.1 Detailed Description

#### 11.4.2 Function Documentation

#### 11.4.2.1 OS\_GetLocalTime()

```
int32 OS_GetLocalTime (
    OS_time_t * time_struct )
```

Get the local time.

This function gets the local time from the underlying OS.

##### Note

Mission time management typically uses the cFE Time Service

##### Parameters

out	<i>time_struct</i>	An <a href="#">OS_time_t</a> that will be set to the current time
-----	--------------------	---

##### Returns

Get local time status, see [OSAL Return Code Defines](#)

#### 11.4.2.2 OS\_SetLocalTime()

```
int32 OS_SetLocalTime (
    const OS_time_t * time_struct )
```

Set the local time.

This function sets the local time on the underlying OS.

##### Note

Mission time management typically uses the cFE Time Services

##### Parameters

in	<i>time_struct</i>	An <a href="#">OS_time_t</a> containing the current time
----	--------------------	--

##### Returns

Set local time status, see [OSAL Return Code Defines](#)

## 11.4.2.3 OS\_TimeAdd()

```
static OS_time_t OS_TimeAdd (
    OS_time_t time1,
    OS_time_t time2 ) [inline], [static]
```

Computes the sum of two time intervals.

## Parameters

in	<i>time1</i>	The first interval
in	<i>time2</i>	The second interval

## Returns

The sum of the two intervals (time1 + time2)

Definition at line 384 of file osapi-clock.h.

References OS\_time\_t::ticks.

## 11.4.2.4 OS\_TimeAssembleFromMicroseconds()

```
static OS_time_t OS_TimeAssembleFromMicroseconds (
    int64 seconds,
    uint32 microseconds ) [inline], [static]
```

Assemble/Convert a number of seconds + microseconds into an OS\_time\_t interval.

This creates an OS\_time\_t value using a whole number of seconds and a fractional part in units of microseconds. This is the inverse of OS\_TimeGetTotalSeconds() and OS\_TimeGetMicrosecondsPart(), and should recreate the original OS\_time\_t value from these separate values (aside from any potential conversion losses due to limited resolution of the data types/units).

## See also

[OS\\_TimeGetTotalSeconds\(\)](#), [OS\\_TimeGetMicrosecondsPart\(\)](#)

## Parameters

in	<i>seconds</i>	Whole number of seconds
in	<i>microseconds</i>	Number of microseconds (fractional part only)

## Returns

The input arguments represented as an OS\_time\_t interval

Definition at line 319 of file osapi-clock.h.

References `OS_TIME_TICKS_PER_SECOND`, `OS_TIME_TICKS_PER_USEC`, and `OS_time_t::ticks`.

#### 11.4.2.5 `OS_TimeAssembleFromMilliseconds()`

```
static OS_time_t OS_TimeAssembleFromMilliseconds (
    int64 seconds,
    uint32 milliseconds ) [inline], [static]
```

Assemble/Convert a number of seconds + milliseconds into an `OS_time_t` interval.

This creates an `OS_time_t` value using a whole number of seconds and a fractional part in units of milliseconds. This is the inverse of `OS_TimeGetTotalSeconds()` and `OS_TimeGetMillisecondsPart()`, and should recreate the original `OS_time_t` value from these separate values (aside from any potential conversion losses due to limited resolution of the data types/units).

See also

[OS\\_TimeGetTotalSeconds\(\)](#), [OS\\_TimeGetMillisecondsPart\(\)](#)

#### Parameters

in	<i>seconds</i>	Whole number of seconds
in	<i>milliseconds</i>	Number of milliseconds (fractional part only)

#### Returns

The input arguments represented as an `OS_time_t` interval

Definition at line 343 of file osapi-clock.h.

References `OS_TIME_TICKS_PER_MSEC`, `OS_TIME_TICKS_PER_SECOND`, and `OS_time_t::ticks`.

#### 11.4.2.6 `OS_TimeAssembleFromNanoseconds()`

```
static OS_time_t OS_TimeAssembleFromNanoseconds (
    int64 seconds,
    uint32 nanoseconds ) [inline], [static]
```

Assemble/Convert a number of seconds + nanoseconds into an `OS_time_t` interval.

This creates an `OS_time_t` value using a whole number of seconds and a fractional part in units of nanoseconds. This is the inverse of `OS_TimeGetTotalSeconds()` and `OS_TimeGetNanosecondsPart()`, and should recreate the original `OS_time_t` value from these separate values (aside from any potential conversion losses due to limited resolution of the data types/units).

See also

[OS\\_TimeGetTotalSeconds\(\)](#), [OS\\_TimeGetNanosecondsPart\(\)](#)

**Parameters**

in	<i>seconds</i>	Whole number of seconds
in	<i>nanoseconds</i>	Number of nanoseconds (fractional part only)

**Returns**

The input arguments represented as an [OS\\_time\\_t](#) interval

Definition at line 295 of file osapi-clock.h.

References [OS\\_TIME\\_TICK\\_RESOLUTION\\_NS](#), [OS\\_TIME\\_TICKS\\_PER\\_SECOND](#), and [OS\\_time\\_t::ticks](#).

**11.4.2.7 OS\_TimeAssembleFromSubseconds()**

```
static OS_time_t OS_TimeAssembleFromSubseconds (
    int64 seconds,
    uint32 subseconds ) [inline], [static]
```

Assemble/Convert a number of seconds + subseconds into an [OS\\_time\\_t](#) interval.

This creates an [OS\\_time\\_t](#) value using a whole number of seconds and a fractional part in units of sub-seconds ( $1/2^{32}$ ). This is the inverse of [OS\\_TimeGetTotalSeconds\(\)](#) and [OS\\_TimeGetSubsecondsPart\(\)](#), and should recreate the original [OS\\_time\\_t](#) value from these separate values (aside from any potential conversion losses due to limited resolution of the data types/units).

**See also**

[OS\\_TimeGetTotalSeconds\(\)](#), [OS\\_TimeGetNanosecondsPart\(\)](#)

**Parameters**

in	<i>seconds</i>	Whole number of seconds
in	<i>subseconds</i>	Number of subseconds (32 bit fixed point fractional part)

**Returns**

The input arguments represented as an [OS\\_time\\_t](#) interval

Definition at line 366 of file osapi-clock.h.

References [OS\\_TIME\\_TICKS\\_PER\\_SECOND](#), and [OS\\_time\\_t::ticks](#).

#### 11.4.2.8 OS\_TimeGetFractionalPart()

```
static int64 OS_TimeGetFractionalPart (
    OS_time_t tm ) [inline], [static]
```

Get subseconds portion (fractional part only) from an [OS\\_time\\_t](#) object.

Extracts the fractional part from a given [OS\\_time\\_t](#) object. Units returned are in ticks, not normalized to any standard time unit.

##### Parameters

in	tm	Time interval value
----	----	---------------------

##### Returns

Fractional/subsecond portion of time interval in ticks

Definition at line 187 of file osapi-clock.h.

References `OS_TIME_TICKS_PER_SECOND`, and `OS_time_t::ticks`.

Referenced by `OS_TimeGetMicrosecondsPart()`, `OS_TimeGetMillisecondsPart()`, `OS_TimeGetNanosecondsPart()`, and `OS_TimeGetSubsecondsPart()`.

#### 11.4.2.9 OS\_TimeGetMicrosecondsPart()

```
static uint32 OS_TimeGetMicrosecondsPart (
    OS_time_t tm ) [inline], [static]
```

Get microseconds portion (fractional part only) from an [OS\\_time\\_t](#) object.

Extracts the fractional part from a given [OS\\_time\\_t](#) object normalized to units of microseconds.

This function may be used to adapt applications initially implemented using an older OSAL version where [OS\\_time\\_t](#) was a structure containing a "seconds" and "microsecs" field.

This function will obtain a value that is compatible with the "microsecs" field of [OS\\_time\\_t](#) as it was defined in previous versions of OSAL, as well as the "tv\_usec" field of POSIX-style "struct timeval" values.

##### See also

[OS\\_TimeGetTotalSeconds\(\)](#)

##### Parameters

in	tm	Time interval value
----	----	---------------------



**Returns**

Number of microseconds in time interval

Definition at line 255 of file osapi-clock.h.

References `OS_TIME_TICKS_PER_USEC`, and `OS_TimeGetFractionalPart()`.

Here is the call graph for this function:

**11.4.2.10 OS\_TimeGetMillisecondsPart()**

```
static uint32 OS_TimeGetMillisecondsPart (
    OS_time_t tm ) [inline], [static]
```

Get milliseconds portion (fractional part only) from an `OS_time_t` object.

Extracts the fractional part from a given `OS_time_t` object normalized to units of milliseconds.

**See also**

[OS\\_TimeGetTotalSeconds\(\)](#)

**Parameters**

in	<i>tm</i>	Time interval value
----	-----------	---------------------

**Returns**

Number of milliseconds in time interval

Definition at line 230 of file osapi-clock.h.

References `OS_TIME_TICKS_PER_MSEC`, and `OS_TimeGetFractionalPart()`.

Here is the call graph for this function:



#### 11.4.2.11 OS\_TimeGetNanosecondsPart()

```
static uint32 OS_TimeGetNanosecondsPart (
    OS_time_t tm ) [inline], [static]
```

Get nanoseconds portion (fractional part only) from an [OS\\_time\\_t](#) object.

Extracts the only number of nanoseconds from a given [OS\\_time\\_t](#) object.

This function will obtain a value that is compatible with the "tv\_nsec" field of POSIX-style "struct timespec" values.

See also

[OS\\_TimeGetTotalSeconds\(\)](#)

#### Parameters

in	<i>tm</i>	Time interval value
----	-----------	---------------------

#### Returns

Number of nanoseconds in time interval

Definition at line 274 of file `osapi-clock.h`.

References `OS_TIME_TICK_RESOLUTION_NS`, and `OS_TimeGetFractionalPart()`.

Here is the call graph for this function:



## 11.4.2.12 OS\_TimeGetSubsecondsPart()

```
static uint32 OS_TimeGetSubsecondsPart (
    OS_time_t tm ) [inline], [static]
```

Get 32-bit normalized subseconds (fractional part only) from an [OS\\_time\\_t](#) object.

Extracts the fractional part from a given [OS\\_time\\_t](#) object in maximum precision, with units of  $2^{(-32)}$  sec. This is a base-2 fixed-point fractional value with the point left-justified in the 32-bit value (i.e. left of MSB).

This is (mostly) compatible with the CFE "subseconds" value, where 0x80000000 represents exactly one half second, and 0 represents a full second.

## Parameters

in	<i>tm</i>	Time interval value
----	-----------	---------------------

## Returns

Fractional/subsecond portion of time interval as 32-bit fixed point value

Definition at line 206 of file osapi-clock.h.

References OS\_TIME\_TICKS\_PER\_SECOND, and OS\_TimeGetFractionalPart().

Here is the call graph for this function:



## 11.4.2.13 OS\_TimeGetTotalMicroseconds()

```
static int64 OS_TimeGetTotalMicroseconds (
    OS_time_t tm ) [inline], [static]
```

Get interval from an [OS\\_time\\_t](#) object normalized to microsecond units.

Note this refers to the complete interval, not just the fractional part.

## Parameters

in	<i>tm</i>	Time interval value
----	-----------	---------------------

**Returns**

Whole number of microseconds in time interval

Definition at line 154 of file osapi-clock.h.

References OS\_TIME\_TICKS\_PER\_USEC, and OS\_time\_t::ticks.

**11.4.2.14 OS\_TimeGetTotalMilliseconds()**

```
static int64 OS_TimeGetTotalMilliseconds (
    OS_time_t tm ) [inline], [static]
```

Get interval from an [OS\\_time\\_t](#) object normalized to millisecond units.

Note this refers to the complete interval, not just the fractional part.

**Parameters**

in	<i>tm</i>	Time interval value
----	-----------	---------------------

**Returns**

Whole number of milliseconds in time interval

Definition at line 140 of file osapi-clock.h.

References OS\_TIME\_TICKS\_PER\_MSEC, and OS\_time\_t::ticks.

**11.4.2.15 OS\_TimeGetTotalNanoseconds()**

```
static int64 OS_TimeGetTotalNanoseconds (
    OS_time_t tm ) [inline], [static]
```

Get interval from an [OS\\_time\\_t](#) object normalized to nanosecond units.

Note this refers to the complete interval, not just the fractional part.

**Note**

There is no protection against overflow of the 64-bit return value. Applications must use caution to ensure that the interval does not exceed the representable range of a signed 64 bit integer - approximately 140 years.

**Parameters**

in	<i>tm</i>	Time interval value
----	-----------	---------------------

**Returns**

Whole number of microseconds in time interval

Definition at line 172 of file osapi-clock.h.

References OS\_TIME\_TICK\_RESOLUTION\_NS, and OS\_time\_t::ticks.

**11.4.2.16 OS\_TimeGetTotalSeconds()**

```
static int64 OS_TimeGetTotalSeconds (
    OS_time_t tm ) [inline], [static]
```

Get interval from an [OS\\_time\\_t](#) object normalized to whole number of seconds.

Extracts the number of whole seconds from a given [OS\\_time\\_t](#) object, discarding any fractional component.

This may also replace a direct read of the "seconds" field from the [OS\\_time\\_t](#) object from previous versions of OSAL, where the structure was defined with separate seconds/microseconds fields.

**See also**

[OS\\_TimeGetMicrosecondsPart\(\)](#)

**Parameters**

in	<i>tm</i>	Time interval value
----	-----------	---------------------

**Returns**

Whole number of seconds in time interval

Definition at line 126 of file osapi-clock.h.

References OS\_TIME\_TICKS\_PER\_SECOND, and OS\_time\_t::ticks.

**11.4.2.17 OS\_TimeSubtract()**

```
static OS_time_t OS_TimeSubtract (
    OS_time_t time1,
    OS_time_t time2 ) [inline], [static]
```

Computes the difference between two time intervals.

**Parameters**

in	<i>time1</i>	The first interval
in	<i>time2</i>	The second interval

**Returns**

The difference of the two intervals (time1 - time2)

Definition at line 398 of file osapi-clock.h.

References OS\_time\_t::ticks.

## 11.5 OSAL Core Operation APIs

### Functions

- void [OS\\_Application\\_Startup](#) (void)  
*Application startup.*
- void [OS\\_Application\\_Run](#) (void)  
*Application run.*
- [int32 OS\\_API\\_Init](#) (void)  
*Initialization of API.*
- void [OS\\_IdleLoop](#) (void)  
*Background thread implementation - waits forever for events to occur.*
- void [OS\\_DeleteAllObjects](#) (void)  
*delete all resources created in OSAL.*
- void [OS\\_ApplicationShutdown](#) (uint8 flag)  
*Initiate orderly shutdown.*
- void [OS\\_ApplicationExit](#) (int32 Status)  
*Exit/Abort the application.*
- [int32 OS\\_RegisterEventHandler](#) ([OS\\_EventHandler\\_t](#) handler)  
*Callback routine registration.*

### 11.5.1 Detailed Description

These are for OSAL core operations for startup/initialization, running, and shutdown. Typically only used in bsps, unit tests, psp, etc.

Not intended for user application use

### 11.5.2 Function Documentation

#### 11.5.2.1 OS\_API\_Init()

```
int32 OS_API_Init (
    void )
```

Initialization of API.

This function returns initializes the internal data structures of the OS Abstraction Layer. It must be called in the application startup code before calling any other OS routines.

### Returns

Execution status, see [OSAL Return Code Defines](#). Any error code (negative) means the OSAL can not be initialized. Typical platform specific response is to abort since additional OSAL calls will have undefined behavior.

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	Failed execution.

**11.5.2.2 OS\_Application\_Run()**

```
void OS_Application_Run (
    void )
```

Application run.

Run abstraction such that the same BSP can be used for operations and testing.

**11.5.2.3 OS\_Application\_Startup()**

```
void OS_Application_Startup (
    void )
```

Application startup.

Startup abstraction such that the same BSP can be used for operations and testing.

**11.5.2.4 OS\_ApplicationExit()**

```
void OS_ApplicationExit (
    int32 Status )
```

Exit/Abort the application.

Indicates that the OSAL application should exit and return control to the OS This is intended for e.g. scripted unit testing where the test needs to end without user intervention.

This function does not return. Production code typically should not ever call this.

**Note**

This exits the entire process including tasks that have been created.

**11.5.2.5 OS\_ApplicationShutdown()**

```
void OS_ApplicationShutdown (
    uint8 flag )
```

Initiate orderly shutdown.

Indicates that the OSAL application should perform an orderly shutdown of ALL tasks, clean up all resources, and exit the application.

This allows the task currently blocked in [OS\\_IdleLoop\(\)](#) to wake up, and for that function to return to its caller.

This is preferred over e.g. [OS\\_ApplicationExit\(\)](#) which exits immediately and does not provide for any means to clean up first.



**Parameters**

in	<i>flag</i>	set to true to initiate shutdown, false to cancel
----	-------------	---

**11.5.2.6 OS\_DeleteAllObjects()**

```
void OS_DeleteAllObjects (
    void )
```

delete all resources created in OSAL.

provides a means to clean up all resources allocated by this instance of OSAL. It would typically be used during an orderly shutdown but may also be helpful for testing purposes.

**11.5.2.7 OS\_IdleLoop()**

```
void OS_IdleLoop (
    void )
```

Background thread implementation - waits forever for events to occur.

This should be called from the BSP main routine or initial thread after all other board and application initialization has taken place and all other tasks are running.

Typically just waits forever until "OS\_shutdown" flag becomes true.

**11.5.2.8 OS\_RegisterEventHandler()**

```
int32 OS_RegisterEventHandler (
    OS_EventHandler_t handler )
```

Callback routine registration.

This hook enables the application code to perform extra platform-specific operations on various system events such as resource creation/deletion.

**Note**

Some events are invoked while the resource is "locked" and therefore application-defined handlers for these events should not block or attempt to access other OSAL resources.

**Parameters**

in	<i>handler</i>	The application-provided event handler
----	----------------	--

### Returns

Execution status, see [OSAL Return Code Defines](#).

### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	Failed execution.

## 11.6 OSAL Counting Semaphore APIs

### Functions

- `int32 OS_CountSemCreate (osal_id_t *sem_id, const char *sem_name, uint32 sem_initial_value, uint32 options)`  
*Creates a counting semaphore.*
- `int32 OS_CountSemGive (osal_id_t sem_id)`  
*Increment the semaphore value.*
- `int32 OS_CountSemTake (osal_id_t sem_id)`  
*Decrement the semaphore value.*
- `int32 OS_CountSemTimedWait (osal_id_t sem_id, uint32 msecs)`  
*Decrement the semaphore value with timeout.*
- `int32 OS_CountSemDelete (osal_id_t sem_id)`  
*Deletes the specified counting Semaphore.*
- `int32 OS_CountSemGetIdByName (osal_id_t *sem_id, const char *sem_name)`  
*Find an existing semaphore ID by name.*
- `int32 OS_CountSemGetInfo (osal_id_t sem_id, OS_count_sem_prop_t *count_prop)`  
*Fill a property object buffer with details regarding the resource.*

### 11.6.1 Detailed Description

### 11.6.2 Function Documentation

#### 11.6.2.1 OS\_CountSemCreate()

```
int32 OS_CountSemCreate (
    osal_id_t * sem_id,
    const char * sem_name,
    uint32 sem_initial_value,
    uint32 options )
```

Creates a counting semaphore.

Creates a counting semaphore with initial value specified by `sem_initial_value` and name specified by `sem_name`. `sem_id` will be returned to the caller

#### Parameters

out	<i>sem_id</i>	will be set to the non-zero ID of the newly-created resource
in	<i>sem_name</i>	the name of the new resource to create
in	<i>sem_initial_value</i>	the initial value of the counting semaphore
in	<i>options</i>	Reserved for future use, should be passed as 0.

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if sen name or sem_id are NULL
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NO_FREE_IDS</a>	if all of the semaphore ids are taken
<a href="#">OS_ERR_NAME_TAKEN</a>	if this is already the name of a counting semaphore
<a href="#">OS_SEM_FAILURE</a>	if the OS call failed
<a href="#">OS_INVALID_SEM_VALUE</a>	if the semaphore value is too high

**11.6.2.2 OS\_CountSemDelete()**

```
int32 OS_CountSemDelete (
    osal_id_t sem_id )
```

Deletes the specified counting Semaphore.

**Parameters**

in	<i>sem</i> ↔ <i>_id</i>	The object ID to delete
----	----------------------------	-------------------------

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a valid counting semaphore
<a href="#">OS_SEM_FAILURE</a>	the OS call failed

**11.6.2.3 OS\_CountSemGetIdByName()**

```
int32 OS_CountSemGetIdByName (
    osal_id_t * sem_id,
    const char * sem_name )
```

Find an existing semaphore ID by name.

This function tries to find a counting sem Id given the name of a count\_sem The id is returned through sem\_id

## Parameters

out	<i>sem_id</i>	will be set to the ID of the existing resource
in	<i>sem_name</i>	the name of the existing resource to find

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	is semid or sem_name are NULL pointers
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NAME_NOT_FOUND</a>	if the name was not found in the table

## 11.6.2.4 OS\_CountSemGetInfo()

```
int32 OS_CountSemGetInfo (
    osal_id_t sem_id,
    OS_count_sem_prop_t * count_prop )
```

Fill a property object buffer with details regarding the resource.

This function will pass back a pointer to structure that contains all of the relevant info( name and creator) about the specified counting semaphore.

## Parameters

in	<i>sem_id</i>	The object ID to operate on
out	<i>count_prop</i>	The property object buffer to fill

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a valid semaphore
<a href="#">OS_INVALID_POINTER</a>	if the count_prop pointer is null

### 11.6.2.5 OS\_CountSemGive()

```
int32 OS_CountSemGive (
    osal_id_t sem_id )
```

Increment the semaphore value.

The function unlocks the semaphore referenced by `sem_id` by performing a semaphore unlock operation on that semaphore. If the semaphore value resulting from this operation is positive, then no threads were blocked waiting for the semaphore to become unlocked; the semaphore value is simply incremented for this semaphore.

#### Parameters

in	<code>sem_id</code>	The object ID to operate on
----	---------------------	-----------------------------

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_SEM_FAILURE</a>	the semaphore was not previously initialized or is not in the array of semaphores defined by the system
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a counting semaphore

### 11.6.2.6 OS\_CountSemTake()

```
int32 OS_CountSemTake (
    osal_id_t sem_id )
```

Decrement the semaphore value.

The locks the semaphore referenced by `sem_id` by performing a semaphore lock operation on that semaphore. If the semaphore value is currently zero, then the calling thread shall not return from the call until it either locks the semaphore or the call is interrupted.

#### Parameters

in	<code>sem_id</code>	The object ID to operate on
----	---------------------	-----------------------------

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	the Id passed in is not a valid counting semaphore
<a href="#">OS_SEM_FAILURE</a>	if the OS call failed

**11.6.2.7 OS\_CountSemTimedWait()**

```
int32 OS_CountSemTimedWait (
    osal_id_t sem_id,
    uint32 msec )
```

Decrement the semaphore value with timeout.

The function locks the semaphore referenced by sem\_id. However, if the semaphore cannot be locked without waiting for another process or thread to unlock the semaphore, this wait shall be terminated when the specified timeout, msec, expires.

**Parameters**

in	<i>sem_id</i>	The object ID to operate on
in	<i>msec</i>	The maximum amount of time to block, in milliseconds

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_SEM_TIMEOUT</a>	if semaphore was not relinquished in time
<a href="#">OS_SEM_FAILURE</a>	the semaphore was not previously initialized or is not in the array of semaphores defined by the system
<a href="#">OS_ERR_INVALID_ID</a>	if the ID passed in is not a valid semaphore ID

## 11.7 OSAL Directory APIs

### Functions

- [int32 OS\\_DirectoryOpen](#) ([osal\\_id\\_t](#) \*dir\_id, const char \*path)  
*Opens a directory.*
- [int32 OS\\_DirectoryClose](#) ([osal\\_id\\_t](#) dir\_id)  
*Closes an open directory.*
- [int32 OS\\_DirectoryRewind](#) ([osal\\_id\\_t](#) dir\_id)  
*Rewinds an open directory.*
- [int32 OS\\_DirectoryRead](#) ([osal\\_id\\_t](#) dir\_id, [os\\_dirent\\_t](#) \*dirent)  
*Reads the next name in the directory.*
- [int32 OS\\_mkdir](#) (const char \*path, [uint32](#) access)  
*Makes a new directory.*
- [int32 OS\\_rmdir](#) (const char \*path)  
*Removes a directory from the file system.*

### 11.7.1 Detailed Description

### 11.7.2 Function Documentation

#### 11.7.2.1 OS\_DirectoryClose()

```
int32 OS_DirectoryClose (
    osal_id_t dir_id )
```

Closes an open directory.

The directory referred to by dir\_id will be closed

#### Parameters

in	<i>dir_id</i>	The handle ID of the directory
----	---------------	--------------------------------

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### 11.7.2.2 OS\_DirectoryOpen()

```
int32 OS_DirectoryOpen (
    osal_id_t * dir_id,
    const char * path )
```



Opens a directory.

Prepares for reading the files within a directory

#### Parameters

out	<i>dir↔ _id</i>	The non-zero handle ID of the directory
in	<i>path</i>	The directory to open

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### 11.7.2.3 OS\_DirectoryRead()

```
int32 OS_DirectoryRead (
    osal_id_t dir_id,
    os_dirent_t * dirent )
```

Reads the next name in the directory.

Obtains directory entry data for the next file from an open directory

#### Parameters

in	<i>dir↔ _id</i>	The handle ID of the directory
out	<i>dirent</i>	Buffer to store directory entry information

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### 11.7.2.4 OS\_DirectoryRewind()

```
int32 OS_DirectoryRewind (
    osal_id_t dir_id )
```

Rewinds an open directory.

Resets a directory read handle back to the first file.

**Parameters**

in	<i>dir</i> ↔ <i>_id</i>	The handle ID of the directory
----	----------------------------	--------------------------------

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.7.2.5 OS\_mkdir()**

```
int32 OS_mkdir (
    const char * path,
    uint32 access )
```

Makes a new directory.

Makes a directory specified by path.

**Parameters**

in	<i>path</i>	The new directory name
in	<i>access</i>	The permissions for the directory (reserved for future use)

**Note**

Current implementations do not utilize the "access" parameter. Applications should still pass the intended value ([OS\\_READ\\_WRITE](#) or [OS\\_READ\\_ONLY](#)) to be compatible with future implementations.

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if path is NULL
<a href="#">OS_FS_ERR_PATH_TOO_LONG</a>	if the path is too long to be stored locally
<a href="#">OS_FS_ERR_PATH_INVALID</a>	if path cannot be parsed
<a href="#">OS_ERROR</a>	if the OS call fails

## 11.7.2.6 OS\_rmdir()

```
int32 OS_rmdir (
    const char * path )
```

Removes a directory from the file system.

Removes a directory from the structure. The directory must be empty prior to this operation.

## Parameters

in	<i>path</i>	The directory to remove
----	-------------	-------------------------

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if path is NULL
<a href="#">OS_FS_ERR_PATH_INVALID</a>	if path cannot be parsed
<a href="#">OS_FS_ERR_PATH_TOO_LONG</a>	
<a href="#">OS_ERROR</a>	if the directory remove operation failed

## 11.8 OSAL Return Code Defines

### Macros

- `#define OS_SUCCESS (0)`  
*Successful execution.*
- `#define OS_ERROR (-1)`  
*Failed execution.*
- `#define OS_INVALID_POINTER (-2)`  
*Invalid pointer.*
- `#define OS_ERROR_ADDRESS_MISALIGNED (-3)`  
*Address misalignment.*
- `#define OS_ERROR_TIMEOUT (-4)`  
*Error timeout.*
- `#define OS_INVALID_INT_NUM (-5)`  
*Invalid Interrupt number.*
- `#define OS_SEM_FAILURE (-6)`  
*Semaphore failure.*
- `#define OS_SEM_TIMEOUT (-7)`  
*Semaphore timeout.*
- `#define OS_QUEUE_EMPTY (-8)`  
*Queue empty.*
- `#define OS_QUEUE_FULL (-9)`  
*Queue full.*
- `#define OS_QUEUE_TIMEOUT (-10)`  
*Queue timeout.*
- `#define OS_QUEUE_INVALID_SIZE (-11)`  
*Queue invalid size.*
- `#define OS_QUEUE_ID_ERROR (-12)`  
*Queue ID error.*
- `#define OS_ERR_NAME_TOO_LONG (-13)`  
*name length including null terminator greater than `OS_MAX_API_NAME`*
- `#define OS_ERR_NO_FREE_IDS (-14)`  
*No free IDs.*
- `#define OS_ERR_NAME_TAKEN (-15)`  
*Name taken.*
- `#define OS_ERR_INVALID_ID (-16)`  
*Invalid ID.*
- `#define OS_ERR_NAME_NOT_FOUND (-17)`  
*Name not found.*
- `#define OS_ERR_SEM_NOT_FULL (-18)`  
*Semaphore not full.*
- `#define OS_ERR_INVALID_PRIORITY (-19)`  
*Invalid priority.*
- `#define OS_INVALID_SEM_VALUE (-20)`  
*Invalid semaphore value.*
- `#define OS_ERR_FILE (-27)`

- File error.*

  - #define `OS_ERR_NOT_IMPLEMENTED` (-28)
- Not implemented.*

  - #define `OS_TIMER_ERR_INVALID_ARGS` (-29)
- Timer invalid arguments.*

  - #define `OS_TIMER_ERR_TIMER_ID` (-30)
- Timer ID error.*

  - #define `OS_TIMER_ERR_UNAVAILABLE` (-31)
- Timer unavailable.*

  - #define `OS_TIMER_ERR_INTERNAL` (-32)
- Timer internal error.*

  - #define `OS_ERR_OBJECT_IN_USE` (-33)
- Object in use.*

  - #define `OS_ERR_BAD_ADDRESS` (-34)
- Bad address.*

  - #define `OS_ERR_INCORRECT_OBJ_STATE` (-35)
- Incorrect object state.*

  - #define `OS_ERR_INCORRECT_OBJ_TYPE` (-36)
- Incorrect object type.*

  - #define `OS_ERR_STREAM_DISCONNECTED` (-37)
- Stream disconnected.*

  - #define `OS_ERR_OPERATION_NOT_SUPPORTED` (-38)
- Requested operation not support on supplied object(s)*

  - #define `OS_ERR_INVALID_SIZE` (-40)
- Invalid Size.*

  - #define `OS_FS_ERR_PATH_TOO_LONG` (-103)
- FS path too long.*

  - #define `OS_FS_ERR_NAME_TOO_LONG` (-104)
- FS name too long.*

  - #define `OS_FS_ERR_DRIVE_NOT_CREATED` (-106)
- FS drive not created.*

  - #define `OS_FS_ERR_DEVICE_NOT_FREE` (-107)
- FS device not free.*

  - #define `OS_FS_ERR_PATH_INVALID` (-108)
- FS path invalid.*

### 11.8.1 Detailed Description

### 11.8.2 Macro Definition Documentation

#### 11.8.2.1 OS\_ERR\_BAD\_ADDRESS

```
#define OS_ERR_BAD_ADDRESS (-34)
```

Bad address.

Definition at line 81 of file osapi-error.h.

#### 11.8.2.2 OS\_ERR\_FILE

```
#define OS_ERR_FILE (-27)
```

File error.

Definition at line 74 of file osapi-error.h.

#### 11.8.2.3 OS\_ERR\_INCORRECT\_OBJ\_STATE

```
#define OS_ERR_INCORRECT_OBJ_STATE (-35)
```

Incorrect object state.

Definition at line 82 of file osapi-error.h.

#### 11.8.2.4 OS\_ERR\_INCORRECT\_OBJ\_TYPE

```
#define OS_ERR_INCORRECT_OBJ_TYPE (-36)
```

Incorrect object type.

Definition at line 83 of file osapi-error.h.

#### 11.8.2.5 OS\_ERR\_INVALID\_ID

```
#define OS_ERR_INVALID_ID (-16)
```

Invalid ID.

Definition at line 69 of file osapi-error.h.

#### 11.8.2.6 OS\_ERR\_INVALID\_PRIORITY

```
#define OS_ERR_INVALID_PRIORITY (-19)
```

Invalid priority.

Definition at line 72 of file osapi-error.h.

#### 11.8.2.7 OS\_ERR\_INVALID\_SIZE

```
#define OS_ERR_INVALID_SIZE (-40)
```

Invalid Size.

Definition at line 86 of file osapi-error.h.

#### 11.8.2.8 OS\_ERR\_NAME\_NOT\_FOUND

```
#define OS_ERR_NAME_NOT_FOUND (-17)
```

Name not found.

Definition at line 70 of file osapi-error.h.

#### 11.8.2.9 OS\_ERR\_NAME\_TAKEN

```
#define OS_ERR_NAME_TAKEN (-15)
```

Name taken.

Definition at line 68 of file osapi-error.h.

#### 11.8.2.10 OS\_ERR\_NAME\_TOO\_LONG

```
#define OS_ERR_NAME_TOO_LONG (-13)
```

name length including null terminator greater than [OS\\_MAX\\_API\\_NAME](#)

Definition at line 66 of file osapi-error.h.

**11.8.2.11 OS\_ERR\_NO\_FREE\_IDS**

```
#define OS_ERR_NO_FREE_IDS (-14)
```

No free IDs.

Definition at line 67 of file osapi-error.h.

**11.8.2.12 OS\_ERR\_NOT\_IMPLEMENTED**

```
#define OS_ERR_NOT_IMPLEMENTED (-28)
```

Not implemented.

Definition at line 75 of file osapi-error.h.

**11.8.2.13 OS\_ERR\_OBJECT\_IN\_USE**

```
#define OS_ERR_OBJECT_IN_USE (-33)
```

Object in use.

Definition at line 80 of file osapi-error.h.

**11.8.2.14 OS\_ERR\_OPERATION\_NOT\_SUPPORTED**

```
#define OS_ERR_OPERATION_NOT_SUPPORTED (-38)
```

Requested operation not support on supplied object(s)

Definition at line 85 of file osapi-error.h.

**11.8.2.15 OS\_ERR\_SEM\_NOT\_FULL**

```
#define OS_ERR_SEM_NOT_FULL (-18)
```

Semaphore not full.

Definition at line 71 of file osapi-error.h.



**11.8.2.16 OS\_ERR\_STREAM\_DISCONNECTED**

```
#define OS_ERR_STREAM_DISCONNECTED (-37)
```

Stream disconnected.

Definition at line 84 of file osapi-error.h.

**11.8.2.17 OS\_ERROR**

```
#define OS_ERROR (-1)
```

Failed execution.

Definition at line 54 of file osapi-error.h.

**11.8.2.18 OS\_ERROR\_ADDRESS\_MISALIGNED**

```
#define OS_ERROR_ADDRESS_MISALIGNED (-3)
```

Address misalignment.

Definition at line 56 of file osapi-error.h.

**11.8.2.19 OS\_ERROR\_TIMEOUT**

```
#define OS_ERROR_TIMEOUT (-4)
```

Error timeout.

Definition at line 57 of file osapi-error.h.

**11.8.2.20 OS\_FS\_ERR\_DEVICE\_NOT\_FREE**

```
#define OS_FS_ERR_DEVICE_NOT_FREE (-107)
```

FS device not free.

Definition at line 99 of file osapi-error.h.

**11.8.2.21 OS\_FS\_ERR\_DRIVE\_NOT\_CREATED**

```
#define OS_FS_ERR_DRIVE_NOT_CREATED (-106)
```

FS drive not created.

Definition at line 98 of file osapi-error.h.

**11.8.2.22 OS\_FS\_ERR\_NAME\_TOO\_LONG**

```
#define OS_FS_ERR_NAME_TOO_LONG (-104)
```

FS name too long.

Definition at line 97 of file osapi-error.h.

**11.8.2.23 OS\_FS\_ERR\_PATH\_INVALID**

```
#define OS_FS_ERR_PATH_INVALID (-108)
```

FS path invalid.

Definition at line 100 of file osapi-error.h.

**11.8.2.24 OS\_FS\_ERR\_PATH\_TOO\_LONG**

```
#define OS_FS_ERR_PATH_TOO_LONG (-103)
```

FS path too long.

Definition at line 96 of file osapi-error.h.

**11.8.2.25 OS\_INVALID\_INT\_NUM**

```
#define OS_INVALID_INT_NUM (-5)
```

Invalid Interrupt number.

Definition at line 58 of file osapi-error.h.

**11.8.2.26 OS\_INVALID\_POINTER**

```
#define OS_INVALID_POINTER (-2)
```

Invalid pointer.

Definition at line 55 of file osapi-error.h.

**11.8.2.27 OS\_INVALID\_SEM\_VALUE**

```
#define OS_INVALID_SEM_VALUE (-20)
```

Invalid semaphore value.

Definition at line 73 of file osapi-error.h.

**11.8.2.28 OS\_QUEUE\_EMPTY**

```
#define OS_QUEUE_EMPTY (-8)
```

Queue empty.

Definition at line 61 of file osapi-error.h.

**11.8.2.29 OS\_QUEUE\_FULL**

```
#define OS_QUEUE_FULL (-9)
```

Queue full.

Definition at line 62 of file osapi-error.h.

**11.8.2.30 OS\_QUEUE\_ID\_ERROR**

```
#define OS_QUEUE_ID_ERROR (-12)
```

Queue ID error.

Definition at line 65 of file osapi-error.h.

**11.8.2.31 OS\_QUEUE\_INVALID\_SIZE**

```
#define OS_QUEUE_INVALID_SIZE (-11)
```

Queue invalid size.

Definition at line 64 of file osapi-error.h.

**11.8.2.32 OS\_QUEUE\_TIMEOUT**

```
#define OS_QUEUE_TIMEOUT (-10)
```

Queue timeout.

Definition at line 63 of file osapi-error.h.

**11.8.2.33 OS\_SEM\_FAILURE**

```
#define OS_SEM_FAILURE (-6)
```

Semaphore failure.

Definition at line 59 of file osapi-error.h.

**11.8.2.34 OS\_SEM\_TIMEOUT**

```
#define OS_SEM_TIMEOUT (-7)
```

Semaphore timeout.

Definition at line 60 of file osapi-error.h.

**11.8.2.35 OS\_SUCCESS**

```
#define OS_SUCCESS (0)
```

Successful execution.

Definition at line 53 of file osapi-error.h.

**11.8.2.36 OS\_TIMER\_ERR\_INTERNAL**

```
#define OS_TIMER_ERR_INTERNAL (-32)
```

Timer internal error.

Definition at line 79 of file osapi-error.h.

**11.8.2.37 OS\_TIMER\_ERR\_INVALID\_ARGS**

```
#define OS_TIMER_ERR_INVALID_ARGS (-29)
```

Timer invalid arguments.

Definition at line 76 of file osapi-error.h.

**11.8.2.38 OS\_TIMER\_ERR\_TIMER\_ID**

```
#define OS_TIMER_ERR_TIMER_ID (-30)
```

Timer ID error.

Definition at line 77 of file osapi-error.h.

**11.8.2.39 OS\_TIMER\_ERR\_UNAVAILABLE**

```
#define OS_TIMER_ERR_UNAVAILABLE (-31)
```

Timer unavailable.

Definition at line 78 of file osapi-error.h.

## 11.9 OSAL Error Info APIs

### Functions

- [int32 OS\\_GetErrorName](#) ([int32](#) error\_num, [os\\_err\\_name\\_t](#) \*err\_name)  
*Convert an error number to a string.*

### 11.9.1 Detailed Description

### 11.9.2 Function Documentation

#### 11.9.2.1 OS\_GetErrorName()

```
int32 OS_GetErrorName (
    int32 error_num,
    os_err_name_t * err_name )
```

Convert an error number to a string.

#### Parameters

in	<i>error_num</i>	Error number to convert
out	<i>err_name</i>	Buffer to store error string

#### Returns

Execution status, see [OSAL Return Code Defines](#)

## 11.10 OSAL File Access Option Defines

### Macros

- `#define OS_READ_ONLY 0`
- `#define OS_WRITE_ONLY 1`
- `#define OS_READ_WRITE 2`

#### 11.10.1 Detailed Description

#### 11.10.2 Macro Definition Documentation

##### 11.10.2.1 OS\_READ\_ONLY

```
#define OS_READ_ONLY 0
```

Read only file access

Definition at line 35 of file osapi-file.h.

##### 11.10.2.2 OS\_READ\_WRITE

```
#define OS_READ_WRITE 2
```

Read write file access

Definition at line 37 of file osapi-file.h.

##### 11.10.2.3 OS\_WRITE\_ONLY

```
#define OS_WRITE_ONLY 1
```

Write only file access

Definition at line 36 of file osapi-file.h.

## 11.11 OSAL Reference Point For Seek Offset Defines

### Macros

- `#define OS_SEEK_SET 0`
- `#define OS_SEEK_CUR 1`
- `#define OS_SEEK_END 2`

#### 11.11.1 Detailed Description

#### 11.11.2 Macro Definition Documentation

##### 11.11.2.1 OS\_SEEK\_CUR

```
#define OS_SEEK_CUR 1
```

Seek offset current

Definition at line 44 of file osapi-file.h.

##### 11.11.2.2 OS\_SEEK\_END

```
#define OS_SEEK_END 2
```

Seek offset end

Definition at line 45 of file osapi-file.h.

##### 11.11.2.3 OS\_SEEK\_SET

```
#define OS_SEEK_SET 0
```

Seek offset set

Definition at line 43 of file osapi-file.h.



## 11.12 OSAL Standard File APIs

### Functions

- `int32 OS_OpenCreate (osal_id_t *filedes, const char *path, int32 flags, int32 access)`  
*Open or create a file.*
- `int32 OS_close (osal_id_t filedes)`  
*Closes an open file handle.*
- `int32 OS_read (osal_id_t filedes, void *buffer, size_t nbytes)`  
*Read from a file handle.*
- `int32 OS_write (osal_id_t filedes, const void *buffer, size_t nbytes)`  
*Write to a file handle.*
- `int32 OS_TimedRead (osal_id_t filedes, void *buffer, size_t nbytes, int32 timeout)`  
*File/Stream input read with a timeout.*
- `int32 OS_TimedWrite (osal_id_t filedes, const void *buffer, size_t nbytes, int32 timeout)`  
*File/Stream output write with a timeout.*
- `int32 OS_chmod (const char *path, uint32 access)`  
*Changes the permissions of a file.*
- `int32 OS_stat (const char *path, os_fstat_t *filestats)`  
*Obtain information about a file or directory.*
- `int32 OS_lseek (osal_id_t filedes, int32 offset, uint32 whence)`  
*Seeks to the specified position of an open file.*
- `int32 OS_remove (const char *path)`  
*Removes a file from the file system.*
- `int32 OS_rename (const char *old_filename, const char *new_filename)`  
*Renames a file.*
- `int32 OS_cp (const char *src, const char *dest)`  
*Copies a single file from src to dest.*
- `int32 OS_mv (const char *src, const char *dest)`  
*Move a single file from src to dest.*
- `int32 OS_FDGetInfo (osal_id_t filedes, OS_file_prop_t *fd_prop)`  
*Obtain information about an open file.*
- `int32 OS_FileOpenCheck (const char *Filename)`  
*Checks to see if a file is open.*
- `int32 OS_CloseAllFiles (void)`  
*Close all open files.*
- `int32 OS_CloseFileByName (const char *Filename)`  
*Close a file by filename.*

### 11.12.1 Detailed Description

### 11.12.2 Function Documentation

#### 11.12.2.1 OS\_chmod()

```
int32 OS_chmod (
    const char * path,
    uint32 access )
```

Changes the permissions of a file.

**Parameters**

in	<i>path</i>	File to change
in	<i>access</i>	Desired access mode - see <a href="#">OSAL File Access Option Defines</a>

**Note**

Some file systems do not implement permissions

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.12.2.2 OS\_close()**

```
int32 OS_close (
    osal_id_t filedes )
```

Closes an open file handle.

This closes regular file handles and any other file-like resource, such as network streams or pipes.

**Parameters**

in	<i>filedes</i>	The handle ID to operate on
----	----------------	-----------------------------

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	if file descriptor could not be closed
<a href="#">OS_ERR_INVALID_ID</a>	if the file descriptor passed in is invalid

**11.12.2.3 OS\_CloseAllFiles()**

```
int32 OS_CloseAllFiles (
    void )
```

Close all open files.

Closes All open files that were opened through the OSAL

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	if one or more file close returned an error

**11.12.2.4 OS\_CloseFileByName()**

```
int32 OS_CloseFileByName (
    const char * Filename )
```

Close a file by filename.

Allows a file to be closed by name. This will only work if the name passed in is the same name used to open the file.

**Parameters**

in	<i>Filename</i>	The file to close
----	-----------------	-------------------

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_FS_ERR_PATH_INVALID</a>	if the file is not found
<a href="#">OS_ERROR</a>	if the file close returned an error

**11.12.2.5 OS\_cp()**

```
int32 OS_cp (
    const char * src,
    const char * dest )
```

Copies a single file from src to dest.

**Note**

The behavior of this API on an open file is not defined at the OSAL level due to dependencies on the underlying OS which may or may not allow the related operation based on a variety of potential configurations. For portability, it is recommended that applications ensure the file is closed prior to removal.

**Parameters**

in	<i>src</i>	The source file to operate on
in	<i>dest</i>	The destination file

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	if the file could not be accessed
<a href="#">OS_INVALID_POINTER</a>	if src or dest are NULL
<a href="#">OS_FS_ERR_PATH_INVALID</a>	if path cannot be parsed
<a href="#">OS_FS_ERR_PATH_TOO_LONG</a>	if the paths given are too long to be stored locally
<a href="#">OS_FS_ERR_NAME_TOO_LONG</a>	if the dest name is too long to be stored locally

**11.12.2.6 OS\_FDGetInfo()**

```
int32 OS_FDGetInfo (
    osal_id_t filedes,
    OS_file_prop_t * fd_prop )
```

Obtain information about an open file.

Copies the information of the given file descriptor into a structure passed in

**Parameters**

in	<i>filedes</i>	The handle ID to operate on
out	<i>fd_prop</i>	Storage buffer for file information

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the file descriptor passed in is invalid

## 11.12.2.7 OS\_FileOpenCheck()

```
int32 OS_FileOpenCheck (
    const char * Filename )
```

Checks to see if a file is open.

This function takes a filename and determines if the file is open. The function will return success if the file is open.

## Parameters

in	<i>Filename</i>	The file to operate on
----	-----------------	------------------------

## Returns

OS\_SUCCESS if the file is open, or appropriate error code

## Return values

<a href="#">OS_ERROR</a>	if the file is not open
--------------------------	-------------------------

## 11.12.2.8 OS\_lseek()

```
int32 OS_lseek (
    osal_id_t filedес,
    int32 offset,
    uint32 whence )
```

Seeks to the specified position of an open file.

Sets the read/write pointer to a specific offset in a specific file.

## Parameters

in	<i>filedes</i>	The handle ID to operate on
in	<i>offset</i>	The file offset to seek to
in	<i>whence</i>	The reference point for offset, see <a href="#">OSAL Reference Point For Seek Offset Defines</a>

## Returns

Byte offset from the beginning of the file or appropriate error code, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_ERR_INVALID_ID</a>	if the file descriptor passed in is invalid
<a href="#">OS_ERROR</a>	if OS call failed

### 11.12.2.9 OS\_mv()

```
int32 OS_mv (
    const char * src,
    const char * dest )
```

Move a single file from src to dest.

This first attempts to rename the file, which is faster if the source and destination reside on the same file system.

If this fails, it falls back to copying the file and removing the original.

#### Note

The behavior of this API on an open file is not defined at the OSAL level due to dependencies on the underlying OS which may or may not allow the related operation based on a variety of potential configurations. For portability, it is recommended that applications ensure the file is closed prior to removal.

#### Parameters

in	<i>src</i>	The source file to operate on
in	<i>dest</i>	The destination file

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	if the file could not be renamed.
<a href="#">OS_INVALID_POINTER</a>	if src or dest are NULL
<a href="#">OS_FS_ERR_PATH_INVALID</a>	if path cannot be parsed
<a href="#">OS_FS_ERR_PATH_TOO_LONG</a>	if the paths given are too long to be stored locally
<a href="#">OS_FS_ERR_NAME_TOO_LONG</a>	if the dest name is too long to be stored locally

### 11.12.2.10 OS\_OpenCreate()

```
int32 OS_OpenCreate (
    osal_id_t * filedes,
    const char * path,
    int32 flags,
    int32 access )
```

Open or create a file.

Implements the same as `OS_open/OS_creat` but follows the OSAL paradigm of outputting the ID/descriptor separately from the return value, rather than relying on the user to convert it back.

#### Parameters

out	<i>filedes</i>	The handle ID
in	<i>path</i>	File name to create or open
in	<i>flags</i>	The file permissions - see <a href="#">OS_file_flag_t</a>
in	<i>access</i>	Intended access mode - see <a href="#">OSAL File Access Option Defines</a>

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	if the command was not executed properly

#### 11.12.2.11 OS\_read()

```
int32 OS_read (
    osal_id_t filedes,
    void * buffer,
    size_t nbytes )
```

Read from a file handle.

Reads up to `nbytes` from a file, and puts them into `buffer`.

#### Parameters

in	<i>filedes</i>	The handle ID to operate on
out	<i>buffer</i>	Storage location for file data
in	<i>nbytes</i>	Maximum number of bytes to read

#### Note

All OSAL error codes are negative `int32` values. Failure of this call can be checked by testing if the result is less than 0.

#### Returns

A non-negative byte count or appropriate error code, see [OSAL Return Code Defines](#)

## Return values

<a href="#"><i>OS_INVALID_POINTER</i></a>	if buffer is a null pointer
<a href="#"><i>OS_ERROR</i></a>	if OS call failed
<a href="#"><i>OS_ERR_INVALID_ID</i></a>	if the file descriptor passed in is invalid

## 11.12.2.12 OS\_remove()

```
int32 OS_remove (
    const char * path )
```

Removes a file from the file system.

Removes a given filename from the drive

## Note

The behavior of this API on an open file is not defined at the OSAL level due to dependencies on the underlying OS which may or may not allow the related operation based on a variety of potential configurations. For portability, it is recommended that applications ensure the file is closed prior to removal.

## Parameters

in	<i>path</i>	The file to operate on
----	-------------	------------------------

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#"><i>OS_SUCCESS</i></a>	Successful execution.
<a href="#"><i>OS_ERROR</i></a>	if there is no device or the driver returns error
<a href="#"><i>OS_INVALID_POINTER</i></a>	if path is NULL
<a href="#"><i>OS_FS_ERR_PATH_TOO_LONG</i></a>	if path is too long to be stored locally
<a href="#"><i>OS_FS_ERR_PATH_INVALID</i></a>	if path cannot be parsed
<a href="#"><i>OS_FS_ERR_NAME_TOO_LONG</i></a>	if the name of the file to remove is too long

## 11.12.2.13 OS\_rename()

```
int32 OS_rename (
    const char * old_filename,
    const char * new_filename )
```



Renames a file.

Changes the name of a file, where the source and destination reside on the same file system.

#### Note

The behavior of this API on an open file is not defined at the OSAL level due to dependencies on the underlying OS which may or may not allow the related operation based on a variety of potential configurations. For portability, it is recommended that applications ensure the file is closed prior to removal.

#### Parameters

in	<i>old_filename</i>	The original filename
in	<i>new_filename</i>	The desired filename

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	if the file could not be opened or renamed.
<a href="#">OS_INVALID_POINTER</a>	if old or new are NULL
<a href="#">OS_FS_ERR_PATH_INVALID</a>	if path cannot be parsed
<a href="#">OS_FS_ERR_PATH_TOO_LONG</a>	if the paths given are too long to be stored locally
<a href="#">OS_FS_ERR_NAME_TOO_LONG</a>	if the new name is too long to be stored locally

#### 11.12.2.14 OS\_stat()

```
int32 OS_stat (
    const char * path,
    os_fstat_t * filestats )
```

Obtain information about a file or directory.

Returns information about a file or directory in a [os\\_fstat\\_t](#) structure

#### Parameters

in	<i>path</i>	The file to operate on
out	<i>filestats</i>	Buffer to store file information

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if path or filestats is NULL
<a href="#">OS_FS_ERR_PATH_TOO_LONG</a>	if the path is too long to be stored locally
<a href="#">OS_FS_ERR_NAME_TOO_LONG</a>	if the name of the file is too long to be stored
<a href="#">OS_FS_ERR_PATH_INVALID</a>	if path cannot be parsed
<a href="#">OS_ERROR</a>	if the OS call failed

**11.12.2.15 OS\_TimedRead()**

```
int32 OS_TimedRead (
    osal_id_t filedес,
    void * buffer,
    size_t nbytes,
    int32 timeout )
```

File/Stream input read with a timeout.

This implements a time-limited read and is primarily intended for use with sockets but may also work with any other stream-like resource that the underlying OS supports.

If data is immediately available on the file/socket, this will return that data along with the actual number of bytes that were immediately available. It will not block.

If no data is immediately available, this will wait up to the given timeout for data to appear. If no data appears within the timeout period, then this returns an error code (not zero).

In all cases this will return successfully as soon as at least 1 byte of actual data is available. It will not attempt to read the entire input buffer.

If an EOF condition occurs prior to timeout, this function returns zero.

**Parameters**

in	<i>filedes</i>	The handle ID to operate on
in	<i>buffer</i>	Source location for file data
in	<i>nbytes</i>	Maximum number of bytes to read
in	<i>timeout</i>	Maximum time to wait, in milliseconds (OS_PEND = forever)

**Returns**

Byte count on success, zero for timeout, or appropriate error code, see [OSAL Return Code Defines](#)

### 11.12.2.16 OS\_TimedWrite()

```
int32 OS_TimedWrite (
    osal_id_t filedes,
    const void * buffer,
    size_t nbytes,
    int32 timeout )
```

File/Stream output write with a timeout.

This implements a time-limited write and is primarily intended for use with sockets but may also work with any other stream-like resource that the underlying OS supports.

If output buffer space is immediately available on the file/socket, this will place data into the buffer and return the actual number of bytes that were queued for output. It will not block.

If no output buffer space is immediately available, this will wait up to the given timeout for space to become available. If no space becomes available within the timeout period, then this returns an error code (not zero).

In all cases this will return successfully as soon as at least 1 byte of actual data is output. It will *not* attempt to write the entire output buffer.

If an EOF condition occurs prior to timeout, this function returns zero.

#### Parameters

in	<i>filedes</i>	The handle ID to operate on
in	<i>buffer</i>	Source location for file data
in	<i>nbytes</i>	Maximum number of bytes to read
in	<i>timeout</i>	Maximum time to wait, in milliseconds (OS_PEND = forever)

#### Returns

Byte count on success, zero for timeout, or appropriate error code, see [OSAL Return Code Defines](#)

### 11.12.2.17 OS\_write()

```
int32 OS_write (
    osal_id_t filedes,
    const void * buffer,
    size_t nbytes )
```

Write to a file handle.

Writes to a file. copies up to a maximum of nbytes of buffer to the file described in filedes

**Parameters**

in	<i>filedes</i>	The handle ID to operate on
in	<i>buffer</i>	Source location for file data
in	<i>nbytes</i>	Maximum number of bytes to read

**Note**

All OSAL error codes are negative int32 values. Failure of this call can be checked by testing if the result is less than 0.

**Returns**

A non-negative byte count or appropriate error code, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_INVALID_POINTER</a>	if buffer is NULL
<a href="#">OS_ERROR</a>	if OS call failed
<a href="#">OS_ERR_INVALID_ID</a>	if the file descriptor passed in is invalid

## 11.13 OSAL File System Level APIs

### Functions

- [int32 OS\\_FileSysAddFixedMap](#) ([osal\\_id\\_t](#) \*fileys\_id, const char \*phys\_path, const char \*virt\_path)  
*Create a fixed mapping between an existing directory and a virtual OSAL mount point.*
- [int32 OS\\_mkfs](#) (char \*address, const char \*devname, const char \*volname, size\_t blocksize, [osal\\_blockcount\\_t](#) numblocks)  
*Makes a file system on the target.*
- [int32 OS\\_mount](#) (const char \*devname, const char \*mountpoint)  
*Mounts a file system.*
- [int32 OS\\_initfs](#) (char \*address, const char \*devname, const char \*volname, size\_t blocksize, [osal\\_blockcount\\_t](#) numblocks)  
*Initializes an existing file system.*
- [int32 OS\\_rmfs](#) (const char \*devname)  
*Removes a file system.*
- [int32 OS\\_unmount](#) (const char \*mountpoint)  
*Unmounts a mounted file system.*
- [int32 OS\\_FileSysStatVolume](#) (const char \*name, [OS\\_statvfs\\_t](#) \*statbuf)  
*Obtains information about size and free space in a volume.*
- [int32 OS\\_chkfs](#) (const char \*name, bool repair)  
*Checks the health of a file system and repairs it if necessary.*
- [int32 OS\\_FS\\_GetPhysDriveName](#) (char \*PhysDriveName, const char \*MountPoint)  
*Obtains the physical drive name associated with a mount point.*
- [int32 OS\\_TranslatePath](#) (const char \*VirtualPath, char \*LocalPath)  
*Translates a OSAL Virtual file system path to a host Local path.*
- [int32 OS\\_GetFsInfo](#) ([os\\_fsinfo\\_t](#) \*fileys\_info)  
*Returns information about the file system.*

### 11.13.1 Detailed Description

### 11.13.2 Function Documentation

#### 11.13.2.1 OS\_chkfs()

```
int32 OS_chkfs (
    const char * name,
    bool repair )
```

Checks the health of a file system and repairs it if necessary.

Checks the drives for inconsistencies and optionally also repairs it

#### Note

not all operating systems implement this function

**Parameters**

in	<i>name</i>	The device/path to operate on
in	<i>repair</i>	Whether to also repair inconsistencies

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#"><i>OS_SUCCESS</i></a>	Successful execution.
<a href="#"><i>OS_INVALID_POINTER</i></a>	Name is NULL
<a href="#"><i>OS_ERR_NOT_IMPLEMENTED</i></a>	Not implemented.
<a href="#"><i>OS_ERROR</i></a>	Failed execution.

**11.13.2.2 OS\_FileSysAddFixedMap()**

```
int32 OS_FileSysAddFixedMap (
    osal_id_t * filesys_id,
    const char * phys_path,
    const char * virt_path )
```

Create a fixed mapping between an existing directory and a virtual OSAL mount point.

This mimics the behavior of a "FS\_BASED" entry in the VolumeTable but is registered at runtime. It is intended to be called by the PSP/BSP prior to starting the application.

**Note**

OSAL virtual mount points are required to be a single, non-empty top-level directory name. Virtual path names always follow the form /<virt\_mount\_point>/<relative\_path>/<file>. Only the relative path may be omitted/empty (i.e. /<virt\_mount\_point>/<file>) but the virtual mount point must be present and not an empty string. In particular this means it is not possible to directly refer to files in the "root" of the native file system from OSAL. However it is possible to create a virtual map to the root, such as by calling:

```
OS_FileSysAddFixedMap(&fs_id, "/", "/root");
```

**Parameters**

out	<i>filesys_id</i>	A non-zero OSAL ID reflecting the file system
in	<i>phys_path</i>	The native system directory (an existing mount point)
in	<i>virt_path</i>	The virtual mount point of this filesystem

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.13.2.3 OS\_FileSysStatVolume()**

```
int32 OS_FileSysStatVolume (
    const char * name,
    OS_statvfs_t * statbuf )
```

Obtains information about size and free space in a volume.

Populates the supplied [OS\\_statvfs\\_t](#) structure, which includes the block size and total/free blocks in a file system volume.

This replaces two older OSAL calls:

OS\_fsBlocksFree() is determined by reading the blocks\_free output struct member OS\_fsBytesFree() is determined by multiplying blocks\_free by the block\_size member

**Parameters**

in	<i>name</i>	The device/path to operate on
out	<i>statbuf</i>	Output structure to populate

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if name or statbuf is NULL
<a href="#">OS_ERROR</a>	if the OS call failed

**11.13.2.4 OS\_FS\_GetPhysDriveName()**

```
int32 OS_FS_GetPhysDriveName (
    char * PhysDriveName,
    const char * MountPoint )
```

Obtains the physical drive name associated with a mount point.

Returns the name of the physical volume associated with the drive, when given the OSAL mount point of the drive

**Parameters**

out	<i>PhysDriveName</i>	Buffer to store physical drive name
in	<i>MountPoint</i>	OSAL mount point

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if either parameter is NULL
<a href="#">OS_ERROR</a>	if the mountpoint could not be found

**11.13.2.5 OS\_GetFsInfo()**

```
int32 OS_GetFsInfo (
    os_fsinfo_t * filesystem_info )
```

Returns information about the file system.

Returns information about the file system in an [os\\_fsinfo\\_t](#). This includes the number of open files and file systems

**Parameters**

out	<i>filesystem_info</i>	Buffer to store filesystem information
-----	------------------------	--

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if filesystem_info is NULL

**11.13.2.6 OS\_initfs()**

```
int32 OS_initfs (
    char * address,
```



```

const char * devname,
const char * volname,
size_t blocksize,
osal_blockcount_t numblocks )

```

Initializes an existing file system.

Initializes a file system on the target.

#### Note

The "volname" parameter of RAM disks should always begin with the string "RAM", e.g. "RAMDISK" or "RAM0", "RAM1", etc if multiple devices are created. The underlying implementation uses this to select the correct filesystem type/format, and this may also be used to differentiate between RAM disks and real physical disks.

#### Parameters

in	<i>address</i>	The address at which to start the new disk. If address == 0, then space will be allocated by the OS
in	<i>devname</i>	The underlying kernel device to use, if applicable.
in	<i>volname</i>	The name of the volume (see note)
in	<i>blocksize</i>	The size of a single block on the drive
in	<i>numblocks</i>	The number of blocks to allocate for the drive

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if devname or volname are NULL
<a href="#">OS_FS_ERR_PATH_TOO_LONG</a>	if the name is too long
<a href="#">OS_FS_ERR_DEVICE_NOT_FREE</a>	if the volume table is full
<a href="#">OS_FS_ERR_DRIVE_NOT_CREATED</a>	on error

#### 11.13.2.7 OS\_mkfs()

```

int32 OS_mkfs (
    char * address,
    const char * devname,
    const char * volname,
    size_t blocksize,
    osal_blockcount_t numblocks )

```

Makes a file system on the target.

Makes a file system on the target. Highly dependent on underlying OS and dependent on OS volume table definition.

**Note**

The "volname" parameter of RAM disks should always begin with the string "RAM", e.g. "RAMDISK" or "RAM0", "RAM1", etc if multiple devices are created. The underlying implementation uses this to select the correct filesystem type/format, and this may also be used to differentiate between RAM disks and real physical disks.

**Parameters**

in	<i>address</i>	The address at which to start the new disk. If address == 0 space will be allocated by the OS.
in	<i>devname</i>	The underlying kernel device to use, if applicable.
in	<i>volname</i>	The name of the volume (see note)
in	<i>blocksize</i>	The size of a single block on the drive
in	<i>numblocks</i>	The number of blocks to allocate for the drive

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_INVALID_POINTER</a>	if devname is NULL
<a href="#">OS_FS_ERR_DRIVE_NOT_CREATED</a>	if the OS calls to create the the drive failed
<a href="#">OS_FS_ERR_DEVICE_NOT_FREE</a>	if the volume table is full
<a href="#">OS_SUCCESS</a>	on creating the disk

**11.13.2.8 OS\_mount()**

```
int32 OS_mount (
    const char * devname,
    const char * mountpoint )
```

Mounts a file system.

Mounts a file system / block device at the given mount point.

**Parameters**

in	<i>devname</i>	The name of the drive to mount. devname is the same from <a href="#">OS_mkfs</a>
in	<i>mountpoint</i>	The name to call this disk from now on

**Returns**

Execution status, see [OSAL Return Code Defines](#)

## 11.13.2.9 OS\_rmfs()

```
int32 OS_rmfs (
    const char * devname )
```

Removes a file system.

This function will remove or un-map the target file system. Note that this is not the same as un-mounting the file system.

## Parameters

in	<i>devname</i>	The name of the "generic" drive
----	----------------	---------------------------------

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if devname is NULL
<a href="#">OS_ERROR</a>	is the drive specified cannot be located

## 11.13.2.10 OS\_TranslatePath()

```
int32 OS_TranslatePath (
    const char * VirtualPath,
    char * LocalPath )
```

Translates a OSAL Virtual file system path to a host Local path.

Translates a virtual path to an actual system path name

## Parameters

in	<i>VirtualPath</i>	OSAL virtual path name
out	<i>LocalPath</i>	Buffer to store native/translated path name

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if either parameter is NULL

### 11.13.2.11 OS\_unmount()

```
int32 OS_unmount (
    const char * mountpoint )
```

Unmounts a mounted file system.

This function will unmount a drive from the file system and make all open file descriptors useless.

#### Note

Any open file descriptors referencing this file system should be closed prior to unmounting a drive

#### Parameters

in	<i>mountpoint</i>	The mount point to remove from <a href="#">OS_mount</a>
----	-------------------	---

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if name is NULL
<a href="#">OS_FS_ERR_PATH_TOO_LONG</a>	if the absolute path given is too long
<a href="#">OS_ERROR</a>	if the OS calls failed

## 11.14 OSAL Heap APIs

### Functions

- [int32 OS\\_HeapGetInfo](#) ([OS\\_heap\\_prop\\_t](#) \*heap\_prop)  
*Return current info on the heap.*

### 11.14.1 Detailed Description

### 11.14.2 Function Documentation

#### 11.14.2.1 OS\_HeapGetInfo()

```
int32 OS_HeapGetInfo (  
    OS_heap_prop_t * heap_prop )
```

Return current info on the heap.

#### Parameters

out	<i>heap_prop</i>	Storage buffer for heap info
-----	------------------	------------------------------

#### Returns

Execution status, see [OSAL Return Code Defines](#)

## 11.15 OSAL Object Type Defines

### Macros

- #define `OS_OBJECT_TYPE_UNDEFINED` 0x00  
*Object type undefined.*
- #define `OS_OBJECT_TYPE_OS_TASK` 0x01  
*Object task type.*
- #define `OS_OBJECT_TYPE_OS_QUEUE` 0x02  
*Object queue type.*
- #define `OS_OBJECT_TYPE_OS_COUNTSEM` 0x03  
*Object counting semaphore type.*
- #define `OS_OBJECT_TYPE_OS_BINSEM` 0x04  
*Object binary semaphore type.*
- #define `OS_OBJECT_TYPE_OS_MUTEX` 0x05  
*Object mutex type.*
- #define `OS_OBJECT_TYPE_OS_STREAM` 0x06  
*Object stream type.*
- #define `OS_OBJECT_TYPE_OS_DIR` 0x07  
*Object directory type.*
- #define `OS_OBJECT_TYPE_OS_TIMEBASE` 0x08  
*Object timebase type.*
- #define `OS_OBJECT_TYPE_OS_TIMECB` 0x09  
*Object timer callback type.*
- #define `OS_OBJECT_TYPE_OS_MODULE` 0x0A  
*Object module type.*
- #define `OS_OBJECT_TYPE_OS_FILESYS` 0x0B  
*Object file system type.*
- #define `OS_OBJECT_TYPE_OS_CONSOLE` 0x0C  
*Object console type.*
- #define `OS_OBJECT_TYPE_USER` 0x10  
*Object user type.*

### 11.15.1 Detailed Description

### 11.15.2 Macro Definition Documentation

#### 11.15.2.1 `OS_OBJECT_TYPE_OS_BINSEM`

```
#define OS_OBJECT_TYPE_OS_BINSEM 0x04
```

Object binary semaphore type.

Definition at line 42 of file `osapi-idmap.h`.

#### 11.15.2.2 OS\_OBJECT\_TYPE\_OS\_CONSOLE

```
#define OS_OBJECT_TYPE_OS_CONSOLE 0x0C
```

Object console type.

Definition at line 50 of file osapi-idmap.h.

#### 11.15.2.3 OS\_OBJECT\_TYPE\_OS\_COUNTSEM

```
#define OS_OBJECT_TYPE_OS_COUNTSEM 0x03
```

Object counting semaphore type.

Definition at line 41 of file osapi-idmap.h.

#### 11.15.2.4 OS\_OBJECT\_TYPE\_OS\_DIR

```
#define OS_OBJECT_TYPE_OS_DIR 0x07
```

Object directory type.

Definition at line 45 of file osapi-idmap.h.

#### 11.15.2.5 OS\_OBJECT\_TYPE\_OS\_FILESYS

```
#define OS_OBJECT_TYPE_OS_FILESYS 0x0B
```

Object file system type.

Definition at line 49 of file osapi-idmap.h.

#### 11.15.2.6 OS\_OBJECT\_TYPE\_OS\_MODULE

```
#define OS_OBJECT_TYPE_OS_MODULE 0x0A
```

Object module type.

Definition at line 48 of file osapi-idmap.h.

#### 11.15.2.7 OS\_OBJECT\_TYPE\_OS\_MUTEX

```
#define OS_OBJECT_TYPE_OS_MUTEX 0x05
```

Object mutex type.

Definition at line 43 of file osapi-idmap.h.

#### 11.15.2.8 OS\_OBJECT\_TYPE\_OS\_QUEUE

```
#define OS_OBJECT_TYPE_OS_QUEUE 0x02
```

Object queue type.

Definition at line 40 of file osapi-idmap.h.

#### 11.15.2.9 OS\_OBJECT\_TYPE\_OS\_STREAM

```
#define OS_OBJECT_TYPE_OS_STREAM 0x06
```

Object stream type.

Definition at line 44 of file osapi-idmap.h.

#### 11.15.2.10 OS\_OBJECT\_TYPE\_OS\_TASK

```
#define OS_OBJECT_TYPE_OS_TASK 0x01
```

Object task type.

Definition at line 39 of file osapi-idmap.h.

#### 11.15.2.11 OS\_OBJECT\_TYPE\_OS\_TIMEBASE

```
#define OS_OBJECT_TYPE_OS_TIMEBASE 0x08
```

Object timebase type.

Definition at line 46 of file osapi-idmap.h.



**11.15.2.12 OS\_OBJECT\_TYPE\_OS\_TIMECB**

```
#define OS_OBJECT_TYPE_OS_TIMECB 0x09
```

Object timer callback type.

Definition at line 47 of file osapi-idmap.h.

**11.15.2.13 OS\_OBJECT\_TYPE\_UNDEFINED**

```
#define OS_OBJECT_TYPE_UNDEFINED 0x00
```

Object type undefined.

Definition at line 38 of file osapi-idmap.h.

**11.15.2.14 OS\_OBJECT\_TYPE\_USER**

```
#define OS_OBJECT_TYPE_USER 0x10
```

Object user type.

Definition at line 51 of file osapi-idmap.h.

## 11.16 OSAL Object ID Utility APIs

### Functions

- static unsigned long [OS\\_ObjectIdToInteger](#) ([osal\\_id\\_t](#) object\_id)  
*Obtain an integer value corresponding to an object ID.*
- static [osal\\_id\\_t](#) [OS\\_ObjectIdFromInteger](#) (unsigned long value)  
*Obtain an osal ID corresponding to an integer value.*
- static bool [OS\\_ObjectIdEqual](#) ([osal\\_id\\_t](#) object\_id1, [osal\\_id\\_t](#) object\_id2)  
*Check two OSAL object ID values for equality.*
- static bool [OS\\_ObjectIdDefined](#) ([osal\\_id\\_t](#) object\_id)  
*Check if an object ID is defined.*
- [int32](#) [OS\\_GetResourceName](#) ([osal\\_id\\_t](#) object\_id, char \*buffer, [size\\_t](#) buffer\_size)  
*Obtain the name of an object given an arbitrary object ID.*
- [osal\\_objtype\\_t](#) [OS\\_IdentifyObject](#) ([osal\\_id\\_t](#) object\_id)  
*Obtain the type of an object given an arbitrary object ID.*
- [int32](#) [OS\\_ConvertToArrayIndex](#) ([osal\\_id\\_t](#) object\_id, [osal\\_index\\_t](#) \*ArrayIndex)  
*Converts an abstract ID into a number suitable for use as an array index.*
- [int32](#) [OS\\_ObjectIdToArrayIndex](#) ([osal\\_objtype\\_t](#) idtype, [osal\\_id\\_t](#) object\_id, [osal\\_index\\_t](#) \*ArrayIndex)  
*Converts an abstract ID into a number suitable for use as an array index.*
- void [OS\\_ForEachObject](#) ([osal\\_id\\_t](#) creator\_id, [OS\\_ArgCallback\\_t](#) callback\_ptr, void \*callback\_arg)  
*call the supplied callback function for all valid object IDs*
- void [OS\\_ForEachObjectOfType](#) ([osal\\_objtype\\_t](#) objtype, [osal\\_id\\_t](#) creator\_id, [OS\\_ArgCallback\\_t](#) callback\_ptr, void \*callback\_arg)  
*call the supplied callback function for valid object IDs of a specific type*

### 11.16.1 Detailed Description

### 11.16.2 Function Documentation

#### 11.16.2.1 OS\_ConvertToArrayIndex()

```
int32 OS_ConvertToArrayIndex (
    osal\_id\_t object_id,
    osal\_index\_t * ArrayIndex )
```

Converts an abstract ID into a number suitable for use as an array index.

This will return a unique zero-based integer number in the range of [0,MAX) for any valid object ID. This may be used by application code as an array index for indexing into local tables.

#### Note

This does NOT verify the validity of the ID, that is left to the caller. This is only the conversion logic.

This routine accepts any object type, and returns a value based on the maximum number of objects for that type. This is equivalent to invoking [OS\\_ObjectIdToArrayIndex\(\)](#) with the idtype set to OS\_OBJECT\_TYPE\_UNDEFINED.

#### See also

[OS\\_ObjectIdToArrayIndex](#)

**Parameters**

in	<i>object_id</i>	The object ID to operate on
out	<i>*ArrayIndex</i>	The Index to return

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INCORRECT_OBJ_TYPE</a>	Incorrect object type.

Referenced by OS\_ObjectIdDefined().

**11.16.2.2 OS\_ForEachObject()**

```
void OS_ForEachObject (
    osal_id_t creator_id,
    OS_ArgCallback_t callback_ptr,
    void * callback_arg )
```

call the supplied callback function for all valid object IDs

Loops through all defined OSAL objects of all types and calls callback\_ptr on each one. If creator\_id is nonzero then only objects with matching creator id are processed.

**Parameters**

in	<i>creator_id</i>	Filter objects to those created by a specific task. This may be passed as OS_OBJECT_CREATOR_ANY to return all objects.
in	<i>callback_ptr</i>	Function to invoke for each matching object ID.
in	<i>callback_arg</i>	Opaque Argument to pass to callback function.

Referenced by OS\_ObjectIdDefined().

**11.16.2.3 OS\_ForEachObjectOfType()**

```
void OS_ForEachObjectOfType (
    osal_objtype_t objtype,
    osal_id_t creator_id,
```

```

OS_ArgCallback_t callback_ptr,
void * callback_arg )

```

call the supplied callback function for valid object IDs of a specific type

Loops through all defined OSAL objects of a specific type and calls callback\_ptr on each one. If creator\_id is nonzero then only objects with matching creator id are processed.

#### Parameters

in	<i>objtype</i>	The type of objects to iterate
in	<i>creator_id</i>	Filter objects to those created by a specific task. This may be passed as OS_OBJECT_CREATOR_ANY to return all objects.
in	<i>callback_ptr</i>	Function to invoke for each matching object ID
in	<i>callback_arg</i>	Opaque Argument to pass to callback function

Referenced by OS\_ObjectIdDefined().

#### 11.16.2.4 OS\_GetResourceName()

```

int32 OS_GetResourceName (
    osal_id_t object_id,
    char * buffer,
    size_t buffer_size )

```

Obtain the name of an object given an arbitrary object ID.

All OSAL resources generally have a name associated with them. This allows application code to retrieve the name of any valid OSAL object ID.

#### Parameters

in	<i>object_id</i>	The object ID to operate on
out	<i>buffer</i>	Buffer in which to store the name
in	<i>buffer_size</i>	Size of the output storage buffer

#### Returns

OS\_SUCCESS if successful OS\_ERR\_INVALID\_ID if the passed-in ID is not a valid OSAL ID OS\_INVALID\_POINTER if the passed-in buffer is invalid OS\_ERR\_NAME\_TOO\_LONG if the name will not fit in the buffer provided

Referenced by OS\_ObjectIdDefined().

## 11.16.2.5 OS\_IdentifyObject()

```
osal_objtype_t OS_IdentifyObject (
    osal_id_t object_id )
```

Obtain the type of an object given an arbitrary object ID.

Given an arbitrary object ID, get the type of the object

## Parameters

in	<i>object</i> ↔ _id	The object ID to operate on
----	------------------------	-----------------------------

## Returns

The object type portion of the object\_id, see [OSAL Object Type Defines](#) for expected values

Referenced by OS\_ObjectIdDefined().

## 11.16.2.6 OS\_ObjectIdDefined()

```
static bool OS_ObjectIdDefined (
    osal_id_t object_id ) [inline], [static]
```

Check if an object ID is defined.

The OSAL ID values should be treated as abstract values by applications, and not directly manipulated using standard C operators.

This returns false if the ID is NOT a defined resource (i.e. free/empty/invalid).

## Note

OS\_ObjectIdDefined(OS\_OBJECT\_ID\_UNDEFINED) is always guaranteed to be false.

## Parameters

in	<i>object</i> ↔ _id	The first object ID
----	------------------------	---------------------

Definition at line 139 of file osapi-idmap.h.

References OS\_ConvertToArrayIndex(), OS\_ForEachObject(), OS\_ForEachObjectOfType(), OS\_GetResourceName(), OS\_IdentifyObject(), and OS\_ObjectIdToArrayIndex().

### 11.16.2.7 OS\_ObjectIdEqual()

```
static bool OS_ObjectIdEqual (
    osal_id_t object_id1,
    osal_id_t object_id2 ) [inline], [static]
```

Check two OSAL object ID values for equality.

The OSAL ID values should be treated as abstract values by applications, and not directly manipulated using standard C operators.

This checks two values for equality, replacing the "==" operator.

#### Parameters

in	<i>object_id1</i>	The first object ID
in	<i>object_id2</i>	The second object ID

#### Returns

true if the object IDs are equal

Definition at line 118 of file osapi-idmap.h.

### 11.16.2.8 OS\_ObjectIdFromInteger()

```
static osal_id_t OS_ObjectIdFromInteger (
    unsigned long value ) [inline], [static]
```

Obtain an osal ID corresponding to an integer value.

Provides the inverse of [OS\\_ObjectIdToInteger\(\)](#). Reconstitutes the original `osal_id_t` type from an integer representation.

#### Parameters

in	<i>value</i>	The integer representation of an OSAL ID
----	--------------	--

#### Returns

The ID value converted to an `osal_id_t`

Definition at line 97 of file osapi-idmap.h.

## 11.16.2.9 OS\_ObjectIdToArrayIndex()

```
int32 OS_ObjectIdToArrayIndex (
    osal_objtype_t idtype,
    osal_id_t object_id,
    osal_index_t * ArrayIndex )
```

Converts an abstract ID into a number suitable for use as an array index.

This will return a unique zero-based integer number in the range of [0,MAX) for any valid object ID. This may be used by application code as an array index for indexing into local tables.

This routine operates on a specific object type, and returns a value based on the maximum number of objects for that type.

If the idtype is passed as [OS\\_OBJECT\\_TYPE\\_UNDEFINED](#), then object type verification is skipped and any object ID will be accepted and converted to an index. In this mode, the range of the output depends on the actual passed-in object type.

If the idtype is passed as any other value, the passed-in ID value is first confirmed to be the correct type. This check will guarantee that the output is within an expected range; for instance, if the type is passed as [OS\\_OBJECT\\_TYPE\\_OS\\_TASK](#), then the output index is guaranteed to be between 0 and [OS\\_MAX\\_TASKS](#)-1 after successful conversion.

## Parameters

in	<i>idtype</i>	The object type to convert
in	<i>object_id</i>	The object ID to operate on
out	<i>*ArrayIndex</i>	The Index to return

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INCORRECT_OBJ_TYPE</a>	Incorrect object type.

Referenced by OS\_ObjectIdDefined().

## 11.16.2.10 OS\_ObjectIdToInteger()

```
static unsigned long OS_ObjectIdToInteger (
    osal_id_t object_id ) [inline], [static]
```

Obtain an integer value corresponding to an object ID.

Obtains an integer representation of an object id, generally for the purpose of printing to the console or system logs.

The returned value is of the type "unsigned long" for direct use with printf-style functions. It is recommended to use the "%lx" conversion specifier as the hexadecimal encoding clearly delineates the internal fields.

**Note**

This provides the raw integer value and is *not* suitable for use as an array index, as the result is not zero-based. See the [OS\\_ConvertToArrayIndex\(\)](#) to obtain a zero-based index value.

**Parameters**

in	<i>object</i> ↔ <i>_id</i>	The object ID
----	-------------------------------	---------------

**Returns**

integer value representation of object ID

Definition at line 79 of file osapi-idmap.h.



## 11.17 OSAL Dynamic Loader and Symbol APIs

### Functions

- [int32 OS\\_SymbolLookup](#) ([cpuaddr](#) \*symbol\_address, const char \*symbol\_name)  
*Find the Address of a Symbol.*
- [int32 OS\\_ModuleSymbolLookup](#) ([osal\\_id\\_t](#) module\_id, [cpuaddr](#) \*symbol\_address, const char \*symbol\_name)  
*Find the Address of a Symbol within a module.*
- [int32 OS\\_SymbolTableDump](#) (const char \*filename, [size\\_t](#) size\_limit)  
*Dumps the system symbol table to a file.*
- [int32 OS\\_ModuleLoad](#) ([osal\\_id\\_t](#) \*module\_id, const char \*module\_name, const char \*filename, [uint32](#) flags)  
*Loads an object file.*
- [int32 OS\\_ModuleUnload](#) ([osal\\_id\\_t](#) module\_id)  
*Unloads the module file.*
- [int32 OS\\_ModuleInfo](#) ([osal\\_id\\_t](#) module\_id, [OS\\_module\\_prop\\_t](#) \*module\_info)  
*Obtain information about a module.*

### 11.17.1 Detailed Description

### 11.17.2 Function Documentation

#### 11.17.2.1 OS\_ModuleInfo()

```
int32 OS_ModuleInfo (
    osal\_id\_t module_id,
    OS\_module\_prop\_t * module_info )
```

Obtain information about a module.

Returns information about the loadable module

#### Parameters

in	<a href="#">module_id</a>	OSAL ID of the previously the loaded module
out	<a href="#">module_info</a>	Buffer to store module information

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the module id invalid
<a href="#">OS_INVALID_POINTER</a>	if the pointer to the ModuleInfo structure is invalid

### 11.17.2.2 OS\_ModuleLoad()

```
int32 OS_ModuleLoad (
    osal_id_t * module_id,
    const char * module_name,
    const char * filename,
    uint32 flags )
```

Loads an object file.

Loads an object file into the running operating system

The "flags" parameter may influence how the loaded module symbols are made available for use in the application. See [OS\\_MODULE\\_FLAG\\_LOCAL\\_SYMBOLS](#) and [OS\\_MODULE\\_FLAG\\_GLOBAL\\_SYMBOLS](#) for descriptions.

#### Parameters

out	<i>module_id</i>	Non-zero OSAL ID corresponding to the loaded module
in	<i>module_name</i>	Name of module
in	<i>filename</i>	File containing the object code to load
in	<i>flags</i>	Options for the loaded module

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	if the module cannot be loaded
<a href="#">OS_INVALID_POINTER</a>	if one of the parameters is NULL
<a href="#">OS_ERR_NO_FREE_IDS</a>	if the module table is full
<a href="#">OS_ERR_NAME_TAKEN</a>	if the name is in use

### 11.17.2.3 OS\_ModuleSymbolLookup()

```
int32 OS_ModuleSymbolLookup (
    osal_id_t module_id,
    cpuaddr * symbol_address,
    const char * symbol_name )
```

Find the Address of a Symbol within a module.

This is similar to [OS\\_SymbolLookup\(\)](#) but for a specific module ID. This should be used to look up a symbol in a module that has been loaded with the [OS\\_MODULE\\_FLAG\\_LOCAL\\_SYMBOLS](#) flag.

**Parameters**

in	<i>module_id</i>	Module ID that should contain the symbol
out	<i>symbol_address</i>	Set to the address of the symbol
in	<i>symbol_name</i>	Name of the symbol to look up

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	if the symbol could not be found
<a href="#">OS_INVALID_POINTER</a>	if one of the pointers passed in are NULL

**11.17.2.4 OS\_ModuleUnload()**

```
int32 OS_ModuleUnload (
    osal_id_t module_id )
```

Unloads the module file.

Unloads the module file from the running operating system

**Parameters**

in	<i>module↔ _id</i>	OSAL ID of the previously the loaded module
----	------------------------	---

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	if the module is invalid or cannot be unloaded

**11.17.2.5 OS\_SymbolLookup()**

```
int32 OS_SymbolLookup (
```

```

    cpuaddr * symbol_address,
    const char * symbol_name )

```

Find the Address of a Symbol.

This calls to the OS dynamic symbol lookup implementation, and/or checks a static symbol table for a matching symbol name.

The static table is intended to support embedded targets that do not have module loading capability or have it disabled.

#### Parameters

out	<i>symbol_address</i>	Set to the address of the symbol
in	<i>symbol_name</i>	Name of the symbol to look up

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	if the symbol could not be found
<a href="#">OS_INVALID_POINTER</a>	if one of the pointers passed in are NULL

#### 11.17.2.6 OS\_SymbolTableDump()

```

int32 OS_SymbolTableDump (
    const char * filename,
    size_t size_limit )

```

Dumps the system symbol table to a file.

Dumps the system symbol table to the specified filename

#### Parameters

in	<i>filename</i>	File to write to
in	<i>size_limit</i>	Maximum number of bytes to write

#### Returns

Execution status, see [OSAL Return Code Defines](#)

Return values

<i>OS_SUCCESS</i>	Successful execution.
<i>OS_ERR_NOT_IMPLEMENTED</i>	Not implemented.
<i>OS_ERROR</i>	if the symbol table could not be read or dumped

## 11.18 OSAL Mutex APIs

### Functions

- [int32 OS\\_MutSemCreate](#) ([osal\\_id\\_t](#) \*sem\_id, const char \*sem\_name, [uint32](#) options)  
*Creates a mutex semaphore.*
- [int32 OS\\_MutSemGive](#) ([osal\\_id\\_t](#) sem\_id)  
*Releases the mutex object referenced by sem\_id.*
- [int32 OS\\_MutSemTake](#) ([osal\\_id\\_t](#) sem\_id)  
*Acquire the mutex object referenced by sem\_id.*
- [int32 OS\\_MutSemDelete](#) ([osal\\_id\\_t](#) sem\_id)  
*Deletes the specified Mutex Semaphore.*
- [int32 OS\\_MutSemGetIdByName](#) ([osal\\_id\\_t](#) \*sem\_id, const char \*sem\_name)  
*Find an existing mutex ID by name.*
- [int32 OS\\_MutSemGetInfo](#) ([osal\\_id\\_t](#) sem\_id, [OS\\_mut\\_sem\\_prop\\_t](#) \*mut\_prop)  
*Fill a property object buffer with details regarding the resource.*

### 11.18.1 Detailed Description

### 11.18.2 Function Documentation

#### 11.18.2.1 OS\_MutSemCreate()

```
int32 OS_MutSemCreate (
    osal_id_t * sem_id,
    const char * sem_name,
    uint32 options )
```

Creates a mutex semaphore.

Mutex semaphores are always created in the unlocked (full) state.

#### Parameters

out	<i>sem_id</i>	will be set to the non-zero ID of the newly-created resource
in	<i>sem_name</i>	the name of the new resource to create
in	<i>options</i>	reserved for future use. Should be passed as 0.

#### Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if sem_id or sem_name are NULL
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NO_FREE_IDS</a>	if there are no more free mutex Ids
<a href="#">OS_ERR_NAME_TAKEN</a>	if there is already a mutex with the same name
<a href="#">OS_SEM_FAILURE</a>	if the OS call failed

## 11.18.2.2 OS\_MutSemDelete()

```
int32 OS_MutSemDelete (
    osal_id_t sem_id )
```

Deletes the specified Mutex Semaphore.

Delete the semaphore. This also frees the respective sem\_id such that it can be used again when another is created.

## Parameters

in	<i>sem_id</i>	The object ID to delete
----	---------------	-------------------------

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a valid mutex
<a href="#">OS_SEM_FAILURE</a>	if the OS call failed

## 11.18.2.3 OS\_MutSemGetIdByName()

```
int32 OS_MutSemGetIdByName (
    osal_id_t * sem_id,
    const char * sem_name )
```

Find an existing mutex ID by name.

This function tries to find a mutex sem Id given the name of a mut\_sem. The id is returned through sem\_id

**Parameters**

out	<i>sem_id</i>	will be set to the ID of the existing resource
in	<i>sem_name</i>	the name of the existing resource to find

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	is semid or sem_name are NULL pointers
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NAME_NOT_FOUND</a>	if the name was not found in the table

**11.18.2.4 OS\_MutSemGetInfo()**

```
int32 OS_MutSemGetInfo (
    osal_id_t sem_id,
    OS_mut_sem_prop_t * mut_prop )
```

Fill a property object buffer with details regarding the resource.

This function will pass back a pointer to structure that contains all of the relevant info( name and creator) about the specified mutex semaphore.

**Parameters**

in	<i>sem_id</i>	The object ID to operate on
out	<i>mut_prop</i>	The property object buffer to fill

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a valid semaphore
<a href="#">OS_INVALID_POINTER</a>	if the mut_prop pointer is null



## 11.18.2.5 OS\_MutSemGive()

```
int32 OS_MutSemGive (
    osal_id_t sem_id )
```

Releases the mutex object referenced by sem\_id.

If there are threads blocked on the mutex object referenced by mutex when this function is called, resulting in the mutex becoming available, the scheduling policy shall determine which thread shall acquire the mutex.

## Parameters

in	<i>sem</i> ↔ _id	The object ID to operate on
----	---------------------	-----------------------------

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a valid mutex
<a href="#">OS_SEM_FAILURE</a>	if an unspecified error occurs

## 11.18.2.6 OS\_MutSemTake()

```
int32 OS_MutSemTake (
    osal_id_t sem_id )
```

Acquire the mutex object referenced by sem\_id.

If the mutex is already locked, the calling thread shall block until the mutex becomes available. This operation shall return with the mutex object referenced by mutex in the locked state with the calling thread as its owner.

## Parameters

in	<i>sem</i> ↔ _id	The object ID to operate on
----	---------------------	-----------------------------

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<i>OS_SUCCESS</i>	Successful execution.
<i>OS_SEM_FAILURE</i>	if the semaphore was not previously initialized or is not in the array of semaphores defined by the system
<i>OS_ERR_INVALID_ID</i>	the id passed in is not a valid mutex

## 11.19 Network ID APIs

### Functions

- [int32 OS\\_NetworkGetID](#) (void)  
*Gets the network ID of the local machine.*
- [int32 OS\\_NetworkGetHostName](#) (char \*host\_name, size\_t name\_len)  
*Gets the local machine network host name.*

### 11.19.1 Detailed Description

Provides some basic methods to query a network host name and ID

### 11.19.2 Function Documentation

#### 11.19.2.1 OS\_NetworkGetHostName()

```
int32 OS_NetworkGetHostName (  
    char * host_name,  
    size_t name_len )
```

Gets the local machine network host name.

If configured in the underlying network stack, this function retrieves the local hostname of the system.

#### Parameters

out	<i>host_name</i>	Buffer to hold name information
in	<i>name_len</i>	Maximum length of host name buffer

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### 11.19.2.2 OS\_NetworkGetID()

```
int32 OS_NetworkGetID (  
    void )
```

Gets the network ID of the local machine.

The ID is an implementation-defined value and may not be consistent in meaning across different platform types.

**Note**

This API may be removed in a future version of OSAL due to inconsistencies between platforms.

**Returns**

The ID or fixed value of -1 if the host id could not be found. Note it is not possible to differentiate between error codes and valid network IDs here. It is assumed, however, that -1 is never a valid ID.

## 11.20 OSAL Printf APIs

### Functions

- void [OS\\_printf](#) (const char \*string,...) [OS\\_PRINTF](#)(1  
*Abstraction for the system printf() call.*
- void void [OS\\_printf\\_disable](#) (void)  
*This function disables the output from OS\_printf.*
- void [OS\\_printf\\_enable](#) (void)  
*This function enables the output from OS\_printf.*

### 11.20.1 Detailed Description

### 11.20.2 Function Documentation

#### 11.20.2.1 OS\_printf()

```
void OS_printf (
    const char * string,
    ... )
```

Abstraction for the system printf() call.

This function abstracts out the printf type statements. This is useful for using OS- specific thats that will allow non-pollled print statements for the real time systems.

Operates in a manner similar to the printf() call defined by the standard C library and takes all the parameters and formatting options of printf. This abstraction may implement additional buffering, if necessary, to improve the real-time performance of the call.

Strings (including terminator) longer than [OS\\_BUFFER\\_SIZE](#) will be truncated.

The output of this routine also may be dynamically enabled or disabled by the [OS\\_printf\\_enable\(\)](#) and [OS\\_printf\\_disable\(\)](#) calls, respectively.

#### Parameters

in	<i>string</i>	Format string, followed by additional arguments
----	---------------	---

#### 11.20.2.2 OS\_printf\_disable()

```
void void OS_printf_disable (
    void )
```

This function disables the output from OS\_printf.

#### 11.20.2.3 OS\_printf\_enable()

```
void OS_printf_enable (
    void )
```

This function enables the output from OS\_printf.

## 11.21 OSAL Message Queue APIs

### Functions

- `int32 OS_QueueCreate (osal_id_t *queue_id, const char *queue_name, osal_blockcount_t queue_depth, size_t data_size, uint32 flags)`  
*Create a message queue.*
- `int32 OS_QueueDelete (osal_id_t queue_id)`  
*Deletes the specified message queue.*
- `int32 OS_QueueGet (osal_id_t queue_id, void *data, size_t size, size_t *size_copied, int32 timeout)`  
*Receive a message on a message queue.*
- `int32 OS_QueuePut (osal_id_t queue_id, const void *data, size_t size, uint32 flags)`  
*Put a message on a message queue.*
- `int32 OS_QueueGetIdByName (osal_id_t *queue_id, const char *queue_name)`  
*Find an existing queue ID by name.*
- `int32 OS_QueueGetInfo (osal_id_t queue_id, OS_queue_prop_t *queue_prop)`  
*Fill a property object buffer with details regarding the resource.*

### 11.21.1 Detailed Description

### 11.21.2 Function Documentation

#### 11.21.2.1 OS\_QueueCreate()

```
int32 OS_QueueCreate (
    osal_id_t * queue_id,
    const char * queue_name,
    osal_blockcount_t queue_depth,
    size_t data_size,
    uint32 flags )
```

Create a message queue.

This is the function used to create a queue in the operating system. Depending on the underlying operating system, the memory for the queue will be allocated automatically or allocated by the code that sets up the queue. Queue names must be unique; if the name already exists this function fails. Names cannot be NULL.

#### Parameters

out	<i>queue_id</i>	will be set to the non-zero ID of the newly-created resource
in	<i>queue_name</i>	the name of the new resource to create
in	<i>queue_depth</i>	the maximum depth of the queue
in	<i>data_size</i>	the size of each entry in the queue
in	<i>flags</i>	options for the queue (reserved for future use, pass as 0)

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if a pointer passed in is NULL
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NO_FREE_IDS</a>	if there are already the max queues created
<a href="#">OS_ERR_NAME_TAKEN</a>	if the name is already being used on another queue
<a href="#">OS_QUEUE_INVALID_SIZE</a>	if the queue depth exceeds the limit
<a href="#">OS_ERROR</a>	if the OS create call fails

**11.21.2.2 OS\_QueueDelete()**

```
int32 OS_QueueDelete (
    osal_id_t queue_id )
```

Deletes the specified message queue.

This is the function used to delete a queue in the operating system. This also frees the respective queue\_id to be used again when another queue is created.

**Note**

If There are messages on the queue, they will be lost and any subsequent calls to QueueGet or QueuePut to this queue will result in errors

**Parameters**

in	<i>queue_id</i>	The object ID to delete
----	-----------------	-------------------------

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in does not exist
<a href="#">OS_ERROR</a>	if the OS call to delete the queue fails



## 11.21.2.3 OS\_QueueGet()

```
int32 OS_QueueGet (
    osal_id_t queue_id,
    void * data,
    size_t size,
    size_t * size_copied,
    int32 timeout )
```

Receive a message on a message queue.

If a message is pending, it is returned immediately. Otherwise the calling task will block until a message arrives or the timeout expires.

## Parameters

in	<i>queue_id</i>	The object ID to operate on
out	<i>data</i>	The buffer to store the received message
in	<i>size</i>	The size of the data buffer
out	<i>size_copied</i>	Set to the actual size of the message
in	<i>timeout</i>	The maximum amount of time to block, or OS_PEND to wait forever

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the given ID does not exist
<a href="#">OS_INVALID_POINTER</a>	if a pointer passed in is NULL
<a href="#">OS_QUEUE_EMPTY</a>	if the Queue has no messages on it to be recieved
<a href="#">OS_QUEUE_TIMEOUT</a>	if the timeout was OS_PEND and the time expired
<a href="#">OS_QUEUE_INVALID_SIZE</a>	if the size copied from the queue was not correct

## 11.21.2.4 OS\_QueueGetIdByName()

```
int32 OS_QueueGetIdByName (
    osal_id_t * queue_id,
    const char * queue_name )
```

Find an existing queue ID by name.

This function tries to find a queue Id given the name of the queue. The id of the queue is passed back in queue\_id.

**Parameters**

out	<i>queue_id</i>	will be set to the ID of the existing resource
in	<i>queue_name</i>	the name of the existing resource to find

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if the name or id pointers are NULL
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NAME_NOT_FOUND</a>	the name was not found in the table

**11.21.2.5 OS\_QueueGetInfo()**

```
int32 OS_QueueGetInfo (
    osal_id_t queue_id,
    OS_queue_prop_t * queue_prop )
```

Fill a property object buffer with details regarding the resource.

This function will pass back a pointer to structure that contains all of the relevant info (name and creator) about the specified queue.

**Parameters**

in	<i>queue_id</i>	The object ID to operate on
out	<i>queue_prop</i>	The property object buffer to fill

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if queue_prop is NULL
<a href="#">OS_ERR_INVALID_ID</a>	if the ID given is not a valid queue

## 11.21.2.6 OS\_QueuePut()

```
int32 OS_QueuePut (
    osal_id_t queue_id,
    const void * data,
    size_t size,
    uint32 flags )
```

Put a message on a message queue.

## Parameters

in	<i>queue_id</i>	The object ID to operate on
in	<i>data</i>	The buffer containing the message to put
in	<i>size</i>	The size of the data buffer
in	<i>flags</i>	Currently reserved/unused, should be passed as 0

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the queue id passed in is not a valid queue
<a href="#">OS_INVALID_POINTER</a>	if the data pointer is NULL
<a href="#">OS_QUEUE_FULL</a>	if the queue cannot accept another message
<a href="#">OS_ERROR</a>	if the OS call returns an error

## 11.22 OSAL Select APIs

### Functions

- `int32 OS_SelectMultiple (OS_FdSet *ReadSet, OS_FdSet *WriteSet, int32 msec)`  
*Wait for events across multiple file handles.*
- `int32 OS_SelectSingle (osal_id_t objid, uint32 *StateFlags, int32 msec)`  
*Wait for events on a single file handle.*
- `int32 OS_SelectFdZero (OS_FdSet *Set)`  
*Clear a FdSet structure.*
- `int32 OS_SelectFdAdd (OS_FdSet *Set, osal_id_t objid)`  
*Add an ID to an FdSet structure.*
- `int32 OS_SelectFdClear (OS_FdSet *Set, osal_id_t objid)`  
*Clear an ID from an FdSet structure.*
- `bool OS_SelectFdsSet (OS_FdSet *Set, osal_id_t objid)`  
*Check if an FdSet structure contains a given ID.*

### 11.22.1 Detailed Description

### 11.22.2 Function Documentation

#### 11.22.2.1 OS\_SelectFdAdd()

```
int32 OS_SelectFdAdd (
    OS_FdSet * Set,
    osal_id_t objid )
```

Add an ID to an FdSet structure.

After this call the set will contain the given OSAL ID

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### 11.22.2.2 OS\_SelectFdClear()

```
int32 OS_SelectFdClear (
    OS_FdSet * Set,
    osal_id_t objid )
```

Clear an ID from an FdSet structure.

After this call the set will no longer contain the given OSAL ID

#### Returns

Execution status, see [OSAL Return Code Defines](#)

### 11.22.2.3 OS\_SelectFdsSet()

```
bool OS_SelectFdsIsSet (
    OS_FdSet * Set,
    osal_id_t objid )
```

Check if an FdSet structure contains a given ID.

#### Returns

Boolean set status

#### Return values

<i>true</i>	FdSet structure contains ID
<i>false</i>	FdSet structure does not contain ID

### 11.22.2.4 OS\_SelectFdZero()

```
int32 OS_SelectFdZero (
    OS_FdSet * Set )
```

Clear a FdSet structure.

After this call the set will contain no OSAL IDs

#### Returns

Execution status, see [OSAL Return Code Defines](#)

### 11.22.2.5 OS\_SelectMultiple()

```
int32 OS_SelectMultiple (
    OS_FdSet * ReadSet,
    OS_FdSet * WriteSet,
    int32 msec )
```

Wait for events across multiple file handles.

Wait for any of the given sets of IDs to become readable or writable

This function will block until any of the following occurs:

- At least one OSAL ID in the ReadSet is readable
- At least one OSAL ID in the WriteSet is writable
- The timeout has elapsed

The sets are input/output parameters. On entry, these indicate the file handle(s) to wait for. On exit, these are set to the actual file handle(s) that have activity.

If the timeout occurs this returns an error code and all output sets should be empty.

**Note**

This does not lock or otherwise protect the file handles in the given sets. If a filehandle supplied via one of the `FdSet` arguments is closed or modified by another while this function is in progress, the results are undefined. Because of this limitation, it is recommended to use [OS\\_SelectSingle\(\)](#) whenever possible.

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.22.2.6 OS\_SelectSingle()**

```
int32 OS_SelectSingle (
    osal_id_t objid,
    uint32 * StateFlags,
    int32 msec )
```

Wait for events on a single file handle.

Wait for a single OSAL filehandle to change state

This function can be used to wait for a single OSAL stream ID to become readable or writable. On entry, the "StateFlags" parameter should be set to the desired state (`OS_STREAM_STATE_READABLE` and/or `OS_STREAM_STATE_WRITEABLE`) and upon return the flags will be set to the state actually detected.

As this operates on a single ID, the filehandle is protected during this call, such that another thread accessing the same handle will return an error. However, it is important to note that once the call returns then other threads may then also read/write and affect the state before the current thread can service it.

To mitigate this risk the application may prefer to use the `OS_TimedRead/OS_TimedWrite` calls.

**Returns**

Execution status, see [OSAL Return Code Defines](#)

## 11.23 OSAL Shell APIs

### Functions

- [int32 OS\\_ShellOutputToFile](#) (const char \*Cmd, [osal\\_id\\_t](#) filedes)  
*Executes the command and sends output to a file.*

### 11.23.1 Detailed Description

### 11.23.2 Function Documentation

#### 11.23.2.1 OS\_ShellOutputToFile()

```
int32 OS_ShellOutputToFile (
    const char * Cmd,
    osal_id_t filedes )
```

Executes the command and sends output to a file.

Takes a shell command in and writes the output of that command to the specified file. The output file must be opened previously with write access (OS\_WRITE\_ONLY or OS\_READ\_WRITE).

#### Parameters

in	<i>Cmd</i>	Command to pass to shell
in	<i>filedes</i>	File to send output to.

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	if the command was not executed properly
<a href="#">OS_ERR_INVALID_ID</a>	if the file descriptor passed in is invalid

## 11.24 OSAL Socket Address APIs

### Functions

- `int32 OS_SocketAddrInit (OS_SockAddr_t *Addr, OS_SocketDomain_t Domain)`  
*Initialize a socket address structure to hold an address of the given family.*
- `int32 OS_SocketAddrToString (char *buffer, size_t buflen, const OS_SockAddr_t *Addr)`  
*Get a string representation of a network host address.*
- `int32 OS_SocketAddrFromString (OS_SockAddr_t *Addr, const char *string)`  
*Set a network host address from a string representation.*
- `int32 OS_SocketAddrGetPort (uint16 *PortNum, const OS_SockAddr_t *Addr)`  
*Get the port number of a network address.*
- `int32 OS_SocketAddrSetPort (OS_SockAddr_t *Addr, uint16 PortNum)`  
*Set the port number of a network address.*

### 11.24.1 Detailed Description

These functions provide a means to manipulate network addresses in a manner that is (mostly) agnostic to the actual network address type.

Every network address should be representable as a string (i.e. dotted decimal IP, etc). This can serve as a the "common denominator" to all address types.

### 11.24.2 Function Documentation

#### 11.24.2.1 OS\_SocketAddrFromString()

```
int32 OS_SocketAddrFromString (
    OS_SockAddr_t * Addr,
    const char * string )
```

Set a network host address from a string representation.

The specific format of the output string depends on the address family.

The address structure should have been previously initialized using `OS_SocketAddrInit()` to set the address family type.

#### Note

For IPv4, this would typically be the dotted-decimal format (X.X.X.X). It is up to the discretion of the underlying implementation whether to accept hostnames, as this depends on the availability of DNS services. Since many embedded deployments do not have name services, this should not be relied upon.



**Parameters**

out	<i>Addr</i>	The address buffer to initialize
in	<i>string</i>	The string to initialize the address from.

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.24.2.2 OS\_SocketAddrGetPort()**

```
int32 OS_SocketAddrGetPort (
    uint16 * PortNum,
    const OS_SockAddr_t * Addr )
```

Get the port number of a network address.

For network protocols that have the concept of a port number (such as TCP/IP and UDP/IP) this function gets the port number from the address structure.

**Parameters**

out	<i>PortNum</i>	Buffer to store the port number
in	<i>Addr</i>	The network address buffer

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.24.2.3 OS\_SocketAddrInit()**

```
int32 OS_SocketAddrInit (
    OS_SockAddr_t * Addr,
    OS_SocketDomain_t Domain )
```

Initialize a socket address structure to hold an address of the given family.

The address is set to a suitable default value for the family.

**Parameters**

out	<i>Addr</i>	The address buffer to initialize
in	<i>Domain</i>	The address family

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.24.2.4 OS\_SocketAddrSetPort()**

```
int32 OS_SocketAddrSetPort (
    OS_SockAddr_t * Addr,
    uint16 PortNum )
```

Set the port number of a network address.

For network protocols that have the concept of a port number (such as TCP/IP and UDP/IP) this function sets the port number from the address structure.

**Parameters**

in	<i>PortNum</i>	The port number to set
out	<i>Addr</i>	The network address buffer

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.24.2.5 OS\_SocketAddrToString()**

```
int32 OS_SocketAddrToString (
    char * buffer,
    size_t buflen,
    const OS_SockAddr_t * Addr )
```

Get a string representation of a network host address.

The specific format of the output string depends on the address family.

This string should be suitable to pass back into [OS\\_SocketAddrFromString\(\)](#) which should recreate the same network address, and it should also be meaningful to a user of printed or logged as a C string.

**Note**

For IPv4, this would typically be the dotted-decimal format (X.X.X.X).

**Parameters**

out	<i>buffer</i>	Buffer to hold the output string
in	<i>buflen</i>	Maximum length of the output string
in	<i>Addr</i>	The network address buffer to convert

#### Returns

Execution status, see [OSAL Return Code Defines](#)

## 11.25 OSAL Socket Management APIs

### Functions

- `int32 OS_SocketOpen (osal_id_t *sock_id, OS_SocketDomain_t Domain, OS_SocketType_t Type)`  
*Opens a socket.*
- `int32 OS_SocketBind (osal_id_t sock_id, const OS_SockAddr_t *Addr)`  
*Binds a socket to a given local address.*
- `int32 OS_SocketConnect (osal_id_t sock_id, const OS_SockAddr_t *Addr, int32 timeout)`  
*Connects a socket to a given remote address.*
- `int32 OS_SocketAccept (osal_id_t sock_id, osal_id_t *connsock_id, OS_SockAddr_t *Addr, int32 timeout)`  
*Waits for and accept the next incoming connection on the given socket.*
- `int32 OS_SocketRecvFrom (osal_id_t sock_id, void *buffer, size_t buflen, OS_SockAddr_t *RemoteAddr, int32 timeout)`  
*Reads data from a message-oriented (datagram) socket.*
- `int32 OS_SocketSendTo (osal_id_t sock_id, const void *buffer, size_t buflen, const OS_SockAddr_t *RemoteAddr)`  
*Sends data to a message-oriented (datagram) socket.*
- `int32 OS_SocketGetIdByName (osal_id_t *sock_id, const char *sock_name)`  
*Gets an OSAL ID from a given name.*
- `int32 OS_SocketGetInfo (osal_id_t sock_id, OS_socket_prop_t *sock_prop)`  
*Gets information about an OSAL Socket ID.*
- `int32 OS_NetworkGetID (void)`  
*Gets the network ID of the local machine.*
- `int32 OS_NetworkGetHostName (char *host_name, size_t name_len)`  
*Gets the local machine network host name.*

### 11.25.1 Detailed Description

These functions are loosely related to the BSD Sockets API but made to be more consistent with other OSAL API functions. That is, they operate on OSAL IDs (32-bit opaque number values) and return an OSAL error code.

OSAL Socket IDs are very closely related to File IDs and share the same ID number space. Additionally, the file `OS_read()` / `OS_write()` / `OS_close()` calls also work on sockets.

Note that all of functions may return `OS_ERR_NOT_IMPLEMENTED` if network support is not configured at compile time.

### 11.25.2 Function Documentation

#### 11.25.2.1 OS\_NetworkGetHostName()

```
int32 OS_NetworkGetHostName (
    char * host_name,
    size_t name_len )
```

Gets the local machine network host name.

If configured in the underlying network stack, this function retrieves the local hostname of the system.

**Parameters**

out	<i>host_name</i>	Buffer to hold name information
in	<i>name_len</i>	Maximum length of host name buffer

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.25.2.2 OS\_NetworkGetID()**

```
int32 OS_NetworkGetID (
    void )
```

Gets the network ID of the local machine.

The ID is an implementation-defined value and may not be consistent in meaning across different platform types.

**Note**

This API may be removed in a future version of OSAL due to inconsistencies between platforms.

**Returns**

The ID or fixed value of -1 if the host id could not be found. Note it is not possible to differentiate between error codes and valid network IDs here. It is assumed, however, that -1 is never a valid ID.

**11.25.2.3 OS\_SocketAccept()**

```
int32 OS_SocketAccept (
    osal_id_t sock_id,
    osal_id_t * connsock_id,
    OS_SockAddr_t * Addr,
    int32 timeout )
```

Waits for and accept the next incoming connection on the given socket.

This is used for sockets operating in a "server" role. The socket must be a stream type (connection-oriented) and previously bound to a local address using [OS\\_SocketBind\(\)](#). This will block the caller up to the given timeout or until an incoming connection request occurs, whichever happens first.

The new stream connection is then returned to the caller and the original server socket ID can be reused for the next connection.

**Parameters**

in	<i>sock_id</i>	The server socket ID, previously bound using <a href="#">OS_SocketBind()</a>
out	<i>connsock↔ _id</i>	The connection socket, a new ID that can be read/written
in	<i>Addr</i>	The remote address of the incoming connection
in	<i>timeout</i>	The maximum amount of time to wait, or OS_PEND to wait forever

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.25.2.4 OS\_SocketBind()**

```
int32 OS_SocketBind (
    osal_id_t sock_id,
    const OS_SockAddr_t * Addr )
```

Binds a socket to a given local address.

The specified socket will be bound to the local address and port, if available.

If the socket is connectionless, then it only binds to the local address.

If the socket is connection-oriented (stream), then this will also put the socket into a listening state for incoming connections at the local address.

**Parameters**

in	<i>sock↔ _id</i>	The socket ID
in	<i>Addr</i>	The local address to bind to

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.25.2.5 OS\_SocketConnect()**

```
int32 OS_SocketConnect (
    osal_id_t sock_id,
    const OS_SockAddr_t * Addr,
    int32 timeout )
```

Connects a socket to a given remote address.

The socket will be connected to the remote address and port, if available. This only applies to stream-oriented sockets. Calling this on a datagram socket will return an error (these sockets should use SendTo/RecvFrom).

**Parameters**

in	<i>sock_id</i>	The socket ID
in	<i>Addr</i>	The remote address to connect to
in	<i>timeout</i>	The maximum amount of time to wait, or OS_PEND to wait forever

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.25.2.6 OS\_SocketGetIdByName()**

```
int32 OS_SocketGetIdByName (
    osal_id_t * sock_id,
    const char * sock_name )
```

Gets an OSAL ID from a given name.

**Note**

OSAL Sockets use generated names according to the address and type.

**See also**

[OS\\_SocketGetInfo\(\)](#)

**Parameters**

out	<i>sock_id</i>	Buffer to hold result
in	<i>sock_name</i>	Name of socket to find

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	is id or name are NULL pointers
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NAME_NOT_FOUND</a>	if the name was not found in the table



## 11.25.2.7 OS\_SocketGetInfo()

```
int32 OS_SocketGetInfo (
    osal_id_t sock_id,
    OS_socket_prop_t * sock_prop )
```

Gets information about an OSAL Socket ID.

OSAL Sockets use generated names according to the address and type. This allows applications to find the name of a given socket.

## Parameters

in	<i>sock_id</i>	The socket ID
out	<i>sock_prop</i>	Buffer to hold socket information

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a valid semaphore
<a href="#">OS_INVALID_POINTER</a>	if the count_prop pointer is null

## 11.25.2.8 OS\_SocketOpen()

```
int32 OS_SocketOpen (
    osal_id_t * sock_id,
    OS_SocketDomain_t Domain,
    OS_SocketType_t Type )
```

Opens a socket.

A new, unconnected and unbound socket is allocated of the given domain and type.

## Parameters

out	<i>sock_id</i>	Buffer to hold the non-zero OSAL ID
in	<i>Domain</i>	The domain / address family of the socket (INET or INET6, etc)
in	<i>Type</i>	The type of the socket (STREAM or DATAGRAM)

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.25.2.9 OS\_SocketRecvFrom()**

```
int32 OS_SocketRecvFrom (
    osal_id_t sock_id,
    void * buffer,
    size_t buflen,
    OS_SockAddr_t * RemoteAddr,
    int32 timeout )
```

Reads data from a message-oriented (datagram) socket.

If a message is already available on the socket, this should immediately return that data without blocking. Otherwise, it may block up to the given timeout.

**Parameters**

in	<i>sock_id</i>	The socket ID, previously bound using <a href="#">OS_SocketBind()</a>
out	<i>buffer</i>	Pointer to message data receive buffer
in	<i>buflen</i>	The maximum length of the message data to receive
out	<i>RemoteAddr</i>	Buffer to store the remote network address (may be NULL)
in	<i>timeout</i>	The maximum amount of time to wait, or OS_PEND to wait forever

**Returns**

Count of actual bytes received or error status, see [OSAL Return Code Defines](#)

**11.25.2.10 OS\_SocketSendTo()**

```
int32 OS_SocketSendTo (
    osal_id_t sock_id,
    const void * buffer,
    size_t buflen,
    const OS_SockAddr_t * RemoteAddr )
```

Sends data to a message-oriented (datagram) socket.

This sends data in a non-blocking mode. If the socket is not currently able to queue the message, such as if its outbound buffer is full, then this returns an error code.

**Parameters**

in	<i>sock_id</i>	The socket ID, which must be of the datagram type
in	<i>buffer</i>	Pointer to message data to send
in	<i>buflen</i>	The length of the message data to send
in	<i>RemoteAddr</i>	Buffer containing the remote network address to send to

#### Returns

Count of actual bytes sent or error status, see [OSAL Return Code Defines](#)

## 11.26 OSAL Task APIs

### Functions

- `int32 OS_TaskCreate (osal_id_t *task_id, const char *task_name, osal_task_entry function_pointer, osal_stackptr_t stack_pointer, size_t stack_size, osal_priority_t priority, uint32 flags)`  
*Creates a task and starts running it.*
- `int32 OS_TaskDelete (osal_id_t task_id)`  
*Deletes the specified Task.*
- `void OS_TaskExit (void)`  
*Exits the calling task.*
- `int32 OS_TaskInstallDeleteHandler (osal_task_entry function_pointer)`  
*Installs a handler for when the task is deleted.*
- `int32 OS_TaskDelay (uint32 millisecond)`  
*Delay a task for specified amount of milliseconds.*
- `int32 OS_TaskSetPriority (osal_id_t task_id, osal_priority_t new_priority)`  
*Sets the given task to a new priority.*
- `int32 OS_TaskRegister (void)`  
*Obsolete.*
- `osal_id_t OS_TaskGetId (void)`  
*Obtain the task id of the calling task.*
- `int32 OS_TaskGetIdByName (osal_id_t *task_id, const char *task_name)`  
*Find an existing task ID by name.*
- `int32 OS_TaskGetInfo (osal_id_t task_id, OS_task_prop_t *task_prop)`  
*Fill a property object buffer with details regarding the resource.*
- `int32 OS_TaskFindIdBySystemData (osal_id_t *task_id, const void *sysdata, size_t sysdata_size)`  
*Reverse-lookup the OSAL task ID from an operating system ID.*

### 11.26.1 Detailed Description

### 11.26.2 Function Documentation

#### 11.26.2.1 OS\_TaskCreate()

```
int32 OS_TaskCreate (
    osal_id_t * task_id,
    const char * task_name,
    osal_task_entry function_pointer,
    osal_stackptr_t stack_pointer,
    size_t stack_size,
    osal_priority_t priority,
    uint32 flags )
```

Creates a task and starts running it.

Creates a task and passes back the id of the task created. Task names must be unique; if the name already exists this function fails. Names cannot be NULL.

## Parameters

out	<i>task_id</i>	will be set to the non-zero ID of the newly-created resource
in	<i>task_name</i>	the name of the new resource to create
in	<i>function_pointer</i>	the entry point of the new task
in	<i>stack_pointer</i>	pointer to the stack for the task, or NULL to allocate a stack from the system memory heap
in	<i>stack_size</i>	the size of the stack, or 0 to use a default stack size.
in	<i>priority</i>	initial priority of the new task
in	<i>flags</i>	initial options for the new task

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if any of the necessary pointers are NULL
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_INVALID_PRIORITY</a>	if the priority is bad
<a href="#">OS_ERR_NO_FREE_IDS</a>	if there can be no more tasks created
<a href="#">OS_ERR_NAME_TAKEN</a>	if the name specified is already used by a task
<a href="#">OS_ERROR</a>	if an unspecified/other error occurs

## 11.26.2.2 OS\_TaskDelay()

```
int32 OS_TaskDelay (
    uint32 millisecond )
```

Delay a task for specified amount of milliseconds.

Causes the current thread to be suspended from execution for the period of millisecond.

## Parameters

in	<i>millisecond</i>	Amount of time to delay
----	--------------------	-------------------------

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERROR</a>	if sleep fails or millisecond = 0

### 11.26.2.3 OS\_TaskDelete()

```
int32 OS_TaskDelete (
    osal_id_t task_id )
```

Deletes the specified Task.

The task will be removed from the local tables. and the OS will be configured to stop executing the task at the next opportunity.

#### Parameters

in	<i>task_id</i>	The object ID to operate on
----	----------------	-----------------------------

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the ID given to it is invalid
<a href="#">OS_ERROR</a>	if the OS delete call fails

### 11.26.2.4 OS\_TaskExit()

```
void OS_TaskExit (
    void )
```

Exits the calling task.

The calling thread is terminated. This function does not return.

### 11.26.2.5 OS\_TaskFindIdBySystemData()

```
int32 OS_TaskFindIdBySystemData (
    osal_id_t * task_id,
    const void * sysdata,
    size_t sysdata_size )
```

Reverse-lookup the OSAL task ID from an operating system ID.

This provides a method by which an external entity may find the OSAL task ID corresponding to a system-defined identifier (e.g. TASK\_ID, pthread\_t, rtems\_id, etc).

Normally OSAL does not expose the underlying OS-specific values to the application, but in some circumstances, such as exception handling, the OS may provide this information directly to a BSP handler outside of the normal OSAL API.

**Parameters**

out	<i>task_id</i>	The buffer where the task id output is stored
in	<i>sysdata</i>	Pointer to the system-provided identification data
in	<i>sysdata_size</i>	Size of the system-provided identification data

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
----------------------------	-----------------------

**11.26.2.6 OS\_TaskGetId()**

```
osal_id_t OS_TaskGetId (  
    void )
```

Obtain the task id of the calling task.

This function returns the task id of the calling task

**Returns**

Task ID, or zero if the operation failed (zero is never a valid task ID)

**11.26.2.7 OS\_TaskGetIdByName()**

```
int32 OS_TaskGetIdByName (  
    osal_id_t * task_id,  
    const char * task_name )
```

Find an existing task ID by name.

This function tries to find a task Id given the name of a task

**Parameters**

out	<i>task_id</i>	will be set to the ID of the existing resource
in	<i>task_name</i>	the name of the existing resource to find

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if the pointers passed in are NULL
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NAME_NOT_FOUND</a>	if the name wasn't found in the table

**11.26.2.8 OS\_TaskGetInfo()**

```
int32 OS_TaskGetInfo (
    osal_id_t task_id,
    OS_task_prop_t * task_prop )
```

Fill a property object buffer with details regarding the resource.

This function will pass back a pointer to structure that contains all of the relevant info (creator, stack size, priority, name) about the specified task.

**Parameters**

in	<i>task_id</i>	The object ID to operate on
out	<i>task_prop</i>	The property object buffer to fill

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the ID passed to it is invalid
<a href="#">OS_INVALID_POINTER</a>	if the task_prop pointer is NULL

**11.26.2.9 OS\_TaskInstallDeleteHandler()**

```
int32 OS_TaskInstallDeleteHandler (
    osal_task_entry function_pointer )
```

Installs a handler for when the task is deleted.



This function is used to install a callback that is called when the task is deleted. The callback is called when OS\_TaskDelete is called with the task ID. A task delete handler is useful for cleaning up resources that a task creates, before the task is removed from the system.

#### Parameters

in	<i>function_pointer</i>	function to be called when task exits
----	-------------------------	---------------------------------------

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### 11.26.2.10 OS\_TaskRegister()

```
int32 OS_TaskRegister (
    void )
```

Obsolete.

**Deprecated** Explicit registration call no longer needed

Obsolete function retained for compatibility purposes. Does Nothing in the current implementation.

#### Returns

[OS\\_SUCCESS](#) (always), see [OSAL Return Code Defines](#)

#### 11.26.2.11 OS\_TaskSetPriority()

```
int32 OS_TaskSetPriority (
    osal_id_t task_id,
    osal_priority_t new_priority )
```

Sets the given task to a new priority.

#### Parameters

in	<i>task_id</i>	The object ID to operate on
in	<i>new_priority</i>	Set the new priority

### Returns

Execution status, see [OSAL Return Code Defines](#)

### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the ID passed to it is invalid
<a href="#">OS_ERR_INVALID_PRIORITY</a>	if the priority is greater than the max allowed
<a href="#">OS_ERROR</a>	if the OS call to change the priority fails

## 11.27 OSAL Time Base APIs

### Functions

- `int32 OS_TimeBaseCreate (osal_id_t *timebase_id, const char *timebase_name, OS_TimerSync_t external_sync)`  
*Create an abstract Time Base resource.*
- `int32 OS_TimeBaseSet (osal_id_t timebase_id, uint32 start_time, uint32 interval_time)`  
*Sets the tick period for simulated time base objects.*
- `int32 OS_TimeBaseDelete (osal_id_t timebase_id)`  
*Deletes a time base object.*
- `int32 OS_TimeBaseGetIdByName (osal_id_t *timebase_id, const char *timebase_name)`  
*Find the ID of an existing time base resource.*
- `int32 OS_TimeBaseGetInfo (osal_id_t timebase_id, OS_timebase_prop_t *timebase_prop)`  
*Obtain information about a timebase resource.*
- `int32 OS_TimeBaseGetFreeRun (osal_id_t timebase_id, uint32 *freerun_val)`  
*Read the value of the timebase free run counter.*

### 11.27.1 Detailed Description

### 11.27.2 Function Documentation

#### 11.27.2.1 OS\_TimeBaseCreate()

```
int32 OS_TimeBaseCreate (
    osal_id_t * timebase_id,
    const char * timebase_name,
    OS_TimerSync_t external_sync )
```

Create an abstract Time Base resource.

An OSAL time base is an abstraction of a "timer tick" that can, in turn, be used for measurement of elapsed time between events.

Time bases can be simulated by the operating system using the OS kernel-provided timing facilities, or based on a hardware timing source if provided by the BSP.

A time base object has a servicing task associated with it, that runs at elevated priority and will thereby interrupt user-level tasks when timing ticks occur.

If the `external_sync` function is passed as `NULL`, the operating system kernel timing resources will be utilized for a simulated timer tick.

If the `external_sync` function is not `NULL`, this should point to a BSP-provided function that will block the calling task until the next tick occurs. This can be used for synchronizing with hardware events.

#### Note

When provisioning a tunable RTOS kernel, such as RTEMS, the kernel should be configured to support at least `(OS_MAX_TASKS + OS_MAX_TIMEBASES)` threads, to account for the helper threads associated with time base objects.

**Parameters**

out	<i>timebase_id</i>	A non-zero ID corresponding to the timebase resource
in	<i>timebase_name</i>	The name of the time base
in	<i>external_sync</i>	A synchronization function for BSP hardware-based timer ticks

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.27.2.2 OS\_TimeBaseDelete()**

```
int32 OS_TimeBaseDelete (
    osal_id_t timebase_id )
```

Deletes a time base object.

The helper task and any other resources associated with the time base abstraction will be freed.

**Parameters**

in	<i>timebase_id</i>	The timebase resource to delete
----	--------------------	---------------------------------

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.27.2.3 OS\_TimeBaseGetFreeRun()**

```
int32 OS_TimeBaseGetFreeRun (
    osal_id_t timebase_id,
    uint32 * freerun_val )
```

Read the value of the timebase free run counter.

Poll the timer free-running time counter in a lightweight fashion.

The free run count is a monotonically increasing value reflecting the total time elapsed since the timebase inception. Units are the same as the timebase itself, usually microseconds.

Applications may quickly and efficiently calculate relative time differences by polling this value and subtracting the previous counter value.

The absolute value of this counter is not relevant, because it will "roll over" after  $2^{32}$  units of time. For a timebase with microsecond units, this occurs approximately every 4294 seconds, or about 1.2 hours.

**Note**

To ensure consistency of results, the application should sample the value at a minimum of two times the roll over frequency, and calculate the difference between the consecutive samples.

**Parameters**

in	<i>timebase_id</i>	The timebase to operate on
out	<i>freerun_val</i>	Buffer to store the free run counter

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a valid timebase

**11.27.2.4 OS\_TimeBaseGetIdByName()**

```
int32 OS_TimeBaseGetIdByName (
    osal_id_t * timebase_id,
    const char * timebase_name )
```

Find the ID of an existing time base resource.

Given a time base name, find and output the ID associated with it.

**Parameters**

out	<i>timebase_id</i>	The timebase resource ID
in	<i>timebase_name</i>	The name of the timebase resource to find

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if timebase_id or timebase_name are NULL pointers
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NAME_NOT_FOUND</a>	if the name was not found in the table

## 11.27.2.5 OS\_TimeBaseGetInfo()

```
int32 OS_TimeBaseGetInfo (
    osal_id_t timebase_id,
    OS_timebase_prop_t * timebase_prop )
```

Obtain information about a timebase resource.

Fills the buffer referred to by the timebase\_prop parameter with relevant information about the time base resource.

This function will pass back a pointer to structure that contains all of the relevant info( name and creator) about the specified timebase.

## Parameters

in	<i>timebase_id</i>	The timebase resource ID
out	<i>timebase_prop</i>	Buffer to store timebase properties

## Returns

Execution status, see [OSAL Return Code Defines](#)

## Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a valid timebase
<a href="#">OS_INVALID_POINTER</a>	if the timebase_prop pointer is null

## 11.27.2.6 OS\_TimeBaseSet()

```
int32 OS_TimeBaseSet (
    osal_id_t timebase_id,
    uint32 start_time,
    uint32 interval_time )
```

Sets the tick period for simulated time base objects.

This sets the actual tick period for timing ticks that are simulated by the RTOS kernel (i.e. the "external\_sync" parameter on the call to [OS\\_TimeBaseCreate\(\)](#) is NULL).

The RTOS will be configured to wake up the helper thread at the requested interval.

This function has no effect for time bases that are using a BSP-provided external\_sync function.

## Parameters

in	<i>timebase_id</i>	The timebase resource to configure
in	<i>start_time</i>	The amount of delay for the first tick, in microseconds.
in	<i>interval_time</i>	The amount of delay between ticks, in microseconds.

## Returns

Execution status, see [OSAL Return Code Defines](#)



## 11.28 OSAL Timer APIs

### Functions

- `int32 OS_TimerCreate (osal_id_t *timer_id, const char *timer_name, uint32 *clock_accuracy, OS_Timer↵  
Callback_t callback_ptr)`  
*Create a timer object.*
- `int32 OS_TimerAdd (osal_id_t *timer_id, const char *timer_name, osal_id_t timebase_id, OS_ArgCallback_↵  
t callback_ptr, void *callback_arg)`  
*Add a timer object based on an existing TimeBase resource.*
- `int32 OS_TimerSet (osal_id_t timer_id, uint32 start_time, uint32 interval_time)`  
*Configures a periodic or one shot timer.*
- `int32 OS_TimerDelete (osal_id_t timer_id)`  
*Deletes a timer resource.*
- `int32 OS_TimerGetIdByName (osal_id_t *timer_id, const char *timer_name)`  
*Locate an existing timer resource by name.*
- `int32 OS_TimerGetInfo (osal_id_t timer_id, OS_timer_prop_t *timer_prop)`  
*Gets information about an existing timer.*

### 11.28.1 Detailed Description

### 11.28.2 Function Documentation

#### 11.28.2.1 OS\_TimerAdd()

```
int32 OS_TimerAdd (
    osal_id_t * timer_id,
    const char * timer_name,
    osal_id_t timebase_id,
    OS_ArgCallback_t callback_ptr,
    void * callback_arg )
```

Add a timer object based on an existing TimeBase resource.

A timer object is a resource that invokes the specified application-provided function upon timer expiration. Timers may be one-shot or periodic in nature.

This function uses an existing time base object to service this timer, which must exist prior to adding the timer. The precision of the timer is the same as that of the underlying time base object. Multiple timer objects can be created referring to a single time base object.

This routine also uses a different callback function prototype from [OS\\_TimerCreate\(\)](#), allowing a single opaque argument to be passed to the callback routine. The OSAL implementation does not use this parameter, and may be set NULL.

#### Warning

Depending on the OS, the `callback_ptr` function may be similar to an interrupt service routine. Calls that cause the code to block or require an application context (like sending events) are generally not supported.

**Parameters**

out	<i>timer_id</i>	The non-zero resource ID of the timer object
in	<i>timer_name</i>	Name of the timer object
in	<i>timebase_id</i>	The time base resource to use as a reference
in	<i>callback_ptr</i>	Application-provided function to invoke
in	<i>callback_arg</i>	Opaque argument to pass to callback function

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**11.28.2.2 OS\_TimerCreate()**

```
int32 OS_TimerCreate (
    osal_id_t * timer_id,
    const char * timer_name,
    uint32 * clock_accuracy,
    OS_TimerCallback_t callback_ptr )
```

Create a timer object.

A timer object is a resource that invokes the specified application-provided function upon timer expiration. Timers may be one-shot or periodic in nature.

This function creates a dedicated (hidden) time base object to service this timer, which is created and deleted with the timer object itself. The internal time base is configured for an OS simulated timer tick at the same interval as the timer.

**Note**

*clock\_accuracy* comes from the underlying OS tick value. The nearest integer microsecond value is returned, so may not be exact.

**Warning**

Depending on the OS, the *callback\_ptr* function may be similar to an interrupt service routine. Calls that cause the code to block or require an application context (like sending events) are generally not supported.

**Parameters**

out	<i>timer_id</i>	The non-zero resource ID of the timer object
in	<i>timer_name</i>	Name of the timer object
out	<i>clock_accuracy</i>	Expected precision of the timer, in microseconds. This is the underlying tick value rounded to the nearest microsecond integer.
in	<i>callback_ptr</i>	The function pointer of the timer callback or ISR that will be called by the timer. The user's function is declared as follows: <code>void timer_callback(uint32 timer_id)</code> Where the <i>timer_id</i> is passed in to the function by the OSAL

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if any parameters are NULL
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NAME_TAKEN</a>	if the name is already in use by another timer.
<a href="#">OS_ERR_NO_FREE_IDS</a>	if all of the timers are already allocated.
<a href="#">OS_TIMER_ERR_INVALID_ARGS</a>	if the callback pointer is zero.
<a href="#">OS_TIMER_ERR_UNAVAILABLE</a>	if the timer cannot be created.

**11.28.2.3 OS\_TimerDelete()**

```
int32 OS_TimerDelete (
    osal_id_t timer_id )
```

Deletes a timer resource.

The application callback associated with the timer will be stopped, and the resources freed for future use.

**Parameters**

in	<i>timer</i> ↔ _id	The timer ID to operate on
----	-----------------------	----------------------------

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the timer_id is invalid.
<a href="#">OS_TIMER_ERR_INTERNAL</a>	if there was a problem deleting the timer in the host OS.

**11.28.2.4 OS\_TimerGetIdByName()**

```
int32 OS_TimerGetIdByName (
    osal_id_t * timer_id,
    const char * timer_name )
```

Locate an existing timer resource by name.

Outputs the ID associated with the given timer, if it exists.

#### Parameters

out	<i>timer_id</i>	The timer ID corresponding to the name
in	<i>timer_name</i>	The timer name to find

#### Returns

Execution status, see [OSAL Return Code Defines](#)

#### Return values

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_INVALID_POINTER</a>	if <i>timer_id</i> or <i>timer_name</i> are NULL pointers
<a href="#">OS_ERR_NAME_TOO_LONG</a>	name length including null terminator greater than <a href="#">OS_MAX_API_NAME</a>
<a href="#">OS_ERR_NAME_NOT_FOUND</a>	if the name was not found in the table

#### 11.28.2.5 OS\_TimerGetInfo()

```
int32 OS_TimerGetInfo (
    osal_id_t timer_id,
    OS_timer_prop_t * timer_prop )
```

Gets information about an existing timer.

This function takes *timer\_id*, and looks it up in the OS table. It puts all of the information known about that timer into a structure pointer to by *timer\_prop*.

#### Parameters

in	<i>timer_id</i>	The timer ID to operate on
out	<i>timer_prop</i>	Buffer containing timer properties <ul style="list-style-type: none"> <li>• creator: the OS task ID of the task that created this timer</li> <li>• name: the string name of the timer</li> <li>• start_time: the start time in microseconds, if any</li> <li>• interval_time: the interval time in microseconds, if any</li> <li>• accuracy: the accuracy of the timer in microseconds</li> </ul>

**Returns**

Execution status, see [OSAL Return Code Defines](#)

**Return values**

<a href="#">OS_SUCCESS</a>	Successful execution.
<a href="#">OS_ERR_INVALID_ID</a>	if the id passed in is not a valid timer
<a href="#">OS_INVALID_POINTER</a>	if the timer_prop pointer is null

**11.28.2.6 OS\_TimerSet()**

```
int32 OS_TimerSet (
    osal_id_t timer_id,
    uint32 start_time,
    uint32 interval_time )
```

Configures a periodic or one shot timer.

This function programs the timer with a start time and an optional interval time. The start time is the time in microseconds when the user callback function will be called. If the interval time is non-zero, the timer will be reprogrammed with that interval in microseconds to call the user callback function periodically. If the start time and interval time are zero, the function will return an error.

For a "one-shot" timer, the start\_time configures the expiration time, and the interval\_time should be passed as zero to indicate the timer is not to be automatically reset.

**Note**

The resolution of the times specified is limited to the clock accuracy returned in the OS\_TimerCreate call. If the times specified in the start\_msec or interval\_msec parameters are less than the accuracy, they will be rounded up to the accuracy of the timer.

**Parameters**

in	<i>timer_id</i>	The timer ID to operate on
in	<i>start_time</i>	Time in microseconds to the first expiration
in	<i>interval_time</i>	Time in microseconds between subsequent intervals, value of zero will only call the user callback function once after the start_msec time.

**Returns**

Execution status, see [OSAL Return Code Defines](#)

## Return values

<i>OS_SUCCESS</i>	Successful execution.
<i>OS_ERR_INVALID_ID</i>	if the timer_id is not valid.
<i>OS_TIMER_ERR_INTERNAL</i>	if there was an error programming the OS timer.
<i>OS_ERROR</i>	if both start time and interval time are zero.

## 12 Data Structure Documentation

### 12.1 OS\_bin\_sem\_prop\_t Struct Reference

OSAL binary semaphore properties.

```
#include <osapi-binsem.h>
```

#### Data Fields

- char [name](#) [[OS\\_MAX\\_API\\_NAME](#)]
- [osal\\_id\\_t](#) creator
- [int32](#) value

#### 12.1.1 Detailed Description

OSAL binary semaphore properties.

Definition at line 39 of file [osapi-binsem.h](#).

#### 12.1.2 Field Documentation

##### 12.1.2.1 creator

```
osal\_id\_t OS_bin_sem_prop_t::creator
```

Definition at line 42 of file [osapi-binsem.h](#).

##### 12.1.2.2 name

```
char OS_bin_sem_prop_t::name [OS\_MAX\_API\_NAME]
```

Definition at line 41 of file [osapi-binsem.h](#).

##### 12.1.2.3 value

```
int32 OS_bin_sem_prop_t::value
```

Definition at line 43 of file [osapi-binsem.h](#).

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-binsem.h](#)

## 12.2 OS\_count\_sem\_prop\_t Struct Reference

OSAL counting semaphore properties.

```
#include <osapi-countsem.h>
```

### Data Fields

- char [name](#) [[OS\\_MAX\\_API\\_NAME](#)]
- [osal\\_id\\_t](#) [creator](#)
- [int32](#) [value](#)

### 12.2.1 Detailed Description

OSAL counting semaphore properties.

Definition at line 32 of file [osapi-countsem.h](#).

### 12.2.2 Field Documentation

#### 12.2.2.1 creator

[osal\\_id\\_t](#) [OS\\_count\\_sem\\_prop\\_t::creator](#)

Definition at line 35 of file [osapi-countsem.h](#).

#### 12.2.2.2 name

char [OS\\_count\\_sem\\_prop\\_t::name](#) [[OS\\_MAX\\_API\\_NAME](#)]

Definition at line 34 of file [osapi-countsem.h](#).

#### 12.2.2.3 value

[int32](#) [OS\\_count\\_sem\\_prop\\_t::value](#)

Definition at line 36 of file [osapi-countsem.h](#).

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-countsem.h](#)



## 12.3 os\_dirent\_t Struct Reference

Directory entry.

```
#include <osapi-dir.h>
```

### Data Fields

- char [FileName](#) [[OS\\_MAX\\_FILE\\_NAME](#)]

#### 12.3.1 Detailed Description

Directory entry.

Definition at line 32 of file osapi-dir.h.

#### 12.3.2 Field Documentation

##### 12.3.2.1 FileName

```
char os_dirent_t::FileName[OS\_MAX\_FILE\_NAME]
```

Definition at line 34 of file osapi-dir.h.

The documentation for this struct was generated from the following file:

- osal/src/os/inc/[osapi-dir.h](#)

## 12.4 OS\_FdSet Struct Reference

An abstract structure capable of holding several OSAL IDs.

```
#include <osapi-select.h>
```

### Data Fields

- [uint8 object\\_ids](#) [[\(OS\\_MAX\\_NUM\\_OPEN\\_FILES+7\)/8](#)]

### 12.4.1 Detailed Description

An abstract structure capable of holding several OSAL IDs.

This is part of the select API and is manipulated using the related API calls. It should not be modified directly by applications.

See also

[OS\\_SelectFdZero\(\)](#), [OS\\_SelectFdAdd\(\)](#), [OS\\_SelectFdClear\(\)](#), [OS\\_SelectFdsSet\(\)](#)

Definition at line 39 of file `osapi-select.h`.

### 12.4.2 Field Documentation

#### 12.4.2.1 `object_ids`

```
uint8 OS_FdSet::object_ids[(OS_MAX_NUM_OPEN_FILES+7)/8]
```

Definition at line 41 of file `osapi-select.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-select.h`

## 12.5 `OS_file_prop_t` Struct Reference

OSAL file properties.

```
#include <osapi-file.h>
```

### Data Fields

- `char Path[OS_MAX_PATH_LEN]`
- `osal_id_t User`
- `uint8 IsValid`

### 12.5.1 Detailed Description

OSAL file properties.

Definition at line 49 of file `osapi-file.h`.

### 12.5.2 Field Documentation

#### 12.5.2.1 IsValid

```
uint8 OS_file_prop_t::IsValid
```

Definition at line 53 of file osapi-file.h.

#### 12.5.2.2 Path

```
char OS_file_prop_t::Path[OS_MAX_PATH_LEN]
```

Definition at line 51 of file osapi-file.h.

#### 12.5.2.3 User

```
osal_id_t OS_file_prop_t::User
```

Definition at line 52 of file osapi-file.h.

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-file.h](#)

## 12.6 os\_fsinfo\_t Struct Reference

OSAL file system info.

```
#include <osapi-filesys.h>
```

### Data Fields

- [uint32 MaxFds](#)  
*Total number of file descriptors.*
- [uint32 FreeFds](#)  
*Total number that are free.*
- [uint32 MaxVolumes](#)  
*Maximum number of volumes.*
- [uint32 FreeVolumes](#)  
*Total number of volumes free.*

### 12.6.1 Detailed Description

OSAL file system info.

Definition at line 35 of file osapi-filesys.h.

### 12.6.2 Field Documentation

#### 12.6.2.1 FreeFds

```
uint32 os_fsinfo_t::FreeFds
```

Total number that are free.

Definition at line 38 of file osapi-filesys.h.

#### 12.6.2.2 FreeVolumes

```
uint32 os_fsinfo_t::FreeVolumes
```

Total number of volumes free.

Definition at line 40 of file osapi-filesys.h.

#### 12.6.2.3 MaxFds

```
uint32 os_fsinfo_t::MaxFds
```

Total number of file descriptors.

Definition at line 37 of file osapi-filesys.h.

#### 12.6.2.4 MaxVolumes

```
uint32 os_fsinfo_t::MaxVolumes
```

Maximum number of volumes.

Definition at line 39 of file osapi-filesys.h.

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-filesys.h](#)

## 12.7 os\_fstat\_t Struct Reference

File system status.

```
#include <osapi-file.h>
```

### Data Fields

- [uint32 FileModeBits](#)
- [OS\\_time\\_t FileTime](#)
- [size\\_t FileSize](#)

#### 12.7.1 Detailed Description

File system status.

#### Note

This used to be directly typedef'ed to the "struct stat" from the C library

Some C libraries (glibc in particular) actually define member names to reference into sub-structures, so attempting to reuse a name like "st\_mtime" might not work.

Definition at line 64 of file osapi-file.h.

#### 12.7.2 Field Documentation

##### 12.7.2.1 FileModeBits

```
uint32 os_fstat_t::FileModeBits
```

Definition at line 66 of file osapi-file.h.

##### 12.7.2.2 FileSize

```
size_t os_fstat_t::FileSize
```

Definition at line 68 of file osapi-file.h.

### 12.7.2.3 FileTime

`OS_time_t os_fstat_t::FileTime`

Definition at line 67 of file `osapi-file.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-file.h`

## 12.8 OS\_heap\_prop\_t Struct Reference

OSAL heap properties.

```
#include <osapi-heap.h>
```

### Data Fields

- `size_t free_bytes`
- `osal_blockcount_t free_blocks`
- `size_t largest_free_block`

### 12.8.1 Detailed Description

OSAL heap properties.

#### See also

[`OS\_HeapGetInfo\(\)`](#)

Definition at line 36 of file `osapi-heap.h`.

### 12.8.2 Field Documentation

#### 12.8.2.1 free\_blocks

`osal_blockcount_t OS_heap_prop_t::free_blocks`

Definition at line 39 of file `osapi-heap.h`.

### 12.8.2.2 free\_bytes

```
size_t OS_heap_prop_t::free_bytes
```

Definition at line 38 of file `osapi-heap.h`.

### 12.8.2.3 largest\_free\_block

```
size_t OS_heap_prop_t::largest_free_block
```

Definition at line 40 of file `osapi-heap.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-heap.h`

## 12.9 OS\_module\_address\_t Struct Reference

OSAL module address properties.

```
#include <osapi-module.h>
```

### Data Fields

- `uint32 valid`
- `uint32 flags`
- `cpuaddr code_address`
- `cpuaddr code_size`
- `cpuaddr data_address`
- `cpuaddr data_size`
- `cpuaddr bss_address`
- `cpuaddr bss_size`

### 12.9.1 Detailed Description

OSAL module address properties.

Definition at line 78 of file `osapi-module.h`.

### 12.9.2 Field Documentation

#### 12.9.2.1 `bss_address`

`cpuaddr OS_module_address_t::bss_address`

Definition at line 86 of file `osapi-module.h`.

#### 12.9.2.2 `bss_size`

`cpuaddr OS_module_address_t::bss_size`

Definition at line 87 of file `osapi-module.h`.

#### 12.9.2.3 `code_address`

`cpuaddr OS_module_address_t::code_address`

Definition at line 82 of file `osapi-module.h`.

#### 12.9.2.4 `code_size`

`cpuaddr OS_module_address_t::code_size`

Definition at line 83 of file `osapi-module.h`.

#### 12.9.2.5 `data_address`

`cpuaddr OS_module_address_t::data_address`

Definition at line 84 of file `osapi-module.h`.

#### 12.9.2.6 `data_size`

`cpuaddr OS_module_address_t::data_size`

Definition at line 85 of file `osapi-module.h`.



### 12.9.2.7 flags

`uint32 OS_module_address_t::flags`

Definition at line 81 of file `osapi-module.h`.

### 12.9.2.8 valid

`uint32 OS_module_address_t::valid`

Definition at line 80 of file `osapi-module.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-module.h`

## 12.10 OS\_module\_prop\_t Struct Reference

OSAL module properties.

```
#include <osapi-module.h>
```

### Data Fields

- `cpuaddr entry_point`
- `cpuaddr host_module_id`
- `char filename [OS_MAX_PATH_LEN]`
- `char name [OS_MAX_API_NAME]`
- `OS_module_address_t addr`

### 12.10.1 Detailed Description

OSAL module properties.

Definition at line 91 of file `osapi-module.h`.

### 12.10.2 Field Documentation

#### 12.10.2.1 addr

```
OS_module_address_t OS_module_prop_t::addr
```

Definition at line 97 of file osapi-module.h.

#### 12.10.2.2 entry\_point

```
cpuaddr OS_module_prop_t::entry_point
```

Definition at line 93 of file osapi-module.h.

#### 12.10.2.3 filename

```
char OS_module_prop_t::filename[OS_MAX_PATH_LEN]
```

Definition at line 95 of file osapi-module.h.

#### 12.10.2.4 host\_module\_id

```
cpuaddr OS_module_prop_t::host_module_id
```

Definition at line 94 of file osapi-module.h.

#### 12.10.2.5 name

```
char OS_module_prop_t::name[OS_MAX_API_NAME]
```

Definition at line 96 of file osapi-module.h.

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-module.h](#)

### 12.11 OS\_mut\_sem\_prop\_t Struct Reference

OSAL mutex properties.

```
#include <osapi-mutex.h>
```

### Data Fields

- char [name](#) [OS\_MAX\_API\_NAME]
- [osal\\_id\\_t](#) creator

#### 12.11.1 Detailed Description

OSAL mutex properties.

Definition at line 32 of file osapi-mutex.h.

#### 12.11.2 Field Documentation

##### 12.11.2.1 creator

[osal\\_id\\_t](#) OS\_mut\_sem\_prop\_t::creator

Definition at line 35 of file osapi-mutex.h.

##### 12.11.2.2 name

char OS\_mut\_sem\_prop\_t::name [OS\_MAX\_API\_NAME]

Definition at line 34 of file osapi-mutex.h.

The documentation for this struct was generated from the following file:

- osal/src/os/inc/[osapi-mutex.h](#)

## 12.12 OS\_queue\_prop\_t Struct Reference

OSAL queue properties.

```
#include <osapi-queue.h>
```

### Data Fields

- char [name](#) [OS\_MAX\_API\_NAME]
- [osal\\_id\\_t](#) creator

### 12.12.1 Detailed Description

OSAL queue properties.

Definition at line 32 of file `osapi-queue.h`.

### 12.12.2 Field Documentation

#### 12.12.2.1 creator

`osal_id_t OS_queue_prop_t::creator`

Definition at line 35 of file `osapi-queue.h`.

#### 12.12.2.2 name

`char OS_queue_prop_t::name[OS_MAX_API_NAME]`

Definition at line 34 of file `osapi-queue.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-queue.h`

## 12.13 OS\_SockAddr\_t Struct Reference

Encapsulates a generic network address.

```
#include <osapi-sockets.h>
```

### Data Fields

- `size_t ActualLength`  
*Length of the actual address data.*
- `OS_SockAddrData_t AddrData`  
*Abstract Address data.*

### 12.13.1 Detailed Description

Encapsulates a generic network address.

This is just an abstract buffer type that holds a network address. It is allocated for the worst-case size defined by OS\_SOCKADDR\_MAX\_LEN, and the real size is stored within.

Definition at line 99 of file osapi-sockets.h.

### 12.13.2 Field Documentation

#### 12.13.2.1 ActualLength

```
size_t OS_SockAddr_t::ActualLength
```

Length of the actual address data.

Definition at line 101 of file osapi-sockets.h.

#### 12.13.2.2 AddrData

```
OS_SockAddrData_t OS_SockAddr_t::AddrData
```

Abstract Address data.

Definition at line 102 of file osapi-sockets.h.

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-sockets.h](#)

## 12.14 OS\_SockAddrData\_t Union Reference

Storage buffer for generic network address.

```
#include <osapi-sockets.h>
```

### Data Fields

- [uint8 Buffer \[OS\\_SOCKADDR\\_MAX\\_LEN\]](#)  
*Ensures length of at least OS\_SOCKADDR\_MAX\_LEN.*
- [uint32 AlignU32](#)  
*Ensures uint32 alignment.*
- [void \\* AlignPtr](#)  
*Ensures pointer alignment.*

### 12.14.1 Detailed Description

Storage buffer for generic network address.

This is a union type that helps to ensure a minimum alignment value for the data storage, such that it can be cast to the system-specific type without increasing alignment requirements.

Definition at line 85 of file `osapi-sockets.h`.

### 12.14.2 Field Documentation

#### 12.14.2.1 AlignPtr

```
void* OS_SockAddrData_t::AlignPtr
```

Ensures pointer alignment.

Definition at line 89 of file `osapi-sockets.h`.

#### 12.14.2.2 AlignU32

```
uint32 OS_SockAddrData_t::AlignU32
```

Ensures uint32 alignment.

Definition at line 88 of file `osapi-sockets.h`.

#### 12.14.2.3 Buffer

```
uint8 OS_SockAddrData_t::Buffer[OS_SOCKADDR_MAX_LEN]
```

Ensures length of at least `OS_SOCKADDR_MAX_LEN`.

Definition at line 87 of file `osapi-sockets.h`.

The documentation for this union was generated from the following file:

- `osal/src/os/inc/osapi-sockets.h`

## 12.15 OS\_socket\_prop\_t Struct Reference

Encapsulates socket properties.

```
#include <osapi-sockets.h>
```

### Data Fields

- char [name](#) [OS\_MAX\_API\_NAME]  
*Name of the socket.*
- [osal\\_id\\_t](#) [creator](#)  
*OSAL TaskID which opened the socket.*

### 12.15.1 Detailed Description

Encapsulates socket properties.

This is for consistency with other OSAL resource types. Currently no extra properties are exposed here but this could change in a future revision of OSAL as needed.

Definition at line 112 of file osapi-sockets.h.

### 12.15.2 Field Documentation

#### 12.15.2.1 creator

```
osal\_id\_t OS_socket_prop_t::creator
```

OSAL TaskID which opened the socket.

Definition at line 115 of file osapi-sockets.h.

#### 12.15.2.2 name

```
char OS_socket_prop_t::name[OS\_MAX\_API\_NAME]
```

Name of the socket.

Definition at line 114 of file osapi-sockets.h.

The documentation for this struct was generated from the following file:

- osal/src/os/inc/[osapi-sockets.h](#)

## 12.16 OS\_static\_symbol\_record\_t Struct Reference

Associates a single symbol name with a memory address.

```
#include <osapi-module.h>
```

### Data Fields

- const char \* [Name](#)
- void(\* [Address](#) )(void)
- const char \* [Module](#)

### 12.16.1 Detailed Description

Associates a single symbol name with a memory address.

If the OS\_STATIC\_SYMBOL\_TABLE feature is enabled, then an array of these structures should be provided by the application. When the application needs to find a symbol address, the static table will be checked in addition to (or instead of) the OS/library-provided lookup function.

This static symbol allows systems that do not implement dynamic module loading to maintain the same semantics as dynamically loaded modules.

Definition at line 113 of file osapi-module.h.

### 12.16.2 Field Documentation

#### 12.16.2.1 Address

```
void(* OS_static_symbol_record_t::Address) (void)
```

Definition at line 116 of file osapi-module.h.

#### 12.16.2.2 Module

```
const char* OS_static_symbol_record_t::Module
```

Definition at line 117 of file osapi-module.h.



### 12.16.2.3 Name

```
const char* OS_static_symbol_record_t::Name
```

Definition at line 115 of file osapi-module.h.

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-module.h](#)

## 12.17 OS\_statvfs\_t Struct Reference

```
#include <osapi-filesystem.h>
```

### Data Fields

- [size\\_t](#) [block\\_size](#)
- [osal\\_blockcount\\_t](#) [total\\_blocks](#)
- [osal\\_blockcount\\_t](#) [blocks\\_free](#)

### 12.17.1 Detailed Description

Definition at line 49 of file osapi-filesystem.h.

### 12.17.2 Field Documentation

#### 12.17.2.1 block\_size

```
size_t OS_statvfs_t::block_size
```

Block size of underlying FS

Definition at line 51 of file osapi-filesystem.h.

#### 12.17.2.2 blocks\_free

```
osal\_blockcount\_t OS_statvfs_t::blocks_free
```

Available blocks in underlying FS

Definition at line 53 of file osapi-filesystem.h.

### 12.17.2.3 total\_blocks

`osal_blockcount_t OS_statvfs_t::total_blocks`

Total blocks in underlying FS

Definition at line 52 of file `osapi-filesys.h`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-filesys.h`

## 12.18 OS\_task\_prop\_t Struct Reference

OSAL task properties.

```
#include <osapi-task.h>
```

### Data Fields

- `char name [OS_MAX_API_NAME]`
- `osal_id_t creator`
- `size_t stack_size`
- `osal_priority_t priority`

### 12.18.1 Detailed Description

OSAL task properties.

Definition at line 57 of file `osapi-task.h`.

### 12.18.2 Field Documentation

#### 12.18.2.1 creator

`osal_id_t OS_task_prop_t::creator`

Definition at line 60 of file `osapi-task.h`.

### 12.18.2.2 name

```
char OS_task_prop_t::name[OS_MAX_API_NAME]
```

Definition at line 59 of file osapi-task.h.

### 12.18.2.3 priority

```
osal_priority_t OS_task_prop_t::priority
```

Definition at line 62 of file osapi-task.h.

### 12.18.2.4 stack\_size

```
size_t OS_task_prop_t::stack_size
```

Definition at line 61 of file osapi-task.h.

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-task.h](#)

## 12.19 OS\_time\_t Struct Reference

OSAL time interval structure.

```
#include <osapi-clock.h>
```

### Data Fields

- [int64 ticks](#)

### 12.19.1 Detailed Description

OSAL time interval structure.

This is used to represent a basic time interval.

When used with OS\_GetLocalTime/OS\_SetLocalTime, this represents the interval from the OS's epoch point, typically 01 Jan 1970 00:00:00 UTC on systems that have a persistent real time clock (RTC), or the system boot time if there is no RTC available.

Applications should not directly access fields within this structure, as the definition may change in future versions of OSAL. Instead, applications should use the accessor/conversion methods defined below.

Definition at line 45 of file osapi-clock.h.

## 12.19.2 Field Documentation

### 12.19.2.1 ticks

```
int64 OS_time_t::ticks
```

Ticks elapsed since reference point

Definition at line 47 of file `osapi-clock.h`.

Referenced by `OS_TimeAdd()`, `OS_TimeAssembleFromMicroseconds()`, `OS_TimeAssembleFromMilliseconds()`, `OS_TimeAssembleFromNanoseconds()`, `OS_TimeAssembleFromSubseconds()`, `OS_TimeGetFractionalPart()`, `OS_TimeGetTotalMicroseconds()`, `OS_TimeGetTotalMilliseconds()`, `OS_TimeGetTotalNanoseconds()`, `OS_TimeGetTotalSeconds()`, and `OS_TimeSubtract()`.

The documentation for this struct was generated from the following file:

- `osal/src/os/inc/osapi-clock.h`

## 12.20 OS\_timebase\_prop\_t Struct Reference

Time base properties.

```
#include <osapi-timebase.h>
```

### Data Fields

- `char name [OS_MAX_API_NAME]`
- `osal_id_t creator`
- `uint32 nominal_interval_time`
- `uint32 freerun_time`
- `uint32 accuracy`

### 12.20.1 Detailed Description

Time base properties.

Definition at line 37 of file `osapi-timebase.h`.

### 12.20.2 Field Documentation

### 12.20.2.1 accuracy

```
uint32 OS_timebase_prop_t::accuracy
```

Definition at line 43 of file osapi-timebase.h.

### 12.20.2.2 creator

```
osal_id_t OS_timebase_prop_t::creator
```

Definition at line 40 of file osapi-timebase.h.

### 12.20.2.3 freerun\_time

```
uint32 OS_timebase_prop_t::freerun_time
```

Definition at line 42 of file osapi-timebase.h.

### 12.20.2.4 name

```
char OS_timebase_prop_t::name[OS_MAX_API_NAME]
```

Definition at line 39 of file osapi-timebase.h.

### 12.20.2.5 nominal\_interval\_time

```
uint32 OS_timebase_prop_t::nominal_interval_time
```

Definition at line 41 of file osapi-timebase.h.

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-timebase.h](#)

## 12.21 OS\_timer\_prop\_t Struct Reference

Timer properties.

```
#include <osapi-timer.h>
```

## Data Fields

- char [name](#) [[OS\\_MAX\\_API\\_NAME](#)]
- [osal\\_id\\_t](#) creator
- [uint32](#) start\_time
- [uint32](#) interval\_time
- [uint32](#) accuracy

### 12.21.1 Detailed Description

Timer properties.

Definition at line 37 of file `osapi-timer.h`.

### 12.21.2 Field Documentation

#### 12.21.2.1 accuracy

[uint32](#) `OS_timer_prop_t::accuracy`

Definition at line 43 of file `osapi-timer.h`.

#### 12.21.2.2 creator

[osal\\_id\\_t](#) `OS_timer_prop_t::creator`

Definition at line 40 of file `osapi-timer.h`.

#### 12.21.2.3 interval\_time

[uint32](#) `OS_timer_prop_t::interval_time`

Definition at line 42 of file `osapi-timer.h`.

#### 12.21.2.4 name

char `OS_timer_prop_t::name` [[OS\\_MAX\\_API\\_NAME](#)]

Definition at line 39 of file `osapi-timer.h`.

#### 12.21.2.5 start\_time

```
uint32 OS_timer_prop_t::start_time
```

Definition at line 41 of file osapi-timer.h.

The documentation for this struct was generated from the following file:

- [osal/src/os/inc/osapi-timer.h](#)

## 13 File Documentation

### 13.1 build/doc/osconfig-example.h File Reference

#### Macros

- `#define OS_MAX_TASKS`  
*Configuration file Operating System Abstraction Layer.*
- `#define OS_MAX_QUEUES`  
*The maximum number of queues to support.*
- `#define OS_MAX_COUNT_SEMAPHORES`  
*The maximum number of counting semaphores to support.*
- `#define OS_MAX_BIN_SEMAPHORES`  
*The maximum number of binary semaphores to support.*
- `#define OS_MAX_MUTEXES`  
*The maximum number of mutexes to support.*
- `#define OS_MAX_MODULES`  
*The maximum number of modules to support.*
- `#define OS_MAX_TIMEBASES`  
*The maximum number of timebases to support.*
- `#define OS_MAX_TIMERS`  
*The maximum number of timer callbacks to support.*
- `#define OS_MAX_NUM_OPEN_FILES`  
*The maximum number of concurrently open files to support.*
- `#define OS_MAX_NUM_OPEN_DIRS`  
*The maximum number of concurrently open directories to support.*
- `#define OS_MAX_FILE_SYSTEMS`  
*The maximum number of file systems to support.*
- `#define OS_MAX_SYM_LEN`  
*The maximum length of symbols.*
- `#define OS_MAX_FILE_NAME`  
*The maximum length of OSAL file names.*
- `#define OS_MAX_PATH_LEN`  
*The maximum length of OSAL path names.*
- `#define OS_MAX_API_NAME`

- The maximum length of OSAL resource names.*

  - #define [OS\\_SOCKADDR\\_MAX\\_LEN](#)

*The maximum size of the socket address structure.*
- #define [OS\\_BUFFER\\_SIZE](#)

*The maximum size of output produced by a single [OS\\_printf\(\)](#)*
- #define [OS\\_BUFFER\\_MSG\\_DEPTH](#)

*The maximum number of [OS\\_printf\(\)](#) output strings to buffer.*
- #define [OS\\_UTILITYTASK\\_PRIORITY](#)

*Priority level of the background utility task.*
- #define [OS\\_UTILITYTASK\\_STACK\\_SIZE](#)

*The stack size of the background utility task.*
- #define [OS\\_MAX\\_CMD\\_LEN](#)

*The maximum size of a shell command.*
- #define [OS\\_QUEUE\\_MAX\\_DEPTH](#)

*The maximum depth of OSAL queues.*
- #define [OS\\_SHELL\\_CMD\\_INPUT\\_FILE\\_NAME](#) ""

*The name of the temporary file used to store shell commands.*
- #define [OS\\_PRINTF\\_CONSOLE\\_NAME](#) ""

*The name of the primary console device.*
- #define [OS\\_MAX\\_CONSOLES](#) 1

*The maximum number of console devices to support.*
- #define [OS\\_MODULE\\_FILE\\_EXTENSION](#) ".so"

*The system-specific file extension used on loadable module files.*
- #define [OS\\_FS\\_DEV\\_NAME\\_LEN](#) 32
- #define [OS\\_FS\\_PHYS\\_NAME\\_LEN](#) 64
- #define [OS\\_FS\\_VOL\\_NAME\\_LEN](#) 32

### 13.1.1 Macro Definition Documentation

#### 13.1.1.1 OS\_BUFFER\_MSG\_DEPTH

```
#define OS_BUFFER_MSG_DEPTH
```

The maximum number of [OS\\_printf\(\)](#) output strings to buffer.

Based on the OSAL\_CONFIG\_PRINTF\_BUFFER\_DEPTH configuration option

Definition at line 199 of file osconfig-example.h.



#### 13.1.1.2 OS\_BUFFER\_SIZE

```
#define OS_BUFFER_SIZE
```

The maximum size of output produced by a single [OS\\_printf\(\)](#)

Based on the OSAL\_CONFIG\_PRINTF\_BUFFER\_SIZE configuration option

Definition at line 192 of file osconfig-example.h.

#### 13.1.1.3 OS\_FS\_DEV\_NAME\_LEN

```
#define OS_FS_DEV_NAME_LEN 32
```

Device name length

Definition at line 284 of file osconfig-example.h.

#### 13.1.1.4 OS\_FS\_PHYS\_NAME\_LEN

```
#define OS_FS_PHYS_NAME_LEN 64
```

Physical drive name length

Definition at line 285 of file osconfig-example.h.

#### 13.1.1.5 OS\_FS\_VOL\_NAME\_LEN

```
#define OS_FS_VOL_NAME_LEN 32
```

Volume name length

Definition at line 286 of file osconfig-example.h.

#### 13.1.1.6 OS\_MAX\_API\_NAME

```
#define OS_MAX_API_NAME
```

The maximum length of OSAL resource names.

Based on the OSAL\_CONFIG\_MAX\_API\_NAME configuration option

##### Note

This value must include a terminating NUL character

Definition at line 175 of file osconfig-example.h.

### 13.1.1.7 OS\_MAX\_BIN\_SEMAPHORES

```
#define OS_MAX_BIN_SEMAPHORES
```

The maximum number of binary semaphores to support.

Based on the OSAL\_CONFIG\_MAX\_BIN\_SEMAPHORES configuration option

Definition at line 84 of file osconfig-example.h.

### 13.1.1.8 OS\_MAX\_CMD\_LEN

```
#define OS_MAX_CMD_LEN
```

The maximum size of a shell command.

This limit is only applicable if shell support is enabled.

Based on the OSAL\_CONFIG\_MAX\_CMD\_LEN configuration option

#### Note

This value must include a terminating NUL character

Definition at line 230 of file osconfig-example.h.

### 13.1.1.9 OS\_MAX\_CONSOLES

```
#define OS_MAX_CONSOLES 1
```

The maximum number of console devices to support.

Fixed value based on current OSAL implementation, not user configurable.

Definition at line 272 of file osconfig-example.h.

### 13.1.1.10 OS\_MAX\_COUNT\_SEMAPHORES

```
#define OS_MAX_COUNT_SEMAPHORES
```

The maximum number of counting semaphores to support.

Based on the OSAL\_CONFIG\_MAX\_COUNT\_SEMAPHORES configuration option

Definition at line 77 of file osconfig-example.h.

#### 13.1.1.11 OS\_MAX\_FILE\_NAME

```
#define OS_MAX_FILE_NAME
```

The maximum length of OSAL file names.

This limit applies specifically to the file name portion, not the directory portion, of a path name.

Based on the OSAL\_CONFIG\_MAX\_FILE\_NAME configuration option

##### Note

This value must include a terminating NUL character

Definition at line 154 of file osconfig-example.h.

#### 13.1.1.12 OS\_MAX\_FILE\_SYSTEMS

```
#define OS_MAX_FILE_SYSTEMS
```

The maximum number of file systems to support.

Based on the OSAL\_CONFIG\_MAX\_FILE\_SYSTEMS configuration option

Definition at line 133 of file osconfig-example.h.

#### 13.1.1.13 OS\_MAX\_MODULES

```
#define OS_MAX_MODULES
```

The maximum number of modules to support.

Based on the OSAL\_CONFIG\_MAX\_MODULES configuration option

Definition at line 98 of file osconfig-example.h.

#### 13.1.1.14 OS\_MAX\_MUTEXES

```
#define OS_MAX_MUTEXES
```

The maximum number of mutexes to support.

Based on the OSAL\_CONFIG\_MAX\_MUTEXES configuration option

Definition at line 91 of file osconfig-example.h.

#### 13.1.1.15 OS\_MAX\_NUM\_OPEN\_DIRS

```
#define OS_MAX_NUM_OPEN_DIRS
```

The maximum number of concurrently open directories to support.

Based on the OSAL\_CONFIG\_MAX\_NUM\_OPEN\_DIRS configuration option

Definition at line 126 of file osconfig-example.h.

#### 13.1.1.16 OS\_MAX\_NUM\_OPEN\_FILES

```
#define OS_MAX_NUM_OPEN_FILES
```

The maximum number of concurrently open files to support.

Based on the OSAL\_CONFIG\_MAX\_NUM\_OPEN\_FILES configuration option

Definition at line 119 of file osconfig-example.h.

#### 13.1.1.17 OS\_MAX\_PATH\_LEN

```
#define OS_MAX_PATH_LEN
```

The maximum length of OSAL path names.

This limit applies to the overall length of a path name, including the file name and directory portions.

Based on the OSAL\_CONFIG\_MAX\_PATH\_LEN configuration option

##### Note

This value must include a terminating NUL character

Definition at line 166 of file osconfig-example.h.

#### 13.1.1.18 OS\_MAX\_QUEUES

```
#define OS_MAX_QUEUES
```

The maximum number of queues to support.

Based on the OSAL\_CONFIG\_MAX\_QUEUES configuration option

Definition at line 70 of file osconfig-example.h.

#### 13.1.1.19 OS\_MAX\_SYM\_LEN

```
#define OS_MAX_SYM_LEN
```

The maximum length of symbols.

Based on the OSAL\_CONFIG\_MAX\_SYM\_LEN configuration option

##### Note

This value must include a terminating NUL character

Definition at line 142 of file osconfig-example.h.

#### 13.1.1.20 OS\_MAX\_TASKS

```
#define OS_MAX_TASKS
```

Configuration file Operating System Abstraction Layer.

The specific definitions in this file may only be modified by setting the respective OSAL configuration options in the CMake build.

Any direct modifications to the generated copy will be overwritten each time CMake executes.

##### Note

This file was automatically generated by CMake from /home/runner/work/cFS/cFS/cfe/default\_config.cmake The maximum number of to support

Based on the OSAL\_CONFIG\_MAX\_TASKS configuration option

Definition at line 63 of file osconfig-example.h.

#### 13.1.1.21 OS\_MAX\_TIMEBASES

```
#define OS_MAX_TIMEBASES
```

The maximum number of timebases to support.

Based on the OSAL\_CONFIG\_MAX\_TIMEBASES configuration option

Definition at line 105 of file osconfig-example.h.

### 13.1.1.22 OS\_MAX\_TIMERS

```
#define OS_MAX_TIMERS
```

The maximum number of timer callbacks to support.

Based on the OSAL\_CONFIG\_MAX\_TIMERS configuration option

Definition at line 112 of file osconfig-example.h.

### 13.1.1.23 OS\_MODULE\_FILE\_EXTENSION

```
#define OS_MODULE_FILE_EXTENSION ".so"
```

The system-specific file extension used on loadable module files.

Fixed value based on system selection, not user configurable.

Definition at line 279 of file osconfig-example.h.

### 13.1.1.24 OS\_PRINTF\_CONSOLE\_NAME

```
#define OS_PRINTF_CONSOLE_NAME ""
```

The name of the primary console device.

This is the device to which [OS\\_printf\(\)](#) output is written. The output may be configured to tag each line with this prefix for identification.

Based on the OSAL\_CONFIG\_PRINTF\_CONSOLE\_NAME configuration option

Definition at line 257 of file osconfig-example.h.

### 13.1.1.25 OS\_QUEUE\_MAX\_DEPTH

```
#define OS_QUEUE_MAX_DEPTH
```

The maximum depth of OSAL queues.

Based on the OSAL\_CONFIG\_QUEUE\_MAX\_DEPTH configuration option

Definition at line 237 of file osconfig-example.h.

#### 13.1.1.26 OS\_SHELL\_CMD\_INPUT\_FILE\_NAME

```
#define OS_SHELL_CMD_INPUT_FILE_NAME ""
```

The name of the temporary file used to store shell commands.

This configuration is only applicable if shell support is enabled, and only necessary/relevant on some OS implementations.

Based on the OSAL\_CONFIG\_SHELL\_CMD\_INPUT\_FILE\_NAME configuration option

Definition at line 247 of file osconfig-example.h.

#### 13.1.1.27 OS\_SOCKADDR\_MAX\_LEN

```
#define OS_SOCKADDR_MAX_LEN
```

The maximum size of the socket address structure.

This is part of the Socket API, and should be set large enough to hold the largest address type in use on the target system.

Based on the OSAL\_CONFIG\_SOCKADDR\_MAX\_LEN configuration option

Definition at line 185 of file osconfig-example.h.

#### 13.1.1.28 OS\_UTILITYTASK\_PRIORITY

```
#define OS_UTILITYTASK_PRIORITY
```

Priority level of the background utility task.

This task is responsible for writing buffered output of OS\_printf to the actual console device, and any other future maintenance task.

Based on the OSAL\_CONFIG\_UTILITYTASK\_PRIORITY configuration option

Definition at line 209 of file osconfig-example.h.

#### 13.1.1.29 OS\_UTILITYTASK\_STACK\_SIZE

```
#define OS_UTILITYTASK_STACK_SIZE
```

The stack size of the background utility task.

This task is responsible for writing buffered output of OS\_printf to the actual console device, and any other future maintenance task.

Based on the OSAL\_CONFIG\_UTILITYTASK\_STACK\_SIZE configuration option

Definition at line 219 of file osconfig-example.h.

### 13.2 cfe/docs/src/cfs\_versions.dox File Reference

### 13.3 cfe/docs/src/osal\_fs.dox File Reference

### 13.4 cfe/docs/src/osal\_timer.dox File Reference

### 13.5 cfe/docs/src/osalmain.dox File Reference

### 13.6 osal/src/os/inc/common\_types.h File Reference

```
#include <stdint.h>
#include <stddef.h>
#include <stdbool.h>
```

#### Macros

- #define [CompileTimeAssert](#)(Condition, Message) typedef char Message[(Condition) ? 1 : -1]
- #define [\\_EXTENSION\\_](#)
- #define [OS\\_USED](#)
- #define [OS\\_PRINTF](#)(n, m)
- #define [NULL](#) ((void \*)0)
- #define [OSAL\\_SIZE\\_C](#)(X) ((size\_t)(X))
- #define [OSAL\\_BLOCKCOUNT\\_C](#)(X) ((osal\_blockcount\_t)(X))
- #define [OSAL\\_INDEX\\_C](#)(X) ((osal\_index\_t)(X))
- #define [OSAL\\_OBJTYPE\\_C](#)(X) ((osal\_objtype\_t)(X))

#### Typedefs

- typedef int8\_t [int8](#)
- typedef int16\_t [int16](#)
- typedef int32\_t [int32](#)
- typedef int64\_t [int64](#)
- typedef uint8\_t [uint8](#)
- typedef uint16\_t [uint16](#)
- typedef uint32\_t [uint32](#)
- typedef uint64\_t [uint64](#)
- typedef intptr\_t [intptr](#)
- typedef uintptr\_t [cpuaddr](#)
- typedef size\_t [cpusize](#)
- typedef ptrdiff\_t [cpudiff](#)
- typedef uint32\_t [osal\\_id\\_t](#)
- typedef size\_t [osal\\_blockcount\\_t](#)
- typedef [uint32](#) [osal\\_index\\_t](#)
- typedef [uint32](#) [osal\\_objtype\\_t](#)
- typedef void(\* [OS\\_ArgCallback\\_t](#)) ([osal\\_id\\_t](#) object\_id, void \*arg)

*General purpose OSAL callback function.*



## Functions

- [CompileTimeAssert](#) (sizeof([uint8](#))==1, TypeUInt8WrongSize)
- [CompileTimeAssert](#) (sizeof([uint16](#))==2, TypeUInt16WrongSize)
- [CompileTimeAssert](#) (sizeof([uint32](#))==4, TypeUInt32WrongSize)
- [CompileTimeAssert](#) (sizeof([uint64](#))==8, TypeUInt64WrongSize)
- [CompileTimeAssert](#) (sizeof([int8](#))==1, TypeInt8WrongSize)
- [CompileTimeAssert](#) (sizeof([int16](#))==2, TypeInt16WrongSize)
- [CompileTimeAssert](#) (sizeof([int32](#))==4, TypeInt32WrongSize)
- [CompileTimeAssert](#) (sizeof([int64](#))==8, TypeInt64WrongSize)
- [CompileTimeAssert](#) (sizeof([cpuaddr](#)) >=sizeof(void \*), TypePtrWrongSize)

### 13.6.1 Macro Definition Documentation

#### 13.6.1.1 `_EXTENSION_`

```
#define _EXTENSION_
```

Definition at line 67 of file `common_types.h`.

#### 13.6.1.2 `CompileTimeAssert`

```
#define CompileTimeAssert(  
    Condition,  
    Message ) typedef char Message[(Condition) ? 1 : -1]
```

Definition at line 50 of file `common_types.h`.

#### 13.6.1.3 `NULL`

```
#define NULL ((void *)0)
```

Definition at line 129 of file `common_types.h`.

#### 13.6.1.4 `OS_PRINTF`

```
#define OS_PRINTF(  
    n,  
    m )
```

Definition at line 69 of file `common_types.h`.

### 13.6.1.5 OS\_USED

```
#define OS_USED
```

Definition at line 68 of file common\_types.h.

### 13.6.1.6 OSAL\_BLOCKCOUNT\_C

```
#define OSAL_BLOCKCOUNT_C(  
    X ) ((osal_blockcount_t) (X))
```

Definition at line 187 of file common\_types.h.

### 13.6.1.7 OSAL\_INDEX\_C

```
#define OSAL_INDEX_C(  
    X ) ((osal_index_t) (X))
```

Definition at line 188 of file common\_types.h.

### 13.6.1.8 OSAL\_OBJTYPE\_C

```
#define OSAL_OBJTYPE_C(  
    X ) ((osal_objtype_t) (X))
```

Definition at line 189 of file common\_types.h.

### 13.6.1.9 OSAL\_SIZE\_C

```
#define OSAL_SIZE_C(  
    X ) ((size_t) (X))
```

Definition at line 186 of file common\_types.h.

## 13.6.2 Typedef Documentation

### 13.6.2.1 cpuaddr

```
typedef uintptr_t cpuaddr
```

Definition at line 90 of file common\_types.h.

### 13.6.2.2 cpudiff

```
typedef ptrdiff_t cpudiff
```

Definition at line 92 of file common\_types.h.

### 13.6.2.3 cpusize

```
typedef size_t cpusize
```

Definition at line 91 of file common\_types.h.

### 13.6.2.4 int16

```
typedef int16_t int16
```

Definition at line 82 of file common\_types.h.

### 13.6.2.5 int32

```
typedef int32_t int32
```

Definition at line 83 of file common\_types.h.

### 13.6.2.6 int64

```
typedef int64_t int64
```

Definition at line 84 of file common\_types.h.

### 13.6.2.7 int8

```
typedef int8_t int8
```

Definition at line 81 of file common\_types.h.

### 13.6.2.8 intptr

```
typedef intptr_t intptr
```

Definition at line 89 of file common\_types.h.

### 13.6.2.9 OS\_ArgCallback\_t

```
typedef void(* OS_ArgCallback_t) (osal_id_t object_id, void *arg)
```

General purpose OSAL callback function.

This may be used by multiple APIS

Definition at line 126 of file common\_types.h.

### 13.6.2.10 osal\_blockcount\_t

```
typedef size_t osal_blockcount_t
```

A type used to represent a number of blocks or buffers

This is used with file system and queue implementations.

Definition at line 104 of file common\_types.h.

### 13.6.2.11 osal\_id\_t

```
typedef uint32_t osal_id_t
```

A type to be used for OSAL resource identifiers.

Definition at line 97 of file common\_types.h.

#### 13.6.2.12 osal\_index\_t

```
typedef uint32 osal_index_t
```

A type used to represent an index into a table structure

This is used when referring directly to a table index as opposed to an object ID. It is primarily intended for internal use, but is also output from public APIs such as [OS\\_ObjectIdToArrayIndex\(\)](#).

Definition at line 114 of file common\_types.h.

#### 13.6.2.13 osal\_objtype\_t

```
typedef uint32 osal_objtype_t
```

A type used to represent the runtime type or category of an OSAL object

Definition at line 119 of file common\_types.h.

#### 13.6.2.14 uint16

```
typedef uint16_t uint16
```

Definition at line 86 of file common\_types.h.

#### 13.6.2.15 uint32

```
typedef uint32_t uint32
```

Definition at line 87 of file common\_types.h.

#### 13.6.2.16 uint64

```
typedef uint64_t uint64
```

Definition at line 88 of file common\_types.h.

#### 13.6.2.17 uint8

```
typedef uint8_t uint8
```

Definition at line 85 of file common\_types.h.

### 13.6.3 Function Documentation

#### 13.6.3.1 CompileTimeAssert() [1/9]

```
CompileTimeAssert (
    sizeof(uint8)  = 1,
    TypeUint8WrongSize )
```

#### 13.6.3.2 CompileTimeAssert() [2/9]

```
CompileTimeAssert (
    sizeof(uint16) = 2,
    TypeUint16WrongSize )
```

#### 13.6.3.3 CompileTimeAssert() [3/9]

```
CompileTimeAssert (
    sizeof(uint32) = 4,
    TypeUint32WrongSize )
```

#### 13.6.3.4 CompileTimeAssert() [4/9]

```
CompileTimeAssert (
    sizeof(uint64) = 8,
    TypeUint64WrongSize )
```

#### 13.6.3.5 CompileTimeAssert() [5/9]

```
CompileTimeAssert (
    sizeof(int8)  = 1,
    Typeint8WrongSize )
```

#### 13.6.3.6 CompileTimeAssert() [6/9]

```
CompileTimeAssert (
    sizeof(int16) = 2,
    Typeint16WrongSize )
```

### 13.6.3.7 CompileTimeAssert() [7/9]

```
CompileTimeAssert (
    sizeof(int32)  == 4,
    Typeint32WrongSize )
```

### 13.6.3.8 CompileTimeAssert() [8/9]

```
CompileTimeAssert (
    sizeof(int64)  == 8,
    Typeint64WrongSize )
```

### 13.6.3.9 CompileTimeAssert() [9/9]

```
CompileTimeAssert (
    sizeof(cpuaddr) >= sizeof(void *) ,
    TypePtrWrongSize )
```

## 13.7 osal/src/os/inc/osapi-binsem.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

### Data Structures

- struct [OS\\_bin\\_sem\\_prop\\_t](#)  
*OSAL binary semaphore properties.*

### Macros

- #define [OS\\_SEM\\_FULL](#) 1  
*Semaphore full state.*
- #define [OS\\_SEM\\_EMPTY](#) 0  
*Semaphore empty state.*

## Functions

- [int32 OS\\_BinSemCreate](#) ([osal\\_id\\_t](#) \*sem\_id, const char \*sem\_name, [uint32](#) sem\_initial\_value, [uint32](#) options)  
*Creates a binary semaphore.*
- [int32 OS\\_BinSemFlush](#) ([osal\\_id\\_t](#) sem\_id)  
*Unblock all tasks pending on the specified semaphore.*
- [int32 OS\\_BinSemGive](#) ([osal\\_id\\_t](#) sem\_id)  
*Increment the semaphore value.*
- [int32 OS\\_BinSemTake](#) ([osal\\_id\\_t](#) sem\_id)  
*Decrement the semaphore value.*
- [int32 OS\\_BinSemTimedWait](#) ([osal\\_id\\_t](#) sem\_id, [uint32](#) msec)
- [int32 OS\\_BinSemDelete](#) ([osal\\_id\\_t](#) sem\_id)  
*Deletes the specified Binary Semaphore.*
- [int32 OS\\_BinSemGetIdByName](#) ([osal\\_id\\_t](#) \*sem\_id, const char \*sem\_name)  
*Find an existing semaphore ID by name.*
- [int32 OS\\_BinSemGetInfo](#) ([osal\\_id\\_t](#) sem\_id, [OS\\_bin\\_sem\\_prop\\_t](#) \*bin\_prop)  
*Fill a property object buffer with details regarding the resource.*

## 13.8 osal/src/os/inc/osapi-bsp.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

## Functions

- [uint32 OS\\_BSP\\_GetArgC](#) (void)
- char \*const \* [OS\\_BSP\\_GetArgV](#) (void)
- void [OS\\_BSP\\_SetExitCode](#) ([int32](#) code)

## 13.9 osal/src/os/inc/osapi-clock.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

## Data Structures

- struct [OS\\_time\\_t](#)  
*OSAL time interval structure.*



## Enumerations

- enum { `OS_TIME_TICK_RESOLUTION_NS` = 100, `OS_TIME_TICKS_PER_SECOND` = 1000000000 / `OS_TIME_TICK_RESOLUTION_NS`, `OS_TIME_TICKS_PER_MSEC` = 1000000 / `OS_TIME_TICK_RESOLUTION_NS`, `OS_TIME_TICKS_PER_USEC` = 1000 / `OS_TIME_TICK_RESOLUTION_NS` }

*Multipliers/divisors to convert ticks into standardized units.*

## Functions

- `int32 OS_GetLocalTime (OS_time_t *time_struct)`  
*Get the local time.*
- `int32 OS_SetLocalTime (const OS_time_t *time_struct)`  
*Set the local time.*
- static `int64 OS_TimeGetTotalSeconds (OS_time_t tm)`  
*Get interval from an `OS_time_t` object normalized to whole number of seconds.*
- static `int64 OS_TimeGetTotalMilliseconds (OS_time_t tm)`  
*Get interval from an `OS_time_t` object normalized to millisecond units.*
- static `int64 OS_TimeGetTotalMicroseconds (OS_time_t tm)`  
*Get interval from an `OS_time_t` object normalized to microsecond units.*
- static `int64 OS_TimeGetTotalNanoseconds (OS_time_t tm)`  
*Get interval from an `OS_time_t` object normalized to nanosecond units.*
- static `int64 OS_TimeGetFractionalPart (OS_time_t tm)`  
*Get subseconds portion (fractional part only) from an `OS_time_t` object.*
- static `uint32 OS_TimeGetSubsecondsPart (OS_time_t tm)`  
*Get 32-bit normalized subseconds (fractional part only) from an `OS_time_t` object.*
- static `uint32 OS_TimeGetMillisecondsPart (OS_time_t tm)`  
*Get milliseconds portion (fractional part only) from an `OS_time_t` object.*
- static `uint32 OS_TimeGetMicrosecondsPart (OS_time_t tm)`  
*Get microseconds portion (fractional part only) from an `OS_time_t` object.*
- static `uint32 OS_TimeGetNanosecondsPart (OS_time_t tm)`  
*Get nanoseconds portion (fractional part only) from an `OS_time_t` object.*
- static `OS_time_t OS_TimeAssembleFromNanoseconds (int64 seconds, uint32 nanoseconds)`  
*Assemble/Convert a number of seconds + nanoseconds into an `OS_time_t` interval.*
- static `OS_time_t OS_TimeAssembleFromMicroseconds (int64 seconds, uint32 microseconds)`  
*Assemble/Convert a number of seconds + microseconds into an `OS_time_t` interval.*
- static `OS_time_t OS_TimeAssembleFromMilliseconds (int64 seconds, uint32 milliseconds)`  
*Assemble/Convert a number of seconds + milliseconds into an `OS_time_t` interval.*
- static `OS_time_t OS_TimeAssembleFromSubseconds (int64 seconds, uint32 subseconds)`  
*Assemble/Convert a number of seconds + subseconds into an `OS_time_t` interval.*
- static `OS_time_t OS_TimeAdd (OS_time_t time1, OS_time_t time2)`  
*Computes the sum of two time intervals.*
- static `OS_time_t OS_TimeSubtract (OS_time_t time1, OS_time_t time2)`  
*Computes the difference between two time intervals.*

## 13.9.1 Enumeration Type Documentation

### 13.9.1.1 anonymous enum

`anonymous enum`

Multipliers/divisors to convert ticks into standardized units.

Various fixed conversion factor constants used by the conversion routines

A 100ns tick time allows max intervals of about +/- 14000 years in a 64-bit signed integer value.

#### Note

Applications should not directly use these values, but rather use conversion routines below to obtain standardized units (seconds/microseconds/etc).

#### Enumerator

OS_TIME_TICK_RESOLUTION_NS	
OS_TIME_TICKS_PER_SECOND	
OS_TIME_TICKS_PER_MSEC	
OS_TIME_TICKS_PER_USEC	

Definition at line 61 of file `osapi-clock.h`.

## 13.10 `osal/src/os/inc/osapi-common.h` File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

#### Typedefs

- typedef `int32(* OS_EventHandler_t)` (`OS_Event_t` event, `osal_id_t` object\_id, void \*data)  
*A callback routine for event handling.*

#### Enumerations

- enum `OS_Event_t` {  
`OS_EVENT_RESERVED` = 0, `OS_EVENT_RESOURCE_ALLOCATED`, `OS_EVENT_RESOURCE_CREATED`,  
`OS_EVENT_RESOURCE_DELETED`,  
`OS_EVENT_TASK_STARTUP`, `OS_EVENT_MAX` }  
*A set of events that can be used with BSP event callback routines.*

## Functions

- void [OS\\_Application\\_Startup](#) (void)  
*Application startup.*
- void [OS\\_Application\\_Run](#) (void)  
*Application run.*
- [int32 OS\\_API\\_Init](#) (void)  
*Initialization of API.*
- void [OS\\_IdleLoop](#) (void)  
*Background thread implementation - waits forever for events to occur.*
- void [OS\\_DeleteAllObjects](#) (void)  
*delete all resources created in OSAL.*
- void [OS\\_ApplicationShutdown](#) (uint8 flag)  
*Initiate orderly shutdown.*
- void [OS\\_ApplicationExit](#) (int32 Status)  
*Exit/Abort the application.*
- [int32 OS\\_RegisterEventHandler](#) ([OS\\_EventHandler\\_t](#) handler)  
*Callback routine registration.*

### 13.10.1 Typedef Documentation

#### 13.10.1.1 OS\_EventHandler\_t

```
typedef int32(* OS_EventHandler_t) (OS\_Event\_t event, osal\_id\_t object_id, void *data)
```

A callback routine for event handling.

#### Parameters

in	<i>event</i>	The event that occurred
in	<i>object↔ _id</i>	The associated object_id, or 0 if not associated with an object
in, out	<i>data</i>	An abstract data/context object associated with the event, or NULL.

#### Returns

status Execution status, see [OSAL Return Code Defines](#).

Definition at line 98 of file osapi-common.h.

### 13.10.2 Enumeration Type Documentation

### 13.10.2.1 OS\_Event\_t

enum `OS_Event_t`

A set of events that can be used with BSP event callback routines.

#### Enumerator

<code>OS_EVENT_RESERVED</code>	no-op/reserved event id value
<code>OS_EVENT_RESOURCE_ALLOCATED</code>	resource/id has been newly allocated but not yet created. This event is invoked from WITHIN the locked region, in the context of the task which is allocating the resource. If the handler returns non-success, the error will be returned to the caller and the creation process is aborted.
<code>OS_EVENT_RESOURCE_CREATED</code>	resource/id has been fully created/finalized. Invoked outside locked region, in the context of the task which created the resource. Data object is not used, passed as NULL. Return value is ignored - this is for information purposes only.
<code>OS_EVENT_RESOURCE_DELETED</code>	resource/id has been deleted. Invoked outside locked region, in the context of the task which deleted the resource. Data object is not used, passed as NULL. Return value is ignored - this is for information purposes only.
<code>OS_EVENT_TASK_STARTUP</code>	New task is starting. Invoked outside locked region, in the context of the task which is currently starting, before the entry point is called. Data object is not used, passed as NULL. If the handler returns non-success, task startup is aborted and the entry point is not called.
<code>OS_EVENT_MAX</code>	placeholder for end of enum, not used

Definition at line 34 of file `osapi-common.h`.

### 13.11 osal/src/os/inc/osapi-constants.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

#### Macros

- `#define OS_PEND (-1)`
- `#define OS_CHECK (0)`
- `#define OS_OBJECT_ID_UNDEFINED ((osal_id_t) {0})`  
*Initializer for the `osal_id_t` type which will not match any valid value.*
- `#define OS_OBJECT_CREATOR_ANY OS_OBJECT_ID_UNDEFINED`  
*Constant that may be passed to `OS_ForEachObject()`/`OS_ForEachObjectOfType()` to match any creator (i.e. get all objects)*
- `#define OS_MAX_LOCAL_PATH_LEN (OS_MAX_PATH_LEN + OS_FS_PHYS_NAME_LEN)`  
*Maximum length of a local/native path name string.*

### 13.11.1 Macro Definition Documentation

#### 13.11.1.1 OS\_CHECK

```
#define OS_CHECK (0)
```

Definition at line 35 of file osapi-constants.h.

#### 13.11.1.2 OS\_MAX\_LOCAL\_PATH\_LEN

```
#define OS_MAX_LOCAL_PATH_LEN (OS_MAX_PATH_LEN + OS_FS_PHYS_NAME_LEN)
```

Maximum length of a local/native path name string.

This is a concatenation of the OSAL virtual path with the system mount point or device name

Definition at line 54 of file osapi-constants.h.

#### 13.11.1.3 OS\_OBJECT\_CREATOR\_ANY

```
#define OS_OBJECT_CREATOR_ANY OS_OBJECT_ID_UNDEFINED
```

Constant that may be passed to [OS\\_ForEachObject\(\)](#)/[OS\\_ForEachObjectOfType\(\)](#) to match any creator (i.e. get all objects)

Definition at line 46 of file osapi-constants.h.

#### 13.11.1.4 OS\_OBJECT\_ID\_UNDEFINED

```
#define OS_OBJECT_ID_UNDEFINED ((osal_id_t) {0})
```

Initializer for the `osal_id_t` type which will not match any valid value.

Definition at line 40 of file osapi-constants.h.

#### 13.11.1.5 OS\_PEND

```
#define OS_PEND (-1)
```

Definition at line 34 of file osapi-constants.h.

### 13.12 osal/src/os/inc/osapi-countsem.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

#### Data Structures

- struct [OS\\_count\\_sem\\_prop\\_t](#)  
*OSAL counting semaphore properties.*

#### Functions

- [int32 OS\\_CountSemCreate](#) ([osal\\_id\\_t](#) \*sem\_id, const char \*sem\_name, [uint32](#) sem\_initial\_value, [uint32](#) options)  
*Creates a counting semaphore.*
- [int32 OS\\_CountSemGive](#) ([osal\\_id\\_t](#) sem\_id)  
*Increment the semaphore value.*
- [int32 OS\\_CountSemTake](#) ([osal\\_id\\_t](#) sem\_id)  
*Decrement the semaphore value.*
- [int32 OS\\_CountSemTimedWait](#) ([osal\\_id\\_t](#) sem\_id, [uint32](#) msec)
- [int32 OS\\_CountSemDelete](#) ([osal\\_id\\_t](#) sem\_id)  
*Deletes the specified counting Semaphore.*
- [int32 OS\\_CountSemGetIdByName](#) ([osal\\_id\\_t](#) \*sem\_id, const char \*sem\_name)  
*Find an existing semaphore ID by name.*
- [int32 OS\\_CountSemGetInfo](#) ([osal\\_id\\_t](#) sem\_id, [OS\\_count\\_sem\\_prop\\_t](#) \*count\_prop)  
*Fill a property object buffer with details regarding the resource.*

### 13.13 osal/src/os/inc/osapi-dir.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

#### Data Structures

- struct [os\\_dirent\\_t](#)  
*Directory entry.*

#### Macros

- [#define OS\\_DIRENTRY\\_NAME\(x\) \(\(x\).FileName\)](#)  
*Access filename part of the dirent structure.*

## Functions

- [int32 OS\\_DirectoryOpen](#) ([osal\\_id\\_t](#) \*dir\_id, const char \*path)  
*Opens a directory.*
- [int32 OS\\_DirectoryClose](#) ([osal\\_id\\_t](#) dir\_id)  
*Closes an open directory.*
- [int32 OS\\_DirectoryRewind](#) ([osal\\_id\\_t](#) dir\_id)  
*Rewinds an open directory.*
- [int32 OS\\_DirectoryRead](#) ([osal\\_id\\_t](#) dir\_id, [os\\_dirent\\_t](#) \*dirent)  
*Reads the next name in the directory.*
- [int32 OS\\_mkdir](#) (const char \*path, [uint32](#) access)  
*Makes a new directory.*
- [int32 OS\\_rmdir](#) (const char \*path)  
*Removes a directory from the file system.*

### 13.13.1 Macro Definition Documentation

#### 13.13.1.1 OS\_DIRENTRY\_NAME

```
#define OS_DIRENTRY_NAME(  
    x ) ((x).FileName)
```

Access filename part of the dirent structure.

Definition at line 38 of file osapi-dir.h.

## 13.14 osal/src/os/inc/osapi-error.h File Reference

```
#include "common_types.h"
```

## Macros

- [#define OS\\_ERROR\\_NAME\\_LENGTH](#) 35  
*Error string name length.*
- [#define OS\\_SUCCESS](#) (0)  
*Successful execution.*
- [#define OS\\_ERROR](#) (-1)  
*Failed execution.*
- [#define OS\\_INVALID\\_POINTER](#) (-2)  
*Invalid pointer.*
- [#define OS\\_ERROR\\_ADDRESS\\_MISALIGNED](#) (-3)  
*Address misalignment.*

- `#define OS_ERROR_TIMEOUT` (-4)  
*Error timeout.*
- `#define OS_INVALID_INT_NUM` (-5)  
*Invalid Interrupt number.*
- `#define OS_SEM_FAILURE` (-6)  
*Semaphore failure.*
- `#define OS_SEM_TIMEOUT` (-7)  
*Semaphore timeout.*
- `#define OS_QUEUE_EMPTY` (-8)  
*Queue empty.*
- `#define OS_QUEUE_FULL` (-9)  
*Queue full.*
- `#define OS_QUEUE_TIMEOUT` (-10)  
*Queue timeout.*
- `#define OS_QUEUE_INVALID_SIZE` (-11)  
*Queue invalid size.*
- `#define OS_QUEUE_ID_ERROR` (-12)  
*Queue ID error.*
- `#define OS_ERR_NAME_TOO_LONG` (-13)  
*name length including null terminator greater than `OS_MAX_API_NAME`*
- `#define OS_ERR_NO_FREE_IDS` (-14)  
*No free IDs.*
- `#define OS_ERR_NAME_TAKEN` (-15)  
*Name taken.*
- `#define OS_ERR_INVALID_ID` (-16)  
*Invalid ID.*
- `#define OS_ERR_NAME_NOT_FOUND` (-17)  
*Name not found.*
- `#define OS_ERR_SEM_NOT_FULL` (-18)  
*Semaphore not full.*
- `#define OS_ERR_INVALID_PRIORITY` (-19)  
*Invalid priority.*
- `#define OS_INVALID_SEM_VALUE` (-20)  
*Invalid semaphore value.*
- `#define OS_ERR_FILE` (-27)  
*File error.*
- `#define OS_ERR_NOT_IMPLEMENTED` (-28)  
*Not implemented.*
- `#define OS_TIMER_ERR_INVALID_ARGS` (-29)  
*Timer invalid arguments.*
- `#define OS_TIMER_ERR_TIMER_ID` (-30)  
*Timer ID error.*
- `#define OS_TIMER_ERR_UNAVAILABLE` (-31)  
*Timer unavailable.*
- `#define OS_TIMER_ERR_INTERNAL` (-32)  
*Timer internal error.*
- `#define OS_ERR_OBJECT_IN_USE` (-33)



- *Object in use.*
- `#define OS_ERR_BAD_ADDRESS (-34)`
- *Bad address.*
- `#define OS_ERR_INCORRECT_OBJ_STATE (-35)`
- *Incorrect object state.*
- `#define OS_ERR_INCORRECT_OBJ_TYPE (-36)`
- *Incorrect object type.*
- `#define OS_ERR_STREAM_DISCONNECTED (-37)`
- *Stream disconnected.*
- `#define OS_ERR_OPERATION_NOT_SUPPORTED (-38)`
- *Requested operation not support on supplied object(s)*
- `#define OS_ERR_INVALID_SIZE (-40)`
- *Invalid Size.*
- `#define OS_FS_ERR_PATH_TOO_LONG (-103)`
- *FS path too long.*
- `#define OS_FS_ERR_NAME_TOO_LONG (-104)`
- *FS name too long.*
- `#define OS_FS_ERR_DRIVE_NOT_CREATED (-106)`
- *FS drive not created.*
- `#define OS_FS_ERR_DEVICE_NOT_FREE (-107)`
- *FS device not free.*
- `#define OS_FS_ERR_PATH_INVALID (-108)`
- *FS path invalid.*

#### Typedefs

- `typedef char os_err_name_t[OS_ERROR_NAME_LENGTH]`  
*For the `OS_GetErrorName()` function, to ensure everyone is making an array of the same length.*

#### Functions

- `int32 OS_GetErrorName (int32 error_num, os_err_name_t *err_name)`  
*Convert an error number to a string.*

### 13.14.1 Macro Definition Documentation

#### 13.14.1.1 OS\_ERROR\_NAME\_LENGTH

```
#define OS_ERROR_NAME_LENGTH 35
```

Error string name length.

The sizes of strings in OSAL functions are built with this limit in mind. Always check the uses of `os_err_name_t` when changing this value.

Definition at line 35 of file `osapi-error.h`.

### 13.14.2 Typedef Documentation

#### 13.14.2.1 os\_err\_name\_t

```
typedef char os_err_name_t[OS_ERROR_NAME_LENGTH]
```

For the [OS\\_GetErrorName\(\)](#) function, to ensure everyone is making an array of the same length.

Implementation note for developers:

The sizes of strings in OSAL functions are built with this [OS\\_ERROR\\_NAME\\_LENGTH](#) limit in mind. Always check the uses of `os_err_name_t` when changing this value.

Definition at line 47 of file `osapi-error.h`.

### 13.15 osal/src/os/inc/osapi-file.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
#include "osapi-clock.h"
```

#### Data Structures

- struct [OS\\_file\\_prop\\_t](#)  
*OSAL file properties.*
- struct [os\\_fstat\\_t](#)  
*File system status.*

#### Macros

- `#define OS_READ_ONLY 0`
- `#define OS_WRITE_ONLY 1`
- `#define OS_READ_WRITE 2`
- `#define OS_SEEK_SET 0`
- `#define OS_SEEK_CUR 1`
- `#define OS_SEEK_END 2`
- `#define OS_FILESTAT_MODE(x) ((x).FileModeBits)`  
*Access file stat mode bits.*
- `#define OS_FILESTAT_ISDIR(x) ((x).FileModeBits & OS_FILESTAT_MODE_DIR)`  
*File stat is directory logical.*
- `#define OS_FILESTAT_EXEC(x) ((x).FileModeBits & OS_FILESTAT_MODE_EXEC)`  
*File stat is executable logical.*
- `#define OS_FILESTAT_WRITE(x) ((x).FileModeBits & OS_FILESTAT_MODE_WRITE)`  
*File stat is write enabled logical.*
- `#define OS_FILESTAT_READ(x) ((x).FileModeBits & OS_FILESTAT_MODE_READ)`  
*File stat is read enabled logical.*
- `#define OS_FILESTAT_SIZE(x) ((x).FileSize)`  
*Access file stat size field.*
- `#define OS_FILESTAT_TIME(x) (OS_TimeGetTotalSeconds((x).FileTime))`  
*Access file stat time field as a whole number of seconds.*

## Enumerations

- enum { `OS_FILESTAT_MODE_EXEC` = 0x00001, `OS_FILESTAT_MODE_WRITE` = 0x00002, `OS_FILESTAT_MODE_READ` = 0x00004, `OS_FILESTAT_MODE_DIR` = 0x10000 }

*File stat mode bits.*

- enum `OS_file_flag_t` { `OS_FILE_FLAG_NONE` = 0x00, `OS_FILE_FLAG_CREATE` = 0x01, `OS_FILE_FLAG_TRUNCATE` = 0x02 }

*Flags that can be used with opening of a file (bitmask)*

## Functions

- `int32 OS_OpenCreate` (`osal_id_t` \*filedes, const char \*path, `int32` flags, `int32` access)  
*Open or create a file.*
- `int32 OS_close` (`osal_id_t` filedes)  
*Closes an open file handle.*
- `int32 OS_read` (`osal_id_t` filedes, void \*buffer, `size_t` nbytes)  
*Read from a file handle.*
- `int32 OS_write` (`osal_id_t` filedes, const void \*buffer, `size_t` nbytes)  
*Write to a file handle.*
- `int32 OS_TimedRead` (`osal_id_t` filedes, void \*buffer, `size_t` nbytes, `int32` timeout)  
*File/Stream input read with a timeout.*
- `int32 OS_TimedWrite` (`osal_id_t` filedes, const void \*buffer, `size_t` nbytes, `int32` timeout)  
*File/Stream output write with a timeout.*
- `int32 OS_chmod` (const char \*path, `uint32` access)  
*Changes the permissions of a file.*
- `int32 OS_stat` (const char \*path, `os_fstat_t` \*filestats)  
*Obtain information about a file or directory.*
- `int32 OS_lseek` (`osal_id_t` filedes, `int32` offset, `uint32` whence)  
*Seeks to the specified position of an open file.*
- `int32 OS_remove` (const char \*path)  
*Removes a file from the file system.*
- `int32 OS_rename` (const char \*old\_filename, const char \*new\_filename)  
*Renames a file.*
- `int32 OS_cp` (const char \*src, const char \*dest)  
*Copies a single file from src to dest.*
- `int32 OS_mv` (const char \*src, const char \*dest)  
*Move a single file from src to dest.*
- `int32 OS_FDGetInfo` (`osal_id_t` filedes, `OS_file_prop_t` \*fd\_prop)  
*Obtain information about an open file.*
- `int32 OS_FileOpenCheck` (const char \*Filename)  
*Checks to see if a file is open.*
- `int32 OS_CloseAllFiles` (void)  
*Close all open files.*
- `int32 OS_CloseFileByName` (const char \*Filename)  
*Close a file by filename.*

### 13.15.1 Macro Definition Documentation

#### 13.15.1.1 OS\_FILESTAT\_EXEC

```
#define OS_FILESTAT_EXEC(  
    x ) ((x).FileModeBits & OS_FILESTAT_MODE_EXEC)
```

File stat is executable logical.

Definition at line 92 of file osapi-file.h.

#### 13.15.1.2 OS\_FILESTAT\_ISDIR

```
#define OS_FILESTAT_ISDIR(  
    x ) ((x).FileModeBits & OS_FILESTAT_MODE_DIR)
```

File stat is directory logical.

Definition at line 90 of file osapi-file.h.

#### 13.15.1.3 OS\_FILESTAT\_MODE

```
#define OS_FILESTAT_MODE(  
    x ) ((x).FileModeBits)
```

Access file stat mode bits.

Definition at line 88 of file osapi-file.h.

#### 13.15.1.4 OS\_FILESTAT\_READ

```
#define OS_FILESTAT_READ(  
    x ) ((x).FileModeBits & OS_FILESTAT_MODE_READ)
```

File stat is read enabled logical.

Definition at line 96 of file osapi-file.h.

### 13.15.1.5 OS\_FILESTAT\_SIZE

```
#define OS_FILESTAT_SIZE(  
    x ) ((x).FileSize)
```

Access file stat size field.

Definition at line 98 of file osapi-file.h.

### 13.15.1.6 OS\_FILESTAT\_TIME

```
#define OS_FILESTAT_TIME(  
    x ) (OS_TimeGetTotalSeconds((x).FileTime))
```

Access file stat time field as a whole number of seconds.

Definition at line 100 of file osapi-file.h.

### 13.15.1.7 OS\_FILESTAT\_WRITE

```
#define OS_FILESTAT_WRITE(  
    x ) ((x).FileModeBits & OS_FILESTAT_MODE_WRITE)
```

File stat is write enabled logical.

Definition at line 94 of file osapi-file.h.

## 13.15.2 Enumeration Type Documentation

### 13.15.2.1 anonymous enum

anonymous enum

File stat mode bits.

We must also define replacements for the stat structure's mode bits. This is currently just a small subset since the OSAL just presents a very simplified view of the filesystem to the upper layers. And since not all OS'es are POSIX, the more POSIX-specific bits are not relevant anyway.

Enumerator

OS_FILESTAT_MODE_EXEC	
OS_FILESTAT_MODE_WRITE	
OS_FILESTAT_MODE_READ	
OS_FILESTAT_MODE_DIR	

Definition at line 79 of file osapi-file.h.

### 13.15.2.2 OS\_file\_flag\_t

```
enum OS_file_flag_t
```

Flags that can be used with opening of a file (bitmask)

#### Enumerator

OS_FILE_FLAG_NONE	
OS_FILE_FLAG_CREATE	
OS_FILE_FLAG_TRUNCATE	

Definition at line 105 of file osapi-file.h.

## 13.16 osal/src/os/inc/osapi-filesys.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

#### Data Structures

- struct [os\\_fsinfo\\_t](#)  
*OSAL file system info.*
- struct [OS\\_statvfs\\_t](#)

#### Macros

- #define [OS\\_CHK\\_ONLY](#) 0
- #define [OS\\_REPAIR](#) 1

#### Functions

- [int32 OS\\_FileSysAddFixedMap](#) ([osal\\_id\\_t](#) \*filesys\_id, const char \*phys\_path, const char \*virt\_path)  
*Create a fixed mapping between an existing directory and a virtual OSAL mount point.*
- [int32 OS\\_mkfs](#) (char \*address, const char \*devname, const char \*volname, size\_t blocksize, [osal\\_blockcount\\_t](#) numblocks)  
*Makes a file system on the target.*
- [int32 OS\\_mount](#) (const char \*devname, const char \*mountpoint)  
*Mounts a file system.*

- [int32 OS\\_initfs](#) (char \*address, const char \*devname, const char \*volname, size\_t blocksize, [osal\\_blockcount\\_t](#) numblocks)  
*Initializes an existing file system.*
- [int32 OS\\_rmfs](#) (const char \*devname)  
*Removes a file system.*
- [int32 OS\\_unmount](#) (const char \*mountpoint)  
*Unmounts a mounted file system.*
- [int32 OS\\_FileSysStatVolume](#) (const char \*name, [OS\\_statvfs\\_t](#) \*statbuf)  
*Obtains information about size and free space in a volume.*
- [int32 OS\\_chkfs](#) (const char \*name, bool repair)  
*Checks the health of a file system and repairs it if necessary.*
- [int32 OS\\_FS\\_GetPhysDriveName](#) (char \*PhysDriveName, const char \*MountPoint)  
*Obtains the physical drive name associated with a mount point.*
- [int32 OS\\_TranslatePath](#) (const char \*VirtualPath, char \*LocalPath)  
*Translates a OSAL Virtual file system path to a host Local path.*
- [int32 OS\\_GetFsInfo](#) ([os\\_fsinfo\\_t](#) \*filesys\_info)  
*Returns information about the file system.*

### 13.16.1 Macro Definition Documentation

#### 13.16.1.1 OS\_CHK\_ONLY

```
#define OS_CHK_ONLY 0
```

Unused, API takes bool

Definition at line 31 of file osapi-filesys.h.

#### 13.16.1.2 OS\_REPAIR

```
#define OS_REPAIR 1
```

Unused, API takes bool

Definition at line 32 of file osapi-filesys.h.

### 13.17 osal/src/os/inc/osapi-heap.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

## Data Structures

- struct [OS\\_heap\\_prop\\_t](#)  
*OSAL heap properties.*

## Functions

- [int32 OS\\_HeapGetInfo](#) ([OS\\_heap\\_prop\\_t](#) \*heap\_prop)  
*Return current info on the heap.*

## 13.18 osal/src/os/inc/osapi-idmap.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

## Macros

- [#define OS\\_OBJECT\\_INDEX\\_MASK](#) 0xFFFF  
*Object index mask.*
- [#define OS\\_OBJECT\\_TYPE\\_SHIFT](#) 16  
*Object type shift.*
- [#define OS\\_OBJECT\\_TYPE\\_UNDEFINED](#) 0x00  
*Object type undefined.*
- [#define OS\\_OBJECT\\_TYPE\\_OS\\_TASK](#) 0x01  
*Object task type.*
- [#define OS\\_OBJECT\\_TYPE\\_OS\\_QUEUE](#) 0x02  
*Object queue type.*
- [#define OS\\_OBJECT\\_TYPE\\_OS\\_COUNTSEM](#) 0x03  
*Object counting semaphore type.*
- [#define OS\\_OBJECT\\_TYPE\\_OS\\_BINSEM](#) 0x04  
*Object binary semaphore type.*
- [#define OS\\_OBJECT\\_TYPE\\_OS\\_MUTEX](#) 0x05  
*Object mutex type.*
- [#define OS\\_OBJECT\\_TYPE\\_OS\\_STREAM](#) 0x06  
*Object stream type.*
- [#define OS\\_OBJECT\\_TYPE\\_OS\\_DIR](#) 0x07  
*Object directory type.*
- [#define OS\\_OBJECT\\_TYPE\\_OS\\_TIMEBASE](#) 0x08  
*Object timebase type.*
- [#define OS\\_OBJECT\\_TYPE\\_OS\\_TIMECB](#) 0x09  
*Object timer callback type.*
- [#define OS\\_OBJECT\\_TYPE\\_OS\\_MODULE](#) 0x0A  
*Object module type.*
- [#define OS\\_OBJECT\\_TYPE\\_OS\\_FILESYS](#) 0x0B  
*Object file system type.*
- [#define OS\\_OBJECT\\_TYPE\\_OS\\_CONSOLE](#) 0x0C  
*Object console type.*
- [#define OS\\_OBJECT\\_TYPE\\_USER](#) 0x10  
*Object user type.*



## Functions

- static unsigned long [OS\\_ObjectIdToInteger](#) ([osal\\_id\\_t](#) object\_id)  
*Obtain an integer value corresponding to an object ID.*
- static [osal\\_id\\_t](#) [OS\\_ObjectIdFromInteger](#) (unsigned long value)  
*Obtain an osal ID corresponding to an integer value.*
- static bool [OS\\_ObjectIdEqual](#) ([osal\\_id\\_t](#) object\_id1, [osal\\_id\\_t](#) object\_id2)  
*Check two OSAL object ID values for equality.*
- static bool [OS\\_ObjectIdDefined](#) ([osal\\_id\\_t](#) object\_id)  
*Check if an object ID is defined.*
- [int32](#) [OS\\_GetResourceName](#) ([osal\\_id\\_t](#) object\_id, char \*buffer, [size\\_t](#) buffer\_size)  
*Obtain the name of an object given an arbitrary object ID.*
- [osal\\_objtype\\_t](#) [OS\\_IdentifyObject](#) ([osal\\_id\\_t](#) object\_id)  
*Obtain the type of an object given an arbitrary object ID.*
- [int32](#) [OS\\_ConvertToArrayIndex](#) ([osal\\_id\\_t](#) object\_id, [osal\\_index\\_t](#) \*ArrayIndex)  
*Converts an abstract ID into a number suitable for use as an array index.*
- [int32](#) [OS\\_ObjectIdToArrayIndex](#) ([osal\\_objtype\\_t](#) idtype, [osal\\_id\\_t](#) object\_id, [osal\\_index\\_t](#) \*ArrayIndex)  
*Converts an abstract ID into a number suitable for use as an array index.*
- void [OS\\_ForEachObject](#) ([osal\\_id\\_t](#) creator\_id, [OS\\_ArgCallback\\_t](#) callback\_ptr, void \*callback\_arg)  
*call the supplied callback function for all valid object IDs*
- void [OS\\_ForEachObjectOfType](#) ([osal\\_objtype\\_t](#) objtype, [osal\\_id\\_t](#) creator\_id, [OS\\_ArgCallback\\_t](#) callback\_ptr, void \*callback\_arg)  
*call the supplied callback function for valid object IDs of a specific type*

## 13.18.1 Macro Definition Documentation

## 13.18.1.1 OS\_OBJECT\_INDEX\_MASK

```
#define OS_OBJECT_INDEX_MASK 0xFFFF
```

Object index mask.

Definition at line 32 of file osapi-idmap.h.

## 13.18.1.2 OS\_OBJECT\_TYPE\_SHIFT

```
#define OS_OBJECT_TYPE_SHIFT 16
```

Object type shift.

Definition at line 33 of file osapi-idmap.h.

### 13.19 osal/src/os/inc/osapi-macros.h File Reference

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include "osconfig.h"
#include "common_types.h"
#include "osapi-printf.h"
```

#### Macros

- `#define BUGREPORT(...) OS_printf(__VA_ARGS__)`
- `#define BUGCHECK(cond, errcode)`  
*Basic Bug-Checking macro.*
- `#define ARGCHECK(cond, errcode)`  
*Generic argument checking macro for non-critical values.*
- `#define LENGTHCHECK(str, len, errcode) ARGCHECK(memchr(str, '\0', len), errcode)`  
*String length limit check macro.*

#### 13.19.1 Macro Definition Documentation

##### 13.19.1.1 ARGCHECK

```
#define ARGCHECK(
    cond,
    errcode )
```

#### Value:

```
if (! (cond) ) \
{ \
    return errcode; \
}
```

Generic argument checking macro for non-critical values.

This macro checks a conditional that is expected to be true, and return a value if it evaluates false.

ARGCHECK can be used to check for out of range or other invalid argument conditions which may (validly) occur at runtime and do not necessarily indicate bugs in the application.

These argument checks are NOT considered a fatal errors. The application continues to run normally. This does not report the error on the console.

As such, ARGCHECK actions are always compiled in - not selectable at compile-time.

#### See also

[BUGCHECK](#) for checking critical values that indicate bugs

Definition at line 122 of file osapi-macros.h.

### 13.19.1.2 BUGCHECK

```
#define BUGCHECK(
    cond,
    errcode )
```

#### Value:

```
if (! (cond))
{
    \
    \BUGREPORT("\n**BUG** %s():%d:check \'%s\' FAILED --> %s\n", __func__, __LINE__, #cond, #errcode);
    \
    \return errcode;
    \
}
```

Basic Bug-Checking macro.

This macro checks a conditional, and if it is FALSE, then it generates a report - which may in turn contain additional actions.

BUGCHECK should only be used for conditions which are critical and must always be true. If such a condition is ever false then it indicates a bug in the application which must be resolved. It may or may not be possible to continue operation if a bugcheck fails.

#### See also

[ARGCHECK](#) for checking non-critical values

Definition at line 96 of file osapi-macros.h.

### 13.19.1.3 BUGREPORT

```
#define BUGREPORT(
    ... ) OS_printf(__VA_ARGS__)
```

Definition at line 79 of file osapi-macros.h.

### 13.19.1.4 LENGTHCHECK

```
#define LENGTHCHECK(
    str,
    len,
    errcode ) ARGCHECK(memchr(str, '\0', len), errcode)
```

String length limit check macro.

This macro is a specialized version of ARGCHECK that confirms a string will fit into a buffer of the specified length, and return an error code if it will not.

#### Note

this uses ARGCHECK, thus treating a string too long as a normal runtime (i.e. non-bug) error condition with a typical error return to the caller.

Definition at line 137 of file osapi-macros.h.

## 13.20 osal/src/os/inc/osapi-module.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

### Data Structures

- struct [OS\\_module\\_address\\_t](#)  
*OSAL module address properties.*
- struct [OS\\_module\\_prop\\_t](#)  
*OSAL module properties.*
- struct [OS\\_static\\_symbol\\_record\\_t](#)  
*Associates a single symbol name with a memory address.*

### Macros

- #define [OS\\_MODULE\\_FLAG\\_GLOBAL\\_SYMBOLS](#) 0x00  
*Requests [OS\\_ModuleLoad\(\)](#) to add the symbols to the global symbol table.*
- #define [OS\\_MODULE\\_FLAG\\_LOCAL\\_SYMBOLS](#) 0x01  
*Requests [OS\\_ModuleLoad\(\)](#) to keep the symbols local/private to this module.*

### Functions

- [int32 OS\\_SymbolLookup](#) ([cpuaddr](#) \*symbol\_address, const char \*symbol\_name)  
*Find the Address of a Symbol.*
- [int32 OS\\_ModuleSymbolLookup](#) ([osal\\_id\\_t](#) module\_id, [cpuaddr](#) \*symbol\_address, const char \*symbol\_name)  
*Find the Address of a Symbol within a module.*
- [int32 OS\\_SymbolTableDump](#) (const char \*filename, [size\\_t](#) size\_limit)  
*Dumps the system symbol table to a file.*
- [int32 OS\\_ModuleLoad](#) ([osal\\_id\\_t](#) \*module\_id, const char \*module\_name, const char \*filename, [uint32](#) flags)  
*Loads an object file.*
- [int32 OS\\_ModuleUnload](#) ([osal\\_id\\_t](#) module\_id)  
*Unloads the module file.*
- [int32 OS\\_ModuleInfo](#) ([osal\\_id\\_t](#) module\_id, [OS\\_module\\_prop\\_t](#) \*module\_info)  
*Obtain information about a module.*

#### 13.20.1 Macro Definition Documentation

### 13.20.1.1 OS\_MODULE\_FLAG\_GLOBAL\_SYMBOLS

```
#define OS_MODULE_FLAG_GLOBAL_SYMBOLS 0x00
```

Requests [OS\\_ModuleLoad\(\)](#) to add the symbols to the global symbol table.

When supplied as the "flags" argument to [OS\\_ModuleLoad\(\)](#), this indicates that the symbols in the loaded module should be added to the global symbol table. This will make symbols in this library available for use when resolving symbols in future module loads.

This is the default mode of operation for [OS\\_ModuleLoad\(\)](#).

#### Note

On some operating systems, use of this option may make it difficult to unload the module in the future, if the symbols are in use by other entities.

Definition at line 49 of file osapi-module.h.

### 13.20.1.2 OS\_MODULE\_FLAG\_LOCAL\_SYMBOLS

```
#define OS_MODULE_FLAG_LOCAL_SYMBOLS 0x01
```

Requests [OS\\_ModuleLoad\(\)](#) to keep the symbols local/private to this module.

When supplied as the "flags" argument to [OS\\_ModuleLoad\(\)](#), this indicates that the symbols in the loaded module should NOT be added to the global symbol table. This means the symbols in the loaded library will not be available for use by other modules.

Use of this option is recommended for cases where no other entities will need to reference symbols within this module. This helps ensure that the module can be more safely unloaded in the future, by preventing other modules from binding to it. It also helps reduce the likelihood of symbol name conflicts among modules.

#### Note

To look up symbols within a module loaded with this flag, use [OS\\_SymbolLookupInModule\(\)](#) instead of [OS\\_SymbolLookup\(\)](#). Also note that references obtained using this method are not tracked by the OS; the application must ensure that all references obtained in this manner have been cleaned up/released before unloading the module.

Definition at line 71 of file osapi-module.h.

## 13.21 osal/src/os/inc/osapi-mutex.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

## Data Structures

- struct [OS\\_mut\\_sem\\_prop\\_t](#)  
*OSAL mutex properties.*

## Functions

- [int32 OS\\_MutSemCreate](#) ([osal\\_id\\_t](#) \*sem\_id, const char \*sem\_name, [uint32](#) options)  
*Creates a mutex semaphore.*
- [int32 OS\\_MutSemGive](#) ([osal\\_id\\_t](#) sem\_id)  
*Releases the mutex object referenced by sem\_id.*
- [int32 OS\\_MutSemTake](#) ([osal\\_id\\_t](#) sem\_id)  
*Acquire the mutex object referenced by sem\_id.*
- [int32 OS\\_MutSemDelete](#) ([osal\\_id\\_t](#) sem\_id)  
*Deletes the specified Mutex Semaphore.*
- [int32 OS\\_MutSemGetIdByName](#) ([osal\\_id\\_t](#) \*sem\_id, const char \*sem\_name)  
*Find an existing mutex ID by name.*
- [int32 OS\\_MutSemGetInfo](#) ([osal\\_id\\_t](#) sem\_id, [OS\\_mut\\_sem\\_prop\\_t](#) \*mut\_prop)  
*Fill a property object buffer with details regarding the resource.*

## 13.22 osal/src/os/inc/osapi-network.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

## Functions

- [int32 OS\\_NetworkGetID](#) (void)  
*Gets the network ID of the local machine.*
- [int32 OS\\_NetworkGetHostName](#) (char \*host\_name, [size\\_t](#) name\_len)  
*Gets the local machine network host name.*

## 13.23 osal/src/os/inc/osapi-printf.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

## Functions

- void [OS\\_printf](#) (const char \*string,...) [OS\\_PRINTF](#)(1)  
*Abstraction for the system printf() call.*
- void [OS\\_printf\\_disable](#) (void)  
*This function disables the output from OS\_printf.*
- void [OS\\_printf\\_enable](#) (void)  
*This function enables the output from OS\_printf.*

## 13.24 osal/src/os/inc/osapi-queue.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

### Data Structures

- struct [OS\\_queue\\_prop\\_t](#)  
*OSAL queue properties.*

### Functions

- [int32 OS\\_QueueCreate](#) ([osal\\_id\\_t](#) \*queue\_id, const char \*queue\_name, [osal\\_blockcount\\_t](#) queue\_depth, [size\\_t](#) data\_size, [uint32](#) flags)  
*Create a message queue.*
- [int32 OS\\_QueueDelete](#) ([osal\\_id\\_t](#) queue\_id)  
*Deletes the specified message queue.*
- [int32 OS\\_QueueGet](#) ([osal\\_id\\_t](#) queue\_id, void \*data, [size\\_t](#) size, [size\\_t](#) \*size\_copied, [int32](#) timeout)  
*Receive a message on a message queue.*
- [int32 OS\\_QueuePut](#) ([osal\\_id\\_t](#) queue\_id, const void \*data, [size\\_t](#) size, [uint32](#) flags)  
*Put a message on a message queue.*
- [int32 OS\\_QueueGetIdByName](#) ([osal\\_id\\_t](#) \*queue\_id, const char \*queue\_name)  
*Find an existing queue ID by name.*
- [int32 OS\\_QueueGetInfo](#) ([osal\\_id\\_t](#) queue\_id, [OS\\_queue\\_prop\\_t](#) \*queue\_prop)  
*Fill a property object buffer with details regarding the resource.*

## 13.25 osal/src/os/inc/osapi-select.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

### Data Structures

- struct [OS\\_FdSet](#)  
*An abstract structure capable of holding several OSAL IDs.*

### Enumerations

- enum [OS\\_StreamState\\_t](#) { [OS\\_STREAM\\_STATE\\_BOUND](#) = 0x01, [OS\\_STREAM\\_STATE\\_CONNECTED](#) = 0x02, [OS\\_STREAM\\_STATE\\_READABLE](#) = 0x04, [OS\\_STREAM\\_STATE\\_WRITABLE](#) = 0x08 }  
*For the [OS\\_SelectSingle\(\)](#) function's in/out StateFlags parameter, the state(s) of the stream and the result of the select is a combination of one or more of these states.*

## Functions

- [int32 OS\\_SelectMultiple](#) ([OS\\_FdSet](#) \*ReadSet, [OS\\_FdSet](#) \*WriteSet, [int32](#) msec)
 

*Wait for events across multiple file handles.*
- [int32 OS\\_SelectSingle](#) ([osal\\_id\\_t](#) objid, [uint32](#) \*StateFlags, [int32](#) msec)
 

*Wait for events on a single file handle.*
- [int32 OS\\_SelectFdZero](#) ([OS\\_FdSet](#) \*Set)
 

*Clear a FdSet structure.*
- [int32 OS\\_SelectFdAdd](#) ([OS\\_FdSet](#) \*Set, [osal\\_id\\_t](#) objid)
 

*Add an ID to an FdSet structure.*
- [int32 OS\\_SelectFdClear](#) ([OS\\_FdSet](#) \*Set, [osal\\_id\\_t](#) objid)
 

*Clear an ID from an FdSet structure.*
- [bool OS\\_SelectFdsSet](#) ([OS\\_FdSet](#) \*Set, [osal\\_id\\_t](#) objid)
 

*Check if an FdSet structure contains a given ID.*

## 13.25.1 Enumeration Type Documentation

### 13.25.1.1 OS\_StreamState\_t

```
enum OS\_StreamState\_t
```

For the [OS\\_SelectSingle\(\)](#) function's in/out StateFlags parameter, the state(s) of the stream and the result of the select is a combination of one or more of these states.

See also

[OS\\_SelectSingle\(\)](#)

## Enumerator

<a href="#">OS_STREAM_STATE_BOUND</a>	whether the stream is bound
<a href="#">OS_STREAM_STATE_CONNECTED</a>	whether the stream is connected
<a href="#">OS_STREAM_STATE_READABLE</a>	whether the stream is readable
<a href="#">OS_STREAM_STATE_WRITABLE</a>	whether the stream is writable

Definition at line 51 of file [osapi-select.h](#).

## 13.26 [osal/src/os/inc/osapi-shell.h](#) File Reference

```
#include "osconfig.h"
#include "common_types.h"
```



## Functions

- [int32 OS\\_ShellOutputToFile](#) (const char \*Cmd, [osal\\_id\\_t](#) filedes)  
*Executes the command and sends output to a file.*

## 13.27 osal/src/os/inc/osapi-sockets.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

## Data Structures

- union [OS\\_SockAddrData\\_t](#)  
*Storage buffer for generic network address.*
- struct [OS\\_SockAddr\\_t](#)  
*Encapsulates a generic network address.*
- struct [OS\\_socket\\_prop\\_t](#)  
*Encapsulates socket properties.*

## Macros

- [#define OS\\_SOCKADDR\\_MAX\\_LEN](#) 28

## Enumerations

- enum [OS\\_SocketDomain\\_t](#) { [OS\\_SocketDomain\\_INVALID](#), [OS\\_SocketDomain\\_INET](#), [OS\\_SocketDomain\\_INET6](#), [OS\\_SocketDomain\\_MAX](#) }  
*Socket domain.*
- enum [OS\\_SocketType\\_t](#) { [OS\\_SocketType\\_INVALID](#), [OS\\_SocketType\\_DATAGRAM](#), [OS\\_SocketType\\_STREAM](#), [OS\\_SocketType\\_MAX](#) }  
*Socket type.*

## Functions

- [int32 OS\\_SocketAddrInit](#) ([OS\\_SockAddr\\_t](#) \*Addr, [OS\\_SocketDomain\\_t](#) Domain)  
*Initialize a socket address structure to hold an address of the given family.*
- [int32 OS\\_SocketAddrToString](#) (char \*buffer, size\_t buflen, const [OS\\_SockAddr\\_t](#) \*Addr)  
*Get a string representation of a network host address.*
- [int32 OS\\_SocketAddrFromString](#) ([OS\\_SockAddr\\_t](#) \*Addr, const char \*string)  
*Set a network host address from a string representation.*
- [int32 OS\\_SocketAddrGetPort](#) (uint16 \*PortNum, const [OS\\_SockAddr\\_t](#) \*Addr)  
*Get the port number of a network address.*
- [int32 OS\\_SocketAddrSetPort](#) ([OS\\_SockAddr\\_t](#) \*Addr, uint16 PortNum)

*Set the port number of a network address.*

- `int32 OS_SocketOpen (osal_id_t *sock_id, OS_SocketDomain_t Domain, OS_SocketType_t Type)`

*Opens a socket.*

- `int32 OS_SocketBind (osal_id_t sock_id, const OS_SockAddr_t *Addr)`

*Binds a socket to a given local address.*

- `int32 OS_SocketConnect (osal_id_t sock_id, const OS_SockAddr_t *Addr, int32 timeout)`

*Connects a socket to a given remote address.*

- `int32 OS_SocketAccept (osal_id_t sock_id, osal_id_t *connsock_id, OS_SockAddr_t *Addr, int32 timeout)`

*Waits for and accept the next incoming connection on the given socket.*

- `int32 OS_SocketRecvFrom (osal_id_t sock_id, void *buffer, size_t buflen, OS_SockAddr_t *RemoteAddr, int32 timeout)`

*Reads data from a message-oriented (datagram) socket.*

- `int32 OS_SocketSendTo (osal_id_t sock_id, const void *buffer, size_t buflen, const OS_SockAddr_t *RemoteAddr)`

*Sends data to a message-oriented (datagram) socket.*

- `int32 OS_SocketGetIdByName (osal_id_t *sock_id, const char *sock_name)`

*Gets an OSAL ID from a given name.*

- `int32 OS_SocketGetInfo (osal_id_t sock_id, OS_socket_prop_t *sock_prop)`

*Gets information about an OSAL Socket ID.*

- `int32 OS_NetworkGetID (void)`

*Gets the network ID of the local machine.*

- `int32 OS_NetworkGetHostName (char *host_name, size_t name_len)`

*Gets the local machine network host name.*

## 13.27.1 Macro Definition Documentation

### 13.27.1.1 OS\_SOCKADDR\_MAX\_LEN

```
#define OS_SOCKADDR_MAX_LEN 28
```

Definition at line 45 of file osapi-sockets.h.

## 13.27.2 Enumeration Type Documentation

### 13.27.2.1 OS\_SocketDomain\_t

```
enum OS_SocketDomain_t
```

Socket domain.

**Enumerator**

OS_SocketDomain_INVALID	Invalid.
OS_SocketDomain_INET	IPv4 address family, most commonly used)
OS_SocketDomain_INET6	IPv6 address family, depends on OS/network stack support.
OS_SocketDomain_MAX	Maximum.

Definition at line 60 of file osapi-sockets.h.

**13.27.2.2 OS\_SocketType\_t**

```
enum OS_SocketType_t
```

Socket type.

**Enumerator**

OS_SocketType_INVALID	Invalid.
OS_SocketType_DATAGRAM	A connectionless, message-oriented socket.
OS_SocketType_STREAM	A stream-oriented socket with the concept of a connection.
OS_SocketType_MAX	Maximum.

Definition at line 69 of file osapi-sockets.h.

**13.28 osal/src/os/inc/osapi-task.h File Reference**

```
#include "osconfig.h"
#include "common_types.h"
```

**Data Structures**

- struct [OS\\_task\\_prop\\_t](#)  
*OSAL task properties.*

**Macros**

- #define [OS\\_MAX\\_TASK\\_PRIORITY](#) 255  
*Upper limit for OSAL task priorities.*
- #define [OS\\_FP\\_ENABLED](#) 1  
*Floating point enabled state for a task.*
- #define [OSAL\\_PRIORITY\\_C\(X\)](#) (([osal\\_priority\\_t](#)) {X})
- #define [OSAL\\_STACKPTR\\_C\(X\)](#) (([osal\\_stackptr\\_t](#)) {X})
- #define [OSAL\\_TASK\\_STACK\\_ALLOCATE](#) [OSAL\\_STACKPTR\\_C\(NULL\)](#)

## Typedefs

- typedef uint8\_t [osal\\_priority\\_t](#)  
*Type to be used for OSAL task priorities.*
- typedef void \* [osal\\_stackptr\\_t](#)  
*Type to be used for OSAL stack pointer.*
- typedef void [osal\\_task](#)  
*For task entry point.*

## Functions

- typedef [osal\\_task](#) ((\*osal\_task\_entry)(void))  
*For task entry point.*
- [int32 OS\\_TaskCreate](#) ([osal\\_id\\_t](#) \*task\_id, const char \*task\_name, [osal\\_task\\_entry](#) function\_pointer, [osal\\_stackptr\\_t](#) stack\_pointer, size\_t stack\_size, [osal\\_priority\\_t](#) priority, [uint32](#) flags)  
*Creates a task and starts running it.*
- [int32 OS\\_TaskDelete](#) ([osal\\_id\\_t](#) task\_id)  
*Deletes the specified Task.*
- void [OS\\_TaskExit](#) (void)  
*Exits the calling task.*
- [int32 OS\\_TaskInstallDeleteHandler](#) ([osal\\_task\\_entry](#) function\_pointer)  
*Installs a handler for when the task is deleted.*
- [int32 OS\\_TaskDelay](#) ([uint32](#) millisecond)  
*Delay a task for specified amount of milliseconds.*
- [int32 OS\\_TaskSetPriority](#) ([osal\\_id\\_t](#) task\_id, [osal\\_priority\\_t](#) new\_priority)  
*Sets the given task to a new priority.*
- [int32 OS\\_TaskRegister](#) (void)  
*Obsolete.*
- [osal\\_id\\_t OS\\_TaskGetId](#) (void)  
*Obtain the task id of the calling task.*
- [int32 OS\\_TaskGetIdByName](#) ([osal\\_id\\_t](#) \*task\_id, const char \*task\_name)  
*Find an existing task ID by name.*
- [int32 OS\\_TaskGetInfo](#) ([osal\\_id\\_t](#) task\_id, [OS\\_task\\_prop\\_t](#) \*task\_prop)  
*Fill a property object buffer with details regarding the resource.*
- [int32 OS\\_TaskFindIdBySystemData](#) ([osal\\_id\\_t](#) \*task\_id, const void \*sysdata, size\_t sysdata\_size)  
*Reverse-lookup the OSAL task ID from an operating system ID.*

## 13.28.1 Macro Definition Documentation

### 13.28.1.1 OS\_FP\_ENABLED

```
#define OS_FP_ENABLED 1
```

Floating point enabled state for a task.

Definition at line 35 of file `osapi-task.h`.

### 13.28.1.2 OS\_MAX\_TASK\_PRIORITY

```
#define OS_MAX_TASK_PRIORITY 255
```

Upper limit for OSAL task priorities.

Definition at line 32 of file osapi-task.h.

### 13.28.1.3 OSAL\_PRIORITY\_C

```
#define OSAL_PRIORITY_C(  
    X ) ((osal_priority_t) {X})
```

Definition at line 46 of file osapi-task.h.

### 13.28.1.4 OSAL\_STACKPTR\_C

```
#define OSAL_STACKPTR_C(  
    X ) ((osal_stackptr_t) {X})
```

Definition at line 53 of file osapi-task.h.

### 13.28.1.5 OSAL\_TASK\_STACK\_ALLOCATE

```
#define OSAL_TASK_STACK_ALLOCATE OSAL_STACKPTR_C(NULL)
```

Definition at line 54 of file osapi-task.h.

## 13.28.2 Typedef Documentation

### 13.28.2.1 osal\_priority\_t

```
typedef uint8_t osal_priority_t
```

Type to be used for OSAL task priorities.

OSAL priorities are in reverse order, and range from 0 (highest; will preempt all other tasks) to 255 (lowest; will not preempt any other task).

Definition at line 44 of file osapi-task.h.

### 13.28.2.2 `osal_stackptr_t`

```
typedef void* osal_stackptr_t
```

Type to be used for OSAL stack pointer.

Definition at line 51 of file `osapi-task.h`.

### 13.28.2.3 `osal_task`

```
typedef void osal_task
```

For task entry point.

Definition at line 68 of file `osapi-task.h`.

## 13.28.3 Function Documentation

### 13.28.3.1 `osal_task()`

```
typedef osal_task (  
    (*) (void) osal_task_entry )
```

For task entry point.

## 13.29 `osal/src/os/inc/osapi-timebase.h` File Reference

```
#include "osconfig.h"  
#include "common_types.h"
```

### Data Structures

- struct `OS_timebase_prop_t`  
*Time base properties.*

### Typedefs

- typedef `uint32`(\* `OS_TimerSync_t`) (`osal_id_t` timer\_id)  
*Timer sync.*

## Functions

- [int32 OS\\_TimeBaseCreate](#) ([osal\\_id\\_t](#) \*timebase\_id, const char \*timebase\_name, [OS\\_TimerSync\\_t](#) external\_↵ sync)  
*Create an abstract Time Base resource.*
- [int32 OS\\_TimeBaseSet](#) ([osal\\_id\\_t](#) timebase\_id, [uint32](#) start\_time, [uint32](#) interval\_time)  
*Sets the tick period for simulated time base objects.*
- [int32 OS\\_TimeBaseDelete](#) ([osal\\_id\\_t](#) timebase\_id)  
*Deletes a time base object.*
- [int32 OS\\_TimeBaseGetIdByName](#) ([osal\\_id\\_t](#) \*timebase\_id, const char \*timebase\_name)  
*Find the ID of an existing time base resource.*
- [int32 OS\\_TimeBaseGetInfo](#) ([osal\\_id\\_t](#) timebase\_id, [OS\\_timebase\\_prop\\_t](#) \*timebase\_prop)  
*Obtain information about a timebase resource.*
- [int32 OS\\_TimeBaseGetFreeRun](#) ([osal\\_id\\_t](#) timebase\_id, [uint32](#) \*freerun\_val)  
*Read the value of the timebase free run counter.*

## 13.29.1 Typedef Documentation

### 13.29.1.1 OS\_TimerSync\_t

```
typedef uint32(* OS_TimerSync_t) (osal\_id\_t timer_id)
```

Timer sync.

Definition at line 34 of file osapi-timebase.h.

## 13.30 osal/src/os/inc/osapi-timer.h File Reference

```
#include "osconfig.h"
#include "common_types.h"
```

## Data Structures

- struct [OS\\_timer\\_prop\\_t](#)  
*Timer properties.*

## Typedefs

- typedef void(\* [OS\\_TimerCallback\\_t](#)) ([osal\\_id\\_t](#) timer\_id)  
*Timer callback.*

## Functions

- `int32 OS_TimerCreate (osal_id_t *timer_id, const char *timer_name, uint32 *clock_accuracy, OS_Timer↔ Callback_t callback_ptr)`  
*Create a timer object.*
- `int32 OS_TimerAdd (osal_id_t *timer_id, const char *timer_name, osal_id_t timebase_id, OS_ArgCallback_↔ t callback_ptr, void *callback_arg)`  
*Add a timer object based on an existing TimeBase resource.*
- `int32 OS_TimerSet (osal_id_t timer_id, uint32 start_time, uint32 interval_time)`  
*Configures a periodic or one shot timer.*
- `int32 OS_TimerDelete (osal_id_t timer_id)`  
*Deletes a timer resource.*
- `int32 OS_TimerGetIdByName (osal_id_t *timer_id, const char *timer_name)`  
*Locate an existing timer resource by name.*
- `int32 OS_TimerGetInfo (osal_id_t timer_id, OS_timer_prop_t *timer_prop)`  
*Gets information about an existing timer.*

### 13.30.1 Typedef Documentation

#### 13.30.1.1 OS\_TimerCallback\_t

```
typedef void(* OS_TimerCallback_t) (osal_id_t timer_id)
```

Timer callback.

Definition at line 34 of file osapi-timer.h.

### 13.31 osal/src/os/inc/osapi-version.h File Reference

Purpose:

## Macros

- `#define OS_BUILD_NUMBER 280`
- `#define OS_BUILD_BASELINE "v5.1.0-rc1"`
- `#define OS_MAJOR_VERSION 5`  
*ONLY APPLY for OFFICIAL releases. Major version number.*
- `#define OS_MINOR_VERSION 0`  
*ONLY APPLY for OFFICIAL releases. Minor version number.*
- `#define OS_REVISION 99`  
*ONLY APPLY for OFFICIAL releases. Revision version number. A value of "99" indicates an unreleased \ development version.*
- `#define OS_MISSION_REV 0`  
*ONLY USED by MISSION Implementations. Mission revision.*



- `#define OS_STR_HELPER(x) #x`  
*Helper function to concatenate strings from integer.*
- `#define OS_STR(x) OS_STR_HELPER(x)`  
*Helper function to concatenate strings from integer.*
- `#define OS_VERSION OS_BUILD_BASELINE "+dev" OS_STR(OS_BUILD_NUMBER)`  
*Development Build Version Number.*
- `#define OS_VERSION_STRING`  
*Development Build Version String.*
- `#define OSAL_API_VERSION ((OS_MAJOR_VERSION * 10000) + (OS_MINOR_VERSION * 100) + OS_REVISION)`  
*Combines the revision components into a single value.*

### 13.31.1 Detailed Description

Purpose:

Provide version identifiers for cFS' Operating System Abstraction Layer See [Version Numbers](#) for version and build number and description

### 13.31.2 Macro Definition Documentation

#### 13.31.2.1 OS\_BUILD\_BASELINE

```
#define OS_BUILD_BASELINE "v5.1.0-rc1"
```

Definition at line 34 of file osapi-version.h.

#### 13.31.2.2 OS\_BUILD\_NUMBER

```
#define OS_BUILD_NUMBER 280
```

Definition at line 33 of file osapi-version.h.

#### 13.31.2.3 OS\_MAJOR\_VERSION

```
#define OS_MAJOR_VERSION 5
```

ONLY APPLY for OFFICIAL releases. Major version number.

Definition at line 39 of file osapi-version.h.

#### 13.31.2.4 OS\_MINOR\_VERSION

```
#define OS_MINOR_VERSION 0
```

ONLY APPLY for OFFICIAL releases. Minor version number.

Definition at line 40 of file osapi-version.h.

#### 13.31.2.5 OS\_MISSION\_REV

```
#define OS_MISSION_REV 0
```

ONLY USED by MISSION Implementations. Mission revision.

Definition at line 46 of file osapi-version.h.

#### 13.31.2.6 OS\_REVISION

```
#define OS_REVISION 99
```

ONLY APPLY for OFFICIAL releases. Revision version number. A value of "99" indicates an unreleased \ development version.

Definition at line 41 of file osapi-version.h.

#### 13.31.2.7 OS\_STR

```
#define OS_STR(  
    x ) OS_STR_HELPER(x)
```

Helper function to concatenate strings from integer.

Definition at line 52 of file osapi-version.h.

#### 13.31.2.8 OS\_STR\_HELPER

```
#define OS_STR_HELPER(  
    x ) #x
```

Helper function to concatenate strings from integer.

Definition at line 51 of file osapi-version.h.

### 13.31.2.9 OS\_VERSION

```
#define OS_VERSION OS_BUILD_BASELINE "+dev" OS_STR(OS_BUILD_NUMBER)
```

Development Build Version Number.

Baseline git tag + Number of commits since baseline.

See [Version Numbers](#) for format differences between development and release versions.

Definition at line 58 of file osapi-version.h.

### 13.31.2.10 OS\_VERSION\_STRING

```
#define OS_VERSION_STRING
```

#### Value:

```
" OSAL Development Build\n"
" " OS_VERSION " (Codename: Bootes)\n" /* Codename for current development */ \
" Latest Official Version: osal v5.0.0" /* For full support please use official release version */
```

Development Build Version String.

Reports the current development build's baseline, number, and name. Also includes a note about the latest official version.

See [Version Numbers](#) for format differences between development and release versions.

Definition at line 64 of file osapi-version.h.

### 13.31.2.11 OSAL\_API\_VERSION

```
#define OSAL_API_VERSION ((OS_MAJOR_VERSION * 10000) + (OS_MINOR_VERSION * 100) + OS_REVISION)
```

Combines the revision components into a single value.

Applications can check against this number

e.g. `"#if OSAL_API_VERSION >= 40100"` would check if some feature added in OSAL 4.1 is present.

Definition at line 74 of file osapi-version.h.

### 13.32 osal/src/os/inc/osapi.h File Reference

```
#include <stdio.h>
#include <stdlib.h>
#include <stdarg.h>
#include "common_types.h"
#include "osapi-version.h"
#include "osconfig.h"
#include "osapi-binsem.h"
#include "osapi-clock.h"
#include "osapi-common.h"
#include "osapi-constants.h"
#include "osapi-countsem.h"
#include "osapi-dir.h"
#include "osapi-error.h"
#include "osapi-file.h"
#include "osapi-filesys.h"
#include "osapi-heap.h"
#include "osapi-macros.h"
#include "osapi-idmap.h"
#include "osapi-module.h"
#include "osapi-mutex.h"
#include "osapi-network.h"
#include "osapi-printf.h"
#include "osapi-queue.h"
#include "osapi-select.h"
#include "osapi-shell.h"
#include "osapi-sockets.h"
#include "osapi-task.h"
#include "osapi-timebase.h"
#include "osapi-timer.h"
#include "osapi-bsp.h"
```

## Index

- `_EXTENSION_`  
`common_types.h`, 177
- ARGCHECK
  - `osapi-macros.h`, 202
- accuracy
  - `OS_timebase_prop_t`, 164
  - `OS_timer_prop_t`, 166
- ActualLength
  - `OS_SockAddr_t`, 157
- addr
  - `OS_module_prop_t`, 153
- AddrData
  - `OS_SockAddr_t`, 157
- Address
  - `OS_static_symbol_record_t`, 160
- AlignPtr
  - `OS_SockAddrData_t`, 158
- AlignU32
  - `OS_SockAddrData_t`, 158
- BUGCHECK
  - `osapi-macros.h`, 202
- BUGREPORT
  - `osapi-macros.h`, 203
- block\_size
  - `OS_statvfs_t`, 161
- blocks\_free
  - `OS_statvfs_t`, 161
- bss\_address
  - `OS_module_address_t`, 151
- bss\_size
  - `OS_module_address_t`, 152
- Buffer
  - `OS_SockAddrData_t`, 158
- `build/doc/osconfig-example.h`, 167
- `cfe/docs/src/cfs_versions.dox`, 176
- `cfe/docs/src/osal_fs.dox`, 176
- `cfe/docs/src/osal_timer.dox`, 176
- `cfe/docs/src/osalmain.dox`, 176
- code\_address
  - `OS_module_address_t`, 152
- code\_size
  - `OS_module_address_t`, 152
- `common_types.h`
  - `_EXTENSION_`, 177
  - `CompileTimeAssert`, 177, 182, 183
  - `cpuaddr`, 178
  - `cpudiff`, 179
  - `cpusize`, 179
  - `creator`
    - `OS_bin_sem_prop_t`, 143
    - `OS_count_sem_prop_t`, 144
    - `OS_mut_sem_prop_t`, 155
    - `OS_queue_prop_t`, 156
    - `OS_socket_prop_t`, 159
    - `OS_task_prop_t`, 162
    - `OS_timebase_prop_t`, 165
    - `OS_timer_prop_t`, 166
  - `data_address`
    - `OS_module_address_t`, 152
  - `data_size`
    - `OS_module_address_t`, 152
  - `entry_point`
    - `OS_module_prop_t`, 154
  - `FileModeBits`
    - `os_fstat_t`, 149
  - `FileName`
    - `os_dirent_t`, 145
  - `FileSize`
    - `os_fstat_t`, 149
  - `int16`, 179
  - `int32`, 179
  - `int64`, 179
  - `int8`, 179
  - `intptr`, 180
  - `NULL`, 177
  - `OS_ArgCallback_t`, 180
  - `OS_PRINTF`, 177
  - `OS_USED`, 177
  - `OSAL_BLOCKCOUNT_C`, 178
  - `OSAL_INDEX_C`, 178
  - `OSAL_OBJTYPE_C`, 178
  - `OSAL_SIZE_C`, 178
  - `osal_blockcount_t`, 180
  - `osal_id_t`, 180
  - `osal_index_t`, 180
  - `osal_objtype_t`, 181
  - `uint16`, 181
  - `uint32`, 181
  - `uint64`, 181
  - `uint8`, 181

- FileTime
  - os\_fstat\_t, [149](#)
- filename
  - OS\_module\_prop\_t, [154](#)
- flags
  - OS\_module\_address\_t, [152](#)
- free\_blocks
  - OS\_heap\_prop\_t, [150](#)
- free\_bytes
  - OS\_heap\_prop\_t, [150](#)
- FreeFds
  - os\_fsinfo\_t, [148](#)
- FreeVolumes
  - os\_fsinfo\_t, [148](#)
- freerun\_time
  - OS\_timebase\_prop\_t, [165](#)
- host\_module\_id
  - OS\_module\_prop\_t, [154](#)
- int16
  - common\_types.h, [179](#)
- int32
  - common\_types.h, [179](#)
- int64
  - common\_types.h, [179](#)
- int8
  - common\_types.h, [179](#)
- interval\_time
  - OS\_timer\_prop\_t, [166](#)
- intptr
  - common\_types.h, [180](#)
- IsValid
  - OS\_file\_prop\_t, [147](#)
- LENGTHCHECK
  - osapi-macros.h, [203](#)
- largest\_free\_block
  - OS\_heap\_prop\_t, [151](#)
- MaxFds
  - os\_fsinfo\_t, [148](#)
- MaxVolumes
  - os\_fsinfo\_t, [148](#)
- Module
  - OS\_static\_symbol\_record\_t, [160](#)
- NULL
  - common\_types.h, [177](#)
- Name
  - OS\_static\_symbol\_record\_t, [160](#)
- name
  - OS\_bin\_sem\_prop\_t, [143](#)
  - OS\_count\_sem\_prop\_t, [144](#)
  - OS\_module\_prop\_t, [154](#)
  - OS\_mut\_sem\_prop\_t, [155](#)
  - OS\_queue\_prop\_t, [156](#)
  - OS\_socket\_prop\_t, [159](#)
  - OS\_task\_prop\_t, [162](#)
  - OS\_timebase\_prop\_t, [165](#)
  - OS\_timer\_prop\_t, [166](#)
- Network ID APIs, [99](#)
  - OS\_NetworkGetHostName, [99](#)
  - OS\_NetworkGetID, [99](#)
- nominal\_interval\_time
  - OS\_timebase\_prop\_t, [165](#)
- OS\_API\_Init
  - OSAL Core Operation APIs, [31](#)
- OS\_Application\_Run
  - OSAL Core Operation APIs, [32](#)
- OS\_Application\_Startup
  - OSAL Core Operation APIs, [32](#)
- OS\_ApplicationExit
  - OSAL Core Operation APIs, [32](#)
- OS\_ApplicationShutdown
  - OSAL Core Operation APIs, [32](#)
- OS\_ArgCallback\_t
  - common\_types.h, [180](#)
- OS\_BSP\_GetArgC
  - OSAL BSP low level access APIs, [18](#)
- OS\_BSP\_GetArgV
  - OSAL BSP low level access APIs, [18](#)
- OS\_BSP\_SetExitCode
  - OSAL BSP low level access APIs, [18](#)
- OS\_BUFFER\_MSG\_DEPTH
  - osconfig-example.h, [168](#)
- OS\_BUFFER\_SIZE
  - osconfig-example.h, [168](#)
- OS\_BUILD\_BASELINE
  - osapi-version.h, [217](#)
- OS\_BUILD\_NUMBER
  - osapi-version.h, [217](#)
- OS\_BinSemCreate
  - OSAL Binary Semaphore APIs, [12](#)
- OS\_BinSemDelete
  - OSAL Binary Semaphore APIs, [13](#)
- OS\_BinSemFlush
  - OSAL Binary Semaphore APIs, [13](#)
- OS\_BinSemGetIdByName
  - OSAL Binary Semaphore APIs, [14](#)
- OS\_BinSemGetInfo
  - OSAL Binary Semaphore APIs, [15](#)
- OS\_BinSemGive
  - OSAL Binary Semaphore APIs, [15](#)
- OS\_BinSemTake
  - OSAL Binary Semaphore APIs, [16](#)
- OS\_BinSemTimedWait
  - OSAL Binary Semaphore APIs, [16](#)

- OS\_CHECK
  - osapi-constants.h, [189](#)
- OS\_CHK\_ONLY
  - osapi-filesys.h, [199](#)
- OS\_CloseAllFiles
  - OSAL Standard File APIs, [58](#)
- OS\_CloseFileByName
  - OSAL Standard File APIs, [59](#)
- OS\_ConvertToArrayIndex
  - OSAL Object ID Utility APIs, [82](#)
- OS\_CountSemCreate
  - OSAL Counting Semaphore APIs, [35](#)
- OS\_CountSemDelete
  - OSAL Counting Semaphore APIs, [36](#)
- OS\_CountSemGetIdByName
  - OSAL Counting Semaphore APIs, [36](#)
- OS\_CountSemGetInfo
  - OSAL Counting Semaphore APIs, [37](#)
- OS\_CountSemGive
  - OSAL Counting Semaphore APIs, [37](#)
- OS\_CountSemTake
  - OSAL Counting Semaphore APIs, [38](#)
- OS\_CountSemTimedWait
  - OSAL Counting Semaphore APIs, [39](#)
- OS\_DIRENTRY\_NAME
  - osapi-dir.h, [191](#)
- OS\_DeleteAllObjects
  - OSAL Core Operation APIs, [33](#)
- OS\_DirectoryClose
  - OSAL Directory APIs, [40](#)
- OS\_DirectoryOpen
  - OSAL Directory APIs, [40](#)
- OS\_DirectoryRead
  - OSAL Directory APIs, [41](#)
- OS\_DirectoryRewind
  - OSAL Directory APIs, [41](#)
- OS\_ERR\_BAD\_ADDRESS
  - OSAL Return Code Defines, [45](#)
- OS\_ERR\_FILE
  - OSAL Return Code Defines, [46](#)
- OS\_ERR\_INCORRECT\_OBJ\_STATE
  - OSAL Return Code Defines, [46](#)
- OS\_ERR\_INCORRECT\_OBJ\_TYPE
  - OSAL Return Code Defines, [46](#)
- OS\_ERR\_INVALID\_ID
  - OSAL Return Code Defines, [46](#)
- OS\_ERR\_INVALID\_PRIORITY
  - OSAL Return Code Defines, [46](#)
- OS\_ERR\_INVALID\_SIZE
  - OSAL Return Code Defines, [47](#)
- OS\_ERR\_NAME\_NOT\_FOUND
  - OSAL Return Code Defines, [47](#)
- OS\_ERR\_NAME\_TAKEN
  - OSAL Return Code Defines, [47](#)
- OS\_ERR\_NAME\_TOO\_LONG
  - OSAL Return Code Defines, [47](#)
- OS\_ERR\_NO\_FREE\_IDS
  - OSAL Return Code Defines, [47](#)
- OS\_ERR\_NOT\_IMPLEMENTED
  - OSAL Return Code Defines, [48](#)
- OS\_ERR\_OBJECT\_IN\_USE
  - OSAL Return Code Defines, [48](#)
- OS\_ERR\_OPERATION\_NOT\_SUPPORTED
  - OSAL Return Code Defines, [48](#)
- OS\_ERR\_SEM\_NOT\_FULL
  - OSAL Return Code Defines, [48](#)
- OS\_ERR\_STREAM\_DISCONNECTED
  - OSAL Return Code Defines, [48](#)
- OS\_ERROR\_ADDRESS\_MISALIGNED
  - OSAL Return Code Defines, [49](#)
- OS\_ERROR\_NAME\_LENGTH
  - osapi-error.h, [193](#)
- OS\_ERROR\_TIMEOUT
  - OSAL Return Code Defines, [49](#)
- OS\_ERROR
  - OSAL Return Code Defines, [49](#)
- OS\_Event\_t
  - osapi-common.h, [187](#)
- OS\_EventHandler\_t
  - osapi-common.h, [187](#)
- OS\_FDGetInfo
  - OSAL Standard File APIs, [60](#)
- OS\_FILESTAT\_EXEC
  - osapi-file.h, [196](#)
- OS\_FILESTAT\_ISDIR
  - osapi-file.h, [196](#)
- OS\_FILESTAT\_MODE
  - osapi-file.h, [196](#)
- OS\_FILESTAT\_READ
  - osapi-file.h, [196](#)
- OS\_FILESTAT\_SIZE
  - osapi-file.h, [196](#)
- OS\_FILESTAT\_TIME
  - osapi-file.h, [197](#)
- OS\_FILESTAT\_WRITE
  - osapi-file.h, [197](#)
- OS\_FP\_ENABLED
  - osapi-task.h, [212](#)
- OS\_FS\_DEV\_NAME\_LEN
  - osconfig-example.h, [169](#)
- OS\_FS\_ERR\_DEVICE\_NOT\_FREE
  - OSAL Return Code Defines, [49](#)
- OS\_FS\_ERR\_DRIVE\_NOT\_CREATED
  - OSAL Return Code Defines, [49](#)
- OS\_FS\_ERR\_NAME\_TOO\_LONG
  - OSAL Return Code Defines, [50](#)
- OS\_FS\_ERR\_PATH\_INVALID
  - OSAL Return Code Defines, [50](#)

- OS\_FS\_ERR\_PATH\_TOO\_LONG
  - OSAL Return Code Defines, [50](#)
- OS\_FS\_GetPhysDriveName
  - OSAL File System Level APIs, [71](#)
- OS\_FS\_PHYS\_NAME\_LEN
  - osconfig-example.h, [169](#)
- OS\_FS\_VOL\_NAME\_LEN
  - osconfig-example.h, [169](#)
- OS\_FdSet, [145](#)
  - object\_ids, [146](#)
- OS\_FileOpenCheck
  - OSAL Standard File APIs, [60](#)
- OS\_FileSysAddFixedMap
  - OSAL File System Level APIs, [70](#)
- OS\_FileSysStatVolume
  - OSAL File System Level APIs, [71](#)
- OS\_ForEachObject
  - OSAL Object ID Utility APIs, [83](#)
- OS\_ForEachObjectOfType
  - OSAL Object ID Utility APIs, [83](#)
- OS\_GetErrorName
  - OSAL Error Info APIs, [54](#)
- OS\_GetFsInfo
  - OSAL File System Level APIs, [72](#)
- OS\_GetLocalTime
  - OSAL Real Time Clock APIs, [19](#)
- OS\_GetResourceName
  - OSAL Object ID Utility APIs, [84](#)
- OS\_HeapGetInfo
  - OSAL Heap APIs, [77](#)
- OS\_INVALID\_INT\_NUM
  - OSAL Return Code Defines, [50](#)
- OS\_INVALID\_POINTER
  - OSAL Return Code Defines, [50](#)
- OS\_INVALID\_SEM\_VALUE
  - OSAL Return Code Defines, [51](#)
- OS\_IdentifyObject
  - OSAL Object ID Utility APIs, [84](#)
- OS\_IdleLoop
  - OSAL Core Operation APIs, [33](#)
- OS\_MAJOR\_VERSION
  - osapi-version.h, [217](#)
- OS\_MAX\_API\_NAME
  - osconfig-example.h, [169](#)
- OS\_MAX\_BIN\_SEMAPHORES
  - osconfig-example.h, [169](#)
- OS\_MAX\_CMD\_LEN
  - osconfig-example.h, [170](#)
- OS\_MAX\_CONSOLES
  - osconfig-example.h, [170](#)
- OS\_MAX\_COUNT\_SEMAPHORES
  - osconfig-example.h, [170](#)
- OS\_MAX\_FILE\_NAME
  - osconfig-example.h, [170](#)
- OS\_MAX\_FILE\_SYSTEMS
  - osconfig-example.h, [171](#)
- OS\_MAX\_LOCAL\_PATH\_LEN
  - osapi-constants.h, [189](#)
- OS\_MAX\_MODULES
  - osconfig-example.h, [171](#)
- OS\_MAX\_MUTEXES
  - osconfig-example.h, [171](#)
- OS\_MAX\_NUM\_OPEN\_DIRS
  - osconfig-example.h, [171](#)
- OS\_MAX\_NUM\_OPEN\_FILES
  - osconfig-example.h, [172](#)
- OS\_MAX\_PATH\_LEN
  - osconfig-example.h, [172](#)
- OS\_MAX\_QUEUES
  - osconfig-example.h, [172](#)
- OS\_MAX\_SYM\_LEN
  - osconfig-example.h, [172](#)
- OS\_MAX\_TASK\_PRIORITY
  - osapi-task.h, [212](#)
- OS\_MAX\_TASKS
  - osconfig-example.h, [173](#)
- OS\_MAX\_TIMEBASES
  - osconfig-example.h, [173](#)
- OS\_MAX\_TIMERS
  - osconfig-example.h, [173](#)
- OS\_MINOR\_VERSION
  - osapi-version.h, [217](#)
- OS\_MISSION\_REV
  - osapi-version.h, [218](#)
- OS\_MODULE\_FILE\_EXTENSION
  - osconfig-example.h, [174](#)
- OS\_MODULE\_FLAG\_GLOBAL\_SYMBOLS
  - osapi-module.h, [204](#)
- OS\_MODULE\_FLAG\_LOCAL\_SYMBOLS
  - osapi-module.h, [205](#)
- OS\_ModuleInfo
  - OSAL Dynamic Loader and Symbol APIs, [89](#)
- OS\_ModuleLoad
  - OSAL Dynamic Loader and Symbol APIs, [90](#)
- OS\_ModuleSymbolLookup
  - OSAL Dynamic Loader and Symbol APIs, [90](#)
- OS\_ModuleUnload
  - OSAL Dynamic Loader and Symbol APIs, [91](#)
- OS\_MutSemCreate
  - OSAL Mutex APIs, [94](#)
- OS\_MutSemDelete
  - OSAL Mutex APIs, [95](#)
- OS\_MutSemGetIdByName
  - OSAL Mutex APIs, [95](#)
- OS\_MutSemGetInfo
  - OSAL Mutex APIs, [96](#)
- OS\_MutSemGive
  - OSAL Mutex APIs, [96](#)



- OS\_MutSemTake
  - OSAL Mutex APIs, [97](#)
- OS\_NetworkGetHostName
  - Network ID APIs, [99](#)
  - OSAL Socket Management APIs, [116](#)
- OS\_NetworkGetID
  - Network ID APIs, [99](#)
  - OSAL Socket Management APIs, [117](#)
- OS\_OBJECT\_CREATOR\_ANY
  - osapi-constants.h, [189](#)
- OS\_OBJECT\_ID\_UNDEFINED
  - osapi-constants.h, [189](#)
- OS\_OBJECT\_INDEX\_MASK
  - osapi-idmap.h, [201](#)
- OS\_OBJECT\_TYPE\_OS\_BINSEM
  - OSAL Object Type Defines, [78](#)
- OS\_OBJECT\_TYPE\_OS\_CONSOLE
  - OSAL Object Type Defines, [78](#)
- OS\_OBJECT\_TYPE\_OS\_COUNTSEM
  - OSAL Object Type Defines, [79](#)
- OS\_OBJECT\_TYPE\_OS\_DIR
  - OSAL Object Type Defines, [79](#)
- OS\_OBJECT\_TYPE\_OS\_FILESYS
  - OSAL Object Type Defines, [79](#)
- OS\_OBJECT\_TYPE\_OS\_MODULE
  - OSAL Object Type Defines, [79](#)
- OS\_OBJECT\_TYPE\_OS\_MUTEX
  - OSAL Object Type Defines, [79](#)
- OS\_OBJECT\_TYPE\_OS\_QUEUE
  - OSAL Object Type Defines, [80](#)
- OS\_OBJECT\_TYPE\_OS\_STREAM
  - OSAL Object Type Defines, [80](#)
- OS\_OBJECT\_TYPE\_OS\_TASK
  - OSAL Object Type Defines, [80](#)
- OS\_OBJECT\_TYPE\_OS\_TIMEBASE
  - OSAL Object Type Defines, [80](#)
- OS\_OBJECT\_TYPE\_OS\_TIMECB
  - OSAL Object Type Defines, [80](#)
- OS\_OBJECT\_TYPE\_SHIFT
  - osapi-idmap.h, [201](#)
- OS\_OBJECT\_TYPE\_UNDEFINED
  - OSAL Object Type Defines, [81](#)
- OS\_OBJECT\_TYPE\_USER
  - OSAL Object Type Defines, [81](#)
- OS\_ObjectIdDefined
  - OSAL Object ID Utility APIs, [85](#)
- OS\_ObjectIdEqual
  - OSAL Object ID Utility APIs, [85](#)
- OS\_ObjectIdFromInteger
  - OSAL Object ID Utility APIs, [86](#)
- OS\_ObjectIdToArrayIndex
  - OSAL Object ID Utility APIs, [86](#)
- OS\_ObjectIdToInteger
  - OSAL Object ID Utility APIs, [87](#)
- OS\_OpenCreate
  - OSAL Standard File APIs, [62](#)
- OS\_PEND
  - osapi-constants.h, [189](#)
- OS\_PRINTF\_CONSOLE\_NAME
  - osconfig-example.h, [174](#)
- OS\_PRINTF
  - common\_types.h, [177](#)
- OS\_QUEUE\_EMPTY
  - OSAL Return Code Defines, [51](#)
- OS\_QUEUE\_FULL
  - OSAL Return Code Defines, [51](#)
- OS\_QUEUE\_ID\_ERROR
  - OSAL Return Code Defines, [51](#)
- OS\_QUEUE\_INVALID\_SIZE
  - OSAL Return Code Defines, [51](#)
- OS\_QUEUE\_MAX\_DEPTH
  - osconfig-example.h, [174](#)
- OS\_QUEUE\_TIMEOUT
  - OSAL Return Code Defines, [52](#)
- OS\_QueueCreate
  - OSAL Message Queue APIs, [103](#)
- OS\_QueueDelete
  - OSAL Message Queue APIs, [104](#)
- OS\_QueueGet
  - OSAL Message Queue APIs, [105](#)
- OS\_QueueGetIdByName
  - OSAL Message Queue APIs, [105](#)
- OS\_QueueGetInfo
  - OSAL Message Queue APIs, [106](#)
- OS\_QueuePut
  - OSAL Message Queue APIs, [106](#)
- OS\_READ\_ONLY
  - OSAL File Access Option Defines, [55](#)
- OS\_READ\_WRITE
  - OSAL File Access Option Defines, [55](#)
- OS\_REPAIR
  - osapi-filesystem.h, [199](#)
- OS\_REVISION
  - osapi-version.h, [218](#)
- OS\_RegisterEventHandler
  - OSAL Core Operation APIs, [33](#)
- OS\_SEEK\_CUR
  - OSAL Reference Point For Seek Offset Defines, [56](#)
- OS\_SEEK\_END
  - OSAL Reference Point For Seek Offset Defines, [56](#)
- OS\_SEEK\_SET
  - OSAL Reference Point For Seek Offset Defines, [56](#)
- OS\_SEM\_EMPTY
  - OSAL Semaphore State Defines, [11](#)
- OS\_SEM\_FAILURE
  - OSAL Return Code Defines, [52](#)
- OS\_SEM\_FULL
  - OSAL Semaphore State Defines, [11](#)

- OS\_SEM\_TIMEOUT
  - OSAL Return Code Defines, [52](#)
- OS\_SHELL\_CMD\_INPUT\_FILE\_NAME
  - osconfig-example.h, [174](#)
- OS\_SOCKADDR\_MAX\_LEN
  - osapi-sockets.h, [210](#)
  - osconfig-example.h, [175](#)
- OS\_STR\_HELPER
  - osapi-version.h, [218](#)
- OS\_STR
  - osapi-version.h, [218](#)
- OS\_SUCCESS
  - OSAL Return Code Defines, [52](#)
- OS\_SelectFdAdd
  - OSAL Select APIs, [108](#)
- OS\_SelectFdClear
  - OSAL Select APIs, [108](#)
- OS\_SelectFdsSet
  - OSAL Select APIs, [108](#)
- OS\_SelectFdZero
  - OSAL Select APIs, [109](#)
- OS\_SelectMultiple
  - OSAL Select APIs, [109](#)
- OS\_SelectSingle
  - OSAL Select APIs, [110](#)
- OS\_SetLocalTime
  - OSAL Real Time Clock APIs, [20](#)
- OS\_ShellOutputToFile
  - OSAL Shell APIs, [111](#)
- OS\_SockAddr\_t, [156](#)
  - ActualLength, [157](#)
  - AddrData, [157](#)
- OS\_SockAddrData\_t, [157](#)
  - AlignPtr, [158](#)
  - AlignU32, [158](#)
  - Buffer, [158](#)
- OS\_SocketAccept
  - OSAL Socket Management APIs, [117](#)
- OS\_SocketAddrFromString
  - OSAL Socket Address APIs, [112](#)
- OS\_SocketAddrGetPort
  - OSAL Socket Address APIs, [113](#)
- OS\_SocketAddrInit
  - OSAL Socket Address APIs, [113](#)
- OS\_SocketAddrSetPort
  - OSAL Socket Address APIs, [114](#)
- OS\_SocketAddrToString
  - OSAL Socket Address APIs, [114](#)
- OS\_SocketBind
  - OSAL Socket Management APIs, [118](#)
- OS\_SocketConnect
  - OSAL Socket Management APIs, [118](#)
- OS\_SocketDomain\_t
  - osapi-sockets.h, [210](#)
- OS\_SocketGetIdByName
  - OSAL Socket Management APIs, [120](#)
- OS\_SocketGetInfo
  - OSAL Socket Management APIs, [121](#)
- OS\_SocketOpen
  - OSAL Socket Management APIs, [121](#)
- OS\_SocketRecvFrom
  - OSAL Socket Management APIs, [122](#)
- OS\_SocketSendTo
  - OSAL Socket Management APIs, [122](#)
- OS\_SocketType\_t
  - osapi-sockets.h, [211](#)
- OS\_StreamState\_t
  - osapi-select.h, [208](#)
- OS\_SymbolLookup
  - OSAL Dynamic Loader and Symbol APIs, [91](#)
- OS\_SymbolTableDump
  - OSAL Dynamic Loader and Symbol APIs, [92](#)
- OS\_TIMER\_ERR\_INTERNAL
  - OSAL Return Code Defines, [52](#)
- OS\_TIMER\_ERR\_INVALID\_ARGS
  - OSAL Return Code Defines, [53](#)
- OS\_TIMER\_ERR\_TIMER\_ID
  - OSAL Return Code Defines, [53](#)
- OS\_TIMER\_ERR\_UNAVAILABLE
  - OSAL Return Code Defines, [53](#)
- OS\_TaskCreate
  - OSAL Task APIs, [124](#)
- OS\_TaskDelay
  - OSAL Task APIs, [125](#)
- OS\_TaskDelete
  - OSAL Task APIs, [126](#)
- OS\_TaskExit
  - OSAL Task APIs, [126](#)
- OS\_TaskFindIdBySystemData
  - OSAL Task APIs, [126](#)
- OS\_TaskGetId
  - OSAL Task APIs, [127](#)
- OS\_TaskGetIdByName
  - OSAL Task APIs, [127](#)
- OS\_TaskGetInfo
  - OSAL Task APIs, [128](#)
- OS\_TaskInstallDeleteHandler
  - OSAL Task APIs, [128](#)
- OS\_TaskRegister
  - OSAL Task APIs, [129](#)
- OS\_TaskSetPriority
  - OSAL Task APIs, [129](#)
- OS\_TimeAdd
  - OSAL Real Time Clock APIs, [20](#)
- OS\_TimeAssembleFromMicroseconds
  - OSAL Real Time Clock APIs, [21](#)
- OS\_TimeAssembleFromMilliseconds
  - OSAL Real Time Clock APIs, [22](#)

- OS\_TimeAssembleFromNanoseconds
  - OSAL Real Time Clock APIs, [22](#)
- OS\_TimeAssembleFromSubseconds
  - OSAL Real Time Clock APIs, [23](#)
- OS\_TimeBaseCreate
  - OSAL Time Base APIs, [131](#)
- OS\_TimeBaseDelete
  - OSAL Time Base APIs, [132](#)
- OS\_TimeBaseGetFreeRun
  - OSAL Time Base APIs, [132](#)
- OS\_TimeBaseGetIdByName
  - OSAL Time Base APIs, [134](#)
- OS\_TimeBaseGetInfo
  - OSAL Time Base APIs, [134](#)
- OS\_TimeBaseSet
  - OSAL Time Base APIs, [135](#)
- OS\_TimeGetFractionalPart
  - OSAL Real Time Clock APIs, [23](#)
- OS\_TimeGetMicrosecondsPart
  - OSAL Real Time Clock APIs, [24](#)
- OS\_TimeGetMillisecondsPart
  - OSAL Real Time Clock APIs, [25](#)
- OS\_TimeGetNanosecondsPart
  - OSAL Real Time Clock APIs, [26](#)
- OS\_TimeGetSubsecondsPart
  - OSAL Real Time Clock APIs, [26](#)
- OS\_TimeGetTotalMicroseconds
  - OSAL Real Time Clock APIs, [27](#)
- OS\_TimeGetTotalMilliseconds
  - OSAL Real Time Clock APIs, [28](#)
- OS\_TimeGetTotalNanoseconds
  - OSAL Real Time Clock APIs, [28](#)
- OS\_TimeGetTotalSeconds
  - OSAL Real Time Clock APIs, [29](#)
- OS\_TimeSubtract
  - OSAL Real Time Clock APIs, [29](#)
- OS\_TimedRead
  - OSAL Standard File APIs, [66](#)
- OS\_TimedWrite
  - OSAL Standard File APIs, [67](#)
- OS\_TimerAdd
  - OSAL Timer APIs, [137](#)
- OS\_TimerCallback\_t
  - osapi-timer.h, [216](#)
- OS\_TimerCreate
  - OSAL Timer APIs, [138](#)
- OS\_TimerDelete
  - OSAL Timer APIs, [139](#)
- OS\_TimerGetIdByName
  - OSAL Timer APIs, [139](#)
- OS\_TimerGetInfo
  - OSAL Timer APIs, [140](#)
- OS\_TimerSet
  - OSAL Timer APIs, [141](#)
- OS\_TimerSync\_t
  - osapi-timebase.h, [215](#)
- OS\_TranslatePath
  - OSAL File System Level APIs, [75](#)
- OS\_USED
  - common\_types.h, [177](#)
- OS\_UTILITYTASK\_PRIORITY
  - osconfig-example.h, [175](#)
- OS\_UTILITYTASK\_STACK\_SIZE
  - osconfig-example.h, [175](#)
- OS\_VERSION\_STRING
  - osapi-version.h, [219](#)
- OS\_VERSION
  - osapi-version.h, [218](#)
- OS\_WRITE\_ONLY
  - OSAL File Access Option Defines, [55](#)
- OS\_bin\_sem\_prop\_t, [143](#)
  - creator, [143](#)
  - name, [143](#)
  - value, [143](#)
- OS\_chkfs
  - OSAL File System Level APIs, [69](#)
- OS\_chmod
  - OSAL Standard File APIs, [57](#)
- OS\_close
  - OSAL Standard File APIs, [58](#)
- OS\_count\_sem\_prop\_t, [144](#)
  - creator, [144](#)
  - name, [144](#)
  - value, [144](#)
- OS\_cp
  - OSAL Standard File APIs, [59](#)
- OS\_file\_flag\_t
  - osapi-file.h, [198](#)
- OS\_file\_prop\_t, [146](#)
  - IsValid, [147](#)
  - Path, [147](#)
  - User, [147](#)
- OS\_heap\_prop\_t, [150](#)
  - free\_blocks, [150](#)
  - free\_bytes, [150](#)
  - largest\_free\_block, [151](#)
- OS\_initfs
  - OSAL File System Level APIs, [72](#)
- OS\_lseek
  - OSAL Standard File APIs, [61](#)
- OS\_mkdir
  - OSAL Directory APIs, [42](#)
- OS\_mkfs
  - OSAL File System Level APIs, [73](#)
- OS\_module\_address\_t, [151](#)
  - bss\_address, [151](#)
  - bss\_size, [152](#)
  - code\_address, [152](#)

- code\_size, 152
- data\_address, 152
- data\_size, 152
- flags, 152
- valid, 153
- OS\_module\_prop\_t, 153
  - addr, 153
  - entry\_point, 154
  - filename, 154
  - host\_module\_id, 154
  - name, 154
- OS\_mount
  - OSAL File System Level APIs, 74
- OS\_mut\_sem\_prop\_t, 154
  - creator, 155
  - name, 155
- OS\_mv
  - OSAL Standard File APIs, 62
- OS\_printf
  - OSAL Printf APIs, 101
- OS\_printf\_disable
  - OSAL Printf APIs, 101
- OS\_printf\_enable
  - OSAL Printf APIs, 102
- OS\_queue\_prop\_t, 155
  - creator, 156
  - name, 156
- OS\_read
  - OSAL Standard File APIs, 63
- OS\_remove
  - OSAL Standard File APIs, 64
- OS\_rename
  - OSAL Standard File APIs, 64
- OS\_rmdir
  - OSAL Directory APIs, 42
- OS\_rmfs
  - OSAL File System Level APIs, 74
- OS\_socket\_prop\_t, 159
  - creator, 159
  - name, 159
- OS\_stat
  - OSAL Standard File APIs, 65
- OS\_static\_symbol\_record\_t, 160
  - Address, 160
  - Module, 160
  - Name, 160
- OS\_statvfs\_t, 161
  - block\_size, 161
  - blocks\_free, 161
  - total\_blocks, 161
- OS\_task\_prop\_t, 162
  - creator, 162
  - name, 162
  - priority, 163
  - stack\_size, 163
- OS\_time\_t, 163
  - ticks, 164
- OS\_timebase\_prop\_t, 164
  - accuracy, 164
  - creator, 165
  - freerun\_time, 165
  - name, 165
  - nominal\_interval\_time, 165
- OS\_timer\_prop\_t, 165
  - accuracy, 166
  - creator, 166
  - interval\_time, 166
  - name, 166
  - start\_time, 166
- OS\_unmount
  - OSAL File System Level APIs, 76
- OS\_write
  - OSAL Standard File APIs, 67
- OSAL BSP low level access APIs, 18
  - OS\_BSP\_GetArgC, 18
  - OS\_BSP\_GetArgV, 18
  - OS\_BSP\_SetExitCode, 18
- OSAL Binary Semaphore APIs, 12
  - OS\_BinSemCreate, 12
  - OS\_BinSemDelete, 13
  - OS\_BinSemFlush, 13
  - OS\_BinSemGetIdByName, 14
  - OS\_BinSemGetInfo, 15
  - OS\_BinSemGive, 15
  - OS\_BinSemTake, 16
  - OS\_BinSemTimedWait, 16
- OSAL Core Operation APIs, 31
  - OS\_API\_Init, 31
  - OS\_Application\_Run, 32
  - OS\_Application\_Startup, 32
  - OS\_ApplicationExit, 32
  - OS\_ApplicationShutdown, 32
  - OS\_DeleteAllObjects, 33
  - OS\_IdleLoop, 33
  - OS\_RegisterEventHandler, 33
- OSAL Counting Semaphore APIs, 35
  - OS\_CountSemCreate, 35
  - OS\_CountSemDelete, 36
  - OS\_CountSemGetIdByName, 36
  - OS\_CountSemGetInfo, 37
  - OS\_CountSemGive, 37
  - OS\_CountSemTake, 38
  - OS\_CountSemTimedWait, 39
- OSAL Directory APIs, 40
  - OS\_DirectoryClose, 40
  - OS\_DirectoryOpen, 40
  - OS\_DirectoryRead, 41
  - OS\_DirectoryRewind, 41

- OS\_mkdir, [42](#)
- OS\_rmdir, [42](#)
- OSAL Dynamic Loader and Symbol APIs, [89](#)
  - OS\_ModuleInfo, [89](#)
  - OS\_ModuleLoad, [90](#)
  - OS\_ModuleSymbolLookup, [90](#)
  - OS\_ModuleUnload, [91](#)
  - OS\_SymbolLookup, [91](#)
  - OS\_SymbolTableDump, [92](#)
- OSAL Error Info APIs, [54](#)
  - OS\_GetErrorName, [54](#)
- OSAL File Access Option Defines, [55](#)
  - OS\_READ\_ONLY, [55](#)
  - OS\_READ\_WRITE, [55](#)
  - OS\_WRITE\_ONLY, [55](#)
- OSAL File System Level APIs, [69](#)
  - OS\_FS\_GetPhysDriveName, [71](#)
  - OS\_FileSysAddFixedMap, [70](#)
  - OS\_FileSysStatVolume, [71](#)
  - OS\_GetFsInfo, [72](#)
  - OS\_TranslatePath, [75](#)
  - OS\_chkfs, [69](#)
  - OS\_initfs, [72](#)
  - OS\_mkfs, [73](#)
  - OS\_mount, [74](#)
  - OS\_rmfs, [74](#)
  - OS\_unmount, [76](#)
- OSAL Heap APIs, [77](#)
  - OS\_HeapGetInfo, [77](#)
- OSAL Message Queue APIs, [103](#)
  - OS\_QueueCreate, [103](#)
  - OS\_QueueDelete, [104](#)
  - OS\_QueueGet, [105](#)
  - OS\_QueueGetIdByName, [105](#)
  - OS\_QueueGetInfo, [106](#)
  - OS\_QueuePut, [106](#)
- OSAL Mutex APIs, [94](#)
  - OS\_MutSemCreate, [94](#)
  - OS\_MutSemDelete, [95](#)
  - OS\_MutSemGetIdByName, [95](#)
  - OS\_MutSemGetInfo, [96](#)
  - OS\_MutSemGive, [96](#)
  - OS\_MutSemTake, [97](#)
- OSAL Object ID Utility APIs, [82](#)
  - OS\_ConvertToArrayIndex, [82](#)
  - OS\_ForEachObject, [83](#)
  - OS\_ForEachObjectOfType, [83](#)
  - OS\_GetResourceName, [84](#)
  - OS\_IdentifyObject, [84](#)
  - OS\_ObjectIdDefined, [85](#)
  - OS\_ObjectIdEqual, [85](#)
  - OS\_ObjectIdFromInteger, [86](#)
  - OS\_ObjectIdToArrayIndex, [86](#)
  - OS\_ObjectIdToInteger, [87](#)
- OSAL Object Type Defines, [78](#)
  - OS\_OBJECT\_TYPE\_OS\_BINSEM, [78](#)
  - OS\_OBJECT\_TYPE\_OS\_CONSOLE, [78](#)
  - OS\_OBJECT\_TYPE\_OS\_COUNTSEM, [79](#)
  - OS\_OBJECT\_TYPE\_OS\_DIR, [79](#)
  - OS\_OBJECT\_TYPE\_OS\_FILESYS, [79](#)
  - OS\_OBJECT\_TYPE\_OS\_MODULE, [79](#)
  - OS\_OBJECT\_TYPE\_OS\_MUTEX, [79](#)
  - OS\_OBJECT\_TYPE\_OS\_QUEUE, [80](#)
  - OS\_OBJECT\_TYPE\_OS\_STREAM, [80](#)
  - OS\_OBJECT\_TYPE\_OS\_TASK, [80](#)
  - OS\_OBJECT\_TYPE\_OS\_TIMEBASE, [80](#)
  - OS\_OBJECT\_TYPE\_OS\_TIMECB, [80](#)
  - OS\_OBJECT\_TYPE\_UNDEFINED, [81](#)
  - OS\_OBJECT\_TYPE\_USER, [81](#)
- OSAL Printf APIs, [101](#)
  - OS\_printf, [101](#)
  - OS\_printf\_disable, [101](#)
  - OS\_printf\_enable, [102](#)
- OSAL Real Time Clock APIs, [19](#)
  - OS\_GetLocalTime, [19](#)
  - OS\_SetLocalTime, [20](#)
  - OS\_TimeAdd, [20](#)
  - OS\_TimeAssembleFromMicroseconds, [21](#)
  - OS\_TimeAssembleFromMilliseconds, [22](#)
  - OS\_TimeAssembleFromNanoseconds, [22](#)
  - OS\_TimeAssembleFromSubseconds, [23](#)
  - OS\_TimeGetFractionalPart, [23](#)
  - OS\_TimeGetMicrosecondsPart, [24](#)
  - OS\_TimeGetMillisecondsPart, [25](#)
  - OS\_TimeGetNanosecondsPart, [26](#)
  - OS\_TimeGetSubsecondsPart, [26](#)
  - OS\_TimeGetTotalMicroseconds, [27](#)
  - OS\_TimeGetTotalMilliseconds, [28](#)
  - OS\_TimeGetTotalNanoseconds, [28](#)
  - OS\_TimeGetTotalSeconds, [29](#)
  - OS\_TimeSubtract, [29](#)
- OSAL Reference Point For Seek Offset Defines, [56](#)
  - OS\_SEEK\_CUR, [56](#)
  - OS\_SEEK\_END, [56](#)
  - OS\_SEEK\_SET, [56](#)
- OSAL Return Code Defines, [44](#)
  - OS\_ERR\_BAD\_ADDRESS, [45](#)
  - OS\_ERR\_FILE, [46](#)
  - OS\_ERR\_INCORRECT\_OBJ\_STATE, [46](#)
  - OS\_ERR\_INCORRECT\_OBJ\_TYPE, [46](#)
  - OS\_ERR\_INVALID\_ID, [46](#)
  - OS\_ERR\_INVALID\_PRIORITY, [46](#)
  - OS\_ERR\_INVALID\_SIZE, [47](#)
  - OS\_ERR\_NAME\_NOT\_FOUND, [47](#)
  - OS\_ERR\_NAME\_TAKEN, [47](#)
  - OS\_ERR\_NAME\_TOO\_LONG, [47](#)
  - OS\_ERR\_NO\_FREE\_IDS, [47](#)
  - OS\_ERR\_NOT\_IMPLEMENTED, [48](#)

- OS\_ERR\_OBJECT\_IN\_USE, [48](#)
- OS\_ERR\_OPERATION\_NOT\_SUPPORTED, [48](#)
- OS\_ERR\_SEM\_NOT\_FULL, [48](#)
- OS\_ERR\_STREAM\_DISCONNECTED, [48](#)
- OS\_ERROR\_ADDRESS\_MISALIGNED, [49](#)
- OS\_ERROR\_TIMEOUT, [49](#)
- OS\_ERROR, [49](#)
- OS\_FS\_ERR\_DEVICE\_NOT\_FREE, [49](#)
- OS\_FS\_ERR\_DRIVE\_NOT\_CREATED, [49](#)
- OS\_FS\_ERR\_NAME\_TOO\_LONG, [50](#)
- OS\_FS\_ERR\_PATH\_INVALID, [50](#)
- OS\_FS\_ERR\_PATH\_TOO\_LONG, [50](#)
- OS\_INVALID\_INT\_NUM, [50](#)
- OS\_INVALID\_POINTER, [50](#)
- OS\_INVALID\_SEM\_VALUE, [51](#)
- OS\_QUEUE\_EMPTY, [51](#)
- OS\_QUEUE\_FULL, [51](#)
- OS\_QUEUE\_ID\_ERROR, [51](#)
- OS\_QUEUE\_INVALID\_SIZE, [51](#)
- OS\_QUEUE\_TIMEOUT, [52](#)
- OS\_SEM\_FAILURE, [52](#)
- OS\_SEM\_TIMEOUT, [52](#)
- OS\_SUCCESS, [52](#)
- OS\_TIMER\_ERR\_INTERNAL, [52](#)
- OS\_TIMER\_ERR\_INVALID\_ARGS, [53](#)
- OS\_TIMER\_ERR\_TIMER\_ID, [53](#)
- OS\_TIMER\_ERR\_UNAVAILABLE, [53](#)
- OSAL Select APIs, [108](#)
  - OS\_SelectFdAdd, [108](#)
  - OS\_SelectFdClear, [108](#)
  - OS\_SelectFdsSet, [108](#)
  - OS\_SelectFdZero, [109](#)
  - OS\_SelectMultiple, [109](#)
  - OS\_SelectSingle, [110](#)
- OSAL Semaphore State Defines, [11](#)
  - OS\_SEM\_EMPTY, [11](#)
  - OS\_SEM\_FULL, [11](#)
- OSAL Shell APIs, [111](#)
  - OS\_ShellOutputToFile, [111](#)
- OSAL Socket Address APIs, [112](#)
  - OS\_SocketAddrFromString, [112](#)
  - OS\_SocketAddrGetPort, [113](#)
  - OS\_SocketAddrInit, [113](#)
  - OS\_SocketAddrSetPort, [114](#)
  - OS\_SocketAddrToString, [114](#)
- OSAL Socket Management APIs, [116](#)
  - OS\_NetworkGetHostName, [116](#)
  - OS\_NetworkGetID, [117](#)
  - OS\_SocketAccept, [117](#)
  - OS\_SocketBind, [118](#)
  - OS\_SocketConnect, [118](#)
  - OS\_SocketGetIdByName, [120](#)
  - OS\_SocketGetInfo, [121](#)
  - OS\_SocketOpen, [121](#)
  - OS\_SocketRecvFrom, [122](#)
  - OS\_SocketSendTo, [122](#)
- OSAL Standard File APIs, [57](#)
  - OS\_CloseAllFiles, [58](#)
  - OS\_CloseFileByName, [59](#)
  - OS\_FDGetInfo, [60](#)
  - OS\_FileOpenCheck, [60](#)
  - OS\_OpenCreate, [62](#)
  - OS\_TimedRead, [66](#)
  - OS\_TimedWrite, [67](#)
  - OS\_chmod, [57](#)
  - OS\_close, [58](#)
  - OS\_cp, [59](#)
  - OS\_lseek, [61](#)
  - OS\_mv, [62](#)
  - OS\_read, [63](#)
  - OS\_remove, [64](#)
  - OS\_rename, [64](#)
  - OS\_stat, [65](#)
  - OS\_write, [67](#)
- OSAL Task APIs, [124](#)
  - OS\_TaskCreate, [124](#)
  - OS\_TaskDelay, [125](#)
  - OS\_TaskDelete, [126](#)
  - OS\_TaskExit, [126](#)
  - OS\_TaskFindIdBySystemData, [126](#)
  - OS\_TaskGetId, [127](#)
  - OS\_TaskGetIdByName, [127](#)
  - OS\_TaskGetInfo, [128](#)
  - OS\_TaskInstallDeleteHandler, [128](#)
  - OS\_TaskRegister, [129](#)
  - OS\_TaskSetPriority, [129](#)
- OSAL Time Base APIs, [131](#)
  - OS\_TimeBaseCreate, [131](#)
  - OS\_TimeBaseDelete, [132](#)
  - OS\_TimeBaseGetFreeRun, [132](#)
  - OS\_TimeBaseGetIdByName, [134](#)
  - OS\_TimeBaseGetInfo, [134](#)
  - OS\_TimeBaseSet, [135](#)
- OSAL Timer APIs, [137](#)
  - OS\_TimerAdd, [137](#)
  - OS\_TimerCreate, [138](#)
  - OS\_TimerDelete, [139](#)
  - OS\_TimerGetIdByName, [139](#)
  - OS\_TimerGetInfo, [140](#)
  - OS\_TimerSet, [141](#)
- OSAL\_API\_VERSION
  - osapi-version.h, [219](#)
- OSAL\_BLOCKCOUNT\_C
  - common\_types.h, [178](#)
- OSAL\_INDEX\_C
  - common\_types.h, [178](#)
- OSAL\_OBJTYPE\_C
  - common\_types.h, [178](#)

- OSAL\_PRIORITY\_C
  - osapi-task.h, 213
- OSAL\_SIZE\_C
  - common\_types.h, 178
- OSAL\_STACKPTR\_C
  - osapi-task.h, 213
- OSAL\_TASK\_STACK\_ALLOCATE
  - osapi-task.h, 213
- object\_ids
  - OS\_FdSet, 146
- os\_dirent\_t, 145
  - FileName, 145
- os\_err\_name\_t
  - osapi-error.h, 194
- os\_fsinfo\_t, 147
  - FreeFds, 148
  - FreeVolumes, 148
  - MaxFds, 148
  - MaxVolumes, 148
- os\_fstat\_t, 149
  - FileModeBits, 149
  - FileSize, 149
  - FileTime, 149
- osal/src/os/inc/common\_types.h, 176
- osal/src/os/inc/osapi-binsem.h, 183
- osal/src/os/inc/osapi-bsp.h, 184
- osal/src/os/inc/osapi-clock.h, 184
- osal/src/os/inc/osapi-common.h, 186
- osal/src/os/inc/osapi-constants.h, 188
- osal/src/os/inc/osapi-countsem.h, 190
- osal/src/os/inc/osapi-dir.h, 190
- osal/src/os/inc/osapi-error.h, 191
- osal/src/os/inc/osapi-file.h, 194
- osal/src/os/inc/osapi-filesys.h, 198
- osal/src/os/inc/osapi-heap.h, 199
- osal/src/os/inc/osapi-idmap.h, 200
- osal/src/os/inc/osapi-macros.h, 202
- osal/src/os/inc/osapi-module.h, 204
- osal/src/os/inc/osapi-mutex.h, 205
- osal/src/os/inc/osapi-network.h, 206
- osal/src/os/inc/osapi-printf.h, 206
- osal/src/os/inc/osapi-queue.h, 207
- osal/src/os/inc/osapi-select.h, 207
- osal/src/os/inc/osapi-shell.h, 208
- osal/src/os/inc/osapi-sockets.h, 209
- osal/src/os/inc/osapi-task.h, 211
- osal/src/os/inc/osapi-timebase.h, 214
- osal/src/os/inc/osapi-timer.h, 215
- osal/src/os/inc/osapi-version.h, 216
- osal/src/os/inc/osapi.h, 220
- osal\_blockcount\_t
  - common\_types.h, 180
- osal\_id\_t
  - common\_types.h, 180
- osal\_index\_t
  - common\_types.h, 180
- osal\_objtype\_t
  - common\_types.h, 181
- osal\_priority\_t
  - osapi-task.h, 213
- osal\_stackptr\_t
  - osapi-task.h, 213
- osal\_task
  - osapi-task.h, 214
- osapi-common.h
  - OS\_Event\_t, 187
  - OS\_EventHandler\_t, 187
- osapi-constants.h
  - OS\_CHECK, 189
  - OS\_MAX\_LOCAL\_PATH\_LEN, 189
  - OS\_OBJECT\_CREATOR\_ANY, 189
  - OS\_OBJECT\_ID\_UNDEFINED, 189
  - OS\_PEND, 189
- osapi-dir.h
  - OS\_DIRENTRY\_NAME, 191
- osapi-error.h
  - OS\_ERROR\_NAME\_LENGTH, 193
  - os\_err\_name\_t, 194
- osapi-file.h
  - OS\_FILESTAT\_EXEC, 196
  - OS\_FILESTAT\_ISDIR, 196
  - OS\_FILESTAT\_MODE, 196
  - OS\_FILESTAT\_READ, 196
  - OS\_FILESTAT\_SIZE, 196
  - OS\_FILESTAT\_TIME, 197
  - OS\_FILESTAT\_WRITE, 197
  - OS\_file\_flag\_t, 198
- osapi-filesys.h
  - OS\_CHK\_ONLY, 199
  - OS\_REPAIR, 199
- osapi-idmap.h
  - OS\_OBJECT\_INDEX\_MASK, 201
  - OS\_OBJECT\_TYPE\_SHIFT, 201
- osapi-macros.h
  - ARGCHECK, 202
  - BUGCHECK, 202
  - BUGREPORT, 203
  - LENGTHCHECK, 203
- osapi-module.h
  - OS\_MODULE\_FLAG\_GLOBAL\_SYMBOLS, 204
  - OS\_MODULE\_FLAG\_LOCAL\_SYMBOLS, 205
- osapi-select.h
  - OS\_StreamState\_t, 208
- osapi-sockets.h
  - OS\_SOCKADDR\_MAX\_LEN, 210
  - OS\_SocketDomain\_t, 210
  - OS\_SocketType\_t, 211
- osapi-task.h



- OS\_FP\_ENABLED, [212](#)
- OS\_MAX\_TASK\_PRIORITY, [212](#)
- OSAL\_PRIORITY\_C, [213](#)
- OSAL\_STACKPTR\_C, [213](#)
- OSAL\_TASK\_STACK\_ALLOCATE, [213](#)
- osal\_priority\_t, [213](#)
- osal\_stackptr\_t, [213](#)
- osal\_task, [214](#)
- osapi-timebase.h
  - OS\_TimerSync\_t, [215](#)
- osapi-timer.h
  - OS\_TimerCallback\_t, [216](#)
- osapi-version.h
  - OS\_BUILD\_BASELINE, [217](#)
  - OS\_BUILD\_NUMBER, [217](#)
  - OS\_MAJOR\_VERSION, [217](#)
  - OS\_MINOR\_VERSION, [217](#)
  - OS\_MISSION\_REV, [218](#)
  - OS\_REVISION, [218](#)
  - OS\_STR\_HELPER, [218](#)
  - OS\_STR, [218](#)
  - OS\_VERSION\_STRING, [219](#)
  - OS\_VERSION, [218](#)
  - OSAL\_API\_VERSION, [219](#)
- osconfig-example.h
  - OS\_BUFFER\_MSG\_DEPTH, [168](#)
  - OS\_BUFFER\_SIZE, [168](#)
  - OS\_FS\_DEV\_NAME\_LEN, [169](#)
  - OS\_FS\_PHYS\_NAME\_LEN, [169](#)
  - OS\_FS\_VOL\_NAME\_LEN, [169](#)
  - OS\_MAX\_API\_NAME, [169](#)
  - OS\_MAX\_BIN\_SEMAPHORES, [169](#)
  - OS\_MAX\_CMD\_LEN, [170](#)
  - OS\_MAX\_CONSOLES, [170](#)
  - OS\_MAX\_COUNT\_SEMAPHORES, [170](#)
  - OS\_MAX\_FILE\_NAME, [170](#)
  - OS\_MAX\_FILE\_SYSTEMS, [171](#)
  - OS\_MAX\_MODULES, [171](#)
  - OS\_MAX\_Mutexes, [171](#)
  - OS\_MAX\_NUM\_OPEN\_DIRS, [171](#)
  - OS\_MAX\_NUM\_OPEN\_FILES, [172](#)
  - OS\_MAX\_PATH\_LEN, [172](#)
  - OS\_MAX\_QUEUES, [172](#)
  - OS\_MAX\_SYM\_LEN, [172](#)
  - OS\_MAX\_TASKS, [173](#)
  - OS\_MAX\_TIMEBASES, [173](#)
  - OS\_MAX\_TIMERS, [173](#)
  - OS\_MODULE\_FILE\_EXTENSION, [174](#)
  - OS\_PRINTF\_CONSOLE\_NAME, [174](#)
  - OS\_QUEUE\_MAX\_DEPTH, [174](#)
  - OS\_SHELL\_CMD\_INPUT\_FILE\_NAME, [174](#)
  - OS\_SOCKADDR\_MAX\_LEN, [175](#)
  - OS\_UTILITYTASK\_PRIORITY, [175](#)
  - OS\_UTILITYTASK\_STACK\_SIZE, [175](#)
- Path
  - OS\_file\_prop\_t, [147](#)
- priority
  - OS\_task\_prop\_t, [163](#)
- stack\_size
  - OS\_task\_prop\_t, [163](#)
- start\_time
  - OS\_timer\_prop\_t, [166](#)
- ticks
  - OS\_time\_t, [164](#)
- total\_blocks
  - OS\_statvfs\_t, [161](#)
- uint16
  - common\_types.h, [181](#)
- uint32
  - common\_types.h, [181](#)
- uint64
  - common\_types.h, [181](#)
- uint8
  - common\_types.h, [181](#)
- User
  - OS\_file\_prop\_t, [147](#)
- valid
  - OS\_module\_address\_t, [153](#)
- value
  - OS\_bin\_sem\_prop\_t, [143](#)
  - OS\_count\_sem\_prop\_t, [144](#)