



# **Get started with StorageGRID**

## **StorageGRID**

NetApp  
May 17, 2022

This PDF was generated from <https://docs.netapp.com/us-en/storagegrid-116/admin/web-browser-requirements.html> on May 17, 2022. Always check docs.netapp.com for the latest.

# Table of Contents

- Get started with StorageGRID ..... 1
  - Web browser requirements ..... 1
  - Sign in to the Grid Manager ..... 1
  - Sign out of the Grid Manager ..... 5
  - Change your password ..... 6
  - Change the browser session timeout ..... 6
  - View StorageGRID license information ..... 7
  - Update StorageGRID license information ..... 8
  - Use the API ..... 9

# Get started with StorageGRID

## Web browser requirements

You must use a supported web browser.

Web browser	Minimum supported version
Google Chrome	96
Microsoft Edge	96
Mozilla Firefox	94

You should set the browser window to a recommended width.

Browser width	Pixels
Minimum	1024
Optimum	1280

## Sign in to the Grid Manager

You access the Grid Manager sign-in page by entering the fully qualified domain name (FQDN) or IP address of an Admin Node into the address bar of a supported web browser.

### What you'll need

- You have your login credentials.
- You have the URL for the Grid Manager.
- You are using a [supported web browser](#).
- Cookies are enabled in your web browser.
- You have specific access permissions.

### About this task

Each StorageGRID system includes one primary Admin Node and any number of non-primary Admin Nodes. You can sign in to the Grid Manager on any Admin Node to manage the StorageGRID system. However, the Admin Nodes are not exactly the same:

- Alarm acknowledgments (legacy system) made on one Admin Node are not copied to other Admin Nodes. For this reason, the information displayed for alarms might not look the same on each Admin Node.
- Some maintenance procedures can only be performed from the primary Admin Node.

If Admin Nodes are included in a high availability (HA) group, you connect using the virtual IP address of the HA group or a fully qualified domain name that maps to the virtual IP address. The primary Admin Node should

be selected as the group's primary interface, so that when you access the Grid Manager, you access it on the primary Admin Node unless the primary Admin Node is not available.

## Steps

1. Launch a supported web browser.
2. In the browser's address bar, enter the URL for the Grid Manager:

```
https://FQDN_or_Admin_Node_IP/
```

where *FQDN\_or\_Admin\_Node\_IP* is a fully qualified domain name or the IP address of an Admin Node or the virtual IP address of an HA group of Admin Nodes.


If you must access the Grid Manager on a port other than the standard port for HTTPS (443), enter the following, where *FQDN\_or\_Admin\_Node\_IP* is a fully qualified domain name or IP address, and port is the port number:

```
https://FQDN_or_Admin_Node_IP:port/
```

3. If you are prompted with a security alert, install the certificate using the browser's installation wizard (see [About security certificates](#)).
4. Sign in to the Grid Manager:
  - If single sign-on (SSO) is not being used for your StorageGRID system:
    - i. Enter your username and password for the Grid Manager.
    - ii. Select **Sign In**.

The image shows the login interface for the StorageGRID Grid Manager. On the left side, there is the NetApp logo, which consists of a blue square with a white 'N' shape inside, and the word 'NetApp' in black text below it. To the right of the logo, the text 'StorageGRID® Grid Manager' is displayed in a blue font. Below this text, there are two input fields: the first is labeled 'Username' and the second is labeled 'Password'. Both fields are white with a light gray border. To the right of the 'Password' field, there is a 'Sign in' button with a light gray background and a thin black border.

- If SSO is enabled for your StorageGRID system and this is the first time you have accessed the URL on this browser:
  - i. Select **Sign in**. You can leave the Account ID field blank.




StorageGRID® Sign in

Account ID

For Grid Manager, leave this field blank.

ii. Enter your standard SSO credentials on your organization's SSO sign-in page. For example:



Sign in with your organizational account

◦ If SSO is enabled for your StorageGRID system and you have previously accessed the Grid Manager or a tenant account:

i. Do either of the following:

- Enter **0** (the account ID for the Grid Manager), and select **Sign in**.
- Select **Grid Manager** if it appears in the list of recent accounts, and select **Sign in**.




StorageGRID® Sign in

Recent

Account ID

ii. Sign in with your standard SSO credentials on your organization's SSO sign-in page. When you are

signed in, the home page of the Grid Manager appears, which includes the Dashboard. To learn what information is provided, see [View the Dashboard](#).



5. If you want to sign in to another Admin Node:

Option	Steps
SSO not enabled	<ol style="list-style-type: none"> <li>In the browser's address bar, enter the fully qualified domain name or IP address of the other Admin Node. Include the port number as required.</li> <li>Enter your username and password for the Grid Manager.</li> <li>Select <b>Sign In</b>.</li> </ol>
SSO enabled	<p>In the browser's address bar, enter the fully qualified domain name or IP address of the other Admin Node.</p> <p>If you have signed in to one Admin Node, you can access other Admin Nodes without having to sign in again. However, if your SSO session expires, you are prompted for your credentials again.</p> <p><b>Note:</b> SSO is not available on the restricted Grid Manager port. You must use the default HTTPS port (443) if you want users to authenticate with single sign-on.</p>

#### Related information

- [Control access through firewalls](#)
- [Configure single sign-on](#)

- [Manage admin groups](#)
- [Manage high availability groups](#)
- [Use a tenant account](#)
- [Monitor and troubleshoot](#)

## Sign out of the Grid Manager

When you are done working with the Grid Manager, you must sign out to ensure that unauthorized users cannot access the StorageGRID system. Closing your browser might not sign you out of the system, based on browser cookie settings.

### Steps

1. Select your user name in the top-right corner.



2. Select **Sign Out**.

Option	Description
SSO not in use	<p>You are signed out of the Admin Node.</p> <p>The Grid Manager sign in page is displayed.</p> <p><b>Note:</b> If you signed into more than one Admin Node, you must sign out of each node.</p>
SSO enabled	<p>You are signed out of all Admin Nodes you were accessing. The StorageGRID sign in page is displayed. <b>Grid Manager</b> is listed as the default in the <b>Recent Accounts</b> drop-down, and the <b>Account ID</b> field shows 0.</p> <p><b>Note:</b> If SSO is enabled and you are also signed in to the Tenant Manager, you must also sign out of the tenant account to sign out of SSO.</p>

### Related information

- [Configure single sign-on](#)
- [Use a tenant account](#)

# Change your password

If you are a local user of the Grid Manager, you can change your own password.

## What you'll need

You are signed in to the Grid Manager using a [supported web browser](#).

## About this task

If you sign in to StorageGRID as a federated user or if single sign-on (SSO) is enabled, you cannot change your password in Grid Manager. Instead, you must change your password in the external identity source, for example, Active Directory or OpenLDAP.

## Steps

1. From the Grid Manager header, select ***your name*** > **Change password**.
2. Enter your current password.
3. Type a new password.

Your password must contain at least 8 and no more than 32 characters. Passwords are case-sensitive.

4. Re-enter the new password.
5. Select **Save**.

# Change the browser session timeout

You can control whether Grid Manager and Tenant Manager users are signed out if they are inactive for more than a certain amount of time.

## What you'll need

- You are signed in to the Grid Manager using a [supported web browser](#).
- You have specific access permissions.

## About this task

The GUI Inactivity Timeout defaults to 900 seconds (15 minutes). If a user's browser session is not active for this amount of time, the session times out.

As required, you can increase or decrease the timeout period by setting the GUI Inactivity Timeout display option.

If single sign-on (SSO) is enabled and a user's browser session times out, the system behaves as if the user selected **Sign Out** manually. The user must reenter their SSO credentials to access StorageGRID again. See [Configure single sign-on](#).



User session timeout can also be controlled by the following:



- A separate, non-configurable StorageGRID timer, which is included for system security. By default, each user's authentication token expires 16 hours after the user signs in. When a user's authentication expires, that user is automatically signed out, even if the value for the GUI Inactivity Timeout has not been reached. To renew the token, the user must sign back in.
- Timeout settings for the identity provider, assuming SSO is enabled for StorageGRID.

### Steps

1. Select **CONFIGURATION > System > Display options**.
2. For **GUI Inactivity Timeout**, enter a timeout period of 60 seconds or more.

Set this field to 0 if you do not want to use this functionality. Users are signed out 16 hours after they sign in, when their authentication tokens expire.



## Display Options

Updated: 2017-03-09 20:36:53 MST

Current Sender	ADMIN-DC1-ADM1
Preferred Sender	ADMIN-DC1-ADM1
GUI Inactivity Timeout	900
Notification Suppress All	<input type="checkbox"/>

Apply Changes

3. Select **Apply Changes**.

The new setting does not affect currently signed in users. Users must sign in again or refresh their browsers for the new timeout setting to take effect.

## View StorageGRID license information

You can view the license information for your StorageGRID system, such as the maximum storage capacity of your grid, whenever necessary.

### What you'll need

- You are signed in to the Grid Manager using a [supported web browser](#).

### About this task

If there is an issue with the software license for this StorageGRID system, the Health panel on the Dashboard includes a License Status icon and a **License** link. The number indicates how many license-related issues there are.



### Step

To view the license, do one of the following:

- From the Health panel on the Dashboard, select the License status icon or the **License** link. This link appears only if there is an issue with the license.
- Select **MAINTENANCE > System > License**.

The License Page appears and provides the following, read-only information about the current license:

- StorageGRID system ID, which is the unique identification number for this StorageGRID installation
- License serial number
- Licensed storage capacity of the grid
- Software license end date
- Support service contract end date
- Contents of the license text file



For licenses issued before StorageGRID 10.3, the licensed storage capacity is not included in the license file, and a "See License Agreement" message is displayed instead of a value.

## Update StorageGRID license information

You must update the license information for your StorageGRID system any time the terms of your license change. For example, you must update the license information if you purchase additional storage capacity for your grid.

### What you'll need

- You have a new license file to apply to your StorageGRID system.
- You have specific access permissions.
- You have the provisioning passphrase.

### Steps

1. Select **MAINTENANCE > System > License**.
2. Enter the provisioning passphrase for your StorageGRID system in the **Provisioning Passphrase** text box.
3. Select **Browse**.

4. In the Open dialog box, locate and select the new license file (.txt), and select **Open**.

The new license file is validated and displayed.

5. Select **Save**.

## Use the API

### Use the Grid Management API

You can perform system management tasks using the Grid Management REST API instead of the Grid Manager user interface. For example, you might want to use the API to automate operations or to create multiple entities, such as users, more quickly.

#### Top-level resources

The Grid Management API provides the following top-level resources:

- /grid: Access is restricted to Grid Manager users and is based on the configured group permissions.
- /org: Access is restricted to users who belong to a local or federated LDAP group for a tenant account. For details, see [Use a tenant account](#).
- /private: Access is restricted to Grid Manager users and is based on the configured group permissions. The private APIs are subject to change without notice. StorageGRID private endpoints also ignore the API version of the request.

#### Issue API requests

The Grid Management API uses the Swagger open source API platform. Swagger provides an intuitive user interface that allows developers and non-developers to perform real-time operations in StorageGRID with the API.

The Swagger user interface provides complete details and documentation for each API operation.

#### What you'll need


- You are signed in to the Grid Manager using a [supported web browser](#).
- You have specific access permissions.



Any API operations you perform using the API Docs webpage are live operations. Be careful not to create, update, or delete configuration data or other data by mistake.

#### Steps

1. From the Grid Manager header, select the help icon and select **API Documentation**.



2. To perform an operation with the private API, select **Go to private API documentation** on the StorageGRID Management API page.

The private APIs are subject to change without notice. StorageGRID private endpoints also ignore the API version of the request.

3. Select the desired operation.

When you expand an API operation, you can see the available HTTP actions, such as GET, PUT, UPDATE, and DELETE.

4. Select an HTTP action to see the request details, including the endpoint URL, a list of any required or optional parameters, an example of the request body (when required), and the possible responses.

GET
/grid/groups
Lists Grid Administrator Groups

Try it out

Name	Description
type string (query)	filter by group type Available values : local, federated <div> -- </div>
limit integer (query)	maximum number of results Default value : 25 <div> 25 </div>
marker string (query)	marker-style pagination offset (value is Group's URN) <div> marker - marker-style pagination offset (value </div>
includeMarker boolean (query)	if set, the marker element is also returned <div> -- </div>
order string (query)	pagination order (desc requires marker) Available values : asc, desc <div> -- </div>

Responses
Response content type application/json

Code	Description
200	successfully retrieved Example Value   Model <pre> {   "responseTime": "2021-03-29T14:22:19.673Z",   "status": "success",   "apiVersion": "3.3",   "deprecated": false,   "data": [     {       "displayName": "Developers", </pre>

- Determine if the request requires additional parameters, such as a group or user ID. Then, obtain these values. You might need to issue a different API request first to get the information you need.
- Determine if you need to modify the example request body. If so, you can select **Model** to learn the requirements for each field.
- Select **Try it out**.
- Provide any required parameters, or modify the request body as required.
- Select **Execute**.
- Review the response code to determine if the request was successful.

## Grid Management API operations

The Grid Management API organizes the available operations into the following sections.



This list only includes operations available in the public API.

- **accounts** — Operations to manage storage tenant accounts, including creating new accounts and retrieving storage usage for a given account.
- **alarms** — Operations to list current alarms (legacy system), and return information about the health of the grid, including the current alerts and a summary of node connection states.
- **alert-history** — Operations on resolved alerts.
- **alert-receivers** — Operations on alert notification receivers (email).
- **alert-rules** — Operations on alert rules.
- **alert-silences** — Operations on alert silences.
- **alerts** — Operations on alerts.
- **audit** — Operations to list and update the audit configuration.
- **auth** — Operations to perform user session authentication.

The Grid Management API supports the Bearer Token Authentication Scheme. To sign in, you provide a username and password in the JSON body of the authentication request (that is, `POST /api/v3/authorize`). If the user is successfully authenticated, a security token is returned. This token must be provided in the header of subsequent API requests ("Authorization: Bearer *token*").



If single sign-on is enabled for the StorageGRID system, you must perform different steps to authenticate. See “Authenticating in to the API if single sign-on is enabled.”

See “Protecting against Cross-Site Request Forgery” for information on improving authentication security.

- **client-certificates** — Operations to configure client certificates so that StorageGRID can be accessed securely using external monitoring tools.
- **config** — Operations related to the product release and versions of the Grid Management API. You can list the product release version and the major versions of the Grid Management API supported by that release, and you can disable deprecated versions of the API.
- **deactivated-features** — Operations to view features that might have been deactivated.
- **dns-servers** — Operations to list and change configured external DNS servers.
- **endpoint-domain-names** — Operations to list and change endpoint domain names.
- **erasure-coding** — Operations on Erasure Coding profiles.
- **expansion** — Operations on expansion (procedure-level).
- **expansion-nodes** — Operations on expansion (node-level).
- **expansion-sites** — Operations on expansion (site-level).
- **grid-networks** — Operations to list and change the Grid Network List.
- **grid-passwords** — Operations for grid password management.
- **groups** — Operations to manage local Grid Administrator Groups and to retrieve federated Grid Administrator Groups from an external LDAP server.

- **identity-source** — Operations to configure an external identity source and to manually synchronize federated group and user information.
- **ilm** — Operations on information lifecycle management (ILM).
- **license** — Operations to retrieve and update the StorageGRID license.
- **logs** — Operations for collecting and downloading log files.
- **metrics** — Operations on StorageGRID metrics including instant metric queries at a single point in time and range metric queries over a range of time. The Grid Management API uses the Prometheus systems monitoring tool as the backend data source. For information about constructing Prometheus queries, see the Prometheus web site.



Metrics that include *private* in their names are intended for internal use only. These metrics are subject to change between StorageGRID releases without notice.

- **node-details** — Operations on node details.
- **node-health** — Operations on node health status.
- **ntp-servers** — Operations to list or update external Network Time Protocol (NTP) servers.
- **objects** — Operations on objects and object metadata.
- **recovery** — Operations for the recovery procedure.
- **recovery-package** — Operations to download the Recovery Package.
- **regions** — Operations to view and create regions.
- **s3-object-lock** — Operations on global S3 Object Lock settings.
- **server-certificate** — Operations to view and update Grid Manager server certificates.
- **snmp** — Operations on the current SNMP configuration.
- **traffic-classes** — Operations for traffic classification policies.
- **untrusted-client-network** — Operations on the untrusted Client Network configuration.
- **users** — Operations to view and manage Grid Manager users.

## Grid Management API versioning

The Grid Management API uses versioning to support non-disruptive upgrades.

For example, this Request URL specifies version 3 of the API.

`https://hostname_or_ip_address/api/v3/authorize`

The major version of the Tenant Management API is bumped when changes are made that are **not compatible** with older versions. The minor version of the Tenant Management API is bumped when changes are made that **are compatible** with older versions. Compatible changes include the addition of new endpoints or new properties. The following example illustrates how the API version is bumped based on the type of changes made.

Type of change to API	Old version	New version
Compatible with older versions	2.1	2.2

Type of change to API	Old version	New version
Not compatible with older versions	2.1	3.0

When you install StorageGRID software for the first time, only the most recent version of the Grid Management API is enabled. However, when you upgrade to a new feature release of StorageGRID, you continue to have access to the older API version for at least one StorageGRID feature release.



You can use the Grid Management API to configure the supported versions. See the “config” section of the Swagger API documentation for more information. You should deactivate support for the older version after updating all Grid Management API clients to use the newer version.

Outdated requests are marked as deprecated in the following ways:

- The response header is "Deprecated: true"
- The JSON response body includes "deprecated": true
- A deprecated warning is added to nms.log. For example:

```
Received call to deprecated v1 API at POST "/api/v1/authorize"
```

## Determine which API versions are supported in the current release

Use the following API request to return a list of the supported API major versions:

```
GET https://{IP-Address}/api/versions
{
  "responseTime": "2019-01-10T20:41:00.845Z",
  "status": "success",
  "apiVersion": "3.0",
  "data": [
    2,
    3
  ]
}
```

## Specify an API version for a request

You can specify the API version using a path parameter (/api/v3) or a header (Api-Version: 3). If you provide both values, the header value overrides the path value.

```
curl https://[IP-Address]/api/v3/grid/accounts

curl -H "Api-Version: 3" https://[IP-Address]/api/grid/accounts
```



## Protect against Cross-Site Request Forgery (CSRF)

You can help protect against Cross-Site Request Forgery (CSRF) attacks against StorageGRID by using CSRF tokens to enhance authentication that uses cookies. The Grid Manager and Tenant Manager automatically enable this security feature; other API clients can choose whether to enable it when they sign in.

An attacker that can trigger a request to a different site (such as with an HTTP form POST) can cause certain requests to be made using the signed-in user's cookies.

StorageGRID helps protect against CSRF attacks by using CSRF tokens. When enabled, the contents of a specific cookie must match the contents of either a specific header or a specific POST body parameter.

To enable the feature, set the `csrfToken` parameter to `true` during authentication. The default is `false`.

```
curl -X POST --header "Content-Type: application/json" --header "Accept: application/json" -d "{
  \"username\": \"MyUserName\",
  \"password\": \"MyPassword\",
  \"cookie\": true,
  \"csrfToken\": true
}" "https://example.com/api/v3/authorize"
```

When `true`, a `GridCsrfToken` cookie is set with a random value for sign-ins to the Grid Manager, and the `AccountCsrfToken` cookie is set with a random value for sign-ins to the Tenant Manager.

If the cookie is present, all requests that can modify the state of the system (POST, PUT, PATCH, DELETE) must include one of the following:

- The `X-Csrf-Token` header, with the value of the header set to the value of the CSRF token cookie.
- For endpoints that accept a form-encoded body: A `csrfToken` form-encoded request body parameter.

See the online API documentation for additional examples and details.



Requests that have a CSRF token cookie set will also enforce the `"Content-Type: application/json"` header for any request that expects a JSON request body as an additional protection against CSRF attacks.

## Use the API if single sign-on is enabled

### Use the API if single sign-on is enabled (Active Directory)

If you have [configured and enabled single sign-on \(SSO\)](#) and you use Active Directory as the SSO provider, you must issue a series of API requests to obtain an authentication token that is valid for the Grid Management API or the Tenant Management API.

## Sign in to the API if single sign-on is enabled

These instructions apply if you are using Active Directory as the SSO identity provider.

### What you'll need

- You know the SSO username and password for a federated user who belongs to a StorageGRID user group.
- If you want to access the Tenant Management API, you know the tenant account ID.

### About this task

To obtain an authentication token, you can use one of the following examples:

- The `storagegrid-ssoauth.py` Python script, which is located in the StorageGRID installation files directory (`./rpms` for Red Hat Enterprise Linux or CentOS, `./debs` for Ubuntu or Debian, and `./vsphere` for VMware).
- An example workflow of curl requests.

The curl workflow might time out if you perform it too slowly. You might see the error: A valid SubjectConfirmation was not found on this Response.



The example curl workflow does not protect the password from being seen by other users.

If you have a URL-encoding issue, you might see the error: `Unsupported SAML version`.

### Steps

1. Select one of the following methods to obtain an authentication token:
  - Use the `storagegrid-ssoauth.py` Python script. Go to step 2.
  - Use curl requests. Go to step 3.
2. If you want to use the `storagegrid-ssoauth.py` script, pass the script to the Python interpreter and run the script.

When prompted, enter values for the following arguments:

- The SSO method. Enter ADFS or adfs.
- The SSO username
- The domain where StorageGRID is installed
- The address for StorageGRID
- The tenant account ID, if you want to access the Tenant Management API.

```
python3 storagegrid-ssoauth.py
sso_method: adfs
saml_user: my-sso-username
saml_domain: my-domain
sg_address: storagegrid.example.com
tenant_account_id: 12345
Enter the user's SAML password:
*****

*****

StorageGRID Auth Token: 56eb07bf-21f6-40b7-afob-5c6cacfb25e7
```

The StorageGRID authorization token is provided in the output. You can now use the token for other requests, similar to how you would use the API if SSO was not being used.

3. If you want to use curl requests, use the following procedure.

a. Declare the variables needed to sign in.

```
export SAMLUSER='my-sso-username'
export SAMLPASSWORD='my-password'
export SAMLDOMAIN='my-domain'
export TENANTACCOUNTID='12345'
export STORAGEGRID_ADDRESS='storagegrid.example.com'
export AD_FS_ADDRESS='adfs.example.com'
```



To access the Grid Management API, use 0 as TENANTACCOUNTID.

b. To receive a signed authentication URL, issue a POST request to `/api/v3/authorize-saml`, and remove the additional JSON encoding from the response.

This example shows a POST request for a signed authentication URL for TENANTACCOUNTID. The results will be passed to `python -m json.tool` to remove the JSON encoding.

```
curl -X POST "https://$STORAGEGRID_ADDRESS/api/v3/authorize-saml" \
-H "accept: application/json" -H "Content-Type: application/json" \
--data "{\"accountId\": \"$TENANTACCOUNTID\"}" | python -m
json.tool
```

The response for this example includes a signed URL that is URL-encoded, but it does not include the additional JSON-encoding layer.

```
{
  "apiVersion": "3.0",
  "data":
    "https://adfs.example.com/adfs/ls/?SAMLRequest=fZHLbsIwEEV%2FJTuv7...
    sSl%2BfQ33cvfwA%3D&RelayState=12345",
  "responseTime": "2018-11-06T16:30:23.355Z",
  "status": "success"
}
```

- c. Save the SAMLRequest from the response for use in subsequent commands.

```
export SAMLREQUEST='fZHLbsIwEEV%2FJTuv7...sSl%2BfQ33cvfwA%3D'
```

- d. Get a full URL that includes the client request ID from AD FS.

One option is to request the login form using the URL from the previous response.

```
curl "https://$AD_FS_ADDRESS/adfs/ls/?SAMLRequest=
$SAMLREQUEST&RelayState=$TENANTACCOUNTID" | grep 'form method="post"
id="loginForm"'
```

The response includes the client request ID:

```
<form method="post" id="loginForm" autocomplete="off"
novalidate="novalidate" onKeyPress="if (event && event.keyCode == 13)
Login.submitLoginRequest();" action="/adfs/ls/?
SAMLRequest=fZHRToMwFIZfhh...UJikvo77sXPw%3D%3D&RelayState=12345&clie
nt-request-id=00000000-0000-0000-ee02-0080000000de" >
```

- e. Save the client request ID from the response.

```
export SAMLREQUESTID='00000000-0000-0000-ee02-0080000000de'
```

- f. Send your credentials to the form action from the previous response.

```
curl -X POST "https://$AD_FS_ADDRESS
/adfs/ls/?SAMLRequest=$SAMLREQUEST&RelayState=$TENANTACCOUNTID&client
-request-id=$SAMLREQUESTID" \
--data "UserName=$SAMLUSER@$SAMLDOMAIN&Password=
$SAMLPASSWORD&AuthMethod=FormsAuthentication" --include
```

AD FS returns a 302 redirect, with additional information in the headers.



If multi-factor authentication (MFA) is enabled for your SSO system, the form post will also contain the second password or other credentials.

```
HTTP/1.1 302 Found
Content-Length: 0
Content-Type: text/html; charset=utf-8
Location:
https://adfs.example.com/adfs/ls/?SAMLRequest=fZHRT0MwFIZfhb...UJikvo
77sXPw%3D%3D&RelayState=12345&client-request-id=00000000-0000-0000-
ee02-0080000000de
Set-Cookie: MSISAuth=AAEAADAvsHpXk6ApV...pmP0aEiNtJvWY=; path=/adfs;
HttpOnly; Secure
Date: Tue, 06 Nov 2018 16:55:05 GMT
```

g. Save the MSISAuth cookie from the response.

```
export MSISAuth='AAEAADAvsHpXk6ApV...pmP0aEiNtJvWY='
```

h. Send a GET request to the specified location with the cookies from the authentication POST.

```
curl "https://$AD_FS_ADDRESS/adfs/ls/?SAMLRequest=
$SAMLREQUEST&RelayState=$TENANTACCOUNTID&client-request-
id=$SAMLREQUESTID" \
--cookie "MSISAuth=$MSISAuth" --include
```

The response headers will contain AD FS session information for later logout usage, and the response body contains the SAMLResponse in a hidden form field.

```

HTTP/1.1 200 OK
Cache-Control: no-cache,no-store
Pragma: no-cache
Content-Length: 5665
Content-Type: text/html; charset=utf-8
Expires: -1
Server: Microsoft-HTTPAPI/2.0
P3P: ADFS doesn't have P3P policy, please contact your site's admin
for more details
Set-Cookie:
SamlSession=a3dpbnRlcnMtUHJpbWFyeS1BZG1pbi0xNzgmRmFsc2Umcng4NnJDZmFKV
XFxVWx3bk1lMnFuUSUzZCUzZCYmJiYmXzE3MjAyZTA5LTNmMDgtNDRkZC04Yzg5LTQ3ND
UxYzA3ZjkzYw==; path=/adfs; HttpOnly; Secure
Set-Cookie: MSISAuthenticated=MTEvNy8yMDE4IDQ6MzI6NTkgUE0=;
path=/adfs; HttpOnly; Secure
Set-Cookie: MSISLoopDetectionCookie=MjAxOC0xMS0wNzoxNjozMj01OVpcMQ==;
path=/adfs; HttpOnly; Secure
Date: Wed, 07 Nov 2018 16:32:59 GMT

<form method="POST" name="hiddenform"
action="https://storagegrid.example.com:443/api/saml-response">
  <input type="hidden" name="SAMLResponse"
value="PHNhbWxwOlJlc3Bvb3N...1scDpSZXNwb25zZT4=" /><input
type="hidden" name="RelayState" value="12345" />

```

- i. Save the SAMLResponse from the hidden field:

```
export SAMLResponse='PHNhbWxwOlJlc3Bvb3N...1scDpSZXNwb25zZT4='
```

- j. Using the saved SAMLResponse, make a StorageGRID/api/saml-response request to generate a StorageGRID authentication token.

For RelayState, use the tenant account ID or use 0 if you want to sign in to the Grid Management API.

```

curl -X POST "https://$STORAGEGRID_ADDRESS:443/api/saml-response" \
-H "accept: application/json" \
--data-urlencode "SAMLResponse=$SAMLResponse" \
--data-urlencode "RelayState=$TENANTACCOUNTID" \
| python -m json.tool

```

The response includes the authentication token.

```
{
  "apiVersion": "3.0",
  "data": "56eb07bf-21f6-40b7-af0b-5c6cacfb25e7",
  "responseTime": "2018-11-07T21:32:53.486Z",
  "status": "success"
}
```

k. Save the authentication token in the response as MYTOKEN.

```
export MYTOKEN="56eb07bf-21f6-40b7-af0b-5c6cacfb25e7"
```

You can now use MYTOKEN for other requests, similar to how you would use the API if SSO was not being used.

### Sign out of the API if single sign-on is enabled

If single sign-on (SSO) has been enabled, you must issue a series of API requests to sign out of the Grid Management API or the Tenant Management API. These instructions apply if you are using Active Directory as the SSO identity provider

#### About this task

If required, you can sign out of the StorageGRID API simply by logging out from your organization's single logout page. Or, you can trigger single logout (SLO) from StorageGRID, which requires a valid StorageGRID bearer token.

#### Steps

1. To generate a signed logout request, pass cookie "sso=true" to the SLO API:

```
curl -k -X DELETE "https://$STORAGEGRID_ADDRESS/api/v3/authorize" \
-H "accept: application/json" \
-H "Authorization: Bearer $MYTOKEN" \
--cookie "sso=true" \
| python -m json.tool
```

A logout URL is returned:

```
{
  "apiVersion": "3.0",
  "data":
  "https://adfs.example.com/adfs/ls/?SAMLRequest=fZDNboMwEIRfhZ...HcQ%3D%3D",
  "responseTime": "2018-11-20T22:20:30.839Z",
  "status": "success"
}
```

## 2. Save the logout URL.

```
export LOGOUT_REQUEST
='https://adfs.example.com/adfs/ls/?SAMLRequest=fZDNboMwEIRfhZ...HcQ%3D%3D'
```

## 3. Send a request to the logout URL to trigger SLO and to redirect back to StorageGRID.

```
curl --include "$LOGOUT_REQUEST"
```

The 302 response is returned. The redirect location is not applicable to API-only logout.

```
HTTP/1.1 302 Found
Location: https://$STORAGEGRID_ADDRESS:443/api/saml-logout?SAMLResponse=fVLLasMwEPwVo7ss%...%23rsa-sha256
Set-Cookie: MSISSignoutProtocol=U2FtbA==; expires=Tue, 20 Nov 2018 22:35:03 GMT; path=/adfs; HttpOnly; Secure
```

## 4. Delete the StorageGRID bearer token.

Deleting the StorageGRID bearer token works the same way as without SSO. If cookie "sso=true" is not provided, the user is logged out of StorageGRID without affecting the SSO state.

```
curl -X DELETE "https://$STORAGEGRID_ADDRESS/api/v3/authorize" \
-H "accept: application/json" \
-H "Authorization: Bearer $MYTOKEN" \
--include
```

A 204 No Content response indicates the user is now signed out.

```
HTTP/1.1 204 No Content
```



## Use the API if single sign-on is enabled (Azure)

If you have [configured and enabled single sign-on \(SSO\)](#) and you use Azure as the SSO provider, you can use two example scripts to obtain an authentication token that is valid for the Grid Management API or the Tenant Management API.

### Sign in to the API if Azure single sign-on is enabled

These instructions apply if you are using Azure as the SSO identity provider

#### What you'll need

- You know the SSO email address and password for a federated user who belongs to a StorageGRID user group.
- If you want to access the Tenant Management API, you know the tenant account ID.

#### About this task

To obtain an authentication token, you can use the following example scripts:

- The `storagegrid-ssoauth-azure.py` Python script
- The `storagegrid-ssoauth-azure.js` Node.js script

Both scripts are located in the StorageGRID installation files directory (`./rpms` for Red Hat Enterprise Linux or CentOS, `./debs` for Ubuntu or Debian, and `./vsphere` for VMware).

To write your own API integration with Azure, see the `storagegrid-ssoauth-azure.py` script. The Python script makes two requests to StorageGRID directly (first to get the SAMLRequest, and later to get the authorization token), and also calls the Node.js script to interact with Azure to perform the SSO operations.

SSO operations can be executed using a series of API requests, but doing so is not straightforward. The Puppeteer Node.js module is used to scrape the Azure SSO interface.

If you have a URL-encoding issue, you might see the error: `Unsupported SAML version`.

#### Steps

1. Install the required dependencies, as follows:
  - a. Install Node.js (see <https://nodejs.org/en/download/>).
  - b. Install the required Node.js modules (puppeteer and jsdom):

```
npm install -g <module>
```

2. Pass the Python script to the Python interpreter to run the script.

The Python script will then call the corresponding Node.js script to perform the Azure SSO interactions.

3. When prompted, enter values for the following arguments (or pass them in using parameters):
  - The SSO email address used to sign in to Azure
  - The address for StorageGRID
  - The tenant account ID, if you want to access the Tenant Management API
4. When prompted, enter the password and be prepared to provide an MFA authorization to Azure if

requested.

```
c:\Users\user\Documents\azure_sso>py storagegrid-azure-ssoauth.py --sso-email-address user@my-domain.com
--sg-address storagegrid.examp.e.com --tenant-account-id 0
Enter the user's SSO password:
*****

Watch for and approve a 2FA authorization request
*****

StorageGRID Auth Token: {'responseTime': '2021-10-04T21:30:48.807Z', 'status': 'success', 'apiVersion':
'3.4', 'data': '4807d93e-a3df-48f2-9680-906cd255979e'}
```



The script assumes MFA is done using Microsoft Authenticator. You might need to modify the script to support other forms of MFA (such as entering a code received via text message).

The StorageGRID authorization token is provided in the output. You can now use the token for other requests, similar to how you would use the API if SSO was not being used.

### Use the API if single sign-on is enabled (PingFederate)

If you have [configured and enabled single sign-on \(SSO\)](#) and you use PingFederate as the SSO provider, you must issue a series of API requests to obtain an authentication token that is valid for the Grid Management API or the Tenant Management API.

#### Sign in to the API if single sign-on is enabled

These instructions apply if you are using PingFederate as the SSO identity provider

#### What you'll need

- You know the SSO username and password for a federated user who belongs to a StorageGRID user group.
- If you want to access the Tenant Management API, you know the tenant account ID.

#### About this task

To obtain an authentication token, you can use one of the following examples:

- The `storagegrid-ssoauth.py` Python script, which is located in the StorageGRID installation files directory (`./rpms` for Red Hat Enterprise Linux or CentOS, `./debs` for Ubuntu or Debian, and `./vsphere` for VMware).
- An example workflow of curl requests.

The curl workflow might time out if you perform it too slowly. You might see the error: A valid SubjectConfirmation was not found on this Response.



The example curl workflow does not protect the password from being seen by other users.

If you have a URL-encoding issue, you might see the error: Unsupported SAML version.

### Steps

1. Select one of the following methods to obtain an authentication token:
  - Use the `storagegrid-ssoauth.py` Python script. Go to step 2.

- Use curl requests. Go to step 3.
2. If you want to use the `storagegrid-ssoauth.py` script, pass the script to the Python interpreter and run the script.

When prompted, enter values for the following arguments:

- The SSO method. You can enter any variation of “pingfederate” (PINGFEDERATE, pingfederate, and so on).
- The SSO username
- The domain where StorageGRID is installed. This field is not used for PingFederate. You can leave it blank or enter any value.
- The address for StorageGRID
- The tenant account ID, if you want to access the Tenant Management API.

```
python3 storagegrid-ssoauth.py
sso_method: pingfederate
saml_user: my-sso-username
saml_domain:
sg_address: storagegrid.example.com
tenant_account_id: 12345
Enter the user's SAML password:
*****

*****
StorageGRID Auth Token: 56eb07bf-21f6-40b7-afob-5c6cacfb25e7
```

The StorageGRID authorization token is provided in the output. You can now use the token for other requests, similar to how you would use the API if SSO was not being used.

3. If you want to use curl requests, use the following procedure.
- a. Declare the variables needed to sign in.

```
export SAMLUSER='my-sso-username'
export SAMLPASSWORD='my-password'
export TENANTACCOUNTID='12345'
export STORAGEGRID_ADDRESS='storagegrid.example.com'
```



To access the Grid Management API, use 0 as TENANTACCOUNTID.

- b. To receive a signed authentication URL, issue a POST request to `/api/v3/authorize-saml`, and remove the additional JSON encoding from the response.

This example shows a POST request for a signed authentication URL for TENANTACCOUNTID. The results will be passed to `python -m json.tool` to remove the JSON encoding.

```
curl -X POST "https://$STORAGEGRID_ADDRESS/api/v3/authorize-saml" \
  -H "accept: application/json" -H "Content-Type: application/json" \
  --data "{\"accountId\": \"$TENANTACCOUNTID\"}" | python -m
json.tool
```

The response for this example includes a signed URL that is URL-encoded, but it does not include the additional JSON-encoding layer.

```
{
  "apiVersion": "3.0",
  "data": "https://my-pf-baseurl/ldap/SSO.saml2?...",
  "responseTime": "2018-11-06T16:30:23.355Z",
  "status": "success"
}
```

- c. Save the SAMLRequest from the response for use in subsequent commands.

```
export SAMLREQUEST="https://my-pf-baseurl/ldap/SSO.saml2?..."
```

- d. Export the response and cookie, and echo the response:

```
RESPONSE=$(curl -c - "$SAMLREQUEST")
```

```
echo "$RESPONSE" | grep 'input type="hidden" name="pf.adapterId"
id="pf.adapterId"'
```

- e. Export the 'pf.adapterId' value, and echo the response:

```
export ADAPTER='myAdapter'
```

```
echo "$RESPONSE" | grep 'base'
```

- f. Export the 'href' value (remove the trailing slash /), and echo the response:

```
export BASEURL='https://my-pf-baseurl'
```

```
echo "$RESPONSE" | grep 'form method="POST"'
```

g. Export the 'action' value:

```
export SSOPING='/idp/.../resumeSAML20/idp/SSO.ping'
```

h. Send cookies along with credentials:

```
curl -b <(echo "$RESPONSE") -X POST "$BASEURL$SSOPING" \
--data "pf.username=$SAMLUSER&pf.pass=$SAMPLPASSWORD&pf.ok=clicked&pf.cancel=&pf.adapterId=$ADAPTER"
--include
```

i. Save the SAMLResponse from the hidden field:

```
export SAMLResponse='PHNhbWxwOlJlc3BvbnN...1scDpSZXNwb25zZT4='
```

j. Using the saved SAMLResponse, make a StorageGRID/api/saml-response request to generate a StorageGRID authentication token.

For RelayState, use the tenant account ID or use 0 if you want to sign in to the Grid Management API.

```
curl -X POST "https://$STORAGEGRID_ADDRESS:443/api/saml-response" \
-H "accept: application/json" \
--data-urlencode "SAMLResponse=$SAMLResponse" \
--data-urlencode "RelayState=$TENANTACCOUNTID" \
| python -m json.tool
```

The response includes the authentication token.

```
{
  "apiVersion": "3.0",
  "data": "56eb07bf-21f6-40b7-af0b-5c6cacfb25e7",
  "responseTime": "2018-11-07T21:32:53.486Z",
  "status": "success"
}
```

k. Save the authentication token in the response as MYTOKEN.

```
export MYTOKEN="56eb07bf-21f6-40b7-af0b-5c6cacfb25e7"
```

You can now use MYTOKEN for other requests, similar to how you would use the API if SSO was not being used.

### Sign out of the API if single sign-on is enabled

If single sign-on (SSO) has been enabled, you must issue a series of API requests to sign out of the Grid Management API or the Tenant Management API. These instructions apply if you are using PingFederate as the SSO identity provider

#### About this task

If required, you can sign out of the StorageGRID API simply by logging out from your organization's single logout page. Or, you can trigger single logout (SLO) from StorageGRID, which requires a valid StorageGRID bearer token.

#### Steps

1. To generate a signed logout request, pass cookie "sso=true" to the SLO API:

```
curl -k -X DELETE "https://$STORAGEGRID_ADDRESS/api/v3/authorize" \
-H "accept: application/json" \
-H "Authorization: Bearer $MYTOKEN" \
--cookie "sso=true" \
| python -m json.tool
```

A logout URL is returned:

```
{
  "apiVersion": "3.0",
  "data": "https://my-ping-
url/idp/SLO.saml2?SAMLRequest=fZDNboMwEIRfhZ...HcQ%3D%3D",
  "responseTime": "2021-10-12T22:20:30.839Z",
  "status": "success"
}
```

2. Save the logout URL.

```
export LOGOUT_REQUEST='https://my-ping-
url/idp/SLO.saml2?SAMLRequest=fZDNboMwEIRfhZ...HcQ%3D%3D'
```

3. Send a request to the logout URL to trigger SLO and to redirect back to StorageGRID.

```
curl --include "$LOGOUT_REQUEST"
```

The 302 response is returned. The redirect location is not applicable to API-only logout.

```
HTTP/1.1 302 Found
Location: https://$STORAGEGRID_ADDRESS:443/api/saml-logout?SAMLResponse=fVLLasMwEPwVo7ss%...%23rsa-sha256
Set-Cookie: PF=QoKs...SgCC; Path=/; Secure; HttpOnly; SameSite=None
```

#### 4. Delete the StorageGRID bearer token.

Deleting the StorageGRID bearer token works the same way as without SSO. If cookie "sso=true" is not provided, the user is logged out of StorageGRID without affecting the SSO state.

```
curl -X DELETE "https://$STORAGEGRID_ADDRESS/api/v3/authorize" \
-H "accept: application/json" \
-H "Authorization: Bearer $MYTOKEN" \
--include
```

A 204 No Content response indicates the user is now signed out.

```
HTTP/1.1 204 No Content
```

## Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

## Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.