
OpenSDS Aruba POC Test Plan

June 2018

Revision: 0.3

Author: OpenSDS

Document Revision History

Version	Date	Comments
0.1	6/12/2018	Initial revision.
0.2	6/15/2018	Added content to sections host-based replication, array-based replication, CLI guide, Cinder compatible APIs.
0.3	6/20/2018	Modified dates after reviewing it at OSS Summit Tokyo

Related Documents

Author	Documents

Table of Contents

1	Overview.....	1
1.1	<i>Project Scope and Objectives.....</i>	1
1.2	<i>POC Timeline</i>	2
2	System requirements.....	2
2.1	<i>Hardware</i>	2
2.2	<i>Software.....</i>	2
2.2.1	<i>OS</i>	2
3	Features	3
4	Installation.....	4
4.1	<i>Prerequisite for the Kubernetes Environment</i>	4
4.1.1	<i>Packages.....</i>	4
4.1.2	<i>docker.....</i>	4
4.1.3	<i>Golang.....</i>	5
4.1.4	<i>Etcd.....</i>	5
4.1.5	<i>kubernetes local cluster.....</i>	5
4.2	<i>OpenSDS Deployment</i>	5
4.2.1	<i>Pre-config (Ubuntu 16.04).....</i>	6
4.2.2	<i>Install docker</i>	6
4.2.3	<i>Download opensds-installer code.....</i>	6
4.2.4	<i>Install ansible tool.....</i>	6
4.2.5	<i>Configure OpenSDS cluster variables.....</i>	7
4.2.5.1	<i>System environment</i>	7
4.2.5.2	<i>LVM.....</i>	7
4.2.5.3	<i>Ceph</i>	7
4.2.5.4	<i>Cinder.....</i>	8
4.2.6	<i>Check if the hosts can be reached.....</i>	9
4.2.7	<i>Run opensds-ansible playbook to start deploy</i>	9
4.3	<i>Test OpenSDS.....</i>	9
4.3.1	<i>Use OpenSDS CLI Tool.....</i>	9

4.3.2	Test CSI Plugin	10
4.3.3	OpenSDS Dashboard.....	11
4.4	<i>Cleanup OpenSDS</i>	11
4.4.1	Run opensds-ansible playbook to clean the environment.....	11
4.4.2	Run ceph-ansible playbook to clean ceph cluster if ceph is deployed.....	11
4.4.3	Remove ceph-ansible source code (optional)	11
4.5	<i>Troubleshooting</i>	11
4.5.1	Problem Starting CSI Plugin.....	11
5	Use Cases	12
5.1	<i>Multitenancy using Keystone and Dashboard</i>	13
5.1.1	Admin	13
5.1.2	Tenant.....	13
5.2	<i>Kubernetes</i>	13
5.3	<i>OpenStack</i>	14
5.3.1	Test Cinder Compatible API.....	14
5.3.1.1	<i>Installation</i>	14
5.3.1.2	<i>Volume Types</i>	15
5.3.1.2.1	List all volume types (default policy)	15
	<i>cinder type-list</i>	15
5.3.1.2.2	Delete a volume type	15
	<i>cinder type-delete</i>	15
5.3.1.2.3	List all volume types(0).....	15
5.3.1.2.4	Create a volume type	16
5.3.1.2.5	Show volume type detail	16
5.3.1.2.6	Create a volume type (2nd)	16
5.3.1.2.7	List all volume types (2).....	16
5.3.1.2.8	Update an encryption type.....	17
	<i>cinder type-update 7abff35e-0cbb-4c48-8bab-4fe7c3286792 --name type0 --description test_type_0 --is-public true</i>	17
5.3.1.2.9	Lists current volume types and extra specs.....	17
5.3.1.2.10	Create or update extra specs for volume type.....	18
5.3.1.2.11	Delete extra specification for volume type	18
5.3.1.3	<i>Volumes</i>	18
5.3.1.3.1	List accessible volumes with details (0)	18

5.3.1.3.2	Create a volume (1st)	19
5.3.1.3.3	List accessible volumes with details (1)	19
5.3.1.3.4	Show a volume's details	19
5.3.1.3.5	Delete a volume.....	19
5.3.1.4	<i>Snapshots</i>	19
5.3.1.4.1	Create a snapshot	20
5.3.1.4.2	List snapshots and details.....	20
5.3.1.4.3	Show a snapshot's details	20
5.3.1.4.4	Delete a snapshot.....	20
5.3.1.5	<i>Attachments</i>	20
5.3.1.5.1	Create attachment	20
5.3.1.5.2	Show attachment.....	20
5.3.1.5.3	List attachment	21
5.3.1.5.4	Update attachment.....	21
5.3.1.5.5	Delete attachment.....	22
5.4	<i>Array-based Replication using Dorado</i>	23
5.4.1	Without Kubernetes	23
5.4.1.1	<i>Configuration</i>	23
5.4.1.2	<i>Testing</i>	26
5.4.2	With Kubernetes.....	29
5.5	<i>Host-based Replication using DRBD</i>	29
5.5.1	Prepare	29
5.5.2	Install DRBD	29
5.5.3	Configuration	29
5.5.4	Create Replication	30
5.5.5	Check result	31
6	OpenSDS CLI Guide	32
6.1	<i>List Docks</i>	32
6.2	<i>List Pools</i>	33
6.3	<i>Create/Delete Profile</i>	34
6.4	<i>Create/Delete/Get/List Volume(s)</i>	35
6.5	<i>Create/Delete/Get/List Snapshot(s)</i>	37
6.6	<i>Create Volume from Snapshot</i>	39
6.7	<i>Expand Volume</i>	40


6.8	<i>Create/Delete/Get/List Volume Groups.....</i>	41
6.9	<i>Replication</i>	43

1 Overview

OpenSDS Aruba will be released in the week of June 27, 2018. This document serves as the OpenSDS Aruba POC Test Plan. It covers the following topics:

1. Overall project scope and objectives
2. Test objectives and success criteria
3. Test resources required
4. Test schedule
5. Use cases
 - a. OpenStack/Kubernetes/bare-metal/mixed environment provisioning
 - b. Host and storage replication, and local and remote replication
 - c. Test cases for each use case

1.1 Project Scope and Objectives



In the Zealand release, basic volume and snapshot CRUD functionalities were added and Kubernetes CSI/FlexVolume support was also added.

During the Aruba release, the focus has been on storage orchestration, building advanced automated storage and data services across traditional data centers, private and public clouds. Functionalities in this release include basic OpenStack integration, integrating with Keystone for identity service, array-based and host-based replication, and storage profiles design based on Swordfish. A deployment tool using Ansible is also available to install OpenSDS with Keystone and Dashboard.

1.2 POC Timeline

June 15: POC plan draft ready for EUAC review

June 20: Aruba release. POC plan approval.

July 1-31: POC testing

August 7: POC results/comments/testimonials

2 System requirements

2.1 Hardware

The hardware requirements are described in this section.

For array-based replication, two physical servers and two Dorado arrays are needed.

For host-based replication, two physical servers are needed.

For other tests described in this POC, one physical server or one VM can be used for basic testing.

2.2 Software

The software requirements are described in this section.

2.2.1 OS

Ubuntu 16.04.2 has been used during the testing and therefore should be used in this POC:

```
root@proxy:~# cat /etc/issue
Ubuntu 16.04.2 LTS \n \l
```


For host-based replication, required DRBD software is described in the relevant section later. Other required software is described in the installation section.

3 Features

Features to be tested include the following:

- Multitenancy using Keystone
- Create/delete volume
- Expand volume
- Create/delete snapshot
- Create volume from snapshot
- Create volume group
- Create/delete profile
- Array-based replication
- Host-based replication
- Use Cinder-compatible API in OpenStack

Supported storage backends include the following:

- LVM
- Ceph
- Dorado
- IBM storage via Cinder driver?
- Cinder stand alone with LVM
- Cinder in an OpenStack deployment with LVM

Supported protocols:

- iSCSI

- FC
- RBD

Testing environment includes the following:

- OpenSDS with Kubernetes
- OpenSDS with OpenStack (full OpenStack deployment or Cinder stand-alone)
- Hotpot only on bare-metal or a VM

4 Installation

In the section, how to install OpenSDS using Ansible playbook will be discussed. If you are testing OpenSDS with Kubernetes, read section 4.1 *Prerequisite for the Kubernetes Environment* first. Otherwise, go to section 4.2 directly.

4.1 Prerequisite for the Kubernetes Environment

4.1.1 Packages

Install following packages:

```
apt-get install vim git curl make gcc zip
```

4.1.2 docker

Install docker:

```
curl -sSL https://get.docker.com/ | sh
```

Version information:

```
root@proxy:~# docker version
Client:
 Version:      18.05.0-ce
 API version:  1.37
 Go version:   go1.9.5
 Git commit:   f150324
 Built:        Wed May  9 22:16:25 2018
 OS/Arch:      linux/amd64
 Experimental: false
 Orchestrator: swarm

Server:
 Engine:
```

```
Version:      18.05.0-ce
API version:  1.37 (minimum version 1.12)
Go version:   go1.9.5
Git commit:   f150324
Built:        Wed May  9 22:14:32 2018
OS/Arch:      linux/amd64
Experimental: false
```

4.1.3 Golang

Check golang version information:

```
root@proxy:~# go version
go version go1.9.2 linux/amd64
```

You can install golang by executing commands blow:

```
wget https://storage.googleapis.com/golang/go1.9.2.linux-amd64.tar.gz
tar -C /usr/local -xzf go1.9.2.linux-amd64.tar.gz
echo 'export PATH=$PATH:/usr/local/go/bin' >> /etc/profile
echo 'export GOPATH=$HOME/gopath' >> /etc/profile
source /etc/profile
```

4.1.4 Etcd

You can install etcd by executing commands blow:

```
cd $HOME
wget https://github.com/coreos/etcd/releases/download/v3.3.0/etcd-v3.3.0-
linux-amd64.tar.gz
tar -xzf etcd-v3.3.0-linux-amd64.tar.gz
cd etcd-v3.3.0-linux-amd64
sudo cp -f etcd etcdctl /usr/local/bin/
```

4.1.5 kubernetes local cluster

You can start the latest k8s local cluster by executing commands blow:

```
cd $HOME
git clone https://github.com/kubernetes/kubernetes.git
cd $HOME/kubernetes
git checkout v1.10.0
make
echo alias kubectl='$HOME/kubernetes/cluster/kubectl.sh' >> /etc/profile
ALLOW_PRIVILEGED=true
FEATURE_GATES=CSIPersistentVolume=true,MountPropagation=true
RUNTIME_CONFIG="storage.k8s.io/v1alpha1=true" LOG_LEVEL=5 hack/local-up-
cluster.sh
```

4.2 OpenSDS Deployment

In this section, the steps to deploy an OpenSDS local cluster are described.

4.2.1 Pre-config (Ubuntu 16.04)

First download some system packages:

```
sudo apt-get install -y openssh-server git make gcc
```

Then config `/etc/ssh/sshd_config` file and change one line:

```
PermitRootLogin yes
```

Next generate ssh-token:

```
ssh-keygen -t rsa

ssh-copy-id -i ~/.ssh/id_rsa.pub <ip_address> # IP address of the target machine of the
installation
```

4.2.2 Install docker

If using a standalone cinder as the backend, install docker to run cinder service. See the docker installation document for details.

The following command can be used to install docker:

```
curl -sSL https://get.docker.com/ | sh
```

4.2.3 Download opensds-installer code

```
git clone https://github.com/opensds/opensds-installer.git

cd opensds-installer/ansible
```

4.2.4 Install ansible tool

To install ansible, run the commands below:

```
sudo add-apt-repository ppa:ansible/ansible # This step is needed to upgrade ansible to
version 2.4.2 which is required for the "include_tasks" ansible command.

sudo apt-get update

sudo apt-get install ansible

ansible --version # Ansible version 2.4.2 or higher is required.
```

4.2.5 Configure OpenSDS cluster variables

4.2.5.1 System environment

To integrate OpenSDS with cloud platform (for example k8s), modify `nbp_plugin_type` variable in `group_vars/common.yml`:

```
nbp_plugin_type: hotpot_only # hotpot_only is the default integration method. Other
available options are 'csi' and 'flexvolume'.
```

Note: If 'csi' is the selected `nbp_plugin_type`, make sure section 3.1 *Prerequisite for the Kubernetes Environment* is followed before proceeding.

Change `opensds_endpoint` to the actual IP address:

```
opensds_endpoint: http://127.0.0.1:50040 # The IP (127.0.0.1) should be replaced with
the opensds actual endpoint IP
```

4.2.5.2 LVM

If `lvm` is chosen as the storage backend, there is no need to modify `group_vars/osdsdock.yml` because it is the default choice:

```
enabled_backend: lvm # Change it according to the chosen backend. Supported backends
include 'lvm', 'ceph', and 'cinder'
```

Change `tgtBindIp` variable in `group_vars/lvm/lvm.yml` to your real host IP address.

```
tgtBindIp: 127.0.0.1 # change tgtBindIp to your real host ip, run 'ifconfig' to check
```

4.2.5.3 Ceph

If `ceph` is chosen as storage backend, modify `group_vars/osdsdock.yml`:

```
enabled_backend: ceph # Change it according to the chosen backend. Supported backends
include 'lvm', 'ceph', and 'cinder'.
```

```
ceph_pools: # Specify pool name randomly if choosing ceph
```

```
- rbd
```

```
#- ssd
```

```
#- sas
```

Modify `group_vars/ceph/ceph.yaml`, change pool name to be the same as `ceph_pool_name`. But if you enable multiple pools, please append the current pool format:

```
"rbd" # change pool name to be the same as ceph pool
```

Configure two files under `group_vars/ceph`: `all.yaml` and `osds.yaml`. Here is an example:

`group_vars/ceph/all.yaml`:

```
ceph_origin: repository

ceph_repository: community

ceph_stable_release: luminous # Choose luminous as default version

public_network: "192.168.3.0/24" # Run 'ip -4 address' to check the ip address

cluster_network: "{{ public_network }}"

monitor_interface: eth1 # Change to the network interface on the target machine
```

`group_vars/ceph/osds.yaml`:

```
devices: # For ceph devices, append ONE or MULTIPLE devices like the example below:

  - '/dev/sda' # Ensure this device exists and available if ceph is chosen

  - '/dev/sdb' # Ensure this device exists and available if ceph is chosen

osd_scenario: colocated
```

4.2.5.4 Cinder

If cinder is chosen as storage backend, modify `group_vars/osdsdock.yaml`:

```
enabled_backend: cinder # Change it according to the chosen backend. Supported backends
include 'lvm', 'ceph', and 'cinder'

# Use block-box install cinder_standalone if true, see details in:

use_cinder_standalone: true

# If true, you can configure cinder_container_platform, cinder_image_tag,

# cinder_volume_group.
```

```
# Default: debian:stretch, and ubuntu:xenial, centos:7 is also supported.

cinder_container_platform: debian:stretch

# The image tag can be arbitrarily modified, as long as follow the image naming
# conventions, default: debian-cinder

cinder_image_tag: debian-cinder

# The cinder standalone use lvm driver as default driver, therefore `volume_group`
# should be configured, the default is: cinder-volumes. The volume group will be
# removed when use ansible script clean environment.

cinder_volume_group: cinder-volumes
```

Configure the auth and pool options to access cinder in `group_vars/cinder/cinder.yaml`. Do not need to make additional configure changes if using cinder standalone.

4.2.6 Check if the hosts can be reached

```
sudo ansible all -m ping -i local.hosts
```

4.2.7 Run opensds-ansible playbook to start deploy

```
sudo ansible-playbook site.yml -i local.hosts
```

4.3 Test OpenSDS

4.3.1 Use OpenSDS CLI Tool

Configure OpenSDS CLI tool:

```
cd $GOPATH/src/github.com/opensds/opensds && sudo cp build/out/bin/osdsctl
/usr/local/bin

export OPENSDDS_ENDPOINT=http://{your_real_host_ip}:50040

export OPENSDDS_AUTH_STRATEGY=noauth
```

```
osdsctl pool list # Check if the pool resource is available
```

Create a default profile:

```
osdsctl profile create '{"name": "default", "description": "default policy"}'
```

Create a volume:

```
osdsctl volume create 1 --name=test-001
```

For cinder, az needs to be specified.

```
osdsctl volume create 1 --name=test-001 --az nova
```

List all volumes:

```
osdsctl volume list
```

Delete the volume:

```
osdsctl volume delete <your_volume_id>
```

4.3.2 Test CSI Plugin

After running the ansible deployment tool in “csi” mode, three CSI plugin pods can be found by `kubectl get pods` like below:

- csi-provisioner-opensdsplugin
- csi-attacher-opensdsplugin
- csi-nodeplugin-opensdsplugin

More design details about CSI can be found from [CSI Volume Plugins in Kubernetes Design Doc](#).

To test the OpenSDS CSI plugin, create an example nginx application:

```
kubectl create -f csi/server/examples/kubernetes/nginx.yaml
```

This will create an OpenSDS volume and mount the volume at `/var/lib/www/html`.

Use the following command to inspect the nginx container to verify it.

```
docker exec -it <nginx container id> /bin/bash
```

Clean up example nginx application by the following commands:

```
kubectl delete -f csi/server/examples/kubernetes/nginx.yaml
```


4.3.3 OpenSDS Dashboard

Log into the dashboard using the default admin credentials: admin/opensds@123. Create tenant, user, and profiles as admin.

Log out of the dashboard as admin and log into the dashboard as a non-admin user to create volume, snapshot, expand volume, create volume from snapshot, create volume group.

4.4 Cleanup OpenSDS

4.4.1 Run opensds-ansible playbook to clean the environment

```
sudo ansible-playbook clean.yml -i local.hosts
```

This should clean up hotpot as well as nbp (including the CSI plugin).

4.4.2 Run ceph-ansible playbook to clean ceph cluster if ceph is deployed

```
cd /opt/ceph-ansible
```

```
sudo ansible-playbook infrastructure-playbooks/purge-cluster.yml -i ceph.hosts
```

In addition, clean up the logical partition on the physical block device used by ceph, using the `fdisk` tool.

4.4.3 Remove ceph-ansible source code (optional)

```
cd ..
```

```
sudo rm -rf /opt/ceph-ansible
```

4.5 Troubleshooting

4.5.1 Problem Starting CSI Plugin

If the CSI plugin cannot be started, check if OpenSDS endpoint IP is configured.

```
vi csi/server/deploy/kubernetes/csi-configmap-opensdsplugin.yaml
```

The IP (127.0.0.1) should be replaced with the opensds actual endpoint IP.

```
kind: ConfigMap

apiVersion: v1

metadata:

name: csi-configmap-opensdsplugin

data:

opensdsendpoint: http://127.0.0.1:50040
```

Manually create OpenSDS CSI pods:

```
kubectl create -f csi/server/deploy/kubernetes
```

After this, three pods can be found by `kubectl get pods` like below:

- csi-provisioner-opensdsplugin
- csi-attacher-opensdsplugin
- csi-nodeplugin-opensdsplugin

To test the OpenSDS CSI plugin, create an example nginx application:

```
kubectl create -f csi/server/examples/kubernetes/nginx.yaml
```

This will mount an OpenSDS volume into `/var/lib/www/html`.

Use the following command to inspect the nginx container to verify it.

```
docker exec -it <nginx container id> /bin/bash
```

Clean up example nginx application and opensds CSI pods by the following commands.

```
kubectl delete -f csi/server/examples/kubernetes/nginx.yaml

kubectl delete -f csi/server/deploy/kubernetes
```

5 Use Cases

5.1 Multitenancy using Keystone and Dashboard

5.1.1 Admin

Log into dashboard as admin. Password is opensds@123.

- Check Resource tab
- Go to Identity tab and Create two tenants (tenant1 and tenant2)
- Create a user (user1) to be in the tenant1 group created above
- Create a second user (user2) to be in the tenant2 group created above
- Go to Profile tab and Create a profile

5.1.2 Tenant

Log in as non-admin user1 using credentials created above.

- Go to Volume tab. Create a volume using the profile created earlier.
- Create snapshot
- Expand the volume
- View volume details
- Create a volume from the snapshot
- Create a volume group

Log out and log in as non-admin user2 and verify that user2 cannot view volumes created by user1 because they belong to different tenant groups.

5.2 Kubernetes

Kubernetes cluster runs on baremetal or VM using OpenSDS to provision storage, using the following drivers:

- Native LVM driver
- Native Ceph driver
- Native Dorado driver
- Cinder driver with Cinder stand-alone (LVM by default)

Refer to the *Installation* section to see how to use the OpenSDS CSI plugin to provision storage for Kubernetes.

5.3 OpenStack

There are two ways for OpenSDS to integrate with OpenStack.

- OpenSDS provisions storage through the southbound Cinder driver. Cinder can be Cinder stand-alone or part of an OpenStack deployment. See the Installation section on how to install OpenSDS to test with Cinder driver.
- OpenSDS provisions storage in an OpenStack deployment through the Cinder compatible API. It can be southbound native driver or Cinder driver below OpenSDS in this case.

5.3.1 Test Cinder Compatible API

Cinder Compatible API adapter is not built in as part of the ansible deployment tool. Follow the following instruction to install it.

5.3.1.1 Installation

1. The Cinder Compatible API only supports cinder's current Api(v3). You can use devstack to install cinder when testing, but in order to use cinder's current Api(v3), branch for devstack must be stable/queens.
2. When devstack is installed, kill all cinder processes.
3. Run the "source /opt/stack/devstack/openrc admin admin" command to execute the openstack's cli command.
4. Run the "openstack endpoint list" command to view the cinder endpoint.
5. Run the command "export CINDER_ENDPOINT=http://10.10.10.10:8776/v3". The actual value of CINDER_ENDPOINT is determined by the previous step.
6. Run the command export OPENSDDS_ENDPOINT=http://127.0.0.1:50040.
7. Download the opensds source (<https://github.com/opensds/opensds.git>) and install opensds.
8. Run the command "go build -o ./build/out/bin/cindercompatibleapi github.com/opensds/opensds/contrib/cindercompatibleapi".
9. Execute the command "./build/out/bin/cindercompatibleapi".

10. Execute some cinder cli commands to see if the result is correct. For example, if you execute the command "cinder type-list", the results will show the profile of opensds.

5.3.1.2 Volume Types

5.3.1.2.1 List all volume types (default policy)

cinder type-list

```
root@openstack:~# cinder type-list
+-----+-----+-----+-----+
| ID                | Name   | Description | Is_Public |
+-----+-----+-----+-----+
| 02e50100-e2b5-499e-a938-9b2a5f079c9c | default | default policy | True      |
+-----+-----+-----+-----+

2018/05/07 09:31:31.659 [0] 192.168.56.104 - - [07/May/2018 09:31:31] "GET /v3/28e79796cfd84db294a756b90b8d845f/types?is_public=None HTTP/1.1 200 0" 0.003206 python-cinderclient
```

5.3.1.2.2 Delete a volume type

cinder type-delete

```
root@openstack:~# cinder type-list
+-----+-----+-----+-----+
| ID                | Name   | Description | Is_Public |
+-----+-----+-----+-----+
| 02e50100-e2b5-499e-a938-9b2a5f079c9c | default | default policy | True      |
+-----+-----+-----+-----+
root@openstack:~#
root@openstack:~# cinder type-delete 02e50100-e2b5-499e-a938-9b2a5f079c9c
Request to delete volume type 02e50100-e2b5-499e-a938-9b2a5f079c9c has been accepted.
root@openstack:~#

2018/05/07 09:34:45.736 [0] 192.168.56.104 - - [07/May/2018 09:34:45] "DELETE /v3/28e79796cfd84db294a756b90b8d845f/types/02e50100-e2b5-499e-a938-9b2a5f079c9c HTTP/1.1 200 0" 0.003395 python-cinderclient
```

5.3.1.2.3 List all volume types(0)

cinder type-list

```
root@openstack:~# cinder type-list
+-----+-----+-----+-----+
| ID | Name | Description | Is_Public |
+-----+-----+-----+-----+
+-----+-----+-----+-----+

2018/05/07 09:37:28.842 [0] 192.168.56.104 - - [07/May/2018 09:37:28] "GET /v3/28e79796cfd84db294a756b90b8d845f/types?is_public=None HTTP/1.1 200 0" 0.002610 python-cinderclient
```

5.3.1.2.4 Create a volume type

cinder type-create type00 --description test_type_00

```
root@openstack:~# cinder type-create type00 --description test_type_00
+-----+-----+-----+-----+
| ID                               | Name   | Description | Is_Public |
+-----+-----+-----+-----+
| 7abff35e-0cbb-4c48-8bab-4fe7c3286792 | type00 | test_type_00 | True      |
+-----+-----+-----+-----+
root@openstack:~#
```

```
2018/05/07 09:38:10.991 [0] 192.168.56.104 - - [07/May/2018 09:38:10] "POST /v3/28e79796cfd84db294a756b90b8d845f/types HTTP/1.1 200 0" 0.002892 python-cinderclient
```

5.3.1.2.5 Show volume type detail

cinder type-show Id

```
root@openstack:~# cinder type-show 7abff35e-0cbb-4c48-8bab-4fe7c3286792
+-----+-----+
| Property | Value |
+-----+-----+
| description | test_type_00 |
| extra_specs | None |
| id | 7abff35e-0cbb-4c48-8bab-4fe7c3286792 |
| is_public | True |
| name | type00 |
+-----+-----+
```

```
2018/05/07 09:39:45.513 [0] 192.168.56.104 - - [07/May/2018 09:39:45] "GET /v3/28e79796cfd84db294a756b90b8d845f/types/7abff35e-0cbb-4c48-8bab-4fe7c3286792 HTTP/1.1 200 0" 0.002401 python-cinderclient
```

5.3.1.2.6 Create a volume type (2nd)

cinder type-create type01 --description test_type_01

```
root@openstack:~# cinder type-create type01 --description test_type_01
+-----+-----+-----+-----+
| ID                               | Name   | Description | Is_Public |
+-----+-----+-----+-----+
| 8ddce5f5-03a1-4397-9d82-5e002a2742cd | type01 | test_type_01 | True      |
+-----+-----+-----+-----+
root@openstack:~#
```

```
2018/05/07 09:41:48.712 [0] 192.168.56.104 - - [07/May/2018 09:41:48] "POST /v3/28e79796cfd84db294a756b90b8d845f/types HTTP/1.1 200 0" 0.003471 python-cinderclient
```

5.3.1.2.7 List all volume types (2)

cinder type-list

```
root@openstack:~# cinder type-list
```

ID	Name	Description	Is_Public
7abff35e-0cbb-4c48-8bab-4fe7c3286792	type00	test_type_00	True
8ddce5f5-03a1-4397-9d82-5e002a2742cd	type01	test_type_01	True

```
2018/05/07 09:42:42.333 [0] 192.168.56.104 - - [07/May/2018 09:42:42] "GET /v3/28e79796cfd84db294a756b90b0d845f/types?is_public=None HTTP/1.1 200 0" 0.003555 python-cinderclient
```

5.3.1.2.8 Update an encryption type

cinder type-update 7abff35e-0cbb-4c48-8bab-4fe7c3286792 --name type0 --description test_type_0 --is-public true

```
root@openstack:~# cinder type-update 7abff35e-0cbb-4c48-8bab-4fe7c3286792 --name type0 --description test_type_0 --is-public true
```

ID	Name	Description	Is_Public
7abff35e-0cbb-4c48-8bab-4fe7c3286792	type0	test_type_0	True

```
2018/05/07 09:47:33.650 [0] 192.168.56.104 - - [07/May/2018 09:47:33] "PUT /v3/28e79796cfd84db294a756b90b0d845f/types/7abff35e-0cbb-4c48-8bab-4fe7c3286792 HTTP/1.1 200 0" 0.003619 python-cinderclient
```

If `is-public` is not set, `false` is the default which is not supported by opensds:

```
root@openstack:~# cinder type-update 7abff35e-0cbb-4c48-8bab-4fe7c3286792 --name type0 --description test_type_0
ERROR: Update a volume type failed: OpenSDS does not support is_public = false (HTTP 400)
```

```
2018/05/07 09:46:35.930 [0] 192.168.56.104 - - [07/May/2018 09:46:35] "PUT /v3/28e79796cfd84db294a756b90b0d845f/types/7abff35e-0cbb-4c48-8bab-4fe7c3286792 HTTP/1.1 400 0" 0.000870 python-cinderclient
```

5.3.1.2.9 Lists current volume types and extra specs.

cinder extra-specs-list

```
root@openstack:~# cinder type-list
```

ID	Name	Description	Is_Public
7abff35e-0cbb-4c48-8bab-4fe7c3286792	type0	test_type_0	True
8ddce5f5-03a1-4397-9d82-5e002a2742cd	type01	test_type_01	True

```
root@openstack:~# cinder extra-specs-list
```

ID	Name	extra_specs
7abff35e-0cbb-4c48-8bab-4fe7c3286792	type0	-
8ddce5f5-03a1-4397-9d82-5e002a2742cd	type01	-

```
2018/05/07 09:57:14.497 [0] 192.168.56.104 - - [07/May/2018 09:57:14] "GET /v3/28e79796cfd84db294a756b90b0d845f/types?is_public=None HTTP/1.1 200 0" 0.002168 python-cinderclient
```

```
2018/05/07 09:57:40.984 [0] 192.168.56.104 - - [07/May/2018 09:57:40] "GET /v3/28e79796cfd84db294a756b90b0d845f/types?is_public=None HTTP/1.1 200 0" 0.002751 python-cinderclient
```

5.3.1.2.10 Create or update extra specs for volume type

cinder type-key 7abff35e-0cbb-4c48-8bab-4fe7c3286792 set key1=value1

```
root@openstack:~# cinder type-key 7abff35e-0cbb-4c48-8bab-4fe7c3286792 set key1=value1
root@openstack:~# cinder extra-specs-list
```

ID	Name	extra_specs
7abff35e-0cbb-4c48-8bab-4fe7c3286792	type0	{'key1': 'value1'}
8ddce5f5-03a1-4397-9d82-5e002a2742cd	type01	-

```
2018/05/07 10:09:53.361 [D] 192.168.56.104 - - [07/May/2018 10:09:53] "POST /v3/28e79796cf804db294a756b90bd845f/types/7abff35e-0cbb-4c48-8bab-4fe7c3286792/extra_specs HTTP/1.1 200 0" 0.003180 python-cinderclient
```

5.3.1.2.11 Delete extra specification for volume type

cinder type-key 7abff35e-0cbb-4c48-8bab-4fe7c3286792 unset key1

```
root@openstack:~# cinder extra-specs-list
```

ID	Name	extra_specs
7abff35e-0cbb-4c48-8bab-4fe7c3286792	type0	{'key1': 'value1'}
8ddce5f5-03a1-4397-9d82-5e002a2742cd	type01	-

```
root@openstack:~# cinder type-key 7abff35e-0cbb-4c48-8bab-4fe7c3286792 unset key1
root@openstack:~# cinder extra-specs-list
```

ID	Name	extra_specs
7abff35e-0cbb-4c48-8bab-4fe7c3286792	type0	-
8ddce5f5-03a1-4397-9d82-5e002a2742cd	type01	-

```
2018/05/07 10:14:44.450 [D] 192.168.56.104 - - [07/May/2018 10:14:44] "DELETE /v3/28e79796cf804db294a756b90bd845f/types/7abff35e-0cbb-4c48-8bab-4fe7c3286792/extra_specs/key1 HTTP/1.1 200 0" 0.002390 python-cinderclient
```

5.3.1.3 Volumes

5.3.1.3.1 List accessible volumes with details (0)

cinder list

```
root@openstack:~# cinder list
```

ID	Status	Name	Size	Volume Type	Bootable	Attached to
----	--------	------	------	-------------	----------	-------------

```
root@openstack:~#
```


5.3.1.3.2 Create a volume (1st)

cinder create 1 --name volume00

```
root@openstack:~# cinder create 1 --name volume00
+-----+-----+
| Property | Value |
+-----+-----+
| attachments | [] |
| availability_zone | default |
| created_at | 2018-05-07T10:44:55 |
| description | |
| id | de54b33f-8d66-45b6-887c-0c9acfe56dc7 |
| metadata | {} |
| name | volume00 |
| size | 1 |
| status | creating |
| updated_at | |
| user_id | |
+-----+-----+
```

```
2018/05/07 10:44:55.174 [D] 192.168.56.184 - - [07/May/2018 10:44:55] "POST /v3/28e79796cfd84db294a756b90b8d845f/volumes HTTP/1.1 202 0" 0.004293 python-cinderclient
2018/05/07 10:44:55.178 [D] 192.168.56.184 - - [07/May/2018 10:44:55] "GET /v3/28e79796cfd84db294a756b90b8d845f/volumes/de54b33f-8d66-45b6-887c-0c9acfe56dc7 HTTP/1.1 200 0" 0.001601 python-cinderclient
```

5.3.1.3.3 List accessible volumes with details (1)

cinder list

```
root@openstack:~# cinder list
+-----+-----+-----+-----+-----+
| ID | Status | Name | Size | Attached to |
+-----+-----+-----+-----+-----+
| de54b33f-8d66-45b6-887c-0c9acfe56dc7 | creating | volume00 | 1 | |
+-----+-----+-----+-----+-----+
```

```
2018/05/07 10:46:07.854 [D] 192.168.56.184 - - [07/May/2018 10:46:07] "GET /v3/28e79796cfd84db294a756b90b8d845f/volumes/detail HTTP/1.1 200 0" 0.002999 python-cinderclient
```

5.3.1.3.4 Show a volume's details

cinder show <volume uuid>

5.3.1.3.5 Delete a volume

cinder delete <volume uuid>

5.3.1.4 Snapshots

5.3.1.4.1 Create a snapshot

cinder snapshot-create <volume uuid>

5.3.1.4.2 List snapshots and details

cinder snapshot-list

```
root@ubuntu:~/gopath/src/github.com/opensds/opensds# cinder snapshot-list
```

ID	Volume ID	Status	Name	Size	User ID
b94acf3a-59cc-4117-8f94-7615eb9360e4	3c51e853-51dc-4cfd-b795-8bc9b57a0b79	available	snap-001	1	

5.3.1.4.3 Show a snapshot's details

cinder snapshot-show <snapshot uuid>

5.3.1.4.4 Delete a snapshot

cinder snapshot-delete <snapshot uuid>

5.3.1.5 Attachments**5.3.1.5.1 Create attachment**

cinder attachment-create

cinder results:

```
root@ubuntu:~/cinder_data_dir/cinder/contrib/block-box# cinder attachment-create ec555584-83a0-4aef-809b-a2d2ef4c5ac5 8149b0b3-fa8c-4a13-b54e-8251f5778807
```

Property	Value
attach_mode	None
attached_at	
detached_at	
id	f7a84c08-5943-4d23-a89b-b056042a3506
instance	8149b0b3-fa8c-4a13-b54e-8251f5778807
status	reserved
volume_id	ec555584-83a0-4aef-809b-a2d2ef4c5ac5

Cinder compatible API results:

```
root@ubuntu:~/gopath/src/github.com/opensds/opensds# cinder attachment-create babaed1a-2e9d-4b61-9631-0e9242c76c0f babaed1a-2e9d-4b61-9631-0e9242c76c0f
```

Property	Value
id	fd32832d-5d91-4f9e-b0c2-2b2ecc424166
instance	babaed1a-2e9d-4b61-9631-0e9242c76c0f
status	creating
volume_id	babaed1a-2e9d-4b61-9631-0e9242c76c0f

```
{
  "data": {
    "u'attachment': u'attachment'"
  }
}
```

5.3.1.5.2 Show attachment

Cinder attachment-show

cinder results:

```
root@ubuntu:~/cinder_data_dir/cinder/contrib/block-box# cinder attachment-show f7a84c08-5943-4d23-a89b-b056042a3506
```

Property	Value
attach_mode	None
attached_at	
detached_at	
id	f7a84c08-5943-4d23-a89b-b056042a3506
instance	8149b0b3-fa8c-4a13-b54e-8251f5778807
status	reserved
volume_id	ec555584-83a0-4aef-809b-a2d2ef4c5ac5

Cinder compatible API results:

```
root@ubuntu:~/gopath/src/github.com/opensds/opensds# cinder attachment-show fd32832d-5d91-4f9e-b0c2-2b2ecc424166
```

Property	Value
id	fd32832d-5d91-4f9e-b0c2-2b2ecc424166
instance	babaed1a-2e9d-4b61-9631-0e9242c76c0f
status	error
volume_id	babaed1a-2e9d-4b61-9631-0e9242c76c0f

Property	Value
data	{u'attachment': u'attachment'}

5.3.1.5.3 List attachment

cinder attachment-list

cinder results:

```
root@ubuntu:~/cinder_data_dir/cinder/contrib/block-box# cinder attachment-list
```

ID	Volume ID	Status	Server ID
8fa3413f-07dc-48f5-a7b2-fdbea19ded1c	c64a4d98-c194-4c75-a37b-05722c7ee349	reserved	
f7a84c08-5943-4d23-a89b-b056042a3506	ec555584-83a0-4aef-809b-a2d2ef4c5ac5	reserved	

Cinder compatible API results:

```
root@ubuntu:~/gopath/src/github.com/opensds/opensds# cinder attachment-list
```

ID	Volume ID	Status	Server ID
95d4e9f5-88db-4015-9467-1ed0045b6469	3c51e853-51dc-4cfd-b795-8bc9b57a0b79	error	
caa2a055-a9c2-43e0-96d4-391398f7c8b4	bb04ad9a-75bd-40a4-ac5e-3c92a7e66956	error	

5.3.1.5.4 Update attachment

cinder attachment-update

Cinder compatible API results:

```

root@ubuntu:~/gopath/src/github.com/opensds/opensds# cinder attachment-update fd32832d-5d91-4f9e-b0c2-2b2ecc424166 --ip 127.0.0.1
+-----+-----+
| Property | Value |
+-----+-----+
| id        | fd32832d-5d91-4f9e-b0c2-2b2ecc424166 |
| instance  | babaed1a-2e9d-4b61-9631-0e9242c76c0f |
| status    | error |
| volume_id | babaed1a-2e9d-4b61-9631-0e9242c76c0f |
+-----+-----+
+-----+-----+
| Property | Value |
+-----+-----+
| data     | {u'attachment': u'attachment'} |
+-----+-----+
root@ubuntu:~/gopath/src/github.com/opensds/opensds# osdsctl volume attachment show fd32832d-5d91-4f9e-b0c2-2b2ecc424166
WARNING: Not found Env OPENSDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+
| Property | Value |
+-----+-----+
| Id        | fd32832d-5d91-4f9e-b0c2-2b2ecc424166 |
| CreatedAt | 2018-04-24T10:41:28 |
| UpdatedAt | 2018-04-24T10:54:56 |
| TenantId  | ef305038-cd12-4f3b-90bd-0612f83e14ee |
| UserId    | |
| VolumeId  | babaed1a-2e9d-4b61-9631-0e9242c76c0f |
| Mountpoint | |
| Status    | error |
| HostInfo  | {
  "platform": "x86_64",
  "osType": "linux2",
  "ip": "127.0.0.1"
}
| ConnectionInfo | {
  "data": {
    "attachment": "attachment"
  },
  "additionalProperties": {
    "attachment": "attachment"
  }
}
+-----+-----+

```

5.3.1.5.5 Delete attachment

cinder attachment-delete

cinder results:

```

root@ubuntu:~/cinder_data_dir/cinder/contrib/block-box# cinder attachment-list
+-----+-----+-----+-----+
| ID | Volume ID | Status | Server ID |
+-----+-----+-----+-----+
| 8fa3413f-07dc-48f5-a7b2-fdbea19ded1c | c64a4d98-c194-4c75-a37b-05722c7ee349 | reserved | |
| f7a84c08-5943-4d23-a89b-b056042a3506 | ec555584-83a0-4aef-809b-a2d2ef4c5ac5 | reserved | |
+-----+-----+-----+-----+
root@ubuntu:~/cinder_data_dir/cinder/contrib/block-box#
root@ubuntu:~/cinder_data_dir/cinder/contrib/block-box#
root@ubuntu:~/cinder_data_dir/cinder/contrib/block-box# cinder attachment-delete 8fa3413f-07dc-48f5-a7b2-fdbea19ded1c
root@ubuntu:~/cinder_data_dir/cinder/contrib/block-box# cinder attachment-list
+-----+-----+-----+-----+
| ID | Volume ID | Status | Server ID |
+-----+-----+-----+-----+
| f7a84c08-5943-4d23-a89b-b056042a3506 | ec555584-83a0-4aef-809b-a2d2ef4c5ac5 | reserved | |
+-----+-----+-----+-----+

```

Cinder compatible API results:

```

root@ubuntu:~/gopath/src/github.com/opensds/opensds# cinder attachment-list
+-----+-----+-----+-----+
| ID | Volume ID | Status | Server ID |
+-----+-----+-----+-----+
| 95d4e9f5-88db-4015-9467-1ed0045b6469 | 3c51e853-51dc-4cfd-b795-8bc9b57a0b79 | error | |
| caa2a055-a9c2-43e0-96d4-391398f7c8b4 | bb04ad9a-75bd-40a4-ac5e-3c92a7e66956 | error | |
+-----+-----+-----+-----+
root@ubuntu:~/gopath/src/github.com/opensds/opensds# cinder attachment-delete 95d4e9f5-88db-4015-9467-1ed0045b6469
root@ubuntu:~/gopath/src/github.com/opensds/opensds# cinder attachment-list
+-----+-----+-----+-----+
| ID | Volume ID | Status | Server ID |
+-----+-----+-----+-----+
| caa2a055-a9c2-43e0-96d4-391398f7c8b4 | bb04ad9a-75bd-40a4-ac5e-3c92a7e66956 | error | |
+-----+-----+-----+-----+

```


5.4 Array-based Replication using Dorado

5.4.1 Without Kubernetes

Test using Dashboard and CLI

5.4.1.1 Configuration

In host based replication scenario ,we need to depoly opensds in two nodes. Node A includes osdslet, osdsdock-provisioner, osdsdock-attacher and etcd. For simplifying the testing scenario, node B includes just only includes osdsdock-provisioner and osdsdock-attacher.



There are three configurations we need to config:

- /etc/opensds/opensds.conf
- /etc/opensds/attacher.conf
- /etc/opensds/driver/lvm.conf

An example in Node A (192.168.56.100) would be like this:

1. /etc/opensds/opensds.conf

```
[osdslet]
api_endpoint = 0.0.0.0:50040
graceful = True
log_file = /var/log/opensds/osdslet.log
socket_order = inc

[osdsdock]
api_endpoint = 192.168.56.100:50050
log_file = /var/log/opensds/osdsdock.log
# Specify which backends should be enabled, sample,ceph,cinder,lvm and so on.
enabled_backends = lvm
host_based_replication_driver=drbd

[database]
endpoint = 192.168.56.100:2379,192.168.56.101:2380
driver = etcd

[lvm]
name = lvm
description = LVM Test
driver_name = lvm
config_path = /etc/opensds/driver/lvm.yaml
```

2. /etc/opensds/attacher.conf

```
[osdsdock]
api_endpoint = localhost:50051
log_file = /var/log/opensds/osdsdock.log
bind_ip = 192.168.56.100
dock_type = attacher

[database]
endpoint = 192.168.56.100:2379,192.168.56.101:2380
driver = etcd
```

3. /etc/opensds/driver/lvm.conf

```
tgtBindIp: 192.168.56.100
pool:
  opensds-volumes-default:
    diskType: NL-SAS
    AZ: default
    extras:
      dataStorage:
        provisioningPolicy: Thin
        isSpaceEfficient: false
      ioConnectivity:
        accessProtocol: iscsi
        maxIOPS: 7000000
        maxBWS: 600
      advanced:
        diskType: SSD
        latency: 5ms
~
```

Then you can start opensds servers.

Start etcd server:

```
etcd --advertise-client-urls http://192.168.56.100:2379 --listen-client-urls
http://192.168.56.100:2379 --listen-peer-urls http://127.0.0.1:2380
```

Start up osdslet:

```
osdslet --logtostderr -v 8
```

Start up osdsdock-provisioner:

```
osdsdock --logtostderr -v 8
```

Start up osdsdock-attacher:

```
osdsdock --config-file /etc/opensds/attacher.conf --logtostderr -v 8
```

In node B you just should start up osdsdock-provisioner and osdsdock-attacher.

5.4.1.2 Testing

Here is the usage of replication CLI.

1. Create replication.

Usage:

```
osdsctl replication create <primary volume id> <secondary volume id> [flags]
```

Flags:

```
-d, --description string    the description of created replication
-h, --help                  help for create
-n, --name string           the name of created replication
-p, --primary_driver_data string  the primary replication driver data of created replication
-m, --replication_model string  the replication mode of created replication, value can be sync/async
-t, --replication_period int    the replication period of created replication, the value must greater than 0
                                (default 120)
-s, --secondary_driver_data string  the secondary replication driver data of created replication
```

2. List replication.

Usage:

```
osdsctl replication list [flags]
```

Flags:

```
-h, --help  help for list
```

Global Flags:

```
--debug  shows debugging output.
```


3. Show a replication

Usage:

```
osdsctl replication show <replication id> [flags]
```

Flags:

```
-h, --help  help for show
```

Global Flags:

```
--debug  shows debugging output.
```

4. Enable replication.

Usage:

```
osdsctl replication enable <replication id> [flags]
```

Flags:

```
-h, --help  help for enable
```

Global Flags:

```
--debug  shows debugging output.
```

5.disable replication

Usage:

```
osdsctl replication disable <replication id> [flags]
```

Flags:

-h, --help help for disable

Global Flags:

--debug shows debugging output.

6. Failover replication

Usage:

osdsctl replication failover <replication id> [flags]

Flags:

-a, --allow_attached_volume whether allow attached volume when failing over replication

-h, --help help for failover

-s, --secondary_backend_id string the secondary backend id of failover replication

Global Flags:

--debug shows debugging output.

7. delete replication

Usage:

osdsctl replication delete <replication id> [flags]

Flags:

-h, --help help for delete

Global Flags:

--debug shows debugging output.

5.4.2 With Kubernetes

How to test CSI plugin for array-based replication will be covered later.

5.5 Host-based Replication using DRBD

5.5.1 Prepare

We need to prepare two hosts for this test, say HostA(IP: 192.168.0.131) and HostB(IP: 192.168.0.66). And before we start, please make sure the OpenSDS is already installed on both hosts. And copy *etcdctl*, *etcd*, *osdslet*, *osdsdock*, *osdsctl* to */opt/opensds/bin/*.

5.5.2 Install DRBD

Install DRBD as the following steps on both hosts:

- *sudo add-apt-repository ppa:linbit/linbit-drbd9-stack*
- *sudo apt-get update*
- *sudo apt-get install drbd-utils python-drbdmanage drbd-dkms*

5.5.3 Configuration

Before do configuration, please stop opensds service first. That is find out the process id of *etcd*, *osdslet* and *osdsdock*, and kill them.

Modify */etc/opensds/opensds.conf*:

- Add *host_based_replication_driver* for the *osdsdock* part on both hosts
- Change *endpoint* of *database* on hostB to the same as HostA.

Here is the example:

```
[lvm]
name = lvm
description = LVM Test
driver_name = lvm
config_path = /etc/opensds/driver/lvm.yaml

[osdslet]
api_endpoint = 0.0.0.0:50040
graceful = True
log_file = /var/log/opensds/osdslet.log
socket_order = inc
auth_strategy = noauth

[osdsdock]
api_endpoint = 192.168.0.131:50050
log_file = /var/log/opensds/osdsdock.log
# Specify which backends should be enabled, sample,ceph,cinder,lvm and so on.
enabled_backends = lvm
host_based_replication_driver = drbd

[database]
```

```
endpoint = 192.168.0.131:62379,192.168.0.131:62380
driver = etcd
```

Add a new configuration file `/etc/opensds/attacher.conf` on both hosts, here is an example:

```
[osdsdock]
api_endpoint = 192.168.0.131:50051
log_file = /var/log/opensds/osdsdock.log
bind_ip = 192.168.0.131
dock_type = attacher

[database]
endpoint = 192.168.0.131:62379,192.168.0.131:62380
driver = etcd
```

Note: both hosts have the same endpoint of database, but api endpoint and bind ip of osdsdock should be the host ip respectively.

Add a new configuration file `/etc/opensds/drbd.yaml` on both hosts, the content is:

```
# Minimum and Maximum TCP/IP ports used for DRBD replication
PortMin: 7000
PortMax: 8000

# Exactly two hosts between resources are replicated.
# Never ever change the Node-ID associated with a Host(name)
Hosts:
- Hostname: ecs-37cc
  IP: 192.168.0.66
  Node-ID: 1

- Hostname: ecs-32bc
  IP: 192.168.0.131
  Node-ID: 0
```

Note: Hostname and IP should be the real value of each hosts.

Modify `/etc/opensds/driver/lvm.yaml` on hostB, change `availabilityZone` to a new value. Here is an example:

```
tgtBindIp: 192.168.0.66
tgtConfDir: /etc/tgt/conf.d
pool:
  opensds-volumes-default:
    diskType: NL-SAS
    availabilityZone: secondary
  extras:
    dataStorage:
      provisioningPolicy: Thin
      isSpaceEfficient: false
    ioConnectivity:
      accessProtocol: iscsi
      maxIOPS: 7000000
      maxBWS: 600
    advanced:
      diskType: SSD
      latency: 5ms
```

5.5.4 Create Replication

Start services on HostA:

- `cd /opt/opensds/bin`

- `./etcd --advertise-client-urls http://192.168.0.131:62379 --listen-client-urls http://192.168.0.131:62379 --listen-peer-urls http://192.168.0.131:62380 --data-dir /opt/opensds/etcd/data >> /var/log/opensds/etcd.log 2>&1 &`
- `./osdslet &`
- `./osdsdock &`
- `./osdsdock --config-file /etc/opensds/attacher.conf &`

Start services on HostB:

- `./osdslet &`
- `./osdsdock &`
- `./osdsdock --config-file /etc/opensds/attacher.conf &`

Create volumes (run them on HostA or hostB):

- `./osdsctl volume create 1 -n primary`
- `./osdsctl volume create 1 -n secondary -a secondary`

Id	Name	Description	GroupId	Size	AvailabilityZone	Status	PoolId	ProfileId
e0b1c9e3-0c88-4601-b0e7-c09448a89e5c	primary			1	default	available	8c09d3ca-ba57-5cc9-88f0-5ef1205efc43	89669a7b-4ec3-45b3-bd44
3ea2e681-4884-4d84-a2e3-d5e3318763b2	secondary			1	secondary	available	5afc6857-a2f2-5f5f-ac5c-636c43f65892	89669a7b-4ec3-45b3-bd44

Create replication:

- `./osdsctl replication create e0b1c9e3-0c88-4601-b0e7-c09448a89e5c 3ea2e681-4884-4d84-a2e3-d5e3318763b2`

```
root@ecs-32bc:/opt/opensds/bin# ./osdsctl replication create e0b1c9e3-0c88-4601-b0e7-c09448a89e5c 3ea2e681-4884-4d84-a2e3-d5e3318763b2
WARNING: Not found Env OPENSOS_AUTH_STRATEGY, use default(noauth)
s[0xc420750e90 0xc420750e98 0xc42012a5a0]
s[0xc42021df50 attacher 192.168.0.131:50051 ecs-32bc map[OsType:linux Platform:amd64 HostIp:192.168.0.131 Initiator:ign.1993-08.org.debian:01:42e1a22343c]]
s[0xc420750ce0 0xc420750cf0 0xc4208741e0]
s[0xc4207e0260 attacher 192.168.0.66:50051 ecs-37cc map[HostIp:192.168.0.66 Initiator:ign.1993-08.org.debian:01:42e1a22343c OsType:linux Platform:amd64]]
2018/06/08 11:48:07.996 [D] :: 108/Jun/2018 11:48:04 "POST /v1beta/ef305038-cd12-4f3b-90bd-0612f83014e/block/replications HTTP/1.1 202 0" 3.465986 beegoServer
```

Property	Value
Id	1badf257-a3ad-459a-bcd7-c9506aed43cb
CreatedAt	2018-06-08T11:48:04
UpdatedAt	
Name	
Description	
PrimaryVolumeId	e0b1c9e3-0c88-4601-b0e7-c09448a89e5c
SecondaryVolumeId	3ea2e681-4884-4d84-a2e3-d5e3318763b2
AvailabilityZone	
PrimaryReplicationDriverData	{ "AttachmentId": "dda38c28-5a80-4b52-858d-f195bf7b173b", "HostIp": "192.168.0.131", "HostName": "ecs-32bc", "Mountpoint": "/dev/disk/by-path/ip-192.168.0.131:3260-iscsi-ign.2017-10.io.opensds:e0b1c9e3-0c88-4601-b0e7-c09448a89e5c-lun-1", "e0b1c9e3-0c88-4601-b0e7-c09448a89e5c-drbd-minor": "1", "e0b1c9e3-0c88-4601-b0e7-c09448a89e5c-drbd-port": "7000", "lvPath": "/dev/opensds-volumes-default/volume-e0b1c9e3-0c88-4601-b0e7-c09448a89e5c" }
SecondaryReplicationDriverData	{ "3ea2e681-4884-4d84-a2e3-d5e3318763b2-drbd-minor": "1", "3ea2e681-4884-4d84-a2e3-d5e3318763b2-drbd-port": "7000", "AttachmentId": "9440eeec-57b7-493f-85bd-8c8af6058e0a", "HostIp": "192.168.0.66", "HostName": "ecs-37cc", "Mountpoint": "/dev/disk/by-path/ip-192.168.0.66:3260-iscsi-ign.2017-10.io.opensds:3ea2e681-4884-4d84-a2e3-d5e3318763b2-lun-1", "lvPath": "/dev/opensds-volumes-default/volume-3ea2e681-4884-4d84-a2e3-d5e3318763b2" }
ReplicationStatus	enabled
ReplicationMode	sync
ReplicationPeriod	0
ProfileId	

5.5.5 Check result

See the block device.

```

root@ecs-32bc:/opt/opensds/bin# lsblk
NAME                                MAJ:MIN RM   SIZE RO TYPE MOUNTPOINT
sda                                  8:0      0    1G  0 disk
xvda                                202:0     0    60G  0 disk
├─xvda1                             202:1     0    60G  0 part /
└─loop0                             7:0      0    20G  0 loop
└─opensds--volumes--default-volume--e0b1c9e3--0c88--4601--b0e7--c09448a89e5c 252:0     0    1G  0 lvm
    └─drbd1                         147:1     0 1023.8M  1 disk

```

Create some data on HostA.

- `mkfs.ext4 /dev/drbd1`
- `mount /dev/drbd1 ./reptest/`
- `touch test`
- `dd if=/dev/zero of=./2 bs=1M count=500`
- `touch test`
-

Check the synchronous status on both hosts.

```

root@ecs-32bc:/opt/opensds/bin# drbdsetup status
lbadf257-a3ad-459a-bcd7-c9506aed43cb role:Primary
  disk:UpToDate
ecs-37cc role:Secondary
  peer-disk:UpToDate

```

Check if the data is updated on HostB.

- `umount` on HostA
- `mount` on HostB
- Check data on HostB, and you can see the data is updated.

```

root@ecs-37cc:/home/reptest# ll
total 512044
drwxr-xr-x 3 root root    4096 Jun  8 11:56 ./
drwxr-xr-x 4 root root    4096 Jun  8 11:54 ../
-rw-r--r-- 1 root root 524288000 Jun  8 13:39 2
-rw-r--r-- 1 root root    29 Jun  8 11:56 3
-rw-r--r-- 1 root root    29 Jun  8 11:56 4
-rw-r--r-- 1 root root    29 Jun  8 11:56 5
drwx----- 2 root root   16384 Jun  8 11:51 lost+found/
-rw-r--r-- 1 root root    29 Jun  8 11:51 test
root@ecs-37cc:/home/reptest#

```

6 OpenSDS CLI Guide

6.1 List Docks

Use the following command to display the docks information.

```
osdsctl dock list
```

Sample results are as follows:

```
root@ecs-fe68:~# osdsctl dock list
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+
| Id | Name | Description | Endpoint | DriverName |
+-----+-----+-----+-----+-----+
| 410203b0-3bcd-5239-b9c2-3cd63d8fbdfd | lvm | LVM Test | 192.168.0.172:50050 | lvm |
+-----+-----+-----+-----+-----+
```

Display specific results by filter parameters. Filter parameters can be displayed by the following command.

```
osdsctl dock list -h
```

Results are as follows:

```
root@ecs-fe68:~# osdsctl dock list -h
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
get all dock resources

Usage:
  osdsctl dock list [flags]

Flags:
  --description string  list docks by description
  --driverName string   list docks by driver name
  --endpoint string     list docks by endpoint
  -h, --help            help for list
  --id string           list docks by id
  --limit string        the number of entries displayed per page (default "50")
  --name string         list docks by name
  --offset string       all requested data offsets (default "0")
  --sortDir string      the sort direction of all requested data. supports asc or desc(default) (default "desc")
  --sortKey string      the sort key of all requested data. supports id(default), name, status, endpoint, drivername, description (default "id")
  --status string       list docks by status
  --storageType string  list docks by storage type

Global Flags:
  --debug  shows debugging output.

root@ecs-fe68:~#
```

Example:

```
root@ecs-fe68:~# osdsctl dock list
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+
| Id | Name | Description | Endpoint | DriverName |
+-----+-----+-----+-----+-----+
| 410203b0-3bcd-5239-b9c2-3cd63d8fbdfd | lvm | LVM Test | 192.168.0.172:50050 | lvm |
+-----+-----+-----+-----+-----+

root@ecs-fe68:~# osdsctl dock list --name test
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+
| Id | Name | Description | Endpoint | DriverName | Parameters |
+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+-----+

root@ecs-fe68:~# osdsctl dock list --name lvm
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+
| Id | Name | Description | Endpoint | DriverName |
+-----+-----+-----+-----+-----+
| 410203b0-3bcd-5239-b9c2-3cd63d8fbdfd | lvm | LVM Test | 192.168.0.172:50050 | lvm |
+-----+-----+-----+-----+-----+
```

6.2 List Pools

Use the following command to display the pools information.

```
osdsctl pool list
```

Sample results are as follows:

```

root@ecs-fe68:~# osdsctl pool list
WARNING: Not found Env OPENSIDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | Status | AvailabilityZone | TotalCapacity | FreeCapacity |
+-----+-----+-----+-----+-----+-----+-----+
| dcef211c-0f21-58b4-873c-2bd871ab169a | opensds-volumes-default | | | default | 20 | 20 |
+-----+-----+-----+-----+-----+-----+-----+

```

Display specific results by filter parameters. Filter parameters can be displayed by the following command.

```
osdsctl pool list -h
```

Results are as follows:

```

root@ecs-fe68:~# osdsctl pool list -h
WARNING: Not found Env OPENSIDS_AUTH_STRATEGY, use default(noauth)
get all pool resources

Usage:
  osdsctl pool list [flags]

Flags:
  --availabilityZone string  list pools by availability zone
  --description string       list pools by description
  --dockId string           list pools by dock id
  -h, --help                help for list
  --id string               list pools by id
  --limit string            the number of entries displayed per page (default "50")
  --name string             list pools by name
  --offset string           all requested data offsets (default "0")
  --sortDir string          the sort direction of all requested data. supports asc or desc(default) (default "desc")
  --sortKey string          the sort key of all requested data. supports id(default), name, status, availabilityzone, dock id, description (default "id")
  --status string           list pools by status
  --storageType string      list pools by storage type

Global Flags:
  --debug  shows debugging output.
root@ecs-fe68:~#

```

Example:

```

root@ecs-fe68:~# osdsctl pool list
WARNING: Not found Env OPENSIDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | Status | AvailabilityZone | TotalCapacity | FreeCapacity |
+-----+-----+-----+-----+-----+-----+-----+
| dcef211c-0f21-58b4-873c-2bd871ab169a | opensds-volumes-default | | | default | 20 | 20 |
+-----+-----+-----+-----+-----+-----+-----+

root@ecs-fe68:~# osdsctl pool list --limit 0
WARNING: Not found Env OPENSIDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | Status | AvailabilityZone | TotalCapacity | FreeCapacity |
+-----+-----+-----+-----+-----+-----+-----+

root@ecs-fe68:~# osdsctl pool list --limit 2
WARNING: Not found Env OPENSIDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | Status | AvailabilityZone | TotalCapacity | FreeCapacity |
+-----+-----+-----+-----+-----+-----+-----+
| dcef211c-0f21-58b4-873c-2bd871ab169a | opensds-volumes-default | | | default | 20 | 20 |
+-----+-----+-----+-----+-----+-----+-----+

```

6.3 Create/Delete Profile

Use the following command to create profile.

```
osdsctl profile create *
```

Example:


```

root@ecs-fe68:~# osdsctl profile create '{"name": "default", "description": "default policy"}'
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+
| Property | Value |
+-----+-----+
| Id        | 4140e670-38fb-4de2-b7f4-ac5f038622e4 |
| CreatedAt | 2018-06-14T19:46:54 |
| UpdatedAt | |
| Name      | default |
| Description | default policy |
| Extras    | null |
+-----+-----+
root@ecs-fe68:~# osdsctl profile list
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+
| Id | Name | Description |
+-----+-----+-----+
| eee31757-1ace-43aa-9ebd-1a3cf79ceb69 | default | default policy |
| 4140e670-38fb-4de2-b7f4-ac5f038622e4 | default | default policy |
+-----+-----+-----+

```

Use the following command to delete profile.

```
osdsctl profile delete *
```

Example:

```

root@ecs-fe68:~# osdsctl profile delete 4140e670-38fb-4de2-b7f4-ac5f038622e4
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
root@ecs-fe68:~# osdsctl profile list
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+
| Id | Name | Description |
+-----+-----+-----+
| eee31757-1ace-43aa-9ebd-1a3cf79ceb69 | default | default policy |
+-----+-----+-----+
root@ecs-fe68:~# █

```

6.4 Create/Delete/Get/List Volume(s)

Use the following command to create volume.

```
osdsctl volume create 3
```

Example:

```

root@ecs-fe68:~# osdsctl volume create 3
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+
| Property | Value |
+-----+-----+
| Id        | 8590553f-050f-4dd4-9a8f-92eb675d66ce |
| CreatedAt | 2018-06-14T20:02:51 |
| UpdatedAt | |
| Name      | |
| Description | |
| GroupId   | |
| Size      | 3 |
| AvailabilityZone | default |
| Status     | creating |
| PoolId     | |
| ProfileId  | |
| Metadata  | map[] |
+-----+-----+
root@ecs-fe68:~#

```

Use the following command to display the volume details.

```
osdsctl volume show *
```

Example:

```

root@ecs-fe68:~# osdsctl volume show 8590553f-050f-4dd4-9a8f-92eb675d66ce
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+
| Property | Value |
+-----+-----+
| Id        | 8590553f-050f-4dd4-9a8f-92eb675d66ce |
| CreatedAt | 2018-06-14T20:02:51 |
| UpdatedAt | 2018-06-14T20:02:51 |
| Name      | |
| Description | |
| GroupId   | |
| Size      | 3 |
| AvailabilityZone | default |
| Status     | available |
| PoolId     | dcef211c-0f21-58b4-873c-2bd871ab169a |
| ProfileId  | eee31757-1ace-43aa-9ebd-1a3cf79ceb69 |
| Metadata  | map[lvPath:/dev/opensdds-volumes-default/volume-8590553f-050f-4dd4-9a8f-92eb675d66ce] |
| SnapshotId | |
+-----+-----+
root@ecs-fe68:~#

```

Use the following command to delete the volume.

```
osdsctl volume delete *
```

Example:

```

root@ecs-fe68:~# osdsctl volume delete 8590553f-050f-4dd4-9a8f-92eb675d66ce
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
root@ecs-fe68:~# osdsctl volume show 8590553f-050f-4dd4-9a8f-92eb675d66ce
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
ERROR: Get volume failed: specified volume(8590553f-050f-4dd4-9a8f-92eb675d66ce) can't find
root@ecs-fe68:~#

```

Display specific results by filter parameters. Filter parameters can be displayed by the following command.

```
osdsctl volume list -h
```

Results are as follows:

```
root@ecs-fe68:~# osdsctl volume list -h
WARNING: Not found Env OPENSDFS_AUTH_STRATEGY, use default(noauth)
list all volumes in the cluster

Usage:
  osdsctl volume list [flags]

Flags:
  --availabilityZone string  list volume by availability zone
  --description string       list volume by description
  --groupid string           list volume by volume group id
  -h, --help                help for list
  --id string               list volume by id
  --limit string            the number of entries displayed per page (default "50")
  --name string             list volume by name
  --offset string           all requested data offsets (default "0")
  --poolid string          list volume by poolid
  --profileid string        list volume by profile id
  --sortDir string          the sort direction of all requested data. supports asc or desc(default) (default "desc")
  --sortKey string          the sort key of all requested data. supports id(default), name, status, availabilityzone, profileid, tenantid, size, poolid, description (default "id")
  --status string           list volume by status
  --tenantid string         list volume by tenantid
  --userid string           list volume by storage userid

Global flags:
  -debug                shows debugging output.
  -p, --profile string  the name of profile configured by admin

root@ecs-fe68:~#
```

Example:

```
root@ecs-fe68:~# osdsctl volume list
WARNING: Not found Env OPENSDFS_AUTH_STRATEGY, use default(noauth)

+-----+-----+-----+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | GroupId | Size | AvailabilityZone | Status | PoolId | ProfileId |
+-----+-----+-----+-----+-----+-----+-----+-----+-----+
| eedc8173-771d-4cdb-a7a9-880faf9292d8 | | | | 0 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| e1214c32-c526-4ce3-bc6c-333382e85abe | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| 9ced97d8-1109-4c50-aab1-594c8dc42259 | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| 8088c20f-c099-484a-8f47-9b0a1af4ec96 | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| 678ba124-8df6-4afc-985a-62a280413f27 | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| 049519e2-98c4-419d-b92c-81991fab9a32 | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
+-----+-----+-----+-----+-----+-----+-----+-----+-----+

root@ecs-fe68:~# osdsctl volume list --sortDir asc --sortKey Size
WARNING: Not found Env OPENSDFS_AUTH_STRATEGY, use default(noauth)

+-----+-----+-----+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | GroupId | Size | AvailabilityZone | Status | PoolId | ProfileId |
+-----+-----+-----+-----+-----+-----+-----+-----+-----+
| 049519e2-98c4-419d-b92c-81991fab9a32 | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| 678ba124-8df6-4afc-985a-62a280413f27 | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| 8088c20f-c099-484a-8f47-9b0a1af4ec96 | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| 9ced97d8-1109-4c50-aab1-594c8dc42259 | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| e1214c32-c526-4ce3-bc6c-333382e85abe | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| eedc8173-771d-4cdb-a7a9-880faf9292d8 | | | | 0 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
+-----+-----+-----+-----+-----+-----+-----+-----+-----+

root@ecs-fe68:~# osdsctl volume list --sortDir asc --sortKey Size --limit 3
WARNING: Not found Env OPENSDFS_AUTH_STRATEGY, use default(noauth)

+-----+-----+-----+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | GroupId | Size | AvailabilityZone | Status | PoolId | ProfileId |
+-----+-----+-----+-----+-----+-----+-----+-----+-----+
| 049519e2-98c4-419d-b92c-81991fab9a32 | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| 678ba124-8df6-4afc-985a-62a280413f27 | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| 8088c20f-c099-484a-8f47-9b0a1af4ec96 | | | | 1 | default | available | dcef211c-0f21-58b4-873c-2bd871ab169a | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
+-----+-----+-----+-----+-----+-----+-----+-----+-----+

root@ecs-fe68:~#
```

6.5 Create/Delete/Get/List Snapshot(s)

Use the following command to create snapshot.

```
osdsctl volume snapshot create *
```

Example:

```
root@ecs-fe68:~# osdsctl volume snapshot create e1214c32-c526-4ce3-bc6c-333382e85abe
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+
| Property | Value |
+-----+-----+
| Id        | c793cc1f-c6e3-4982-b7f2-1c37bed78f7e |
| CreatedAt | 2018-06-14T20:24:24 |
| UpdatedAt | |
| Name      | |
| Description | |
| Size      | 1 |
| Status    | creating |
| VolumeId  | e1214c32-c526-4ce3-bc6c-333382e85abe |
+-----+-----+
root@ecs-fe68:~#
```

Use the following command to display snapshot details.

```
osdsctl volume snapshot show *
```

Example:

```
root@ecs-fe68:~# osdsctl volume snapshot show c793cc1f-c6e3-4982-b7f2-1c37bed78f7e
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+
| Property | Value |
+-----+-----+
| Id        | c793cc1f-c6e3-4982-b7f2-1c37bed78f7e |
| CreatedAt | 2018-06-14T20:24:24 |
| UpdatedAt | 2018-06-14T20:24:24 |
| Name      | |
| Description | |
| Size      | 1 |
| Status    | available |
| VolumeId  | e1214c32-c526-4ce3-bc6c-333382e85abe |
+-----+-----+
root@ecs-fe68:~#
```

Use the following command to delete snapshot.

```
osdsctl volume snapshot delete *
```

Example:

```
root@ecs-fe68:~# osdsctl volume snapshot list
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | Size | Status | VolumeId |
+-----+-----+-----+-----+-----+-----+
| c793cc1f-c6e3-4982-b7f2-1c37bed78f7e | | | 1 | available | e1214c32-c526-4ce3-bc6c-333382e85abe |
+-----+-----+-----+-----+-----+-----+
root@ecs-fe68:~# osdsctl volume snapshot delete c793cc1f-c6e3-4982-b7f2-1c37bed78f7e
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
root@ecs-fe68:~# osdsctl volume snapshot list
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | Size | Status | VolumeId |
+-----+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+-----+-----+
root@ecs-fe68:~#
```

Display specific results by filter parameters. Filter parameters can be displayed by the following command.

```
osdsctl volume snapshot list -h
```

Results are as follows:

```
root@ecs-fe68:~# osdsctl volume snapshot list -h
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
list all volume snapshots in the cluster

Usage:
  osdsctl volume snapshot list [flags]

Flags:
  --description string  list volume snapshot by description
  -h, --help            help for list
  --id string           list volume snapshot by id
  --limit string        the number of entries displayed per page (default "50")
  --name string         list volume snapshot by Name
  --offset string       all requested data offsets (default "0")
  --sortDir string      the sort direction of all requested data, supports asc or desc(default) (default "desc")
  --sortKey string      the sort key of all requested data, supports id(default), volumeid, status, userid, tenantid, size (default "id")
  --status string       list volume snapshot by status
  --userId string       list volume snapshot by storage userId
  --volumeId string     list volume snapshot by volume id

Global Flags:
  --debug            shows debugging output.
  -p, --profile string the name of profile configured by admin
root@ecs-fe68:~#
```

Example:

```
root@ecs-fe68:~# osdsctl volume snapshot list
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | Size | Status | VolumeId |
+-----+-----+-----+-----+-----+-----+
| f261b56d-70e2-409b-a78d-19387450a2cf | | | 1 | available | 8088c20f-c009-484a-8f47-9b0a1af4ec96 |
| eb0a2dcc-421f-46be-b7b1-ca9bd084a32c | | | 3 | available | eedc8173-771d-4cdb-a7a9-880faf9292d8 |
| ada0a527-5f9f-49d3-90a8-d8ec3b32294a | | | 1 | available | 049519e2-90c4-419d-b92c-81991fab9a32 |
| 3309a81f-4827-48e1-a407-5348cf8877a0 | | | 3 | available | eedc8173-771d-4cdb-a7a9-880faf9292d8 |
+-----+-----+-----+-----+-----+-----+
root@ecs-fe68:~# osdsctl volume snapshot list --volumeId eedc8173-771d-4cdb-a7a9-880faf9292d8 --sortKey id --sortDir asc
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | Size | Status | VolumeId |
+-----+-----+-----+-----+-----+-----+
| 3309a81f-4827-48e1-a407-5348cf8877a0 | | | 3 | available | eedc8173-771d-4cdb-a7a9-880faf9292d8 |
| eb0a2dcc-421f-46be-b7b1-ca9bd084a32c | | | 3 | available | eedc8173-771d-4cdb-a7a9-880faf9292d8 |
+-----+-----+-----+-----+-----+-----+
root@ecs-fe68:~#
```

6.6 Create Volume from Snapshot

Use the following command to create volume from snapshot.

```
osdsctl volume create 1 -s *
```

Example:

```

root@ecs-fe68:~# osdsctl volume snapshot list
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | Size | Status | VolumeId |
+-----+-----+-----+-----+-----+-----+
| f261b56d-70e2-409b-a78d-19387450a2cf | | | 1 | available | 8088c20f-c009-484a-8f47-9b0a1af4ec96 |
| eb0a2dcc-421f-46be-b7b1-ca9bd084a32c | | | 3 | available | eedc8173-771d-4cdb-a7a9-880faf9292d8 |
| ada0a527-5f9f-49d3-90a8-d8ec3b32294a | | | 1 | available | 049519e2-90c4-419d-b92c-81991fab9a32 |
| 3309a81f-4827-48e1-a407-5348cf8877a0 | | | 3 | available | eedc8173-771d-4cdb-a7a9-880faf9292d8 |
+-----+-----+-----+-----+-----+-----+
root@ecs-fe68:~# osdsctl volume create 1 -s f261b56d-70e2-409b-a78d-19387450a2cf
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+
| Property | Value |
+-----+-----+
| Id | 4c54dfe0-f243-44e9-a633-2c4a0e5080cf |
| CreatedAt | 2018-06-15T11:19:17 |
| UpdatedAt | |
| Name | |
| Description | |
| GroupId | |
| Size | 1 |
| AvailabilityZone | default |
| Status | creating |
| PoolId | |
| ProfileId | |
| Metadata | map[] |
+-----+-----+
root@ecs-fe68:~# osdsctl volume show 4c54dfe0-f243-44e9-a633-2c4a0e5080cf
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+
| Property | Value |
+-----+-----+
| Id | 4c54dfe0-f243-44e9-a633-2c4a0e5080cf |
| CreatedAt | 2018-06-15T11:19:17 |
| UpdatedAt | 2018-06-15T11:19:20 |
| Name | |
| Description | |
| GroupId | |
| Size | 1 |
| AvailabilityZone | default |
| Status | available |
| PoolId | dcef211c-0f21-58b4-873c-2bd871ab169a |
| ProfileId | eee31757-lace-43aa-9ebd-1a3cf79ceb69 |
| Metadata | map[lvPath:/dev/opensds-volumes-default/volume-4c54dfe0-f243-44e9-a633-2c4a0e5080cf] |
| SnapshotId | f261b56d-70e2-409b-a78d-19387450a2cf |
+-----+-----+
root@ecs-fe68:~#

```

6.7 Expand Volume

Use the following command to expand volume size.

```
osdsctl volume extend * *
```

Example:

```

root@ecs-fe68:~# osdsctl volume extend 9fbcfadb-2a53-441c-921b-c3e5e87ff856 2
WARNING: Not found Env OPENSDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+
| Property | Value |
+-----+-----+
| Id        | 9fbcfadb-2a53-441c-921b-c3e5e87ff856 |
| CreatedAt | 2018-06-15T10:21:51 |
| UpdatedAt | 2018-06-15T17:00:14 |
| Name      | |
| Description | |
| GroupId   | |
| Size      | 1 |
| AvailabilityZone | default |
| Status     | extending |
| PoolId     | dcef211c-0f21-58b4-873c-2bd871ab169a |
| ProfileId  | eee31757-1ace-43aa-9ebd-1a3cf79ceb69 |
| Metadata   | map[lvPath:/dev/opensds-volumes-default/volume-9fbcfadb-2a53-441c-921b-c3e5e87ff856] |
+-----+-----+
root@ecs-fe68:~# osdsctl volume show 9fbcfadb-2a53-441c-921b-c3e5e87ff856
WARNING: Not found Env OPENSDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+
| Property | Value |
+-----+-----+
| Id        | 9fbcfadb-2a53-441c-921b-c3e5e87ff856 |
| CreatedAt | 2018-06-15T10:21:51 |
| UpdatedAt | 2018-06-15T17:00:14 |
| Name      | |
| Description | |
| GroupId   | |
| Size      | 2 |
| AvailabilityZone | default |
| Status     | available |
| PoolId     | dcef211c-0f21-58b4-873c-2bd871ab169a |
| ProfileId  | eee31757-1ace-43aa-9ebd-1a3cf79ceb69 |
| Metadata   | map[lvPath:/dev/opensds-volumes-default/volume-9fbcfadb-2a53-441c-921b-c3e5e87ff856] |
| SnapshotId | |
+-----+-----+
root@ecs-fe68:~#

```

6.8 Create/Delete/Get/List Volume Groups

Use the following command to create volume group.

```
osdsctl volume group create --profiles *
```

Example:

```

root@ecs-fe68:~# osdsctl volume group create --profiles eee31757-1ace-43aa-9ebd-1a3cf79ceb69
WARNING: Not found Env OPENSDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+
| Property | Value |
+-----+-----+
| Id        | 38555558-afb7-4860-9e38-eb6a83e0285e |
| CreatedAt | |
| UpdatedAt | |
| Name      | |
| Status     | creating |
| Description | |
| Profiles   | [eee31757-1ace-43aa-9ebd-1a3cf79ceb69] |
| AvailabilityZone | default |
| PoolId     | |
+-----+-----+

```

Use the following command to show volume group.

```
osdsctl volume group show *
```

Example:

```

root@ecs-fe68:~# osdsctl volume group show 38555558-afb7-4860-9e38-eb6a83e0285e
WARNING: Not found Env OPENSDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+
| Property | Value |
+-----+-----+
| Id        | 38555558-afb7-4860-9e38-eb6a83e0285e |
| CreatedAt | 2018-06-15T17:41:57 |
| UpdatedAt | |
| Name      | |
| Status    | available |
| Description | |
| Profiles  | [eee31757-1ace-43aa-9ebd-1a3cf79ceb69] |
| AvailabilityZone | default |
| PoolId    | dcef211c-0f21-58b4-873c-2bd871ab169a |
+-----+-----+
root@ecs-fe68:~#

```

Display specific results by filter parameters. Filter parameters can be displayed by the following command.

```
osdsctl volume group list -h
```

Results are as follows:

```

root@ecs-fe68:~# osdsctl volume group list -h
WARNING: Not found Env OPENSDS_AUTH_STRATEGY, use default(noauth)
list all volume groups in the cluster

Usage:
  osdsctl volume group list [flags]

Flags:
  --availabilityZone string  list volume group by availability zone
  --description string       list volume group by description
  -h, --help                 help for list
  --id string                list volume group by id
  --limit string             the number of entries displayed per page (default "50")
  --name string              list volume group by Name
  --offset string            all requested data offsets (default "0")
  --poolId string            list volume group by pool id
  --sortDir string           the sort direction of all requested data. supports asc or desc(default) (default "desc")
  --sortKey string           the sort key of all requested data. supports id(default), name, status, availability zone, tenantid, pool id (default "id")
  --status string            list volume group by status
  --tenantId string          list volume group by tenantId
  --userId string            list volume group by storage userId

Global Flags:
  --debug                shows debugging output.
  -p, --profile string    the name of profile configured by admin
root@ecs-fe68:~#

```

Example:

```

root@ecs-fe68:~# osdsctl volume group list
WARNING: Not found Env OPENSDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+-----+
| Id | Name | Status | Description | Profiles | AvailabilityZone | PoolId |
+-----+-----+-----+-----+-----+-----+
| 38555558-afb7-4860-9e38-eb6a83e0285e | | available | | [eee31757-1ace-43aa-9ebd-1a3cf79ceb69] | default | dcef211c-0f21-58b4-873c-2bd871ab169a |
+-----+-----+-----+-----+-----+-----+
root@ecs-fe68:~# osdsctl volume group list --poolId dcef211c-0f21-58b4-873c-2bd871ab169a
WARNING: Not found Env OPENSDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+-----+
| Id | Name | Status | Description | Profiles | AvailabilityZone | PoolId |
+-----+-----+-----+-----+-----+-----+
| 38555558-afb7-4860-9e38-eb6a83e0285e | | available | | [eee31757-1ace-43aa-9ebd-1a3cf79ceb69] | default | dcef211c-0f21-58b4-873c-2bd871ab169a |
+-----+-----+-----+-----+-----+-----+
root@ecs-fe68:~#

```

Use the following command to delete volume group.

```
osdsctl volume group delete *
```

Example:


```

root@ecs-fe68:~# osdsctl volume group delete 38555558-afb7-4860-9e38-eb6a83e0285e
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
Delete group(38555558-afb7-4860-9e38-eb6a83e0285e) success.
root@ecs-fe68:~# osdsctl volume group list --id 38555558-afb7-4860-9e38-eb6a83e0285e
WARNING: Not found Env OPENSDDS_AUTH_STRATEGY, use default(noauth)
+-----+-----+-----+-----+-----+-----+-----+
| Id | Name | Description | Status | AvailabilityZone | PoolId | Profiles |
+-----+-----+-----+-----+-----+-----+-----+
+-----+-----+-----+-----+-----+-----+-----+
root@ecs-fe68:~#

```

6.9 Replication

Here is the usage of replication CLI.

1. Create replication.

Usage:

```
osdsctl replication create <primary volume id> <secondary volume id> [flags]
```

Flags:

```

-d, --description string    the description of created replication
-h, --help                  help for create
-n, --name string           the name of created replication
-p, --primary_driver_data string  the primary replication driver data of created replication
-m, --replication_model string  the replication mode of created replication, value can be sync/async
-t, --replication_period int  the replication period of created replication, the value must greater than 0
                              (default 120)
-s, --secondary_driver_data string  the secondary replication driver data of created replication

```

2. List replication.

Usage:

```
osdsctl replication list [flags]
```

Flags:

```
-h, --help  help for list
```

Global Flags:

--debug shows debugging output.

3. Show a replication

Usage:

osdsctl replication show <replication id> [flags]

Flags:

-h, --help help for show

Global Flags:

--debug shows debugging output.

4. Enable replication.

Usage:

osdsctl replication enable <replication id> [flags]

Flags:

-h, --help help for enable

Global Flags:

--debug shows debugging output.

5.disable replication

Usage:

osdsctl replication disable <replication id> [flags]

Flags:

-h, --help help for disable

Global Flags:

--debug shows debugging output.

6. Failover replication

Usage:

osdsctl replication failover <replication id> [flags]

Flags:

-a, --allow_attached_volume whether allow attached volume when failing over replication

-h, --help help for failover

-s, --secondary_backend_id string the secondary backend id of failover replication

Global Flags:

--debug shows debugging output.

7. delete replication

Usage:

osdsctl replication delete <replication id> [flags]

Flags:

-h, --help help for delete

Global Flags:

--debug shows debugging output.