



Palm OS® Programming Development Tools Guide

Palm OS® 5 SDK (68K) R3

CONTRIBUTORS

Written by Brian Maas

Engineering contributions by Keith Rollin, Ken Krugler, Jesse Donaldson, Andy Stewart, Kenneth Albowski, and Derek Johnson

Copyright © 1996 - 2003, PalmSource, Inc. and its affiliates. All rights reserved. This documentation may be printed and copied solely for use in developing products for Palm OS® software. In addition, two (2) copies of this documentation may be made for archival and backup purposes. Except for the foregoing, no part of this documentation may be reproduced or transmitted in any form or by any means or used to make any derivative work (such as translation, transformation or adaptation) without express written consent from PalmSource, Inc.

PalmSource, Inc. reserves the right to revise this documentation and to make changes in content from time to time without obligation on the part of PalmSource, Inc. to provide notification of such revision or changes.

PALMSOURCE, INC. AND ITS SUPPLIERS MAKE NO REPRESENTATIONS OR WARRANTIES THAT THE DOCUMENTATION IS FREE OF ERRORS OR THAT THE DOCUMENTATION IS SUITABLE FOR YOUR USE. THE DOCUMENTATION IS PROVIDED ON AN "AS IS" BASIS. PALMSOURCE, INC. AND ITS SUPPLIERS MAKE NO WARRANTIES, TERMS OR CONDITIONS, EXPRESS OR IMPLIED, EITHER IN FACT OR BY OPERATION OF LAW, STATUTORY OR OTHERWISE, INCLUDING WARRANTIES, TERMS, OR CONDITIONS OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, AND SATISFACTORY QUALITY. TO THE FULL EXTENT ALLOWED BY LAW, PALMSOURCE, INC. ALSO EXCLUDES FOR ITSELF AND ITS SUPPLIERS ANY LIABILITY, WHETHER BASED IN CONTRACT OR TORT (INCLUDING NEGLIGENCE), FOR DIRECT, INCIDENTAL, CONSEQUENTIAL, INDIRECT, SPECIAL, OR PUNITIVE DAMAGES OF ANY KIND, OR FOR LOSS OF REVENUE OR PROFITS, LOSS OF BUSINESS, LOSS OF INFORMATION OR DATA, OR OTHER FINANCIAL LOSS ARISING OUT OF OR IN CONNECTION WITH THIS DOCUMENTATION, EVEN IF PALMSOURCE, INC. OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

PalmSource, the PalmSource logo, AnyDay, EventClub, Graffiti, HandFAX, HandMAIL, HandSTAMP, HandWEB, HotSync, the HotSync logo, iMessenger, MultiMail, MyPalm, Palm, the Palm logo, the Palm trade dress, Palm Computing, Palm OS, Palm Powered, PalmConnect, PalmGear, PalmGlove, PalmModem, PalmPak, PalmPix, PalmPoint, PalmPower, PalmPrint, Palm.Net, Simply Palm, ThinAir, and WeSync are trademarks of PalmSource, Inc. or its affiliates. All other product and brand names may be trademarks or registered trademarks of their respective owners.

IF THIS DOCUMENTATION IS PROVIDED ON A COMPACT DISC, THE OTHER SOFTWARE AND DOCUMENTATION ON THE COMPACT DISC ARE SUBJECT TO THE LICENSE AGREEMENT ACCOMPANYING THE COMPACT DISC.

Palm OS Programming Development Tools Guide
Document Number 3011-006
November 6, 2003
For the latest version of this document, visit
<http://www.palmos.com/dev/support/docs/>.

PalmSource, Inc.
1240 Crossman Avenue
Sunnyvale, CA 94089
USA
www.palmsource.com

Table of Contents

About This Document	xi
Palm OS Documentation.	xi
What This Volume Contains	xi
Summary of Changes	xii
Additional Resources	xiii
 1 Using Palm Debugger	 1
About Palm Debugger.	2
Connecting Palm Debugger With a Target	3
Connecting to The Palm OS Emulator.	4
Connecting to The Handheld Device	4
Using the Console and Debugging Windows Together	8
Entering Palm Debugger Commands	9
Palm Debugger Menus	10
Palm Debugger Command Syntax	12
Using the Debugging Window	15
Using Debugger Expressions	17
Performing Basic Debugging Tasks	22
Advanced Debugging Features.	29
Using the Source Window	32
Debugging With the Source Window	33
Using Symbol Files	33
Using the Source Menu	34
Source Window Debugging Limitations	36
Palm Debugger Error Messages.	36
Palm Debugger Tips and Examples	37
Performing Calculations	38
Shortcut Characters.	38
Repeating Commands	38
Finding a Specific Function	38
Finding Memory Corruption Problems	42
Displaying Local Variables and Function Parameters	44
Changing the Baud Rate Used by Palm Debugger	47
Debugging Applications That Use the Serial Port	48

Importing System Extensions and Libraries	48
Determining the Current Location Within an Application . .	49

2 Palm Debugger Command Reference 51

Command Syntax.	51
Specifying Numeric and Address Values	53
Using the Expression Language	53
Debugging Window Commands	53
>	54
alias	55
aliases	55
atb	55
atc	56
atd	56
atr	56
att	56
bootstrap	57
br	57
brc	58
brd	58
cardinfo.	58
cl.	59
db	59
dir	59
dl	61
dm	61
dump.	62
dw	62
dx	62
fb	63
fill	63
fl.	63
ft.	64
fw	64
g.	65

gt	65
hchk	65
hd	66
help	67
hl	68
ht	68
il	69
info.	69
keywords	70
load	70
opened	71
penv	71
reg	72
reset	72
run	72
s	73
save	73
sb	73
sc	73
sc6	74
sc7	75
sizeof	75
sl	75
ss	76
storeinfo	76
sw	77
t	77
templates	77
typedef	78
typeend	78
var	79
variables	79
wh	79
Debugging Command Summary	80
Flow Control Commands	80

Memory Commands	81
Template Commands	82
Register Commands	82
Utility Commands	82
Console Commands	83
Miscellaneous Debugger Commands	83
Debugger Environment Variables.	83
Predefined Constants	84

3 Debugger Protocol Reference 85

About the Palm Debugger Protocol	85
Packets	86
Packet Structure	86
Packet Communications.	88
Constants	88
Packet Constants	88
State Constants	89
Breakpoint Constants	89
Command Constants	89
Data Structures.	91
_SysPktBodyCommon	91
SysPktBodyType	91
SysPktRPCParamType	92
BreakpointType	92
Debugger Protocol Commands	93
Continue	93
Find	94
Get Breakpoints	95
Get Routine Name	96
Get Trap Breaks	98
Get Trap Conditionals.	99
Message	100
Read Memory	101
Read Registers	102
RPC	103

Set Breakpoints	103
Set Trap Breaks	104
Set Trap Conditionals	105
State	106
Toggle Debugger Breaks	108
Write Memory	109
Write Registers.	110
Summary of Debugger Protocol Packets	111

4 Using the Console Window 113

About the Console Window	113
Connecting the Console Window	114
Activating Console Input	114
Using Shortcut Numbers to Activate the Windows	115
Entering Console Window Commands	117
Command Syntax.	120
Specifying Numeric and Address Values	121
Console Window Commands	122
addrecord	123
addresource	123
attachrecord	124
attachresource	124
battery	124
cardformat	125
cardinfo.	125
changerecord	126
changeresource	126
close	126
coldboot	126
create.	127
del	128
delrecord	128
delresource	129
detachrecord.	129
detachresource.	129

dir	129
dm	131
doze	131
exit.	132
export	132
feature	133
findrecord.	134
free.	135
gdb.	135
getresource	135
gremlin	136
gremlinoff.	136
hc	136
hchk	136
hd	137
help	138
hf	138
hi	139
hl	139
hs	139
ht	140
htorture.	140
import	141
info.	142
kinfo	143
launch	144
listrecords.	144
listresources	144
lock	145
log	145
mdebug.	145
moverecord	147
new	147
open	148
opened	148

performance	148
poweron	149
reset	149
resize	150
saveimages	150
sb	150
setinfo	151
setowner	151
setrecordinfo	152
setresourceinfo.	152
simsync	152
sleep	153
storeinfo	153
switch	154
sysalarmdump.	154
unlock	155
Console Command Summary	155
Card Information Commands	155
Chunk Utility Commands	156
Database Utility Commands	156
Debugging Utility Commands	156
Gremlin Commands	157
Heap Utility Commands	157
Host Control Commands	157
Miscellaneous Utility Commands	157
Record Utility Commands.	158
Resource Utility Commands	158
System Commands	159

5 Using Palm Reporter 161

About Palm Reporter	161
Palm Reporter Features	161
Downloading Palm Reporter	162
Palm Reporter Package Files	162
Installing Palm Reporter	162

Adding Trace Calls to Your Application	163
Specifying Trace Strings	164
Trace Functions in a Code Sample	165
Displaying Trace Information in Palm Reporter	165
Starting a Palm Reporter Session	166
Filtering Information in a Palm Reporter Session	167
Using the Palm Reporter Toolbar	168
Troubleshooting Palm Reporter	169
6 Using the Overlay Tools	173
Using Overlays to Localize Resources	173
Overlay Database Names	174
Overlay Specification Resources	174
About the Overlay Tools	175
Using the PRC-to-Overlay Function	175
How the PRC-to-Overlay Function Works	175
Choosing a Locale	175
Modifying the Filter Set	176
PRC2OVL Example	177
Using the Patch Overlay Function	178
PRC2OVL Options Summary	179
Getting Help	181
Using PRC2OVL on the Macintosh	181
Opening a PRC file	181
Selecting Resources	181
A Resource Tools	183
B Simple Data Types	185
Index	187

About This Document

Palm OS® Programming Development Tools Guide describes various tools you can use to develop software for Palm Powered™ handhelds.

Palm OS Documentation

In addition to this book, you may be interested in the following Palm OS documentation:

Document	Description
<i>Palm OS Programmer's API Reference</i>	An API reference document that contains descriptions of all Palm OS function calls and important data structures.
<i>Palm OS Programmer's Companion</i> , vol. I and <i>Palm OS Programmer's Companion</i> , vol. II, <i>Communications</i>	A guide to application programming for the Palm OS. These volumes contain conceptual and "how-to" information that complements <i>Palm OS Programmer's API Reference</i> .
<i>Using Palm OS Emulator</i>	A guide to testing applications with Palm OS Emulator, including a reference of the Host Control API functions. The information in this book was previously part of <i>Palm OS Programming Development Tools Guide</i> .
<i>Testing with Palm OS Simulator</i>	A guide to testing application with Palm OS Simulator.
<i>Constructor for Palm OS</i>	A guide to creating application interfaces using Constructor for Palm OS.
<i>Palm OS User Interface Guidelines</i>	A guide describing how to design applications for Palm Powered handhelds.

What This Volume Contains

This volume is designed for random access. That is, you can read any chapter in any order. In general, each chapter covers a different

About This Document

Summary of Changes

Palm OS development tool, though chapters 2 through 4 discuss topics relating to Palm Debugger.

Here is an overview of this volume:

- [Chapter 1, “Using Palm Debugger,”](#) on page 1. Provides an introduction to Palm Debugger, which is an assembly language and limited source code level debugger for Palm OS programs. This chapter describes how to use Palm Debugger, including a description of its expression language and a variety of debugging strategies and tips.
- [Chapter 2, “Palm Debugger Command Reference,”](#) on page 51. Provides a complete reference description for each command available in Palm Debugger.
- [Chapter 3, “Debugger Protocol Reference,”](#) on page 85. Describes the API for sending commands and responses between a debugging host, such as Palm Debugger, and a debugging target, which can be a Palm Powered handheld ROM or an emulator program such as Palm OS Emulator.
- [Chapter 4, “Using the Console Window,”](#) on page 113. Describes how the Console Window can be used to perform maintenance and do high-level debugging of a Palm handheld device.
- [Chapter 5, “Using Palm Reporter,”](#) on page 161. Describes Palm Reporter, which is a trace utility that can be used with Palm OS Emulator.
- [Chapter 6, “Using the Overlay Tools,”](#) on page 173. Describes how you can create national language versions of your application by creating interface overlays.
- [Appendix A, “Resource Tools,”](#) on page 183. Provides a short description of resource tools that can be used to develop application resources.
- [Appendix B, “Simple Data Types,”](#) on page 185. Describes the simple data type name changes made in recent versions of the Palm OS software.

Summary of Changes

- Chapters from the prior edition of this manual (“Using Palm OS Emulator” and “Host Control API”) have been moved

from this book into a new manual called *Using Palm OS Emulator*. For more information, see the Palm OS documentation web page.

- [Chapter 5, “Using Palm Reporter,”](#) on page 161 has been updated to include information on the Macintosh version of Palm Reporter.

Additional Resources

- Documentation

PalmSource publishes its latest versions of this and other documents for Palm OS developers at

<http://www.palmos.com/dev/support/docs/>

- Training

PalmSource and its partners host training classes for Palm OS developers. For topics and schedules, check

<http://www.palmos.com/dev/training>

- Knowledge Base

The Knowledge Base is a fast, web-based database of technical information. Search for frequently asked questions (FAQs), sample code, white papers, and the development documentation at

<http://www.palmos.com/dev/support/kb/>

Using Palm Debugger

Palm Debugger is a tool for debugging Palm OS® applications. Palm Debugger is available for use on both Mac OS and Windows platforms.

This chapter provides an introduction to and overview of using Palm Debugger. The commands that you can use are described in [Chapter 2](#), “[Palm Debugger Command Reference](#).”

This chapter contains the following sections:

- “[About Palm Debugger](#)” on page 2 provides a broad overview of the program and a description of its windows.
- “[Connecting to The Handheld Device](#)” on page 4 describes how to connect Palm Debugger with the Palm OS Emulator or with a Palm Powered™ handheld device.
- “[Using the Console and Debugging Windows Together](#)” on page 8 describes how to use the menus and keyboard to send commands to the handheld device from the debugging and console windows.
- “[Using the Debugging Window](#)” on page 15 and “[Using the Source Window](#)” on page 32 describe the command and display capabilities available in each of these windows. The debugging window section also includes a full description of “[Using Debugger Expressions](#)” on page 17.
- “[Palm Debugger Error Messages](#)” on page 36 describes how to decode the error messages you receive from Palm Debugger.
- “[Palm Debugger Tips and Examples](#)” on page 37 provides a collection of tips to make your debugging efforts easier and examples of performing common debugging tasks.

About Palm Debugger

Palm Debugger provides source and assembly level debugging of Palm OS applications, and includes the following capabilities:

- support for managing Palm OS databases
- communication with Palm™ handheld devices
- communication with Palm OS Emulator, the Palm emulation program
- command line interface for system administration on Palm handheld devices

NOTE: You can use Palm Debugger with a Palm Powered handheld device, or with the Palm OS Emulator program. Debugging is the same whether you are sending commands to the emulator or to actual hardware. Connecting with either a handheld device or the Emulator is described in [“Connecting Palm Debugger With a Target”](#) on page 3.

Palm Debugger provides two different interfaces that you can use to send commands from your desktop computer to the handheld device:

- The console interface is provided by the *console nub* on the handheld device. You can connect to the console nub and then send console commands to the nub from Palm Debugger’s console window. The console commands are used primarily for administration of databases on the handheld device.

The console can also be used with Palm Simulator and the CodeWarrior Debugger, and is documented in a separate chapter. For more information about the console window and the console commands, see [Chapter 4, “Using the Console Window.”](#)
- The debugging interface is provided by the *debugger nub* on the handheld device. You can attach to the debugger nub and then send debugging commands to the debugger nub from Palm Debugger’s debugging window. For more information about using the debugging window and the debugging commands, see [“Using the Debugging Window”](#) on page 15.

The console window and the debugging window each has its own set of commands that you can use to interface with the handheld device. The debugging commands are described in [Chapter 2](#), “[Palm Debugger Command Reference](#),” and the console window commands are described in [Chapter 4](#), “[Using the Console Window](#).”

NOTE: The Palm OS Emulator emulates the console and debugging nubs, which allows Palm Debugger to send the same commands to the Emulator as it does to a handheld device.

On certain platforms, Palm Debugger also provides a multi-pane source window for source-level debugging. You can use this window if you have compiled your program with certain compilers that generate an appropriate symbol file. [Table 1.1](#) summarizes the Palm Debugger windows.

Table 1.1 Palm Debugger Windows

Window name	Usage
Console	Command language shell for performing administrative tasks, including database management, on the handheld device.
CPU Registers	Assembly language debugging output only window.
Debugging	Assembly language debugging command window.
Source	Source level debugging window.

NOTE: Source level debugging is not currently available in the Macintosh version of palm Debugger.

Connecting Palm Debugger With a Target

You can use Palm Debugger to debug programs running on a Palm Powered handheld device or to debug programs running on a

Using Palm Debugger

Connecting Palm Debugger With a Target

hardware emulator such as the Palm OS Emulator. This section describes how to connect the debugger to each of these targets.

Connecting to The Palm OS Emulator

You can interact with the Palm OS Emulator from Palm Debugger just as you do with actual hardware. With the emulator, you don't need to activate the console or debugger stubs. All you need to do is follow these steps:

1. In the Palm Debugger Communications menu, select **Emulator**. This establishes the emulator program as the "device" with which Palm Debugger is communicating.
2. In the debugging window, type the `att` command.

Connecting to The Handheld Device

You can interact with the handheld device from Palm Debugger by issuing commands from the console window or from the debugging window.

You must activate the console nub on the handheld device before sending commands from the console window. For more information on activating console input, see [Chapter 4, "Using the Console Window."](#)

WARNING! When you activate either the console nub or the debugger nub on the handheld device, the device's serial port is opened. This causes a rapid and significant power drain. The only way to close the port and stop the power drain is to perform a soft reset.

Activating Debugging Input

If you are debugging with the Palm OS Emulator, you can activate debugging input by sending the `att` command from the debugging window to the emulator.

To send debugging commands to a hardware device, you must connect your desktop computer to the handheld device, halt the device in its debugger nub, and then type commands into the debugging window of Palm Debugger.

IMPORTANT: When the handheld device is halted in its debugger nub, a tiny square flashes in the upper left corner of the screen, and the device does not respond to pen taps or key presses.

You can use the following methods to halt the handheld in its debugger nub:

1. Use the to enter debugger mode on the handheld device, as described in “[Using Shortcut Numbers to Activate the Windows](#)” on page 6.
2. If you have already activated the console nub, you can use the **Break** command in the Source menu to activate the debugger nub. The **Break** command sends a key command to the handheld device that is identical to using the sequence.
3. Compile a `DbgBreak()` call into your application, and run the application until you encounter that call.

This method only works if you have already entered debugger mode once, or if you have set the low memory global variable `GDbgWasEntered` to a non-zero value, which tricks the handheld into thinking that the debugger was previously entered. For example, you can use the following code in your application to ensure that your break works:

```
GDbgWasEntered = true;
DbgBreak();
```

4. You can hold the down button and press the reset button in the back of the device.

This halts the device in the *SmallROM* debugger, which is the bootstrap code that can initialize the hardware and start the debugger nub. Enter the `g` command, and the system jumps into the *BigROM*, which contains the same code as the *SmallROM* and all of the system code.

If you press the down button on the handheld device while executing the `g` command, you land in the *BigROM*'s debugger. This lets you set A-trap breaks or single step through the device boot sequence.

Using Palm Debugger

Connecting Palm Debugger With a Target

Verifying Your Connection

If Palm Debugger is running and connected when the handheld device halts into its debugger nub, the debugging window displays a message similar to the following:

```
EXCEPTION ID = $A0
'SysHandleEvent '
+$0512 10C0EEFE *MOVEQ.L #$01,D0 | 7001
```

Alternatively, if Palm Debugger is not connected or running when the device halts, you can use the [att](#) command to attach Palm Debugger to the device.

IMPORTANT: The debugger nub activates at 57,600 baud, and your port configuration must match this if you are connecting over a serial port. You can set the connection parameters correctly with Palm Debugger Connection menu.

After you activate the debugger nub on the handheld device, the nub prevents other applications, including HotSync® from using the serial port. You have to soft-reset the handheld device before the port can be used.

Using Shortcut Numbers to Activate the Windows

The Palm OS responds to a number of “hidden” shortcuts for debugging your programs, including shortcuts for activating the console and debugger nubs on the handheld device. You generate each of these shortcuts by drawing characters on your Palm Powered device, or by drawing them in the Palm OS Emulator program, if you are using Palm OS Emulator to debug your program.

NOTE: If you open the Find dialog box on the handheld device before entering a shortcut number, you get visual feedback as you draw the strokes.

To enter a shortcut number, follow these steps:

1. On your Palm Powered device, or in the emulator program, draw the shortcut symbol. This is a lowercase, cursive “L” character, drawn as follows:




2. Next, tap the stylus twice, to generate a dot (a period).
3. Next, draw a number character in the number entry portion of the device’s text entry area. [Table 1.2](#) shows the different shortcut numbers that you can use.

For example, to activate the console nub on the handheld device, enter the follow sequence:





Table 1.2 Shortcut Numbers for Debugging

Shortcut	Description	Notes
	The device enters debugger mode, and waits for a low-level debugger to connect. A flashing square appears in the top left corner of the device.	<p>This mode opens a serial port, which drains power over time.</p> <p>You must perform a soft reset or use the debugger’s reset command to exit this mode.</p>

Using Palm Debugger

Connecting Palm Debugger With a Target

Table 1.2 Shortcut Numbers for Debugging (*continued*)

Shortcut	Description	Notes
 .2	The device enters console mode, and waits for communication, typically from a high-level debugger.	This mode opens a serial port, which drains power over time. You must perform a soft reset to exit this mode.
 .3	The device's automatic power-off feature is disabled.	You can still use the device's power button to power it on and off. Note that your batteries can drain quickly with automatic power-off disabled. You must perform a soft reset to exit this mode.

NOTE: These debugging shortcuts leave the device in a mode that requires a soft reset. To perform a soft reset, press the reset button on the back of the handheld with a blunt instrument, such as a paper clip.

Using the Console and Debugging Windows Together

When Palm Debugger is attached to a handheld device or emulator program, you cannot talk to the console nub on the device. However, a subset of the console commands — those that do not change the contents of memory — are available from the debugging window. These include the following commands:

- [dir](#)
- [hl](#)
- [hd](#)
- [hchk](#)
- [mdebug](#)

- [reset](#)

You can enter these commands in either the debugging window or the console window when the debugger nub is active. When you enter a console command while the debugging window is attached, the command is sent to the debugger nub rather than the console nub.

You can use the console commands while debugging for purposes such as displaying a heap dump in the console window while stepping through code in the debugging window.

Entering Palm Debugger Commands

Most of your work with Palm Debugger is done with the keyboard. You enter console commands into the console window, and debugging commands into the debugging window. Both of these windows supports standard scrolling and clipboard operations.

[Table 1.3](#) summarizes the keyboard commands that you can use to enter commands in Palm Debugger's console or debugging windows.

Table 1.3 Entering Palm Debugger Commands From the Keyboard

Command description	Windows key(s)	Macintosh key(s)
Execute selected text as command(s). You can select multiple lines to sequentially execute multiple commands.	Enter	Enter on numeric keypad, or CMD+RETURN
Execute the current line (no text selected).		
Display help for a command	Help <cmdName>	Help <cmdName>
Enter a new line without executing the text	SHIFT+ENTER	Return
Copy selected text from window to clipboard	CTRL+C	CMD+C

Using Palm Debugger

Entering Palm Debugger Commands

Table 1.3 Entering Palm Debugger Commands From the Keyboard (*continued*)

Command description	Windows key(s)	Macintosh key(s)
Paste clipboard contents to window	CTRL+V	CMD+V
Cut selected text from window to clipboard	CTRL+X	CMD+X
Delete previous command's output from the window	CTRL+Z	Not available
Delete all text to the end	SHIFT+Backspace	CMD+DELETE

Palm Debugger Menus

Palm Debugger includes five menus, as summarized in [Table 1.4](#). The most commonly used menu commands are on the Connection and Source menus; these commands are described in other sections in this chapter.

Table 1.4 Palm Debugger Menu Commands

Menu	Commands	Descriptions
File	<u>O</u> pen	Commands for saving and printing the contents of a window.
	<u>S</u> ave	
	<u>S</u> ave <u>A</u> s	
	<u>P</u> age Setup...	
	<u>P</u> rint	
Edit	<u>E</u> xit	Standard editing commands
	<u>U</u> ndo	
	<u>R</u> edo	
	Cut	
	Copy	
	Paste	
	Select All	
	Find	
	Find Next	
	Font	
Connection	(select baud rate)	For setting up how to communicate with the handheld device or Palm OS Emulator.
	Handshake	
	(select connection port)	

Using Palm Debugger

Entering Palm Debugger Commands

Table 1.4 Palm Debugger Menu Commands (*continued*)

Menu	Commands	Descriptions
Source	Break	Source code debugging commands, for use in conjunction with the source window.
	Step Into	
	Step Over	
	Go	
	Go Till	NOTE: Source level debugging is not currently available in the Macintosh version of Palm Debugger.
	Toggle Breakpoint	
	Disassemble at Cursor	
	Show Current Location	
	Install Database and Load Symbols	
	Load Symbols	
	Load Symbols for Current Program Counter	
	Remove All Symbols	
Window	Cascade	Standard window access commands.
	Tile	
	Arrange Icons	NOTE: Only available on Windows systems.
	Close All	
	Keyboard Simulator...	
	(select numbered window)	

Palm Debugger Command Syntax

Palm Debugger's help facility uses simple syntax to specify the format of the commands that you can type in the console and debugging windows. This same syntax is used in [Chapter 2](#), "[Palm](#)

[Debugger Command Reference](#).” This section summarizes that syntax.

The basic format of a command is specified as follows:

<code>commandName <parameter>* [options]</code>	
<code>commandName</code>	The name of the command.
<code>parameter</code>	Parameter(s) for the command. Each parameter name is enclosed in angle brackets (< and >). Sometimes a parameter can be one value or another. In this case the parameter names are bracketed by parentheses and separated by the character.
<code>options</code>	Optional flags that you can specify with the command. Note that options are specified with the dash (-) character in the console window and with the backslash (\) character in the debugging window.

NOTE: Any portion of a command that is shown enclosed in square brackets (“[” and “]”) is optional.

The following is an example of a command definition

```
dir (<cardNum>|<srchOptions>) [displayOptions]
```

The `dir` command takes either a card number of a search specification, followed by display options.

Here are two examples of the `dir` command sent from the console window:

```
dir 0 -a
dir -t rsrc
```

And here are the same two commands sent from the debugging window:

```
dir 0 \a
dir \t rsrc
```

Specifying Command Options

All command options and some command parameters are specified as flags that begin with a dash (in the console window) or backslash (in the debugging window). For example:

```
-c
-enable
\enable
```

Some flags are followed by a keyword or value. You must leave white space between the flag and the value. For example:

```
-f D:\temp\myLogFile
\t Rsrc
```

Specifying Numeric and Address Values

Many of the debugging commands take address or numeric arguments. You can specify these values in hexadecimal, decimal, or binary. All values are assumed to be hexadecimal unless preceded by a sign that specifies decimal (#) or binary (%). [Table 1.5](#) shows values specified as binary, decimal, and hexadecimal in a debugging command:

Table 1.5 Specifying Numeric Values in Palm Debugger

Hex value	Decimal value	Binary value
64 or \$64	#100	%01100100
F5 or \$F5	#245	%11110101
100 or \$100	#256	%100000000

IMPORTANT: Some register names, like A0 and D4, look like hexadecimal values. You must preface these values with the dollar sign (\$) character, or you will get the value of the register. For example, A4 + 3 computes to the value of the A4 register added with three, but \$A4 + 3 computes to \$A7.

For more information, see “[Specifying Constants](#)” on page 17.

Using the Debugging Window

You use the debugging window to enter debugging commands, which are used to perform assembly language debugging of applications on the handheld device. Commands that you type into the debugging window are sent to the debugger nub on the handheld device, and the results sent back from the device are displayed in the debugging window.

The debugging window provides numerous capabilities, including the following:

- A rich expression language for specifying command arguments, as described in [“Using Debugger Expressions”](#) on page 17.
- Ability to debug applications, system code, extensions, shared libraries, background threads, and interrupt handlers.
- Custom aliases for commands or groups of commands, as described in [“Defining Aliases”](#) on page 31.
- Script files for saving and reusing complex sequences of commands, as described in [“Using Script Files”](#) on page 31.
- Templates for defining data structure layouts in memory, which allow you to view a structure with the memory display commands. Templates are described in [“Defining Structure Templates”](#) on page 29.
- Your aliases and templates can be saved in files that are automatically loaded for you when Palm Debugger starts execution, as described in [“Automatic Loading of Definitions”](#) on page 31.

This section also provides examples of using some of the more common debugging commands:

- See [“Displaying Registers and Memory”](#) on page 23 for examples of using the debugging commands to display the current register values.
- See [“Using the Flow Control Commands”](#) on page 25 for examples of using commands to set breakpoints.
- See [“Using the Heap and Database Commands”](#) on page 28 for examples of using commands to examine the heap and databases.

Using Palm Debugger

Using the Debugging Window

The remainder of this section describes how to use these capabilities. [Table 1.6](#) shows the most debugging window command categories.

Table 1.6 Debugging Window Command Categories

Category	Description	Commands
Console	Commands shared with the console window for viewing card, database, and heap information.	cardinfo, dir, hchck, hd, hl, ht, info, opened, storeinfo
Flow Control	Commands for working with breakpoints, A-traps, and program execution control.	atb, atc, atd, br, brc, cl, brd, dx, g, gt, s, t, reset
Memory	Commands for viewing the registers, and for displaying and setting memory, the stack, and system function information.	atr, db, dl, dm, dw, fb, fill, fl, ft, fw, il, reg, sb, sc, sc6, sc7, sl, sw, wh
Miscellaneous	Commands for displaying debugging help and current debugging environment information.	att, help, penv
Template	Commands for defining and reviewing structure templates.	>, sizeof, typedef, typeend
Utility	Commands for working with aliases, symbol files, and variables.	alias, aliases, bootstrap, keywords, load, run, save, sym, templates, var, variables

All of the debugging commands are described in detail in [Chapter 2](#), “[Palm Debugger Command Reference](#).”

Before you can use the debugging commands, you must attach Palm Debugger to the debugger nub on the handheld device, as described in “[Activating Debugging Input](#)” on page 4.

Using Debugger Expressions

Palm Debugger provides a rich expression language that you can use when specifying arguments to the debugging commands. This section describes the expression language.

NOTE: Debugger expressions cannot contain white space. White space delimits command parameters; thus, any white space ends an expression.

Specifying Constants

The expression language lets you specify numbers as character constants.

Character Constants

A character is a string enclosed in single quotes. The string can include escape sequences similar to those used in the C language. For example:

```
'xyz1'  
'a\'Y\''  
'\123'
```

Character constants are interpreted as unsigned integer values. The size of the resulting value depends on the number of characters in the string, as follows:

Number of characters	Result type
1 character	UInt8
2 characters	UInt16
more than 2 characters	UInt32

Binary Numbers

To specify a binary number, use the percent sign (%) character followed by any number of binary digits. For example:

Using Palm Debugger

Using the Debugging Window

```
%00111000
```

```
%1010
```

The size of the resulting value is determined as follows:

Number of Digits	Result Type
1 to 8	UInt8
8 to 16	UInt16
more than 16	UInt32

Decimal Numbers

To specify a decimal number, use the # character followed by any number of decimal digits. For example:

```
#256
```

```
#32756
```

Hexadecimal Numbers

Palm Debugger interprets hexadecimal digit strings that are not preceded by a special character as hexadecimal numbers. You can optionally use the dollar sign (\$) character to indicate that a value is hexadecimal. For example:

```
c123
```

```
C123
```

```
F0
```

```
$A0
```

The size of the resulting value is determined as follows:

Number of digits	Result type
1 to 2	UInt8
3 to 4	UInt16
more than 4	UInt32

WARNING! If you want to specify a hexadecimal value that can also be interpreted as a register name, you must preface the value with the dollar sign (\$) symbol. For example, using `A0` in an expression will generate the current value of the `A0` register, while using `$A0` will generate the hexadecimal equivalent of the decimal value `160`.

Using Operators

Palm Debugger expression language includes the typical set of binary and unary operators, as summarized in [Table 1.7](#).

Table 1.7 Palm Debugger Expression Language Operators

Type	Operator	Description	Example
Cast	<code>.a</code>	Casts the value to an address.	<code>0xff0.a</code>
	<code>.b</code>	Casts the value to a byte.	<code>45.b</code>
	<code>.l</code>	Casts the value to a double word.	<code>45.l</code>
	<code>.w</code>	Casts the value to a word.	<code>45.w</code>
	<code>.s</code>	Extends the sign of its operand without changing the operand's size.	<code>45.s</code>
Unary	<code>~</code>	Performs a bitwise NOT of the operand.	<code>~1</code>
	<code>-</code>	Changes the sign of the operand.	<code>2*-1</code>
Dereference	<code>@</code>	Dereferences an address or integer value. See Table 1.8 for more examples.	<code>@A7</code>
Arithmetic	<code>*</code>	Multiplies the two operands together.	<code>A1*2</code>
	<code>/</code>	Divides the first operand by the second operand.	<code>21/3</code>
	<code>+</code>	Adds the two operands together.	<code>A2+2</code>
	<code>-</code>	Subtracts the second operand from the first operand.	<code>A2-2</code>

Table 1.7 Palm Debugger Expression Language Operators (*continued*)

Type	Operator	Description	Example
Assignment	=	Assigns the second operand value to the register specified as the first operand.	d0=45
Bitwise	&	Performs a bitwise AND operation.	A7&FFF
	^	Performs a bitwise XOR operation.	A2^F0F0
		Performs a bitwise OR operation.	A2 %1011

The Dereference Operator

The @ dereference operator is similar to the * dereference operator used in the C programming language. This operators dereferences an address value, as shown in [Table 1.8](#).

Table 1.8 Dereference Operator Examples

Expression	Description	Example
@	Retrieves 4 bytes as an unsigned integer value	@A7
@.a	Retrieves 4 bytes as an address	@.a (A1)
@.b	Retrieves 1 byte as an unsigned integer value	@.b (PC)
@.w	Retrieves 2 bytes as an unsigned integer value	@.w (PC)
@.l	Retrieves 4 bytes as an unsigned integer value	@.l (A2)

Register Variables

The expression language provides named variables for each register. The names of these variables are replaced by their respective register values in any expression. [Table 1.9](#) shows the register name variables.

Table 1.9 The Built-in Register Variables

Variable name	Description
a0	address register 0
a1	address register 1
a2	address register 2
a3	address register 3
a4	address register 4
a5	address register 5
a6	address register 6
a7	address register 7
d0	data register 0
d1	data register 1
d2	data register 2
d3	data register 3
d4	data register 4
d5	data register 5
d6	data register 6
d7	data register 7
pc	the program counter
sr	the status register
sp	the stack pointer (this is an alias for a7)

NOTE: The expression parser interprets any string that can represent a register name as a register name. If you want the string interpreted as a hexadecimal value instead, precede it with either a 0 or the dollar sign (\$) character.

For example, the following expression:

a0+d0

Adds the values stored in the a0 and d0 registers together.

If you want to add the value 0xd0 to the value stored in register a0, use one of the following expressions:

a0+0d0

a0+\$d0

Special Shortcut Characters

Palm Debugger's expression language includes the two special value characters shown in [Table 1.10](#). These characters are converted into values in any expression.

Table 1.10 Special Value Expression Characters

Character	Converts into	Examples
.	The most recently entered address.	dm . dm .+10
:	The starting address of the current routine.	il : il :+24

Performing Basic Debugging Tasks

This section describes how to use Palm Debugger to perform three of the most common debugging tasks:

- displaying memory values
- setting breakpoints and using the flow control commands
- examining the heap

The final section of this chapter, “[Palm Debugger Tips and Examples](#)” on page 37, provides examples of how to perform other debugging tasks.

Assigning Values to Registers

You can use the assignment operator (=) to assign a value to a register. However, if you include white space around the operator, the assignment does not work. For example, the following statement correctly assigns a value to the program counter:

```
pc=010c8954
```

However, this statement does not assign the correct value to the program counter:

```
pc = 010c8954c
```

Displaying Registers and Memory

One of the primary operations you perform with a debugger is to examine and change values in memory. Palm Debugger provides a number of commands for displaying registers, memory locations, the program counter, and the stack. [Table 1.11](#) summarizes the commands you commonly use to examine memory and related values.

Table 1.11 Frequently Used Memory Commands

Command	Description
db	Displays the byte value at a specified address.
d1	Displays the 32-bit long value at a specified address.
dm	Displays memory for a specified number of bytes or templates.
dw	Displays the 16-bit word value at a specified address.
il	Disassembles code in a specified line range or for a specified function name.
reg	Displays all registers.
sb	Sets the value of the byte at the specified address.

Table 1.11 Frequently Used Memory Commands (*continued*)

Command	Description
sc	Lists the A6 stack frame chain, starting at the specified address.
sc7	Lists the A7 stack frame chain, starting at the specified address.
sl	Sets the value of the 32-bit long value at the specified address.
sw	Sets the value of the word at the specified address.

Palm Debugger also lets you define structure templates and use those for displaying memory values. For example, you can define a structure that matches the layout of a complex data structure, and then display that structure with a single **dm** command. For more information about structure templates, see [“Defining Structure Templates”](#) on page 29.

[Listing 1.1](#) shows an example of displaying memory with the **dm** command and disassembling memory with the **il** command. It also provides several examples of using expressions with these commands. In this example, **boldface** is used to denote commands that you type, and **<=** starts a comment.

Listing 1.1 Displaying and Disassembling Memory

```
dm 0                                <=Display memory at address 0
00000000: FF FF FF FF 1A 34 3E 40 10 C0 92 D4 10 C0 92 F2 ".....4>@....."

dm 100                             <=Display memory at address 0x100
00000100: 01 01 00 00 02 B0 00 01 78 30 00 00 00 01 47 EE ".....x0....G."

dm #100                            <=Display memory at address 100 decimal
00000064: 10 C6 BE 32 10 C6 BE 60 10 C6 BE 8E 10 C6 BE BC "...2...`....."

dm 100+20                          <=Specify an address with an expression
00000120: 6F BC 00 00 07 22 00 00 00 06 00 01 7D 72 00 FD "o...."}r.."

dm .+10                            <=Use the'.' character for the most recent addr
00000130: 00 00 00 00 00 00 00 B6 3E C0 69 45 A4 0C 03 4A ".....>.iE...J"
```

```
dm pc                                <=Use the current program counter value
10C0EEFE: 70 01 60 00 01 7E 4E 4F A0 BE 70 01 60 00 01 74 "p.`...~NO..p.`...t"

dm pc+20                             <=An expression using the program counter
10C0EF1E: FF F4 4E 4F A0 AC 38 00 4A 44 50 4F 66 2A 48 6E "...NO..8.JDPOf*Hn"

il pc                                <=Disassemble code at current program counter
'SysHandleEvent 10C0E9EC'
+$0512 10C0EEFE *MOVEQ.L #$01,D0      | 7001
+$0514 10C0EF00 BRA.W SysHandleEvent+$0694 ; 10C0F080      | 6000 017E
+$0518 10C0EF04 _SysLaunchConsole ; $10C0E30C      | 4E4F A0BE
+$051C 10C0EF08 MOVEQ.L #$01,D0      | 7001
+$051E 10C0EF0A BRA.W SysHandleEvent+$0694 ; 10C0F080      | 6000 0174
+$0522 10C0EF0E MOVEQ.L #$00,D0      | 7000
+$0524 10C0EF10 BRA.W SysHandleEvent+$0694 ; 10C0F080      | 6000 016E
+$0528 10C0EF14 CLR.L -$0010(A6)     | 42AE FFF0
+$052C 10C0EF18 PEA -$0006(A6)       | 486E FFFA
+$0530 10C0EF1C PEA -$000C(A6)       | 486E FFF4

il pc-10                             <=Display code at program counter - 0x10
'SysHandleEvent 10C0E9EC'
+$0502 10C0EEEE ORI.B #$01,(A5)+ ; '.'      | 001D 7001
+$0506 10C0EEF2 BRA.W SysHandleEvent+$0694 ; 10C0F080      | 6000 018C
+$050A 10C0EEF6 MOVE.B #$01,$00000101 ; '.'      | 11FC 0001 0101
+$0510 10C0EEFC _DbgBreak      | 4E48
+$0512 10C0EEFE *MOVEQ.L #$01,D0      | 7001
+$0514 10C0EF00 BRA.W SysHandleEvent+$0694 ; 10C0F080      | 6000 017E
+$0518 10C0EF04 _SysLaunchConsole ; $10C0E30C      | 4E4F A0BE
+$051C 10C0EF08 MOVEQ.L #$01,D0      | 7001
+$051E 10C0EF0A BRA.W SysHandleEvent+$0694 ; 10C0F080      | 6000 0174
+$0522 10C0EF0E MOVEQ.L #$00,D0      | 7000
```

All of the commands mentioned in this section are described in detail in [Chapter 2, “Palm Debugger Command Reference.”](#)

Using the Flow Control Commands

Palm Debugger provides a number of commands for setting breakpoints and continuing the flow of execution. [Table 1.12](#) summarizes the commands you commonly use for these purposes.

Table 1.12 Commonly Used Flow Control Commands

Command	Description
atb	Adds an A-trap break.
atc	Clears an A-trap break.
atd	Displays all A-trap breaks.
br	Sets a breakpoint.
brc	Clears a breakpoint. This is the same as the <code>cl</code> command.
brd	Display all breakpoints.
cl	Clears a breakpoint. This is the same as the <code>brc</code> command.
g	Continues execution until the next breakpoint is encountered.
gt	Sets a temporary breakpoint at the specified address, and resumes execution from the current program counter.
s	Single steps one source line, stepping into functions.
ss	Step-spy: step until the value of the specified address changes.
t	Single steps one source line, stepping over functions.

[Listing 1.2](#) shows an example of setting breakpoints, disassembling, and using other flow control commands to debug an application. In this example, **boldface** is used to denote commands that you type, and `<=` starts a comment.

Listing 1.2 Using the Debugging Flow Control Commands

sc <= Display stack crawl, listed from oldest to newest. In this
 <= example, the current fcn was called from EventLoop+0016
Calling chain using A6 Links:
A6 Frame Caller
00000000 10C68982 cjtken+0000
00015086 10C6CA26 __Startup__+0060
00015066 10C6CCCE PilotMain+0250
00014FC2 10C0F808 SysAppLaunch+0458
00014F6E 10C10258 PrvCallWithNewStack+0016
00013418 10CD88B2 __Startup__+0060
000133F8 10CDB504 PilotMain+0036
000133DE 10CDB47C EventLoop+0016

s <= Single-Step one instruction
'SysHandleEvent' Will Branch
+\$0514 10C0EF00 *BRA.W SysHandleEvent+\$0694 ; 10C0F080 | 6000 017E
 <= Single step again by pressing the ENTER key
+\$0694 10C0F080 *MOVEM.L (A7)+,D3-D5/A2-A4 | 4CDF 1C38
 <= Press ENTER again
+\$0698 10C0F084 *UNLK A6 | 4E5E
 <= ... and again
+\$069A 10C0F086 *RTS | 4E75 8E53 7973 4861
 <= ... and again
+\$0018 10CDB47E *TST.B D0 | 4A00

il <= Disassemble at current program counter
'EventLoop 10CDB466'
+\$0018 10CDB47E *TST.B D0 | 4A00
+\$001A 10CDB480 LEA \$000C(A7),A7 | 4FEF 000C
+\$001E 10CDB484 BNE.S EventLoop+\$0050 ; 10CDB4B6 | 6630
... <= Remainder of disassembly removed here

gt 10cdb484 <= Go-Till address 0x10CDB484
+\$001E 10CDB484 *BNE.S EventLoop+\$0050 ; 10CDB4B6 | 6630

br :+50 <= Set a breakpoint at current routine+0x50
Breakpoint set at 10CDB4B6 (EventLoop+0050)

g <= Go until a break occurs
+\$0050 10CDB4B6 *CMPI.W #\$0016,-\$0018(A6) ; '..' | 0C6E 0016 FFE8

brd <= Display all currently set breakpoints
10CDB4B6 (EventLoop+0050)

cl <= Clear all breakpoints

Using Palm Debugger

Using the Debugging Window

All breakpoints cleared

atb "EvtGetEvent" <= Break whenever the EvtGetEvent system trap is called
A-trap set on 011d (EvtGetEvent)

g <= Go until a break occurs
Remote stopped due to: A-TRAP BREAK EXCEPTION
'EvtGetEvent'
+\$0000 10C3B1E2 *LINK A6,\$0000 | 4E56 0000

atc <= Clear all A-Traps
All A-Traps cleared

ss a2 <= Step-Spy until the UInt32 at address 0x15404 changes
<= (the current value of register A2 is 0x15404)
Step Spying on address: 00015404
'EvtGetSysEvent'
+\$00E8 10C1E980 *CLR.B \$0008(A4) | 422C 0008

TIP: Some commands, like the `atb` command, require that the operand be quoted. Forgetting to quote the trap name in the `atb` command is a common mistake with Palm Debugger.

All of the commands mentioned in this section are described in detail in [Chapter 2, “Palm Debugger Command Reference.”](#)

Using the Heap and Database Commands

You can use the heap and database commands to display information about the databases and heaps on the handheld device. These commands, which are summarized in [Table 1.13](#), mirror commands available from the console window.

Table 1.13 Commonly Used Heap and Database Commands

Command	Description
dir	Lists the databases.
hchk	Checks a heap.
hd	Displays a dump of a memory heap.

Table 1.13 Commonly Used Heap and Database Commands (*continued*)

Command	Description
hl	Lists all of the memory heaps on the specified memory card.
ht	Performs a heap summary.

The heap commands take heap ID values as parameters. The following table shows the values you can use for heap IDs.

Heap ID	Description
0	The dynamic heap.
1	The storage heap.

All of the commands mentioned in this section are described in detail in [Chapter 2, “Palm Debugger Command Reference.”](#)

To learn more about the console window and all of the console commands, see [Chapter 4, “Using the Console Window.”](#)

Advanced Debugging Features

This section presents several advanced features of the debugging window of Palm Debugger, including the following:

- defining structure template for displaying memory
- defining aliases for commands
- using script files to run sequences of commands
- automated loading of structure and alias definitions at program start-up time

Defining Structure Templates

You can define structure templates to use with Palm Debugger’s memory display commands. Each template matches a data type or structure type that you use in your application, which lets you display a structure in the debugging window with one command.

You define templates in a manner similar to the way you define structure types in a high-level programming language: start a template definition with the `typedef` command, follow with some number of field definition (`>`) commands, and finish with a `typeend` command. And once you have defined a structure template, you can use fields of that type in other template definitions.

[Table 1.14](#) summarizes the commands you use to define and display templates. For more information about these commands, see [Chapter 2, “Palm Debugger Command Reference.”](#)

Table 1.14 Structure Template Commands

<code>></code>	Defines a structure field.
<code>sizeof</code>	Displays the size, in bytes, of a template.
<code>templates</code>	Lists the names of the debugger templates.
<code>typedef</code>	Begins a structure definition block.
<code>typeend</code>	Ends a structure definition block.

Note that the structure and field names must be quoted in your structure template definition commands. [Listing 1.3](#) shows the debugging commands used to define a template named `PointType`, and then defines a second template named `RectangleType` that uses two `PointType` fields.

Listing 1.3 Defining and using two structure templates

```
typedef struct "PointType"
> Int16 "X"
> Int16 "Y"
typeend

typedef struct "RectangleType"
> PointType "topLeft"
> PointType "extent"
typeend

sizeof PointType
```

```
Size = 4 byte(s)

sizeof RectangleType
Size = 8 byte(s)

dm 0 RectangleType
00000000 struct    RectangleType
        {
00000000    PointType topLeft
            {
00000000        Int16 x          = $-1
00000002        Int16 y          = $-1
            }
00000004    PointType extent
            {
00000004        Int16 x          = $1A34
00000006        Int16 y          = $3E40
            }
        }
    }
```

Defining Aliases

For convenience, you can create aliases. Each alias stands for a specific command sequence. For example:

```
alias "checkheap" "hchk 0 -c"
alias "ls" "dir 0"
```

After defining these aliases, you can type `ls` to display a directory listing for card 0 (built-in RAM), and you can type `checkheap` to check heap 0 with examination of each chunk.

Using Script Files

You use the `run` command to run a script file. A script file is any text file that contains debugging commands. For example, the following command reads and executes the debugging commands found in the text file named `MyCommands`:

```
run "MyCommands"
```

Automatic Loading of Definitions

When Palm Debugger is launched, it automatically runs the script file named `UserStartupPalmDebugger`. You can store your

aliases, script files, and data structure templates in this file to have them available whenever you use Palm Debugger.

Using the Source Window

This section describes the source window, which you can use to perform limited debugging with the source code for your application.

NOTE: Palm Debugger's source level debugging is only available on Windows systems, and is only available for code that has been built using the GNU gcc compiler for Palm OS.

The source window works in conjunction with the debugging and CPU registers windows. For example, if you single step in the debugging window, the source window tracks along and displays any breakpoints that are currently set.

The source window is split into two panes:

- The upper pane displays the values of local variables for the current function.
- The lower pane displays the source code. This pane is automatically updated whenever you move through your code with flow control commands. You can also scroll this pane to view the code or to set a breakpoint.

The left margin of the lower pane displays indicators for breakpoints and the current program counter:

- a solid red circle is displayed next to a line that contains a breakpoint
- a green arrow is displayed next to the line containing the current program location

The two panes in the source window are separated by a thick horizontal line. This line is colored red when the connected handheld device is halted in the debugger nub, and is green when the handheld device is running code.

Debugging With the Source Window

To debug with the source code for an executable, you need to associate a symbol file on your desktop computer with the executable that is running on the handheld device. You can load any number of symbol files into Palm Debugger at once; whenever the device stops in the debugger nub, Palm Debugger automatically determines which symbol file to display in the source window.

You can use the following steps to load an application and its symbol file, and then use the source debugging commands:

1. Activate the console nub, as described in “[Activating Console Input](#)” on page 114.
2. Select **Install Database and Load Symbols** from the Source menu.
3. Select the PRC file to load onto the device.
4. Palm Debugger imports the PRC file into the handheld device and looks in the same directory for the associated symbol file.

Palm Debugger now associates the symbol file with the application that has been imported into the handheld device. Whenever the debugger nub breaks in the code for that application, the source window displays the associated source file and line number.

You can also break into the debugger manually and set a breakpoint on specific source code lines with **Toggle Breakpoint** in the Source menu or on the source window’s context menu.

Using Symbol Files

This section provides information about symbol files. You need to have a symbol file for your executable to use Palm Debugger’s source code debugging facility.

Each symbol file represents a single code resource and is created by the linker. Most Palm OS applications contain a single code resource of type 'code' and a resource ID of 1. Some applications have more than one code resource, and thus more than one symbol file.

A symbol file contains the following items:

- the names of each of the source files that were linked together to create the code resource

Using Palm Debugger

Using the Source Window

- the offset from the start of the code resource to the object code for each source file
- the offset from the start of the code resource for each line in the source file
- descriptions of the data structures used
- descriptions of the name, type, and location of each local variable used in the source code's functions
- descriptions of the name, type, and location of each global variable

To make use of a symbol file, Palm Debugger needs the address of the code resource on the handheld device that corresponds to the symbol file. The **Load Symbols** command on the Source menu associates a symbol file on the desktop computer with a code resource on the handheld device.

Using the Source Menu

Palm Debugger's Source menu contains commands that you can use for source level debugging. [Table 1.15](#) summarizes these commands. Note that several of these commands are also available from the Source context menu, as described in the next section.

Table 1.15 Source Menu Commands

Command	Description
Break	Halts the handheld device in the debugger nub by sending the same key event as does the . The device must be running the console nub to activate this command.
Step Into	Single steps one source line, and stops if it steps into a subroutine.
Step Over	Single steps one source line. If it steps into a subroutine, doesn't stop until the subroutine returns.

Table 1.15 Source Menu Commands (*continued*)

Command	Description
Go	Continues execution until a breakpoint is encountered.
Go Till	Sets a temporary breakpoint at the currently selected line in the source window and then continues execution.
Toggle Breakpoint	Toggles a breakpoint on or off at the currently selected line in the source window.
Disassemble at Cursor	Disassembles code at the currently selected line in the source window. The disassembled output is displayed in the debugging window.
Show Current Location	Scrolls the source window to show the current line in the source file.
Install Database and Load Symbols	Imports a PRC file into the handheld device and looks in the same directory for the associated symbol file.
Load Symbols	Opens a symbol file for use by Palm Debugger.
Remove All Symbols	Unloads any loaded symbols.

Using the Source Window Context Menu

You can activate the source context menu by right clicking your mouse in the source window. The context menu features many of the commands available in the Source menu, including:

- **Break**
- **Go Till**
- **Toggle Breakpoint**
- **Disassemble at Cursor**
- **Show Current Location**

The context menu also lists the source files for each symbol file that is loaded. You can use this list to select which source file you want to view.

Source Window Debugging Limitations

Source level debugging is limited in the current version of Palm Debugger. Although you can perform some of your debugging with the source window, you need to keep the following limitations in mind to remember when you need to switch back to assembly language debugging:

- You cannot display a stack crawl in the source window. You need to switch to the debugging window and use the `sc` command.
- Local variables that are structures or pointers to structures display as hexadecimal addresses in the local variables pane of the source window. To view the contents of these structures, you need to use the `dm` command in the debugging window.
- You cannot view global variables in the source window.
- Local variables are only displayed in hexadecimal format.
- You cannot change the values of local variables from the source window. To change these values, you must use the `sb`, `sw`, or `sl` commands in the debugging window.

Palm Debugger Error Messages

Most of the error messages displayed by Palm Debugger are hexadecimal codes that can be difficult to understand. To determine the meaning of the message, you need to look up the code in the Palm OS header files.

Each error code is a 16-bit value, in which the upper byte represents the code manager that generated the error, and the lower byte represents the specific error code. For example, suppose that you receive the following error message from Palm Debugger:

```
### Error $00000219
```

The code manager code is 0x02, which is the Data Manager, and the error code is 0x19, which is `dmErrAlreadyExists`.

The manager codes are located in the `SystemMgr.h` header file. The value 0x02 is defined as `dmErrorClass`.

The specific error codes for each manager are found in the header file for that manager. For example, the value 0x19 is defined in `DataMgr.h` as `dmErrAlreadyExists`.

Palm Debugger Tips and Examples

This section provides a collection of tips and examples for working with Palm Debugger, including the following sections:

- [“Performing Calculations”](#)
- Saving time with [“Shortcut Characters”](#) and [“Repeating Commands”](#) on page 38
- [“Finding a Specific Function”](#) on page 38
- [“Finding Memory Corruption Problems”](#) on page 42
- [“Displaying Local Variables and Function Parameters”](#) on page 44
- [“Changing the Baud Rate Used by Palm Debugger”](#) on page 47
- [“Debugging Applications That Use the Serial Port”](#) on page 48
- [“Importing System Extensions and Libraries”](#) on page 48
- [“Determining the Current Location Within an Application”](#) on page 49

NOTE: Several of the examples in this section show user input mixed with the output displayed by Palm Debugger. In these cases, the user input—the commands you type—is shown in **boldface**.

Performing Calculations

You can type numeric expressions into the debugging window to use it as a simple hexadecimal calculator. Here are several examples of typing a numeric expression and the results displayed in the debugging window.

Typed Expression	Displayed Result
<code>#20*4+3</code>	\$00000053 #83 #83 '...S'
<code>20*4+3</code>	\$83 #131 #-125 '.'
<code>123+ff</code>	\$0222 #546 #546 '."'

Shortcut Characters

Use the two shortcut characters to simplify your typing efforts: type the period (.) character to specify the address value used for the most recent command, or use the semicolon (;) character to specify the starting address of the current routine.

Repeating Commands

You can repeat several of the debugging commands by pressing the ENTER key repeatedly. For example, you can type the `dm` command to display sixteen bytes of memory, and then press the ENTER key to display the next sixteen bytes of memory. The `s` and `t` commands also provide this capability.

Finding a Specific Function

A typical debugging problem is that you want to single step through some problem code, but need to first find the code. This section presents four different methods that you can use to find code:

- Rebuild the application with a call to `DbgBreak` in the problem routine.
- Use debugging commands to set an A-trap break on a system call that the problem routine makes.
- Use the `ft` command to find the name of your routine.

- Use the source level debugging support to locate your routine.

Rebuilding the Application

If you can rebuild the application that you are debugging, it is often easiest to compile a `DbgBreak` call into the problem routine. Palm Debugger will break on the line containing that call.

Setting an A-trap Break

If you know that the problem routine makes a certain system call, you can use debugging commands to set an a-trap break on that call. The potential problem with this method is that other routines might make the same system call, which means that you will get false triggers.

For example, if you want to find your application's main event loop, you can use the following steps.

1. Set an a-trap break for the `EvtGetEvent` system call, and then tell Palm Debugger to go until it hits a break, as shown here:

```
atb "evtgetevent"
A-trap set on 011d (evtgetevent)
g
Remote stopped due to: A-TRAP BREAK EXCEPTION
'EvtGetEvent'
+$0000 10C3B1E2 *LINK A6,$0000 | 4E56 0000
```

When Palm Debugger breaks due to an a-trap break, the current location is at the beginning of the system call. This means that the return address on the stack is the function that made the system call. In the above example, this will be your application's main event loop.

2. Set a temporary breakpoint at the function return address that is currently on the stack. You can use the `@` operator to fetch the long word at the stack pointer, as shown here:

```
gt @sp
EXCEPTION ID = $80
```

Using Palm Debugger

Palm Debugger Tips and Examples

```
'EventLoop'
+$0016 1001B2E6 *MOVE.L A2,-(A7) | 2F0A
```

The program counter is now at the instruction in your main event loop that immediately follows the `EvtGetEvent` call.

3. Disassemble your main event loop. You can use the colon (:) symbol to easily grab the starting address of the current routine.

```
il :
'EventLoop 1001B2D0'
+$0000 1001B2D0 LINK A6,-$001C | 4E56 FFE4
+$0004 1001B2D4 MOVEM.L D3-D4/A2,-(A7) | 48E7 1820
+$0008 1001B2D8 LEA -$0018(A6),A2 | 45EE FFE8
+$000C 1001B2DC PEA $00000032 ; 00000032 | 4878 0032
+$0010 1001B2E0 MOVE.L A2,-(A7) | 2F0A
+$0012 1001B2E2 _EvtGetEvent ; $10C3B1E2 | 4E4F A11D
+$0016 1001B2E6 *MOVE.L A2,-(A7) | 2F0A
+$0018 1001B2E8 _SysHandleEvent ; $10C0E9EC | 4E4F A0A9
+$001C 1001B2EC ADD.W #$000C,A7 | DEFC 000C
+$0020 1001B2F0 TST.B D0 | 4A00
```

The `atb`, `g`, `gt`, and `il` commands are described in detail in [Chapter 2, “Palm Debugger Command Reference.”](#)

Using the Find Text Command

Another method for finding a certain code routine is to search through memory for the name of the routine. You can use Palm Debugger’s `ft` command to search for text. This command takes three arguments: the text to find, the starting address of the search, and the number of bytes to search.

For example, to search through the first megabyte of RAM on a Palm III™, you can use the following command:

```
ft "EventLoop" 10000000 100000
dm 100005C4 ;100005C4: 45 76 65 6E 74 4C 6F 6F 70 63 61 74 69
6F 6E 00 "EventLoop....."
```

NOTE: RAM starts at address 0x10000000 in all current Palm handheld devices except for the Palm V™. RAM starts at address 0 on the Palm V.

To search ROM instead, use address 0x10C00000.

You can repeat the find, starting from the current location, by pressing the ENTER key.

```
dm 1001B355 ;1001B355: 45 76 65 6E 74 4C 6F 6F 70 00 00 4E 56
00 00 2F "EventLoop..NV../"
```

You can ensure that the routine you've found is the one you want by disassembling the current routine with the [il](#) command and searching through the routine with the [ft](#) command.

NOTE: When you use the [ft](#) command, the first instance of the search string is actually a copy of the search string the debugger nub is using. You must search a second time to find the first "actual" instance of the text string.

Using the Source Level Debugging Support

If you have built your application with the gcc compiler and generated a symbol file, you can find your code by following these steps:

1. Launch the console nub on the handheld device, as described in "[Activating Console Input](#)" on page 114.
2. Open your symbols file. You can use the **Open Symbol File** command from Palm Debugger's Source menu.
3. After the symbol file has loaded, choose the **Break** command from the Source menu to break into the debugger nub on the device.
4. In the source window, select the source line of the routine you want to debug.
5. Select **Toggle Breakpoint** from the Source menu to set the breakpoint.

Finding Memory Corruption Problems

As anyone who has tried knows, finding the routine that is trashing memory can be a very frustrating task. A memory bug can trash the low memory global variables used by the system, the dynamic memory heap, or an application variable, any of which can cause unpredictable behavior. This section provides tips for tracking down two kinds of memory bugs:

- heap corruptions
- application variable corruption

Tracking Down Heap Corruption

If you suspect a corrupted heap, check the heap. You can perform a fast check of the heap with the [hchk](#) command, which verifies the validity of the heap. For example:

```
hchk 0
Heap OK
```

You can also use the `hd 0` command to display a dump of the dynamic heap. If the heap is in a valid state, the heap dump will complete and you will see the heap summary displayed at the bottom of the window. For example:

```
hd 0

Displaying Heap ID: 0000, mapped to 00001480
                                req    act                                resType/
#resID/
  start    handle    localID    size    size    lck own flags type  index attr ctg
uniqueID name
-----
-----
-00001534 00001494 F0001495 000456 00045E #0 #0    fM Graffiti Private
-00001992 00001498 F0001499 000012 00001A #0 #0    fM DataMgr Protect List
(DmProtectEntryPtr*)
-000019AC 00001490 F0001491 00001E 000026 #0 #0    fM Alarm Table
-000019D2 0000148C F000148D 000038 000040 #0 #0    fM
*00001A12 0000149C F000149D 000396 00039E #2 #1    fM Form "3:03 pm"
*00001DB0 000014A0 F00014A1 00049A 0004A2 #2 #0    fM
  00002252 ----- F0002252 00002E 00003E #0 #0    FM
  00002290 ----- F0002290 00EC40 00EC50 #0 #0    FM
-00010EE0 ----- F0010EE0 000600 000608 #0 #15    fM Stack: Console Task
```

...

```
000114E8 ----- F00114E8 000FF8 001008 #0 #0 FM
-000124F0 ----- F00124F0 001000 001008 #0 #15 fM
-00017D30 ----- F0017D30 00003C 000044 #0 #15 fM SysAppInfoPtr: AMX
-00017D74 ----- F0017D74 000008 000010 #0 #15 fM Feature Manager Globals
(FtrGlobalsType)
-00017D84 ----- F0017D84 000024 00002C #0 #15 fM DmOpenInfoPtr: 'Update
3.0.2'
-00017DB0 ----- F0017DB0 00000E 000016 #0 #15 fM DmOpenRef: 'Update
3.0.2'
-00017DC6 ----- F0017DC6 0001F4 0001FC #0 #15 fM Handle Table: 'Ô@Update
3.0.2'
-00017FC2 ----- F0017FC2 000024 00002C #0 #15 fM DmOpenInfoPtr:
'Ô@Update 3.0.2'
-00017FEE ----- F0017FEE 00000E 000016 #0 #15 fM DmOpenRef: 'Ô@Update
3.0.2'
```

Heap Summary:

```
  flags:          8000
  size:           016B80
  numHandles:     #40
  Free Chunks:    #14      (010C50 bytes)
  Movable Chunks: #51      (005E80 bytes)
  Non-Movable Chunks: #0      (000000 bytes)
```

If you break into the debugger nub at various points during the execution of your application and check the heap, you can narrow down where the corruption is occurring in your code.

Another method for tracking down heap corruption is to use the [mdebug](#) command, which puts the handheld device into one of several heap checking modes. Once a heap-checking mode has been activated on the device, the Palm OS performs an automatic heap check and verification after each call to the Memory Manager. If the heap is corrupted, the system automatically breaks into the debugger. The following is an example of the `mdebug` command:

mdebug -partial

```
Current mode = 001A
Only Affected heap checked/scrambled per call
Heap(s) checked on EVERY Mem call
Heap(s) scrambled on EVERY Mem call
Free chunk contents filled & checked
```

Minimum dynamic heap free space recording OFF

Note that the memory checking modes can seriously degenerate the performance of an application. You can enable or disable various `mdebug` options to strike a balance between performance and debugging information. For more information, see “[mdebug](#)” on page 145.

The `hd`, `hchk`, and `mdebug` commands are described in detail in [Chapter 2](#), “[Palm Debugger Command Reference](#).”

Tracking Down Global Variable Corruption

When you have a bug that is trashing a system or application global, you must first determine which address in memory is being corrupted. Once you know that address, you can use the Step-Spy (`ss`) command to watch the address. The `ss` command puts the processor into single-step mode and automatically checks the contents of a specified address after each instruction. If the instruction causes the contents of the address to change, the debugger breaks. For example:

```
ss 100
Step Spying on address: 00000100
```

Note that the `ss` command is single-stepping through instructions, and thus the handheld device runs slowly. Ideally, you can narrow down the range of code involved with the corruption and use this command to watch the execution of this code section.

Displaying Local Variables and Function Parameters

If you are debugging with the source window, the current function’s local variables and parameters are displayed in the upper pane of the window. However, if you do not have access to symbol information, you need to use debugging commands to manually look up the variable values. This section describes the steps you need to take to look up values for a typical function, which is shown in [Listing 1.4](#)

**Listing 1.4 An Example Function for Viewing Local Variables
and Parameters**

```
static Boolean
MainFrmEventHandler (EventPtr eventP)
{
    FormPtr      formP;
    Boolean       handled = false;
    Err           err;
    char          buffer[64];
    UInt32        numBytes=0;
    Int16         i;
    static        char prevChar = 0;

    // See if StdIO can handle it
    if (StdHandleEvent (eventP)) return true;

    // body of function omitted for clarity
    ...

    return false;
}
```

If you break into the debugger and disassemble the code at the beginning of this function, just before it calls the StdHandleEvent function, this is what you see:

```
i1 :
'MainFrmEventHandler 1001E296'
+$0000 1001E296  LINK A6,-$0048| 4E56 FFB8
+$0004 1001E29A  MOVEM.L D3-D5/A2,-(A7)| 48E7 1C20
+$0008 1001E29E  MOVE.L $0008(A6),A2| 246E 0008
+$000C 1001E2A2  CLR.B D5| 4205
+$000E 1001E2A4  CLR.L -$0044(A6)| 42AE FFBC
+$0012 1001E2A8  *MOVE.L A2,-(A7)| 2F0A
+$0014 1001E2AA  BSR.W StdHandleEvent ; 1001F214| 6100 0F68
+$0018 1001E2AE  ADDQ.W #$04,A7| 584F
+$001A 1001E2B0  TST.B D0| 4A00
+$001C 1001E2B2  BEQ.S MainFrmEventHandler+$0024 ; 1001E2BA |
6706
```

The first UInt32 on the stack upon function entry is the return address for the function. Immediately following that are the parameter values, from left to right. In the listing above, if you

Using Palm Debugger

Palm Debugger Tips and Examples

display the memory pointed to by the stack pointer at the beginning of the function, you see the following:

```
dm sp
00014A2A: 10 C4 77 00 00 01 4A 4E 00 01 4A 4E 00 01 51 0E
"..w...JN..JN..Q."
```

The first UInt32 (0x10C47700) is the return address of the function.

The second UInt32 (0x00014A4E) is the value of the function's eventP parameter.

After the LINK instruction executes however, the stack pointer register is changed: the stack pointer is decremented to make room for a saved value of the A6 register and for local variables; in this example, there are 0x48 bytes of local variables.

After the LINK instruction executes, the A6 register is changed to point to the beginning of the functions' stack frame. This register is used by the function to access parameters and local variables. The following shows what the stack looks like after the LINK instruction executes:

```
Address : Contents
-----
A7 => 149CE                                     <= new "top" of stack
      : ...                                     <= 0x48 bytes of local
variables
A6 => 14A26 : 00 01 4A 3A                       <= saved value of A6
      14A2A : 10 C4 77 00                       <= return address
      14A2E : 00 01 4A 4E <= eventP parameter
```

If you display the memory referenced by register A6 at this time, you see the following:

```
dm a6
00014A26: 00 01 4A 3A 10 C4 77 00 00 01 4A 4E
00 01 4A 4E "..J:..w...JN..JN"
```

The first UInt32 pointed to by A6 is the old value of A6, the next UInt32 is the return address of the routine, and following that are the function parameter values. This means that the first parameter to the function can always be found at 8 (A6).

Any local variables belonging to the function are stored in memory locations preceding A6. In the above example, the numBytes local variable is located at -0044 (A6). Once you know the offset of the variable, you can access by using an offset from the A6 register; thus, you can use the following command to view the numBytes parameter:

```
dm -44+a6
000149E2: 00 00 00 00 00 00 1A 0C 20 00 20 04
00 01 4A 08 "..... . ...J."
```

Changing the Baud Rate Used by Palm Debugger

Both the debugger and console nubs on the handheld device always start communicating at 57,600 baud. You can change this baud rate by selecting a new speed from Palm Debugger's Communications menu.

If you are using a serial cable that does not include hardware handshaking lines, you might need to switch to a lower baud rate. And if you are downloading a large file to the handheld device, you might want to switch higher baud rate. Palm Debugger lets you set the baud rate to values ranging from 2400 baud to 230,400 baud.

When you choose a new baud rate, Palm Debugger sends a request packet to the nub on the handheld device to change its baud rate, and then Palm Debugger changes its own baud rate. If Palm Debugger is attached to the debugger nub on the device, the request goes to the debugger nub; otherwise, the request goes to the console nub.

In either case, changing the baud rate of either nub on the handheld device changes the baud rate of both nubs.

NOTE: The new baud rate is only in effect until you soft reset the handheld device.

Debugging Applications That Use the Serial Port

Although it is very difficult to debug an application that uses the serial port, you can still use a limited set of debugging functions. You cannot use the console nub while an application on the handheld device is using the serial port.

When you do enter the debugger nub on the handheld device while debugging a serial application, the debugger sends data over the serial port and probably disrupts the application's communications. At that point, you can switch the serial cable back over to Palm Debugger, double-check your baud rate setting, attach to the device with the [att](#) command, and perform "post-mortem" analysis of the problem.

Making Sure the Baud Rates Match

If the debugger nub on the handheld device has already been entered at least once, and you later launch a handheld application that opens the serial port, that application might change the port speed. The debugger nub will then use the new baud rate, but you will need to manually change the baud rate that Palm Debugger is using for communications to work. Use Palm Debugger's Communications menu to change the speed.

Importing System Extensions and Libraries

You can use the console window `import` command to copy a new database or replace an existing database on the handheld device. However, the `import` command cannot replace a database that is currently opened.

If you are developing a system extension or shared library and need to use the `import` command, you need to do some extra work. This is due to the fact that system extension databases and shared libraries are generally either opened or marked as protected. To import a newer version of a system extension database or shared library, you have to make sure that the old database has been closed and is not protected; otherwise, the `import` command generates the following message:

```
###Error $00000219 occurred
```

To get around this problem, you need to perform a soft reset on the handheld device and tell the Palm OS to not automatically load system extensions or shared libraries. To do so, follow these steps:

1. Press the Up button on the handheld device while pressing the reset button on the back of the device with a paper clip or similar blunt object. This tells the Palm OS on the device to not load the system extension databases and shared libraries.
2. Start the console nub on the handheld device.
3. Import your system extension or shared library with the `import` command.
4. Perform another soft reset on the device, and the system will use the new version of the extension or library.

Determining the Current Location Within an Application

You can use one of the following three methods to determine where you are in your code:

1. Disassemble code starting at the beginning of the current routine, using the following command:

```
il :
'EventLoop 1001B2D0'
+$0000 1001B2D0  LINK A6,-$001C | 4E56 FFE4
+$0004 1001B2D4  MOVEM.L D3-D4/A2,-(A7) | 48E7 1820
+$0008 1001B2D8  LEA -$0018(A6),A2 | 45EE FFE8
+$000C 1001B2DC  PEA $00000032 ; 00000032 | 4878 0032
+$0010 1001B2E0  MOVE.L A2,-(A7) | 2F0A
+$0012 1001B2E2  _EvtGetEvent ; $10C3B1E2 | 4E4F A11D
+$0016 1001B2E6  *MOVE.L A2,-(A7) | 2F0A
+$0018 1001B2E8  _SysHandleEvent ; $10C0E9EC | 4E4F A0A9
+$001C 1001B2EC  ADD.W #$000C,A7 | DEFC 000C
+$0020 1001B2F0  TST.B D0 | 4A00
```

2. Perform a stack crawl with the `sc` command, which displays the oldest routine at the top and the newest at the bottom. For example:

```
sc
Calling chain using A6 Links:
A6 Frame Caller
00000000 10C68982 cjtken+0000
```

Using Palm Debugger

Palm Debugger Tips and Examples

```
00015086 10C6CA26 __Startup__+0060
00015066 10C6CCCE PilotMain+0250
00014FC2 10C0F808 SysAppLaunch+0458
00014F6E 10C10258 PrvCallWithNewStack+0016
0001491E 1001CC7E start+006E
000148E6 1001CF44 PilotMain+001C
```

3. Get a list of the currently opened databases. Your application should be one of the listed databases. Note that the System and GraffitiShortCuts databases are always opened by the system, and will appear at the bottom of the list. Use the opened command as follows:

opened

name	resDB	cardNum	accessP	ID	openCnt	mode
LauncherDB	no	0	00015146	0001814F	1	0003
*Launcher	yes	0	00016DD2	00D1FA98	1	0001
*Graffiti ShortCuts	yes	0	00017D5C	001FFE7F	1	0007
*System	yes	0	00017FEE	00D20A44	1	0005

Total: 4 databases opened

Palm Debugger Command Reference

This chapter describes Palm Debugger commands. For an introduction to using Palm Debugger, see [Chapter 1, “Using Palm Debugger.”](#)

This chapter begins with a description of the syntax used to describe commands, and then expands into the following sections:

- “[Debugging Window Commands](#)” on page 53 provides a reference description for each command that you can use in the debugging window to communicate with the debugger nub running on the handheld device. The command reference listings are ordered alphabetically.
- “[Debugging Command Summary](#)” on page 80 provides tables that summarize the debugging commands by category.

Command Syntax

This chapter uses the following syntax to specify the format of debugger commands:

<code>commandName <parameter> [options]</code>	
<code>commandName</code>	The name of the command.
<code>parameter</code>	Parameter(s) for the command. Each parameter name is enclosed in angle brackets (< and >). Sometimes a parameter can be one value or another. In this case the parameter names are bracketed by parentheses and separated by the character.

Palm Debugger Command Reference

Command Syntax

options	Optional flags that you can specify with the command. Note that options are specified with the dash (-) character in the console window and with the backslash (\) character in the debugging window.
---------	---

NOTE: Any portion of a command that is shown enclosed in square brackets (“[” and “]”) is optional.

The following is an example of a command definition

```
dir (<cardNum>|<srchOptions>) [displayOptions]
```

The `dir` command takes either a card number or a search specification, followed by display options.

Here are two examples of the `dir` command sent from the console window:

```
dir 0 -a
dir -t rsrc
```

And here are the same two commands sent from the debugging window:

```
dir 0 \a
dir \t rsrc
```

Specifying Command Options

All command options and some command parameters are specified as flags that begin with a dash (in the console window) or backslash (in the debugging window). For example:

```
-c
-enable
\enable
```

Some flags are followed by a keyword or value. You must leave white space between the flag and the value. For example:

```
-f D:\temp\myLogFile
\t Rsrc
```

Specifying Numeric and Address Values

Many of the debugging commands take address or numeric arguments. You can specify these values in hexadecimal, decimal, or binary. All values are assumed to be hexadecimal unless preceded by a sign that specifies decimal (#) or binary (%). [Table 2.1](#) shows values specified as binary, decimal, and hexadecimal in a debugging command:

Table 2.1 Specifying numeric values in Palm Debugger

Hex value	Decimal value	Binary value
64 or \$64	#100	%01100100
F5 or \$F5	#245	%11110101
100 or \$100	#256	%100000000

For more information, see “[Specifying Constants](#)” on page 17.

Using the Expression Language

When you send commands from the debugging window to the debugger nub on the handheld device, you can use Palm Debugger’s expression language to specify the command arguments. This language is described in “[Using Debugger Expressions](#)” on page 17.

Debugging Window Commands

You use Palm Debugger’s debugging window to send commands to the debugger nub that is running on the handheld device.

NOTE: You can use Palm Debugger’s expression language to specify arguments to debugging window commands. The expression language is described in “[Using Debugger Expressions](#)” on page 17.

Palm Debugger Command Reference

>

This section provides a description of all of the commands in alphabetical order. For convenience, the commands are categorized here:

Table 2.2 Debugging window command categories

Category	Commands
Console	cardinfo , dir , hchk , hd , hl , ht , info , opened , storeinfo
Flow Control	att , atb , atc , atd , br , brc , brd , cl , dx , g , gt , s , ss t , reset
Memory	atr , db , dl , dm , dw , fb , fill , fl , ft , fw , il , sb , sc , sc6 , sc7 , sl , sw , wh
Miscellaneous	help , penv
Register	reg
Template	> , sizeof , templates , typedef , typeend
Utility	alias , aliases , bootstrap , keywords , load , run , save , var , variables

>	Purpose	Defines a structure field.				
	Usage	> <typeName> <"fieldName">				
	Parameters	<table><tr><td>typeName</td><td>The type of the field.</td></tr><tr><td>fieldName</td><td>The quoted name of the field in the template.</td></tr></table>	typeName	The type of the field.	fieldName	The quoted name of the field in the template.
typeName	The type of the field.					
fieldName	The quoted name of the field in the template.					
	Comments	Use the > command in conjunction with the typedef and typeend commands to defined structure templates that you can use to display complex structures with a single memory display (dm) command.				
	Example	<pre>typedef struct "PointType" > SWord "X" > SWord "Y" typeend</pre>				

alias	Purpose	Defines or displays an alias.
	Usage	<pre>alias <"name"> alias <"name"> <"definition"></pre>
	Parameters	<p>name The quoted name of the alias.</p> <p>definition The quoted definitional text for the alias.</p>
	Comments	<p>Use the <code>alias</code> command to define an alias for a command or group of commands.</p> <p>If you provide only the name of an alias, this command displays the definition for that name.</p>
	Example	<pre>alias "ls" "dir"</pre>

aliases

	Purpose	Displays the names of all defined aliases.
	Usage	<pre>aliases</pre>
	Parameters	None.
	Example	<pre>aliases ls</pre>

atb	Purpose	Adds an A-Trap break.
	Usage	<pre>atb (<"funcName"> <trapNum>) ([libRefNum> <"libName">])</pre>
	Parameters	<p>funcName The quoted name of the function.</p> <p>trapNum The A-Trap number.</p> <p>libRefNum Optional. the reference number for the library in which the function resides.</p> <p>libName Optional. The quoted name of the library in which the function resides.</p>

Palm Debugger Command Reference

atc

atc **Purpose** Clears an A-Trap break.

Usage `atc (<"funcName"> | <trapNum>)`
 `([libRefNum> | <"libName">])`

Parameters

<code>funcName</code>	The quoted name of the function.
<code>trapNum</code>	The A-Trap number.
<code>libRefNum</code>	Optional. the reference number for the library in which the function resides.
<code>libName</code>	Optional. The quoted name of the library in which the function resides.

atd **Purpose** Displays a list of all the A-Trap breaks currently set.

Usage `atd`

Parameters None.

atr **Purpose** Registers a function name with an A-Trap number.

Usage `atr <"funcName"> <trapNum> [<"libName">]`

Parameters

<code>funcName</code>	The quoted name of the function.
<code>trapNum</code>	The A-Trap number.
<code>libName</code>	Optional. The quoted name of the library in which the function resides.

att **Purpose** Attach to the handheld device.

Usage `att [options]`

Parameters `options` You can optionally specify the following options:

`\async` Attach asynchronously.

Example `att`
 `EXCEPTION ID = $A`
 `+$0512 10C0EEFE *MOVEQ.L #$01,D0 | 7001`

NOTE: The `att` command will not connect Palm Debugger to Palm OS Simulator. Instead, you should connect from Palm OS Simulator to Palm Debugger by either:

- Entering “shortcut . 1” as described in “[Using Shortcut Numbers to Activate the Windows](#)” on page 6 from Palm OS Simulator.
- Entering CTRL+PAUSE (or CTRL+ATTN) from Palm OS Simulator.

Either of these methods will cause Palm OS Simulator to enter debug mode. Next, use the PalmDebugger command `g` to resume debugging.

bootstrap

Purpose	Loads a ROM image into memory on the handheld device, using the bootstrap mode of the processor.
Usage	<code>bootstrap <"hwInitFileName"> <"romFileName"> [options]</code>
Parameters	<div> <div>hwInitFileName</div> <div>The quoted name of the hardware initialization file on your desktop computer.</div> </div> <div> <div>romFileName</div> <div>The quoted name of the ROM image file on your desktop computer.</div> </div> <div> <div>options</div> <div>You can optionally specify the following options:</div> <div>\slow</div> </div>

br	Purpose	Sets a breakpoint at the specified address.
	Usage	<code>br [options] <addr></code>
	Parameters	<div> <div>options</div> <div>Optional. You can specify the following option:</div> <div>\toggle</div> <div>Toggles the breakpoint on or off.</div> </div>

Palm Debugger Command Reference

brc

`addr` The memory address at which to set the breakpoint.

brc **Purpose** Clears a breakpoint or all breakpoints.

Usage `brc`
 `brc <addr>`

Parameters `addr` A memory address.

Comments Use the `br` command to clear a specific breakpoint or to clear all breakpoints. if you specify a valid address value, that breakpoint is cleared. If you do not specify any address value, all breakpoints are cleared.

NOTE: The `cl` and `brc` commands are identical.

brd **Purpose** Displays a list of all of the breakpoints that are currently set.

Usage `brd`

Parameters None.

cardinfo

Purpose Retrieves information about a memory card.

Usage `cardinfo <cardNum>`

Parameters `cardNum` The number of the card for which you want information displayed. You almost always use 0 to specify the built-in RAM.

Comments You can use the `cardinfo` command in either the Console window or the debugging window.

Example `cardinfo 0`

 Name: PalmCard
 Manuf: Palm, Inc
 Version: 0001
 CreationDate: B1243780


```
ROM Size: 00118FFC
RAM Size: 00200000
Free Bytes : 0015ACB2
Number of heaps: #3
```

cl	Purpose	Clears a breakpoint or all breakpoints.
	Usage	cl cl <addr>
	Parameters	addr A memory address.
	Comments	Use the cl command to clear a specific breakpoint or to clear all breakpoints. if you specify a valid address value, that breakpoint is cleared. If you do not specify any address value, all breakpoints are cleared.

NOTE: The cl and brc commands are identical.

db	Purpose	Displays the byte value at a specified address.
	Usage	db <addr>
	Parameters	addr A memory address.
	Example	db 0100 Byte at 00000100 = \$01 #1 #1 '.'

dir	Purpose	Displays a list of the databases on the handheld device.
	Usage	dir (<cardNum> <searchOptions>) [<displayOptions>]
	Parameters	cardNum The card number whose databases you want listed. You almost always use 0 to specify the built-in RAM.
		searchOptions Optional. Options for listing a specific database. Specify any combination of the following flags.
		\c <creatorID> Search for a database by creator ID.

Palm Debugger Command Reference

dir

	<code>\latest</code>	List only the latest version of each database.
	<code>\t <typeID></code>	Search for a database by its type.
<code>displayOptions</code>	Optional. Options for which information is displayed in the listing. Specify any combination of the following flags.	
	<code>\a</code>	Show all information.
	<code>\at</code>	Show the database attributes.
	<code>\d</code>	Show the database creation, modification, and backup dates.
	<code>\i</code>	Show the database appInfo and sortInfo field values.
	<code>\id</code>	Show the database chunk ID
	<code>\s</code>	Show the database size
	<code>\m</code>	Show the database modification number.
	<code>\n</code>	Show the database name.
	<code>\r</code>	Show the number of records in the database.
	<code>\tc</code>	Show the database type ID and creator ID.
	<code>\v</code>	Show the database version number.

Comments Use the `dir` command to display a list of the databases on a specific card or in the handheld device built-in RAM. You typically use the following command to list all of the databases stored in RAM on the handheld device:

```
dir 0
```

Or use the `-a` switch to display all of the information for each database:

```
dir 0 -a
```

NOTE: You can use the `dir` command in either the Console window or the debugging window. However, the command options must be prefaced with the “\” character in the debugging window, rather than with the “-” character that you use in the console window version.

Example `dir 0`

name	ID	total	data
*System	00D20A44	392.691 Kb	390.361 Kb
*AMX	00D209C4	20.275 Kb	20.123 Kb
*UIAppShell	00D20944	1.327 Kb	1.175 Kb
*PADHTAL Library	00D208E2	7.772 Kb	7.674 Kb
*IrDA Library	00D20876	39.518 Kb	39.402 Kb
...			
MailDB	0001817F	1.033 Kb	0.929 Kb
NetworkDB	0001818B	0.986 Kb	0.722 Kb
System MIDI Sounds	000181B3	1.066 Kb	0.842 Kb
DatebookDB	000181FB	0.084 Kb	0.000 Kb

Total: 41

- dl** **Purpose** Displays the 32-bit long value at a specified address.
- Usage** `dl <addr>`
- Parameters** `addr` A memory address.
- Example** `dl 0100`
 Long at 00000100 = \$01010000 #16842752 #16842752 '....'
-
- dm** **Purpose** Displays memory for a specified number of bytes or templates.
- Usage** `dm <addr> [<count>] [<template>]`
- Parameters** `addr` A memory address.
- `count` Optional. The number of bytes to display.

Palm Debugger Command Reference

dump

	template.	The name of the structure template to use. This defines how much memory to display and how to display it.
Comments	Use the <code>dm</code> command to display a range of memory values. You can specify a byte count or a structure template; if you do not specify either, <code>dm</code> displays sixteen bytes of memory.	
Example	<pre>dm 0100 8 00000100: 01 01 00 00 02 B0 00 01</pre>	

dump

Purpose	Dumps memory to a file.	
Usage	<code>dump <"filename"> <addr> <numBytes></code>	
Parameters	filename	The quoted name of the file to which the data is to be written.
	addr	A memory address.
	numBytes	The number of bytes of memory to write to the file.
Comments	Use the <code>dump</code> command to write a dump of a range of memory addresses to file.	

dw **Purpose** Displays the 16-bit word value at a specified address.

Usage `dw <addr>`

Parameters addr A memory address.

Example

```
dw 0100
Word at 00000100 = $0101 #257 #257 '..'
```

dx **Purpose** Enables or disables `DbgBreak()` breaks.

 dx

Parameters None.

fb	Purpose	Searches through a range of memory for a specified byte value.
	Usage	<code>fb <value> <addr> <numBytes> [flags]</code>
	Parameters	<div> <div>value</div> <div>The byte value to find.</div> </div> <div> <div>addr</div> <div>The address at which to start the search.</div> </div> <div> <div>numBytes</div> <div>The number of bytes to search.</div> </div> <div> <div>flags</div> <div>Optional. You can specify the following flags:</div> <div> <div>\a</div> <div>Find all occurrences within the specified range.</div> </div> <div> <div>\i</div> <div>Use caseless comparison.</div> </div> </div>
	Comments	By default, fb uses a case sensitive comparison.
	Example	<pre>fb ff 0100 200 dm 00000110 ;00000110: FF 00 00 00 03 18 00 00 03 BC 00 01 7D 72 00 01 ".....}r.."</pre>
fill	Purpose	Fills memory with a specified byte value.
	Usage	<code>fill <addr> <numBytes> <value></code>
	Parameters	<div> <div>addr</div> <div>A memory address.</div> </div> <div> <div>numBytes</div> <div>The number of bytes to fill with the value.</div> </div> <div> <div>value</div> <div>The value assigned to each byte.</div> </div>
	Example	<code>fill 0100 8 FF</code>
fl	Purpose	Searches through a range of memory for a specified 32-bit long value.
	Usage	<code>fb <value> <addr> <numBytes> [flags]</code>
	Parameters	<div> <div>value</div> <div>The byte value to find.</div> </div> <div> <div>addr</div> <div>The address at which to start the search.</div> </div> <div> <div>numBytes</div> <div>The number of bytes to search.</div> </div> <div> <div>flags</div> <div>Optional. You can specify the following flags:</div> </div>

Palm Debugger Command Reference

ft

\a Find all occurrences within the specified range.

\i Use caseless comparison.

Comments By default, fl uses a case sensitive comparison.

Example fl ffff 0 1000

```
dm 00000034 ;00000034: FF FF 00 00 FF FF 00 00 FF FF 00
00 FF FF 00 00 "....."
```

ft Purpose Searches through a range of memory for the specified text.

Usage ft <text> <addr> <numBytes> [flags]

Parameters text The quoted text to find.

addr The address at which to start the search.

numBytes The number of bytes to search.

flags Optional. You can specify the following flags:

\a Find all occurrences within the specified range.

\i Use caseless comparison.

Comments By default, ft uses a case sensitive comparison.

Example ft "abc" 0 1000

```
dm 000005C4 ;000005C4: 61 62 63 27 00 00 00 00 00 01 4B
06 00 00 0
```

fw Purpose Searches through a range of memory for the specified 16-bit word value.

Usage fw <value> <addr> <numBytes> [flags]

Parameters value The value to find.

addr The address at which to start the search.

numBytes The number of bytes to search.

flags Optional. You can specify the following flags:

		\a	Find all occurrences within the specified range.
		\i	Use caseless comparison.
Comments	By default, fw uses a case sensitive comparison.		
Example	<pre>fw 32000 0 1000 dm 00000258 ;00000258: 00 20 00 00 00 07 A7 0E 00 00 00 01 00 00 00 00 "."</pre>		
g	Purpose	Continues execution.	
	Usage	<pre>g g <addr></pre>	
	Parameters	addr	Optional. The address from which to continue execution.
	Comments	You can optionally specify a starting address for the g command. If you do not specify an address, execution continues from the current program counter location.	
	Example	g	
gt	Purpose	Sets a temporary breakpoint at the specified address, and resumes execution from the current program counter.	
		gt <addr>	
	Parameters	addr	The address at which to set the breakpoint. If you do not specify an address, the current program counter location is used.
hchk	Purpose	Checks the integrity of a heap.	
	Usage	hchk <heapId> [options]	
	Parameters	heapId	The hexadecimal number of the heap whose contents are to be checked. Heap number 0x0000 is always the dynamic heap.

Palm Debugger Command Reference

hd

options

Optional. You can specify the following option:

\c Check the contents of each chunk.

Comments **NOTE:** You can use the `hchk` command in either the Console window or the debugging window. However, the command options must be prefaced with the “\” character in the debugging window, rather than with the “-” character that you use in the console window version.

Example `hchk 0000`
Heap OK

hd **Purpose** Displays a hexadecimal dump of the specified heap.

Usage `hd <heapId>`

Parameters `heapId` The hexadecimal number of the heap whose contents are to be displayed. Heap number 0x0000 is always the dynamic heap.

Comments Use the `hd` command to display a dump of the contents of a specific heap from the handheld device. You can use the [hl](#) command to display the heap IDs.

Example `hd 0`

Displaying Heap ID: 0000, mapped to 00001480

			req	act					resType/
#resID/	start	handle	localID	size	size	lck	own	flags	type
uniqueID	name								index attr ctg

```
-----
-00001534 00001494 F0001495 000456 00045E #0 #0 fM Graffiti Private
-00001992 00001498 F0001499 000012 00001A #0 #0 fM DataMgr Protect List
(DmProtectEntryPtr*)
-000019AC 00001490 F0001491 00001E 000026 #0 #0 fM Alarm Table
-000019D2 0000148C F000148D 000038 000040 #0 #0 fM
*00001A12 0000149C F000149D 000396 00039E #2 #1 fM Form "3:03 pm"
*00001DB0 000014A0 F00014A1 00049A 0004A2 #2 #0 fM
00002252 ----- F0002252 00002E 00003E #0 #0 FM
00002290 ----- F0002290 00EC40 00EC50 #0 #0 FM
-00010EE0 ----- F0010EE0 000600 000608 #0 #15 fM Stack: Console Task
```

...


```

000114E8 ----- F00114E8 000FF8 001008 #0 #0 FM
-000124F0 ----- F00124F0 001000 001008 #0 #15 fM
-00017D30 ----- F0017D30 00003C 000044 #0 #15 fM SysAppInfoPtr: AMX
-00017D74 ----- F0017D74 000008 000010 #0 #15 fM Feature Manager Globals
(FtrGlobalsType)
-00017D84 ----- F0017D84 000024 00002C #0 #15 fM DmOpenInfoPtr: 'Update
3.0.2'
-00017DB0 ----- F0017DB0 00000E 000016 #0 #15 fM DmOpenRef: 'Update
3.0.2'
-00017DC6 ----- F0017DC6 0001F4 0001FC #0 #15 fM Handle Table: 'Ô@Update
3.0.2'
-00017FC2 ----- F0017FC2 000024 00002C #0 #15 fM DmOpenInfoPtr:
'Ô@Update 3.0.2'
-00017FEE ----- F0017FEE 00000E 000016 #0 #15 fM DmOpenRef: 'Ô@Update
3.0.2'

```

Heap Summary:

```

flags:          8000
size:           016B80
numHandles:     #40
Free Chunks:    #14      (010C50 bytes)
Movable Chunks: #51      (005E80 bytes)
Non-Movable Chunks: #0      (000000 bytes)

```

help Purpose Displays a list of commands or help for a specific command.

Usage

```

help
help <command>
?
? <command>

```

Parameters command The name of the command for which you want help displayed.

Comments You can use the help command in either the Console window or the debugging window.

Example help hchk

Do a Heap Check.

Syntax: hchk <hex heapID> [options...]

-c : Check contents of each chunk

Palm Debugger Command Reference

hl

hl	Purpose	Displays a list of memory heaps.	
	Usage	hl <cardNum>	
	Parameters	cardNum	The card number on which the heaps are located. You almost always use 0 to specify the built-in RAM.
	Comments	Use the hl command to list the memory heaps in built-in RAM or on a card. You can use the hl command in either the Console window or the debugging window.	
	Example	hl 0	

index	heapID	heapPtr	size	free	maxFree	flags
0	0000	00001480	00016B80	00010C50	0000EC48	8000
1	0001	1001810E	001E7EF2	0014AD6A	00147D3A	8000
2	0002	10C08212	00118DEE	0000A01C	0000A014	8001

ht	Purpose	Displays summary information for the specified heap.	
	Usage	ht 0	
	Parameters	None.	
	Comments	<p>The ht commands displays the summary information that is also shown at the end of a heap dump generated by the hd command.</p> <p>You can use the ht command in either the Console window or the debugging window.</p>	
	Example	<pre>ht 0000 Displaying Heap ID: 0000, mapped to 00001480 ----- Heap Summary: flags: 8000 size: 016B80 numHandles: #40 Free Chunks: #14 (010CAA bytes) Movable Chunks: #48 (005E26 bytes) Non-Movable Chunks: #0 (000000 bytes)</pre>	

il	Purpose	Disassembles code in a specified line range.	
	Usage	il [<addr> <"funcName"> [lineCount]]	
	Parameters	addr	Optional. The starting address at which to disassemble.
		funcName	Optional. The name of the function whose code you want disassembled.
		lineCount	Optional. If you provide a value for addr, you can also specify the number of lines of code to disassemble starting at addr.
	Comments	Use the il command to disassemble code. If you do not provide a function name or starting address value, disassembly begins at the current program counter value.	

Example il 0100

```

00000100  BTST      D0,D1          | 0101
00000102  ORI.B     #$B0,D0 ; '.'  | 0000 02B0
00000106  ORI.B     #$30,D1 ; '0'  | 0001 7830
0000010A  ORI.B     #$01,D0 ; '.'  | 0000 0001
0000010E                               | 474A
00000110  CoProc    FF00 0000 0318 |
00000116  ORI.B     #$BC,D0 ; '.'  | 0000 03BC
0000011A  ORI.B     #$72,D1 ; 'r'  | 0001 7D72
0000011E  ORI.B     #$BC,D1 ; '.'  | 0001 6FBC
00000122  ORI.B     #$22,D0 ; '"'  | 0000 0722

```

info	Purpose	Displays information about a memory chunk.	
	Usage	info (<hexChunkPtr> localID) [options]	
	Parameters	hexChunkPtr or localID	A pointer to a chunk in memory, or the ID of a chunk on the specified card number.
		options	Optional. You can specify the following options: -card <cardNum> The card number if a local ID is specified instead of a chunk pointer.

Palm Debugger Command Reference

keywords

Comments	NOTE: You can use the <code>info</code> command in either the Console window or the debugging window. However, the command options must be prefaced with the “\” character in the debugging window, rather than with the “-” character that you use in the console window version.
-----------------	---

keywords

Purpose	Lists all debugger keywords.
Usage	<code>keywords</code>
Parameters	None.
Example	<code>keywords</code>

t
g
SR
PC
SP
A7
A6
A5
A4
A3
A2
A1
A0
D7
...

load	Purpose	Loads the data fork of a file at the specified address.
-------------	----------------	---

	Usage	<code>load <"fileName"> <addr></code>
--	--------------	---

Parameters	<code>fileName</code>	The quoted name of the file whose data fork you want loaded.
	<code>addr</code>	The memory address at which you want the data fork loaded.

opened

- Purpose** Lists all of the currently opened databases.
- Usage** `opened`
- Parameters** None.
- Comments** You can use the `opened` command in either the Console window or the debugging window.
- Example** `opened`

name	resDB	cardNum	accessP	ID	openCnt	mode
*Graffiti ShortCuts	yes	0	00017D5C	001FFE7F	1	0007
*System	yes	0	00017FEE	00D20A44	1	0005

Total: 2 databases opened

penv Purpose Displays current environment information for the debugger.

- Usage** `penv`
- Parameters** None.
- Comments** The `penv` command displays the current values of the predefined debugger environment variables, which are summarized in [Debugger Environment Variables](#).

Example `penv`

```

=====
DebOut = false
SymbolsOn = true
StepRegs = false
ReadMemHack = false
Attached = true
.....
dot address = 00000000
last address = 00001022
last count = 0000000a
=====

```

Palm Debugger Command Reference

reg

reg **Purpose** Displays all registers.

Usage `reg`

Parameters None.

Example `reg`

```
D0 = 00000102      A0 = 10C0EEF6      USP = BF6E446F
D1 = 00000013      A1 = 10C0EF0E      SSP = 000132E4
D2 = 00000027      A2 = 000133C2
D3 = 00000000      A3 = 00015404
D4 = 00014B06      A4 = 10CCFB7C
D5 = 00000000      A5 = 000149AA
D6 = 00D1EFE8      A6 = 000133AC      PC = 10C0EEFE
D7 = 0001515E      A7 = 000132E4      SR = tSxnzvc      Int = 0
```

reset

Purpose Performs a soft reset on the handheld device.

Usage `reset`

Parameters None.

Comments This command performs the same reset that is performed when you press the recessed reset button on a Palm Powered handheld device. It resets the memory system and reformats both cards.

 You can use the `reset` command in either the Console window or the debugging window.

Example `reset`
 Resetting system

run **Purpose** Runs a debugger script from file.

Usage `run <"fileName">`

Parameters `filename` The quoted name of the file that contains the debugger script.

S	Purpose	Single steps the processor, stepping into subroutines.
	Usage	s
	Parameters	None.
	Example	<pre>s 'SysHandleEvent' +\$0694 10C0F080 *MOVEM.L (A7)+,D3-D5/A2-A4 4CDF 1C38</pre>
save	Purpose	Saves a range of data from memory to file.
	Usage	save <"fileName"> <addr> <numBytes>
	Parameters	<div> <div>fileName</div> <div>The quoted name of the file to which you want the data saved.</div> </div> <div> <div>addr</div> <div>The starting address in memory to save.</div> </div> <div> <div>numBytes</div> <div>The number of bytes to save.</div> </div>
	Example	<pre>save "savedMem1" 0100 100</pre> <p>Memory set starting at 00000111</p>
sb	Purpose	Sets the value of the byte at the specified address.
	Usage	sb <addr> <value>
	Parameters	<div> <div>addr</div> <div>The address of the byte.</div> </div> <div> <div>value</div> <div>The byte value.</div> </div>
	Example	<pre>sb 0111 0a</pre> <p>Memory set starting at 00000111</p>
SC	Purpose	Displays a list of functions on the stack using information stored in the A6 frame pointer register.
	Usage	sc [<addr> [<frames>]]
	Parameters	<div> <div>addr</div> <div>Optional. The address from which to start listing.</div> </div>

Palm Debugger Command Reference

sc6

frames Optional. The number of frames to list. You can specify this only if you specify a value for addr.

Example

```
sc
Calling chain using A6 Links:
A6 Frame   Caller
00000000   10C68982   cjtkend+0000
00015086   10C6CA26   __Startup__+0060
00015066   10C6CCCE   PilotMain+0250
00014FC2   10C0F808   SysAppLaunch+0458
00014F6E   10C10258   PrvCallWithNewStack+0016
00013414   10CCFBEO   __Startup__+0060
000133F4   10CD08CE   PilotMain+0036
000133DA   10CD6D18   EventLoop+0016
```

SC6 Purpose Lists the A6 stack frame chain, starting at the specified address.

Usage sc6 [<addr> [<frames>]]

Parameters addr Optional. The address from which to start listing.

 frames Optional. The number of frames to list. You can specify this only if you specify a value for addr.

Comments This command is the same as the [sc](#) command.

Example

```
sc
Calling chain using A6 Links:
A6 Frame   Caller
00000000   10C68982   cjtkend+0000
00015086   10C6CA26   __Startup__+0060
00015066   10C6CCCE   PilotMain+0250
00014FC2   10C0F808   SysAppLaunch+0458
00014F6E   10C10258   PrvCallWithNewStack+0016
00013414   10CCFBEO   __Startup__+0060
000133F4   10CD08CE   PilotMain+0036
000133DA   10CD6D18   EventLoop+0016
```

sc7	Purpose	Displays a list of functions on the stack using the stack pointer (A7). This displays information about functions on the stack that do not set up frame pointers.	
	Usage	<code>sc7 [<addr> [<frames>]]</code>	
	Parameters	<code>addr</code>	Optional. The address from which to start listing.
		<code>frames</code>	Optional. The number of frames to list. You can specify this only if you specify a value for <code>addr</code> .
	Comments	Use the <code>sc7</code> command instead of the standard stack crawl command, <code>sc</code> , when you want to display information about routines on the stack that have not set up frame pointers. Note that this command will sometimes display bogus routines.	
	Example	<pre>sc7 Return Addresses on the stack: Stack Addr Caller 00013AFC 00000000 000133B0 10CD6D18 EventLoop+0016 00013344 10C1F964 PrvHandleExchangeEvents+0028</pre>	

sizeof

Purpose	Displays the size, in bytes, of a template.
Usage	<code>sizeof <template></code>
Parameters	<code>template</code> The name of the template.
Comments	You can use the templates command to list the available templates.
Example	<pre>sizeof sdword Size = 4 byte(s)</pre>

sl	Purpose	Sets the value of the 32-bit long integer at the specified address.
	Usage	<code>sl <addr> <value></code>
	Parameters	<code>addr</code> The address of the 32-bit value.
		<code>value</code> The long value.

Palm Debugger Command Reference

SS

Example `sl 0110 ffffffff`
Memory set starting at 00000110

SS Purpose Breaks into the debugger when the value of the long word at the specified address changes.

Usage `ss [<addr>]`

Parameters `addr` Optional. The address of the 32-bit value. If you do not specify an address value, the current program counter location is used.

Example `ss 1000F024`

storeinfo

Purpose Displays information about a memory store.

Usage `storeinfo <cardNum>`

Parameters `cardNum` The card number for which you want information displayed. You almost always use 0 to specify the built-in RAM.

Comments You can use the `storeinfo` command in either the Console window or the debugging window.

Example `storeinfo 0`

```
ROM Store:
  version: 0001
  flags: 0000
  name: ROM Store
  creation date: 00000000
  backup date: 00000000
  heap list offset: 00C08208
  init code offset1: 00C0D652
  init code offset2: 00C1471E
  database dirID: 00D20F7E

RAM Store:
  version: 0001
  flags: 0001
  name: RAM Store 0
  creation date: 00000000
```

```

backup date: 00000000
heap list offset: 00018100
init code offset1: 00000000
init code offset2: 00000000
database dirID: 0001811F

```

SW **Purpose** Sets the value of the word at the specified address.

Usage sw <addr> <value>

Parameters addr The address of the 16-bit value.
 value The word value.

Example sw 0110 ffff
 Memory set starting at 00000110

t **Purpose** Single steps the processor, stepping over subroutines.

Usage t

Parameters None.

Example t

```

'SysHandleEvent'
Will Branch
+$0514 10C0EF00 *BRA.W        SysHandleEvent+$0694 ;
10C0F080        |6000 017E

```

templates

Purpose Lists the names of the debugger templates.

Usage templates

Parameters None.

Example templates

```

Char
Byte
SByte
Word
SWord

```

Palm Debugger Command Reference

typedef

DWord
SDWord

typedef

Purpose	Begins a structure definition block.		
Usage	<code>typedef struct <"name"></code>		
Parameters	<table><tr><td>name</td><td>The quoted name of the template whose definition you are beginning.</td></tr></table>	name	The quoted name of the template whose definition you are beginning.
name	The quoted name of the template whose definition you are beginning.		
Comments	Use the <code>typedef</code> command in conjunction with the ≥ and typeend commands to defined structure templates that you can use to display complex structures with a single memory display (dm) command.		
Example	<pre>typedef struct "PointType" > SWord "X" > SWord "Y" typeend</pre>		

typeend

Purpose	Ends a structure definition block.
Usage	<code>typeend</code>
Parameters	None.
Comments	Use the <code>typedef</code> command in conjunction with the ≥ and typeend commands to defined structure templates that you can use to display complex structures with a single memory display (dm) command.
Example	<pre>typedef struct "PointType" > SWord "X" > SWord "Y" typeend</pre>

var	Purpose	Defines a debugger variable.
	Usage	<code>var <"name"> [<initialValue>]</code>
	Parameters	<div> <div>name</div> <div>The quoted name of the variable that you are defining.</div> </div> <div> <div>initialValue</div> <div>Optional. The initial value for the variable. If you are assigning a string value to the variable, you must quote the initial value.</div> </div>
	Example	<pre>var "testvar" 100 var "testvar" "Hello" WARNING: redefining variable: testvar</pre>

variables

Purpose	Lists the names of the debugger variables.
Usage	<code>variables</code>
Parameters	None.
Example	<pre>variables DebOut SymbolsOn ReadMemHack StepRegs Attached testvar testvar2</pre>

wh	Purpose	Displays system function information for a specified function name or A-Trap number. Also identifies the memory chunk that contains a specific address or lists all system functions.
	Usage	<code>wh [\a <addr>] [<"funcName"> <ATrapNumber>]</code>
	Parameters	<div> <div>addr</div> <div>Specifies an address. The wh command displays the memory chunk that contains this address.</div> </div> <div> <div>funcName</div> <div>The quoted name of the system function for which you want information displayed.</div> </div>

ATrapNumber The number of the A-trap number for which you want information displayed.

Debugging Command Summary

Flow Control Commands

<u>atb</u>	Adds an A-Trap break.
<u>atc</u>	Clears an A-Trap break.
<u>atd</u>	Displays a list of all A-Trap breaks.
<u>att</u>	Attach to the handheld device.
<u>br</u>	Sets a breakpoint at the specified address.
<u>brc</u>	Clears a breakpoint or all breakpoints.
<u>brd</u>	Displays a list of all breakpoints.
<u>cl</u>	Clears a breakpoint or all breakpoints.
<u>dx</u>	Enables or disables <code>DbgBreak()</code> breaks.
<u>g</u>	Continues execution.
<u>gt</u>	Sets a temporary breakpoint at the specified address, and resumes execution from the current program counter.
<u>reset</u>	Resets the memory system and formats both cards.
<u>s</u>	Single steps the processor, stepping into subroutines.
<u>ss</u>	Breaks into the debugger when the long word value at the specified address changes.
<u>t</u>	Single steps the processor, stepping over subroutines.

Memory Commands

<u>atr</u>	Registers a function name with an A-Trap number.
<u>db</u>	Displays the byte value at a specified address.
<u>dl</u>	Displays the 32-bit long value at a specified address.
<u>dm</u>	Displays memory for a specified number of bytes or templates.
<u>dw</u>	Displays the 16-bit word value at a specified address.
<u>fb</u>	Searches through a range of memory for a specified byte value.
<u>fill</u>	Fills memory with a specified byte value.
<u>fl</u>	Searches through a range of memory for a specified 32-bit long value.
<u>ft</u>	Searches through a range of memory for the specified text.
<u>fw</u>	Searches through a range of memory for the specified 16-bit word value.
<u>il</u>	Disassembles code in a specified line range.
<u>sb</u>	Sets the value of the byte at the specified address.
<u>sc</u>	Lists the A6 stack frame chain, starting at the specified address.
<u>sc6</u>	Lists the A6 stack frame chain, starting at the specified address.
<u>sc7</u>	Lists the A7 stack frame chain, starting at the specified address.
<u>sl</u>	Sets the value of the long at the specified address.

Palm Debugger Command Reference

Debugging Command Summary

<u>sw</u>	Sets the value of the word at the specified address.
<u>wh</u>	Displays system function information for a specified function name or A-Trap number. Also identifies the memory chunk that contains a specific address or lists all system functions.

Template Commands

<u>></u>	Defines a structure field.
<u>sizeof</u>	Displays the size, in bytes, of a template.
<u>templates</u>	Lists the names of the debugger templates.
<u>typedef</u>	Begins a structure definition block.
<u>typeend</u>	Ends a structure definition block.

Register Commands

<u>reg</u>	Displays all registers.
----------------------------	-------------------------

Utility Commands

<u>alias</u>	Defines or displays an alias.
<u>aliases</u>	Displays all debugger alias names.
<u>bootstrap</u>	Loads a ROM image into memory on the handheld device, using the bootstrap mode of the processor.
<u>keywords</u>	Lists all debugger keywords.
<u>load</u>	Loads the file's data fork at the specified remote address.
<u>run</u>	Runs a debugger script.
<u>save</u>	Saves a range of data from memory to file.
<u>var</u>	Defines a debugger variable.
<u>variables</u>	Lists the names of the debugger variables.

Console Commands

<u>cardinfo</u>	Retrieves information about a memory card.
<u>dir</u>	Lists the databases.
<u>dump</u>	Dumps a range of memory to a file.
<u>hchk</u>	Checks a heap.
<u>hd</u>	Displays a dump of a memory heap.
<u>hl</u>	Lists all of the memory heaps on the specified memory card.
<u>ht</u>	Performs a heap total.
<u>info</u>	Displays information on a heap chunk.
<u>opened</u>	Lists all currently opened databases.
<u>storeinfo</u>	Retrieves information about a memory store.

Miscellaneous Debugger Commands

<u>help</u>	Displays a list of available commands.
or	
?	
<u>help</u> <cmd>	Displays help for a specific command.
or	
? <cmd>	
<u>penv</u>	Displays debugger environment information.

Debugger Environment Variables

DebOut	A Boolean value that specifies if debug style output is enabled.
ReadMemHack	A Boolean value that specifies if the read memory hack is enabled.

Palm Debugger Command Reference

Debugging Command Summary

<code>SymbolsOn</code>	A Boolean value that specifies if printing of disassembly symbols is enabled.
<code>StepRegs</code>	A Boolean value that specifies if register values should be shown after every step.

Predefined Constants

<code>true</code>	Integer value 1.
<code>false</code>	Integer value 0.
<code>srCmask</code>	The status register Carry bit.
<code>srImask</code>	The status register Interrupt field mask.
<code>srNmask</code>	The status register Negative bit.
<code>srSmask</code>	The status register Supervisor bit.
<code>srTmask</code>	The status register Trace bit.
<code>srVmask</code>	The status register Overflow bit.
<code>srXmask</code>	The status register extend bit.
<code>srZmask</code>	The status register Zero bit.

Debugger Protocol Reference

This chapter describes the debugger protocol, which provides an interface between a debugging target and a debugging host. For example, the Palm Debugger and the Palm OS® Emulator use this protocol to exchange commands and information.

IMPORTANT: This chapter describes the version of the Palm Debugger protocol that shipped on the Metrowerks CodeWarrior for the Palm™ Operating System, Version 6 CD-ROM. If you are using a different version, the features in your version might be different from the features described here.

This chapter covers the following topics:

- [“About the Palm Debugger Protocol”](#) on page 85
- [“Constants”](#) on page 88
- [“Data Structures”](#) on page 91
- [“Debugger Protocol Commands”](#) on page 93
- [“Summary of Debugger Protocol Packets”](#) on page 111

About the Palm Debugger Protocol

The Palm debugger protocol allows a *debugging target*, which is usually a handheld device ROM or an emulator program such as the Palm OS Emulator, to exchange information with a *debugging host*, such as the Palm Debugger or the Metrowerks debugger.

The debugger protocol involves sending packets between the host and the target. When the user of the host debugging program enters a command, the host converts that command into one or more command packets and sends each packet to the debugging target. In

Debugger Protocol Reference

About the Palm Debugger Protocol

most cases, the target subsequently responds by sending a packet back to the host.

Packets

There are three packet types used in the debugger protocol:

- The debugging host sends *command request packets* to the debugging target.
- The debugging target sends *command response packets* back to the host.
- Either the host or the target can send a *message packet* to the other.


Although the typical flow of packets involves the host sending a request and the target sending back a response, although there are some exceptions, as follows:

- The host can send some requests to the target that do not result in a response packet being returned. For example, when the host sends the `Continue` command packet to tell the target to continue execution, the target does not send back a response packet.
- The target can send response packets to the host without receiving a request packet. For example, whenever the debugging target encounters an exception, it sends a `State` response packet to the host.

Packet Structure

Each packet consists of a packet header, a variable-length packet body, and a packet footer, as shown in [Figure 3.1](#).

Figure 3.1 Packet Structure



The Packet Header

The packet header starts with the 24-bit key value \$BEEFFD and includes header information and a checksum of the header itself.

The Packet Body

The packet body contains the command byte, a filler byte, and between 0 and 270 bytes of data. See “[SysPktBodyCommon](#)” on page 91 for a description of the structure used to represent the two byte body header (the command and filler bytes), and see [Table 3.1](#) for a list of the command constants.

The Packet Footer

The packet footer contains a 16-bit CRC of the header and body. Note that the CRC computation does not include the footer.

Packet Communications

The communications protocol between the host and target is very simple: the host sends a request packet to the target and waits for a time-out or for a response from the target.

If a response is not detected within the time-out period, the host does not retry the request. When a response does not come back before timing out, it usually indicates that one of two things is happening:

- the debugging target is busy executing code and has not encountered an exception
- the state of the debugging target has degenerated so badly that it cannot respond

The host has the option of displaying a message to the user to inform him or her that the debugging target is not responding.

Constants

This section describes the constants and structure types that are used with the packets for various commands.

Packet Constants

```
#define sysPktMaxMemChunk    256
#define sysPktMaxBodySize    (sysPktMaxMemChunk+16)
#define sysPktMaxNameLen    32
```

`sysPktMaxMemChunk`

The maximum number of bytes that can be read by the `Read Memory` command or written by the `Write Memory` command.

`sysPktMaxBodySize`

The maximum number of bytes in a request or response packet.

`sysPktMaxNameLen`

The maximum length of a function name.

State Constants

```
#define sysPktStateRspInstWords 15
```

sysPktStateRspInstWords

The number of remote code words sent in the response packet for the State command.

Breakpoint Constants

```
#define dbgNormalBreakpoints 5
#define dbgTempBPIndex  dbgNormalBreakpoints
#define dbgTotalBreakpoints  ( dbgTempBPIndex+1)
```

dbgNormalBreakpoints

The number of normal breakpoints available in the debugging target.

dbgTempBPIndex

The index in the breakpoints array of the temporary breakpoint.

dbgTotalBreakpoints

The total number of breakpoints in the breakpoints array, including the normal breakpoints and the temporary breakpoint.

Command Constants

Each command is represented by a single byte constant. The upper bit of each request command is clear, and the upper bit of each response command is set. [Table 3.1](#) shows the command constants.

Table 3.1 Debugger protocol command constants

Command	Request constant	Response constant
Continue	sysPktContinueCmd	N/A
Find	sysPktFindCmd	sysPktFindRsp
Get Breakpoints	sysPktGetBreakpointsCmd	sysPktGetBreakpointsRsp
Get Routine Name	sysPktGetRtnNameCmd	sysPktGetRtnNameRsp

Debugger Protocol Reference

Constants

Table 3.1 Debugger protocol command constants (*continued*)

Command	Request constant	Response constant
Get Trap Breaks	sysPktGetTrapBreaksCmd	sysPktGetTrapBreaksRsp
Get Trap Conditionals	sysPktGetTrapConditionalsCmd	sysPktGetTrapConditionalsRsp
Message	sysPktRemoteMsgCmd	N/A
Read Memory	sysPktReadMemCmd	sysPktReadMemRsp
Read Registers	sysPktReadRegsCmd	sysPktReadRegsRsp
RPC	sysPktRPCCmd	sysPktRPCRsp
Set Breakpoints	sysPktSetBreakpointsCmd	sysPktSetBreakpointsRsp
Set Trap Breaks	sysPktSetTrapBreaksCmd	sysPktSetTrapBreaksRsp
Set Trap Conditionals	sysPktSetTrapConditionalsCmd	sysPktSetTrapConditionalsRsp
State	sysPktStateCmd	sysPktStateRsp
Toggle Debugger Breaks	sysPktDbgBreakToggleCmd	sysPktDbgBreakToggleRsp
Write Memory	sysPktWriteMemCmd	sysPktWriteMemRsp
Write Registers	sysPktWriteRegsCmd	sysPktWriteRegsRsp

Data Structures

This section describes the data structures used with the request and response packets for the debugger protocol commands.

_SysPktBodyCommon

The `_SysPktBodyCommon` macro defines the fields common to every request and response packet.

```
#define _sysPktBodyCommon \  
    Byte command; \  
    Byte _filler;
```

Fields

<code>command</code>	The 1-byte command value for the packet.
<code>_filler</code>	Included for alignment only. Not used.

SysPktBodyType

The `SysPktBodyType` represents a command packet that is sent to or received from the debugging target.

```
typedef struct SysPktBodyType  
{  
    _SysPktBodyCommon;  
    Byte data[sysPktMaxBodySize-2];  
} SysPktBodyType;
```

Fields

<code>_SysPktBodyCommon</code>	The command header for the packet.
<code>data</code>	The packet data.

SysPktRPCParamType

The SysPktRPCParamType is used to send a parameter in a remote procedure call. See the [RPC](#) command for more information.

```
typedef struct SysPktRPCParamInfo
{
    Byte    byRef;
    Byte    size;
    Word    data[?];
} SysPktRPCParamType;
```

Fields

byRef	Set to 1 if the parameter is passed by reference.
size	The number of bytes in the data array. This must be an even number.
data	The parameter data.

BreakpointType

The BreakpointType structure is used to represent the status of a single breakpoint on the debugging target.

```
typedef struct BreakpointType
{
    Ptr    addr;
    Boolean    enabled;
    Boolean    installed;
} BreakpointType;
```

Fields

addr	The address of the breakpoint. If this is set to 0, the breakpoint is not in use.
enabled	A Boolean value. This is TRUE if the breakpoint is currently enabled, and FALSE if not.
installed	Included for correct alignment only. Not used.

Debugger Protocol Commands

This section describes each command that you can send to the debugging target, including a description of the response packet that the target sends back.

Continue

Purpose Tells the debugging target to continue execution.

Comments This command usually gets sent when the user specifies the Go command. Once the debugging target continues execution, the debugger is not reentered until a breakpoint or other exception is encountered.

NOTE: The debugging target does not send a response to this command.

Commands The Continue request command is defined as follows:

```
#define sysPktContinueCmd0x07
```

Request Packet

```
typedef struct SysPktContinueCmdType
{
    _sysPktBodyCommon;
    M68KresgType regs;
    Boolean stepSpy;
    DWord ssAddr;
    DWord ssCount;
    DWord ssChecksum;
}SysPktContinueCmdType;
```

Fields

<— `_sysPktBodyCommon`

The common packet header, as described in [_SysPktBodyCommon](#).

—> `regs`

The new values for the debugging target processor registers. The new register values are stored in sequential order: D0 to D7, followed by A0 to A6.

Debugger Protocol Reference

Find

—> stepSpy	A Boolean value. If this is TRUE, the debugging target continues execution until the value that starts at the specified step-spy address changes. If this is FALSE, the debugging target continue execution until a breakpoint or other exception is encountered.
—> ssAddr	The step-spy starting address. An exception is generated when the value starting at this address, for ssCount bytes, changes on the debugging target.
—> ssCount	The number of bytes in the “spy” value.
—> ssChecksum	A checksum for the “spy” value.

Find Purpose Searches for data in memory on the debugging target.

Commands The Find request and response commands are defined as follows:

```
#define sysPktFindCmd0x13
#define sysPktFindRsp0x93
```

Request Packet

```
typedef struct SysPktFindCmdType
{
    _sysPktBodyCommon;
    DWord  firstAddr;
    DWord  lastAddr;
    Word   numBytes
    Boolean caseInsensitive;
    Byte   searchData[?];
}SysPktFindCmdType;
```

Fields

—> _sysPktBodyCommon	The common packet header, as described in _SysPktBodyCommon .
—> firstAddr	The starting address of the memory range on the debugging target to search for the data.
—> lastAddr	The ending address of the memory range on the debugging target to search for the data.

- > numBytes The number of bytes of data in the search string.
- > searchData The search string. The length of this array is defined by the value of the numBytes field.

Response Packet

```
typedef struct SysPktFindRspType
{
    _sysPktBodyCommon;
    DWord addr;
    Boolean found;
}SysPktFindRspType
```

Fields

- <— _sysPktBodyCommon The common packet header, as described in [_SysPktBodyCommon](#).
- <— addr The address of the data string in memory on the debugging target.
- <— found A Boolean value. If this is TRUE, the search string was found on the debugging target, and the value of addr is valid. If this is FALSE, the search string was not found, and the value of addr is not valid.

Get Breakpoint

S Purpose

Retrieves the current breakpoint settings from the debugging target.

Comments

The body of the response packet contains an array with dbgTotalBreakpoints values in it, one for each possible breakpoint.

If a breakpoint is currently disabled on the debugging target, the enabled field for that breakpoint is set to 0.

If a breakpoint address is set to 0, the breakpoint is not currently in use.

The dbgTotalBreakpoints constant is described in “[Breakpoint Constants](#)” on page 89.

Debugger Protocol Reference

Get Routine Name

Commands The Get Breakpoints command request and response commands are defined as follows:

```
#define sysPktGetBreakpointsCmd 0x0B
#define sysPktGetBreakpointsRsp 0x8B
```

Request Packet

```
typedef struct SysPktGetBreakpointsCmdType
{
    _sysPktBodyCommon;
}SysPktGetBreakpointsCmdType
```

Fields

—> _sysPktBodyCommon
The common packet header, as described in [_SysPktBodyCommon](#).

Response Packet

```
typedef struct SysPktGetBreakpointsRspType
{
    _sysPktBodyCommon;
    BreakpointType db[dbgTotalBreakpoints];
}SysPktGetBreakpointsRspType
```

Fields

<— _sysPktBodyCommon
The common packet header, as described in [_SysPktBodyCommon](#).

<— bp
An array with an entry for each of the possible breakpoints. Each entry is of the type [BreakpointType](#).

Get Routine Name

Purpose Determines the name, starting address, and ending address of the function that contains the specified address.

Comments The name of each function is imbedded into the code when it gets compiled. The debugging target can scan forward and backward in the code to determine the start and end addresses for each function.

Commands The Get Routine Name command request and response commands are defined as follows:

```
#define sysPktGetRtnNameCmd 0x04
#define sysPktGetRtnNameRsp 0x84
```

Request Packet

```
typedef struct SysPktRtnNameCmdType
{
    _sysPktBodyCommon;
    void* address
}SysPktRtnNameCmdType;
```

Fields

—> `_sysPktBodyCommon` The common packet header, as described in [_SysPktBodyCommon](#).

—> `address` The code address whose function name you want to discover.

Response Packet

```
typedef struct SysPktRtnNameRspType
{
    _sysPktBodyCommon;
    void* address;
    void* startAddr;
    void* endAddr;
    charname[sysPktMaxNameLen];
}SysPktRtnNameRspType;
```

Fields

<— `_sysPktBodyCommon` The common packet header, as described in [_SysPktBodyCommon](#).

<— `address` The code address whose function name was determined. This is the same address that was specified in the request packet.

<— `startAddr` The starting address in target memory of the function that includes the address.

<— `endAddr` The ending address in target memory of the function that includes the address. If a function name could not be found, this is the last address that was scanned.

Debugger Protocol Reference

Get Trap Breaks

<— name The name of the function that includes the address. This is a null-terminated string. If a function name could not be found, this is the null string.

Get Trap Breaks

Purpose Retrieves the settings for the trap breaks on the debugging target.

Comments Trap breaks are used to force the debugging target to enter the debugger when a particular system trap is called.

The body of the response packet contains an array with `dbgTotalBreakpoints` values in it, one for each possible trap break.

Each trap break is a single word value that contains the system trap number.

Commands The Get Trap Breaks request and response commands are defined as follows:

```
#define sysPktGetTrapBreaksCmd 0x10
#define sysPktGetTrapBreaksRsp 0x90
```

Request Packet

```
typedef struct SysPktGetTrapBreaksCmdType
{
    _sysPktBodyCommon;
}SysPktGetTrapBreaksCmdType;
```

Fields

—> `_sysPktBodyCommon`

The common packet header, as described in [_SysPktBodyCommon](#).

Response Packet

```
typedef struct SysPktGetTrapBreaksRspType
{
    _sysPktBodyCommon;
    Word trapBP[dbgTotalTrapBreaks];
}SysPktGetTrapBreaksRspType;
```


Fields

<code><— _sysPktBodyCommon</code>	The common packet header, as described in _SysPktBodyCommon .
<code><— trapBP</code>	An array with an entry for each of the possible trap breaks. A value of 0 indicates that the trap break is not used.

Get Trap Conditional

S Purpose

Retrieves the trap conditionals values from the debugging target.

Comments

Trap conditionals are used when setting A-Traps for library calls. You can set a separate conditional value for each A-Trap.

The body of the response packet contains an array with `dbgTotalBreakpoints` values in it, one for each possible trap break.

Each trap conditional is a value; if the value of the first word on the stack matches the conditional value when the trap is called, the debugger breaks.

Commands

The Get Trap Conditionals request and response commands are defined as follows:

```
#define sysPktGetTrapConditionsCmd 0x14
#define sysPktGetTrapConditionsRsp 0x94
```

Request Packet

```
typedef struct SysPktGetTrapConditionsCmdType
{
    _sysPktBodyCommon;
}SysPktGetTrapConditionsCmdType
```

Fields

<code>—> _sysPktBodyCommon</code>	The common packet header, as described in _SysPktBodyCommon .
--------------------------------------	---

Response Packet

```
typedef struct SysPktGetTrapConditionsRspType
{
    _sysPktBodyCommon;
```

Debugger Protocol Reference

Message

```
Word trapParam[dbgTotalTrapBreaks];  
}SysPktGetTrapConditionsRspType
```

Fields

<— `_sysPktBodyCommon` The common packet header, as described in [_SysPktBodyCommon](#).

<— `trapParam` An array with an entry for each of the possible trap breaks. A value of 0 indicates that the trap conditional is not used.

Message

Purpose Sends a message to display on the debugging target.

Comments Application can compile debugger messages into their code by calling the `DbgMessage` function.

 The debugging target does not send back a response packet for this command.

Commands The Message request command is defined as follows:

```
#define sysPktRemoteMsgCmd 0x7F
```

Request Packet

```
typedef struct SysPktRemoteMsgCmdType  
{  
    _sysPktBodyCommon;  
    Byte text[1];  
}SysPktRemoteMsgCmdType;
```

Fields

—> `_sysPktBodyCommon` The common packet header, as described in [_SysPktBodyCommon](#).

—> `text`

Read Memory

Purpose Reads memory values from the debugging target.

Comments This command can read up to `sysPktMaxMemChunk` bytes of memory. The actual size of the response packet depends on the number of bytes requested in the request packet.

Commands The Read Memory command request and response commands are defined as follows:

```
#define sysPktReadMemCmd 0x01
#define sysPktReadMemRsp 0x81
```

Request Packet

```
typedef struct SysPktReadMemCmdType
{
    _sysPktBodyCommon;
    void* address;
    Word numBytes;
}SysPktReadMemCmdType;
```

Fields

- > `_sysPktBodyCommon` The common packet header, as described in [_SysPktBodyCommon](#).
- > `address` The address in target memory from which to read values.
- > `numBytes` The number of bytes to read from target memory.

Response Packet

```
typedef struct SysPktReadMemRspType
{
    _sysPktBodyCommon;
    //Byte    data[?];
}SysPktReadMemRspType;
```

Fields

- <— `_sysPktBodyCommon` The common packet header, as described in [_SysPktBodyCommon](#).

Debugger Protocol Reference

Read Registers

<— data

The returned data. The number of bytes in this field matches the numBytes value in the request packet.

Read Registers

Purpose Retrieves the value of each of the target processor registers.

Comments The eight data registers are stored in the response packet body sequentially, from D0 to D7. The seven address registers are stored in the response packet body sequentially, from A0 to A6.

Commands The Read Registers command request and response commands are defined as follows:

```
#define sysPktReadRegsCmd 0x05
#define sysPktReadRegsRsp 0x85
```

Request Packet

```
typedef struct SysPktReadRegsCmdType
{
    _sysPktBodyCommon;
}SysPktReadRegsCmdType;
```

Fields

—> _sysPktBodyCommon

The common packet header, as described in [_SysPktBodyCommon](#).

Response Packet

```
typedef struct SysPktReadRegsRspType
{
    _sysPktBodyCommon;
    M68KRegsType reg;
}SysPktReadRegsRspType;
```

Fields

<— _sysPktBodyCommon

The common packet header, as described in [_SysPktBodyCommon](#).

<— reg

The register values in sequential order: D0 to D7, followed by A0 to A6.

RPC Purpose Sends a remote procedure call to the debugging target.

Commands The RPC request and response commands are defined as follows:

```
#define sysPktRPCCmd 0x0A
#define sysPktRPCRsp 0x8A
```

Request Packet

```
typedef struct SysPktRPCType
{
    _sysPktBodyCommon;
    Word trapWord;
    DWord resultD0;
    DWord resultA0;
    Word numParams;
    SysPktRPCParamType param[?];
}
```

Fields

- > `_sysPktBodyCommon` The common packet header, as described in [_SysPktBodyCommon](#).
- > `trapWord` The system trap to call.
- > `resultD0` The result from the D0 register.
- > `resultA0` The result from the A0 register.
- > `numParams` The number of RPC parameter structures in the param array that follows.
- > `param` An array of RPC parameter structures, as described in [SysPktRPCParamType](#).

Set Breakpoint

S Purpose Sets breakpoints on the debugging target.

Comments The body of the request packet contains an array with `dbgTotalBreakpoints` values in it, one for each possible breakpoint. If a breakpoint is currently disabled on the debugging target, the enabled field for that breakpoint is set to 0.

The `dbgTotalBreakpoints` constant is described in [Breakpoint Constants](#).

Debugger Protocol Reference

Set Trap Breaks

Commands The Set Breakpoints command request and response commands are defined as follows:

```
#define sysPktSetBreakpointsCmd 0x0C
#define sysPktSetBreakpointsRsp 0x8C
```

Request Packet

```
typedef struct SysPktSetBreakpointsCmdType
{
    _sysPktBodyCommon;
    BreakpointType db[dbgTotalBreakpoints];
}SysPktSetBreakpointsCmdType
```

Fields

—> _sysPktBodyCommon The common packet header, as described in [_SysPktBodyCommon](#).

—> bp An array with an entry for each of the possible breakpoints. Each entry is of the type [BreakpointType](#).

Response Packet

```
typedef struct SysPktSetBreakpointsRspType
{
    _sysPktBodyCommon;
}SysPktSetBreakpointsRspType
```

Fields

<— _sysPktBodyCommon The common packet header, as described in [_SysPktBodyCommon](#).

Set Trap Breaks

Purpose Sets breakpoints on the debugging target.

Comments The body of the request packet contains an array with `dbgTotalBreakpoints` values in it, one for each possible trap break. If a trap break is currently disabled on the debugging target, the value of that break is set to 0.

The `dbgTotalBreakpoints` constant is described in [Breakpoint Constants](#).

Commands The Set Breakpoints command request and response commands are defined as follows:

```
#define sysPktSetTrapBreaksCmd 0x0C
#define sysPktSetTrapBreaksRsp 0x8C
```

Request Packet

```
typedef struct SysPktSetTrapBreaksCmdType
{
    _sysPktBodyCommon;
    Word trapBP[dbgTotalBreakpoints];
}SysPktSetTrapBreaksCmdType
```

Fields

—> _sysPktBodyCommon The common packet header, as described in [_SysPktBodyCommon](#).

—> trapBP An array with an entry for each of the possible trap breaks. If the value of an entry is 0, the break is not currently in use.

Response Packet

```
typedef struct SysPktSetTrapBreaksRspType
{
    _sysPktBodyCommon;
}SysPktSetTrapBreaksRspType
```

Fields

<— _sysPktBodyCommon The common packet header, as described in [_SysPktBodyCommon](#).

Set Trap Conditional

S Purpose Sets the trap conditionals values for the debugging target.

Comments Trap conditionals are used when setting A-Traps for library calls. You can set a separate conditional value for each A-Trap.

The body of the request packet contains an array with `dbgTotalBreakpoints` values in it, one for each possible trap break.

Debugger Protocol Reference

State

Each trap conditional is a value; if the value of the first word on the stack matches the conditional value when the trap is called, the debugger breaks.

Commands The Set Trap Conditionals request and response commands are defined as follows:

```
#define sysPktSetTrapConditionsCmd 0x15
#define sysPktSetTrapConditionsRsp 0x95
```

Request Packet

```
typedef struct SysPktSetTrapConditionsCmdType
{
    _sysPktBodyCommon;
    Word trapParam[dbgTotalTrapBreaks];
}SysPktSetTrapConditionsCmdType
```

Fields

—> _sysPktBodyCommon The common packet header, as described in [_SysPktBodyCommon](#).

—> trapParam An array with an entry for each of the possible trap breaks. A value of 0 indicates that the trap conditional is not used.

Response Packet

```
typedef struct SysPktSetTrapConditionsRspType
{
    _sysPktBodyCommon;
}SysPktSetTrapConditionsRspType
```

Fields

<— _sysPktBodyCommon The common packet header, as described in [_SysPktBodyCommon](#).

State

Purpose Sent by the host program to query the current state of the debugging target, and sent by the target whenever it encounters an exception and enters the debugger.

Comments The debugging target sends the State response packet whenever it enters the debugger for any reason, including a breakpoint, a bus error, a single step, or any other reason.

Commands The State request and response commands are defined as follows:

```
#define sysPktStateCmd 0x00
#define sysPktStateRsp 0x80
```

Request Packet

```
typedef struct SysPktStateCmdType
{
    _sysPktBodyCommon;
} SysPktStateCmdType
```

Fields

—> _sysPktBodyCommon

The common packet header, as described in [_SysPktBodyCommon](#).

Response Packet

```
typedef struct SysPktStateRspType
{
    _sysPktBodyCommon;
    Boolean resetted;
    Word exceptionId;
    M68KregsType reg;
    Word inst[sysPktStateRspInstWords];
    BreakpointType bp[dbgTotalBreakpoints];
    void* startAddr;
    void* endAddr;
    char name[sysPktMaxNameLen];
    Byte trapTableRev;
} SysPktStateRspType;
```

Fields

<— _sysPktBodyCommon

The common packet header, as described in [_SysPktBodyCommon](#).

<— resetted A Boolean value. This is TRUE if the debugging target has just been reset.

<— exceptionId The ID of the exception that caused the debugger to be entered.

<— reg The register values in sequential order: D0 to D7, followed by A0 to A6.

Debugger Protocol Reference

Toggle Debugger Breaks

<code><— inst</code>	A buffer of the instructions starting at the current program counter on the debugging target.
<code><— bp</code>	An array with an entry for each of the possible breakpoints. Each entry is of the type BreakpointType .
<code><— startAddr</code>	The starting address of the function that generated the exception.
<code><— endAddr</code>	The ending address of the function that generated the exception.
<code><— name</code>	The name of the function that generated the exception. This is a null-terminated string. If no name can be found, this is the null string.
<code><— trapTableRev</code>	The revision number of the trap table on the debugging target. You can use this to determine when the trap table cache on the host computer is invalid.

Toggle Debugger Breaks

Purpose Enables or disables breakpoints that have been compiled into the code.

Comments A breakpoint that has been compiled into the code is a special TRAP instruction that is generated when source code includes calls to the `DbgBreak` and `DbgSrcBreak` functions.

Sending this command toggles the debugging target between enabling and disabling these breakpoints.

Commands The `Toggle Debugger Breaks` request and response commands are defined as follows:

```
#define sysPktDbgBreakToggleCmd 0x0D
#define sysPktDbgBreakToggleRsp 0x8D
```

Request Packet `typedef struct SysPktDbgBreakToggleCmdType`

```
{
    _sysPktBodyCommon;
}SysPktDbgBreakToggleCmdType;
```

Fields

—>_sysPktBodyCommon The common packet header, as described in [_SysPktBodyCommon](#).

Response Packet

```
typedef struct SysPktDbgBreakToggleRspType
{
    _sysPktBodyCommon;
    Boolean newState
}SysPktDbgBreakToggleRspType;
```

Fields

<— _sysPktBodyCommon The common packet header, as described in [_SysPktBodyCommon](#).

<— newState A Boolean value. If this is set to TRUE, the new state has been set to enable breakpoints that were compiled into the code. If this is set to FALSE, the new state has been set to disable breakpoints that were compiled into the code.

Write Memory

Purpose Writes memory values to the debugging target.

Comments This command can write up to sysPktMaxMemChunk bytes of memory. The actual size of the request packet depends on the number of bytes that you want to write.

Commands The Write Memory command request and response commands are defined as follows:

```
#define sysPktWriteMemCmd 0x02
#define sysPktWriteMemRsp 0x82
```

Request Packet

```
typedef struct SysPktWriteMemCmdType
{
    _sysPktBodyCommon;
```

Debugger Protocol Reference

Write Registers

```
void* address;
Word numBytes;
//Byte data[?]
}SysPktWriteMemCmdType;
```

Fields

—> `_sysPktBodyCommon` The common packet header, as described in [_SysPktBodyCommon](#).

--> `address` The address in target memory to which the values are written.

--> `numBytes` The number of bytes to write.

--> `data` The bytes to write into target memory. The size of this field is defined by the `numBytes` parameter.

Response Packet

```
typedef struct SysPktWriteMemRspType
{
    _sysPktBodyCommon;
}SysPktWriteMemRspType;
```

Fields

<-- `_sysPktBodyCommon` The common packet header, as described in [_SysPktBodyCommon](#).

Write Registers

- Purpose** Sets the value of each of the target processor registers.
- Comments** The eight data registers are stored in the request packet body sequentially, from D0 to D7. The seven address registers are stored in the request packet body sequentially, from A0 to A6.
- Commands** The Write Registers command request and response commands are defined as follows:

```
#define sysPktWriteRegsCmd 0x06
#define sysPktWriteRegsRsp 0x86
```

Request Packet

```
typedef struct SysPktWriteRegsCmdType
{
    _sysPktBodyCommon;
    M68KRegsType reg;
}SysPktWriteRegsCmdType;
```

Fields

--> _sysPktBodyCommon

The common packet header, as described in [_SysPktBodyCommon](#).

—> reg

The new register values in sequential order: D0 to D7, followed by A0 to A6.

Response Packet

```
typedef struct SysPktWriteRegsRspType
{
    _sysPktBodyCommon;
}SysPktWriteRegsRspType;
```

Fields

<— _sysPktBodyCommon

The common packet header, as described in [_SysPktBodyCommon](#).

Summary of Debugger Protocol Packets

[Table 3.2](#) summarizes the command packets that you can use with the debugger protocol.

Table 3.2 Debugger protocol command packets

Command	Description
Continue	Tells the debugging target to continue execution.
Find	Searches for data in memory on the debugging target.
Get Breakpoints	Retrieves the current breakpoint settings from the debugging target.
Get Routine Name	Determines the name, starting address, and ending address of the function that contains the specified address.

Debugger Protocol Reference

Summary of Debugger Protocol Packets

Table 3.2 Debugger protocol command packets (*continued*)

Command	Description
Get Trap Breaks	Retrieves the settings for the trap breaks on the debugging target.
Get Trap Conditionals	Retrieves the trap conditionals values from the debugging target.
Message	Sends a message to display on the debugging target.
Read Memory	Reads memory values from the debugging target.
Read Registers	Retrieves the value of each of the target processor registers.
RPC	Sends a remote procedure call to the debugging target.
Set Breakpoints	Sets breakpoints on the debugging target.
Set Trap Breaks	Sets breakpoints on the debugging target.
Set Trap Conditionals	Sets the trap conditionals values for the debugging target.
State	Sent by the host program to query the current state of the debugging target, and sent by the target whenever it encounters an exception and enters the debugger.
Toggle Debugger Breaks	Enables or disables breakpoints that have been compiled into the code.
Write Memory	Writes memory values to the debugging target.
Write Registers	Sets the value of each of the target processor registers.

Using the Console Window

This chapter describes the console window, which you can use with Palm Debugger, Palm Simulator, and the Metrowerks CodeWarrior environment to perform maintenance and high-level debugging of a Palm™ handheld device.

The following topics are covered in this chapter:

- [“About the Console Window”](#)
- [“Connecting the Console Window”](#) on page 114
- [“Entering Console Window Commands”](#) on page 117
- [“Command Syntax”](#) on page 120
- [“Console Window Commands”](#) on page 122
- [“Console Command Summary”](#) on page 155

About the Console Window

The console window interfaces with a handheld device by sending information packets to and receiving information packets from the *console nub* on the device. The console interface provides a number of commands, which are used primarily for administration of databases and heap testing on handheld devices.

The console is available in three environments:

- as a separate window for sending and receiving commands in the Palm Debugger program, which is described in [Chapter 1, “Using Palm Debugger.”](#)
- as a separate window that you can open from within Palm Simulator program.
- as a separate window that you can open within the Metrowerks CodeWarrior environment.

Using the Console Window

Connecting the Console Window

The console window provides the same commands and same interface in all three environments.

To use the console commands, you must connect your desktop computer with the console nub on the device, as described in the next section, [Connecting the Console Window](#).

To learn more about using console commands, see the section “[Entering Console Window Commands](#)” on page 117. For a complete reference description of each console command, see “[Console Window Commands](#)” on page 122. The commands are summarized in “[Console Command Summary](#)” on page 155.

Connecting the Console Window

Activating Console Input

To send console commands to the handheld device, you must connect your desktop computer to the handheld device, activate the console nub on the device, and then type commands into the console window.

The console nub runs as a background thread on the device, listening for commands on the serial or USB port. To activate the console nub, use the , as described in “[Using Shortcut Numbers to Activate the Windows](#)” on page 115.

When the console nub activates, it sends out a “Ready” message. If your desktop computer is connected to the device when the nub is activated, this message will display in the console window.

IMPORTANT: The console nub activates at 57,600 baud, and your port configuration must match this is you are connecting over a serial port. You must set the connection parameters correctly for communications to work.

After you activate the console nub on the handheld device, the nub prevents other applications, including HotSync® from using the serial port. You have to soft-reset the handheld device before the port can be used.

Verifying Your Connection

To verify your device connection, you can type one of the simple console commands, such as `dir` or `hl 0`. If your connection is working and the console nub is active on the handheld device, you will see a list of memory heaps displayed in the window.

If the console nub is not running on the handheld device, or if the communications connection is not correctly configured, you will see an error message:

```
### Error $00000404 occurred
```

If you are certain that the console nub is running on the handheld, you need to set the connection parameters correctly. If you are using the console with Palm Debugger, you can use the Communications menu to set the parameters.

Using Shortcut Numbers to Activate the Windows

Palm OS responds to a number of “hidden” shortcuts for debugging your programs, including shortcuts for activating the console nub on the handheld device. You generate each of these shortcuts by drawing characters on your Palm Powered™ device, or by drawing them in the Palm OS® Emulator emulator program, if you are using Palm OS Emulator to debug your program.

NOTE: If you open the Find dialog box on the handheld device before entering a shortcut number, you get visual feedback as you draw the strokes.

To enter a shortcut number, follow these steps:

1. On your Palm Powered device, or in the emulator program, draw the shortcut symbol. This is a lowercase, cursive “L” character, drawn as follows:

Using the Console Window

Connecting the Console Window



2. Next, tap the stylus twice, to generate a dot (a period).
3. Next, draw a number character in the number entry portion of the device's text entry area. [Table 4.1](#) shows the different shortcut numbers that you can use.

For example, to activate the console nub on the handheld device, enter the follow sequence:



Table 4.1 Shortcut Numbers for Debugging




Number	Description	Notes
 .1	The device enters debugger mode, and waits for a low-level debugger to connect. A flashing square appears in the top left corner of the device.	<p>This mode opens a serial port, which drains power over time.</p> <p>You must perform a soft reset or use the debugger's <code>reset</code> command to exit this mode.</p>

Table 4.1 Shortcut Numbers for Debugging (*continued*)

Number	Description	Notes
 .2	The device enters console mode, and waits for communication, typically from a high-level debugger.	This mode opens a serial port, which drains power over time. You must perform a soft reset to exit this mode.
 .3	The device's automatic power-off feature is disabled.	You can still use the device's power button to power it on and off. Note that your batteries can drain quickly with automatic power-off disabled. You must perform a soft reset to exit this mode.

NOTE: These debugging shortcuts leave the device in a mode that requires a soft reset. To perform a soft reset, press the reset button on the back of the handheld with a blunt instrument, such as a paper clip.

Entering Console Window Commands

You use the console window to enter console commands, which are typically used for administrative tasks such as managing databases on the handheld device. Commands that you type into the console window are sent to the console nub on the handheld device, and the results sent back from the device are displayed in the console window.

NOTE: Console command input is not case sensitive.

[Table 4.2](#) shows the most commonly used console window commands.

Using the Console Window

Entering Console Window Commands

Table 4.2 Commonly Used Console Commands

Command	Description
<u>del</u>	Deletes a database from the handheld device.
<u>dir</u>	Displays a list of the databases on the handheld device.
<u>export</u>	Copies a Palm OS database from the handheld device to the desktop computer.
<u>import</u>	Copies a Palm OS database from the desktop computer to the handheld device.

[Listing 4.1](#) shows an example of using console commands. In this example, **boldface** is used to denote commands that you type.

Listing 4.1 Importing a Database into the Handheld Device

```
import 0 "C:\Documents\MyDbs\Tex2HexApp.prc"
```

```
Creating Database on card 0
name: Text to Hex
type appl, creator TxHx
```

```
Importing resource 'code'=0....
Importing resource 'data'=0....
Importing resource 'pref'=0....
Importing resource 'rloc'=0....
Importing resource 'code'=1....
Importing resource 'tFRM'=1000....
Importing resource 'tver'=1....
Importing resource 'tAIB'=1000....
Importing resource 'Tbmp'=1000....
Importing resource 'Tbmp'=1001....
Importing resource 'MBAR'=1000....
Importing resource 'Talt'=1000....
Importing resource 'Talt'=1001....
Success!!
```

```
dir 0
```

```
name                ID        total      data
-----
```

Using the Console Window

Entering Console Window Commands

*System	00D20A44	392.691 Kb	390.361 Kb
*AMX	00D209C4	20.275 Kb	20.123 Kb
*UIAppShell	00D20944	1.327 Kb	1.175 Kb
*PADHTAL Library	00D208E2	7.772 Kb	7.674 Kb
*IrDA Library	00D20876	39.518 Kb	39.402 Kb
*Net Library	00D207E2	86.968 Kb	86.780 Kb
*PPP NetIF	00D2073A	30.462 Kb	30.238 Kb
*SLIP NetIF	00D20692	15.812 Kb	15.588 Kb
*Loopback NetIF	00D20630	1.810 Kb	1.712 Kb
*MS-CHAP Support	00D205C4	4.342 Kb	4.226 Kb
*Network	00D203D2	40.442 Kb	39.624 Kb
*Address Book	00D20226	59.825 Kb	59.133 Kb
*Calculator	00D2002A	14.597 Kb	13.761 Kb
*Date Book	00D1FCF8	106.200 Kb	104.806 Kb
*Launcher	00D1FA98	36.633 Kb	35.617 Kb
*Memo Pad	00D1F91E	24.267 Kb	23.665 Kb
*Preferences	00D1F876	1.403 Kb	1.179 Kb
*Security	00D1F706	8.414 Kb	7.830 Kb
*HotSync	00D1F334	39.078 Kb	37.396 Kb
*To Do List	00D1F1E2	33.232 Kb	32.702 Kb
*Digitizer	00D1F126	2.002 Kb	1.742 Kb
*General	00D1EFE8	8.749 Kb	8.255 Kb
*Formats	00D1EF4A	4.732 Kb	4.526 Kb
*ShortCuts	00D1EE34	6.499 Kb	6.077 Kb
*Owner	00D1ED5A	4.095 Kb	3.781 Kb
*Buttons	00D1EC4E	7.419 Kb	7.015 Kb
*Modem	00D1EB74	8.222 Kb	7.908 Kb
*Mail	00D1E838	59.765 Kb	58.353 Kb
*Expense	00D1E614	42.304 Kb	41.396 Kb
*Unsaved Preferences	0001811B	0.898 Kb	0.550 Kb
*Net Prefs	00018133	0.084 Kb	0.000 Kb
AddressDB	00018137	66.149 Kb	51.945 Kb
MemoDB	0001815F	2.186 Kb	1.902 Kb
ToDoDB	00018173	1.000 Kb	0.876 Kb
MailDB	0001817F	1.033 Kb	0.929 Kb
DatebookDB	000181EB	53.162 Kb	29.678 Kb
System MIDI Sounds	000181B3	1.066 Kb	0.842 Kb
*Saved Preferences	00018123	3.753 Kb	3.031 Kb
NetworkDB	0001818B	0.986 Kb	0.722 Kb
*Giraffe High Score	00018273	0.126 Kb	0.020 Kb
Datebk3DB	0001827B	0.084 Kb	0.000 Kb
ReDoDB	0001827F	0.084 Kb	0.000 Kb
LauncherDB	0001814F	0.294 Kb	0.190 Kb
*MineHunt	00018287	9.810 Kb	9.264 Kb
*SubHunt	000182DF	17.700 Kb	16.758 Kb
*Puzzle	0001837F	5.256 Kb	4.886 Kb
*HardBall	000183B7	18.877 Kb	18.177 Kb
Pictures	0001842B	0.084 Kb	0.000 Kb

Using the Console Window

Command Syntax

```
*Jot                0001842F  120.409 Kb  119.841 Kb
*Graffiti ShortCuts 001FFE7F    2.872 Kb   2.766 Kb
*UnDupe             001FFE87    9.462 Kb   9.070 Kb
*WordView           001FFEC3   17.320 Kb  16.752 Kb
*SheetView          001FFF1F   56.753 Kb  55.877 Kb
  AOU Birds of NA   001FFE15  130.265 Kb  90.021 Kb
  ExpenseDB         001FBCB5    0.150 Kb   0.046 Kb
  DocsToGoDB        001FBCC1    0.326 Kb   0.202 Kb
  birds.PDB         001FBCD1    0.709 Kb   0.585 Kb
  foo               0001812F    0.084 Kb   0.000 Kb
*Text To Hex        001FFF85   34.725 Kb  33.827 Kb
-----
---
Total: 59
```

These and all of the other console commands are described in detail in “[Console Window Commands](#)” on page 122.

Command Syntax

This chapter uses the following syntax to specify the format of debugger commands:

```
commandName <parameter> [options]
```

commandName The name of the command.

parameter Parameter(s) for the command. Each parameter name is enclosed in angle brackets (< and >).

Sometimes a parameter can be one value or another. In this case the parameter names are bracketed by parentheses and separated by the | character.

options Optional flags that you can specify with the command. Note that options are specified with the dash (-) character in the console window.

NOTE: Any portion of a command that is shown enclosed in square brackets (“[” and “]”) is optional.

The following is an example of a command definition

```
dir (<cardNum>|<srchOptions>) [displayOptions]
```

The [dir](#) command takes either a card number or a search specification, followed by display options.

Here are two examples of the `dir` command sent from the console window:

```
dir 0 -a  
dir -t rsrc
```

Specifying Command Options

All command options and some command parameters are specified as flags that begin with a dash. For example:

```
-c  
-enable
```

Some flags are followed by a keyword or value. You must leave white space between the flag and the value. For example:

```
-f D:\temp\myLogFile  
-t Rsrc
```

NOTE: You use the dash (-) character to specify options for console commands. If you are using Palm Debugger, you must use the backslash (\) character to specify options for commands that you type in the debugging window; this is because the expression parser used for debugging commands interprets the dash as a minus sign.

Specifying Numeric and Address Values

Many of the console commands take address or numeric arguments. You can specify these values in hexadecimal, decimal, or binary. All values are assumed to be hexadecimal unless preceded by a sign that specifies decimal (#) or binary (%). [Table 4.3](#) shows values specified as binary, decimal, and hexadecimal in a debugging command:

Using the Console Window

Console Window Commands

Table 4.3 Specifying Numeric Values in Palm Debugger

Hex value	Decimal value	Binary value
64 or \$64	#100	%01100100
F5 or \$F5	#245	%11110101
100 or \$100	#256	%100000000

Console Window Commands

You use the console window to send commands to the console nub that is running on the handheld device.

This section provides a description of all of the commands in alphabetical order. For convenience, the commands are categorized here:

Table 4.4 Console Window Command Categories

Command category	Commands
Card Information	cardformat , cardinfo , and storeinfo .
Chunk Utility	free , info , lock , new , resize , setowner , and unlock .
Database Utility	close , create , del , dir , export , import , open , opened , and setinfo .
Debugging Utility	dm , gdb , mdebug , and sb .
Gremlin	gremlin and gremlinoff .
Heap Utility	hc , hchk , hd , hf , hi , hl , hs , ht , and htorture .
Host Control	help , log , and saveimages .
Miscellaneous Utility	simsync and sysalarmdump .
Record Utility	addrecord , delrecord , detachrecord , findrecord , listrecords , moverecord , and setrecordinfo .

Table 4.4 Console Window Command Categories (*continued*)

Command category	Commands
Resource Utility	addresource , attachresource , changeresource , delresource , detachresource , listresources , and setresourceinfo .
System	battery , coldboot , doze , exit , feature , kinfo , launch , performance , poweron , reset , sleep , and switch .

addrecord

Purpose	Adds a record to a database.						
Usage	<code>addrecord <accessPtr> <index> <recordText></code>						
Parameters	<table> <tr> <td><code>accessPtr</code></td><td>A pointer to the database.</td></tr> <tr> <td><code>index</code></td><td>The index of the record in the database.</td></tr> <tr> <td><code>recordText</code></td><td>The record data.</td></tr> </table>	<code>accessPtr</code>	A pointer to the database.	<code>index</code>	The index of the record in the database.	<code>recordText</code>	The record data.
<code>accessPtr</code>	A pointer to the database.						
<code>index</code>	The index of the record in the database.						
<code>recordText</code>	The record data.						

addresource

Purpose	Adds a resource to a database.								
Usage	<code>addresource <accessPtr> -t <type> -id <id> <resourceText></code>								
Parameters	<table> <tr> <td><code>accessPtr</code></td><td>A pointer to the database.</td></tr> <tr> <td><code>type</code></td><td>The type of the resource that you are adding.</td></tr> <tr> <td><code>id</code></td><td>The ID for the resource that you are adding.</td></tr> <tr> <td><code>resourceText</code></td><td>The resource data.</td></tr> </table>	<code>accessPtr</code>	A pointer to the database.	<code>type</code>	The type of the resource that you are adding.	<code>id</code>	The ID for the resource that you are adding.	<code>resourceText</code>	The resource data.
<code>accessPtr</code>	A pointer to the database.								
<code>type</code>	The type of the resource that you are adding.								
<code>id</code>	The ID for the resource that you are adding.								
<code>resourceText</code>	The resource data.								

Using the Console Window

attachrecord

attachrecord

Purpose	Attaches a record to a database.	
Usage	<code>attachrecord <accessPtr> <recordHandle> <index> [options]</code>	
Parameters	<code>accessPtr</code>	A pointer to the database.
	<code>recordHandle</code>	A handle to the record that you are attaching to the database.
	<code>index</code>	The index of the record.
	<code>options</code>	Optional. You can specify the following option: -r Replaces the existing record with the same index, if one exists.

attachresource

Purpose	Attaches a resource to a database.	
Usage	<code>attachrecord <accessPtr> <recordHandle> <index> [options]</code>	
Parameters	<code>accessPtr</code>	A pointer to the database.
	<code>recordHandle</code>	A handle to the resource that you are attaching to the database.
	<code>index</code>	The index of the resource.
	<code>options</code>	Optional. You can specify the following option: -r Replaces the existing resource with the same index, if one exists.

battery

Purpose	A battery utility command for performing battery operations.	
Usage	<code>battery [options]</code>	
Parameters	<code>options</code>	Optional. Specifies the battery operation to perform. Use one of the following values:

Example `battery -rStop`

Using the Console Window

changerecord

Free Bytes : 0015ACB2
Number of heaps: #3

changerecord

Purpose Replaces a record in a database.

Usage `changerecord <accessPtr> <index> <recordText>`

Parameters

<code>accessPtr</code>	A pointer to the database.
<code>index</code>	The index of the record in the database.
<code>recordText</code>	The new record data.

changeresource

Purpose Replaces a resource in a database.

Usage `changeresource <accessPtr> <index> <recordText>`

Parameters

<code>accessPtr</code>	A pointer to the database.
<code>index</code>	The index of the resource in the database.
<code>resourceText</code>	The new resource data.

close

Purpose Closes a database.

Usage `close <accessPtr>`

Parameters

<code>accessPtr</code>	A pointer to the database.
------------------------	----------------------------

coldboot

Purpose Initiates a hard reset on the handheld device.

Usage `coldboot`

Parameters None

Comments Use the `coldboot` command to perform a hard reset of the handheld device. A hard reset erases all data on the device, restoring it to its new condition.

The handheld device requires confirmation of this operation. You are prompted to press the Up button on the device to confirm that you want to perform a hard reset, or press any other button to cancel the operation.

Example `coldboot`

create

Purpose Creates a new database on the handheld device.

Usage `create <cardNum> <name> [options]`

Parameters

<code>cardNum</code>	The card number whose databases you want listed. You almost always use 0 to specify the built-in RAM.
<code>name</code>	The name for the new database on the handheld device.
<code>options</code>	Optional. Specifies information about the new database: <ul style="list-style-type: none"> <code>-t <type></code> The 4-character database type identifier. <code>-c <creator></code> The 4-character database creator ID. <code>-v <version></code> The database version number. <code>-r</code> Specify to indicate that the database is a resource database.

Comments Use the `create` command to create a new record or resource database on the handheld device.

Using the Console Window

del

del	Purpose	Deletes a database from the handheld device.	
	Usage	del <cardNum> <fileName>	
	Parameters	cardNum	The card number on which the database is located. You almost always use 0 to specify the built-in RAM.
		fileName	The name of the database on the handheld device. Note that you must quote the database name if it contains spaces.
	Comments	<p>Use the del command to delete a database from the specified card on the handheld device.</p> <p>You can get a list of the databases on the device with the dir command.</p> <p>You cannot delete an open database.</p>	
	Result	If the database you want to delete is not found or is currently opened, you receive an error message.	
	Example	<pre>del 0 birds.pdb</pre> <pre>Success!!</pre>	

delrecord

Purpose	Deletes a record from a database.				
Usage	<code>delrecord <accessPtr> <index></code>				
Parameters	<table><tr><td><code>accessPtr</code></td><td>A pointer to the database.</td></tr><tr><td><code>index</code></td><td>The index of the record in the database.</td></tr></table>	<code>accessPtr</code>	A pointer to the database.	<code>index</code>	The index of the record in the database.
<code>accessPtr</code>	A pointer to the database.				
<code>index</code>	The index of the record in the database.				
Comments	Use the <code>delrecord</code> command to delete the record at the specified <code>index</code> value from the database specified by <code>accessPtr</code> .				

delresource

e Purpose	Deletes a resource from a database.	
Usage	<code>delresource <accessPtr> <index></code>	
Parameters	<code>accessPtr</code>	A pointer to the database.
	<code>index</code>	The index of the resource in the database.
Comments	Use the <code>delresource</code> command to delete the resource at the specified <code>index</code> value from the database specified by <code>accessPtr</code> .	

detachrecord

rd Purpose	Detaches a record from a database.	
Usage	<code>detachrecord <accessPtr> <index></code>	
Parameters	<code>accessPtr</code>	A pointer to the database.
	<code>index</code>	The index of the record in the database.
Comments	Use the <code>detachrecord</code> command to detach the record at the specified <code>index</code> value from the database specified by <code>accessPtr</code> .	

detachresource

urce Purpose	Detaches a resource from a database.	
Usage	<code>detachresource <accessPtr> <index></code>	
Parameters	<code>accessPtr</code>	A pointer to the database.
	<code>index</code>	The index of the resource in the database.
Comments	Use the <code>detachresource</code> command to detach the resource at the specified <code>index</code> value from the database specified by <code>accessPtr</code> .	

dir

Purpose	Displays a list of the databases on the handheld device.	
Usage	<code>dir (<cardNum> <searchOptions>) [<displayOptions>]</code>	
Parameters	<code>cardNum</code>	The card number whose databases you want listed. You almost always use 0 to specify the built-in RAM.

Using the Console Window

dir

<code>searchOptions</code>	<p>Optional. Options for listing a specific database. Specify any combination of the following flags.</p> <ul style="list-style-type: none"><code>-c <creatorID></code> Search for a database by creator ID.<code>-latest</code> List only the latest version of each database.<code>-t <typeID></code> Search for a database by its type.
<code>displayOptions</code>	<p>Optional. Options for which information is displayed in the listing. Specify any combination of the following flags.</p> <ul style="list-style-type: none"><code>-a</code> Show all information.<code>-at</code> Show the database attributes.<code>-d</code> Show the database creation, modification, and backup dates.<code>-i</code> Show the database appInfo and sortInfo field values.<code>-id</code> Show the database chunk ID<code>-s</code> Show the database size<code>-m</code> Show the database modification number.<code>-n</code> Show the database name.<code>-r</code> Show the number of records in the database.<code>-tc</code> Show the database type ID and creator ID.<code>-v</code> Show the database version number.

Comments Use the `dir` command to display a list of the databases on a specific card or in the handheld device built-in RAM. You typically use the following command to list all of the databases stored in RAM on the handheld device:


```
dir 0
```

Or use the -a switch to display all of the information for each database:

```
dir 0 -a
```

Example

```
dir 0
```

name	ID	total	data

*System	00D20A44	392.691 Kb	390.361 Kb
*AMX	00D209C4	20.275 Kb	20.123 Kb
*UIAppShell	00D20944	1.327 Kb	1.175 Kb
*PADHTAL Library	00D208E2	7.772 Kb	7.674 Kb
*IrDA Library	00D20876	39.518 Kb	39.402 Kb
...			
MailDB	0001817F	1.033 Kb	0.929 Kb
NetworkDB	0001818B	0.986 Kb	0.722 Kb
System MIDI Sounds	000181B3	1.066 Kb	0.842 Kb
DatebookDB	000181FB	0.084 Kb	0.000 Kb

Total: 41			

dm Purpose Displays a range of memory values.

Usage dm <addr> [<count>]

Parameters

addr	The starting memory address to be displayed.
count	The number of bytes to be displayed. If this is omitted, eight bytes of data are displayed.

Example dm 0000f000

```
0000F000: 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00
.....
```

doze Purpose Instructs the handheld device's CPU to sleep while maintaining the peripherals and the clock.

Usage doze [options]

Parameters options You can optionally specify the following flags:

Using the Console Window

exit

`-light`

The handheld device will awaken in response to any interrupt.

Example `doze -light`

exit **Purpose** Exits the debugger.

Usage `exit`

Parameters None.

export

Purpose Copies a Palm OS database from the handheld device to the desktop computer.

Usage `export <cardNum> <fileName>`

Parameters `cardNum` The card number on which the database is located. You almost always use 0 to specify the built-in RAM.

`fileName` The name of the database on the handheld device. Note that you must quote the database name if it contains spaces.

Comments Use the `export` command to copy a database from the handheld device to your desktop computer. You can get a list of the databases on the device with the [dir](#) command.

If the database contains resources, it is copied in standard PRC format; if the database contains records, it is copied in standard PDB format. Note that these two formats are actually identical.

The exported file is stored in the `Device` subdirectory of the directory in which Palm Debugger executable is stored.

The exported file is named `fileName`, with no added extensions.

Example `export 0 "Text to Hex"`

```
Exporting resource 'code'=0....
Exporting resource 'data'=0....
Exporting resource 'pref'=0....
```

```
Exporting resource 'rloc'=0....
Exporting resource 'code'=1....
Exporting resource 'tFRM'=1000....
Exporting resource 'tver'=1....
Exporting resource 'tAIB'=1000....
Exporting resource 'Tbmp'=1000....
Exporting resource 'Tbmp'=1001....
Exporting resource 'MBAR'=1000....
Exporting resource 'Talt'=1000....
Exporting resource 'Talt'=1001....
Success!!
```

feature

Purpose	Accesses features.
Usage	feature [options]

Using the Console Window

findrecord

Parameters options Optional. You can use the following options:

- all
Displays a list of all known features
- unreg <creator> <num>
Unregisters the specified feature
- get <creator> <num>
Displays the value of a feature
- set <creator> <num> <value>
Sets the value of a feature.

Example feature -all

```
ROM:  creator  number  value
      'psys'    #1      03003000
      'psys'    #2      00010000
RAM:   creator  number  value
      'psys'    #3      00000001
      'psys'    #4      00000001
      'psys'    #7      00000001
      'netl'    #0      02003000
      'irda'    #0      03003000
```

```
feature -get psys 3
```

```
Value = 00000001
```

findrecord

Purpose Finds a record by ID.

Usage findrecord <accessPtr> <id>

Parameters

accessPtr	A pointer to the database.
id	The unique record ID.

free	Purpose	Disposes of a chunk.
	Usage	<code>free (<hexChunkPtr> localID>) [options]</code>
	Parameters	<div> <div>hexChunkPtr or localID</div> <div>A pointer to a chunk in memory, or the ID of a chunk on the specified card number.</div> </div> <div> <div>options</div> <div>Optional. You can specify the following options:</div> <div>-card <cardNum></div> <div>The card number if a local ID is specified instead of a chunk pointer.</div> </div>
gdb	Purpose	Enables or disables gdb debugging
	Usage	<code>gdb [options]</code>
	Parameters	<div> <div>options</div> <div>Optional. You can specify the following options:</div> <div>-enable</div> <div>Enables gdb debugging.</div> <div>-disable</div> <div>Disables gdb debugging.</div> </div>
getresource		
e	Purpose	Retrieves the specified resource.
	Usage	<code>getresource -t <type> -id <id></code>
	Parameters	<div> <div>type</div> <div>The type of resource that you want to retrieve.</div> </div> <div> <div>id</div> <div>The ID of the resource that you want to retrieve.</div> </div>

Using the Console Window

gremlin

gremlin

Purpose	Activates a Gremlin until the specified event occurs.	
Usage	gremlin <num> <until>	
Parameters	num	The number of the Gremlin to activate.
	until	The event that deactivates the Gremlin.

gremlinoff

Purpose	Deactivates the current Gremlin.
Usage	gremlinoff
Parameters	None
Example	gremlinoff

hc

Purpose	Compacts a memory heap.	
Usage	hc <heapId>	
Parameters	heapId	The hexadecimal number of the heap to be compacted. Heap number 0x0000 is always the dynamic heap.
Example	hc 0002 Heap Compacted	

hchk

Purpose	Checks the integrity of a heap.	
Usage	hchk <heapId> [options]	
Parameters	heapId	The hexadecimal number of the heap whose contents are to be checked. Heap number 0x0000 is always the dynamic heap.
	options	Optional. You can specify the following option: -c Check the contents of each chunk.
Example	hchk 0000 Heap OK	

hd	Purpose	Displays a hexadecimal dump of the specified heap.										
	Usage	hd <heapId>										
	Parameters	heapId	The hexadecimal number of the heap whose contents are to be displayed. Heap number 0x0000 is always the dynamic heap.									
	Comments	Use the hd command to display a dump of the contents of a specific heap from the handheld device. You can use the hl command to display the heap IDs.										
	Example	hd 0										
		Displaying Heap ID: 0000, mapped to 00001480										
		req	act									
		resType/	#resID/									
		start	handle	localID	size	size	lck	own	flags	type		
		index	attr	ctg	uniqueID	name						

		-00001534	00001494	F0001495	000456	00045E	#0	#0		fM		
		Graffiti Private										
		-00001992	00001498	F0001499	000012	00001A	#0	#0		fM		
		DataMgr Protect List (DmProtectEntryPtr*)										
		-000019AC	00001490	F0001491	00001E	000026	#0	#0		fM	Alarm	
		Table										
		-000019D2	0000148C	F000148D	000038	000040	#0	#0		fM		
		*00001A12	0000149C	F000149D	000396	00039E	#2	#1		fM	Form	
		"3:03 pm"										
		*00001DB0	000014A0	F00014A1	00049A	0004A2	#2	#0		fM		
		00002252	-----	F0002252	00002E	00003E	#0	#0		FM		
		00002290	-----	F0002290	00EC40	00EC50	#0	#0		FM		
		-00010EE0	-----	F0010EE0	000600	000608	#0	#15		fM		
		Stack: Console Task										
		...										
		000114E8	-----	F00114E8	000FF8	001008	#0	#0		FM		
		-000124F0	-----	F00124F0	001000	001008	#0	#15		fM		
		-00017D30	-----	F0017D30	00003C	000044	#0	#15		fM		
		SysAppInfoPtr: AMX										
		-00017D74	-----	F0017D74	000008	000010	#0	#15		fM		
		Feature Manager Globals (FtrGlobalsType)										
		-00017D84	-----	F0017D84	000024	00002C	#0	#15		fM		
		DmOpenInfoPtr: 'Update 3.0.2'										
		-00017DB0	-----	F0017DB0	00000E	000016	#0	#15		fM		
		DmOpenRef: 'Update 3.0.2'										

Using the Console Window

help

```
-00017DC6 ----- F0017DC6 0001F4 0001FC #0 #15 fM
Handle Table: 'Ô@Update 3.0.2'
-00017FC2 ----- F0017FC2 000024 00002C #0 #15 fM
DmOpenInfoPtr: 'Ô@Update 3.0.2'
-00017FEE ----- F0017FEE 00000E 000016 #0 #15 fM
DmOpenRef: 'Ô@Update 3.0.2'
```

Heap Summary:

```
flags:                8000
size:                 016B80
numHandles:           #40
Free Chunks:          #14      (010C50 bytes)
Movable Chunks:       #51      (005E80 bytes)
Non-Movable Chunks:  #0        (000000 bytes)
```

help **Purpose** Displays a list of commands or help for a specific command.

Usage help
 help <command>

Parameters command The name of the command for which you want help displayed.

Example help hchk

Do a Heap Check.

Syntax: hchk <hex heapID> [options...]

 -c : Check contents of each chunk

hf **Purpose** Allocates almost all of the free bytes in a heap, reserving the specified amount of free space.

Usage hf <heapId> <freeBytes>

Parameters heapId The hexadecimal number of the heap. Heap number 0x0000 is always the dynamic heap.

 freeBytes The number of bytes to leave unallocated.

Example hf 0000 20

hi **Purpose** Initializes the specified memory heap.

Usage hi <heapId>

Parameters heapId The hexadecimal number of the heap to be initialized. Heap number 0x0000 is always the dynamic heap.

Example hi 0006

hl **Purpose** Displays a list of memory heaps.

Usage hl <cardNum>

Parameters cardNum The card number on which the heaps are located. You almost always use 0 to specify the built-in RAM.

Comments Use the hl command to list the memory heaps in built-in RAM or on a card.

Example hl 0

index	heapID	heapPtr	size	free	maxFree	flags
0	0000	00001480	00016B80	00010C50	0000EC48	8000
1	0001	1001810E	001E7EF2	0014AD6A	00147D3A	8000
2	0002	10C08212	00118DEE	0000A01C	0000A014	8001

hs **Purpose** Scrambles the specified heap.

Usage hs <heapId>

Parameters heapId The hexadecimal number of the heap to be scrambled. Heap number 0x0000 is always the dynamic heap.

Comments Scrambling a heap moves its contents around. You can use this to verify that the program is using handles in the prescribed manner.

Example hs 0002
 heap scrambled

Using the Console Window

ht

ht	Purpose	Displays summary information for the specified heap.	
	Usage	ht <heapId>	
	Parameters	heapId	The hexadecimal number of the heap to be scrambled. Heap number 0x0000 is always the dynamic heap.
	Comments	The ht command displays the summary information that is also shown at the end of a heap dump generated by the hd command.	
	Example	<pre>ht 0000 Displaying Heap ID: 0000, mapped to 00001480 ----- Heap Summary: flags: 8000 size: 016B80 numHandles: #40 Free Chunks: #14 (010CAA bytes) Movable Chunks: #48 (005E26 bytes) Non-Movable Chunks: #0 (000000 bytes)</pre>	

htorture

Purpose	Tortures a heap to test its integrity.		
Usage	htorture <heapId> [options]		
Parameters	heapId	The hexadecimal number of the heap to be tortured. Heap number 0x0000 is always the dynamic heap.	
	options	Optional. You can specify a combination of the following options:	
		-c	Checks the contents of every chunk.
		-f <number>	Reports if the heap is filled beyond the specified percentage. The default is 90 percent.
		-l <filename>	Specifies the name of the log file

`-m <hexSize>`

The maximum chunk size. The default value is 0x400.

`-p <level>`

The progress level to display. Specify a number between 0 (minimum detail) and 2 (maximum detail). The default value is 0.

Comments Use the `htorture` command to torture-test a memory heap. You can specify a logging file to which the output of the test is sent. You can also use the `-p` command to control how progress is displayed.

import

Purpose Copies a Palm OS database from the desktop computer to the handheld device.

Usage `import <cardNum> <fileName>`

Parameters

<code>cardNum</code>	The card number on which the database is to be installed. You almost always use 0 to specify the built-in RAM.
<code>fileName</code>	The name of the file on the desktop computer. You can specify an absolute file name path, or a relative file name path.

The default search path is the `Device` subdirectory of the directory in which Palm Debugger executable is stored.

Comments Use the `import` command to load a new version of your application or database onto the handheld device.

This command provides a more convenient install operation and has the same functionality as the installer tool provided with the HotSync Manager application.

The name of the database on the handheld device is the name stored in the file, and is not the same as the file name. If a database with a matching name is already open on the handheld device, an error is generated. If a database with a matching name is already stored on

Using the Console Window

info

the handheld device, that database is deleted and replaced by the file.

Result If a database with a matching name is currently open on the handheld device, the `dmErrAlreadyExists` error code (0x0219) is generated.

Example

```
import 0 Tex2HexApp.prc

Creating Database on card 0
name: Text to Hex
type appl, creator TxHx

Importing resource 'code'=0....
Importing resource 'data'=0....
Importing resource 'pref'=0....
Importing resource 'rloc'=0....
Importing resource 'code'=1....
Importing resource 'tFRM'=1000....
Importing resource 'tver'=1....
Importing resource 'tAIB'=1000....
Importing resource 'Tbmp'=1000....
Importing resource 'Tbmp'=1001....
Importing resource 'MBAR'=1000....
Importing resource 'Talt'=1000....
Importing resource 'Talt'=1001....
Success!!
```

info Purpose Displays information about a memory chunk.

Usage `info (<hexChunkPtr> | localID) [options]`

Parameters `hexChunkPtr` or `localID`

A pointer to a chunk in memory, or the ID of a chunk on the specified card number.

`options` Optional. You can specify the following options:

`-card <cardNum>`

The card number if a local ID is specified instead of a chunk pointer.

kinfo Purpose	Displays a list of all system kernel information.		
Usage	kinfo [options]		
Parameters	options	Optional. Specify the kernel information that you want to see displayed. Use a combination of the following flags:	
	-all	Display all kernel information.	
	-task (<id> all)	Display task information.	
	-sem (<id> all)	Display semaphore information.	
	-tmr (<id> all)	Display timer information.	
Comments	Use the kinfo command to display a list of system kernel information, including tasks, semaphores, event groups, and timers.		
Example	kinfo -all		

Task Information:

taskID	tag	priority	stackPtr	status

000176EA	AMX	# 0	00017556	Idle: Waiting for Trigger
000178BE	psys	# 30	00013364	Waiting on event timer
0001795A	CONS	# 10	0001103E	Running

Semaphore Information:

semID	tag	type	initValue	curValue	nesting	ownerID

000177EE	MemM	resource	#-1	#1 (free)	#0	00000000
00017822	SlkM	counting	#1	#1 (avail.)	#0	00000000
0001788A	SndM	counting	#1	#1 (avail.)	#0	00000000
00017A5E	SerM	counting	#0	#0 (unavail.)	#0	00000000

Timer Information:

tmrID	tag	ticksLeft	period	procPtr

000177BA	psys	# 83	# 0	10C6C618

Using the Console Window

launch

launch

Purpose Launches an application on the handheld device.

Usage `launch [-t] [-ns] [-ng] <cardNum> <name> [<cmd>
<cmdStr>`

Parameters	-t	Launches the application as a separate task.
	-ns	Use the caller's stack.
	-ng	Use the caller's globals environment.
	cardNum	The card number on which application is located. You almost always use 0 to specify the built-in RAM.
	name	The name of the application to be launched.
	cmd	Optional. Use to specify a command for the application.
	cmdStr	Optional. Use to specify an arguments string for cmd.

listrecords

Purpose Lists the records in a database.

Usage `listrecords <accessPtr>`

Parameters `accessPtr` A pointer to the database.

listresources

Purpose Lists the resources in a database.

Usage `listresources <accessPtr>`

Parameters `accessPtr` A pointer to the database.

lock	Purpose	Locks a memory chunk.
	Usage	<code>lock (<hexChunkPtr> localID) [options]</code>
	Parameters	<div> <div>hexChunkPtr or localID</div> <div>A pointer to a chunk in memory, or the ID of a chunk on the specified card number.</div> </div> <div> <div>options</div> <div>Optional. You can specify the following options:</div> <div> <div>-card <cardNum></div> <div>The card number if a local ID is specified instead of a chunk pointer.</div> </div> </div>

log	Purpose	Toggles logging of debugger output to a file.
	Usage	<code>log <fileName></code>
	Parameters	<div> <div>fileName</div> <div>The name of the file to which debugger output is sent.</div> </div>
	Comments	Use the <code>log</code> command to start or stop logging of debugger output to a file.

mdebug

	Purpose	Sets the Memory Manager debug mode, which you can use to track down memory corruption problems.
	Usage	<code>mdebug [options]</code>
	Parameters	<div> <div>options</div> <div>Optional. Specify the kernel information that you want to see displayed. Use a combination of the following flags:</div> <div> <div>-full</div> <div>Shortcut for full debugging.</div> <div>-partial</div> <div>Shortcut for partial debugging.</div> <div>-off</div> <div>Shortcut to disable debugging.</div> </div> </div>

Using the Console Window

mdebug

- a Check/scramble all heaps each time.
- a- Check only the heap currently in use.
- c Check heap(s) on some memory calls.
- ca Check heap(s) on all memory calls.
- c- Do not check heaps.
- f Check free chunk contents.
- f- Do not check free chunk contents.
- min
Store minimum available free space in
dynamic heap in the global variable
GMemMinDynHeapFree.
- min-
Do not record minimum free space.
- s Scramble heap(s) on some memory calls.
- sa Scramble heap(s) on all memory calls.
- s- Do not scramble heaps.

Comments Use the `mdebug` command to enable debugging for tracking down memory corruption problems.

IMPORTANT: The different debug modes enabled by `mdebug` can significantly slow down operations on the handheld device. Full checking is slowest, partial checking is slow, and only enabling specific options is the fastest.

Example

```
mdebug -full
Current mode = 003A
Every heap checked/scrambled per call
Heap(s) checked on EVERY Mem call
Heap(s) scrambled on EVERY Mem call
Free chunk contents filled & checked
Minimum dynamic heap free space recording OFF
```


moverecor

d

Purpose	Moves a record in the database by changing its index.						
Usage	<code>moverecord <accessPtr> <fromIndex> <toIndex></code>						
Parameters	<table><tr><td><code>accessPtr</code></td><td>A pointer to the database.</td></tr><tr><td><code>fromIndex</code></td><td>The original index of the record in the database.</td></tr><tr><td><code>toIndex</code></td><td>The new index for the record in the database.</td></tr></table>	<code>accessPtr</code>	A pointer to the database.	<code>fromIndex</code>	The original index of the record in the database.	<code>toIndex</code>	The new index for the record in the database.
<code>accessPtr</code>	A pointer to the database.						
<code>fromIndex</code>	The original index of the record in the database.						
<code>toIndex</code>	The new index for the record in the database.						

new **Purpose** Allocates a new chunk in a heap.

Usage `new <heapId> <hexChunkSize> [options]`

Parameters	<table> <tr> <td><code>heapId</code></td><td>The hexadecimal number of the heap in which to allocate a new chunk. Heap number 0x0000 is always the dynamic heap. Note that <code>heapId</code> is ignored if you specify the <code>-near</code> option.</td></tr> <tr> <td><code>hexChunkSize</code></td><td>The number of bytes in the new chunk, specified as a hexadecimal number.</td></tr> <tr> <td><code>options</code></td><td> <p>Optional. You can specify a combination of the following options:</p> <ul style="list-style-type: none"> <code>-c</code> Fill the chunk contents. <code>-lock</code> Pre-lock the chunk. <code>-n</code> Make the chunk unmoveable. <code>-near <ptr></code> Allocate the new chunk in the same heap as the specified pointer. If this option is specified, the <code>heapId</code> is ignored. <code>-o <ownerId></code> Set the owner of the chunk to the specified ID value. </td></tr> </table>	<code>heapId</code>	The hexadecimal number of the heap in which to allocate a new chunk. Heap number 0x0000 is always the dynamic heap. Note that <code>heapId</code> is ignored if you specify the <code>-near</code> option.	<code>hexChunkSize</code>	The number of bytes in the new chunk, specified as a hexadecimal number.	<code>options</code>	<p>Optional. You can specify a combination of the following options:</p> <ul style="list-style-type: none"> <code>-c</code> Fill the chunk contents. <code>-lock</code> Pre-lock the chunk. <code>-n</code> Make the chunk unmoveable. <code>-near <ptr></code> Allocate the new chunk in the same heap as the specified pointer. If this option is specified, the <code>heapId</code> is ignored. <code>-o <ownerId></code> Set the owner of the chunk to the specified ID value.
<code>heapId</code>	The hexadecimal number of the heap in which to allocate a new chunk. Heap number 0x0000 is always the dynamic heap. Note that <code>heapId</code> is ignored if you specify the <code>-near</code> option.						
<code>hexChunkSize</code>	The number of bytes in the new chunk, specified as a hexadecimal number.						
<code>options</code>	<p>Optional. You can specify a combination of the following options:</p> <ul style="list-style-type: none"> <code>-c</code> Fill the chunk contents. <code>-lock</code> Pre-lock the chunk. <code>-n</code> Make the chunk unmoveable. <code>-near <ptr></code> Allocate the new chunk in the same heap as the specified pointer. If this option is specified, the <code>heapId</code> is ignored. <code>-o <ownerId></code> Set the owner of the chunk to the specified ID value. 						

Using the Console Window

open

open

Purpose Opens a database.

Usage `open <cardNum> <name> [options]`

Parameters

<code>cardNum</code>	The card number on which the database is located. You almost always use 0 to specify the built-in RAM.
<code>name</code>	The name of the database.
<code>options</code>	Optional. You can specify the following options: -r Open the database for read-only access. -p Leave the database open.

opened

Purpose Lists all of the currently opened databases.

Usage `opened`

Parameters None.

Example `opened`

name	resDB	cardNum	accessP	ID	openCnt	mode
*Graffiti ShortCuts	yes	0	00017D5C	001FFE7F	1	0007
*System	yes	0	00017FEE	00D20A44	1	0005

Total: 2 databases opened

performance

Purpose Sets the performance level of the handheld device.

Usage `performance [options]`

Parameters

<code>options</code>	You can specify the following options: -b <baud> Uses the specified <baud> rate to
----------------------	--

calculate the nearest clock frequency value.

- d <duty>
Set the CPU duty cycle. The <duty> value specifies the number of CPU cycles out of every 31 system clock ticks.
- f <freq>
Set the system clock frequency to the specified Hz value; select the nearest baud multiple as the frequency.
- ff <freq>
Set the system clock frequency to the specified Hz value; do not pick the nearest baud multiple.

poweron

Purpose	Powers on the handheld device.
Usage	poweron
Parameters	None.
Example	poweron

reset

Purpose	Performs a soft reset on the handheld device.
Usage	reset
Parameters	None.
Comments	This command performs the same reset that is performed when you press the recessed reset button on a Palm Powered handheld device.
Example	reset Resetting system

Using the Console Window

resize

resize

Purpose Resizes an existing memory chunk.

Usage `resize (<hexChunkPtr> | localID>) <hexNewSize>
[options]`

Parameters `hexChunkPtr` or `localID` A pointer to a chunk in memory, or the ID of a chunk on the specified card number.

`hexNewSize` The new size of the chunk, in bytes.

`options` Optional. You can specify the following options:

- `-c` Checks and fills the contents of the resized chunk.
- `-card <cardNum>` The card number if a local ID is specified instead of a chunk pointer.

saveimage

S Purpose Saves a memory card image.

Usage `saveimages`

Parameters None.

sb Purpose Sets the value of a byte in memory.

Usage `sb <addr> <value>`

Parameters `addr` The address of the byte.

`value` The new value of the byte.

setinfo

Purpose	Sets new information values for a database.	
Usage	<code>setinfo <cardNum> <dbName> [options]</code>	
Parameters	<code>cardNum</code>	The card number on which the database is located. You almost always use 0 to specify the built-in RAM.
	<code>dbName</code>	The name of the database.
	<code>options</code>	Options. You can specify a combination of the following values:
	<code>-m <modification></code>	Sets the modification number for the database.
	<code>-n <name></code>	Sets the name of the database.
	<code>-v <version></code>	Sets the version number of the database.

setowner

Purpose	Sets the owner ID of a memory chunk.	
Usage	<code>setowner (<hexChunkPtr> <localID>) <owner> [options]</code>	
Parameters	<code>hexChunkPtr</code> or <code>localID</code>	A pointer to a chunk in memory, or the ID of a chunk on the specified card number.
	<code>hexNewSize</code>	The new size of the chunk, in bytes.
	<code>owner</code>	The new owner ID for the chunk.
	<code>options</code>	Optional. You can specify the following options:
	<code>-card <cardNum></code>	The card number if a local ID is specified instead of a chunk pointer. Use 0 to specify the built-in RAM.

Using the Console Window

setrecordinfo

setrecordinfo

Purpose	Changes information for a record in a database.	
Usage	setrecordinfo <accessPtr> <index> [options]	
Parameters	accessPtr	A pointer to the database.
	index	The index of the record in the database.
	options	Optional. You can specify a combination of the following options:
	<ul style="list-style-type: none">-a <hexAttr> Sets attribute bit settings for the record.-u <uniqueId> Sets unique record ID for the record.	

setresourceinfo

Purpose	Changes information for a resource in a database.	
Usage	setresourceinfo <accessPtr> <index> [options]	
Parameters	accessPtr	A pointer to the database.
	index	The index of the resource in the database.
	options	Optional. You can specify a combination of the following options:
	<ul style="list-style-type: none">-t <resType> Sets resource type for the resource.-id <resId> Sets resource ID for the resource.	

simsync

Purpose	Simulates a synchronization operation on a specific database.	
Usage	simsync <accessPtr>	
Parameters	accessPtr	A pointer to the database.

sleep

Purpose	Shuts down all peripherals, the CPU, and the system clock.
Usage	sleep
Parameters	None.

storeinfo

Purpose	Displays information about a memory store.
Usage	storeinfo <cardNum>
Parameters	cardNum The card number for which you want information displayed. You almost always use 0 to specify the built-in RAM.

Example storeinfo 0

```
ROM Store:
version: 0001
flags: 0000
name: ROM Store
creation date: 00000000
backup date: 00000000
heap list offset: 00C08208
init code offset1: 00C0D652
init code offset2: 00C1471E
database dirID: 00D20F7E
```

```
RAM Store:
version: 0001
flags: 0001
name: RAM Store 0
creation date: 00000000
backup date: 00000000
heap list offset: 00018100
init code offset1: 00000000
init code offset2: 00000000
database dirID: 0001811F
```

Using the Console Window

switch

switch

Purpose Switches the application that is used to provide the user interface on the handheld device.

Usage `switch <cardNum> <name> [<cmd> <cmdStr>]`

Parameters	<code>cardNum</code>	The number of the card on which the user interface application is stored. You almost always use 0 to specify the built-in RAM.
	<code>name</code>	The name of the application.
	<code>cmd</code>	Optional. Use to specify a command for the application.
	<code>cmdStr</code>	Optional. Use to specify an arguments string for <code>cmd</code> .

sysalarmdu

mp Purpose Displays the system alarm table.

Usage `sysalarmdump`

Parameters None.

Example sysalarmdump

date	time	ref	alarm seconds	dbID	card #	quiet	triged	noted
7/29/1999	00:00	000000000	B3C54A00	00D1FCF8	4004	false	false	false
1/ 1/1904	00:00	000000000	000000000	000000000	0000	false	false	true

unlock

Purpose Unlocks a memory chunk.

Usage unlock (<hexChunkPtr> | localID>) [options]

Parameters hexChunkPtr or localID

A pointer to a chunk in memory, or the ID of a chunk on the specified card number.

options Optional. You can specify the following options:

-card <cardNum>

The card number if a local ID is specified instead of a chunk pointer.

Console Command Summary

Card Information Commands

[cardformat](#) Formats a memory card.

[cardinfo](#) Retrieves information about a memory card.

[storeinfo](#) Retrieves information about a memory store.

Chunk Utility Commands

<u>free</u>	Disposes of a heap chunk.
<u>info</u>	Displays information on a heap chunk.
<u>lock</u>	Locks a heap chunk.
<u>new</u>	Allocates a new chunk in a heap.
<u>resize</u>	Resizes an existing heap chunk.
<u>setowner</u>	Sets the owner of a heap chunk.
<u>unlock</u>	Unlocks a heap chunk.

Database Utility Commands

<u>close</u>	Closes a database.
<u>create</u>	Creates a new database.
<u>del</u>	Deletes a database.
<u>dir</u>	Lists the databases.
<u>export</u>	Exports a database to the desktop computer.
<u>import</u>	Imports a database from the desktop computer.
<u>open</u>	Opens a database.
<u>opened</u>	Lists all currently opened databases.
<u>setinfo</u>	Sets database information, such as its name, version number, and modification number.

Debugging Utility Commands

<u>dm</u>	Displays memory.
<u>gdb</u>	Enables or disables Gdb debugging.
<u>mdebug</u>	Sets the Memory Manager debug mode.
<u>sb</u>	Sets the value of a byte.

Gremlin Commands

<u>gremlin</u>	Activates the specified gremlin until a specified event occurs.
<u>gremlinoff</u>	Deactivates the current gremlin.

Heap Utility Commands

<u>hc</u>	Compacts a memory heap.
<u>hchk</u>	Checks a heap.
<u>hd</u>	Displays a dump of a memory heap.
<u>hf</u>	Allocates all free space in a memory heap, minus a specified number of bytes.
<u>hi</u>	Initializes a memory heap.
<u>hl</u>	Lists all of the memory heaps on the specified memory card.
<u>hs</u>	Scrambles a heap.
<u>ht</u>	Performs a heap total.
<u>htorture</u>	Torture-tests a heap.

Host Control Commands

<u>help</u>	Provides help on the console commands.
<u>log</u>	Starts or stops logging to a file.
<u>saveimages</u>	Saves an image of a memory card to file.

Miscellaneous Utility Commands

<u>simsync</u>	Simulates a synchronization operation on a database.
<u>sysalarmdump</u>	Displays the alarm table.

Record Utility Commands

<u>addrecord</u>	Adds a record to a database.
<u>attachrecord</u>	Attaches a record to a database.
<u>changerecord</u>	Replaces a record in a database.
<u>delrecord</u>	Deletes a record from a database.
<u>detachrecord</u>	Detaches a record from a database.
<u>findrecord</u>	Finds a record by its unique ID.
<u>listrecords</u>	Lists all of the records in a database.
<u>moverecord</u>	Changes the index of a record.
<u>setrecordinfo</u>	Sets record information, such as its ID and attributes.

Resource Utility Commands

<u>addresource</u>	Adds a resource to a database.
<u>attachresource</u>	Attaches a resource to a database.
<u>changeresource</u>	Replaces a resource in a database.
<u>delresource</u>	Deletes a resource from a database.
<u>detachresource</u>	Detaches a resource from a database.
<u>getresource</u>	Retrieves a resource from a database.
<u>listresources</u>	Lists all resources in a database.
<u>setresourceinfo</u>	Sets resource information, such as its ID and resource type.

System Commands

<u>battery</u>	Battery utility command for starting or stopping radio charging, and for setting the loaded status.
<u>coldboot</u>	Boots the handheld device.
<u>doze</u>	Puts the CPU to sleep while keeping the peripherals and clock running on the handheld device.
<u>exit</u>	Exits the console.
<u>feature</u>	Displays, retrieves, registers, or unregisters features.
<u>kinfo</u>	Displays kernel information.
<u>launch</u>	Launches an application.
<u>performance</u>	Sets performance levels, such as the system clock frequency and CPU duty cycle.
<u>poweron</u>	Powers on the handheld device.
<u>reset</u>	Resets the memory system and formats both cards.
<u>sleep</u>	Shuts down all peripherals, the CPU, and the system clock.
<u>switch</u>	Switches the current user interface application.

Using Palm Reporter

This chapter describes Palm Reporter, which you can use to do trace analysis of your Palm OS® applications. The following topics are covered in this chapter:

- “[About Palm Reporter](#)” - An introduction to Palm Reporter concepts
- “[Downloading Palm Reporter](#)” on page 162 - How to download and install the Palm Reporter package
- “[Adding Trace Calls to Your Application](#)” on page 163 - How to add Host Control trace calls to your application
- “[Displaying Trace Information in Palm Reporter](#)” on page 165 - How to open a Palm Reporter session to view the trace information
- “[Troubleshooting Palm Reporter](#)” on page 169 - How to make sure Palm Reporter is running correctly

About Palm Reporter

Palm Reporter is a trace utility that can be used with Palm OS Emulator. As an application runs on Palm OS Emulator, it can send information in real time to Reporter. This information can help pinpoint problems that might be hard to identify when executing code step-by-step or when specifying breakpoints. To view the realtime traces, simply run Reporter at the same time as you run your application on Palm OS Emulator.

Palm Reporter Features

Palm Reporter has a number of features that make it useful:

- High throughput of trace output, allowing for realtime traces
- Trace output filtering, searching, saving, printing, and copying

- Display of Trace output through a TCP/IP connection

Downloading Palm Reporter

The most recent released version of Palm Reporter is posted on the internet in the Palm™ developer zone:

<http://www.palmos.com/developers>

Follow the links from the developer zone main page to the Palm OS Emulator page to retrieve the released version of Palm Reporter.

Palm Reporter Package Files

The Palm Reporter package includes the following files:

Table 5.1 Files Included in the Palm Reporter Package

File	Description
Windows: Reporter.exe	Main Palm Reporter program file
Macintosh: Reporter	
Windows: PalmTrace.dll	Palm OS Emulator add-on that relays traces to Palm Reporter
Macintosh: PalmTraceLib	
TraceTest.prc	Sample application containing HostTrace API calls
Documentation (folder)	Palm Reporter documentation, including: <ul style="list-style-type: none">• Reporter guide.html• Reporter protocol.html

Installing Palm Reporter

Palm Reporter requires Palm OS Emulator. Place the PalmTrace library (PalmTrace.dll or PalmTraceLib) in the same folder as the Palm OS Emulator executable. Emulator will not be able to send trace information to Reporter if it cannot find and load the PalmTrace library.

The Palm Reporter executable can be located in any folder on your system; it does not need to be in the same folder as Palm OS Emulator.

Adding Trace Calls to Your Application

Traces are generated by system calls that are recognized by Palm OS Emulator but ignored by actual handheld devices. These system calls are listed in `hostcontrol.h`, which is part of both the Palm OS SDK and the Palm OS Emulator package. For more information about the Host Control API, see the book *Using Palm OS Emulator*.

The Host Control system calls pertinent to tracing are listed in the following table:

System Call Format	Function Description
<code>void HostTraceInit(void)</code>	Initiate a connection to Reporter
<code>void HostTraceOutputT(UINT16 mod, const char* fmt, ...)</code>	Output a string to Reporter (printf format)
<code>void HostTraceOutputTL(UINT16 mod, const char* fmt, ...)</code>	Output a string to Reporter (printf format) with an additional line break
<code>void HostTraceOutputB(UINT16 mod, const char* buff, UINT32 len)</code>	Send binary data to Reporter
<code>void HostTraceOutputVT(UINT16 mod, const char* fmt, va_list vars)</code>	Output a string to Reporter (vprintf format)
<code>void HostTraceOutputVTL(UINT16 mod, const char* fmt, va_list vars)</code>	Output a string to Reporter (vprintf format) with an additional line break
<code>void HostTraceClose(void)</code>	Close the connection to Reporter

All `HostTraceOutput` functions take an error class identifier as their first parameter. This parameter allows filtering of traces according to their origin. Recognized error classes are listed in

Using Palm Reporter

Adding Trace Calls to Your Application

`SystemMgr.h`. For example, applications should specify the error class `appErrorClass`.

Specifying Trace Strings

Trace strings use the following format:

`% <flags> <width> <type>`

`<flags>`

- Left-justify display (Default is right justify)
- + Always display the sign character (Default is to display the sign character for negative values only)
- space Display a space (when a value is positive) rather than displaying a “+” sign
- # Alternate form specifier

`<width>`

Must be a positive number

`<type>`

- % Display a “%” character
- s Display a null-terminated string
- c Display a character
- ld) Display an Int32 value
- lu Display a UInt32 value
- lX or lX Display an Int32 or UInt32 value in hexadecimal
- hd Display an Int16 value
- hu Display a UInt16 value
- hX or hX Display an Int16 or UInt16 value in hexadecimal

NOTE: The following types are not supported for <type>: o, e, E, f, F, g, G, p, l, n, d, i, u, X, or x.

Trace Functions in a Code Sample

```
void function(void)
{
    unsigned char theBuffer[256];
    unsigned long theUInt32 = 0xFEDC1234;
    unsigned short theUInt16 = 0xFE12;
    int i;

    HostTraceInit();

    HostTraceOutputTL(appErrorClass, "This is an Int32:");
    HostTraceOutputTL(appErrorClass, " unsigned (lu) [4275835444]=[%lu]",
        theUInt32);
    HostTraceOutputTL(appErrorClass, " signed (ld) [-19131852]=[%ld]", theUInt32);
    HostTraceOutputTL(appErrorClass, " hexa (lx) [fedc1234]=[%lx]", theUInt32);

    HostTraceOutputTL(appErrorClass, "This is an Int16:");
    HostTraceOutputTL(appErrorClass, " unsigned (hu) [65042]=[%hu]", theUInt16);
    HostTraceOutputTL(appErrorClass, " signed (hd) [-494]=[%hd]", theUInt16);
    HostTraceOutputTL(appErrorClass, " hexa (hX) [FE12]=[%hX]", theUInt16);

    HostTraceOutputTL(appErrorClass, "This is a string (s) [Hello world]=[%s]",
        "Hello world");
    HostTraceOutputTL(appErrorClass, "This is a char (c) [A]=[%c]", 'A');

    HostTraceOutputTL(appErrorClass, "This is a buffer:");

    for (i = 0 ; i < 256 ; i++) theBuffer[i] = (unsigned char) i;

    HostTraceOutputB(appErrorClass, theBuffer, 256);

    HostTraceClose();
}
```

Displaying Trace Information in Palm Reporter

To view trace information in Palm Reporter, you need to do the following:

Using Palm Reporter

Displaying Trace Information in Palm Reporter

- Add trace calls to your application and build your application
- Start a Palm Reporter session
- Start a Palm OS Emulator session
 - Set the Emulator “Tracing Options” to display output to “Palm Reporter”
 - Install your trace-enabled application in the Emulator session
 - Run your trace-enabled application in the Emulator session

Starting a Palm Reporter Session


To start a Palm Reporter session, run the `Reporter.exe` file. After starting Palm Reporter, you should see an empty window. This window will serve as a container for other windows which display the trace information. A new trace window is created for each `HostTraceInit` to `HostTraceClose` sequence in your trace-enabled application.

Each `HostTraceOutput` call will send information into the current trace window. The `HostTraceOutput` call will fail if there is no active trace window, which can happen if Reporter is not running when the `HostTraceInit` function is called.

Also, a reset in Emulator will close any pending connection. That is, Emulator will call the `HostTraceClose` function for your application if you used `HostTraceInit` to open a trace connection.

[Figure 5.1](#) shows a Palm Reporter session window.

Figure 5.1 Palm Reporter Session Window



Filtering Information in a Palm Reporter Session













You can control the type of trace information Palm Reporter displays. You control this information by setting *filters*. Filters can be set either globally, by using the **Global filters...** menu, or for the current window, by using the **Active view filters...** menu. By enabling or disabling the filters, you can choose to view traces sent by corresponding modules in your application. Global filter settings are saved when you exit the Palm Reporter session.



Using Palm Reporter

Displaying Trace Information in Palm Reporter

Using the Palm Reporter Toolbar

Palm Reporter provides a toolbar with the following functions:

Toolbar Icon	Function
	Save the contents of the Reporter window to a file
	Print the contents of the Reporter window
	Select all of the text in the Reporter window
	Copy the selected text into the system clipboard
	Clear the contents of the Reporter window
	Draw a horizontal line across the Reporter window
	Search the Reporter window for specified text
	Search the Reporter window for the next occurrence of specified text
	Search the Reporter window for the previous occurrence of specified text
	Set “on top” mode to keep the Reporter window always visible on the screen
	Set filters for the current window only
	Set font for the current window only

Toolbar Icon	Function
	Set filters for all new windows
	Set font for all new windows

Troubleshooting Palm Reporter

Table 5.2 How to Solve Possible Palm Reporter Problems

Symptom	Solution
You are unable to set the Emulator “Tracing Options” to display output to “Palm Reporter”.	Make sure that the PalmTrace library is in the same folder as the Palm OS Emulator executable.
The PalmTrace library (PalmTrace.dll or PalmTraceLib file) doesn’t appear in the folder where you decompressed the Reporter’s archive.	Check to see if your system is configured to “Hide system files.”

Using Palm Reporter

Troubleshooting Palm Reporter

Table 5.2 How to Solve Possible Palm Reporter Problems

Symptom	Solution
Nothing appears in the Palm Reporter session window.	Make sure that: <ul style="list-style-type: none">• The PalmTrace library (PalmTrace.dll or PalmTraceLib file) is in the same folder as the Palm OS Emulator executable.• Your application code is calling HostTraceInit.• You are using Palm OS Emulator version 3.0a4 or later.• You have set the Emulator “Tracing Options” to display output to “Palm Reporter”.• Your filters are set correctly, and traces are emitted with the right modules.
You have checked everything in this table, and Reporter still isn’t displaying trace information.	Send a note describing your problem to reporter@palm.com .

Table 5.3 Palm Reporter Error Message

Error Message	Problem	Possible Solution
An error occurred while trying to listen for traces.	Default reception port is already in use.	Check that no other instance of the Reporter is running.
An error occurred while initializing ObjectSet.	Framework initialization failed.	Send a note describing your problem to reporter@palm.com .
An error occurred while ObjectSet was initializing TCP/IP.	TCP/IP related failure.	Check that TCP/IP networking is correctly set up.

Table 5.3 Palm Reporter Error Message (*continued*)

Error Message	Problem	Possible Solution
Cannot load filters description.	The Reporter executable file was altered.	Send a note describing your problem to reporter@palm.com.
Unable to start a reader thread.	Reporter could not create receiver thread.	Free up system resources.
Unable to start a format thread.	Reporter could not create displayer thread.	Free up system resources.

Using the Overlay Tools

This chapter describes how the PRC-to-Overlay tools can be used to produce a localized version of an application. The following topics are covered in this chapter:

- [“Using Overlays to Localize Resources”](#) - An overview of using overlay databases to localize application resources.
- [“About the Overlay Tools”](#) on page 175 - An introduction to the PRC-to-Overlay and Patch Overlay tools.
- [“Using the PRC-to-Overlay Function”](#) on page 175 describes how to create overlay resource databases for localized data.
- [“Using the Patch Overlay Function”](#) on page 178 describes how to use multiple overlay resource databases with a single bases application database.
- [“PRC2OVL Options Summary”](#) on page 179 lists the command line options used with PRC2OVL.
- [“Using PRC2OVL on the Macintosh”](#) on page 181 contains special instructions for using PRC2OVL on a Macintosh system.

Using Overlays to Localize Resources

Palm OS® 3.5 added support for localizing applications through overlay databases. Each overlay database is a separate resource database that provides an appropriately localized set of resources for a single base database (a PRC file) and a single target locale (language and country).

Support for overlay databases is provided by Overlay Manager. To use Overlay Manager, create a base application that has your base resources (usually English) for your user interface and a separate overlay database that has the substitutions you want to make for

Using the Overlay Tools

Using Overlays to Localize Resources

each locale (French, German, Japanese, etc.). When an application runs on a localized version of Palm OS, Overlay Manager automatically substitutes localized resources from the appropriate overlay database at runtime. Alternatively, you can use Data Manager routine `DMOpenDBWithLocale()` to open a base database with an arbitrary overlay.

For more information about Overlay Manager and localizing your applications, see *Palm OS Programmer's Companion*.

Overlay Database Names

Each overlay database name contains a *locale suffix*. A locale consists of a language indicator and a country code:

- The first two letters indicate the language and must be lower case.
- The second two letters indicate the country and must be upper case.

For example, the database name `Address Book_enUS.PRC` indicates that this is an overlay for the language “English” and the country “United States.”

Overlay Specification Resources

Overlay specification resources establish a link between the base and the overlay databases. They bind resources together and are important when you have multiple version of the same database (for example, version 1 and version 2 of an application). Overlay specifications are required for overlay databases, but optional for the base database.

Overlay specification resources contain the following information:

- Type information (`'ovly'` for overlay databases)
- `ID = 1000`
- Target locale (language and country)
- Information about the base database (type, creator, checksum, etc.)
- Information about each overlaid resource. This content specifies exactly which resources are overlaid. Normally, this

content consists of replacements for resources in the base, but it can also specify additional resources that are not in the base.

About the Overlay Tools

The overlay tools allow you to produce an overlay database that can be superimposed on top of another so that any requests for the underlying base database first go through the overlay database. This allows localization to be performed by placing the localized (for example, German) data in an overlay for a particular locale (for example, Germany).

You can edit and distribute the overlay separately from the underlying database. Because the overlay only needs to contain localized data, it does not need to include your application code or other large resources.

Using the PRC-to-Overlay Function

The PRC-to-Overlay function takes a normal resource database (usually an application) as input and produces an overlay. You can also give the tool an overlay as input to create a new overlay for a different locale.

How the PRC-to-Overlay Function Works

The PRC-to-Overlay function takes a single file as input, passes the file through a set of filters to decide which particular resources (components of the database) are localizable and should be put in the overlay. Then, given a particular locale, the tool generates an overlay file.

Choosing a Locale

A locale consists of a language indicator and a country code:

- The first two letters indicate the language and must be lower case.

Using the Overlay Tools

Using the PRC-to-Overlay Function

- The second two letters indicate the country and must be upper case.

To list the available language and country codes, use the following command:

```
prc2ovl -showlocales
```

For example, the following command creates an English language overlay for the country United States (using the default filter set):

```
PRC2OVL NewApp.prc -locale enUS -o  
NewApp_enUS.prc
```

where:

NewApp.prc	Indicates the input file name "NewApp.prc"
-locale enUS	Indicates the language code is "en" for English and the country code is "US" for United States
-o NewApp_enUS.prc	Specifies the output file name "NewApp_enUS.prc"

Modifying the Filter Set

A filter set indicates which particular resources (components of the database) are localizable and which resources should be put in the overlay PRC.

To modify the filter set, use the -a, -n, -i, and -e switches:

- a indicates that all resources are to be localized.
- n indicates that no resources are to be localized.
- i includes a particular set of resources (in the list of localized resources).
- e excludes a particular set.

Each switch operates in the order in which it appears on the command line. The last switch that matches is the one that is operated on. For example, the filter set:

```
-n -i tFRM 1000
```

produces an overlay that only contains the single `'tFRM 1000'` resource (if it is present in the input), but the filter set:

```
-a -e tFRM 1000
```

localizes everything but the `'tFRM 1000'` resource.

Default Filters

Recreate the default filters with the following set of parameters:

```
-a -e CODE -e DATA -e code -e data  
-e boot -e extn -e pref
```

Restricting Resource Matches

You can restrict matches by ID number. For example, if you only want to localize resource type `'BAZZ'` with ID 567, specify the filter set:

```
-i BAZZ 567
```

You can also supply ranges in your filter set, as shown in the following example:

```
-i BAZZ 567-599
```

Note: To see which resources are selected in the output, use the `-v` (for verbose) switch.

PRC2OVL Example

This example shows the files that are included as part of an application that needs to be localized.

The `NewApp.prc` file contains the application named `NewApp` which is written in English. The PRC file contains the following resources:

- Resource 0: `'CODE' 0`, application code
- Resource 1: `'CODE' 1`, more application code
- Resource 2: `'tFRM' 1000`, application form
- Resource 3: `'tSTR' 1000`, UI strings

Using the Overlay Tools

Using the Patch Overlay Function

Using the following command:

```
PRC2OVL NewApp.prc -locale deDE -o
NewApp_deDE.prc
```

Creates a German overlay, `NewApp_deDE.prc`, which is a file containing the following resources:

- Resource 0: `'tFRM'` 1000, application form
- Resource 1: `'tSTR'` 1000, UI strings

Using the Patch Overlay Function

The Patch Overlay function takes two input files, a base PRC and an overlay PRC, and outputs a new overlay PRC that has been modified so it will work with the given base PRC. This is accomplished by copying the appropriate data over the overlay resource in the overlay file, synthesizing necessary data if the base PRC was stripped.

You specify the Patch Overlay function with the `-p` switch. For example,

```
PRC2OVL OrigGermanOvl.prc -c
-p EnglishBase.prc -o FixedGermanOvl.prc
```

where:

`OrigGermanOvl.prc`

Indicates the input overlay PRC filename.

`-c`

Indicates whether to generate a new checksum for the output overlay PRC.

If you omit the `"-c"` parameter, then `PRC2OVL` will copy appropriate data over the overlay resource in the overlay file, synthesizing necessary data if the base PRC was stripped, and will generate a new checksum for the output overlay PRC.

If you include the “-c” parameter, then PRC2OVL will simply generate a new checksum for the output overlay PRC, without copying data over the overlay resource in the overlay PRC.

-p EnglishBase.prc

Indicates this is a Patch Overlay function and EnglishBase.prc is the input base PRC filename.

-o FixedGermanOvl.prc

Indicates the output overlay PRC filename.

Example

This example shows how you could build two language versions as separate projects, and generate two language overlays that would work for a single base:

1. Build your English language project: EnglishApp.prc.
2. Create a second project, where you duplicate the code from the first project, but change the resources for your desired localization. For example: GermanApp.prc.
3. Use PRC-to-Overlay to generate an English overlay: EnglishOvl.prc.
4. Use PRC-to-Overlay to generate a German overlay: GermanOvl.prc.
5. Use the Patch Overlay function to incorporate the checksums and overlay resource descriptions from the English application into the GermanOvl.prc, calling it FixedGermanOvl.prc.

As a result, you would have an EnglishBase.prc that would work with two overlay PRCs: EnglishOvl.prc and FixedGermanOvl.prc.

PRC2OVL Options Summary

The following tables list the PRC2OVL command line options. These options can be specified in any order.

Using the Overlay Tools

PRC2OVL Options Summary

Table 6.1 PRC2OVL Options for the PRC-to-Overlay Function

Option	Description
-h	Display help information.
-o <i>filename</i>	Specify the name of output file.
-showlocales	List the available language and country codes.
-locale <i>llCC</i>	Specify a locale code, where <i>ll</i> indicates the language and <i>CC</i> indicates the country code.
-a	Specify a filter set that localizes all resources.
-n	Specify a filter set that localizes no resources.
-i <i>resourceID(s)</i>	Specify a filter set that includes a particular set of resources, where <i>resourceID(s)</i> can be a single resource ID number (for example, 567) or a range of resource ID numbers (for example, 567-599).
-e <i>resourceID(s)</i>	Specify a filter set that excludes a particular set of resources, where <i>resourceID(s)</i> can be a single resource ID number (for example, 567) or a range of resource ID numbers (for example, 567-599).
-v or -V	Print status information to the screen.

Table 6.2 PRC2OVL Options for the Patch Overlay Function

Option	Description
-h	Display help information.
-c	Generate a new checksum for the output overlay PRC, without copying data over the overlay resource in the overlay PRC.
-p <i>filename</i>	Specify the name of the input base PRC file.
-o <i>filename</i>	Specify the name of output overlay PRC file.

Getting Help

You can get help when you:

- Run PRC2OVL (or MPWPRC2OVL) without arguments.
- Enter invalid arguments.
- Use `-h` on the command line.

Help lists the default resource selection filters.

Using PRC2OVL on the Macintosh

This section describes how to use PRC2OVL on a Macintosh graphical user interface (GUI).

Opening a PRC file

You can use the Mac GUI to create an overlay for a PRC file; typically the PRC file contains an application or a preference panel. Open the PRC file, then pick a target locale (which is the same as the `-locale` switch). The application displays the entire list of resources in the file, using the same default selection criteria, if necessary, to provide a suggested set of resources to localize. You can edit these by clicking on the checkbox by each item in the list. Then you can build an output file by clicking on the Build button.

Selecting Resources

The Mac GUI tool lets you select the resources you want to localize from a list rather than specifying resources with filters on the command line. By default, the tool assumes that all resources are overlaid except those of types `'CODE'`, `'DATA'`, `'code'`, `'data'`, `'boot'`, `'extn'`, and `'pref'`. (You can select other resources via the filter options you use in the command-line tool.)

Resource Tools

There are two tools provided with the Metrowerks CodeWarrior environment that you can use to work with resources:

- Use the Rez tool to compile a textual description of the resources for your application into a resource file.
- Use the DeRez tool to decompile a resource file into a text file.

Both of these tools are standard Apple Computer tools for working with Macintosh OS application resources. Documentation for both the Rez and DeRez programs is found in the Apple book *Building and Managing Programs in MPW, 2nd Edition*. This book is available online at the following URL:

<http://developer.apple.com/tools/mpw-tools/books.html>

Simple Data Types

[Table B.1](#) describes the simple data types, which have been renamed in the newest release of the Palm OS® software.

Table B.1 Simple Data Types

Old data type name	New data type name	Description
Byte	UInt8	unsigned 8-bit value
UChar	UInt8	unsigned 8-bit value
SByte	Int8	signed 8-bit value
Int	Int16	signed 16-bit value
SWord	Int16	signed 16-bit value
Short	Int16	signed 16-bit value
UShort	UInt16	unsigned 16-bit value
UInt	UInt16	unsigned 16-bit value
Word	UInt16	unsigned 16-bit value
Long	Int32	signed 32-bit value
SDWord	Int32	signed 32-bit value
ULong	UInt32	unsigned 32-bit value
DWord	UInt32	unsigned 32-bit value
Handle	MemHandle	a handle to a memory chunk
VoidHand	MemHandle	a handle to a memory chunk
Ptr	MemPtr	a pointer to memory
VoidPtr	MemPtr	a pointer to memory

Index

Symbols

> command 54

A

- adding trace calls 163
- addrecord command 123
- addresource command 123
- alias command 55
- aliases 31
- aliases command 55
- application
 - localizing 173
- application locale 175
- arithmetic operators 19
- assigning values to registers 23
- assignment operator 20
- atb command 55
- atc command 56
- atd command 56
- atr command 56
- att command 56
- attachrecord command 124
- attachresource command 124

B

- basic debugging tasks 22
- battery command 124
- baud rate
 - changing in Palm Debugger 47
- baud rate, changing 47
- BigROM 5
- bitwise operators 20
- bootstrap command 57
- br command 57, 58
- brd command 58
- break command, debugger 5
- breakpoint constants 89
- BreakpointType structure 92

C

- cardformat command 125
- cardinfo command 58, 125

- cast operator 19
- changerecord command 126
- changeresource command 126
- cl command 59
- close command 126
- coldboot command 126
- command constants 89
- command packets
 - Continue 93
 - Find 94
 - Get Breakpoints 95
 - Get Routine Name 96
 - Get Trap Breaks 98
 - Get Trap Conditionals 99
 - Message 100
 - Read Memory 101
 - Read Registers 102
 - RPC 103
 - Set Breakpoints 103
 - Set Trap Breaks 104
 - Set Trap Conditionals 105
 - State 106
 - Toggle Debugger Breaks 108
 - Write Memory 109
 - Write Registers 110
- command request packets 86
- command response packets 86
- command syntax 12
- commands
 - debugger protocol 93
- connecting to handheld device 4
- console commands 118, 122
 - addrecord 123
 - addresource 123
 - attachrecord 124
 - attachresource 124
 - battery 124
 - cardformat 125
 - cardinfo 125
 - changerecord 126
 - changeresource 126
 - close 126
 - coldboot 126
 - create 127
 - del 128
 - delrecord 128

- delresource 129
- detachrecord 129
- detachresource 129
- dir 129
- dm 131
- doze 131
- exit 132
- export 132
- feature 133
- findrecord 134
- free 135
- gdb 135
- getresource 135
- gremlin 136
- gremlinoff 136
- hc 136
- hchk 136
- hd 137
- help 138
- hf 138
- hi 139
- hl 139
- hs 139
- ht 140
- htorture 140
- import 141
- info 142
- kinfo 143
- launch 144
- listrecords 144
- listresources 144
- lock 145
- log 145
- mdebug 145
- moverecord 147
- new 147
- open 148
- opened 148
- performance 148
- poweron 149
- reset 149
- resize 150
- saveimages 150
- sb 150
- setinfo 151
- setowner 151
- setownerinfo 152

- setresourceinfo 152
- simsync 152
- sleep 153
- storeinfo 153
- switch 154
- sysalarmdump 154
- unlock 155
- console stub 114
- console window 3
 - activating input 114
 - using 117
- constants
 - breakpoint 89
 - debugger protocol command 89
 - debugging 84
 - packet 88
 - state 89
- Continue 93
- converting PRC to overlay 173
- country code 175
- CPU registers window 3
- create command 127

D

- database commands 28
- db command 59
- DbgBreak 5
- debugger protocol
 - breakpoint constants 89
 - command constants 89
 - command request packets 86
 - command response packets 86
 - commands 93
 - Continue command 93
 - Find command 94
 - Get Breakpoints command 95
 - Get Routine Name command 96
 - Get Trap Breaks command 98
 - Get Trap Conditionals command 99
 - host and target 85
 - Message command 100
 - message packets 86
 - packet communications 86, 88
 - packet constants 88
 - packet structure 86
 - packet summary 111

packet types 86
Read Memory command 101
Read Registers command 102
RPC command 103
Set Breakpoints command 103
Set Trap Breaks command 104
Set Trap Conditional command 105
State command 106
state constants 89
Toggle Debugger Breaks command 108
Write Memory command 109
Write Registers command 110
debugger protocol API 85
debugger stub 4
debugging commands
 > 54
 alias 55
 aliases 31, 55
 atb 55
 atc 56
 atd 56
 atr 56
 att 56
 automatic loading of definitions 31
 binary numbers in 17
 bootstrap 57
 br 57, 58
 brd 58
 cardinfo 58
 character constants in 17
 cl 59
 db 59
 decimal numbers in 18
 dir 59
 dl 61
 dm 61
 dump 62
 dw 62
 dx 62
 expression operators 19
 fb 63
 fill 63
 fl 63
 flow control 25
 ft 64
 fw 64
 g 65
 gt 65
 hchk 65
 hd 66
 help 67
 hexadecimal numbers in 18
 hl 68
 ht 68
 il 69
 info 69
 keywords 70
 load 70
 opened 71
 penv 71
 reg 72
 reset 72
 run 72
 s 73
 save 73
 sb 73
 sc 73
 sc6 74
 sc7 75
 script files 31
 shortcut characters in 22
 sizeof 75
 sl 75
 ss 76
 storeinfo 76
 structure templates 29
 summary 80
 sw 77
 t 77
 templates 77
 typedef 78
 typeend 78
 using expressions in 17
 var 79
 variables 79
 wh 79
debugging conduits
 shortcut numbers 6, 115
debugging constants 84
debugging host 85
debugging memory corruption problems 42
debugging target 85
debugging variables 83

- debugging window 3
 - activating 4
 - using 15
- debugging window commands 53
- defining structure templates 30
- del command 128
- delrecord command 128
- delresource command 129
- dereference operator 19
- detachrecord command 129
- detachresource command 129
- dir command 59, 129
- disassembling memory 24
- displaying and disassembling memory 24
- displaying memory 24
- displaying registers and memory 23
- displaying trace information 166
- dl command 61
- dm command 61, 131
- downloading
 - reporter 162
- doze command 131
- dump command 62
- dw command 62
- dx command 62

E

- emulator
 - using reporter 166
- entering commands in Palm Debugger 9
- error messages
 - in Palm Debugger 36
- exit command 132
- export command 132
- expression language for Palm Debugger 53
- expressions in Palm Debugger 17

F

- fb command 63
- feature command 133
- fill command 63
- filter set
 - localization 176

- filtering trace information 167
- Find 94
- finding code in the debugger 38
- finding memory corruption problems 42
- finding specific code 38
- findrecord command 134
- fixing reporter problems 169
- fl command 63
- flow control commands 25
- free command 135
- ft command 64
- fw command 64

G

- g command 65
- gdb command 135
- GDbgWasEntered 5
- Get Breakpoints 95
- Get Routine Name 96
- Get Trap Breaks 98
- Get Trap Conditionals 99
- getresource command 135
- gremlin command 136
- gremlinoff command 136
- gt command 65

H

- handheld device
 - connecting with Palm Debugger 4
- hc command 136
- hchk command 65, 136
- hd command 66, 137
- heap and database commands 28
- heap commands 28
- help command 67, 138
- hf command 138
- hi command 139
- hl command 68, 139
- host control
 - adding trace calls 163
 - using reporter 163
- hs command 139
- ht command 68, 140

htorture command 140

I

il command 69
import command 141
importing a database 118
info command 69, 142

K

keywords command 70
kinfo command 143

L

language indication 175
launch command 144
listrecords command 144
listresources command 144
load command 70
loading debugger definitions 31
local variables
 displaying in Palm Debugger 44
localization 173
lock command 145
log command 145

M

mdebug command 145
memory corruption 42
menus in Palm Debugger 10
Message 100
message packets 86
moverecord command 147
MPWPRC2OVL 181

N

new command 147

O

open command 148
opened command 71, 148
operators in debugging commands 19
overlay tool

 about 175
 choosing a locale 175
 filter set 176
 help 181
 Macintosh use 181
 option summary 179
 patch overlay 178
 PRC2OVL 176, 178
 PRC-to-overlay 175
overlay tools 173

P

packet communications 88
packet constants 88
packet types 86
Palm Debugger 38, 47
 > command 54
 about 2
 addrecord command 123
 addresource command 123
 address values 14
 alias command 55
 aliases 31
 aliases command 55
 and memory corruption problems 42
 arithmetic operators 19
 assigning values to registers 23
 assignment operator 20
 atb command 55
 atc command 56
 atd command 56
 atr command 56
 att command 56
 attachrecord command 124
 attachresource command 124
 basic tasks 22
 battery command 124
 bitwise operators 20
 bootstrap command 57
 br command 57, 58
 brd command 58
 cardformat command 125
 cardinfo command 58, 125
 cast operator 19
 changerecord command 126
 changeresource command 126

cl command 59
close command 126
coldboot command 126
command options 14, 52, 121
command syntax 12, 120
connecting to handheld device 4
console commands 122
console window 3, 117
CPU registers window 3
create command 127
db command 59
debugger environment variables 83
debugging command summary 80
debugging window 3
debugging window commands 53
del command 128
delrecord command 128
delresource command 129
dereference operator 19
detachrecord command 129
detachresource command 129
dir command 59, 129
displaying local variables 44
displaying registers and memory 23
dl command 61
dm command 61, 131
doze command 131
dump command 62
dw command 62
dx command 62
entering commands 9
error messages 36
exit command 132
export command 132
expression language 17, 53
fb command 63
feature command 133
fill command 63
findrecord command 134
fl command 63
flow control commands 25
free command 135
ft command 64
fw command 64
g command 65
gdb command 135
getresource command 135
gremlin command 136
gremlinoff command 136
gt command 65
hc command 136
hchk command 65, 136
hd command 66, 137
heap and database commands 28
help command 67, 138
hf command 138
hi command 139
hl command 68, 139
hs command 139
ht command 68, 140
htorture command 140
il command 69
import command 141
importing system extensions and libraries 48
info command 69, 142
keywords command 70
kinfo command 143
launch command 144
listrecords command 144
listresources command 144
load command 70
lock command 145
log command 145
mdebug command 145
menus 10
moverecord command 147
new command 147
numeric and address values 53, 121
numeric values 14
open command 148
opened command 71, 148
penv command 71
performance command 148
performing calculations 38
poweron command 149
predefined constants 84
reg command 72
register variables 20
repeating commands 38
reset command 72, 149
resize command 150
run command 72
s command 73
save command 73

- saveimages command 150
- sb command 73, 150
- sc command 73
- sc6 command 74
- sc7 command 75
- script files 31
- setinfo command 151
- setowner command 151
- setrecordinfo command 152
- setresourceinfo command 152
- shortcut characters 22
- shortcut characters in 38
- simsync command 152
- sizeof command 75
- sl command 75
- sleep command 153
- source debugging limitations 36
- source menu 34
- source window 3, 32
- ss command 76
- storeinfo command 76, 153
- structure templates 29
- sw command 77
- switch command 154
- symbol files 33
- sysalarmdump command 154
- t command 77
- templates command 77
- tips and examples 37
- typedef command 78
- typeend command 78
- unary operators 19
- unlock command 155
- using 1
- using console and debugging windows 8
- using the debugging window 15
- var command 79
- variables command 79
- wh command 79
- windows 3
- Palm reporter 161
- patch overlay 178
- penv command 71
- performance command 148
- performing calculations in Palm Debugger 38
- poweron command 149

- PRC2OVL 176, 178
 - help 181
 - option summary 179
- PRC-to-OVL tool 173

R

- Read Memory 101
- Read Registers 102
- reg command 72
- register variables 20
- reporter 161
 - about 161
 - adding trace calls 163
 - downloading 162
 - features 161
 - filtering information 167
 - functions 168
 - installation errors 169
 - installing 162
 - package file contents 162
 - sample code 165
 - session window 167
 - toolbar 168
 - trace session 166
 - trace strings 164
 - troubleshooting 169
 - using emulator 166
- reset command 72, 149
- resize command 150
- resource tools 183
- RPC 103
- run command 72

S

- s command 73
- save command 73
- saveimages command 150
- sb command 73, 150
- sc command 73
- sc6 command 74
- sc7 command 75
- script files 31
- Set Breakpoints 103
- Set Trap Breaks 104

- Set Trap Conditionals 105
- setinfo command 151
- setowner command 151
- setownerinfo command 152
- setresourceinfo command 152
- shortcut characters in Palm Debugger 38
- shortcut number 6, 115
- shortcut numbers 6, 115
- simple data types 185
- simsync command 152
- sizeof command 75
- sl command 75
- sleep command 153
- SmallROM 5
- soft reset 8, 117
- source window 3, 32
 - and symbol files 33
 - context menu 35
 - debugging limitations 36
 - debugging with 33
 - menu 34
- specifying Palm Debugger numeric and address value 53, 121
- specifying Palm Debugger options 52, 121
- ss command 76
- State 106
- state constants 89
- storeinfo command 76, 153
- structure templates 29
- sw command 77
- switch command 154
- symbol files
 - using 33
- sysalarmdump command 154
- SysPktBodyCommon structure 91
- SysPktBodyType structure 91

- SysPktRPCParamType structure 92
- system extensions
 - importing 48
- system libraries
 - importing 48

T

- t command 77
- templates 29
- templates command 77
- Toggle Debugger Breaks 108
- trace analysis 161
- trace strings 164
- tracing
 - sample code 165
- tracing applications 161
- typedef command 78
- typeend command 78

U

- unary operators 19
- unlock command 155
- using reporter 161

V

- var command 79
- variables 83
- variables command 79

W

- wh command 79
- windows
 - in Palm Debugger 3
- Write Memory 109
- Write Registers 110