



Red Hat Satellite 6.6

Provisioning Guide

A guide to provisioning physical and virtual hosts on Red Hat Satellite Servers.

Red Hat Satellite 6.6 Provisioning Guide

A guide to provisioning physical and virtual hosts on Red Hat Satellite Servers.

Red Hat Satellite Documentation Team

satellite-doc-list@redhat.com

Legal Notice

Copyright © 2020 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux[®] is the registered trademark of Linus Torvalds in the United States and other countries.

Java[®] is a registered trademark of Oracle and/or its affiliates.

XFS[®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL[®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js[®] is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack[®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

The Red Hat Satellite Provisioning Guide has instructions on provisioning physical and virtual hosts. This includes setting up the required network topology, configuring the necessary services, and providing all of the other configuration information to provision hosts on your network.

Table of Contents

CHAPTER 1. INTRODUCTION	5
1.1. PROVISIONING TYPES OVERVIEW	5
1.2. PROVISIONING WORKFLOW OVERVIEW	5
CHAPTER 2. CONFIGURING PROVISIONING CONTEXTS	7
2.1. PROVISIONING CONTEXT OVERVIEW	7
2.2. SETTING THE PROVISIONING CONTEXT	7
CHAPTER 3. CONFIGURING PROVISIONING RESOURCES	8
3.1. CREATING OPERATING SYSTEMS	8
3.2. UPDATING MULTIPLE OPERATING SYSTEMS	9
3.3. CREATING ARCHITECTURES	10
3.4. CREATING HARDWARE MODELS	10
3.5. USING A SYNCED KICKSTART REPOSITORY FOR A HOST'S OPERATING SYSTEM	11
3.6. CREATING PARTITION TABLES	11
3.7. CREATING PROVISIONING TEMPLATES	12
3.7.1. Types of Provisioning Templates	12
3.7.2. Template Syntax and Management	13
3.7.3. Procedure	14
3.8. CREATING COMPUTE PROFILES	15
3.9. SETTING A DEFAULT ENCRYPTED ROOT PASSWORD FOR HOSTS	15
3.10. USING THIRD PARTY INSTALLATION MEDIA	16
3.11. USING NOVNC TO ACCESS VIRTUAL MACHINES	17
CHAPTER 4. CONFIGURING NETWORKING	19
4.1. SATELLITE AND DHCP OPTIONS	19
4.2. PREREQUISITES FOR IMAGE BASED PROVISIONING	21
4.3. CONFIGURING NETWORK SERVICES	22
4.3.1. DHCP, DNS, and TFTP Options for Network Configuration	22
4.3.2. Using TFTP Services through NAT	24
4.4. ADDING A DOMAIN TO SATELLITE SERVER	24
4.5. ADDING A SUBNET TO SATELLITE SERVER	25
4.6. CONFIGURING IPXE TO REDUCE PROVISIONING TIMES	26
4.6.1. Chainbooting virtual machines	27
4.6.2. Chainbooting iPXE directly	29
CHAPTER 5. USING INFOBLOX AS DHCP AND DNS PROVIDERS	32
5.1. LIMITATIONS	32
5.2. PREREQUISITES	32
5.3. INSTALLING THE INFOBLOX CA CERTIFICATE ON CAPSULE SERVER	32
5.4. INSTALLING THE DHCP INFOBLOX MODULE	33
5.5. INSTALLING THE DNS INFOBLOX MODULE	34
CHAPTER 6. PROVISIONING BARE METAL HOSTS	35
6.1. PREREQUISITES FOR BARE METAL PROVISIONING	35
6.2. CONFIGURING THE SECURITY TOKEN VALIDITY DURATION	36
6.3. CREATING HOSTS WITH UNATTENDED PROVISIONING	36
6.4. CONFIGURING RED HAT SATELLITE'S DISCOVERY SERVICE	37
6.4.1. Enabling Discovery service on a Capsule Server	38
6.4.2. Provisioning Template PXELinux Discovery Snippet	39
6.4.3. Changing Templates and Snippets	39
6.4.4. Automatic Contexts for Discovered Hosts	40

6.5. CREATING HOSTS FROM DISCOVERED HOSTS	41
6.6. CREATING DISCOVERY RULES	42
6.7. CREATING HOSTS WITH PXE-LESS PROVISIONING	44
6.8. IMPLEMENTING PXE-LESS DISCOVERY	46
6.9. DEPLOYING SSH KEYS DURING PROVISIONING	48
6.10. BUILDING A SATELLITE DISCOVERY IMAGE	49
CHAPTER 7. PROVISIONING VIRTUAL MACHINES ON A KVM SERVER (LIBVIRT)	52
7.1. PREREQUISITES FOR KVM PROVISIONING	52
7.2. CONFIGURING SATELLITE SERVER FOR KVM CONNECTIONS	53
7.3. ADDING A KVM CONNECTION TO SATELLITE SERVER	53
7.4. ADDING KVM IMAGES TO SATELLITE SERVER	54
7.5. ADDING KVM DETAILS TO A COMPUTE PROFILE	55
7.6. CREATING HOSTS ON A KVM SERVER	56
CHAPTER 8. PROVISIONING VIRTUAL MACHINES IN RED HAT VIRTUALIZATION	59
8.1. PREREQUISITES FOR RED HAT VIRTUALIZATION PROVISIONING	59
8.2. CREATING A RED HAT VIRTUALIZATION USER	59
8.3. ADDING A RED HAT VIRTUALIZATION CONNECTION TO SATELLITE SERVER	60
8.4. ADDING RED HAT VIRTUALIZATION IMAGES TO SATELLITE SERVER	62
8.5. ADDING RED HAT VIRTUALIZATION DETAILS TO A COMPUTE PROFILE	62
8.6. CREATING NETWORK-BASED HOSTS ON A RED HAT VIRTUALIZATION SERVER	63
CHAPTER 9. PROVISIONING VIRTUAL MACHINES IN VMWARE VSPHERE	66
9.1. PREREQUISITES FOR VMWARE VSPHERE PROVISIONING	66
9.2. CREATING A VMWARE VSPHERE USER	66
9.3. ADDING A VMWARE VSPHERE CONNECTION TO SATELLITE SERVER	67
9.4. ADDING VMWARE VSPHERE IMAGES TO SATELLITE SERVER	68
9.5. ADDING VMWARE VSPHERE DETAILS TO A COMPUTE PROFILE	69
9.6. CREATING HOSTS ON A VMWARE VSPHERE SERVER	70
9.7. USING THE VMWARE VSPHERE CLOUD-INIT AND USERDATA TEMPLATES FOR PROVISIONING	72
9.8. CACHING OF VMWARE COMPUTE RESOURCES	74
9.8.1. Enabling Caching of VMware Compute Resources	75
9.8.2. Refreshing the VMware Compute Resources Cache	75
CHAPTER 10. PROVISIONING VIRTUAL MACHINES WITH CONTAINER-NATIVE VIRTUALIZATION	76
10.1. PREREQUISITES FOR CONTAINER-NATIVE VIRTUALIZATION PROVISIONING	76
10.2. ADDING A CONTAINER-NATIVE VIRTUALIZATION CONNECTION TO SATELLITE SERVER	77
CHAPTER 11. PROVISIONING CLOUD INSTANCES IN RED HAT OPENSTACK PLATFORM	79
11.1. PREREQUISITES FOR RED HAT OPENSTACK PLATFORM PROVISIONING:	79
11.2. ADDING A RED HAT OPENSTACK PLATFORM CONNECTION TO THE SATELLITE SERVER	79
11.3. ADDING RED HAT OPENSTACK PLATFORM IMAGES TO THE SATELLITE SERVER	80
11.4. ADDING RED HAT OPENSTACK PLATFORM DETAILS TO A COMPUTE PROFILE	81
11.5. CREATING IMAGE-BASED HOSTS ON RED HAT OPENSTACK PLATFORM	81
CHAPTER 12. PROVISIONING CLOUD INSTANCES IN AMAZON EC2	83
12.1. PREREQUISITES FOR AMAZON EC2 PROVISIONING	83
12.2. ADDING AN AMAZON EC2 CONNECTION TO THE SATELLITE SERVER	83
12.3. USING AN HTTP PROXY WITH COMPUTE RESOURCES	84
12.4. ADDING AMAZON EC2 IMAGES TO SATELLITE SERVER	85
12.5. ADDING AMAZON EC2 DETAILS TO A COMPUTE PROFILE	85
12.6. CREATING IMAGE-BASED HOSTS ON AMAZON EC2	86
12.7. CONNECTING TO AN AMAZON EC2 INSTANCE USING SSH	87
12.8. CONFIGURING A FINISH TEMPLATE FOR AN AMAZON WEB SERVICE EC2 ENVIRONMENT	88

12.9. MORE INFORMATION ABOUT AMAZON WEB SERVICES AND SATELLITE	89
CHAPTER 13. PROVISIONING CLOUD INSTANCES IN GOOGLE COMPUTE ENGINE	90
13.1. PREREQUISITES FOR GCE PROVISIONING	90
13.2. ADDING A GCE CONNECTION TO SATELLITE SERVER	90
13.3. ADDING GCE IMAGES TO SATELLITE SERVER	91
13.4. ADDING GCE DETAILS TO A COMPUTE PROFILE	91
13.5. CREATING IMAGE-BASED HOSTS ON GCE	92
CHAPTER 14. PROVISIONING USING A RED HAT IMAGE BUILDER IMAGE	94
14.1. CREATING AN IMAGE USING RED HAT IMAGE BUILDER	94
14.2. USING A RED HAT IMAGE BUILDER IMAGE IN SATELLITE	94
APPENDIX A. INITIALIZATION SCRIPT FOR PROVISIONING EXAMPLES	96
APPENDIX B. ADDITIONAL HOST PARAMETERS FOR HAMMER CLI	98
B.1. COMMON INTERFACE PARAMETERS	98
B.2. EC2 PARAMETERS	99
B.3. LIBVIRT PARAMETERS	100
B.4. RED HAT OPENSTACK PLATFORM PARAMETERS	101
B.5. RED HAT VIRTUALIZATION PARAMETERS	101
B.6. VMWARE INTERFACE PARAMETERS	102
APPENDIX C. PROVISIONING FIPS-COMPLIANT HOSTS	104
C.1. CHANGE THE PROVISIONING PASSWORD HASHING ALGORITHM	104
C.2. SETTING THE FIPS ENABLED PARAMETER	104
C.3. VERIFYING FIPS MODE IS ENABLED	105
APPENDIX D. BUILDING CLOUD IMAGES FOR RED HAT SATELLITE	106
D.1. CREATING CUSTOM RED HAT ENTERPRISE LINUX IMAGES	106
D.2. CREATING A RED HAT ENTERPRISE LINUX 7 IMAGE	107
D.3. CREATING A RED HAT ENTERPRISE LINUX 6 IMAGE	108
D.4. CONFIGURING A HOST FOR REGISTRATION	109
D.5. REGISTERING A HOST	110
D.6. INSTALLING THE KATELLO AGENT	111
D.7. INSTALLING THE PUPPET AGENT	111
D.8. COMPLETING THE RED HAT ENTERPRISE LINUX 7 IMAGE	112
D.9. COMPLETING THE RED HAT ENTERPRISE LINUX 6 IMAGE	113
D.10. NEXT STEPS	114

CHAPTER 1. INTRODUCTION

Provisioning is a process that starts with a bare physical or virtual machine and ends with a fully configured, ready-to-use operating system. Using Red Hat Satellite, you can define and automate fine-grained provisioning for a large number of hosts.

There are many provisioning methods. For example, you can use Satellite Server's integrated Capsule or an external Capsule Server to provision bare metal hosts using both PXE based and non-PXE based methods. You can also provision cloud instances from specific providers through their APIs. These provisioning methods are part of the Red Hat Satellite 6 application life cycle to create, manage, and update hosts.

1.1. PROVISIONING TYPES OVERVIEW

Red Hat Satellite 6 has different methods for provisioning hosts:

Bare Metal Provisioning

Satellite provisions bare metal hosts primarily through PXE boot and MAC address identification. You can create host entries and specify the MAC address of the physical host to provision. You can also boot blank hosts to use Satellite's discovery service, which creates a pool of ready-to-provision hosts. You can also boot and provision hosts through PXE-less methods.

Cloud Providers

Satellite connects to private and public cloud providers to provision instances of hosts from images that are stored with the Cloud environment. This also includes selecting which hardware profile or flavor to use.

Virtualization Infrastructure

Satellite connects to virtualization infrastructure services such as Red Hat Virtualization and VMware to provision virtual machines from virtual image templates or using the same PXE-based boot methods as bare metal providers.

1.2. PROVISIONING WORKFLOW OVERVIEW

The provisioning process follows a basic workflow:

1. You create a host. Satellite requests an unused IP address from the DHCP Capsule Server that is associated with the subnet. Satellite loads this IP address into the **IP address** field in the Create Host window. When you complete all the options for the new host, submit the new host request.
2. The DHCP Capsule Server that is associated with the subnet reserves an entry for the host.
3. Satellite configures the DNS records:
 - A forward DNS record is created on the Capsule Server that is associated with the domain.
 - A reverse DNS record is created on the DNS Capsule Server that is associated with the subnet.
4. A PXELinux menu is created for the host in the TFTP Capsule Server that is associated with the subnet.
5. The new host requests a DHCP lease from the DHCP server.

6. The DHCP server responds to the lease request and returns TFTP **next-server** and **filename** options.
7. The host requests the bootloader and menu from the TFTP server.
8. The PXELinux menu and OS installer for the host is returned over TFTP.
9. The installer requests the provisioning template or script from Satellite.
10. Satellite renders the template and returns the resulting kickstart file to the host.
11. The host enters a build process that installs the operating system, registers the host to Satellite, and installs management tools such as **katello-agent** and **puppet**.
12. The installer notifies Satellite of a successful build in the **postinstall** script.
13. The PXELinux menu reverts to a local boot template.
14. The host starts its operating system. If you configured the host to use any Puppet classes, the host configures itself using the modules stored on Satellite.

This workflow differs depending on custom options. For example:

Discovery

If you use the Discovery service, Satellite automatically detects the MAC address of the new host and restarts the host after you submit a request. Note that TCP port 8443 must be reachable by the Capsule to which the host is attached for Satellite to restart the host.

PXE-less Provisioning

After you submit a new host request, you must boot the specific host with a boot disk that you download from Satellite.

Compute Resources

The compute resource creates the virtual machine for the host and returns the MAC address to Satellite. If you use image-based provisioning, the host does not follow the standard PXE boot and operating system installation: the compute resource creates a copy of the image for the new host to use.

CHAPTER 2. CONFIGURING PROVISIONING CONTEXTS

Before you provision hosts using Satellite, you must understand the placement strategy for hosts in Satellite. This is known as the provisioning context.

2.1. PROVISIONING CONTEXT OVERVIEW

A provisioning context is the combination of an organization and location that you specify for Satellite components. The organization and location that a component belongs to sets the ownership and access for that component.

Organizations divide Red Hat Satellite 6 components into logical groups based on ownership, purpose, content, security level, and other divisions. You can create and manage multiple organizations through Red Hat Satellite 6 and assign components to each individual organization. This ensures the Satellite Server provisions hosts within a certain organization and only uses components that are assigned to that organization. For more information about organizations, see [Managing Organizations](#) in the *Content Management Guide*.

Locations function similar to organizations. The difference is that locations are based on physical or geographical setting. Users can nest locations in a hierarchy.

For more information about locations, see [Managing Locations](#) in the *Content Management Guide*.

2.2. SETTING THE PROVISIONING CONTEXT

When you set a context, you define which organization and location to use for provisioning hosts.

The organization and location menus are located in the menu bar, on the upper left of the Satellite web UI. If you have not selected an organization and location to use, the menu displays: **Any Organization** and **Any Location**.

Procedure

- To set the provisioning context, click the **Any Organization** and **Any Location** buttons and select the organization and location to use.

Each user can set their default provisioning context in their account settings. Click the user name in the upper right of the Satellite web UI and select **My account** to edit your user account settings.

For CLI Users

While using the CLI, include either **--organization** or **--organization-label** and **--location** or **--location-id** as an option. For example:

```
# hammer host list --organization "Default_Organization" --location "Default_Location"
```

This command outputs hosts allocated for the Default_Organization and Default_Location.

CHAPTER 3. CONFIGURING PROVISIONING RESOURCES

Satellite contains provisioning resources that you must set up and configure to create a host. Satellite includes the following provisioning resources:

Provisioning template

While you can create static provisioning templates, for example, Kickstart templates, Satellite has many provisioning templates in ERB (Embedded Ruby) syntax that you can use to modularize parameters in each host or host group. For example, the timezone setting in a kickstart template can differ depending on the given host parameter. Depending on a provisioning workflow, you can set various combinations.

Partition table

A Partition table is a type of template used only for rendering the disk volume definition part of kickstart. A Partition table uses the same ERB syntax as provisioning templates. You can use a Partition table to define multiple disk layouts and select them for each host or host group depending on the system purpose.

Installation media

Installation media is a parametrized URL that you can add to Satellite that points to a remote repository with operating system packages, for example, **yum** or **apt**. You can use this parameter to install third-party content. Red Hat content is delivered through the repository synchronizing feature instead.

Subscriptions and Repositories

To consume Red Hat content, you must upload subscriptions to Satellite. You must create a Product for the subscription. You must enable and synchronize one or more installation repositories in the initial lifecycle environment **Library**. Optionally, you can filter and promote content to other Lifecycle Environments or Content Views.

3.1. CREATING OPERATING SYSTEMS

An operating system is a collection of resources that define how Satellite Server installs a base operating system on a host. Operating system entries combine previously defined resources, such as installation media, partition tables, provisioning templates, and others.

Importing operating systems from Red Hat's CDN creates new entries on the **Hosts > Operating Systems** page.

You can also add custom operating systems using the following procedure:

Procedure

1. In the Satellite web UI, navigate to **Hosts > Operating systems** and click **New Operating system**.
2. In the **Name** field, enter a name to represent the operating system entry.
3. In the **Major** field, enter the number that corresponds to the major version of the operating system.
4. In the **Minor** field, enter the number that corresponds to the minor version of the operating system.
5. In the **Description** field, enter a description of the operating system.

6. From the **Family** list, select the operating system's family.
7. From the **Root Password Hash** list, select the encoding method for the root password.
8. From the **Architectures** list, select the architectures that the operating system uses.
9. Click the **Partition table** tab and select the possible partition tables that apply to this operating system.
10. Optional: if you use non-Red Hat content, click the **Installation media** tab and select the installation media that apply to this operating system. For more information, see [Section 3.10, "Using Third Party Installation Media"](#).
11. Click the **Templates** tab and select a **PXELinux template**, a **Provisioning template**, and a **Finish template** for your operating system to use. You can select other templates, for example an **iPXE template**, if you plan to use iPXE for provisioning.
12. Click **Submit** to save your provisioning template.

For CLI Users

Create the operating system using the **hammer os create** command:

```
# hammer os create --name "MyOS" \
--description "My_custom_operating_system" \
--major 7 --minor 3 --family "Redhat" --architectures "x86_64" \
--partition-tables "My_Partition" --media "Red_Hat" \
--provisioning-templates "My_Provisioning_Template"
```

3.2. UPDATING MULTIPLE OPERATING SYSTEMS

Use the following procedure to assign each operating system a partition table, configuration template, and provisioning template.

Procedure

To assign each operating system a partition table **Kickstart default**, configuration template **Kickstart default PXELinux**, and provisioning template **Satellite Kickstart Default**, complete the following steps:

1. Run the following Bash script:

```
PARTID=$(hammer --csv partition-table list | grep "Kickstart default," | cut -d, -f1)
PXEID=$(hammer --csv template list --per-page=1000 | grep "Kickstart default PXELinux" |
cut -d, -f1)
SATID=$(hammer --csv template list --per-page=1000 | grep "provision" | grep ",Kickstart
default" | cut -d, -f1)

for i in $(hammer --no-headers --csv os list | awk -F, {'print $1'})
do
    hammer partition-table add-operatingsystem --id="{PARTID}" --operatingsystem-id="{i}"
    hammer template add-operatingsystem --id="{PXEID}" --operatingsystem-id="{i}"
    hammer os set-default-template --id="{i}" --config-template-id={PXEID}
    hammer os add-config-template --id="{i}" --config-template-id={SATID}
    hammer os set-default-template --id="{i}" --config-template-id={SATID}
done
```

2. Display information about the updated operating system to verify that the operating system is updated correctly:

```
# hammer os info --id 1
```

3.3. CREATING ARCHITECTURES

An architecture in Satellite represents a logical grouping of hosts and operating systems. Architectures are created by Satellite automatically when hosts check in with Puppet. Basic i386 and x86_64 architectures are already preset in Satellite 6.

Use this procedure to create an architecture in Satellite.

Supported Architectures

Intel x86_64 architecture is supported only for provisioning using PXE, Discovery, and boot disk. For more information, see Red Hat Knowledgebase solution [Architectures Supported for Satellite 6 Provisioning](#).

Procedure

To create an architecture, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > Architectures**, and in the Architectures window, click **Create Architecture**.
2. In the **Name** field, enter a name for the architecture.
3. From the **Operating Systems** list, select an operating system. If none are available, you can create and assign them under **Hosts > Operating Systems**.
4. Click **Submit**.

For CLI Users

Enter the **hammer architecture create** command to create an architecture. Specify its name and operating systems that include this architecture:

```
# hammer architecture create --name "Architecture_Name" \
--operatingsystems "os"
```

3.4. CREATING HARDWARE MODELS

Use this procedure to create a hardware model in Satellite so that you can specify what hardware model a host uses.

Procedure

To create a hardware model, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > Hardware Models**, and in the Hardware Models window, click **Create Model**.
2. In the **Name** field, enter a name for the hardware model.

3. Optionally, in the **Hardware Model** and **Vendor Class** fields, you can enter corresponding information for your system.
4. In the **Info** field, enter a description of the hardware model.
5. Click **Submit** to save your hardware model.

For CLI Users

Create a hardware model using the **hammer model create** command. The only required parameter is **--name**. Optionally, enter the hardware model with the **--hardware-model** option, a vendor class with the **--vendor-class** option, and a description with the **--info** option:

```
# hammer model create --name "model_name" --info "description" \
--hardware-model "hardware_model" --vendor-class "vendor_class"
```

3.5. USING A SYNCED KICKSTART REPOSITORY FOR A HOST'S OPERATING SYSTEM

Satellite contains a set of synchronized kickstart repositories that you use to install the provisioned host's operating system. For more information about adding repositories, see [Enabling Red Hat Repositories](#) in the *Content Management Guide*.

To set up a kickstart repository, complete the following steps:

1. Add the synchronized kickstart repository that you want to use to the existing Content View or create a new Content View and add the kickstart repository.

For Red Hat Enterprise Linux 8, ensure that you add both **Red Hat Enterprise Linux 8 for x86_64 - AppStream Kickstart x86_64 8** and **Red Hat Enterprise Linux 8 for x86_64 - BaseOS Kickstart x86_64 8** repositories.

If you use a disconnected environment, you must import the Kickstart repositories from a Red Hat Enterprise Linux binary DVD. For more information, see [Importing Kickstart Repositories](#) in the *Content Management Guide*.

2. Publish a new version of the Content View where the kickstart repository is added and promote it to a required lifecycle environment. For more information, see [Managing Content Views](#) in the *Content Management Guide*.
3. When you create a host, in the **Operating System** tab, for **Media Selection**, select the **Synced Content** check box.

To View the Kickstart Tree

To view the kickstart tree enter the following command:

```
# hammer medium list --organization "your_organization"
```

3.6. CREATING PARTITION TABLES

A partition table is a set of directives that defines the way Satellite Server configures the disks available on a new host. Red Hat Satellite 6 contains a set of default partition tables to use, including a **Kickstart default**. You can also edit partition table entries to configure the preferred partitioning scheme, or create a partition table entry and add it to the Red Hat Enterprise Linux operating system entry.

Procedure

To create partition tables, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > Partition Tables** and, in the Partition Tables window, click **Create Partition Table**.
2. In the **Name** field, enter a name to represent the partition table.
3. Select the **Default** check box if you want to set the template to automatically associate with new organizations or locations.
4. Select the **Snippet** check box if you want to identify the template as a reusable snippet for other partition tables.
5. From the **Operating System Family** list, select the distribution or family of the partitioning layout. For example, Red Hat Enterprise Linux, CentOS, and Fedora are in the Red Hat family.
6. In the **Template editor** field, enter the layout for the disk partition. For example:

```
zerombr
clearpart --all --initlabel
autopart
```

You can also use the **Template** file browser to upload a template file.

The format of the layout must match that for the intended operating system. For example, Red Hat Enterprise Linux 7.2 requires a layout that matches a kickstart file.

7. In the **Audit Comment** field, add a summary of changes to the partition layout.
8. Click the **Organizations** and **Locations** tabs to add any other provisioning contexts that you want to associate with the partition table. Satellite adds the partition table to the current provisioning context.
9. Click **Submit** to save your partition table.

For CLI Users

Before you create a partition table with the CLI, create a plain text file that contains the partition layout. This example uses the `~/my-partition` file. Create the installation medium using the **hammer partition-table create** command:

```
# hammer partition-table create --name "My Partition" --snippet false \
--os-family Redhat --file ~/my-partition --organizations "My_Organization" \
--locations "My_Location"
```

3.7. CREATING PROVISIONING TEMPLATES

A provisioning template defines the way Satellite Server installs an operating system on a host.

3.7.1. Types of Provisioning Templates

There are various types of provisioning templates, including:

Provision

The main template for the provisioning process. For example, a kickstart template. For more information about kickstart template syntax, see the [Kickstart Syntax Reference](#) in the *Red Hat Enterprise Linux 7 Installation Guide*.

PXELinux, PXEGrub, PXEGrub2

PXE-based templates that deploy to the template Capsule associated with a subnet to ensure that the host uses the installer with the correct kernel options. For BIOS provisioning, select **PXELinux** template. For UEFI provisioning, select **PXEGrub2**.

Finish

Post-configuration scripts to use when the main provisioning process completes. This is completed as an SSH task. You can use Finishing templates only for imaged-based provisioning in virtual environments. Do not confuse an image with a foreman discovery ISO, which is sometimes called a Foreman discovery image. An image in this context is an install image in a virtualized environment for easy deployment.

Bootdisk

Templates for PXE-less boot methods.

Kernel Execution (kexec)

Kernel execution templates for PXE-less boot methods.



NOTE

Kernel Execution is a Technology Preview feature. Technology Preview features are not fully supported under Red Hat Subscription Service Level Agreements (SLAs), may not be functionally complete, and are not intended for production use. However, these features provide early access to upcoming product innovations, enabling customers to test functionality and provide feedback during the development process.

user_data

Post-configuration scripts for providers that accept user data, such as **cloud-init** scripts. This template does not require Satellite to be able to reach the host. However, the host must be able to reach Satellite.

Script

An arbitrary script not used by default but useful for custom tasks.

ZTP

Zero Touch Provisioning templates.

POAP

PowerOn Auto Provisioning templates.

iPXE

Templates for **iPXE** or **gPXE** environments to use instead of PXELinux.

3.7.2. Template Syntax and Management

Red Hat Satellite includes many template examples. In the Satellite web UI, navigate to **Hosts > Provisioning templates** to view them. You can create a template or clone a template and edit the clone. For help with templates, navigate to **Hosts > Provisioning templates > Create Template > Help**.

Templates accept the Embedded Ruby (ERB) syntax. For more information, see [Template Writing Reference](#) in *Managing Hosts*.

You can download provisioning templates. Before you can download the template, you must create a debug certificate. For more information, see [Creating an Organization Debug Certificate](#) in the *Content Management Guide*.

You can synchronize templates between Satellite Server and a Git repository or a local directory. For more information, see [Appendix F. Synchronizing Templates with Git](#) in the *Content Management guide*.

Change logs and history

To view the history of changes applied to a template, navigate to **Hosts > Provisioning templates**, select one of the templates, and click **History**. Click **Revert** to override the editor content with the previous version. It is possible to revert to an earlier change as well. Click **Show Diff** to see information about a specific change:

1. **Template Diff** tab displays changes in the body of a provisioning template.
2. **Details** tab displays changes in the template description.
3. **History** tab displays the user who made a change to the template and date of the change.

3.7.3. Procedure

To create a template, complete the following step:

- In the Satellite web UI, navigate to **Hosts > Provisioning Templates** and, in the Provisioning Templates window, click **Create Template**.

The **Help** tab provides information about the template syntax. It details the available functions, variables, and methods that can be called on different types of objects within the template.

Alternatively, to clone a template and add your updates to the clone, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > Provisioning Templates** and search for the template that you want to use.
2. On the template that you want to use, click **Clone** to duplicate it.
3. In the **Name** field, enter a name for the provisioning template.
4. Select the **Default** check box to set the template to associate automatically with new organizations or locations.
5. In the **Template editor** field, enter the body of the provisioning template. You can also use the **Template** file browser to upload a template file.
6. In the **Audit Comment** field, enter a summary of changes to the provisioning template for auditing purposes.

7. Click the **Type** tab and if your template is a snippet, select the **Snippet** check box. A snippet is not a standalone provisioning template, but a part of a provisioning template that can be inserted into other provisioning templates.
8. From the **Type** list, select the type of the template. For example, **Provisioning template**.
9. Click the **Association** tab and from the **Applicable Operating Systems** list, select the names of the operating systems that you want to associate with the provisioning template.
10. Optionally, click **Add combination** and select a host group from the **Host Group** list or an environment from the **Environment** list to associate provisioning template with the host groups and environments.
11. Click the **Organizations** and **Locations** tabs to add any additional contexts to the template.
12. Click **Submit** to save your provisioning template.

For CLI Users

Before you create a template with the CLI, create a plain text file that contains the template. This example uses the `~/my-template` file. Create the installation medium using the **hammer template create** command and specify the type with the `--type` option:

```
# hammer template create --name "My Provisioning Template" \
--file ~/my-template --type provision --organizations "My_Organization" \
--locations "My_Location"
```

3.8. CREATING COMPUTE PROFILES

Compute profiles are used in conjunction with compute resources, such as virtualization infrastructure and cloud providers. Compute profiles allow users to predefine hardware such as CPUs, memory, and storage. A default installation of Red Hat Satellite 6 contains three predefined profiles:

- **1-Small**
- **2-Medium**
- **3-Large**

Procedure

1. In the Satellite web UI, navigate to **Infrastructure > Compute Profiles**, and in the Compute Profiles window, click **Create Compute Profile**.
2. In the **Name** field, enter a name for the profile and click **Submit**.

For CLI Users

The compute profile CLI commands are not yet implemented in Red Hat Satellite 6.6.

3.9. SETTING A DEFAULT ENCRYPTED ROOT PASSWORD FOR HOSTS

If you do not want to set a plain text default root password for the hosts that you provision, you can use a default encrypted password.

To set a default encrypted password for your hosts, complete the following steps:

1. Generate an encrypted password. You can use the following command to generate a password:

```
# python -c 'import crypt,getpass;pw=getpass.getpass(); print(crypt.crypt(pw)) if (pw==getpass.getpass("Confirm: ")) else exit()'
```

2. Copy the password for later use.
3. In the Satellite web UI, navigate to **Administer** > **Settings**.
4. On the **Settings** page, select the **Provisioning** tab.
5. In the **Name** column, navigate to **Root password**, and click **Click to edit**
6. Paste the encrypted password that you generate, and click **Save**.

3.10. USING THIRD PARTY INSTALLATION MEDIA

Installation media are sources of files for third parties that Satellite Server uses to install a third-party base operating system on a machine. Installation media must be in the format of an operating system installation tree, and must be accessible to the machine hosting the installer through an HTTP URL. You can view installation media by navigating to **Hosts** > **Installation Media** menu.

For other installation media, for example, a locally mounted ISO image, you can add your own custom media paths using the following procedure.

Procedure

To create installation media, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts** > **Installation Media** and click **Create Medium**.
2. In the **Name** field, enter a name to represent the installation media entry.
3. In the **Path** enter the URL or NFS share that contains the installation tree. You can use following variables in the path to represent multiple different system architectures and versions:

- **\$arch** - The system architecture.
- **\$version** - The operating system version.
- **\$major** - The operating system major version.
- **\$minor** - The operating system minor version.

Example HTTP path:

```
http://download.example.com/centos/$version/Server/$arch/os/
```

Example NFS path:

```
nfs://download.example.com:/centos/$version/Server/$arch/os/
```

Synchronized content on Capsule Servers always uses an HTTP path. Capsule Server managed content does not support NFS paths.

4. From the **Operating system family** list, select the distribution or family of the installation medium. For example, CentOS, and Fedora are in the **Red Hat** family.

5. Click the **Organizations** and **Locations** tabs, to change the provisioning context. Satellite Server adds the installation medium to the set provisioning context.
6. Click **Submit** to save your installation medium.

For CLI Users

Create the installation medium using the **hammer medium create** command:

```
# hammer medium create --name "CustomOS" --os-family "Redhat" \
--path 'http://download.example.com/centos/$version/Server/$arch/os/' \
--organizations "My_Organization" --locations "My_Location"
```

3.11. USING NOVNC TO ACCESS VIRTUAL MACHINES

You can use your browser to access the VNC console of VMs created by Satellite.

Satellite supports using noVNC on the following virtualization platforms:

- VMware
- Libvirt
- RHV

Use the following procedure to configure your virtualization platform and browser to enable the use of the noVNC console.

Prerequisites

- You must have a virtual machine created by Satellite.
- For existing virtual machines, ensure that the **Display type** in the **Compute Resource** settings is **VNC**.
- You must import the Katello root CA certificate into your Satellite Server. Adding a security exception in the browser is not enough for using noVNC. For more information, see the [Installing the Katello Root CA Certificate](#) section in the *Administering Red Hat Satellite* guide.

Procedure

1. On the VM host system, configure the firewall to allow VNC service on ports 5900 to 5930:

- On Red Hat Enterprise Linux 6:

```
# iptables -A INPUT -p tcp --dport 5900:5930 -j ACCEPT
# service iptables save
```

- On Red Hat Enterprise Linux 7:

```
# firewall-cmd --add-port=5900-5930/tcp
# firewall-cmd --add-port=5900-5930/tcp --permanent
```

2. In the Satellite web UI, navigate to **Infrastructure > Compute Resources** and select the name of a compute resource.

3. In the **Virtual Machines** tab, select the name of a VM host. Ensure the machine is powered on and then select **Console**.

CHAPTER 4. CONFIGURING NETWORKING

Each provisioning type requires some network configuration. Use this chapter to configure network services in Satellite Server's integrated Capsule.

New hosts must have access to your Capsule Server. Capsule Server can be either Satellite Server's integrated Capsule or an external Capsule Server. You might want to provision hosts from an external Capsule Server when the hosts are on isolated networks and cannot connect to the Satellite Server directly, or when the content is synchronized with the Capsule Server. Provisioning using the external Capsule Server can save on network bandwidth.

Configuring the Capsule Server has two basic requirements:

1. Configuring network services. This includes:
 - Content delivery services
 - Network services (DHCP, DNS, and TFTP)
 - Puppet configuration
2. Defining network resource data in Satellite Server to help configure network interfaces on new hosts.

Network Resources

Satellite contains networking resources that you must set up and configure to create a host. Satellite includes the following networking resources:

Domain

You must assign every host that you want to manage with Satellite to a domain. Using the domain, Satellite can manage A, AAAA and PTR records. If there is no record integration, you still must create and associate at least one domain. Domains are included in the naming conventions Satellite hosts, for example, a host **test123** in the **example.com** domain has the host name **test123.example.com**.

Subnet

You must assign every host managed by Satellite to a subnet. Using subnets, Satellite can then manage IPv4 reservations. If there are no reservation integrations, you still must create and associate at least one subnet. You can manage IP addresses with one of the following options:

- **Manual:** when the **IPAM** is set to **None**
- **DHCP:** the managed DHCP server requests a free IP from its pool
- **Database:** a serial or random IP address book that is kept in the Satellite database

The following instructions have similar applications to configuring standalone Capsule Servers managing a specific network. To configure Satellite to use external DHCP, DNS, and TFTP services, see [Configuring External Services](#) in *Installing Satellite Server from a Connected Network*.

DHCP Ranges

You can define the same DHCP range in Satellite Server for both discovered and provisioned systems, but use a separate range for each service within the same subnet.

4.1. SATELLITE AND DHCP OPTIONS

Satellite manages DHCP reservations through a DHCP Capsule. Satellite also sets the **next-server** and **filename** DHCP options.

The next-server option

The **next-server** option provides the IP address of the TFTP server to boot from. This option is not set by default and must be set for each TFTP Capsule. You can use the **satellite-installer** command with the **--foreman-proxy-tftp-servername** option to set the TFTP server in the **/etc/foreman-proxy/settings.d/tftp.yml** file:

```
# satellite-installer --foreman-proxy-tftp-servername 1.2.3.4
```

Each TFTP Capsule then reports this setting through the API and Satellite can retrieve the configuration information when it creates the DHCP record.

When the PXE loader is set to **none**, Satellite does not populate the **next-server** option into the DHCP record.

If the **next-server** option remains undefined, Satellite uses reverse DNS search to find a TFTP server address to assign, but you might encounter the following problems:

- DNS timeouts during provisioning
- Querying of incorrect DNS server. For example, authoritative rather than caching
- Errors about incorrect IP address for the TFTP server. For example, **PTR record was invalid**

If you encounter these problems, check the DNS setup on both Satellite and Capsule, specifically the PTR record resolution.

The filename option

The **filename** option contains the full path to the file that downloads and executes during provisioning. The PXE loader that you select for the host or host group defines which **filename** option to use. When the PXE loader is set to **none**, Satellite does not populate the **filename** option into the DHCP record. Depending on the PXE loader option, the **filename** changes as follows:

PXE loader option	filename entry	Notes
PXELinux BIOS	pxelinux.0	
PXELinux UEFI	pxelinux.efi	
iPXE Chain BIOS	undionly.kpxe	
PXEGrub2 UEFI	grub2/grubx64.efi	x64 can differ depending on architecture
iPXE UEFI HTTP	http://capsule.example.com:8000/httpboot/ipxe-x64.efi	Requires the httpboot feature and renders the filename as a full URL where <i>capsule.example.com</i> is a known host name of Capsule in Satellite.

PXE loader option	filename entry	Notes
Grub2 UEFI HTTP	http://capsule.example.com:8000/httpboot/grub2/grubx64.efi	Requires the httpboot feature and renders the filename as a full URL where <i>capsule.example.com</i> is a known host name of Capsule in Satellite.

4.2. PREREQUISITES FOR IMAGE BASED PROVISIONING

Post-Boot Configuration Method

Images that use the **finish** post-boot configuration scripts require a managed DHCP server, such as Satellite's integrated Capsule or an external Capsule. The host must be created with a subnet associated with a DHCP Capsule, and the IP address of the host must be a valid IP address from the DHCP range.

It is possible to use an external DHCP service, but IP addresses must be entered manually. The SSH credentials corresponding to the configuration in the image must be configured in Satellite to enable the post-boot configuration to be made.

Check following items when troubleshooting a virtual machine booted from an image that depends on post-configuration scripts:

- The host has a subnet assigned in Satellite Server.
- The subnet has a DHCP Capsule assigned in Satellite Server.
- The host has a valid IP address assigned in Satellite Server.
- The IP address acquired by the virtual machine using DHCP matches the address configured in Satellite Server.
- The virtual machine created from an image responds to SSH requests.
- The virtual machine created from an image authorizes the user and password, over SSH, which is associated with the image being deployed.
- Satellite Server has access to the virtual machine via SSH keys. This is required for the virtual machine to receive post-configuration scripts from Satellite Server.

Pre-Boot Initialization Configuration Method

Images that use the **cloud-init** scripts require a DHCP server to avoid having to include the IP address in the image. A managed DHCP Capsule is preferred. The image must have the **cloud-init** service configured to start when the system boots and fetch a script or configuration data to use in completing the configuration.

Check the following items when troubleshooting a virtual machine booted from an image that depends on initialization scripts included in the image:

- There is a DHCP server on the subnet.
- The virtual machine has the **cloud-init** service installed and enabled.

For information about the differing levels of support for **finish** and **cloud-init** scripts in virtual-machine images, see the Red Hat Knowledgebase Solution [What are the supported compute resources for the finish and cloud-init scripts](#) on the Red Hat Customer Portal.

4.3. CONFIGURING NETWORK SERVICES

Some provisioning methods use Capsule Server services. For example, a network might require the Capsule Server to act as a DHCP server. A network can also use PXE boot services to install the operating system on new hosts. This requires configuring the Capsule Server to use the main PXE boot services: DHCP, DNS, and TFTP.

Use the **satellite-installer** script with the options to configure these services on the Satellite Server.

To configure these services on an external Capsule Server, run **satellite-installer --scenario capsule**.

Satellite Server uses **eth0** for external communication, such as connecting to Red Hat's CDN.

Procedure

To configure network services on Satellite's integrated Capsule, complete the following steps:

1. Enter the **satellite-installer** command to configure the required network services:

```
# satellite-installer --foreman-proxy-dhcp true \
--foreman-proxy-dhcp-managed true \
--foreman-proxy-dhcp-gateway "192.168.140.1" \
--foreman-proxy-dhcp-interface "eth1" \
--foreman-proxy-dhcp-nameservers "192.168.140.2" \
--foreman-proxy-dhcp-range "192.168.140.10 192.168.140.110" \
--foreman-proxy-dhcp-server "192.168.140.2" \
--foreman-proxy-dns true \
--foreman-proxy-dns-managed true \
--foreman-proxy-dns-forwarders "8.8.8.8; 8.8.4.4" \
--foreman-proxy-dns-interface "eth1" \
--foreman-proxy-dns-reverse "140.168.192.in-addr.arpa" \
--foreman-proxy-dns-server "127.0.0.1" \
--foreman-proxy-dns-zone "example.com" \
--foreman-proxy-tftp true \
--foreman-proxy-tftp-managed true
```

2. Find the Capsule Server that you configure:

```
# hammer proxy list
```

3. Refresh features of the Capsule Server to view the changes:

```
# hammer proxy refresh-features --name "satellite.example.com"
```

4. Verify the services configured on the Capsule Server:

```
# hammer proxy info --name "satellite.example.com"
```

4.3.1. DHCP, DNS, and TFTP Options for Network Configuration

DHCP Options

--foreman-proxy-dhcp

Enables the DHCP service. You can set this option to **true** or **false**.

--foreman-proxy-dhcp-managed

Enables Foreman to manage the DHCP service. You can set this option to **true** or **false**.

--foreman-proxy-dhcp-gateway

The DHCP pool gateway. Set this to the address of the external gateway for hosts on your private network.

--foreman-proxy-dhcp-interface

Sets the interface for the DHCP service to listen for requests. Set this to **eth1**.

--foreman-proxy-dhcp-nameservers

Sets the addresses of the nameservers provided to clients through DHCP. Set this to the address for Satellite Server on **eth1**.

--foreman-proxy-dhcp-range

A space-separated DHCP pool range for Discovered and Unmanaged services.

--foreman-proxy-dhcp-server

Sets the address of the DHCP server to manage.

DNS Options

--foreman-proxy-dns

Enables DNS service. You can set this option to **true** or **false**.

--foreman-proxy-dns-managed

Enables Foreman to manage the DNS service. You can set this option to **true** or **false**.

--foreman-proxy-dns-forwarders

Sets the DNS forwarders. Set this to your DNS servers.

--foreman-proxy-dns-interface

Sets the interface to listen for DNS requests. Set this to **eth1**.

--foreman-proxy-dns-reverse

The DNS reverse zone name.

--foreman-proxy-dns-server

Sets the address of the DNS server to manage.

--foreman-proxy-dns-zone

Sets the DNS zone name.

TFTP Options

--foreman-proxy-tftp

Enables TFTP service. You can set this option to **true** or **false**.

--foreman-proxy-tftp-managed

Enables Foreman to manage the TFTP service. You can set this option to **true** or **false**.

--foreman-proxy-tftp-servername

Sets the TFTP server to use. Ensure that you use Capsule's IP address.

Run **satellite-installer --scenario capsule --help** to view more options related to DHCP, DNS, TFTP, and other Satellite Capsule services

4.3.2. Using TFTP Services through NAT

You can use Satellite TFTP services through NAT. To do this, on all NAT routers or firewalls, you must enable a TFTP service on UDP port 69 and enable the TFTP state tracking feature. For more information, see the documentation for your NAT device.

If your NAT routers or firewalls use Red Hat Enterprise Linux, perform this procedure on all devices.

On Red Hat Enterprise Linux 7:

Use the following command to allow TFTP service on UDP port 69, load the kernel TFTP state tracking module, and make the changes persistent:

```
# firewall-cmd --add-service=tftp && firewall-cmd --runtime-to-permanent
```

On Red Hat Enterprise Linux 6:

1. Configure the firewall to allow TFTP service UDP on port 69.

```
# iptables -A OUTPUT -i eth0 -p udp --sport 69 -m state \
--state ESTABLISHED -j ACCEPT
# service iptables save
```

2. Load the **ip_conntrack_tftp** kernel TFTP state module. In the **/etc/sysconfig/iptables-config** file, locate **IPTABLES_MODULES** and add **ip_conntrack_tftp** as follows:

```
IPTABLES_MODULES="ip_conntrack_tftp"
```

4.4. ADDING A DOMAIN TO SATELLITE SERVER

Satellite Server defines domain names for each host on the network. Satellite Server must have information about the domain and the Capsule Server responsible for domain name assignment. This provides users with a means to group and name hosts within a particular domain and associate them with parameters and Puppet variables.

Checking for Existing Domains

Satellite Server might already have the relevant domain created as part of Satellite Server installation. Switch the context to **Any Organization** and **Any Location** then check the domain list to see if it exists.

Procedure

To add a domain to Satellite, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Domains** and click **Create Domain**.
2. In the **DNS Domain** field, enter the full DNS domain name.
3. In the **Fullname** field, enter the plain text name of the domain.

4. Click the **Parameters** tab and configure any domain level parameters to apply to hosts attached to this domain. For example, user defined Boolean or string parameters to use in templates.
5. Click **Add Parameter** and fill in the **Name** and **Value** fields.
6. Click the **Locations** tab, and add the location where the domain resides.
7. Click the **Organizations** tab, and add the organization that the domain belongs to.
8. Click **Submit** to save the changes.

For CLI Users

Use the **hammer domain create** command to create a domain:

```
# hammer domain create --name "domain_name.com" \
--description "My example domain" --dns-id 1 \
--locations "My_Location" --organizations "My_Organization"
```

In this example, the **--dns-id** option uses **1**, which is the ID of Satellite Server's integrated Capsule.

4.5. ADDING A SUBNET TO SATELLITE SERVER

Subnets in Red Hat Satellite define networks specified for groups of systems. Subnets use standard IP-address settings to define the network and use the Red Hat Satellite Capsule Server DHCP features to assign IP addresses to systems within the subnet.

You must add information for each of your subnets to Satellite Server because Satellite configures interfaces for new hosts. To configure interfaces, Satellite Server must have all the information about the network that connects these interfaces.

Procedure

To add a subnet to Satellite Server, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Subnets**, and in the Subnets window, click **Create Subnet**
2. In the **Name** field, enter a name for the subnet.
3. In the **Description** field, enter a description for the subnet.
4. In the **Network address** field, enter the network address for the subnet.
5. In the **Network prefix** field, enter the network prefix for the subnet.
6. In the **Network mask** field, enter the network mask for the subnet.
7. In the **Gateway address** field, enter the external gateway for the subnet.
8. In the **Primary DNS server** field, enter a primary DNS for the subnet.
9. In the **Secondary DNS server**, enter a secondary DNS for the subnet.
10. From the **IPAM** list, select the method that you want to use for IP address management (IPAM):

- **DHCP** – The subnet contains a DHCP server.
 - **Internal DB** – The subnet does not contain a DHCP server but Satellite can manage the IP address assignment and record IP addresses in its internal database.
 - **None** – No IP address management.
11. Enter the information for the IPAM method that you select.
 12. Click the **Remote Execution** tab and select the capsule that controls the remote execution.
 13. Click the **Domains** tab and select the domains that apply to this subnet.
 14. Click the **Capsules** tab and select the Capsule that you want to provide each service in the subnet.
 15. Click the **Parameters** tab and configure any subnet level parameters to apply to hosts attached to this subnet. For example, user defined Boolean or string parameters to use in templates.
 16. Click the **Locations** tab and select the locations that use this capsule.
 17. Click the **Organizations** tab and select the organizations that use this capsule.
 18. Click **Submit** to save the subnet information.

For CLI Users

Create the subnet with the following command:

```
# hammer subnet create --name "My_Network" \
--description "your_description" \
--network "192.168.140.0" --mask "255.255.255.0" \
--gateway "192.168.140.1" --dns-primary "192.168.140.2" \
--dns-secondary "8.8.8.8" --ipam "DHCP" \
--from "192.168.140.111" --to "192.168.140.250" --boot-mode "DHCP" \
--domains "example.com" --dhcp-id 1 --dns-id 1 --tftp-id 1 --template-id 1 \
--locations "My_Location" --organizations "My_Organization"
```



NOTE

In this example, the **--dhcp-id**, **--dns-id**, and **--tftp-id** options use 1, which is the ID of the integrated Capsule in Satellite Server.

4.6. CONFIGURING IPXE TO REDUCE PROVISIONING TIMES

In Red Hat Satellite 6.6, you can configure PXELinux to chainboot iPXE and boot using the HTTP protocol, which is faster and more reliable on high latency networks than TFTP.

There are three methods of using iPXE with Red Hat Satellite 6.6:

1. Chainbooting virtual machines using hypervisors that use iPXE as primary firmware
2. Using PXELinux through TFTP to chainload iPXE directly on bare metal hosts
3. Using PXELinux through UNDI, which uses HTTP to transfer the kernel and the initial RAM disk on bare metal hosts

Prerequisites

Before you begin, ensure that the following conditions are met:

- A host exists on Red Hat Satellite to use
- The MAC address of the provisioning interface matches the host configuration
- The provisioning interface of the host has a valid DHCP reservation
- The NIC is capable of PXE booting. For more information, see http://ipxe.org/appnote/hardware_drivers
- The NIC is compatible with iPXE

4.6.1. Chainbooting virtual machines

Most virtualization hypervisors use iPXE as primary firmware for PXE booting. Because of this, you can chainboot without TFTP and PXELinux.

Chainbooting virtual machine workflow

Using virtualization hypervisors removes the need for TFTP and PXELinux. It has the following workflow:

1. Virtual machine starts
2. iPXE retrieves the network credentials using DHCP
3. iPXE retrieves the HTTP address using DHCP
4. iPXE chainloads the iPXE template from the template Capsule
5. iPXE loads the kernel and initial RAM disk of the installer

Ensure that the hypervisor that you want to use supports iPXE. The following virtualization hypervisors support iPXE:

- libvirt
- oVirt
- RHEV

Configuring Red Hat Satellite Server to use iPXE

You can use the default template to configure iPXE booting for hosts. If you want to change the default values in the template, clone the template and edit the clone.

Procedure

To configure Satellite to use iPXE, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > Provisioning Templates**, enter **Kickstart default iPXE** and click **Search**.
2. Optional: If you want to change the template, click **Clone**, enter a unique name, and click **Submit**.
3. Click the name of the template you want to use.

4. If you clone the template, you can make changes you require on the **Template** tab.
5. Click the **Association** tab, and select the operating systems that your host uses.
6. Click the **Locations** tab, and add the location where the host resides.
7. Click the **Organizations** tab, and add the organization that the host belongs to.
8. Click **Submit** to save the changes.
9. Navigate to **Hosts > Operating systems** and select the operating system of your host.
10. Click the **Templates** tab.
11. From the **iPXE Template** list, select the template you want to use.
12. Click **Submit** to save the changes.
13. Navigate to **Hosts > All Hosts**.
14. In the **Hosts** page, select the host that you want to use.
15. Select the **Templates** tab.
16. From the **iPXE template** list, select **Review** and verify that the **Kickstart default iPXE** template is the correct template.
17. To prevent an endless loop of chainbooting iPXE firmware, edit the `/etc/dhcp/dhcpd.conf` file to match the following example. If you use an isolated network, use a Capsule Server URL with TCP port 8000, instead of Satellite Server's URL.
 - a. Locate the following lines in the Bootfile Handoff section of the `/etc/dhcp/dhcpd.conf` file:

```
} else {  
    filename "pxelinux.0";  
}
```

- b. Add the following extra **elsif** statement before the else statement:

```
elsif exists user-class and option user-class = "iPXE" {  
    filename "http://satellite.example.com/unattended/iPXE";  
}
```

- c. Verify that the 'if' section matches the following example:

```
if option architecture = 00:06 {  
    filename "grub2/shim.efi";  
} elsif option architecture = 00:07 {  
    filename "grub2/shim.efi";  
} elsif option architecture = 00:09 {  
    filename "grub2/shim.efi";  
} elsif exists user-class and option user-class = "iPXE" {  
    filename "http://satellite.example.com/unattended/iPXE";  
} else {  
    filename "pxelinux.0";  
}
```


**NOTE**

For <http://satellite.example.com/unattended/iPXE>, you can also use a Red Hat Satellite Capsule <http://capsule.example.com:8000/unattended/iPXE>. You must update the `/etc/dhcp/dhcpd.conf` file after every upgrade. The content of the `/etc/dhcp/dhcpd.conf` file is case sensitive.

4.6.2. Chainbooting iPXE directly

Use this procedure to set up iPXE to use a built-in driver for network communication or UNDI interface. There are separate procedures to configure Satellite Server and Capsule to use iPXE.

You can use this procedure only with bare metal hosts.

Chainbooting iPXE directly or with UNDI workflow

1. Host powers on
2. PXE driver retrieves the network credentials using DHCP
3. PXE driver retrieves the PXELinux firmware **pxelinux.0** using TFTP
4. PXELinux searches for the configuration file on the TFTP server
5. PXELinux chainloads iPXE **ipxe.lkrn** or **undionly-ipxe.0**
6. iPXE retrieves the network credentials using DHCP again
7. iPXE retrieves HTTP address using DHCP
8. iPXE chainloads the iPXE template from the template Capsule
9. iPXE loads the kernel and initial RAM disk of the installer

Configuring Red Hat Satellite Server to use iPXE

You can use the default template to configure iPXE booting for hosts. If you want to change the default values in the template, clone the template and edit the clone.

Procedure

To configure Satellite to use iPXE with the UNDI workflow, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > Provisioning Templates**, enter **PXELinux chain iPXE** or, for UNDI, enter **PXELinux chain iPXE UNDI**, and click **Search**.
2. Optional: If you want to change the template, click **Clone**, enter a unique name, and click **Submit**.
3. Click the name of the template you want to use.
4. If you clone the template, you can make changes you require on the **Template** tab.
5. Click the **Association** tab, and select the operating systems that your host uses.
6. Click the **Locations** tab, and add the location where the host resides.
7. Click the **Organizations** tab, and add the organization that the host belongs to.

8. Click **Submit** to save the changes.
9. In the **Provisioning Templates** page, enter **Kickstart default iPXE** into the search field and click **Search**.
10. Optional: If you want to change the template, click **Clone**, enter a unique name, and click **Submit**.
11. Click the name of the template you want to use.
12. If you clone the template, you can make changes you require on the **Template** tab.
13. Click the **Association** tab, and associate the template with the operating system that your host uses.
14. Click the **Locations** tab, and add the location where the host resides.
15. Click the **Organizations** tab, and add the organization that the host belongs to.
16. Click **Submit** to save the changes.
17. Navigate to **Hosts > Operating systems** and select the operating system of your host.
18. Click the **Templates** tab.
19. From the **PXELinux template** list, select the template you want to use.
20. From the **iPXE template** list, select the template you want to use.
21. Click **Submit** to save the changes.
22. Navigate to **Hosts > All Hosts**, and select the host you want to use.
23. Select the **Templates** tab, and from the **PXELinux template** list, select **Review** and verify the template is the correct template.
24. From the **iPXE template** list, select **Review** and verify the template is the correct template. If there is no PXELinux entry, or you cannot find the new template, navigate to **Hosts > All Hosts**, and on your host, click **Edit**. Click the **Operating system** tab and click the Provisioning Template **Resolve** button to refresh the list of templates.
25. To prevent an endless loop of chainbooting iPXE firmware, edit the `/etc/dhcp/dhcpd.conf` file to match the following example. If you use an isolated network, use a Capsule Server URL with TCP port 8000, instead of Satellite Server's URL.
 - a. Locate the following lines in the Bootfile Handoff section of the `/etc/dhcp/dhcpd.conf` file:

```
} else {  
    filename "pxelinux.0";  
}
```

- b. Add the following extra **elsif** statement before the else statement:

```
elsif exists user-class and option user-class = "iPXE" {  
    filename "http://satellite.example.com/unattended/iPXE";  
}
```

- c. Verify that the 'if' section matches the following example:

```
if option architecture = 00:06 {
    filename "grub2/shim.efi";
} elsif option architecture = 00:07 {
    filename "grub2/shim.efi";
} elsif option architecture = 00:09 {
    filename "grub2/shim.efi";
} elsif exists user-class and option user-class = "iPXE" {
    filename "http://satellite.example.com/unattended/iPXE";
} else {
    filename "pxelinux.0";
}
```



NOTE

For <http://satellite.example.com/unattended/iPXE>, you can also use a Red Hat Satellite Capsule <http://capsule.example.comf:8000/unattended/iPXE>. You must update the `/etc/dhcp/dhcpd.conf` file after every upgrade. The content of the `/etc/dhcp/dhcpd.conf` file is case sensitive.

Configuring Red Hat Satellite Capsule to use iPXE

You can use this procedure to configure Capsules to use iPXE.

You must perform this procedure on all Capsules.

Procedure

To configure the Capsule to chainboot iPXE, complete the following steps:

1. Install the **ipxe-bootimgs** RPM package:

```
# yum install ipxe-bootimgs
```

2. Copy the iPXE firmware to the TFTP server's root directory. Do not use symbolic links because TFTP runs in the **chroot** environment.

- For chainbooting directly, enter the following command:

```
# cp /usr/share/ipxe/ipxe.lkrn /var/lib/tftpboot/
```

- For UNDI, enter the following command:

```
# cp /usr/share/ipxe/undionly.kpxe /var/lib/tftpboot/undionly-ipxe.0
```

3. Correct the file contexts:

```
# restorecon -RvF /var/lib/tftpboot/
```

CHAPTER 5. USING INFOBLOX AS DHCP AND DNS PROVIDERS

You can use Capsule Server to connect to your Infoblox application to create and manage DHCP and DNS records, and to reserve IP addresses.

The supported Infoblox version is NIOS 8.0 or higher and Satellite 6.5 or higher.

5.1. LIMITATIONS

All DHCP and DNS records can be managed only in a single Network or DNS view. After you install the Infoblox modules on Capsule and set up the view using the **satellite-installer** command, you cannot edit the view.

Capsule Server communicates with a single Infoblox node using the standard HTTPS web API. If you want to configure clustering and High Availability, make the configurations in Infoblox.

Hosting PXE-related files using Infoblox's TFTP functionality is not supported. You must use Capsule as a TFTP server for PXE provisioning. For more information, see [Chapter 4, Configuring Networking](#).

Satellite does not support using Infoblox IPAM.

5.2. PREREQUISITES

You must have Infoblox account credentials to manage DHCP and DNS entries in Satellite.

Ensure that you have Infoblox administration roles with the names: **DHCP Admin** and **DNS Admin**.

The administration roles must have permissions or belong to an admin group that permits the accounts to perform tasks through the Infoblox API.

5.3. INSTALLING THE INFOBLOX CA CERTIFICATE ON CAPSULE SERVER

You must install Infoblox HTTPS CA certificate on the base system for all Capsules that you want to integrate with Infoblox applications.

You can download the certificate from the Infoblox web UI, or you can use the following OpenSSL commands to download the certificate:

```
# update-ca-trust enable
# openssl s_client -showcerts -connect infoblox_hostname:443 </dev/null | \
openssl x509 -text >/etc/pki/ca-trust/source/anchors/infoblox.crt
# update-ca-trust extract
```

- The **infoblox_hostname** entry must match the host name for the Infoblox application in the X509 certificate.

To test the CA certificate, use a CURL query:

```
# curl -u admin:infoblox https://infoblox_hostname/wapi/v2.0/network
```

Example positive response:

```
[
  {
    "_ref":
    "network/ZG5zLm5ldHdvcm5kMTkyLjE2OC4yMDluMC8yNC8w:infoblox_hostname/24/default",
    "network": "192.168.202.0/24",
    "network_view": "default"
  }
]
```

Use the following Red Hat Knowledgebase article to install the certificate: [How to install a CA certificate on Red Hat Enterprise Linux 6 / 7](#).

5.4. INSTALLING THE DHCP INFOBLOX MODULE

Use this procedure to install the DHCP Infoblox module on Capsule. Note that you cannot manage records in separate views.

You can also install DHCP and DNS Infoblox modules simultaneously by combining this procedure and [Section 5.5, “Installing the DNS Infoblox Module”](#)

DHCP Infoblox Record Type Considerations

Use only the **--foreman-proxy-plugin-dhcp-infoblox-record-type fixedaddress** option to configure the DHCP and DNS modules.

Configuring both DHCP and DNS Infoblox modules with the **host** record type setting causes DNS conflicts and is not supported. If you install the Infoblox module on Capsule Server with the **--foreman-proxy-plugin-dhcp-infoblox-record-type** option set to **host**, you must unset both DNS Capsule and Reverse DNS Capsule options because Infoblox does the DNS management itself. You cannot use the **host** option without creating conflicts and, for example, being unable to rename hosts in Satellite.

Procedure

To install the Infoblox module for DHCP, complete the following steps:

1. On Capsule, enter the following command:

```
# satellite-installer --enable-foreman-proxy-plugin-dhcp-infoblox \
--foreman-proxy-dhcp true \
--foreman-proxy-dhcp-managed false \
--foreman-proxy-dhcp-provider infoblox \
--foreman-proxy-plugin-dhcp-infoblox-record-type fixedaddress \
--foreman-proxy-dhcp-server infoblox_hostname \
--foreman-proxy-plugin-dhcp-infoblox-username admin \
--foreman-proxy-plugin-dhcp-infoblox-password infoblox \
--foreman-proxy-plugin-dhcp-infoblox-network-view default \
--foreman-proxy-plugin-dhcp-infoblox-dns-view default
```

2. In the Satellite web UI, navigate to **Infrastructure > Capsules** and select the Capsule with the Infoblox DHCP module and click **Refresh**.
3. Ensure that the **dhcp** features are listed.
4. For all domains managed through Infoblox, ensure that the DNS Capsule is set for that domain. To verify, in the Satellite web UI, navigate to **Infrastructure > Domains**, and inspect the settings of each domain.

5. For all subnets managed through Infoblox, ensure that DHCP Capsule and Reverse DNS Capsule is set. To verify, in the Satellite web UI, navigate to **Infrastructure > Subnets**, and inspect the settings of each subnet.

5.5. INSTALLING THE DNS INFOBLOX MODULE

Use this procedure to install the DNS Infoblox module on Capsule. You can also install DHCP and DNS Infoblox modules simultaneously by combining this procedure and [Section 5.4, "Installing the DHCP Infoblox module"](#).

DNS records are managed only in the default DNS view, it's not possible to specify which DNS view to use.

To install the DNS Infoblox module, complete the following steps:

1. On Capsule, enter the following command:

```
# satellite-installer --enable-foreman-proxy-plugin-dns-infoblox \
--foreman-proxy-dns true \
--foreman-proxy-dns-managed false \
--foreman-proxy-dns-provider infoblox \
--foreman-proxy-plugin-dns-infoblox-dns-server infoblox_hostname \
--foreman-proxy-plugin-dns-infoblox-username admin \
--foreman-proxy-plugin-dns-infoblox-password infoblox
```

2. In the Satellite web UI, navigate to **Infrastructure > Capsules** and select the Capsule with the Infoblox DNS module and click **Refresh**.
3. Ensure that the **dns** features are listed.

CHAPTER 6. PROVISIONING BARE METAL HOSTS

There are four main ways to provision bare metal instances with Red Hat Satellite 6.6:

Unattended Provisioning

New hosts are identified by a MAC address and Satellite Server provisions the host using a PXE boot process.

Unattended Provisioning with Discovery

New hosts use PXE boot to load the Satellite Discovery service. This service identifies hardware information about the host and lists it as an available host to provision.

PXE-less Provisioning

New hosts are provisioned with a boot disk or PXE-less discovery image that Satellite Server generates.

PXE-less Provisioning with Discovery

New hosts use an ISO boot disk that loads the Satellite Discovery service. This service identifies hardware information about the host and lists it as an available host to provision.

BIOS and UEFI Support

With Red Hat Satellite, you can perform both BIOS and UEFI based PXELinux provisioning.

Both BIOS and UEFI interfaces work as interpreters between the computer's operating system and firmware, initializing the hardware components and starting the operating system at boot time.

While BIOS reads the first section of the hard drive that contains the next address to initialize, UEFI stores all the information about initialization and startup in an **.efi** file instead of the firmware. UEFI systems are newer and becoming more common.

To perform PXELinux provisioning with UEFI you must use a Red Hat Enterprise Linux Server 7 or higher that has Intel x86_64. In Satellite, PXELinux provisioning with UEFI is supported only on bare-metal systems. Because of a GRUB-related limitation, you cannot use UEFI to provision with a full host image. UEFI is not supported for virtual machines. UEFI SecureBoot is also not supported.

In Satellite provisioning, the PXE loader which is a DHCP file name that defines which file to load through TFTP during PXE provisioning. For BIOS system, the file is **pxelinux.0**. For UEFI systems, the file is **grub2/grubx64.efi**.

For BIOS provisioning, you must associate a PXELinux template with the operating system.

For UEFI provisioning you must associate a PXEGrub2 template with the operating system.

If you associate both PXELinux and PXEGrub2 templates, Satellite 6 can deploy configuration files for both on a TFTP server, so that you can switch between PXE loaders easily.

6.1. PREREQUISITES FOR BARE METAL PROVISIONING

The requirements for bare metal provisioning include:

- Synchronized content repositories for the version of Red Hat Enterprise Linux that you want to use. For more information, see [Synchronizing Red Hat Repositories](#) in the *Content Management Guide*.

- A Capsule Server managing the network for bare metal hosts. For unattended provisioning and discovery-based provisioning, Satellite Server requires PXE server settings. For more information, see [Chapter 4, Configuring Networking](#).
- An activation key for host registration. For more information, see [Creating An Activation Key](#) in the *Content Management* guide.
- A blank bare metal host.

For information about the security token for unattended and PXE-less provisioning, see [Section 6.2, “Configuring the Security Token Validity Duration”](#).

6.2. CONFIGURING THE SECURITY TOKEN VALIDITY DURATION

When performing unattended and PXE-less provisioning, as a security measure, Satellite automatically generates a unique token and adds this token to the URL of the ISO image that downloads during the Kickstart provisioning process.

By default, the token is valid for 360 minutes. When you provision a host, ensure that you reboot the host within this time frame. If the token expires, it is deleted and you might receive a 404 error.

To adjust the token’s duration of validity, in the Satellite web UI, navigate to **Administer** > **Settings**, and click the **Provisioning** tab. Find the **Token duration** option, and click the edit icon and edit the duration, or enter **0** to disable token generation.

6.3. CREATING HOSTS WITH UNATTENDED PROVISIONING

Unattended provisioning is the simplest form of host provisioning. You enter the host details on Satellite Server and boot your host. Satellite Server automatically manages the PXE configuration, organizes networking services, and provides the operating system and configuration for the host.

This method of provisioning hosts uses minimal interaction during the process.

Procedure

To create a host with unattended provisioning, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts** > **Create Host**.
2. In the **Name** field, enter a name for the host.
3. Click the **Organization** and **Location** tabs and change the context to match your requirements.
4. From the **Host Group** list, select a host group that you want to use to populate the form.
5. Click the **Interface** tab, and on the host’s interface, click **Edit**.
6. Verify that the fields are populated with values. Note in particular:
 - The **Name** from the **Host** tab becomes the **DNS name**.
 - Satellite Server automatically assigns an IP address for the new host.
7. In the **MAC address** field, enter a MAC address for the host. This ensures the identification of the host during the PXE boot process.

8. Ensure that Satellite Server automatically selects the **Managed**, **Primary**, and **Provision** options for the first interface on the host. If not, select them.
9. Click the **Operating System** tab, and verify that all fields contain values. Confirm each aspect of the operating system.
10. Click **Resolve** in **Provisioning template** to check the new host can identify the right provisioning templates to use.
11. Optional: If you want to use VLAN tagging, you must add the VLAN ID to the PXELinux or PXEGrub2 template. To the **APPEND** line, add **vlanid=example_vlanid**.
For more information about associating provisioning templates, see [Section 3.7, “Creating Provisioning Templates”](#).
12. Click the **Parameters** tab, and ensure that a parameter exists that provides an activation key. If not, add an activation key.
13. Click **Submit** to save the host details.

This creates the host entry and the relevant provisioning settings. This also includes creating the necessary directories and files for PXE booting the bare metal host. If you start the physical host and set its boot mode to PXE, the host detects the DHCP service of Satellite Server’s integrated Capsule and starts installing the operating system from its Kickstart tree. When the installation completes, the host also registers to Satellite Server using the activation key and installs the necessary configuration and management tools from the Red Hat Satellite Tools repository.

For CLI Users

Create the host with the **hammer host create** command.

```
# hammer host create --name "My_Unattended_Host" --organization "My_Organization" \
--location "My_Location" --hostgroup "My_Host_Group" --mac "aa:aa:aa:aa:aa:aa" \
--build true --enabled true --managed true
```


Ensure the network interface options are set using the **hammer host interface update** command.

```
# hammer host interface update --host "test1" --managed true \
--primary true --provision true
```

6.4. CONFIGURING RED HAT SATELLITE’S DISCOVERY SERVICE

Red Hat Satellite provides a method to automatically detect hosts on a network that are not in your Satellite inventory. These hosts boot the discovery image that performs hardware detection and relays this information back to Satellite Server. This method creates a list of ready-to-provision hosts in Satellite Server without needing to enter the MAC address of each host.

The Discovery service is enabled by default on Satellite Server. However, the default setting of the global templates is to boot from the local hard drive. To use discovery you must change the default entry in the template to discovery.



To use Satellite Server to provide the Discovery image, install the **foreman-discovery-image** and **rubygem-smart_proxy_discovery** packages:

```
# satellite-maintain packages install foreman-discovery-image rubygem-smart_proxy_discovery
```

The **foreman-discovery-image** package installs the Discovery ISO to the `/usr/share/foreman-discovery-image/` directory and also creates a PXE boot image from this ISO using the **livecd-iso-to-pxeboot** tool. The tool saves this PXE boot image in the `/var/lib/tftpboot/boot` directory. The **rubygem-smart_proxy_discovery** package configures a Capsule Server, such as Satellite Server's integrated Capsule, to act as a proxy for the Discovery service.

When the installation completes, you can view the new menu option by navigating to **Hosts > Discovered Hosts**.

6.4.1. Enabling Discovery service on a Capsule Server

Complete the following procedure to enable the Discovery service on a Capsule Server.

1. Enter the following commands on the Capsule Server:

```
# yum install foreman-discovery-image rubygem-smart_proxy_discovery
```

```
# satellite-maintain service restart
```

2. In the Satellite web UI, navigate to **Infrastructure > Capsule**.
3. Click the Capsule Server and select **Refresh** from the **Actions** list. Locate **Discovery** in the list of features to confirm the Discovery service is now running.

Subnets

All subnets with discoverable hosts require an appropriate Capsule Server selected to provide the Discovery service.

To check this, navigate to **Infrastructure > Capsules** and verify if the Capsule Server that you want to use lists the Discovery feature. If not, click **Refresh features**.

In the Satellite web UI, navigate to **Infrastructure > Subnets**, select a subnet, click the Capsules tab, and select the **Discovery Proxy** that you want to use. Perform this for each appropriate subnet.

6.4.2. Provisioning Template PXELinux Discovery Snippet

For BIOS provisioning, the **PXELinux global default** template in the **Hosts > Provisioning Templates** window contains the snippet **pxelinux_discovery**. The snippet has the following lines:

```

LABEL discovery
  MENU LABEL Foreman Discovery Image
  KERNEL boot/fdi-image/vmlinuz0
  APPEND initrd=boot/fdi-image/initrd0.img rootflags=loop root=live:/fdi.iso rootfstype=auto ro
rd.live.image acpi=force rd.luks=0 rd.md=0 rd.dm=0 rd.lvm=0 rd.bootif=0 rd.neednet=0 nomodeset
proxy.url=<%= foreman_server_url %> proxy.type=foreman
IPAPPEND 2

```

The **KERNEL** and **APPEND** options boot the Discovery image and ramdisk. The **APPEND** option contains a **proxy.url** parameter, with the **foreman_server_url** macro as its argument. This macro resolves to the full URL of Satellite Server.

For UEFI provisioning, the **PXEgrub2 global default** template in the **Hosts > Provisioning Templates** window contains the snippet **pxegrub2_discovery**:

```

menuentry 'Foreman Discovery Image' --id discovery {
  linuxefi boot/fdi-image/vmlinuz0 rootflags=loop root=live:/fdi.iso rootfstype=auto ro rd.live.image
acpi=force rd.luks=0 rd.md=0 rd.dm=0 rd.lvm=0 rd.bootif=0 rd.neednet=0 nomodeset proxy.url=<%=
foreman_server_url %> proxy.type=foreman BOOTIF=01-$mac
  initrdefi boot/fdi-image/initrd0.img
}

```

To use a Capsule to proxy the discovery steps, edit **/var/lib/tftpboot/pxelinux.cfg/default** or **/var/lib/tftpboot/grub2/grub.cfg** and change the URL to the FQDN of the Capsule Server you want to use.

The global template is available on Satellite Server and all Capsules that have the TFTP feature enabled.

6.4.3. Changing Templates and Snippets

To use a template, in the Satellite web UI, navigate to **Administer > Settings** and click the **Provisioning** tab and set the templates that you want to use.

Templates and snippets are locked to prevent changes. If you want to edit a template or snippet, clone it, save it with a unique name, and then edit the clone.

When you change the template or a snippet it includes, the changes must be propagated to Satellite Server's default PXE template. Navigate to **Hosts > Provisioning Templates** and click **Build PXE Default**. This refreshes the default PXE template on Satellite Server.

The proxy.url argument

During the Satellite installation process, if you use the default option **--enable-foreman-plugin-discovery**, you can edit the **proxy.url** argument in the template to set the URL of Capsule Server that provides the discovery service. You can change the **proxy.url** argument to the IP address or FQDN of another provisioning Capsule that you want to use, but ensure that you append the port number, for example, **9090**. If you use an alternative port number with the **--foreman-proxy-ssl-port** option during Satellite installation, you must add that port number. You can also edit the **proxy.url** argument to use a Satellite IP address or FQDN so that the discovered hosts communicate directly with Satellite Server.

The **proxy.type** argument

If you use a Capsule Server FQDN for the **proxy.url** argument, ensure that you set the **proxy.type** argument to **proxy**. If you use a Satellite FQDN, update the **proxy.type** argument to **foreman**.

```
proxy.url=https://capsule.example.com:9090 proxy.type=proxy
```

Rendering the Capsule's Host Name

Satellite 6 deploys the same template to all TFTP Capsules and there is no variable or macro available to render the Capsule's host name. The hard-coded **proxy.url** does not work with two or more TFTP Capsules. As a workaround, every time you click **Build PXE Defaults**, edit the configuration file in the TFTP directory using SSH.

Setting Discovery Service as Default

For both BIOS and UEFI, to set the Discovery service as the default service that boots for hosts that are not present in your current Satellite inventory, complete the following steps:

1. In the Satellite web UI, navigate to **Administer > Settings** and click the **Provisioning** tab.
2. For the **Default PXE global template entry**, in the **Value** column, enter **discovery**.

Tagged VLAN Provisioning

If you want to use tagged VLAN provisioning, and you want the discovery service to send a discovery request, add the following information to the **KERNEL** option in the discovery template:

```
fdi.vlan.primary=example_VLAN_ID
```

Testing

Test the Discovery service and boot a blank bare metal host on the 192.168.140.0/24 network. A boot menu has two options:

- **local**, which boots from the hard disk
- **discovery**, which boots to the Discovery service

Select **discovery** to boot the Discovery image. After a few minutes, the Discovery image completes booting and a status screen is displayed.

In the Satellite web UI, navigate to **Hosts > Discovered hosts** and view the newly discovered host. The discovered hosts automatically define their host name based on their MAC address. For example, Satellite sets a discovered host with a MAC address of ab:cd:ef:12:34:56 to have **macabcdef123456** as the host name. You can change this host name when provisioning the host.

6.4.4. Automatic Contexts for Discovered Hosts

Satellite Server assigns organization and location to discovered hosts according to the following sequence of rules:

1. If a discovered host uses a subnet defined in Satellite, the host uses the first organization and location associated with the subnet.
2. If the **discovery_organization** or **discovery_location** fact values are set, the discovered host uses these fact values as an organization and location. To set these fact values, navigate to **Administer > Settings > Discovered**, and add these facts to the **Default organization** and **Default location** fields. Ensure that the discovered host's subnet also belongs to the organization and location set by the fact, otherwise Satellite refuses to set it for security reasons.
3. If none of the previous conditions exists, Satellite assigns the first Organization and Location ordered by name.

You can change the organization or location using the bulk actions menu of the **Discovered hosts** page. Select the discovered hosts to modify and select **Assign Organization** or **Assign Location** from the **Select Action** menu.

Note that the **foreman_organization** and **foreman_location** facts are no longer valid values for assigning context for discovered hosts. You still can use these facts to configure the host for Puppet runs. To do this, navigate to **Administer > Settings > Puppet** section and add the **foreman_organization** and **foreman_location** facts to the **Default organization** and **Default location** fields.

6.5. CREATING HOSTS FROM DISCOVERED HOSTS

Provisioning discovered hosts follows a provisioning process that is similar to PXE provisioning. The main difference is that instead of manually entering the host's MAC address, you can select the host to provision from the list of discovered hosts.

Procedure

To create a host from a discovered host, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > Discovered host**. Select the host you want to use and click **Provision** to the right of the list.
2. Select from one of the two following options:
 - To provision a host from a host group, select a host group, organization, and location, and then click **Create Host**.
 - To provision a host with further customization, click **Customize Host** and enter the additional details you want to specify for the new host.
3. Verify that the fields are populated with values. Note in particular:
 - The **Name** from the **Host** tab becomes the **DNS name**.
 - Satellite Server automatically assigns an IP address for the new host.
 - Satellite Server automatically populates the MAC address from the Discovery results.
4. Ensure that Satellite Server automatically selects the **Managed**, **Primary**, and **Provision** options for the first interface on the host. If not, select them.

5. Click the **Operating System** tab, and verify that all fields contain values. Confirm each aspect of the operating system.
6. Click **Resolve** in **Provisioning template** to check the new host can identify the right provisioning templates to use.
For more information about associating provisioning templates, see [Section 3.7, "Creating Provisioning Templates"](#).
7. Click **Submit** to save the host details.

When the host provisioning is complete, the discovered host becomes a content host. To view the host, navigate to **Hosts > Content Hosts**.

For CLI Users

1. Identify the discovered host to use for provisioning:

```
# hammer discovery list
```

2. Select a host and provision it using a host group. Set a new host name with the **--new-name** option:

```
# hammer discovery provision --name "host_name" \
--new-name "new_host_name" --organization "My_Organization" \
--location "My_Location" --hostgroup "My_Host_Group" --build true \
--enabled true --managed true
```

This removes the host from the discovered host listing and creates a host entry with the provisioning settings. The Discovery image automatically resets the host so that it can boot to PXE. The host detects the DHCP service on Satellite Server's integrated Capsule and starts installing the operating system from its Kickstart tree. When the installation completes, the host also registers to Satellite Server using an activation key and installs the necessary configuration and management tools from the Red Hat Satellite Tools repository.

6.6. CREATING DISCOVERY RULES

As a method of automating the provisioning process for discovered hosts, Red Hat Satellite 6 provides a feature to create discovery rules. These rules define how discovered hosts automatically provision themselves, based on the assigned host group. For example, you can automatically provision hosts with a high CPU count as hypervisors. Likewise, you can provision hosts with large hard disks as storage servers.

NIC Considerations

Auto provisioning does not currently allow configuring NICs; all systems are being provisioned with the NIC configuration that was detected during discovery. However, you can set the NIC in an Anaconda kickstart, scriptlet, or using configuration management later on.

Procedure

To create a rule, complete the following steps:

1. In the Satellite web UI, navigate to **Configure > Discovery rules**. Select **Create Rule** and enter the following details:
2. In the **Name** field, enter a name for the rule.

3. In the **Search** field, enter the rules to determine whether to provision a host. This field provides suggestions for values you enter and allows operators for multiple rules. For example:
cpu_count > 8.
4. From the **Host Group** list, select the host group to use as a template for this host.
5. In the **Hostname** field, enter the pattern to determine host names for multiple hosts. This uses the same ERB syntax that provisioning templates use. The host name can use the **@host** attribute for host-specific values and the **rand** function for a random number.
 - **myhost-<%= rand(99999) %>**
 - **abc-<%= @host.facts['bios_vendor'] + '-' + rand(99999).to_s %>**
 - **xyz-<%= @host.hostgroup.name %>**
 - **srv-<%= @host.discovery_rule.name %>**
 - **server-<%= @host.ip.gsub(':', '-') + '-' + @host.hostgroup.subnet.name %>**
Because the **rand()** function returns an integer that cannot be concatenated with a string, use the **to_s** function to change the integer to a string. When creating host name patterns, ensure the resulting host names are unique, do not start with numbers, and do not contain underscores or dots. A good approach is to use unique information provided by Facter, such as the MAC address, BIOS, or serial ID.
6. In the **Hosts limit** field, enter the maximum hosts you can provision with the rule. Enter **0** for unlimited.
7. In the **Priority** field, enter a number to set the precedence the rule has over other rules. Rules with lower values have a higher priority.
8. From the **Enabled** list, select whether you want to enable the rule.
9. To set a different provisioning context for the rule, click the **Organizations** and **Locations** tabs and select the contexts you want to use.
10. Click **Submit** to save your rule.
11. Navigate to **Hosts > Discovered Host** and select one of the following two options:
 - From the **Discovered hosts** list on the right, select **Auto-Provision** to automatically provisions a single host.
 - On the upper right of the window, click **Auto-Provision All** to automatically provisions all hosts.

For CLI Users

Create the rule with the **hammer discovery_rule create** command:

```
# hammer discovery_rule create --name "Hypervisor" \
--search "cpu_count > 8" --hostgroup "My_Host_Group" \
--hostname "hypervisor-<%= rand(99999) %>" \
--hosts-limit 5 --priority 5 --enabled true
```

Automatically provision a host with the **hammer discovery auto-provision** command:

```
# hammer discovery auto-provision --name "macabcdef123456"
```

6.7. CREATING HOSTS WITH PXE-LESS PROVISIONING

Some hardware does not provide a PXE boot interface. Red Hat Satellite 6 provides a PXE-less discovery service that operates without PXE-based services, such as DHCP and TFTP. In Satellite, you can provision a host without PXE boot. This is also known as PXE-less provisioning and involves generating a boot ISO that hosts can use. Using this ISO, the host can connect to Satellite Server, boot the installation media, and install the operating system.

Boot ISO Types

There are four types of boot ISOs:

Host image - A boot ISO for the specific host. This image contains only the boot files that are necessary to access the installation media on Satellite Server. The user defines the subnet data in Satellite and the image is created with static networking.

Full host image - A boot ISO that contains the kernel and initial RAM disk image for the specific host. This image is useful if the host fails to chainload correctly. The provisioning template still downloads from Satellite Server.

Generic image - A boot ISO that is not associated with a specific host. The ISO sends the host's MAC address to Satellite Server, which matches it against the host entry. The image does not store IP address details, and requires access to a DHCP server on the network to bootstrap. This image is also available from the `/bootdisk/disks/generic` URL on your Satellite Server, for example, <https://satellite.example.com/bootdisk/disks/generic>.

Subnet image - A boot ISO that is similar to the generic image but is configured with the address of a Capsule Server. This image is generic to all hosts with a provisioning NIC on the same subnet.

Procedure

To create a host with PXE-less provisioning, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > Create Host**.
2. In the **Name** field, enter a name that you want to become the provisioned system's host name.
3. Click the **Organization** and **Location** tabs and change the context to match your requirements.
4. From the **Host Group** list, select a host group that you want to use to populate the form.
5. Click the **Interface** tab, and on the host's interface, click **Edit**.
6. Verify that the fields are populated with values. Note in particular:
 - The **Name** from the **Host** tab becomes the **DNS name**.
 - Satellite Server automatically assigns an IP address for the new host.
7. In the **MAC address** field, enter a MAC address for the host.
8. Ensure that Satellite Server automatically selects the **Managed**, **Primary**, and **Provision** options for the first interface on the host. If not, select them.

9. Click the **Operating System** tab, and verify that all fields contain values. Confirm each aspect of the operating system.
10. Click **Resolve** in **Provisioning template** to check the new host can identify the right provisioning templates to use.
For more information about associating provisioning templates, see [Section 3.7, "Creating Provisioning Templates"](#).
11. Click the **Parameters** tab, and ensure that a parameter exists that provides an activation key. If not, add an activation key.
12. Click **Submit** to save the host details.

This creates a host entry and the host details page appears.

The options on the upper-right of the window are the **Boot disk** menu. From this menu, one of the following images is available for download: **Host image**, **Full host image**, **Generic image**, and **Subnet image**.



NOTE

The **Full host image** is based on SYSLINUX and works with most hardware. When using a **Host image**, **Generic image**, or **Subnet image**, see http://ipxe.org/appnote/hardware_drivers for a list of hardware drivers expected to work with an iPXE-based boot disk.

For CLI Users

Create the host with the **hammer host create** command.

```
# hammer host create --name "My_Bare_Metal" --organization "My_Organization" \
--location "My_Location" --hostgroup "My_Host_Group" --mac "aa:aa:aa:aa:aa:aa" \
--build true --enabled true --managed true
```

Ensure that your network interface options are set using the **hammer host interface update** command.

```
# hammer host interface update --host "test3" --managed true \
--primary true --provision true
```

Download the boot disk from Satellite Server with the **hammer bootdisk host** command:

- For **Host image**:

```
# hammer bootdisk host --host test3.example.com
```

- For **Full host image**:

```
# hammer bootdisk host --host test3.example.com --full true
```

- For **Generic image**:

```
# hammer bootdisk generic
```

- For **Subnet image**:

```
# hammer bootdisk subnet --subnet subnetName
```

This creates a boot ISO for your host to use.


Write the ISO to a USB storage device using the **dd** utility or **livecd-tools** if required.

When you start the physical host and boot from the ISO or the USB storage device, the host connects to Satellite Server and starts installing operating system from its kickstart tree.

When the installation completes, the host also registers to Satellite Server using the activation key and installs the necessary configuration and management tools from the **Red Hat Satellite Tools** repository.

6.8. IMPLEMENTING PXE-LESS DISCOVERY

Red Hat Satellite 6 provides a PXE-less Discovery service that operates without the need for PXE-based services (DHCP and TFTP). You accomplish this using Satellite Server's Discovery image.



If you have not yet installed the Discovery service or image, follow the *"Installation"* section in [Section 6.4, "Configuring Red Hat Satellite's Discovery Service"](#).

The ISO for the Discovery service resides at **/usr/share/foreman-discovery-image/** and is installed using the **foreman-discovery-image** package.

Attended Use

This ISO acts as bootable media. Copy this media to either a CD, DVD, or a USB stick. For example, to copy to a USB stick at **/dev/sdb**:

```
# dd bs=4M \
if=/usr/share/foreman-discovery-image/foreman-discovery-image-3.4.4-5.iso \
of=/dev/sdb
```

Insert the Discovery boot media into a bare metal host, start the host, and boot from the media. The Discovery Image displays an option for either **Manual network setup** or **Discovery with DHCP**:

- If selecting **Manual network setup**, the Discovery image requests a set of network options. This includes the primary network interface that connects to Satellite Server. This Discovery image also asks for network interface configuration options, such as an **IPv4 Address**, **IPv4 Gateway**, and an **IPv4 DNS** server. After entering these details, select **Next**.
- If selecting **Discovery with DHCP**, the Discovery image requests only the primary network interface that connects to Satellite Server. It attempts to automatically configure the network interface using a DHCP server, such as one that a Capsule Server provides.

After the primary interface configuration, the Discovery image requests the **Server URL**, which is the URL of Satellite Server or Capsule Server offering the Discovery service. For example, to use the integrated Capsule on Satellite Server, use the following URL:

<https://satellite.example.com:9090>

Set the **Connection type** to **Proxy**, then select **Next**.

The Discovery image also provides a set of fields to input **Custom facts** for the Facter tool to relay back to Satellite Server. These are entered in a **name-value** format. Provide any custom facts you require and select **Confirm** to continue.

The Satellite reports a successful communication with Satellite Server's Discovery service. Navigate to **Hosts > Discovered Hosts** and view the newly discovered host.

For more information about provisioning discovered hosts, see [Section 6.5, "Creating Hosts from Discovered Hosts"](#).

Unattended Use and Customization

It is possible to create a customized Discovery ISO, which automates the process of configuring the image after booting. The Discovery image uses a Linux kernel for the operating system, which means you pass kernel parameters to the configure the image's operating system. These kernel parameters include:

proxy.url

The URL of the Capsule Server providing the Discovery service.

proxy.type

The proxy type. This is usually set to **proxy** to connect to Capsule Server. This parameter also supports a legacy **foreman** option, where communication goes directly to Satellite Server instead of a Capsule Server.

fdi.pxmac

The MAC address of the primary interface in the format of **AA:BB:CC:DD:EE:FF**. This is the interface you aim to use for communicating with Capsule Server. In automated mode, the first NIC (using network identifiers in alphabetical order) with a link is used. In semi-automated mode, a screen appears and requests you to select the correct interface.

fdi.pxip, fdi.pxgw, fdi.pxdns

Manually configures IP address (**fdi.pxip**), the gateway (**fdi.pxgw**), and the DNS (**fdi.pxdns**) for the primary network interface. If you omit these parameters, the image uses DHCP to configure the network interface.

fdi.pxfactname1, fdi.pxfactname2 ... fdi.pxfactnameN

Allows you to specify custom fact names.

fdi.pxfactvalue1, fdi.pxfactvalue2 ... fdi.pxfactvalueN

The values for each custom fact. Each value corresponds to a fact name. For example,

fdi.pxfactvalue1 sets the value for the fact named with **fdi.pxfactname1**.

fdi.pxauto

To set automatic or semi-automatic mode. If set to 0, the image uses semi-automatic mode, which allows you to confirm your choices through a set of dialog options. If set to 1, the image uses automatic mode and proceeds without any confirmation.

Satellite Server also provides a tool (**discovery-remaster**) in the **foreman-discovery-image** package. This tool remasters the image to include these kernel parameters. To remaster the image, run the **discovery-remaster** tool. For example:

```
# discovery-remaster ~/iso/foreman-discovery-image-3.4.4-5.iso \
"fdi.pxip=192.168.140.20/24 fdi.pxgw=192.168.140.1 \
fdi.pxdns=192.168.140.2 proxy.url=https://satellite.example.com:9090 \
proxy.type=proxy fdi.pxfactname1=customhostname \
fdi.pxfactvalue1=myhost fdi.pxmac=52:54:00:be:8e:8c fdi.pxauto=1"
```

The tool creates a new ISO file in the same directory as the original discovery image. In this scenario, it saves in the **/usr/share/foreman-discovery-image/** directory.

Copy this media to either a CD, DVD, or a USB stick. For example, to copy to a USB stick at **/dev/sdb**:

```
# dd bs=4M \
if=/usr/share/foreman-discovery-image/foreman-discovery-image-3.4.4-5.iso \
of=/dev/sdb
```

Insert the Discovery boot media into a bare metal host, start the host, and boot from the media.

For more information about provisioning discovered hosts, see [Section 6.5, "Creating Hosts from Discovered Hosts"](#).

Final Notes

The host needs to resolve to the following provisioning templates:

- **kexec Template: Discovery Red Hat kexec**
- **provision Template: Satellite Kickstart Default**

For more information about associating provisioning templates, see [Section 3.7, "Creating Provisioning Templates"](#).

6.9. DEPLOYING SSH KEYS DURING PROVISIONING

Use this procedure to deploy SSH keys added to a user during provisioning. For information on adding SSH keys to a user, see [Adding SSH Keys to a User](#) in *Administering Red Hat Satellite*.

Procedure

To deploy SSH keys during provisioning, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts** > **Provisioning Templates**.
2. Create a provisioning template, or clone and edit an existing template. For more information, see [Section 3.7, "Creating Provisioning Templates"](#).
3. In the template, click the **Template** tab.
4. In the **Template editor** field, add the **create_users** snippet to the **%post** section:

```
<%= snippet('create_users') %>
```

5. Select the **Default** check box.
6. Click the **Association** tab.
7. From the **Application Operating Systems** list, select an operating system.
8. Click **Submit** to save the provisioning template.
9. Create a host that is associated with the provisioning template or rebuild a host using the OS associated with the modified template. For more information, see [Creating a Host in Red Hat Satellite](#) in the *Managing Hosts* guide.
The SSH keys of the **Owned by** user are added automatically when the **create_users** snippet is executed during the provisioning process. You can set **Owned by** to an individual user or a user group. If you set **Owned by** to a user group, the SSH keys of all users in the user group are added automatically.

6.10. BUILDING A SATELLITE DISCOVERY IMAGE

Use this procedure to build a Satellite discovery image or rebuild an image if you change configuration files.

Do not use this procedure on your production Satellite or Capsule.

Prerequisites

Install the **livecd-tools** package:

```
# yum install livecd-tools
```

Because Anaconda installer cannot publish through HTTPS, you must enable publishing through HTTP for Kickstart repositories:

1. In the Satellite web UI, navigate to **Content** > **Products** and in the **Products** window, click the **Repositories** tab.
2. Select a Kickstart repository and for the **Publish via HTTP**, option, click the **Edit** icon, select the check box, and click **Save**.
3. Repeat the previous steps for the Satellite repository.

Note that publishing via HTTP does not apply to any Red Hat repositories.

Procedure

To build the Satellite discovery image, complete the following steps:

1. Open the `/usr/share/foreman-discovery-image/foreman-discovery-image.ks` file for editing:

```
# vim /usr/share/foreman-discovery-image/foreman-discovery-image.ks
```

2. Replace `repo --name=rhel --baseurl=http://download/00000` with with your own repos for RHEL and Satellite with your repository URLs. To find the URLs, navigate to **Content > Products** and click the **Repositories** tab and copy the URL for both repositories into the file:

```
repo --name=rhel --baseurl=http://download/released/RHEL-7/7.4/Server/x86_64/os/
repo --name=sat --baseurl=http://download2/nightly/Satellite/6.6/candidate/latest-Satellite-6.6-RHEL-7/compose/Satellite/x86_64/os/
```

3. Run the **livecd-creator** tool:

```
# livecd-creator --title="Discovery-Image" \
--compression-type=xz \
--cache=var/cache/build-fdi \
--config /usr/share/foreman-discovery-image/foreman-discovery-image.ks \
--fslabel fdi \
--tmpdir /var/tmp
```

If you change **fdi** in the `--fslabel` option, you must also change the root label on the kernel command line when loading the image. **fdi** or the alternative name is appended to the **.iso** file that is created as part of this procedure. The PXE Discovery tool uses this name when converting from **.iso** to PXE.

Use `/var/tmp` because this process requires close to 3GB of space and `/tmp` might have problems if the system is low on swap space.

4. Verify that your **fdi.iso** file is created:

```
# ls *.iso -h
```

When you create the **.iso** file, you can boot the **.iso** file over a network or locally. Complete one of the following procedures.

To boot the iso file over a network:

1. To extract the initial ramdisk and kernel files from the **.iso** file over a network, enter the following command:

```
# discovery-iso-to-pxe fdi.iso
```

2. Create a directory to store your boot files:

```
# mkdir /var/lib/tftpboot/boot/myimage
```

3. Copy the **initrd0.img** and **vmlinuz0** files to your new directory.

4. Edit the **KERNEL** and **APPEND** entries in the `/var/lib/tftpboot/pxelinux.cfg` file to add the information about your own initial ramdisk and kernel files.

To boot the iso file locally:

If you want to create a hybrid **.iso** file for booting locally, complete the following steps:

1. To convert the **.iso** file to an **.iso** hybrid file for PXE provisioning, enter the following command:

```
# isohybrid --partok fdi.iso
```

If you have **grub2** packages installed, you can also use the following command to install a **grub2** bootloader:

```
# isohybrid --partok --uefi fdi.iso
```

2. To add **md5** checksum to the **.iso** file so it can pass installation media validation tests in Satellite, enter the following command:

```
# implantisomd5 fdi.iso
```

CHAPTER 7. PROVISIONING VIRTUAL MACHINES ON A KVM SERVER (LIBVIRT)

Kernel-based Virtual Machines (KVMs) use an open source virtualization daemon and API called **libvirt** running on Red Hat Enterprise Linux. Red Hat Satellite 6 can connect to the **libvirt** API on a KVM server, provision hosts on the hypervisor, and control certain virtualization functions.

7.1. PREREQUISITES FOR KVM PROVISIONING

The requirements for KVM provisioning include:

- Synchronized content repositories for the version of Red Hat Enterprise Linux that you want to use. For more information, see [Synchronizing Red Hat Repositories](#) in the *Content Management Guide*.
- A Capsule Server managing a network on the KVM server. Ensure no other DHCP services run on this network to avoid conflicts with the Capsule Server. For more information about network service configuration for Capsule Servers, see [Chapter 4, Configuring Networking](#).
- An activation key for host registration. For more information, see [Creating An Activation Key](#) in the *Content Management* guide.
- A Red Hat Enterprise Linux server running KVM virtualization tools. For more information, see the [Red Hat Enterprise Linux 7 Virtualization Getting Started Guide](#).
- An existing virtual machine image if you want to use image-based provisioning. Ensure that this image exists in a storage pool on the KVM host. The **default** storage pool is usually located in **/var/lib/libvirt/images**. Only directory pool storage types can be managed through Satellite.

User Roles and Permissions to Provision Libvirt Compute Resources

To provision a Libvirt host in Satellite, you must have a user account with the following roles:

- **Edit hosts**
- **View hosts**

For more information, see [Assigning Roles to a User](#) in the *Administering Red Hat Satellite* guide.

You must also create a custom role with the following permissions:

- **view_compute_resources**
- **destroy_compute_resources_vms**
- **power_compute_resources_vms**
- **create_compute_resources_vms**
- **view_compute_resources_vms**
- **view_locations**
- **view_subnets**

For more information about creating roles, see [Creating a Role](#). For more information about adding permissions to a role, see [Adding Permissions to a Role](#) in the *Administering Red Hat Satellite* guide.

7.2. CONFIGURING SATELLITE SERVER FOR KVM CONNECTIONS

Before adding the KVM connection, Satellite Server requires some configuration to ensure a secure connection. This means creating an SSH key pair for the user that performs the connection, which is the **foreman** user.

Non-root users

These examples use the root user for KVM. However, if you want to use a non-root user on the KVM server, add the user to the **libvirt** group on the KVM server:

```
useradd -G libvirt non_root_user
```

Procedure

To configure Satellite Server for KVM connections, complete the following steps:

1. On Satellite Server, switch to the **foreman** user:

```
# su foreman -s /bin/bash
```

2. Generate the key pair:

```
$ ssh-keygen
```

3. Copy the public key to the KVM server:

```
$ ssh-copy-id root@kvm.example.com
```

4. Exit the bash shell for the **foreman** user:

```
$ exit
```

5. Install the **libvirt-client** package:

```
# satellite-maintain packages install libvirt-client
```

6. Use the following command to test the connection to the KVM server:

```
# su foreman -s /bin/bash -c 'virsh -c qemu+ssh://root@kvm.example.com/system list'
```

When you add the KVM connection in Satellite Server, use the **qemu+ssh** protocol and the address to the server. For example:

```
qemu+ssh://root@kvm.example.com/system
```

7.3. ADDING A KVM CONNECTION TO SATELLITE SERVER

Use this procedure to add a KVM connection to Satellite Server's compute resources.

Procedure

To add a KVM connection to Satellite, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources**, and in the Compute Resources window, click **Create Compute Resource**
2. In the **Name** field, enter a name for the new compute resource.
3. From the **Provider** list, select **Libvirt**
4. In the **Description** field, enter a description for the compute resource.
5. In the **URL** field, enter the connection URL to the KVM server. For example:

```
qemu+ssh://root@kvm.example.com/system
```

6. From the **Display type** list, select either **VNC** or **Spice**.
7. Optional: To secure console access for new hosts with a randomly generated password, select the **Set a randomly generated password on the display connection** check box. You can retrieve the password for the VNC console to access guest virtual machine console from the output of the following command executed on the KVM server:

```
# virsh edit your_VM_name
<graphics type='vnc' port='-1' autoport='yes' listen='0.0.0.0'
passwd='your_randomly_generated_password'>
```

The password is randomly generated every time the console for the virtual machine is opened, for example, with virt-manager.

8. Click **Test Connection** to ensure that Satellite Server connects to the KVM server without fault.
9. Verify that the **Locations** and **Organizations** tabs are automatically set to your current context. If you want, add additional contexts to these tabs.
10. Click **Submit** to save the KVM connection.

For CLI Users

Create the connection with the **hammer compute-resource create** command:

```
# hammer compute-resource create --name "My_KVM_Server" \
--provider "Libvirt" --description "KVM server at kvm.example.com" \
--url "qemu+ssh://root@kvm.example.com/system" --locations "New York" \
--organizations "My_Organization"
```

7.4. ADDING KVM IMAGES TO SATELLITE SERVER

You must add information about the image to your Satellite Server. This includes access details and the image location.

Supported Storage Types

Note that you can manage only directory pool storage types through Satellite.

Procedure

To add KVM images on Satellite Server, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources**, and in the Compute Resources window, click the name of your KVM connection.
2. Click the **Image** tab, and then click **Create Image**.
3. In the **Name** field, enter a name for the image.
4. From the **Operatingssystem** list, select the image's base operating system.
5. From the **Architecture** list, select the operating system architecture.
6. In the **Username** field, enter the SSH user name for image access. This is normally the **root** user.
7. In the **Password** field, enter the SSH password for image access.
8. From the **User data** list, select if you want images to support user data input, such as **cloud-init** data.
9. In the **Image path** field, enter the full path that points to the image on the KVM server. For example:

```
/var/lib/libvirt/images/TestImage.qcow2
```

10. Click **Submit** to save the image details.

For CLI Users

Create the image with the **hammer compute-resource image create** command. Use the **--uuid** field to store the full path of the image location on the KVM server.

```
# hammer compute-resource image create --name "Test KVM Image" \
--operatingsystem "RedHat version" --architecture "x86_64" --username root \
--user-data false --uuid "/var/lib/libvirt/images/TestImage.qcow2" \
--compute-resource "My_KVM_Server"
```

7.5. ADDING KVM DETAILS TO A COMPUTE PROFILE

We can predefine certain hardware settings for KVM-based virtual machines by adding these hardware settings to a compute profile.

Procedure

To add KVM details to a compute profile, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Profiles**.
2. In the Compute Profiles window, click the name of an existing compute resource or click **Create Compute Profile** and select a compute resource to use to create a compute profile.
3. In the **CPUs** field, enter the number of CPUs to allocate to the new host.
4. In the **Memory** field, enter the amount of memory to allocate to the new host.

5. From the **Image** list, select the image to use if performing image-based provisioning.
6. From the **Network Interfaces** list, select the network parameters for the host's network interface. You can create multiple network interfaces. However, at least one interface must point to a Capsule-managed network.
7. In the **Storage** area, enter the storage parameters for the host. You can create multiple volumes for the host.
8. Click **Submit** to save the settings to the compute profile.

For CLI Users

The compute profile CLI commands are not yet implemented in Red Hat Satellite 6.6. As an alternative, you can include the same settings directly during the host creation process.

7.6. CREATING HOSTS ON A KVM SERVER

In Satellite, you can use KVM provisioning to create hosts over a network connection and from an existing image.

If you create a host with an existing image, the new host entry triggers the KVM server to create the virtual machine, using the pre-existing image as a basis for the new volume.

If you want to create a host over a network connection, the new host must have access either to Satellite Server's integrated Capsule or an external Capsule Server on a KVM virtual network, so that the host has access to PXE provisioning services. This new host entry triggers the KVM server to create and start a virtual machine. If the virtual machine detects the defined Capsule Server through the virtual network, the virtual machine boots to PXE and begins to install the chosen operating system.

DHCP Conflicts

For network-based provisioning, if you use a virtual network on the KVM server for provisioning, select a network that does not provide DHCP assignments. This causes DHCP conflicts with Satellite Server when booting new hosts.

Procedure

To create a KVM host, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > Create Host**.
2. In the **Name** field, enter the name that you want to become the provisioned system's host name.
3. Click the **Organization** and **Location** tabs to ensure that the provisioning context is automatically set to the current context.
4. From the **Host Group** list, select the host group that you want to use to populate the form.
5. From the **Deploy on** list, select the KVM connection.
6. From the **Compute Profile** list, select a profile to use to automatically populate virtual machine-based settings.
7. Click the **Interface** tab and click **Edit** on the host's interface.
8. Verify that the fields are automatically populated with values. Note in particular:
 - The **Name** from the **Host** tab becomes the **DNS name**

- The **name** from the **host** tab becomes the **DNS name**.
 - Satellite Server automatically assigns an IP address for the new host.
9. Ensure that the **MAC address** field is blank. The KVM server assigns one to the host.
 10. Verify that the **Managed**, **Primary**, and **Provision** options are automatically selected for the first interface on the host. If not, select them.
 11. In the interface window, review the KVM-specific fields that are populated with settings from your compute profile. Modify these settings to suit your needs.
 12. Click the **Operating System** tab, and confirm that all fields automatically contain values.
 13. For network-based provisioning, ensure that the **Provisioning Method** is set to **Network Based**. For image-based provisioning, ensure that the **Provisioning Method** is set to **Image Based**.
 14. Click **Resolve** in **Provisioning templates** to check the new host can identify the right provisioning templates to use.
 15. Click the **Virtual Machine** tab and confirm that these settings are populated with details from the host group and compute profile. Modify these settings to suit your needs.
 16. Click the **Parameters** tab and ensure that a parameter exists that provides an activation key. If not, add an activation key.
 17. Click **Submit** to save the host entry.

For CLI Users

Create the host with the **hammer host create** command and include **--provision-method build** to use network-based provisioning.

```
# hammer host create --name "kvm-test1" --organization "My_Organization" \
--location "New York" --hostgroup "Base" \
--compute-resource "My_KVM_Server" --provision-method build \
--build true --enabled true --managed true \
--interface
"managed=true,primary=true,provision=true,compute_type=network,compute_network=exemplenetw
ork" \
--compute-attributes="cpus=1,memory=1073741824" \
--volume="pool_name=default,capacity=20G,format_type=qcow2" \
--root-password "password"
```

Create the host with the **hammer host create** command and include **--provision-method image** to use image-based provisioning.

```
# hammer host create --name "kvm-test2" --organization "My_Organization" \
--location "New York" --hostgroup "Base" \
--compute-resource "My_KVM_Server" --provision-method image \
--image "Test KVM Image" --enabled true --managed true \
--interface
"managed=true,primary=true,provision=true,compute_type=network,compute_network=exemplenetwor
k" \
--compute-attributes="cpus=1,memory=1073741824" \
--volume="pool_name=default,capacity=20G,format_type=qcow2"
```

For more information about additional host creation parameters for this compute resource, see [Appendix B, *Additional Host Parameters for Hammer CLI*](#).

CHAPTER 8. PROVISIONING VIRTUAL MACHINES IN RED HAT VIRTUALIZATION

Red Hat Virtualization (version 4.0 and later) or Red Hat Enterprise Virtualization (version 3.6 and earlier) is an enterprise-grade server and desktop virtualization platform built on Red Hat Enterprise Linux.

With Red Hat Satellite 6, you can manage virtualization functions through Red Hat Virtualization's REST API version 3. REST API version 4 is not yet supported by Satellite 6. This includes creating virtual machines and controlling their power states.

Use the following procedures to add a connection to a Red Hat Virtualization environment and provision a virtual machine.

8.1. PREREQUISITES FOR RED HAT VIRTUALIZATION PROVISIONING

The requirements for Red Hat Virtualization provisioning include:

- Synchronized content repositories for the version of Red Hat Enterprise Linux that you want to use. For more information, see [Synchronizing Red Hat Repositories](#) in the *Content Management Guide*.
- A Capsule Server managing a logical network on the Red Hat Virtualization environment. Ensure no other DHCP services run on this network to avoid conflicts with the Capsule Server. For more information, see [Chapter 4, Configuring Networking](#).
- An existing template, other than the **blank** template, if you want to use image-based provisioning. For more information about creating templates for virtual machines, see [Templates](#) in the *Virtual Machine Management Guide*.
- An activation key for host registration. For more information, see [Creating An Activation Key](#) in the *Content Management* guide.

8.2. CREATING A RED HAT VIRTUALIZATION USER

The Red Hat Virtualization server requires an administration-like user for Satellite Server communication. For security reasons, Red Hat advises against using the **admin@internal** user for such communication. Instead, create a new Red Hat Virtualization user with the following permissions:

- System
 - Configure System
 - Login Permissions
- Network
 - Configure vNIC Profile
 - Create
 - Edit Properties
 - Delete
 - Assign vNIC Profile to VM

- Assign vNIC Profile to Template
- Template
 - Provisioning Operations
 - Import/Export
- VM
 - Provisioning Operations
 - Create
 - Delete
 - Import/Export
 - Edit Storage
- Disk
 - Provisioning Operations
 - Create
 - Disk Profile
 - Attach Disk Profile

For more information about how to create a user and add permissions in Red Hat Virtualization, see [Administering User Tasks From the Administration Portal](#) in the *Red Hat Virtualization Administration Guide*.

8.3. ADDING A RED HAT VIRTUALIZATION CONNECTION TO SATELLITE SERVER

Use this procedure to add a Red Hat Virtualization connection to Satellite Server's compute resources.

Procedure

To add a Red Hat Virtualization connection to Satellite, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources**, and in the Compute Resources window, click **Create Compute Resource**.
2. In the **Name** field, enter a name for the new compute resource.
3. From the **Provider** list, select **RHV**.
4. In the **Description** field, enter a description for the compute resource.
5. In the **URL** field, enter the connection URL for the Red Hat Virtualization Manager's API. For example, in RHEV 3.6 and earlier, the URL is of the following form: <https://rhvm.example.com/ovirt-engine/api>. In RHV 4.0 and later, the URL is of the following form: <https://rhvm.example.com/ovirt-engine/api/v3>.
6. Optionally, select the **Use APIv4 (experimental)** check box to evaluate the new engine API.

**WARNING**

The items listed in this step are provided as Technology Previews. For further information about the scope of Technology Preview status, and associated support implications, see [Technology Preview Features Support Scope](#).

7. In the **User** field, enter the name of a user with permissions to access Red Hat Virtualization Manager's resources.
8. In the **Password** field, enter the password of the user.
9. Click **Load Datacenters** to populate the **Datacenter** list with data centers from your Red Hat Virtualization environment.
10. From the **Datacenter** list, select a data center.
11. From the **Quota ID** list, select a quota to limit resources available to Satellite.
12. In the **X509 Certification Authorities** field, enter the certificate authority for SSL/TLS access. Alternatively, if you leave the field blank, a self-signed certificate is generated on the first API request by the server.
13. Click the **Locations** tab and select the location you want to use.
14. Click the **Organizations** tab and select the organization you want to use.
15. Click **Submit** to save the compute resource.

For CLI Users

To create a Red Hat Virtualization connection, enter the **hammer compute-resource create** command with **Ovirt** for **--provider** and the name of the data center you want to use for **--datacenter**.

```
# hammer compute-resource create \
--name "My_RHV" --provider "Ovirt" \
--description "RHV server at rhvm.example.com" \
--url "https://rhvm.example.com/ovirt-engine/api" \
--use-v4 "false" --user "Satellite_User" \
--password "My_Password" \
--locations "New York" --organizations "My_Organization" \
--datacenter "My_Datacenter"
```

Optionally, to evaluate the new engine API, change **false** to **true** for the **--use-v4** option.

**WARNING**

The items listed in this step are provided as Technology Previews. For further information about the scope of Technology Preview status, and associated support implications, see [Technology Preview Features Support Scope](#).

8.4. ADDING RED HAT VIRTUALIZATION IMAGES TO SATELLITE SERVER

Red Hat Virtualization uses templates as images for creating virtual machines. If you use image-based provisioning to create hosts, you must add Red Hat Virtualization template details to your Satellite Server. This includes access details and the template name.

Procedure

To add Red Hat Virtualization images on Satellite Server, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources**, and in the Compute Resources window, click the name of your Red Hat Virtualization connection.
2. Click the **Image** tab, and then click **New Image**.
3. In the **Name** field, enter a name for the image.
4. From the **OperatingSystem** list, select the image's base operating system.
5. From the **Architecture** list, select the operating system architecture.
6. In the **Username** field, enter the SSH user name for image access. This is normally the **root** user.
7. In the **Password** field, enter the SSH password for image access.
8. From the **Image** list, select the name of the image on Red Hat Virtualization.
9. Click **Submit** to save the image details.

For CLI Users

Create the image with the **hammer compute-resource image create** command. Use the **--uuid** option to store the template UUID on the Red Hat Virtualization server.

```
# hammer compute-resource image create --name "Test_RHV_Image" \
--operatingsystem "RedHat 7.2" --architecture "x86_64" --username root \
--uuid "9788910c-4030-4ae0-bad7-603375dd72b1" \
--compute-resource "My_RHV"
```

8.5. ADDING RED HAT VIRTUALIZATION DETAILS TO A COMPUTE PROFILE

You can predefine certain hardware settings for virtual machines on Red Hat Virtualization. You achieve this through adding these hardware settings to a compute profile.

Procedure

To add Red Hat Virtualization details to a compute profile, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Profiles** and in the Compute Profiles window, click the name of the Red Hat Virtualization connection.
2. From the **Cluster** list, select the target host cluster in the Red Hat Virtualization environment.
3. From the **Template** list, select the RHV template to use for the **Cores** and **Memory** settings.
4. In the **Cores** field, enter the number of CPU cores to allocate to the new host.
5. In the **Memory** field, enter the amount of memory to allocate to the new host.
6. From the **Image** list, select image to use for image-based provisioning.
7. In the **Network Interfaces** area, enter the network parameters for the host's network interface. You can create multiple network interfaces. However, at least one interface must point to a Capsule-managed network. For each network interface, enter the following details:
 - a. In the **Name** field, enter the name of the network interface.
 - b. From the **Network** list, select The logical network that you want to use.
8. In the **Storage** area, enter the storage parameters for the host. You can create multiple volumes for the host. For each volume, enter the following details:
 - a. In the **Size (GB)** enter the size, in GB, for the new volume.
 - b. From the **Storage domain** list, select the storage domain for the volume.
 - c. From the **Preallocate disk**, select either thin provisioning or preallocation of the full disk.
 - d. From the **Bootable** list, select whether you want a bootable or non bootable volume.
9. Click **Submit** to save the compute profile.

For CLI Users

The compute profile CLI commands are not yet implemented in Red Hat Satellite 6.6. As an alternative, you can include the same settings directly during the host creation process.

8.6. CREATING NETWORK-BASED HOSTS ON A RED HAT VIRTUALIZATION SERVER

In Satellite, you can create Red Hat Virtualization hosts over a network connection or from an existing image.

To create a host over a network, the new host must have access to either Satellite Server's integrated Capsule or an external Capsule Server on a Red Hat Virtualization virtual network, so that the host has access to PXE provisioning services. The new host entry triggers the Red Hat Virtualization server to create the virtual machine. If the virtual machine detects the defined Capsule Server through the virtual network, the virtual machine boots to PXE and begins to install the chosen operating system.

DHCP conflicts

If you use a virtual network on the Red Hat Virtualization server for provisioning, ensure to select one that does not provide DHCP assignments. This causes DHCP conflicts with Satellite Server when booting new hosts.

When you create a host with an existing image, the new host entry triggers the Red Hat Virtualization server to create the virtual machine, using the pre-existing image as a basis for the new volume.

Procedure

To create a host for Red Hat Virtualization Server, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > New Host**.
2. In the **Name** field, enter the name that you want to become the provisioned system's host name.
3. Click the **Organization** and **Location** tabs to ensure that the provisioning context is automatically set to the current context.
4. From the **Host Group** list, select the host group that you want to use to populate the form.
5. From the **Deploy on** list, select the Red Hat Virtualization connection.
6. From the **Compute Profile** list, select a profile to use to automatically populate virtual machine-based settings.
7. Click the **Interface** tab and click **Edit** on the host's interface.
8. Verify that the fields are automatically populated with values. Note in particular:
 - The **Name** from the **Host** tab becomes the **DNS name**.
 - Satellite Server automatically assigns an IP address for the new host.
9. Ensure that the **MAC address** field is blank. The Red Hat Virtualization server assigns one to the host.
10. Verify that the **Managed**, **Primary**, and **Provision** options are automatically selected for the first interface on the host. If not, select them.
11. In the interface window, ensure that the Red Hat Virtualization-specific fields are populated with settings from the compute profile. Modify these settings to suit your needs.
12. Click the **Operating System** tab, and confirm that all fields automatically contain values.
13. For network-based provisioning, ensure that the **Provisioning Method** is set to **Network Based**. For image-based provisioning, ensure that the **Provisioning Method** is set to **Image Based**.
14. Click **Resolve** in **Provisioning templates** to check the new host can identify the right provisioning templates to use.
15. Click the **Virtual Machine** tab and confirm that these settings are populated with details from the host group and compute profile. Modify these settings to suit your needs.
16. Click the **Parameters** tab and ensure that a parameter exists that provides an activation key. If not, add an activation key.
17. Click **Submit** to save the host entry.

For CLI Users

To create a host with network-based provisioning, use the **hammer host create** command and include **-provision-method build**.

```
# hammer host create --name "rhv-test1" --organization "My_Organization" \
--location "New York" --hostgroup "Base" \
--compute-resource "My_RHV" --provision-method build \
--build true --enabled true --managed true \
--interface
"managed=true,primary=true,provision=true,compute_name=eth0,compute_network=satnetwork" \
--compute-attributes="cluster=Default,cores=1,memory=1073741824,start=true" \
--volume="size_gb=20G,storage_domain=Data,bootable=true"
```

To create a host with image-based provisioning, use the **hammer host create** command and include **--provision-method image**.

```
# hammer host create --name "rhv-test2" --organization "My_Organization" \
--location "New York" --hostgroup "Base" \
--compute-resource "My_RHV" --provision-method image \
--image "Test_RHV_Image" --enabled true --managed true \
--interface
"managed=true,primary=true,provision=true,compute_name=eth0,compute_network=satnetwork" \
--compute-attributes="cluster=Default,cores=1,memory=1073741824,start=true" \
--volume="size_gb=20G,storage_domain=Data,bootable=true"
```

For more information about additional host creation parameters for this compute resource, see [Appendix B, Additional Host Parameters for Hammer CLI](#).

CHAPTER 9. PROVISIONING VIRTUAL MACHINES IN VMWARE VSPHERE

VMware vSphere is an enterprise-level virtualization platform from VMware. Red Hat Satellite 6 can interact with the vSphere platform, including creating new virtual machines and controlling their power management states.

To provision VMware virtual machines using **cloud-init** and **userdata** templates, see [Section 9.7, “Using the VMware vSphere cloud-init and userdata Templates for Provisioning”](#).

9.1. PREREQUISITES FOR VMWARE VSPHERE PROVISIONING

The requirements for VMware vSphere provisioning include:

- Synchronized content repositories for the version of Red Hat Enterprise Linux that you want to use. For more information, see [Synchronizing Red Hat Repositories](#) in the *Content Management Guide*.
- A Capsule Server managing a network on the vSphere environment. Ensure no other DHCP services run on this network to avoid conflicts with the Capsule Server. For more information, see [Chapter 4, Configuring Networking](#).
- An existing VMware template if you want to use image-based provisioning. To associate VMware templates with the operating system, see [Section 3.1, “Creating Operating Systems”](#).

To associate the operating system with the template, see [Section 3.7, “Creating Provisioning Templates”](#).

- An activation key for host registration. For more information, see [Creating An Activation Key](#) in the *Content Management* guide.

If you want to create a host group to reduce the time you spend inputting information for host creation, see [Creating a Host Group](#) in the *Managing Hosts* guide.

9.2. CREATING A VMWARE VSPHERE USER

The VMware vSphere server requires an administration-like user for Satellite Server communication. For security reasons, do not use the **administrator** user for such communication. Instead, create a user with the following permissions:

For VMware vCenter Server version 6.7, set the following permissions:

- All Privileges → Datastore → Allocate Space, Browse datastore, Update Virtual Machine files, Low level file operations
- All Privileges → Network → Assign Network
- All Privileges → Resource → Assign virtual machine to resource pool
- All Privileges → Virtual Machine → Change Config (All)
- All Privileges → Virtual Machine → Interaction (All)
- All Privileges → Virtual Machine → Edit Inventory (All)

- All Privileges → Virtual Machine → Provisioning (All)

For VMware vCenter Server version 6.5, set the following permissions:

- All Privileges → Datastore → Allocate Space, Browse datastore, Update Virtual Machine files, Low level file operations
- All Privileges → Network → Assign Network
- All Privileges → Resource → Assign virtual machine to resource pool
- All Privileges → Virtual Machine → Configuration (All)
- All Privileges → Virtual Machine → Interaction (All)
- All Privileges → Virtual Machine → Inventory (All)
- All Privileges → Virtual Machine → Provisioning (All)

9.3. ADDING A VMWARE VSPHERE CONNECTION TO SATELLITE SERVER

Use this procedure to add a VMware vSphere connection in Satellite Server's compute resources.

Ensure that the host and network-based firewalls are configured to allow Satellite to vCenter communication on TCP port 443. Verify that Satellite is able to resolve the host name of vCenter and vCenter is able to resolve Satellite Server's host name.

Procedure

To add a connection, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources**, and in the Compute Resources window, click **Create Compute Resource**
2. In the **Name** field, enter a name for the resource.
3. From the **Provider** list, select **VMware**.
4. In the **Description** field, enter a description for the resource.
5. In the **VCenter/Server** field, enter the IP address or host name of the vCenter server.
6. In the **User** field, enter the user name with permission to access the vCenter's resources.
7. In the **Password** field, enter the password for the user.
8. Click **Load Datacenters** to populate the list of data centers from your VMware vSphere environment.
9. From the **Datacenter** list, select a specific data center to manage from this list.
10. In the **Fingerprint** field, ensure that this field is populated with the fingerprint from the data center.
11. From the **Display Type** list, select a console type, for example, **VNC** or **VMRC**. Note that VNC consoles are unsupported on VMware ESXi 6.5 and later.

12. Optional: In the **VNC Console Passwords** field, select the **Set a randomly generated password on the display connection** check box to secure console access for new hosts with a randomly generated password. You can retrieve the password for the VNC console to access guest virtual machine console from the **libvirt** host from the output of the following command:

```
# virsh edit your_VM_name
<graphics type='vnc' port='-1' autoport='yes' listen='0.0.0.0'
passwd='your_randomly_generated_password>
```

The password randomly generates every time the console for the virtual machine opens, for example, with virt-manager.

13. From the **Enable Caching** list, you can select whether to enable caching of compute resources. For more information, see [Section 9.8, "Caching of VMware Compute Resources"](#).
14. Click the **Locations** and **Organizations** tabs and verify that the values are automatically set to your current context. You can also add additional contexts.
15. Click **Submit** to save the connection.

For CLI Users

Create the connection with the **hammer compute-resource create** command. Select **Vmware** as the **--provider** and set the data center name:

```
# hammer compute-resource create --name "My_vSphere" \
--provider "Vmware" \
--description "vSphere server at vsphere.example.com" \
--server "vsphere.example.com" --user "My_User" \
--password "My_Password" --locations "My_Location" --organizations "My_Organization" \
--datacenter "My_Datacenter"
```

9.4. ADDING VMWARE VSPHERE IMAGES TO SATELLITE SERVER

VMware vSphere uses templates as images for creating new virtual machines. If using image-based provisioning to create new hosts, you need to add VMware template details to your Satellite Server. This includes access details and the template name.

Procedure

To add an image, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources** and in the Compute Resources window, click the VMware vSphere connection.
2. In the **Name** field, enter a name for the image.
3. From the **OperatingSystem** list, select the image's base operating system.
4. From the **Architecture** list, select the operating system architecture.
5. In the **User** field, enter the SSH user name for image access. This is normally the **root** user.
6. In the **Password** field, enter the SSH password for image access.

7. From the **User data** list, select whether you want the images to support user data input, such as **cloud-init** data.
8. In the **Image** field, enter the relative path and name of the template on the vSphere environment. Do not include the data center in the relative path.
9. Click **Submit** to save the image details.

For CLI Users

Create the image with the **hammer compute-resource image create** command. Use the **--uuid** field to store the relative template path on the vSphere environment.

```
# hammer compute-resource image create --name "Test_vSphere_Image" \
--operatingsystem "RedHat 7.2" --architecture "x86_64" \
--username root --uuid "Templates/RHEL7" \
--compute-resource "My_vSphere"
```

9.5. ADDING VMWARE VSPHERE DETAILS TO A COMPUTE PROFILE

You can predefine certain hardware settings for virtual machines on VMware vSphere. You achieve this through adding these hardware settings to a compute profile.

Procedure

To add VMware vSphere details to a compute profile, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Profiles** and, in the Compute Profiles window, click the name of the compute profile, and then click the vSphere connection.
2. In the **CPUs** field, enter the number of CPUs to allocate to the new host.
3. In the **Cores per socket** field, enter the number of cores to allocate to each CPU.
4. In the **Memory** field, enter the amount of memory to allocate to the new host.
5. In the **Cluster** field, enter the name of the target host cluster on the VMware environment.
6. From the **Resource pool** list, select an available resource allocations for the host.
7. In the **Folder** field, enter the folder to organize the host.
8. From the **Guest OS** list, select the operating system you want to use in VMware vSphere.
9. From the **SCSI controller** list, select the disk access method for the host.
10. From the **Virtual H/W version** list, select the underlying VMware hardware abstraction to use for virtual machines.
11. You can select the **Memory hot add** or **CPU hot add** check boxes if you want to add more resources while the virtual machine is powered.
12. From the **Image** list, select the image to use if performing image-based provisioning.
13. From the **Network Interfaces** list, select the network parameters for the host's network interface. You can create multiple network interfaces. However, at least one interface must point to a Capsule-managed network.

14. Select the **Eager zero** check box if you want to use eager zero thick provisioning. If unchecked, the disk uses lazy zero thick provisioning.
15. Click **Submit** to save the compute profile.

For CLI Users

The compute profile CLI commands are not yet implemented in Red Hat Satellite 6.6. As an alternative, you can include the same settings directly during the host creation process.

9.6. CREATING HOSTS ON A VMWARE VSPHERE SERVER

The VMware vSphere provisioning process provides the option to create hosts over a network connection or using an existing image.

For network-based provisioning, you must create a host to access either Satellite Server's integrated Capsule or an external Capsule Server on a VMware vSphere virtual network, so that the host has access to PXE provisioning services. The new host entry triggers the VMware vSphere server to create the virtual machine. If the virtual machine detects the defined Capsule Server through the virtual network, the virtual machine boots to PXE and begins to install the chosen operating system.

DHCP Conflicts

If you use a virtual network on the VMware vSphere server for provisioning, ensure that you select a virtual network that does not provide DHCP assignments. This causes DHCP conflicts with Satellite Server when booting new hosts.

For image-based provisioning, use the pre-existing image as a basis for the new volume.

Procedure

To create a host for a VMware vSphere server, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > Create Host**.
2. In the **Name** field, enter the name that you want to become the provisioned system's host name.
3. Click the **Organization** and **Location** tabs to ensure that the provisioning context is automatically set to the current context.
4. From the **Host Group** list, select the host group that you want to use to populate the form.
5. From the **Deploy on** list, select the VMware vSphere connection.
6. From the **Compute Profile** list, select a profile to use to automatically populate virtual machine-based settings.
7. Click the **Interface** tab and click **Edit** on the host's interface.
8. Verify that the fields are automatically populated with values. Note in particular:
 - The **Name** from the **Host** tab becomes the **DNS name**.
 - The Satellite Server automatically assigns an IP address for the new host.
9. Ensure that the **MAC address** field is blank. The VMware vSphere server assigns one to the host.

10. Verify that the **Managed**, **Primary**, and **Provision** options are automatically selected for the first interface on the host. If not, select them.
11. In the interface window, review the VMware vSphere-specific fields that are populated with settings from our compute profile. Modify these settings to suit your requirements.
12. Click the **Operating System** tab, and confirm that all fields automatically contain values.
13. Select the Provisioning Method that you want:
 - For network-based provisioning, click **Network Based**.
 - For image-based provisioning, click **Image Based**.
 - For boot-disk provisioning, click **Boot disk based**.
14. Click **Resolve** in **Provisioning templates** to check the new host can identify the right provisioning templates to use.
15. Click the **Virtual Machine** tab and confirm that these settings are populated with details from the host group and compute profile. Modify these settings to suit your requirements.
16. Click the **Parameters** tab and ensure that a parameter exists that provides an activation key. If not, add an activation key.
17. Click **Submit** to save the host entry.

For CLI Users

Create the host from a network with the **hammer host create** command and include **--provision-method build** to use network-based provisioning.

```
# hammer host create --name "vmware-test1" --organization "My_Organization" \
--location "New York" --hostgroup "Base" \
--compute-resource "My_vSphere" --provision-method build \
--build true --enabled true --managed true \
--interface
"managed=true,primary=true,provision=true,compute_type=VirtualE1000,compute_network=mynetwork" \
--compute-
attributes="cpus=1,corespersocket=2,memory_mb=1024,cluster=MyCluster,path=MyVMs,start=true" \
--volume="size_gb=20G,datastore=Data,name=myharddisk,thin=true"
```



NOTE

For more information about additional host creation parameters for this compute resource, see [Appendix B, Additional Host Parameters for Hammer CLI](#).

For CLI Users

Create the host from an image with the **hammer host create** command and include **--provision-method image** to use image-based provisioning.

```
# hammer host create --name "vmware-test2" --organization "My_Organization" \
--location "New York" --hostgroup "Base" \
```

```
--compute-resource "My_vSphere" --provision-method image \
--image "Test VMware Image" --enabled true --managed true \
--interface
"managed=true,primary=true,provision=true,compute_type=VirtualE1000,compute_network=mynetwork
" \
--compute-
attributes="cpus=1,corespersocket=2,memory_mb=1024,cluster=MyCluster,path=MyVMs,start=true"
\
--volume="size_gb=20G,datastore=Data,name=myharddisk,thin=true"
```

For more information about additional host creation parameters for this compute resource, see [Appendix B, Additional Host Parameters for Hammer CLI](#).

9.7. USING THE VMWARE VSPHERE CLOUD-INIT AND USERDATA TEMPLATES FOR PROVISIONING

From Satellite 6.6 and later, you can use VMware with the **Cloud-init** and **userdata** templates to insert user data into the new virtual machine, to make further VMware customization, and to enable the VMware-hosted virtual machine to call back to Satellite at intervals.

You can use the same procedures to set up a VMware compute resource within Satellite, with a few modifications to the work flow.

VMware cloud-init Provisioning Overview

When you set up the compute resource and images for VMware provisioning in Satellite, the following sequence of provisioning events occur:

- The user provisions one or more virtual machines using the Satellite web UI, API, or hammer
- Satellite calls the VMware vCenter to clone the virtual machine template
- Satellite **userdata** provisioning template adds customized identity information
- When provisioning completes, the Satellite **cloud-init** provisioning template instructs the virtual machine to call back to Satellite when **cloud-init** runs
- VMware vCenter clones the template to the virtual machine
- VMware vCenter applies customization for the virtual machine's identity, including the host name, IP, and DNS
- The virtual machine builds, **cloud-init** is invoked and pings Satellite on port **80**, which then redirects to **443**

Port and Firewall Requirements

Because of the **cloud-init** service, the virtual machine always calls back to Satellite even if you register the virtual machine to Capsule. Ensure that you configure port and firewall settings to open any necessary connections.

For more information about port and firewall requirements, see [Ports and Firewalls Requirements](#) in *Installing Satellite Server from a Connected Network* and [Ports and Firewalls Requirements](#) in *Installing Capsule Server*.

Associating the **userdata** and **Cloud-init** Templates with the Operating System

1. In the Satellite web UI, navigate to **Hosts > Operating Systems**, and select the operating system that you want to use for provisioning.
2. Click the **Template** tab.
3. From the **Cloud-init template** list, select **Cloudinit default**.
4. From the **User data template** list, select **UserData open-vm-tools**.
5. Click **Submit** to save the changes.

Preparing an Image to use the cloud-init Template

To prepare an image, you must first configure the settings that you require on a virtual machine that you can then save as an image to use in Satellite.

To use the **cloud-init** template for provisioning, you must configure a virtual machine so that **cloud-init** is installed, enabled, and configured to call back to Satellite. For security purposes, you must add a Satellite X509 certificate to use HTTPs for all communication. This procedure includes steps to clean the virtual machine so that no unwanted information transfers to the image you use for provisioning.

If you have an image with **cloud-init**, you must still follow this procedure to enable **cloud-init** to communicate with Satellite because **cloud-init** is disabled by default.

1. On the virtual machine that you use to create the image, install **cloud-init**, **open-vm-tools**, and **perl**:

```
# yum -y install cloud-init open-vm-tools perl
```

2. Create a configuration file for **cloud-init**:

```
# vi /etc/cloud/cloud.cfg.d/example_cloud-init_config.cfg
```

3. Add the following information to the **example_cloud_init_config.cfg** file:

```
datasource_list: [NoCloud]
datasource:
  NoCloud:
    seedfrom: https://satellite.example.com/userdata/
EOF
```

4. Enable the CA certificates for the image:

```
# update-ca-trust enable
```

5. Download the **katello-server-ca.crt** file from Satellite:

```
# wget http://satellite.example.com/pub/katello-server-ca.crt
```

6. Move the **katello-server-ca.crt** file to the **/etc/pki/ca-trust/source/anchors/** directory:

```
# mv katello-server-ca.crt /etc/pki/ca-trust/source/anchors/katello-server-ca.crt
```

7. To update the record of certificates, enter the following command:

```
■
```

```
# update-ca-trust extract
```

8. Use the following commands to clean the image:

```
# systemctl stop rsyslog
# systemctl stop auditd
# package-cleanup --oldkernels --count=1
# yum clean all
```

9. Use the following commands to reduce logspace, remove old logs, and truncate logs:

```
# logrotate -f /etc/logrotate.conf
# rm -f /var/log/*-???????? /var/log/*.gz
# rm -f /var/log/dmesg.old
# rm -rf /var/log/anaconda
# cat /dev/null > /var/log/audit/audit.log
# cat /dev/null > /var/log/wtmp
# cat /dev/null > /var/log/lastlog
# cat /dev/null > /var/log/grubby
```

10. Remove **udev** hardware rules:

```
# rm -f /etc/udev/rules.d/70*
```

11. Remove the **uuid** from **ifcfg** scripts:

```
# cat > /etc/sysconfig/network-scripts/ifcfg-ens192 <<EOM
DEVICE=ens192
ONBOOT=yes
EOM
```

12. Remove the SSH host keys:

```
# rm -f /etc/ssh/SSH_keys
```

13. Remove root user's shell history:

```
# rm -f ~root/.bash_history
# unset HISTFILE
```

14. Remove root user's SSH history:

```
# rm -rf ~root/.ssh/known_hosts
```

You can now create an image from this virtual machine.

You can use the [Section 9.4, “Adding VMware vSphere Images to Satellite Server”](#) section to add the image to Satellite.

9.8. CACHING OF VMWARE COMPUTE RESOURCES

Caching of compute resources speeds up rendering of VMware information.

9.8.1. Enabling Caching of VMware Compute Resources

To enable or disable caching of VMware compute resources:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources**.
2. Click the **Edit** button to the right of the VMware server you want to update.
3. Select the **Enable caching** check box.

9.8.2. Refreshing the VMware Compute Resources Cache

To refresh the cache of VMware compute resources to update compute resources information:

Procedure

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources**.
2. Select a VMware server you want to refresh the compute resources cache for and click the **Refresh Cache** button.

For CLI Users

Use this API call to refresh the compute resources cache:

```
# curl -H "Accept:application/json,version=2" \  
-H "Content-Type:application/json" -X PUT \  
-u username:password -k \  
https://satellite.example.com/api/compute\_resources/compute\_resource\_id/refresh\_cache
```

Use the **hammer compute-resource list** command to determine the ID of the VMware server you want to refresh the compute resources cache for.

CHAPTER 10. PROVISIONING VIRTUAL MACHINES WITH CONTAINER-NATIVE VIRTUALIZATION

Container-native Virtualization addresses the needs of development teams that have adopted or want to adopt Kubernetes but possess existing virtual machine (VM)-based workloads that cannot be easily containerized. This technology provides a unified development platform where developers can build, modify, and deploy applications residing in application containers and VMs in a shared environment. These capabilities support rapid application modernization across the open hybrid cloud.

With Red Hat Satellite 6, you can create a compute resource for Container-native Virtualization so that you can provision and manage Kubernetes virtual machines using Satellite.

Note that template provisioning is not supported for this release.



IMPORTANT

The Container-native Virtualization compute resource is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process. For more information about the support scope of Red Hat Technology Preview features, see <https://access.redhat.com/support/offerings/techpreview/>.

10.1. PREREQUISITES FOR CONTAINER-NATIVE VIRTUALIZATION PROVISIONING

- A Container-native Virtualization user that has the **cluster-admin** permissions for the Openshift Container Platform virtual cluster. For more information, see [Using RBAC to Define and Apply Permissions](#) in the *Authentication* guide of the Openshift Container Platform documentation.
- A Capsule Server managing a network on the Container-native Virtualization server. Ensure that no other DHCP services run on this network to avoid conflicts with Capsule Server. For more information about network service configuration for Capsule Servers, see [Chapter 4, Configuring Networking](#).
- Synchronized content repositories for the version of Red Hat Enterprise Linux that you want to provision. For more information, see [Synchronizing Red Hat Repositories](#) in the Content Management Guide.
- An activation key for host registration. For more information, see [Creating An Activation Key](#) in the *Content Management* guide.

Enabling the Container-native Virtualization plugin for Satellite

To enable the Container-native Virtualization plugin for Satellite, you must run the **satellite-installer** command with the following option:

```
# satellite-installer --enable-foreman-plugin-kubevirt
```

User Roles and Permissions to Provision using Container-native Virtualization

To provision a Container-native Virtualization virtual machine in Satellite, you must have a user account with the following roles:

- **Edit hosts**
- **View hosts**

For more information, see [Assigning Roles to a User](#) in the *Administering Red Hat Satellite* guide.

You must also create a custom role with the following permissions:

- **view_compute_resources**
- **destroy_compute_resources_vms**
- **power_compute_resources_vms**
- **create_compute_resources_vms**
- **view_compute_resources_vms**
- **view_locations**
- **view_subnets**

Bearer token authentication

Before you can create a Container-native Virtualization compute resource, you must generate a bearer token to use for HTTP and HTTPs authentication.

1. On your Container-native Virtualization server, to list the secrets that contain tokens, enter the following command:

```
# kubectl get secrets
```

2. To list the token for your secret, enter the following command:

```
# kubectl get secrets YOUR_SECRET -o jsonpath='{.data.token}' | base64 -d | xargs
```

10.2. ADDING A CONTAINER-NATIVE VIRTUALIZATION CONNECTION TO SATELLITE SERVER

Use this procedure to add a Container-native Virtualization connection to Satellite Server's compute resources.

Procedure

To add a Container-native Virtualization connection to Satellite, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources**, and click **Create Compute Resource**.
2. In the **Name** field, enter a name for the new compute resource.
3. From the **Provider** list, select **Container-native Virtualization**.

4. In the **Description** field, enter a description for the compute resource.
5. In the **Hostname** field, enter the address of the Container-native Virtualization server that you want to use.
6. In the **API Port** field, enter the port number that you want to use for provisioning requests from Satellite to Container-native Virtualization.
7. In the **Namespace** field, enter the user name of the Container-native Virtualization virtual cluster that you want to use.
8. In the **Token** field, enter a bearer token for HTTP and HTTPs authentication.
9. Optional: In the **X509 Certification Authorities** field, enter a certificate to enable client certificate authentication for API server calls.

CHAPTER 11. PROVISIONING CLOUD INSTANCES IN RED HAT OPENSTACK PLATFORM

Red Hat OpenStack Platform provides the foundation to build a private or public Infrastructure-as-a-Service (IaaS) cloud on Red Hat Enterprise Linux. It offers a massively scalable, fault-tolerant platform for the development of cloud-enabled workloads. In Red Hat Satellite 6, you can interact with Red Hat OpenStack Platform's REST API to create new cloud instances and control their power management states.

11.1. PREREQUISITES FOR RED HAT OPENSTACK PLATFORM PROVISIONING:

Requirements for Red Hat OpenStack Platform Provisioning include:

- Synchronized content repositories for Red Hat Enterprise Linux 7. For more information, see [Synchronizing Red Hat Repositories](#) in the *Content Management Guide*.
- A Capsule Server managing a network in your OpenStack environment. For more information, see [Chapter 4, Configuring Networking](#).
- An image added to OpenStack Image Storage (glance) service for image-based provisioning. For more information, see the [Red Hat OpenStack Platform Instances and Images Guide](#).
- An activation key for host registration. For more information, see [Creating An Activation Key](#) in the *Content Management Guide*.

11.2. ADDING A RED HAT OPENSTACK PLATFORM CONNECTION TO THE SATELLITE SERVER

Use this procedure to add the Red Hat OpenStack Platform connection in the Satellite Server's compute resources.

Procedure

To add a compute resource, use the following procedure:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources** and in the Compute Resources window, click **Create Compute Resource**.
2. In the **Name** field, enter a name to identify the compute resource for future use.
3. From the **Provider** list, select **RHEL OpenStack Platform**.
4. In the **Description** field, enter a description for the resource.
5. In the **URL** field, enter a URL to point to the OpenStack Authentication keystone service's API at the **tokens** resource. Use the following format:
<http://openstack.example.com:5000/v2.0/tokens>.
6. In the **User** and **Password** fields, enter the authentication user and password for Satellite to access the environment.
7. In the **Domain** field, enter the domain for V3 authentication.
8. From the **Tenant** list, select the tenant or project for Satellite Server to manage.

9. To use external networks as primary networks for hosts, select the **Allow external network as main network** check box.
10. Click the **Locations** and **Organizations** tabs and verify that the location and organization that you want to use are set to your current context. Add any additional contexts that you want to these tabs.
11. Click **Submit** to save the Red Hat OpenStack Platform connection.

For CLI Users

Create the connection with the **hammer compute-resource create** command:

```
# hammer compute-resource create --name "My_OpenStack" \  
--provider "OpenStack" \  
--description "My OpenStack environment at openstack.example.com" \  
--url "http://openstack.example.com:5000/v2.0/tokens" --user "My_Username" \  
--password "My_Password" --tenant "openstack" --locations "New York" \  
--organizations "My_Organization"
```

11.3. ADDING RED HAT OPENSTACK PLATFORM IMAGES TO THE SATELLITE SERVER

Red Hat OpenStack Platform uses image-based provisioning to create new hosts. You must add image details to your Satellite Server. This includes access details and image location.

Procedure

To add Red Hat OpenStack Platform images, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources** and in the Computer Resources window, click the name of a Red Hat OpenStack Platform connection.
2. In the **Name** field, enter a name that describes the image.
3. From the **Operatingssystem** list, select the image's base operating system.
4. From the **Architecture** list, select the operating system architecture.
5. In the **User** field, enter the SSH user name for image access. This is normally the **root** user.
6. In the **Password** field, enter the SSH password for image access.
7. From the **Image** list, select the image in OpenStack Image Storage.
8. From the **User data** list, select whether you want to set if images support user data input, such as **cloud-init** data.
9. Click **Submit** to save the image details.

For CLI Users

Create the image with the **hammer compute-resource image create** command. Use the **--uuid** field to store the full path of the image location on the Red Hat OpenStack Platform server.

```
# hammer compute-resource image create --name "Test OpenStack Image" \  

```

```
--operatingsystem "RedHat 7.2" --architecture "x86_64" \
--user root --user-data true \
--compute-resource "My_OpenStack_Platform"
```

11.4. ADDING RED HAT OPENSTACK PLATFORM DETAILS TO A COMPUTE PROFILE

In Satellite, you can define certain hardware settings for instances on Red Hat OpenStack Platform. You can add these hardware settings to a compute profile.

Procedure

To add Red Hat OpenStack Platform details to a compute profile, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Profiles** and in the Compute Profiles window, click the name of the profile you want to use.
2. From the **Flavor** list, select the hardware profile on OpenStack Platform to use for the host.
3. From the **Availability zone** list, select the target cluster to use within the OpenStack Platform environment.
4. From the **Image** list, select the image to use for image-based provisioning.
5. From the **Tenant** list, select the tenant or project for the OpenStack Platform instance.
6. From the **Security Group** list, select the cloud-based access rules for ports and IP addresses.
7. From the **Internal network**, select the private networks for the host to join.
8. From the **Floating IP network**, select the external networks for the host to join and assign a floating IP address.
9. From the **Boot from volume**, select whether a volume is created from the image. If not selected, the instance boots the image directly.
10. In the **New boot volume size (GB)** field, enter the size, in GB, of the new boot volume.
11. Click **Submit** to save the compute profile.

For CLI Users

The compute profile CLI commands are not yet implemented in Red Hat Satellite 6.6. As an alternative, you can include the same settings directly during the host creation process.

11.5. CREATING IMAGE-BASED HOSTS ON RED HAT OPENSTACK PLATFORM

In Satellite, you can provision Red Hat OpenStack Platform hosts from existing images on the Red Hat OpenStack Platform server.

Procedure

To provision a host, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > New Host**.

2. In the **Name** field, enter the name that you want to assign to the provisioned system's host.
3. From the **Host Group** list, you can select a host group to populate the host fields.
4. From the **Deploy on** list, select the OpenStack Platform connection.
5. From the **Compute profile** list, select a profile to use to automatically populate cloud instance-based settings.
6. Click the **Interface** tab, and click **Edit** on the host's interface. Verify that the **Name** from the **Host** tab becomes the **DNS name**, and that the Satellite Server automatically assigns an IP address for the new host.
7. Ensure that the **MAC address** field is blank. The Red Hat OpenStack Platform server assigns a MAC address to the host.
8. Verify that Satellite Server automatically selects the **Managed**, **Primary**, and **Provision** options for the first interface on the host. If not, select them.
9. Click the **Operating System** tab, and confirm that each aspect of the operating system is populated.
10. If you want to change the image that populates automatically from your compute profile, from the **Images** list, select a different image to base the new host's root volume.
11. Click **Resolve** in **Provisioning Templates** to verify that the new host can identify the right provisioning templates to use.
12. Click the **Virtual Machine** tab, and verify that the settings are populated with details from the host groups and compute profile. Modify these settings to suit your needs.
13. Click the **Parameters** tab and ensure that a parameter exists that provides an activation key. If not, add an activation key.
14. Click **Submit** to save the changes.

This new host entry triggers the Red Hat OpenStack Platform server to create the instance, using the pre-existing image as a basis for the new volume.

For CLI Users

Create the host with the **hammer host create** command and include the **--provision-method image** option to use image-based provisioning.

```
# hammer host create --name "openstack-test1" --organization "My_Organization" \  
--location "New York" --hostgroup "Example_Hostgroup" \  
--compute-resource "My_OpenStack_Platform" --provision-method image \  
--image "Test OpenStack Image" --enabled true --managed true \  
--interface "managed=true,primary=true,provision=true" \  
--compute-attributes="flavor_ref=m1.small,tenant_id=openstack,security_groups=default,network=mynetwork"
```

For more information about additional host creation parameters for this compute resource, see [Appendix B, Additional Host Parameters for Hammer CLI](#).

CHAPTER 12. PROVISIONING CLOUD INSTANCES IN AMAZON EC2

Amazon Elastic Compute Cloud (Amazon EC2) is a web service that provides public cloud compute resources. Using Red Hat Satellite 6, you can interact with Amazon EC2's public API to create cloud instances and control their power management states. Use the procedures in this chapter to add a connection to an Amazon EC2 account and provision a cloud instance.

12.1. PREREQUISITES FOR AMAZON EC2 PROVISIONING

The requirements for Amazon EC2 provisioning include:

- Synchronized content repositories for Red Hat Enterprise Linux 7. For more information, see [Synchronizing Red Hat Repositories](#) in the *Content Management Guide*.
- A Capsule Server managing a network in your EC2 environment. Use a Virtual Private Cloud (VPC) to ensure a secure network between the hosts and the Capsule Server.
- An Amazon Machine Image (AMI) for image-based provisioning.
- An activation key for host registration. For more information, see [Creating An Activation Key](#) in the *Content Management* guide.

12.2. ADDING AN AMAZON EC2 CONNECTION TO THE SATELLITE SERVER

Use this procedure to add the Amazon EC2 connection in the Satellite Server's compute resources.

Time Settings and Amazon Web Services

Amazon Web Services uses time settings as part of the authentication process. Ensure that Satellite Server's time is correctly synchronized. Ensure that an NTP service, such as **ntpd** or **chronyd**, is running properly on the Satellite Server. Failure to provide the correct time to Amazon Web Services can lead to authentication failures. For more information about synchronizing time in Satellite, see [Synchronizing the System Clock With chronyd](#) in *Installing Satellite Server from a Connected Network*.

Procedure

To add an Amazon EC2 connection, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources** and in the Compute Resources window, click **Create Compute Resource**.
2. In the **Name** field, enter a name to identify the Amazon EC2 compute resource.
3. From the **Provider** list, select **EC2**.
4. In the **Description** field, enter information that helps distinguish the resource for future use.
5. Optional: From the **HTTP proxy** list, select an HTTP proxy to connect to external API services. You must add HTTP proxies to Satellite before you can select a proxy from this list. For more information, see [Configuring Satellite Server with HTTP Proxy](#) in *Installing Satellite Server from a Connected Network*.

6. In the **Access Key** and **Secret Key** fields, enter the access keys for your Amazon EC2 account. For more information, see [Managing Access Keys for your AWS Account](#) on the Amazon documentation website.
7. Optional: Click the **Load Regions** button to populate the **Regions** list.
8. From the **Region** list, select the Amazon EC2 region or data center to use.
9. Click the **Locations** tab and ensure that the location you want to use is selected, or add a different location.
10. Click the **Organizations** tab and ensure that the organization you want to use is selected, or add a different organization.
11. Click **Submit** to save the Amazon EC2 connection.
12. Select the new compute resource and then click the **SSH keys** tab, and click **Download** to save a copy of the SSH keys to use for SSH authentication. Until [BZ1793138](#) is resolved, you can download a copy of the SSH keys only immediately after creating the Amazon EC2 compute resource. If you require SSH keys at a later stage, follow the procedure in [Section 12.7, "Connecting to an Amazon EC2 instance using SSH"](#).

For CLI Users

Create the connection with the **hammer compute-resource create** command. Use **--user** and **--password** options to add the access key and secret key respectively.

```
# hammer compute-resource create --name "My_EC2" --provider "EC2" \
--description "Amazon EC2 Public Cloud" --user "user_name" \
--password "secret_key" --region "us-east-1" --locations "New York" \
--organizations "My_Organization"
```

12.3. USING AN HTTP PROXY WITH COMPUTE RESOURCES

In some cases, the EC2 compute resource that you use might require a specific HTTP proxy to communicate with Satellite. In Satellite, you can create an HTTP proxy and then assign the HTTP proxy to your EC2 compute resource.

However, if you configure an HTTP proxy for Satellite in **Administer > Settings**, and then add another HTTP proxy for your compute resource, the HTTP proxy that you define in **Administer > Settings** takes precedence.

Procedure

1. In the Satellite web UI, navigate to **Infrastructure > HTTP Proxies**, and select **New HTTP Proxy**.
2. In the **Name** field, enter a name for the HTTP proxy.
3. In the **URL** field, enter the URL for the HTTP proxy, including the port number.
4. Optional: Enter a username and password to authenticate, if the HTTP proxy requires authentication.
5. Click **Test Connection** to ensure that you can connect to the HTTP proxy from Satellite.

6. Click the **Locations** tab and add a location.
7. Click the **Organization** tab and add an organization.
8. Click **Submit**.

12.4. ADDING AMAZON EC2 IMAGES TO SATELLITE SERVER

Amazon EC2 uses image-based provisioning to create hosts. You must add image details to your Satellite Server. This includes access details and image location.

Procedure

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources** and select an Amazon EC2 connection.
2. Click the **Images** tab, and then click **New Image**.
3. In the **Name** field, enter a name to identify the image for future use.
4. From the **Operating System** list, select the operating system that corresponds with the image you want to add.
5. From the **Architecture** list, select the operating system's architecture.
6. In the **Username** field, enter the SSH user name for image access. This is normally the **root** user.
7. In the **Image ID** field, enter the Amazon Machine Image (AMI) ID for the image. This is usually in the following format: **ami-xxxxxxxx**.
8. Optional: Select the **User Data** check box if the images support user data input, such as **cloud-init** data. If you enable user data, the Finish scripts are automatically disabled. This also applies in reverse: if you enable the Finish scripts, this disables user data.
9. Optional: In the **IAM role** field, enter the Amazon security role used for creating the image.
10. Click **Submit** to save the image details.

For CLI Users

Create the image with the **hammer compute-resource image create** command. Use the **--uuid** field to store the full path of the image location on the Amazon EC2 server.

```
# hammer compute-resource image create --name "Test Amazon EC2 Image" \
--operatingsystem "RedHat 7.2" --architecture "x86_64" --username root \
--user-data true --uuid "ami-my_ami_id" --compute-resource "My_EC2"
```

12.5. ADDING AMAZON EC2 DETAILS TO A COMPUTE PROFILE

You can add hardware settings for instances on Amazon EC2 to a compute profile.

Procedure

To add hardware settings, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Profiles** and click the name of your profile, then click an EC2 connection.
2. From the **Flavor** list, select the hardware profile on EC2 to use for the host.
3. From the **Image** list, select the image to use for image-based provisioning.
4. From the **Availability zone** list, select the target cluster to use within the chosen EC2 region.
5. From the **Subnet** list, add the subnet for the EC2 instance. If you have a VPC for provisioning new hosts, use its subnet.
6. From the **Security Groups** list, select the cloud-based access rules for ports and IP addresses to apply to the host.
7. From the **Managed IP** list, select either a **Public** IP or a **Private** IP.
8. Click **Submit** to save the compute profile.

For CLI Users

The compute profile CLI commands are not yet implemented in Red Hat Satellite 6.6. As an alternative, you can include the same settings directly during the host creation process.

12.6. CREATING IMAGE-BASED HOSTS ON AMAZON EC2

The Amazon EC2 provisioning process creates hosts from existing images on the Amazon EC2 server.

Procedure

1. In the Satellite web UI, navigate to **Hosts > Create Host**.
2. In the **Name** field, enter a name for the host.
3. From the **Host Group** list, you can select a host group to populate most of the new host's fields.
4. From the **Deploy on** list, select the EC2 connection.
5. Click the **Interface** tab, and then click **Edit** on the host's interface, and verify that the fields are populated with values. Leave the **Mac Address** field blank. The Satellite Server automatically selects an IP address and the **Managed**, **Primary**, and **Provision** options for the first interface on the host.
6. Click the **Operating System** tab and confirm that all fields are populated with values.
7. Click the **Virtual Machine** tab and confirm that all fields are populated with values.
8. Click the **Parameters** tab, and ensure that a parameter exists that provides an activation key. If not, add an activation key.
9. Click **Submit** to save your changes.

This new host entry triggers the Amazon EC2 server to create the instance, using the pre-existing image as a basis for the new volume.

For CLI Users

Create the host with the **hammer host create** command and include **--provision-method image** to use image-based provisioning.

```
# hammer host create --name "ec2-test1" --organization "My_Organization" \
--location "New York" --hostgroup "Base" \
--compute-resource "My_EC2" --provision-method image \
--image "Test Amazon EC2 Image" --enabled true --managed true \
--interface "managed=true,primary=true,provision=true,subnet_id=EC2" \
--compute-attributes="flavor_id=m1.small,image_id=TestImage,availability_zones=us-east-
1a,security_group_ids=Default,managed_ip=Public"
```

For more information about host creation parameters for this compute resource, see [Appendix B, Additional Host Parameters for Hammer CLI](#).

12.7. CONNECTING TO AN AMAZON EC2 INSTANCE USING SSH

You can connect remotely to an Amazon EC2 instance from Satellite Server using SSH. However, to connect to any Amazon Web Services EC2 instance that you provision through Red Hat Satellite, you must first access the private key that is associated with the compute resource in the Foreman database, and use this key for authentication.

To locate the private key and connect to an Amazon EC2 server using SSH, complete the following steps:

1. To locate the compute resource list, on your Satellite Server base system, enter the following command, and note the ID of the compute resource that you want to use:

```
# hammer compute-resource list
```

2. Switch user to the **postgres** user:

```
# su - postgres
```

3. Initiate the **postgres** shell:

```
$ psql
```

4. Connect to the Foreman database as the user **postgres**:

```
# postgres=# \c foreman
```

5. Select the secret from **key_pairs** where **compute_resource_id = 3**:

```
# select secret from key_pairs where compute_resource_id = 3; secret
```

6. Copy the key from after **-----BEGIN RSA PRIVATE KEY-----** until **-----END RSA PRIVATE KEY-----**.

7. Create a **.pem** file and paste your key into the file:

```
# vim Keyname.pem
```

8. Ensure that you restrict access to the **.pem** file:

```
# chmod 600 Keyname.pem
```

- To connect to the Amazon EC2 instance, enter the following command:

```
ssh -i Keyname.pem ec2-user@example.aws.com
```

12.8. CONFIGURING A FINISH TEMPLATE FOR AN AMAZON WEB SERVICE EC2 ENVIRONMENT

You can use Red Hat Satellite finish templates during the provisioning of Red Hat Enterprise Linux instances in an Amazon EC2 environment.

To configure a finish template for Amazon EC2, complete the following steps:

- In the Red Hat Satellite 6 web UI, navigate to **Hosts** > **Provisioning Templates**.
- In the **Provisioning Templates** page, enter **Kickstart default finish** into the search field and click **Search**.
- On the **Kickstart default finish** template, select **Clone**.
- In the **Name** field, enter a unique name for the template.
- In the template, prefix each command that requires root privileges with **sudo**, except for **subscription-manager register** and **yum** commands, or add the following line to run the entire template as the sudo user:

```
sudo -s << EOS
__Template__Body__
EOS
```

- Click the **Association** tab, and associate the template with a Red Hat Enterprise Linux operating system that you want to use.
- Click the **Locations** tab, and add the the location where the host resides.
- Click the **Organizations** tab, and add the organization that the host belongs to.
- Make any additional customizations or changes that you require, then click **Submit** to save your template.
- Navigate to **Hosts** > **Operating systems** and select the operating system that you want for your host.
- Click the **Templates** tab, and from the **Finish Template** list, select your finish template.
- Navigate to **Hosts** > **Create Host** and enter the information about the host that you want to create.
- Click the **Parameters** tab and navigate to **Host parameters**.
- In **Host parameters**, click the **Add Parameter** button three times to add three new parameter fields. Add the following three parameters:

- In the **Name** field, enter **remote_execution_ssh_keys**. In the corresponding **Value** field,

enter the output of **cat /usr/share/foreman-proxy/.ssh/id_rsa_foreman_proxy.pub**.

- b. In the **Name** field, enter **remote_execution_ssh_user**. In the corresponding **Value** field, enter **ec2-user**.
- c. In the **Name** field, enter **activation_keys**. In the corresponding **Value** field, enter your activation key.

- 15. Click **Submit** to save the changes.

12.9. MORE INFORMATION ABOUT AMAZON WEB SERVICES AND SATELLITE

For information about how to locate Red Hat Gold Images on Amazon Web Services EC2, see [How to Locate Red Hat Cloud Access Gold Images on AWS EC2](#).

For information about how to install and use the Amazon Web Service Client on Linux, see [Install the AWS Command Line Interface on Linux](#) in the Amazon Web Services documentation.

For information about importing and exporting virtual machines in Amazon Web Services, see [VM Import/Export](#) in the Amazon Web Services documentation.

CHAPTER 13. PROVISIONING CLOUD INSTANCES IN GOOGLE COMPUTE ENGINE

Red Hat Satellite 6 can interact with Google Compute Engine (GCE), including creating new virtual machines and controlling their power management states. Only image-based provisioning is supported for creating GCE hosts.

13.1. PREREQUISITES FOR GCE PROVISIONING

Before you begin, ensure that the following conditions are met:

- In your GCE project, configure a service account with the necessary IAM Compute role. For more information, see [Compute Engine IAM roles](#) in the GCE documentation.
- In your GCE project-wise metadata, set the **enable-oslogin** to **FALSE**. For more information, see [Enabling or disabling OS Login](#) in the GCE documentation.
- Optional: If you want to use Puppet with GCE hosts, navigate to **Administer > Settings > Puppet** and enable the **Use UUID for certificates** setting to configure Puppet to use consistent Puppet certificate IDs.
- Based on your needs, associate a **finish** or **user_data** provisioning template with the operating system you want to use. For more information about provisioning templates, see [Section 3.7.1, “Types of Provisioning Templates”](#).
- Synchronize content repositories for the version of Red Hat Enterprise Linux that you want to use. For more information, see [Synchronizing Red Hat Repositories](#) in the *Content Management Guide*.
- Create an activation key for host registration. For more information, see [Creating An Activation Key](#) in the *Content Management* guide.

13.2. ADDING A GCE CONNECTION TO SATELLITE SERVER

Use this procedure to add a GCE connection to Satellite Server to be able to add images and provision hosts on GCE.

Procedure

To add a connection, complete the following steps:

1. In GCE, generate a service account key in JSON format and upload this file to the **/usr/share/foreman/** directory on Satellite Server.
2. On Satellite Server, configure permissions for the service account key to ensure that the file is readable by the **foreman** user:

```
# chown foreman /usr/share/foreman/gce_key.json
# chmod 0600 /usr/share/foreman/gce_key.json
# restorecon -vv /usr/share/foreman/gce_key.json
```

3. In the Satellite web UI, navigate to **Infrastructure > Compute Resources** and click **Create Compute Resource**.
4. In the **Name** field, enter a name for the resource.

5. From the **Provider** list, select **Google**.
6. Optional: In the **Description** field, enter a description for the resource.
7. In the **Google Project ID** field, enter the project ID.
8. In the **Client Email** field, enter the client email.
9. In the **Certificate Path** field, enter the path to the service account key. For example, **/usr/share/foreman/gce_key.json**.
10. Click **Load Zones** to populate the list of zones from your GCE environment.
11. From the **Zone** list, select the GCE zone to use.
12. Click **Submit**.

13.3. ADDING GCE IMAGES TO SATELLITE SERVER

GCE uses image-based provisioning to create hosts. You must add image details to your Satellite Server.

Procedure

To add an image, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Resources** and click the GCE connection.
2. Click the **Images** tab.
3. Click **Create Image**.
4. In the **Name** field, enter a name for the image.
5. From the **Operating system** list, select the base operating system for the image.
6. From the **Architecture** list, select the operating system architecture.
7. In the **User** field, enter the SSH user name for image access. Specify a user other than **root**, because the **root** user cannot connect to a GCE instance using SSH keys. The username must begin with a letter and consist of lowercase letters and numbers.
8. From the **Image** list, select the GCE image.
9. Optional: If the selected image supports **cloud-init**, select the **User data** check box to enable user data input.
10. Click **Submit** to save the image details.

13.4. ADDING GCE DETAILS TO A COMPUTE PROFILE

You can add GCE details to a compute profile to automatically populate virtual machine-based settings on host creation.

Procedure

To add details to a compute profile, complete the following steps:

1. In the Satellite web UI, navigate to **Infrastructure > Compute Profiles** and click the name of your profile.
2. Select a GCE connection.
3. From the **Machine Type** list, select the machine type to use for provisioning.
4. From the **Image** list, select the image to use for provisioning.
5. From the **Network** list, select the GCE network to use for provisioning.
6. Optional: Select the **Associate Ephemeral External IP** check box to assign a dynamic ephemeral IP address that Satellite uses to communicate with the host. This public IP address changes when you reboot the host. If you need a permanent IP address, reserve a static public IP address on GCE and attach it to the host.
7. In the **Size (GB)** field, enter the size of the storage to create on the host.
8. Click **Submit** to save the compute profile.

13.5. CREATING IMAGE-BASED HOSTS ON GCE

The GCE provisioning process creates hosts from existing images on GCE.

Procedure

To create a host on GCE, complete the following steps:

1. In the Satellite web UI, navigate to **Hosts > Create host**.
2. In the **Name** field, enter a name for the host.
3. Click the **Organization** and **Location** tabs to ensure that the provisioning context is automatically set to the current context.
4. Optional: From the **Host Group** list, you can select a host group to populate most of the new host's fields.
5. From the **Deploy on** list, select the GCE connection.
6. From the **Compute Profile** list, select a profile to use to automatically populate virtual machine-based settings.
7. Click the **Interface** tab and click **Edit** on the host's interface.
8. Verify that the fields are automatically populated with values, particularly the following items:
 - The **Name** from the **Host** tab becomes the **DNS name**.
 - The **MAC address** field is blank.
 - The **Domain** field is populated with the required domain.
 - The **Managed**, **Primary**, and **Provision** options are automatically selected for the first interface on the host. If not, select them.

9. Click the **Operating System** tab, and select the operating system to install.
10. Click **Resolve** in **Provisioning templates** to verify that the new host can identify the correct provisioning templates to use. You must select either a **finish** or **user_data** provisioning template.
11. Click the **Parameters** tab and ensure that a parameter exists that provides an activation key. If not, add an activation key.
12. Click **Submit** to save the host entry.

CHAPTER 14. PROVISIONING USING A RED HAT IMAGE BUILDER IMAGE

You can use a provisioned host in Satellite to create a Red Hat Image Builder image and import the image to Satellite to use for host provisioning.

14.1. CREATING AN IMAGE USING RED HAT IMAGE BUILDER

To use a Red Hat Image Builder image in Satellite, create an image using Red Hat Image Builder, then transfer and upload the image to Satellite Server.

Procedure

To create a Red Hat Image Builder image for Satellite, complete the following steps:

1. On Satellite Server, add and synchronize any repositories that you want to use for provisioning. For more information, see [Enabling Red Hat Repositories](#) in the *Content Management Guide*.
2. On Satellite Server, provision a host that can access any repositories that contain packages that you want to include in the image that you build.
3. On the server where you want to create images, install Red Hat Image Builder. For more information, see the [Installing Image Builder](#) chapter in the *Composing a customized RHEL system image* guide.
4. Create a blueprint for your custom image. For more information see the [Creating an Image Builder blueprint with command-line interface](#) procedure in the *Composing a customized RHEL system image* guide.
5. Add the packages that you require to the blueprint. For more information, see [Image Builder blueprint format](#) in the *Composing a customized RHEL system image* guide.
6. Create the image with a file extension that is compatible with Anaconda Kickstart provisioning templates, for example **.tar**. For a valid list of file extensions for Red Hat Image Builder, see [Image Builder output formats](#) in the *Composing a customized RHEL system image* guide. For more information about valid file extensions to use with Anaconda Kickstart, see the **liveimg** entry in the [Kickstart Syntax Reference](#) section of the *Red Hat Enterprise Linux Installation Guide*.
7. Use **scp** or **rsync** to copy the image using SSH to the base operating system of Satellite Server.
8. On Satellite Server, create a custom product, add a custom file repository to this product, and upload the image to the repository. For more information, see [Importing Individual ISO Images and Files](#) in the *Content Management Guide*.

14.2. USING A RED HAT IMAGE BUILDER IMAGE IN SATELLITE

To use the Red Hat Image Builder image in Satellite, you must add the **kickstart_liveimg** parameter to a host group that you can later use with your preferred provisioning method.

For more information about creating host groups, see [Creating a Host Group](#) in the *Managing Hosts* guide.

Procedure

To use the Red Hat Image Builder image with Anaconda Kickstart in Satellite, complete the following steps:

1. In the Satellite web UI, navigate to **Configure > Host Groups**, and select the host group that you want to use.
2. Click the **Parameters** tab, and then click **Add Parameter**.
3. In the **Name** field, enter **kickstart_liveimg**.
4. From the **Type** list, select **string**.
5. In the **Value** field, enter the absolute path or a relative path in the following format **custom/product/repository/image_name** that points to the exact location where you store the image.
6. Click **Submit** to save your changes.

You can use this image for bare metal provisioning and provisioning using a compute resource.

For more information about bare metal provisioning, see [Chapter 6, Provisioning Bare Metal Hosts](#). For more information about provisioning with different compute resources, see the relevant chapter for the compute resource that you want to use.

APPENDIX A. INITIALIZATION SCRIPT FOR PROVISIONING EXAMPLES

If you have not followed the examples in the Red Hat Satellite 6 Content Management Guide, you can use the following initialization script to create an environment for provisioning examples.

Create a script file (**sat6-content-init.sh**) and include the following:

```
#!/bin/bash

MANIFEST=$1

# Import the content from Red Hat CDN
hammer organization create --name "ACME" --label "ACME" \
--description "Our example organization for managing content."
hammer subscription upload --file ~/$MANIFEST --organization "ACME"
hammer repository-set enable \
--name "Red Hat Enterprise Linux 7 Server (RPMs)" \
--releasever "7Server" --basearch "x86_64" \
--product "Red Hat Enterprise Linux Server" --organization "ACME"
hammer repository-set enable \
--name "Red Hat Enterprise Linux 7 Server (Kickstart)" \
--releasever "7Server" --basearch "x86_64" \
--product "Red Hat Enterprise Linux Server" --organization "ACME"
hammer repository-set enable \
--name "Red Hat Satellite Tools {ProductVersion} (for RHEL 7 Server) (RPMs)" \
--basearch "x86_64" --product "Red Hat Enterprise Linux Server" \
--organization "ACME"
hammer product synchronize --name "Red Hat Enterprise Linux Server" \
--organization "ACME"

# Create our application life cycle
hammer lifecycle-environment create --name "Development" \
--description "Environment for ACME's Development Team" \
--prior "Library" --organization "ACME"
hammer lifecycle-environment create --name "Testing" \
--description "Environment for ACME's Quality Engineering Team" \
--prior "Development" --organization "ACME"
hammer lifecycle-environment create --name "Production" \
--description "Environment for ACME's Product Releases" \
--prior "Testing" --organization "ACME"

# Create and publish our Content View
hammer content-view create --name "Base" \
--description "Base operating system" \
--repositories "Red Hat Enterprise Linux 7 Server RPMs x86_64 7Server,Red Hat Satellite Tools {ProductVersion} for RHEL 7 Server RPMs x86_64" \
--organization "ACME"
hammer content-view publish --name "Base" \
--description "Initial content view for our operating system" \
--organization "ACME"
hammer content-view version promote --content-view "Base" --version 1 \
--to-lifecycle-environment "Development" --organization "ACME"
hammer content-view version promote --content-view "Base" --version 1 \
```

```
--to-lifecycle-environment "Testing" --organization "ACME"  
hammer content-view version promote --content-view "Base" --version 1 \  
--to-lifecycle-environment "Production" --organization "ACME"
```

Set executable permissions on the script:

```
# chmod +x sat6-content-init.sh
```

Download a copy of your Subscription Manifest from the Red Hat Customer Portal and run the script on the manifest:

```
# ./sat6-content-init.sh manifest_98f4290e-6c0b-4f37-ba79-3a3ec6e405ba.zip
```

This imports the necessary Red Hat content for the provisioning examples in this guide.

APPENDIX B. ADDITIONAL HOST PARAMETERS FOR HAMMER CLI

This appendix provides some information on additional parameters for the **hammer host create** command.

B.1. COMMON INTERFACE PARAMETERS

These parameters are used with the **--interface** option for all provisioning types:

Parameter	Description	
mac	MAC address for the interface	
ip	IP address for the interface	
type	The type of interface. For example: interface , bmc , or bond	
name	The host name associated with this interface`	
subnet_id	The subnet ID on the Satellite Server	
domain_id	The domain ID on the Satellite Server	
identifier	The device identifier. For example: eth0	
managed	Boolean for managed interfaces. Set to true or false	
primary	Boolean for primary interfaces. Managed hosts needs to have one primary interface. Set to true or false	
provision	Boolean for whether to provision on this interface. Set to true or false	
virtual	Boolean for whether the interface is a VLAN interface. Set to true or false	

Use the following parameters if **virtual** is **true**:

Parameter	Description	
tag	VLAN tag, this attribute has precedence over the subnet VLAN ID. Only for virtual interfaces.	
attached_to	Identifier of the interface to which this interface belongs. For example: eth1 .	

Use the following parameters if **type** is **bond**:

Parameter	Description	
mode	The bonding mode. One of balance-rr , active-backup , balance-xor , broadcast , 802.3ad , balance-tlb , balance-alb	
attached_devices	Identifiers of slave interfaces. For example: [eth1,eth2]	
bond_options	Additional bonding options	

Use the following parameters if **type** is **bmc**:

Parameter	Description	
provider	The BMC provider. Only IPMI is supported	
username	The username for the BMC device	
password	The password for the BMC device	

B.2. EC2 PARAMETERS

Available parameters for **--compute-attributes**:

Parameter	Description	
flavor_id	The EC2 flavor to use	
image_id	The AMI ID of the image to use	

Parameter	Description	
availability_zone	The availability zone within the region of the EC2 provider	
security_group_ids	The IDs for security groups to use	
managed_ip	To utilize a public or private IP	

B.3. LIBVIRT PARAMETERS

Available keys for **--compute-attributes**:

Parameter	Description	
cpus	Number of CPUs	
memory	Amount of memory in bytes	
start	Boolean to start the machine	

Available keys for **--interface**:

Parameter	Description	
compute_type	Either bridge or network	
compute_network / compute_bridge	Name of the network or physical interface	
compute_model	The interface model. One of virtio , rtl8139 , ne2k_pci , pcnet , or e1000	

Available keys for **--volume**:

Parameter	Description	
pool_name	The storage pool to store the volume	
capacity	The capacity of the volume. For example: 10G	

Parameter	Description
format_type	The disk type. Either raw or qcow2

B.4. RED HAT OPENSTACK PLATFORM PARAMETERS

Available keys for **--compute-attributes**:

Parameter	Description
flavor_ref	The flavor to use
image_ref	The image to use
tenant_id	The tenant to use
security_groups	A list of security groups to use
network	The network to connect the instance

B.5. RED HAT VIRTUALIZATION PARAMETERS

Available keys for **--compute-attributes**:

Parameter	Description
cluster	The cluster ID to contain the host
template	The hardware profile to use
cores	The number of CPU cores to use
memory	The amount of memory in bytes
start	Boolean to start the machine

Available keys for **--interface**:

Parameter	Description
compute_name	The interface name. For example: eth0

Parameter	Description	
compute_network	The network in the cluster to use	

Available keys for **--volume**:

Parameter	Description	
size_gb	Volume size in GB	
storage_domain	The storage domain to use	
bootable	Boolean to set the volume as bootable. Only one volume can be bootable	

B.6. VMWARE INTERFACE PARAMETERS

Available keys for **--compute-attributes**:

Parameter	Description	
cpus	Number of CPUs for the host	
corespersocket	Number of cores per CPU socket. Applicable to hosts using hardware versions less than v10.	
memory_mb	Amount of memory in MB	
cluster	Cluster ID for the host	
path	Path to folder to organize the host	
guest_id	Guest OS ID	
scsi_controller_type	ID of the VMware controller	
hardware_version	VMware hardware version ID	
start	Boolean to start the machine	

Available keys for **--interface**:

Parameter	Description	
compute_type	Type of the network adapter. One of VirtualVmxnet , VirtualVmxnet2 , VirtualVmxnet3 , VirtualE1000 , VirtualE1000e , VirtualPCNet32 .	
compute_network	VMware network ID	

Available keys for **--volume**:

Parameter	Description	
datastore	The datastore ID	
name	The name of the volume	
size_gb	The size in GB	
thin	Boolean value to enable thin provisioning	
eager_zero	Boolean value to enable Eager Zero thick provisioning	

APPENDIX C. PROVISIONING FIPS-COMPLIANT HOSTS

Red Hat Satellite 6 supports provisioning hosts that comply with the National Institute of Standards and Technology's [Security Requirements for Cryptographic Modules](#) standard, reference number FIPS 140-2, referred to here as FIPS.

To enable the provisioning of hosts that are FIPS-compliant, complete the following tasks:

- Change the provisioning password hashing algorithm for the operating system
- Create a host group and set a host group parameter to enable FIPS

For more information about creating host groups, see [Creating a Host Group](#) in the *Managing Hosts* guide.

The provisioned hosts have the FIPS-compliant settings applied. To confirm that these settings are enabled, complete the steps in [Section C.3, "Verifying FIPS Mode is Enabled"](#).

C.1. CHANGE THE PROVISIONING PASSWORD HASHING ALGORITHM

To provision FIPS-compliant hosts, you must first set the password hashing algorithm that you use in provisioning to SHA256. This configuration setting must be applied for each operating system you want to deploy as FIPS-compliant.

1. Identify the Operating System IDs.

```
$ hammer os list
```

Example output:

```
---|-----|-----|-----
ID | TITLE      | RELEASE NAME | FAMILY
---|-----|-----|-----
2  | RedHat 6.6  |              | Redhat
3  | RedHat 7.6  |              | Redhat
1  | RedHat 7.7  |              | Redhat
4  | RedHat 6.7  |              | Redhat
---|-----|-----|-----
```

2. Update each operating system's password hash value.

```
$ hammer os update --title Operating_System \
  --password-hash SHA256
```

3. Repeat this command for each of the operating systems, using the matching value in the **TITLE** column:

```
$ hammer os update --title "RedHat version_number" \
  --password-hash SHA256
```

Note that you cannot use a comma-separated list of values.

C.2. SETTING THE FIPS ENABLED PARAMETER

To provision a FIPS-compliant host, you must create a host group and set the host group parameter **fips_enabled** to **true**. If this is not set to **true**, or is absent, the FIPS-specific changes do not apply to the system. You can set this parameter when you provision a host or for a host group.

To set this parameter when provisioning a host, append **--parameters fips_enabled=true** to the Hammer command.

To set this parameter on an existing host group, enter the following command:

```
$ hammer hostgroup set-parameter --name fips_enabled \  
  --value 'true' \  
  --hostgroup prod_servers
```

For more information, see the output of the command **hammer hostgroup set-parameter --help**.

C.3. VERIFYING FIPS MODE IS ENABLED

To verify that FIPS compliance is enabled, after you provision a host, complete the following steps:

1. Log on to the host as **root** or with an admin-level account.
2. Enter the following command:

```
cat /proc/sys/crypto/fips_enabled
```

A value of **1** confirms that FIPS mode is enabled.

APPENDIX D. BUILDING CLOUD IMAGES FOR RED HAT SATELLITE

Use this section to build and register images to Red Hat Satellite.

You can use a preconfigured Red Hat Enterprise Linux KVM guest QCOW2 image:

- [Latest RHEL 7 KVM Guest Image](#)
- [Latest RHEL 6 KVM Guest Image](#)

These images contain **cloud-init**. To function properly, they must use ec2-compatible metadata services for provisioning an SSH key.



NOTE

For the KVM guest images:

- The **root** account in the image is disabled, but **sudo** access is granted to a special user named **cloud-user**.
- There is no **root** password set for this image.

The **root** password is locked in **/etc/shadow** by placing **!!** in the second field.

If you want to create custom Red Hat Enterprise Linux images, see [Creating a Red Hat Enterprise Linux 7 Image](#) and [Creating a Red Hat Enterprise Linux 6 Image](#).

D.1. CREATING CUSTOM RED HAT ENTERPRISE LINUX IMAGES

Prerequisites:

- Use a Linux host machine to create an image. In this example, we use a Red Hat Enterprise Linux 7 Workstation.
- Use **virt-manager** on your workstation to complete this procedure. If you create the image on a remote server, connect to the server from your workstation with **virt-manager**.
- A Red Hat Enterprise Linux 7 or 6 ISO file (see [Red Hat Enterprise Linux 7.4 Binary DVD](#) or [Red Hat Enterprise Linux 6.9 Binary DVD](#)).

For more information about installing a Red Hat Enterprise Linux Workstation, see [Red Hat Enterprise Linux 7 Installation Guide](#).

Before you can create custom images, install the following packages:

- Install **libvirt**, **qemu-kvm** and graphical tools:

```
[root@host]# yum install virt-manager virt-viewer libvirt qemu-kvm
```

- Install the following command line tools:

```
[root@host]# yum install virt-install libguestfs-tools-c
```

**NOTE**

In the following procedures, enter all commands with the **[root@host]#** prompt on the workstation that hosts the **libvirt** environment.

D.2. CREATING A RED HAT ENTERPRISE LINUX 7 IMAGE

Use this section to create an image in the QCOW2 format using a Red Hat Enterprise Linux 7 ISO file.

1. Using your web browser, download the Red Hat Enterprise Linux binary ISO file to a temporary location, for example, the **Downloads** directory.
2. Copy the Red Hat Enterprise Linux binary ISO file to the **/var/lib/libvirt/images/** directory.

```
[root@host]# cp ~/home/user/Downloads/rhel-server-7.4-x86_64-dvd.iso
/var/lib/libvirt/images/
```

3. Verify that **virtbr0** is the virtual bridge:

```
[root@host]# ip a
```

4. Start **libvirtd**:

```
[root@host]# systemctl start libvirtd
```

5. Navigate to the **/var/lib/libvirt/images/** directory:


```
[root@host]# cd /var/lib/libvirt/images/
```

6. Prepare the QEMU image:

```
[root@host]# qemu-img create -f qcow2 rhel7.qcow2 8G
```

7. Start the installation using **virt-install**. Use the following example as a guide:

```
[root@host]# virt-install --virt-type qemu --name rhel7 --ram 2048 \
--cdrom rhel-server-7.4-x86_64-dvd.iso \
--disk rhel7.qcow2,format=qcow2 \
--network=bridge:virbr0 --graphics vnc,listen=0.0.0.0 \
--noautoconsole --os-type=linux --os-variant=rhel7
```

**NOTE**

For GUI users, if the instance does not launch automatically, enter the **virt-manager** command to view the console:

```
[root@host]# virt-manager
```

8. Follow the steps of the Red Hat Enterprise Linux installation wizard.
 - a. For the installation source, add an HTTP link to your repository in Red Hat Satellite, for example
`satellite.example.com/pub/exports/RHEL7/content/dist/rhel/server/7/Server/x86_64/iso/`

satellite.example.com/pub/export/RHEL7/content/dist/rhel/server/7.7/Server/x86_64/os/

- b. For the type of devices your installation uses, select **Auto-detected installation media**
 - c. For the type of installation destination, select **Local Standard Disks**.
 - d. For other storage options, select **Automatically configure partitioning**.
 - e. For software selection, select **Minimal Install**.
 - f. Set the network interface to **ON** to ensure the interface activates on system start.
 - g. Enter a host name, and click **Apply**.
 - h. Enter a **root** password.
9. When the installation completes, reboot the instance and log in as the root user.
 10. Confirm that the network interface is up and that the IP address is assigned:

```
# ip a
```

11. Confirm that the hostname is correct:

```
# hostname
```

12. Create a **/etc/NetworkManager/conf.d/XX-cloud-image.conf** file where *XX* is a two-digit number that indicates order of precedence. Add the following contents to the file:

```
[main]
dns=none
```

13. Proceed to [Configuring a Host for Registration](#).

D.3. CREATING A RED HAT ENTERPRISE LINUX 6 IMAGE

Use this section to create an image in the QCOW2 format using a Red Hat Enterprise Linux 6 ISO file.

1. Start the installation using **virt-install**:

```
[root@host]# qemu-img create -f qcow2 rhel6.qcow2 4G
[root@host]# virt-install --connect=qemu:///system --network=bridge:virbr0 \
--name=rhel6 --os-type linux --os-variant rhel6 \
--disk path=rhel6.qcow2,format=qcow2,size=10,cache=none \
--ram 4096 --vcpus=2 --check-cpu --accelerate \
--hvm --cdrom=rhel-server-6.8-x86_64-dvd.iso
```

This launches an instance and starts the installation process.

**NOTE**

If the instance does not launch automatically, enter the **virt-viewer** command to view the console:

```
[root@host]# virt-viewer rhel6
```

2. Set up the virtual machines as follows:
 - a. At the initial Installer boot menu, select the **Install or upgrade an existing system** option.
 - b. Select the appropriate **Language** and **Keyboard** options.
 - c. When prompted about which type of devices your installation uses, select **Basic Storage Devices**.
 - d. Select a **hostname** for your device. The default host name is **localhost.localdomain**.
 - e. Set a root password.
 - f. Based on the space on the disk, select the type of installation.
 - g. Select the **Basic Server** install, which includes an SSH server.
3. Reboot the instance and log in as the **root** user.
4. Update the **/etc/sysconfig/network-scripts/ifcfg-eth0** file so it only contains the following values:

```
TYPE=Ethernet
DEVICE=eth0
ONBOOT=yes
BOOTPROTO=dhcp
NM_CONTROLLED=no
```

5. Restart the service network:

```
# service network restart
```

6. Proceed to [Configuring a Host for Registration](#).

D.4. CONFIGURING A HOST FOR REGISTRATION

Red Hat Enterprise Linux virtual machines register to Customer Portal Subscription Management by default. You must update each virtual machine configuration so that they receive updates from the correct Satellite Server or Capsule Server.

Prerequisites

- Hosts must be using the following Red Hat Enterprise Linux version:
 - 6.4 or later
 - 7.0 or later

- All architectures of Red Hat Enterprise Linux are supported (i386, x86_64, s390x, ppc_64).
- Ensure that a time synchronization tool is enabled and runs on the Satellite Servers, any Capsule Servers, and the hosts.

- For Red Hat Enterprise Linux 6:

```
# chkconfig ntpd on; service ntpd start
```

- For Red Hat Enterprise Linux 7:

```
# systemctl enable chronyd; systemctl start chronyd
```

- Ensure that the daemon **rhsmcertd** is enabled and running on the hosts.

- For Red Hat Enterprise Linux 6:

```
# chkconfig rhsmcertd on; service rhsmcertd start
```

- For Red Hat Enterprise Linux 7:

```
# systemctl start rhsmcertd
```

To Configure a Host for Registration:

1. Take note of the fully qualified domain name (FQDN) of the Satellite Server or Capsule Server, for example *server.example.com*.
2. On the host, connect to a terminal on the host as the root user
3. Install the consumer RPM from the Satellite Server or Capsule Server to which the host is to be registered. The consumer RPM updates the content source location of the host and allows the host to download content from the content source specified in Red Hat Satellite.

```
# rpm -Uvh http://server.example.com/pub/katello-ca-consumer-latest.noarch.rpm
```

D.5. REGISTERING A HOST

Prerequisites

- Ensure that an activation key that is associated with the appropriate content view and environment exists for the host. For more information, see [Managing Activation Keys](#) in the *Content Management Guide*. By default, an activation key has the **auto-attach** function enabled. The feature is commonly used with hosts used as hypervisors.
- Ensure that the version of the **subscription-manager** utility is 1.10 or higher. The package is available in the standard Red Hat Enterprise Linux repository.
 1. On the Red Hat Enterprise Linux Workstation, connect to a terminal as the root user.
 2. Register the host using Red Hat Subscription Manager:

```
# subscription-manager register --org="My_Organization" --activationkey="MyKey"
```



NOTE

You can use the **--environment** option to override the content view and life cycle environment defined by the activation key. For example, to register a host to the content view "MyView" in a "Development" life cycle environment:

```
# subscription-manager register --org="My_Organization" \
--environment=Development/MyView \
--activationkey="MyKey"
```



NOTE

For Red Hat Enterprise Linux 6.3 hosts, the release version defaults to Red Hat Enterprise Linux 6 Server and must point to the 6.3 repository.

1. On Red Hat Satellite, select **Hosts** > **Content Hosts**.
2. Select the name of the host that needs to be changed.
3. In the **Content Host Content** section click the edit icon to the right of **Release Version**.
4. Select "6.3" from the **Release Version** drop-down menu.
5. Click **Save**.

D.6. INSTALLING THE KATELLO AGENT

Use the following procedure to install the Katello agent on a host registered to Satellite 6. The **katello-agent** package depends on the goferd package that provides the **goferd service**. This service must be enabled so that the Red Hat Satellite Server or Capsule Server can provide information about errata that are applicable for content hosts.

Prerequisites

The **Satellite Tools** repository must be enabled, synchronized to the Red Hat Satellite Server, and made available to your hosts as it provides the required packages.

To Install the Katello Agent

1. Install the **katello-agent** RPM package using the following command:

```
# yum install katello-agent
```

2. Ensure goferd is running:

```
# systemctl start goferd
```

D.7. INSTALLING THE PUPPET AGENT

Use this section to install and configure the Puppet agent on a host. When you have correctly installed and configured the Puppet agent, you can navigate to **Hosts** > **All hosts** to list all hosts visible to Red Hat Satellite Server.

1. Install the Puppet agent RPM package using the following command:

```
# yum install puppet
```

2. Configure the puppet agent to start at boot:
On Red Hat Enterprise Linux 6:

```
# chkconfig puppet on
```

On Red Hat Enterprise Linux 7:

```
# systemctl enable puppet
```

D.8. COMPLETING THE RED HAT ENTERPRISE LINUX 7 IMAGE

1. Update the system:

```
# yum update
```

2. Install the **cloud-init** packages:

```
# yum install cloud-utils-growpart cloud-init
```

3. Open the **/etc/cloud/cloud.cfg** configuration file:

```
# vi /etc/cloud/cloud.cfg
```

4. Under the heading **cloud_init_modules**, add:

```
- resolv-conf
```

The **resolv-conf** option automatically configures the **resolv.conf** when an instance boots for the first time. This file contains information related to the instance such as **nameservers**, **domain** and other options.

5. Open the **/etc/sysconfig/network** file:

```
# vi /etc/sysconfig/network
```

6. Add the following line to avoid problems accessing the EC2 metadata service:

```
NOZEROCONF=yes
```

7. Un-register the virtual machine so that the resulting image does not contain the same subscription details for every instance cloned based on it:

```
# subscription-manager repos --disable=*  
# subscription-manager unregister
```

8. Power off the instance:

```
# poweroff
```

9. On your Red Hat Enterprise Linux Workstation, connect to the terminal as the root user and navigate to the **/var/lib/libvirt/images/** directory:

```
[root@host]# cd /var/lib/libvirt/images/
```

10. Reset and clean the image using the **virt-sysprep** command so it can be used to create instances without issues:

```
[root@host]# virt-sysprep -d rhel7
```

11. Reduce image size using the **virt-sparsify** command. This command converts any free space within the disk image back to free space within the host:

```
[root@host]# virt-sparsify --compress rhel7.qcow2 rhel7-cloud.qcow2
```

This creates a new **rhel7-cloud.qcow2** file in the location where you enter the command.

D.9. COMPLETING THE RED HAT ENTERPRISE LINUX 6 IMAGE

1. Update the system:

```
# yum update
```

2. Install the **cloud-init** packages:

```
# yum install cloud-utils-growpart cloud-init
```

3. Edit the **/etc/cloud/cloud.cfg** configuration file and under **cloud_init_modules** add:

```
- resolv-conf
```

The **resolv-conf** option automatically configures the **resolv.conf** configuration file when an instance boots for the first time. This file contains information related to the instance such as **nameservers**, **domain**, and other options.

4. To prevent network issues, create the **/etc/udev/rules.d/75-persistent-net-generator.rules** file as follows:

```
# echo "#" > /etc/udev/rules.d/75-persistent-net-generator.rules
```

This prevents **/etc/udev/rules.d/70-persistent-net.rules** file from being created. If **/etc/udev/rules.d/70-persistent-net.rules** is created, networking might not function properly when booting from snapshots (the network interface is created as "eth1" rather than "eth0" and IP address is not assigned).

5. Add the following line to **/etc/sysconfig/network** to avoid problems accessing the EC2 metadata service:

```
NOZEROCONF=yes
```

6. Un-register the virtual machine so that the resulting image does not contain the same subscription details for every instance cloned based on it:

```
# subscription-manager repos --disable=*  
# subscription-manager unregister  
# yum clean all
```

7. Power off the instance:

```
# poweroff
```

8. On your Red Hat Enterprise Linux Workstation, log in as root and reset and clean the image using the **virt-sysprep** command so it can be used to create instances without issues:

```
[root@host]# virt-sysprep -d rhel6
```

9. Reduce image size using the **virt-sparsify** command. This command converts any free space within the disk image back to free space within the host:

```
[root@host]# virt-sparsify --compress rhel6.qcow2 rhel6-cloud.qcow2
```

This creates a new **rhel6-cloud.qcow2** file in the location where you enter the command.



NOTE

You must manually resize the partitions of instances based on the image in accordance with the disk space in the flavor that is applied to the instance.

D.10. NEXT STEPS

- Repeat the procedures for every image that you want to provision with Satellite.
- Move the image to the location where you want to store for future use.