

ZZALOG

Logging Application



User Guide

v3.6.1-rc1 16^h July 2025

Introduction

ZZALOG is a logging application that provides the following functionality:

1. Records QSOs in a logging database.
2. Allows the database to be searched.
3. Allows the real-time and off-line entry of QSO records.
4. Allows the user to monitor “worked-before” status in real-time.
5. Exchanges data with QSL web-sites such as eQSL.cc and Logbook of the World.
6. Tracks the status of electronic and paper QSL cards and displaying images of received cards.
7. Includes: a shack clock; weather report and band plan view.
8. Interfaces with a number of modem applications (WSJT-X, FLDIGI etc).

ZZALOG maintains the QSO records in the ADIF .adi format. This allows manual editing, if done carefully. ZZALOG may not be tolerant of error introduced by manual editing.

Although ADIF .adi format does not support the use of non-ASCII character sets, ZZALOG provides support for all Unicode characters coded in UTF-8 format. Exchange of such data with other applications may result in errors.

This document can be opened at any time from the menu:




Illustration 1: Opening this document from the menu

Table of Contents

Introduction.....	2
Installation.....	3
Quick-start Guide.....	3
Starting ZZALOG.....	3
Operating.....	7
Connecting to a rig.....	7
Operating.....	8
Logging the QSO.....	10
Detailed User Guide.....	11

Installation

Installation can currently only be done on an ad-hoc basis. This document currently assumes that installation has already been done by the application's author.

The application has been compiled for Windows and Linux environments.

Quick-start Guide

Starting ZZALOG

On Windows, ZZALOG may be started by double clicking on the icon. It may also be started from a terminal by advanced users.

On starting, a banner window is displayed:




Illustration 2: Banner

Illustration 2: Banner shows the progress of the application as it is loading all the data needed to run. This window shows the latest message output, the latest error message output and the progress of each stage. In the above image, the application is reading in the latest callsign parsing information file and the banner shows the progress in numerical form and in a clock dial form. The “Full” button, when clicked, expands the display to show a scrollable output of all the messages output.

Once ZZALOG has loaded then two or three more windows are displayed. Firstly there is a log-book style view of the log data:

QSO No.	Date	Start	End	QRG	Band	Mode	Callsign	Sent	Rcvd	Pwr	Name	QTH	Loc	STATE
9140	20250626	184920	191034	145.575000	2M	FM	2M0KRG	59		10		Livingston	IO85FV	
9139	20250626	183245	191034	145.575000	2M	FM	MM7GJY	59+30		10				
9138	20250626	183239	191034	145.575000	2M	FM	MM0KKL	59+5		10				
9137	20250626	183229	191035	145.575000	2M	FM	2M0VSA	59+10		10				
9136	20250626	183213	191035	145.575000	2M	FM	MM0KFR	59+30		10				
9135	20250626	183205	191035	145.575000	2M	FM	GM0ERT	59+20		10				
9134	20250626	183159	191036	145.575000	2M	FM	2M0DIF	59		10				
9133	20250626	183036	191036	145.575000	2M	FM	MS0LIV	59+30		10				
9132	20250626	151711	151811	145.012500	2M	FM	GM0ERT			0				
9131	20250622	213245	213330	7.074400	40M	FT8	2E0MRK	+07	+05	49	Mark	High Wycombe	IO91PP	
9130	20250622	213145	213230	7.074400	40M	FT8	2E0XDZ	-03	-03	49			IO91	
9129	20250622	212945	213030	7.074400	40M	FT8	DL4XT/QRP	-01	+01	49			JO53BO	
9128	20250622	212700	212745	7.074873	40M	FT8	I28IFL	+00	+00	49			JN70SN	
9127	20250622	212230	212415	7.074873	40M	FT8	DG1WWSK	-13	-06	49			JN58	
9126	20250622	212100	212145	7.074873	40M	FT8	DJ7XY	-06	-01	49			JO31	
9125	20250622	211806	211915	7.074873	40M	FT8	SM7OYE	+06	-07	49			JO65	
9124	20250622	211130	211215	7.074873	40M	FT8	EH1HSJ	+06	-10	49			IN73	
9123	20250622	210900	210945	7.074873	40M	FT8	OM/OK8VK	-08	-09	49				
9122	20250622	210700	210745	7.074873	40M	FT8	PY7ZZ	-04	-12	49			HI21	
9121	20250622	210600	210645	7.074873	40M	FT8	IK4ICS	-08	-13	49			JN54	
9120	20250621	201315	201400	21.076147	15M	FT8	UR4QWW	+00	-15	49			KN77NU	
9119	20250621	201046	201130	21.076147	15M	FT8	F5PBG	+08	-02	49			IN78TI	
9118	20250621	194215	194318	28.075832	10M	FT8	7Q6UJ	-10	-17	49				
9117	20250620	203430	203430	14.075832	20M	FT8	M7GGV	-14	-06	50			IO91	
9116	20250620	202930	203130	14.075832	20M	FT8	ON7KEI	-08	-03	50			JO21RF	
9115	20250620	195545	195645	50.314748	6M	FT8	YT7KW	-09	-05	51			KN05EJ	
9114	20250620	195515	195515	50.314748	6M	FT8	OM3RP	-14	-11	51				
9113	20250620	193630	193630	50.314748	6M	FT8	MM/ER1DFV	-14	-24	51			IO75TT	

Illustration 3: Log-book view

In **Illustration 3: Log-book view** a section of the log-book showing the most recent entries is displayed. In this view the data that is presented can be configured by selecting different fields to be displayed. The data can be displayed either in chronological order or in reverse chronological order. More information about this window is provided in **Detailed User Guide** below.

Secondly, a dashboard view is available: in **Illustration 4: Dashboard view** ZZALOG provides the user with the ability to enter new QSOs, edit existing QSOs, browse the log and manage all the data exchange functionality. Briefly, the various panes in this window show:

- “Station” - Location, operator and callsign of current operation.
- “QSO Entry” - Viewing and editing pane for QSO records. In some operations this is replaced by a “QSO Query” or “QSO Browse” view.
- “Previous” - Displays any previous QSOs with the entered callsign.
- “DX?” - Shows the “worked-before” status of the DXCC entity etc.
- “QSL” - Displays the QSL status for this QSO – including displaying any card image.
- “Contest” - Is used for contest operating.
- “Controls” - Displays all the operations available in the current state.
- “Rigs” - Displays the status of any connected rigs.
- “Clocks” - Displays the time in UTC (GMT or Zulu) and local time.
- “Log” - Displays the current status of the file.
- “QSLs” - Allows the control of data exchange with on-line QSL services.
- “Apps” - Provides control of other applications such as digital modems.
- “WX” - Displays the local weather obtained from openweather.org.
- “Bandplan” - Displays the local bandplan information.

More details for each pane is provided in **Detailed User Guide** below.

ZZALOG 3.6.0 (3.6.1-rc1): Operating Dashboard

QSO Data

Station QTH Show Operator Show Station Callsign Show

QSO Entry - OM/OK8VK - read only

MY_RIG MY_ANTENNA

QSO_DATE TIME_ON

TIME_OFF CALL

FREQ MODE

TX_PWR RST_RCVD

RST_SENT NAME

QTH GRIDSQUAR

CNTY MY_CITY

MY_GRIDSQ OPERATOR

MY_IOTA CONT

STATION_CA CONTEST_ID

NOTES

Controls

Edit QSO Cancel Activate Start QSO

Edit Net Start Net Browse Log

IC-705 IC-7300

☒ No rig specified CAT

☐ Display instantaneous

Rig

Antenna

Connection

UTC GMT Summer Time

08:41:18

Wed 16 Jul 2025

Log QSLs Apps WX Bandplan

☐ Only handle selected QSO

eQSL ☒

LotW ☒

ClubLog ☒

QRZ.com ☒

Cards ☒

e-Mails ☒

© Philip Rose GM3ZZA 2018-2025. All rights reserved. gm3zza@btinternet.com

Illustration 4: Dashboard view

More detail of each pane is provided later.

Finally, if ZZALOG is so configured, a third window is displayed. This is used, for example, for a club operation where the information about individual operators is required:

Configuration: Define QTH, Operator and working calligns

File Locations Web/Network Fields **Station** User config QSL Design Contest Def. All Settings

QTHs **Operators** Callsigns

Please select or enter the initials of the person intending to operate (NECESSARY for a club station). Add the operator's name and callsign.

Id

Brief Comment

Enter data below if you want the information saved in the log file

Name

Callsign

Save OK Cancel

Illustration 5: Operator selection

In **Illustration 5: Operator selection** the user is being asked to identify themselves. The field labeled “Id” has a drop-down menu so that the user can select themselves or if not listed type in their initials (or callsign suffix). The user can then enter their name and callsign if mandated by the station policy. In **Illustration 6: Filled in operator details** below this information has been filled in.

Id PVR

Brief Comment

Enter data below if you want the information save

Name Phil

Callsign GM3ZZA

Illustration 6: Filled in operator details

To start operating we shall need to connect to a rig.

Operating

Connecting to a rig.

ZZALOG uses the hamlib library for its rig connectivity. The hamlib library is a suite of procedure calls that provides a common interface for most rigs' CAT interfaces. It can also interface with a number of other applications that provide access to rigs' CAT interfaces. Most CAT interfaces use some form of serial interface, and shared access to a serial interface by different applications (such as ZZALOG and any digital modem applications – PSK, FT8, SSTV etc) requires another helper application such as flrig.

ZZALOG can provide a means of starting this helper application, which requires the use of scripts. The rest of this section assumes that FLRig has been launched.




Illustration 7: Rig control

In the bottom left of the dashboard is **Illustration 7: Rig control** screen. The user should select the rig that they are interested in. In this case an ICOM IC-7300. The “Start” button will launch a script, if written, to open up the FLRig application. The “Select” button allows configuration of the interface. These two features will be described in **Detailed User Guide** below.

Assuming that FLRig has been launched then clicking the “Connect” button will connect to that application. **Illustration 8: FLRig connected** shows ZZALOG connected to FLRig and the latter's display alongside. ZZALOG is showing the same frequency, mode, TX power and S-meter reading as FLRig, and as the rig itself. ZZALOG will normally show the highest S-meter and TX power meter readings over the most recent few polls of the rig, and retain the last S-meter reading from a RX period and the last TX Power reading from a TX period.

Note that the “Connect” button has become a “Disconnect” button.




Illustration 8: FLRig connected

Operating

To operate, the user must place ZZALOG into the correct mode. This is achieved by clicking the “Activate” button on the “Controls” section – see **Illustration 4: Dashboard view**. This changes the “QSO Entry” section:

QSO Data

QTH Show Operator Show

QSO Entry - prepared for real-time logging.

MY_RIG	IC-7300	MY_ANTENNA	Trap dipole 10/1
QSO_DATE	20250715	TIME_ON	160352
TIME_OFF		CALL	
FREQ	28.050000	MODE	CW
TX_PWR	0	NAME	
QTH		RST_RCVD	
RST_SENT		GRIDSQUARE	
COUNTRY		APP_ZZA_OP	
MY_NAME	Phil	OPERATOR	GM3ZZA
DXCC		MY_GRIDSQU	IO85FU69
MY_CITY	Livingston	BAND	10M

NOTES

Controls

Start QSO	Add QSO	Edit QSO	Copy QSO	Clone QSO	Quit	Save
View QSO						

Illustration 9: Dashboard ready for operation (“Active”)

Illustration 9: Dashboard ready for operation (“Active”) shows the “QSO Entry” section ready for entry. All the fields shown may be swapped for other fields by selecting the drop-down arrow alongside each. Each field has an associated data entry widget: for some of these the drop-down arrow opens up a menu of possible values:

Illustration 10: Menu of choices

Illustration 11: Menu of formats

Illustration 10: Menu of choices and **Illustration 11: Menu of formats** show examples of this selection.

At this point it is also possible to check on the “worked-before” status of a call. Typing in a callsign that has been copied will result in that call being checked against the history contained in the log. Examples are below:

Illustration 12: Checking "worked-before" status for a call

Illustration 12: Checking "worked-before" status for a call shows the callsign being checked. In this case the station has been worked before but not on the band on the rig (10m – whereas they were worked before on 40m) or on the mode (FT8 versus CW).

Illustration 13: Checking "worked-before" status for a DXCC entity shows the call being decoded as in DXCC Suriname, continent SA (South America) and CQ Zone 9. All three of these have been worked before, but this shows that Suriname is a new DXCC on 10m and also on CW. Similarly for CQ Zone 9. South America has been worked on 10m but is a new continent on CW. As the Locator (Gridsquare) information has not been supplied, it cannot be checked.

QSO Entry - prepared for real-time logging.

MY_RIG	IC-7300	MY_ANTENNA	D/15/20/30/40m
QSO_DATE	20250715	TIME_ON	184400
TIME_OFF		CALL	PZ2ZZ
FREQ	28.050000	MODE	CW
TX_PWR	0	NAME	Fred
QTH		RST_RCVD	
RST_SENT		GRIDSQUARE	
COUNTRY	SURINAME	APP_ZZ_OP	
MY_NAME	Phil	OPERATOR	GM3ZZA
QSL_RCVD		MY_GRIDSQU.	IO85FU69
MY_CITY	Livingston	BAND	10M

NOTES

Previous **X** **DX?** **QSL** **Contest**

PZ2ZZ **QRZ.com**

PZ: SURINAME
Default decode
SA: CQ Zone 9. Loc: 4°N 56°W (PFX)
Distance 7395km, Bearing 240°

Worked Before?

GM3ZZA	ANY	10M	CW
PZ	✓	NEW	NEW
Grid	?	?	?
CQZ 9	✓	NEW	NEW
SA	✓	✓	NEW

Illustration 13: Checking "worked-before" status for a DXCC entity

Logging the QSO

Controls

Start QSO	Add QSO	Edit QSO	Copy QSO	Clone QSO	Quit	Save	Delete QSO	Start Net	Browse Log
View QSO									

Illustration 14: Commands in "Active" state

In the "Active" state the commands available are:

"Start QSO" - moves ZZALOG to "Enter QSO" state with any details already typed in are kept.

"Add QSO" - will start logging a QSO that has already occurred.

"Edit QSO" - will enable editing a QSO that has already been logged.

"Delete QSO" - will remove the QSO from the log.

"View QSO" - will open the selected QSO for viewing – and checking DXCC status etc.

Clicking "Start QSO" will cause the QSO date and time and the information obtained from the rig to become fixed. It also makes a new set of commands available:

Controls

Save	Save & View	Save & New	Save & Edit	Quit QSO	Start Net	U/d Station	B4?	DX?	QRZ.com

Illustration 15: Commands in "Enter QSO" state

"Save" - completes the logging, by setting TIME_OFF field and reverts to "Active" state.

"Save & View" - saves the logging, and keeps the QSO open for viewing.

"Save & New" - saves the logging, and starts a new QSO.

"Save & Edit" - saves the logging, but keeps the QSO in edit mode for further updates.

“Quit QSO” - cancels the logging and removes the QSO from the log.

Detailed User Guide

To be supplied