



Red Hat OpenStack Platform 16.1

Overcloud Parameters

Parameters for customizing the core template collection for a Red Hat OpenStack Platform overcloud

Red Hat OpenStack Platform 16.1 Overcloud Parameters

Parameters for customizing the core template collection for a Red Hat OpenStack Platform overcloud

OpenStack Team
rhos-docs@redhat.com

Legal Notice

Copyright © 2020 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux[®] is the registered trademark of Linus Torvalds in the United States and other countries.

Java[®] is a registered trademark of Oracle and/or its affiliates.

XFS[®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL[®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js[®] is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack[®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This guide provides parameters for customizing the overcloud in Red Hat OpenStack Platform. Use this guide in conjunction with the Advanced Overcloud Customization guide.

Table of Contents

CHAPTER 1. CORE OVERCLOUD PARAMETERS	3
CHAPTER 2. ROLE-BASED PARAMETERS	7
CHAPTER 3. DEBUG PARAMETERS	9
CHAPTER 4. POLICY PARAMETERS	10
CHAPTER 5. KERNEL PARAMETERS	11
CHAPTER 6. CEPH STORAGE PARAMETERS	13
CHAPTER 7. BLOCK STORAGE (CINDER) PARAMETERS	18
CHAPTER 8. IMAGE STORAGE (GLANCE) PARAMETERS	22
CHAPTER 9. ORCHESTRATION (HEAT) PARAMETERS	25
CHAPTER 10. DASHBOARD (HORIZON) PARAMETERS	28
CHAPTER 11. BARE METAL (IRONIC) PARAMETERS	30
CHAPTER 12. IDENTITY (KEYSTONE) PARAMETERS	35
CHAPTER 13. KEY MANAGER (BARABICAN) PARAMETERS	39
CHAPTER 14. SHARED FILE SERVICE (MANILA) PARAMETERS	42
CHAPTER 15. MESSAGING PARAMETERS	43
CHAPTER 16. NETWORKING (NEUTRON) PARAMETERS	44
CHAPTER 17. COMPUTE (NOVA) PARAMETERS	49
CHAPTER 18. OBJECT STORAGE (SWIFT) PARAMETERS	61
CHAPTER 19. TIME PARAMETERS	63

CHAPTER 1. CORE OVERCLOUD PARAMETERS

Parameter	Description
AddVipsToEtcHosts	Set to true to append per network VIPs to /etc/hosts on each node. The default value is True .
CloudDomain	The DNS domain used for the hosts. This must match the <code>overcloud_domain_name</code> configured on the undercloud. The default value is localdomain .
CloudName	The DNS name of this cloud. The default value is overcloud.localdomain .
CloudNameCtlplane	The DNS name of this cloud's control plane endpoint. The default value is overcloud.ctlplane.localdomain .
CloudNameInternal	The DNS name of this cloud's internal API endpoint. The default value is overcloud.internalapi.localdomain .
CloudNameStorage	The DNS name of this cloud's storage endpoint. For example, <i>ci-overcloud.storage.tripleo.org</i> . The default value is overcloud.storage.localdomain .
CloudNameStorageManagement	The DNS name of this cloud's storage management endpoint. The default value is overcloud.storagemgmt.localdomain .
ControlFixedIPs	Defines a fixed VIP for the Control Plane. Value uses the following format: [{ip_address:'1.2.3.4'}]
ControlPlaneSubnet	The name of the undercloud OpenStack Networking (neutron) control plane subnet. The default value is ctlplane-subnet .
ControlPlaneSubnetCidr	The subnet CIDR of the control plane network. The parameter is automatically resolved from the ctlplane subnet's cidr attribute.
DeployIdentifier	Setting this to a unique value will re-run any deployment tasks that perform configuration on a OpenStack Orchestration (heat) stack-update .
DeploymentServerBlacklist	List of server hostnames to blacklist from any triggered deployments.
EndpointMapOverride	Can be used to override the calculated EndpointMap.

Parameter	Description
ExternalVirtualFixedIPs	Control the IP allocation for the ExternalVirtualInterface port. For example, <code>[{ip_address:'1.2.3.4'}]</code> .
ExtraConfig	Additional hiera configuration to inject into the cluster.
ExtraHostFileEntries	List of extra hosts entries to be appended to <code>/etc/hosts</code> .
GlobalConfigExtraMapData	Map of extra global_config_settings data to set on each node.
HypervisorNeutronPhysicalBridge	An Open vSwitch bridge to create on each hypervisor. This defaults to br-ex , which is the same as the control plane nodes. This ensures uniform configuration of the Open vSwitch agent. Typically should not need to be changed. The default value is br-ex .
HypervisorNeutronPublicInterface	What interface to add to the HypervisorNeutronPhysicalBridge . The default value is nic1 .
InternalApiVirtualFixedIPs	Control the IP allocation for the InternalApiVirtualInterface port. Value uses the following format: <code>[{ip_address:'1.2.3.4'}]</code>
NetworkDeploymentActions	OpenStack Orchestration (heat) action when to apply network configuration changes. The default value is ['CREATE'] .
NeutronControlPlaneID	ID or name for Control Plane ctlplane network. The default value is ctlplane .
NeutronPhysicalBridge	An OVS bridge to create for accessing external networks. The default value is br-ex .
NeutronPublicInterface	The interface to attach to the external bridge. The default value is nic1 .
NodeCreateBatchSize	Maximum batch size for creating nodes. It is recommended to not exceed a batch size of 32 nodes. The default value is 30 .
NovaAdditionalCell	Whether this is an cell additional to the default cell. The default value is False .

Parameter	Description
NovaLocalMetadataPerCell	Indicates that the nova-metadata API service has been deployed per-cell, so that we can have better performance and data isolation in a multi-cell deployment. Users should consider the use of this configuration depending on how OpenStack Networking (neutron) is setup. If networks span cells, you might need to run nova-metadata API service globally. If your networks are segmented along cell boundaries, then you can run nova-metadata API service per cell. When running nova-metadata API service per cell, you should also configure each OpenStack Networking (neutron) metadata-agent to point to the corresponding nova-metadata API service. The default value is False .
OVNDBsVirtualFixedIPs	Control the IP allocation for the virtual IP used by OVN DBs. For example, <code>[{ip_address:'1.2.3.4'}]</code> .
PublicVirtualFixedIPs	Control the IP allocation for the PublicVirtualInterface port. Value uses the following format: <code>[{ip_address:'1.2.3.4'}]</code>
RabbitCookieSalt	Salt for the RabbitMQ cookie. Change to force the randomly generated RabbitMQ cookie to change. The default value is unset .
RedisVirtualFixedIPs	Control the IP allocation for the virtual IP used by Redis. Value uses the following format: <code>[{ip_address:'1.2.3.4'}]</code>
ServerMetadata	Extra properties or metadata passed to OpenStack Compute (nova) for the created nodes in the overcloud. Accessible through the OpenStack Compute (nova) metadata API.
StorageMgmtVirtualFixedIPs	Control the IP allocation for the StorageMgmtVirtualInterface port. Value uses the following format: <code>[{ip_address:'1.2.3.4'}]</code>
StorageVirtualFixedIPs	Control the IP allocation for the StorageVirtualInterface port. Value uses the following format: <code>[{ip_address:'1.2.3.4'}]</code>
UndercloudHostsEntries	List of undercloud hosts entries to be appended to <code>/etc/hosts</code> . The value is populated with the HEAT_HOSTS entries on the undercloud by tripleoclient when running deploy.

Parameter	Description
UpdateIdentifier	Set to a previously unused value during stack-update triggers package update on all nodes.

CHAPTER 2. ROLE-BASED PARAMETERS

Substitute `_ROLE_` with the name of the role. For example, for `_ROLE_Count` use **ControllerCount**.

Parameter	Description
<code>_ROLE_AnyErrorsFatal</code>	Sets the any_errors_fatal value when running config-download Ansible playbooks. The default value is True .
<code>_ROLE_Count</code>	The number of nodes to deploy in a role. The default value is 1 .
<code>_ROLE_ExtraConfig</code>	Role specific additional hiera configuration to inject into the cluster.
<code>_ROLE_ExtraGroupVars</code>	Optional extra Ansible group vars.
<code>_ROLE_HostnameFormat</code>	Format for node hostnames. Note that %index% is translated into the index of the node (e.g 0/1/2) and %stackname% is replaced with the stack name (e.g overcloud). The default value is %stackname%_role_%index% .
<code>_ROLE_MaxFailPercentage</code>	Sets the max_fail_percentage value when running config-download Ansible playbooks. The default value is 0 .
<code>_ROLE_NetworkDeploymentActions</code>	OpenStack Orchestration (heat) action when to apply network configuration changes.
<code>_ROLE_Parameters</code>	Optional Role Specific parameters to be provided to service.
<code>_ROLE_RemovalPolicies</code>	List of resources to be removed from the role's ResourceGroup when doing an update that requires removal of specific resources.
<code>_ROLE_RemovalPoliciesMode</code>	How to handle change to RemovalPolicies for <i>ROLE</i> ResourceGroup when doing an update. Default mode <i>append</i> will append to the existing blacklist and <i>update</i> would replace the blacklist. The default value is append .
<code>_ROLE_SchedulerHints</code>	Optional scheduler hints to pass to OpenStack Compute (nova).

Parameter	Description
_ROLE_Services	A list of service resources (configured in the OpenStack Orchestration (heat) resource_registry) which represent nested stacks for each service that should get installed on the <i>ROLE</i> role.

CHAPTER 3. DEBUG PARAMETERS

These parameters allow you to set debug mode on a per-service basis. The **Debug** parameter acts as a global parameter for all services and the per-service parameters can override the effects of global parameter on individual services.

Parameter	Description
BarbicanDebug	Set to True to enable debugging OpenStack Key Manager (barbican) service.
CinderDebug	Set to True to enable debugging on OpenStack Block Storage (cinder) services.
ConfigDebug	Whether to run configuration management (e.g. Puppet) in debug mode. The default value is False .
Debug	Set to True to enable debugging on all services. The default value is False .
GlanceDebug	Set to True to enable debugging OpenStack Image Storage (glance) service.
HeatDebug	Set to True to enable debugging OpenStack Orchestration (heat) services.
HorizonDebug	Set to True to enable debugging OpenStack Dashboard (horizon) service. The default value is False .
IronicDebug	Set to True to enable debugging OpenStack Bare Metal (ironic) services.
KeystoneDebug	Set to True to enable debugging OpenStack Identity (keystone) service.
ManilaDebug	Set to True to enable debugging OpenStack Shared File Systems (manila) services.
NeutronDebug	Set to True to enable debugging OpenStack Networking (neutron) services.
NovaDebug	Set to True to enable debugging OpenStack Compute (nova) services.
SaharaDebug	Set to True to enable debugging OpenStack Clustering (sahara) services.

CHAPTER 4. POLICY PARAMETERS

These parameters allow you to set policies on a per-service basis.

Parameter	Description
BarbicanPolicies	A hash of policies to configure for OpenStack Key Manager (barbican).
CinderApiPolicies	A hash of policies to configure for OpenStack Block Storage (cinder) API.
GlanceApiPolicies	A hash of policies to configure for OpenStack Image Storage (glance) API.
HeatApiPolicies	A hash of policies to configure for OpenStack Orchestration (heat) API.
IroniApiPolicies	A hash of policies to configure for OpenStack Bare Metal (ironic) API.
KeystonePolicies	A hash of policies to configure for OpenStack Identity (keystone).
NeutronApiPolicies	A hash of policies to configure for OpenStack Networking (neutron) API.
NovaApiPolicies	A hash of policies to configure for OpenStack Compute (nova) API.
SaharaApiPolicies	A hash of policies to configure for OpenStack Clustering (sahara) API.

CHAPTER 5. KERNEL PARAMETERS

Parameter	Description
BridgeNfCallArpTables	Configures sysctl net.bridge.bridge-nf-call-arp tables key. The default value is 1 .
BridgeNfCallIp6Tables	Configures sysctl net.bridge.bridge-nf-call-ip6tables key. The default value is 1 .
BridgeNfCallIpTables	Configures sysctl net.bridge.bridge-nf-call-iptables key. The default value is 1 .
ExtraKernelModules	Hash of extra kernel modules to load.
ExtraKernelPackages	List of extra kernel related packages to install.
ExtraSysctlSettings	Hash of extra sysctl settings to apply.
InotifyInstancesMax	Configures sysctl fs.inotify.max_user_instances key. The default value is 1024 .
KernelDisableIPv6	Configures sysctl net.ipv6.{default/all}.disable_ipv6 keys. The default value is 0 .
KernelIpForward	Configures net.ipv4.ip_forward key. The default value is 1 .
KernelIpNonLocalBind	Configures net.ipv{4,6}.ip_nonlocal_bind key. The default value is 1 .
KernelPidMax	Configures sysctl kernel.pid_max key. The default value is 1048576 .
NeighbourGcThreshold1	Configures sysctl net.ipv4.neigh.default.gc_thresh1 value. This is the minimum number of entries to keep in the ARP cache. The garbage collector will not run if there are fewer than this number of entries in the cache. The default value is 1024 .
NeighbourGcThreshold2	Configures sysctl net.ipv4.neigh.default.gc_thresh2 value. This is the soft maximum number of entries to keep in the ARP cache. The garbage collector will allow the number of entries to exceed this for 5 seconds before collection will be performed. The default value is 2048 .

Parameter	Description
NeighbourGcThreshold3	Configures sysctl net.ipv4.neigh.default.gc_thresh3 value. This is the hard maximum number of entries to keep in the ARP cache. The garbage collector will always run if there are more than this number of entries in the cache. The default value is 4096 .

CHAPTER 6. CEPH STORAGE PARAMETERS

Parameter	Description
CephAnsibleDisksConfig	Disks configuration settings for ceph-ansible . The default value is {'devices': ['/dev/vdb'], 'osd_scenario': 'lvm', 'osd_objectstore': 'bluestore'} .
CephAnsibleEnvironmentVariables	Mapping of Ansible environment variables to override defaults.
CephAnsibleExtraConfig	Extra vars for the ceph-ansible playbook.
CephAnsiblePlaybook	List of paths to the ceph-ansible playbooks to execute. If not specified, the playbook will be determined automatically depending on type of operation being performed (deploy/update/upgrade). The default value is ['default'] .
CephAnsiblePlaybookVerbosity	The number of -v , -vv , etc. passed to ansible-playbook command. The default value is 1 .
CephAnsibleRepo	The repository that should be used to install the right ceph-ansible package. This value can be used by tripleo-validations to double check the right ceph-ansible version is installed. The default value is rhceph-4-tools-for-rhel-8-x86_64-rpms .
CephAnsibleSkipTags	List of ceph-ansible tags to skip. The default value is package-install,with_pkg .
CephAnsibleWarning	In particular scenarios we want this validation to show the warning but don't fail because the package is installed on the system but repos are disabled. The default value is True .
CephClientKey	The Ceph client key. Currently only used for external Ceph deployments to create the openstack user keyring. Can be created with: ceph-authtool --gen-print-key
CephClusterFSID	The Ceph cluster FSID. Must be a UUID.
CephClusterName	The Ceph cluster name. The default value is ceph .
CephConfigOverrides	Extra configuration settings to dump into ceph.conf .
CephDashboardAdminPassword	Admin password for the dashboard component.

Parameter	Description
CephDashboardAdminRO	Parameter used to set a read-only admin user. The default value is True .
CephDashboardAdminUser	Admin user for the dashboard component. The default value is admin .
CephEnableDashboard	Parameter used to trigger the dashboard deployment. The default value is False .
CephExternalMonHost	List of externally managed Ceph Mon Host IPs. Only used for external Ceph deployments.
CephExternalMultiConfig	<p>List of maps describing extra overrides which will be applied when configuring extra external Ceph clusters. If this list is non-empty, ceph-ansible will run an extra count(list) times using the same parameters as the first run except each parameter within each map will override the defaults. If the following were used, the second run would configure the overcloud to also use the ceph2 cluster with all the previous parameters except</p> <p>/etc/ceph/ceph2.conf would have a mon_host entry containing the value of external_cluster_mon_ips below, and not the default CephExternalMonHost. Subsequent ceph-ansible runs are restricted to just ceph clients. CephExternalMultiConfig may not be used to deploy additional internal Ceph clusters within one OpenStack Orchestration (heat) stack. The map for each list should contain not tripleo-heat-template parameters but ceph-ansible parameters. - cluster: <i>ceph2</i> fsid: <i>e2cba068-5f14-4b0f-b047-acf375c0004a</i> external_cluster_mon_ips: <i>172.18.0.5,172.18.0.6,172.18.0.7</i> keys: - name: "client.openstack" caps: mgr: "allow *" mon: "profile rbd" osd: "osd: profile rbd pool=volumes, profile rbd pool=backups, profile rbd pool=vms, profile rbd pool=images" key: "AQCwmeRcAAAAABAA6SQU/bGqFjLfLro5KxrB1Q==" mode: "O600" dashboard_enabled: false.</p>
CephExtraKeys	<p>List of maps describing extra keys which will be created on the deployed Ceph cluster. Uses ceph-ansible/library/ceph_key.py ansible module. Each item in the list must be in the following example format - name: "client.glance" caps: mgr: "allow *" mon: "profile rbd" osd: "profile rbd pool=images" key: "AQBrgQ9eAAAAABAav84zEilJYZPNuJ0lwn9Ndg==" mode: "O600".</p>
CephGrafanaAdminPassword	Admin password for grafana component.

Parameter	Description
CephIPv6	Enables Ceph daemons to bind to IPv6 addresses. The default value is False .
CephManilaClientKey	The Ceph client key. Can be created with: ceph-authtool --gen-print-key
CephMsgrSecureMode	Enable Ceph msgr2 secure mode to enable on-wire encryption between Ceph daemons and also between Ceph clients and daemons. The default value is False .
CephOsdPercentageMin	The minimum percentage of Ceph OSDs which must be running and in the Ceph cluster, according to ceph osd stat, for the deployment not to fail. Used to catch deployment errors early. Set this value to 0 to disable this check. The default value is 66 .
CephPoolDefaultPgNum	Default placement group size to use for the RBD pools. The default value is 128 .
CephPoolDefaultSize	Default minimum replication for RBD copies. The default value is 3 .
CephPools	Override settings for one of the predefined pools or to create additional ones. Example: { "volumes": { "size": 5, "pg_num": 128, "pgp_num": 128 } }
CephRbdMirrorConfigure	Perform mirror configuration between local and remote pool. The default value is True .
CephRbdMirrorCopyAdminKey	Copy the admin key to all nodes. The default value is False .
CephRbdMirrorPool	Name of the local pool to mirror to remote cluster.
CephRbdMirrorRemoteCluster	The name given to the remote Ceph cluster from the local cluster. Keys reside in the /etc/ceph directory. The default value is not-ceph .
CephRbdMirrorRemoteUser	The rbd-mirror daemon needs a user to authenticate with the remote cluster. By default, this key should be available under /etc/ceph/<remote_cluster>.client.<remote_user>.keyring .
CephRgwClientName	The client name for the RADOSGW service." The default value is radosgw .

Parameter	Description
CephRgwKey	The cephx key for the RADOSGW client. Can be created with <code>ceph-authtool --gen-print-key</code> .
CephValidationDelay	Interval (in seconds) in between validation checks. The default value is 30 .
CephValidationRetries	Number of retry attempts for Ceph validation. The default value is 40 .
CinderBackupBackend	The short name of the OpenStack Block Storage (cinder) Backup backend to use. The default value is swift .
CinderBackupRbdPoolName	Pool to use if Block Storage (cinder) Backup is enabled. The default value is backups .
CinderEnableRbdBackend	Whether to enable or not the Rbd backend for OpenStack Block Storage (cinder). The default value is False .
CinderRbdExtraPools	List of extra Ceph pools for use with RBD backends for OpenStack Block Storage (cinder). An extra OpenStack Block Storage (cinder) RBD backend driver is created for each pool in the list. This is in addition to the standard RBD backend driver associated with the CinderRbdPoolName.
CinderRbdPoolName	Pool to use for Block Storage (cinder) service. The default value is volumes .
DeploymentServerBlacklist	List of server hostnames to blacklist from any triggered deployments.
GlanceBackend	The short name of the OpenStack Image Storage (glance) backend to use. Set to rbd to use Ceph Storage. The default value is swift .
GlanceRbdPoolName	Pool to use for Image Storage (glance) service. The default value is images .
GnocchiBackend	The short name of the OpenStack Telemetry Metrics (gnocchi) backend to use. Should be one of swift, rbd, file or s3. The default value is swift .
GnocchiRbdPoolName	Pool to use for Telemetry storage. The default value is metrics .

Parameter	Description
LocalCephAnsibleFetchDirectoryBackup	Filesystem path on undercloud to persist a copy of the data from the ceph-ansible fetch directory. Used as an alternative to backing up the <code>fetch_directory</code> in Swift. Path must be writable and readable by the user running ansible from config-download, e.g. the <code>mistral</code> user in the <code>mistral-executor</code> container is able to read/write to <code>/var/lib/mistral/ceph_fetch</code> .
ManilaCephFSCephFSAuthId	The CephFS user ID for Shared Filesystem Service (manila). The default value is manila .
ManilaCephFSDataPoolName	Pool to use for file share storage. The default value is manila_data .
ManilaCephFSDataPoolPGNum	Placement group count for the CephFS data pool for file share storage. The default value is 128 .
ManilaCephFSMetadataPoolName	Pool to use for file share metadata storage. The default value is manila_metadata .
ManilaCephFSMetadataPoolPGNum	Placement group count for the CephFS metadata pool for file share storage. The default value is 128 .
ManilaCephFSShareBackendName	Backend name of the CephFS share for file share storage. The default value is cephfs .
NovaEnableRbdBackend	Whether to enable the Ceph backend for Compute (nova). The default value is False .
NovaRbdPoolName	Pool to use for Compute storage. The default value is vms .

CHAPTER 7. BLOCK STORAGE (CINDER) PARAMETERS

Parameter	Description
CephClusterFSID	The Ceph cluster FSID. Must be a UUID.
CephClusterName	The Ceph cluster name. The default value is ceph .
CinderCronDbPurgeAge	Cron to move deleted instances to another table - Age. The default value is 30 .
CinderCronDbPurgeDestination	Cron to move deleted instances to another table - Log destination. The default value is /var/log/cinder/cinder-rowsflush.log .
CinderCronDbPurgeHour	Cron to move deleted instances to another table - Hour. The default value is 0 .
CinderCronDbPurgeMaxDelay	Cron to move deleted instances to another table - Max Delay. The default value is 3600 .
CinderCronDbPurgeMinute	Cron to move deleted instances to another table - Minute. The default value is 1 .
CinderCronDbPurgeMonth	Cron to move deleted instances to another table - Month. The default value is * .
CinderCronDbPurgeMonthday	Cron to move deleted instances to another table - Month Day. The default value is * .
CinderCronDbPurgeUser	Cron to move deleted instances to another table - User. The default value is cinder .
CinderCronDbPurgeWeekday	Cron to move deleted instances to another table - Week Day. The default value is * .
CinderDefaultVolumeType	The name of the OpenStack Block Storage (cinder) default volume type. The default value is tripleo .
CinderEnableDBPurge	Whether to create cron job for purging soft deleted rows in OpenStack Block Storage (cinder) database. The default value is True .
CinderEnableiscsiBackend	Whether to enable or not the Iscsi backend for OpenStack Block Storage (cinder). The default value is True .

Parameter	Description
CinderEnableNfsBackend	Whether to enable or not the NFS backend for OpenStack Block Storage (cinder). The default value is False .
CinderEnableRbdBackend	Whether to enable or not the Rbd backend for OpenStack Block Storage (cinder). The default value is False .
CinderEtcdLocalConnect	When running OpenStack Block Storage (cinder) A/A, whether to connect to Etcd via the local IP for the Etcd network. If set to true, the ip on the local node will be used. If set to false, the VIP on the Etcd network will be used instead. Defaults to false. The default value is False .
CinderISCSIAvailabilityZone	The availability zone of the lscsi OpenStack Block Storage (cinder) backend. When set, it overrides the default CinderStorageAvailabilityZone.
CinderISCSHelper	The iSCSI helper to use with cinder. The default value is lioadm .
CinderISCSIProtocol	Whether to use TCP (<i>iscsi</i>) or iSER RDMA (<i>iser</i>) for iSCSI. The default value is iscsi .
CinderLVMLoopDeviceSize	The size of the loopback file used by the cinder LVM driver. The default value is 10280 .
CinderNasSecureFileOperations	Controls whether security enhanced NFS file operations are enabled. Valid values are <i>auto</i> , <i>true</i> or <i>false</i> . Effective when CinderEnableNfsBackend is true. The default value is False .
CinderNasSecureFilePermissions	Controls whether security enhanced NFS file permissions are enabled. Valid values are <i>auto</i> , <i>true</i> or <i>false</i> . Effective when CinderEnableNfsBackend is true. The default value is False .
CinderNfsAvailabilityZone	The availability zone of the NFS OpenStack Block Storage (cinder) backend. When set, it overrides the default CinderStorageAvailabilityZone.
CinderNfsMountOptions	Mount options for NFS mounts used by OpenStack Block Storage (cinder) NFS backend. Effective when CinderEnableNfsBackend is true. The default value is context=system_u:object_r:container_file_t:s0 .

Parameter	Description
CinderNfsServers	NFS servers used by OpenStack Block Storage (cinder) NFS backend. Effective when CinderEnableNfsBackend is true.
CinderNfsSnapshotSupport	Whether to enable support for snapshots in the NFS driver. Effective when CinderEnableNfsBackend is true. The default value is True .
CinderPassword	The password for the cinder service and database account.
CinderRbdAvailabilityZone	The availability zone of the RBD OpenStack Block Storage (cinder) backend. When set, it overrides the default CinderStorageAvailabilityZone.
CinderRbdExtraPools	List of extra Ceph pools for use with RBD backends for OpenStack Block Storage (cinder). An extra OpenStack Block Storage (cinder) RBD backend driver is created for each pool in the list. This is in addition to the standard RBD backend driver associated with the CinderRbdPoolName.
CinderRbdFlattenVolumeFromSnapshot	Whether RBD volumes created from a snapshot should be flattened in order to remove a dependency on the snapshot. The default value is False .
CinderRbdPoolName	The Ceph pool to use for cinder volumes. The default value is volumes .
CinderStorageAvailabilityZone	The OpenStack Block Storage (cinder) service's storage availability zone. The default value is nova .
CinderVolumeCluster	The cluster name used for deploying the cinder-volume service in an active-active (A/A) configuration. This configuration requires the OpenStack Block Storage (cinder) backend drivers support A/A, and the cinder-volume service not be managed by pacemaker. If these criteria are not met then the cluster name must be left blank.
CinderVolumeOptEnvVars	Hash of optional environment variables.
CinderVolumeOptVolumes	List of optional volumes to be mounted.

Parameter	Description
CinderWorkers	Set the number of workers for the block storage service. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts. 0 sets to the OpenStack internal default, which is equal to the number of CPU cores on the node. The default value is equal to the number of vCPU cores on the physical node.
DockerCinderVolumeUlimit	Ulimit for OpenStack Block Storage (cinder) Volume Container. The default value is ['nofile=131072'] .
EnableEtcdInternalTLS	Controls whether etcd and the cinder-volume service use TLS for cinder's lock manager, even when the rest of the internal API network is using TLS. The default value is False .
MultipathdEnable	Whether to enable the multipath daemon. The default value is False .
NotificationDriver	Driver or drivers to handle sending notifications. The default value is messagingv2 .

CHAPTER 8. IMAGE STORAGE (GLANCE) PARAMETERS

Parameter	Description
CephClusterName	The Ceph cluster name. The default value is ceph .
GlanceApiOptVolumes	List of optional volumes to be mounted.
GlanceBackend	The short name of the backend to use. Should be one of swift , rbd , or file . The default value is swift .
GlanceBackendID	The default backend's identifier. The default value is default_backend .
GlanceCacheEnabled	Enable OpenStack Image Storage (glance) Image Cache. The default value is False .
GlanceEnabledImportMethods	List of enabled Image Import Methods. Valid values in the list are <i>glance-direct</i> and <i>web-download</i> . The default value is web-download .
GlanceIgnoreUserRoles	List of user roles to be ignored for injecting image metadata properties. The default value is admin .
GlanceImageCacheDir	Base directory that the Image Cache uses. The default value is /var/lib/glance/image-cache .
GlanceImageCacheMaxSize	The upper limit on cache size, in bytes, after which the cache-pruner cleans up the image cache. The default value is 10737418240 .
GlanceImageCacheStallTime	The amount of time, in seconds, to let an image remain in the cache without being accessed. The default value is 86400 .
GlanceImageConversionOutputFormat	Desired output format for image conversion plugin. The default value is raw .
GlanceImageImportPlugins	List of enabled Image Import Plugins. Valid values in the list are <i>image_conversion</i> , <i>inject_metadata</i> , <i>no_op</i> . The default value is ['no_op'] .
GlanceImageMemberQuota	Maximum number of image members per image. Negative values evaluate to unlimited. The default value is 128 .
GlanceImagePrefetcherInterval	The interval in seconds to run periodic job <i>cache_images</i> . The default value is 300 .

Parameter	Description
GlanceInjectMetadataProperties	Metadata properties to be injected in image.
GlanceLogFile	The filepath of the file to use for logging messages from OpenStack Image Storage (glance).
GlanceMultistoreConfig	Dictionary of settings when configuring additional glance backends. The hash key is the backend ID, and the value is a dictionary of parameter values unique to that backend. Multiple rbd backends are allowed, but cinder, file and swift backends are limited to one each. Example: # Default glance store is rbd. GlanceBackend: rbd GlanceStoreDescription: <i>Default rbd store</i> # GlanceMultistoreConfig specifies a second rbd backend, plus a cinder # backend. GlanceMultistoreConfig: rbd2_store: GlanceBackend: rbd GlanceStoreDescription: <i>Second rbd store</i> CephClusterName: ceph2 # Override CephClientUserName if this cluster uses a different # client name. CephClientUserName: client2 cinder_store: GlanceBackend: cinder GlanceStoreDescription: <i>OpenStack Block Storage (cinder) store</i> .
GlanceNetappNfsEnabled	When using GlanceBackend: file , Netapp mounts NFS share for image storage. The default value is False .
GlanceNfsEnabled	When using GlanceBackend: file , mount NFS share for image storage. The default value is False .
GlanceNfsOptions	NFS mount options for image storage when GlanceNfsEnabled is true. The default value is _netdev,bg,intr,context=system_u:object_r:s_virt_sandbox_file_t:s0 .
GlanceNfsShare	NFS share to mount for image storage when GlanceNfsEnabled is true.
GlanceNodeStagingUri	URI that specifies the staging location to use when importing images. The default value is file:///var/lib/glance/staging .
GlanceNotifierStrategy	Strategy to use for OpenStack Image Storage (glance) notification queue. The default value is noop .
GlancePassword	The password for the image storage service and database account.

Parameter	Description
GlanceShowMultipleLocations	Whether to show multiple image locations e.g for copy-on-write support on RBD or Netapp backends. Potential security risk, see glance.conf for more information. The default value is False .
GlanceStagingNfsOptions	NFS mount options for NFS image import staging. The default value is _netdev,bg,intr,context=system_u:object_r:s_virt_sandbox_file_t:s0 .
GlanceStagingNfsShare	NFS share to mount for image import staging.
GlanceStoreDescription	User facing description for the OpenStack Image Storage (glance) backend. The default value is Default glance store backend..
GlanceWorkers	Set the number of workers for the image storage service. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts. 0 sets to the OpenStack internal default, which is equal to the number of CPU cores on the node.
MultipathdEnable	Whether to enable the multipath daemon. The default value is False .
NetappShareLocation	Netapp share to mount for image storage (when GlanceNetappNfsEnabled is true).
NotificationDriver	Driver or drivers to handle sending notifications. The default value is messagingv2 .

CHAPTER 9. ORCHESTRATION (HEAT) PARAMETERS

Parameter	Description
HeatApiOptEnvVars	Hash of optional environment variables.
HeatApiOptVolumes	List of optional volumes to be mounted.
HeatAuthEncryptionKey	Auth encryption key for heat-engine.
HeatConfigureDelegatedRoles	Create delegated roles. The default value is False .
HeatConvergenceEngine	Enables the heat engine with the convergence architecture. The default value is True .
HeatCorsAllowedOrigin	Indicate whether this resource may be shared with the domain received in the request "origin" header.
HeatCronPurgeDeletedAge	Cron to purge database entries marked as deleted and older than \$age - Age. The default value is 30 .
HeatCronPurgeDeletedAgeType	Cron to purge database entries marked as deleted and older than \$age - Age type. The default value is days .
HeatCronPurgeDeletedDestination	Cron to purge database entries marked as deleted and older than \$age - Log destination. The default value is /dev/null .
HeatCronPurgeDeletedEnsure	Cron to purge database entries marked as deleted and older than \$age - Ensure. The default value is present .
HeatCronPurgeDeletedHour	Cron to purge database entries marked as deleted and older than \$age - Hour. The default value is 0 .
HeatCronPurgeDeletedMaxDelay	Cron to purge database entries marked as deleted and older than \$age - Max Delay. The default value is 3600 .
HeatCronPurgeDeletedMinute	Cron to purge database entries marked as deleted and older than \$age - Minute. The default value is 1 .
HeatCronPurgeDeletedMonth	Cron to purge database entries marked as deleted and older than \$age - Month. The default value is * .
HeatCronPurgeDeletedMonthday	Cron to purge database entries marked as deleted and older than \$age - Month Day. The default value is * .

Parameter	Description
HeatCronPurgeDeletedUser	Cron to purge database entries marked as deleted and older than \$age - User. The default value is heat .
HeatCronPurgeDeletedWeekday	Cron to purge database entries marked as deleted and older than \$age - Week Day. The default value is * .
HeatEnableDBPurge	Whether to create cron job for purging soft deleted rows in the OpenStack Orchestration (heat) database. The default value is True .
HeatEngineOptEnvVars	Hash of optional environment variables.
HeatEngineOptVolumes	List of optional volumes to be mounted.
HeatEnginePluginDirs	An array of directories to search for plug-ins.
HeatMaxJsonBodySize	Maximum raw byte size of the OpenStack Orchestration (heat) API JSON request body. The default value is 4194304 .
HeatMaxNestedStackDepth	Maximum number of nested stack depth. The default value is 6 .
HeatMaxResourcesPerStack	Maximum resources allowed per top-level stack. -1 stands for unlimited. The default value is 1000 .
HeatPassword	The password for the Orchestration service and database account.
HeatReauthenticationAuthMethod	Allow reauthentication on token expiry, such that long-running tasks may complete. Note this defeats the expiry of any provided user tokens.
HeatStackDomainAdminPassword	The admin password for the OpenStack Orchestration (heat) domain in OpenStack Identity (keystone).
HeatWorkers	Number of workers for OpenStack Orchestration (heat) service. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts. 0 sets to the OpenStack internal default, which is equal to the number of CPU cores on the node. The default value is 0 .

Parameter	Description
HeatYaqlLimitIterators	The maximum number of elements in collection yaql expressions can take for its evaluation. The default value is 1000 .
HeatYaqlMemoryQuota	The maximum size of memory in bytes that yaql expressions can take for its evaluation. The default value is 100000 .
NotificationDriver	Driver or drivers to handle sending notifications. The default value is messagingv2 .

CHAPTER 10. DASHBOARD (HORIZON) PARAMETERS

Parameter	Description
HorizonAllowedHosts	A list of IP/Hostname for the server OpenStack Dashboard (horizon) is running on. Used for header checks. The default value is * .
HorizonCustomizationModule	OpenStack Dashboard (horizon) has a global overrides mechanism available to perform customizations.
HorizonHelpURL	On top of dashboard there is a Help button. This button could be used to re-direct user to vendor documentation or dedicated help portal. The default value is https://access.redhat.com/documentation/en-us/red_hat_openstack_platform .
HorizonPasswordValidator	Regex for password validation.
HorizonPasswordValidatorHelp	Help text for password validation.
HorizonSecret	Secret key for the webserver.
HorizonSecureCookies	Set CSRF_COOKIE_SECURE / SESSION_COOKIE_SECURE in OpenStack Dashboard (horizon). The default value is False .
HorizonVhostExtraParams	Extra parameters for OpenStack Dashboard (horizon) vhost configuration. The default value is <code>{'add_listen': True, 'priority': 10, 'access_log_format': '%a %l %u %t \"%r\" \"%>s %b \"%%{{Referer}}i\" \"%%{{User-Agent}}i\", 'options': ['FollowSymLinks', 'MultiViews']}</code> .
MemcachedIPv6	Enable IPv6 features in Memcached. The default value is False .
TimeZone	The timezone to be set on the overcloud. The default value is UTC .
WebSSOChoices	Specifies the list of SSO authentication choices to present. Each item is a list of an SSO choice identifier and a display message. The default value is <code>[['OIDC', 'OpenID Connect']]</code> .
WebSSOEnable	Enable support for Web Single Sign-On. The default value is False .

Parameter	Description
WebSSOIDPMapping	Specifies a mapping from SSO authentication choice to identity provider and protocol. The identity provider and protocol names must match the resources defined in keystone. The default value is {'OIDC': ['myidp', 'openid']} .
WebSSOInitialChoice	The initial authentication choice to select by default. The default value is OIDC .

CHAPTER 11. BARE METAL (IRONIC) PARAMETERS

Parameter	Description
AdditionalArchitectures	List of additional architectures to enable.
IPAIimageURLs	IPA image URLs, the format should be ["http://path/to/kernel", "http://path/to/ramdisk"].
IronicAutomatedClean	Enables or disables automated cleaning. Disabling automated cleaning might result in security problems and deployment failures on rebuilds. Do not set to False unless you understand the consequences of disabling this feature. The default value is True .
IronicCleaningDiskErase	Type of disk cleaning before and between deployments. full for full cleaning. metadata to clean only disk metadata (partition table). The default value is full .
IronicCleaningNetwork	Name or UUID of the overcloud network used for cleaning bare metal nodes. Set to provisioning during the initial deployment (when no networks are created yet) and change to an actual UUID in a post-deployment stack update. The default value is provisioning .
IronicConductorGroup	The name of an OpenStack Bare Metal (ironic) Conductor Group.
IronicConfigureSwiftTempUrlKey	Whether to configure Swift temporary URLs for use with the "direct" and "ansible" deploy interfaces. The default value is True .
IronicCorsAllowedOrigin	Indicate whether this resource may be shared with the domain received in the request "origin" header.
IronicDefaultBootOption	How to boot the bare metal instances. Set to local to use local bootloader (requires grub2 for partition images). Set to netboot to make the instances boot from controllers using PXE/iPXE. The default value is local .
IronicDefaultDeployInterface	Deploy interface implementation to use by default. Leave empty to use the hardware type default.
IronicDefaultInspectInterface	Inspect interface implementation to use by default. Leave empty to use the hardware type default.

Parameter	Description
IroniDefaultNetworkInterface	Network interface implementation to use by default. Set to flat to use one flat provider network. Set to neutron to make OpenStack Bare Metal (ironic) interact with the OpenStack Networking (neutron) ML2 driver to enable other network types and certain advanced networking features. Requires IroniProvisioningNetwork to be correctly set. The default value is flat .
IroniDefaultRescueInterface	Default rescue implementation to use. The "agent" rescue requires a compatible ramdisk to be used. The default value is agent .
IroniDefaultResourceClass	Default resource class to use for new nodes.
IroniDeployLogsStorageBackend	Backend to use to store ramdisk logs, either "local" or "swift". The default value is local .
IroniDhcpv6StatefulAddressCount	Number of IPv6 addresses to allocate for ports created for provisioning, cleaning, rescue or inspection on DHCPv6-stateful networks. Different stages of the chain-loading process will request addresses with different CLID/IAID. Due to non-identical identifiers multiple addresses must be reserved for the host to ensure each step of the boot process can successfully lease addresses. The default value is 4 .
IroniEnableStagingDrivers	Whether to enable use of staging drivers. The default value is False .
IroniEnabledBiosInterfaces	Enabled BIOS interface implementations. Each hardware type must have at least one valid implementation enabled. The default value is ['no-bios'] .
IroniEnabledBootInterfaces	Enabled boot interface implementations. Each hardware type must have at least one valid implementation enabled. The default value is ['ipxe', 'pxe'] .
IroniEnabledConsoleInterfaces	Enabled console interface implementations. Each hardware type must have at least one valid implementation enabled. The default value is ['ipmitool-socat', 'no-console'] .

Parameter	Description
IroniEnabledDeployInterfaces	Enabled deploy interface implementations. Each hardware type must have at least one valid implementation enabled. The default value is ['iscsi', 'direct'] .
IroniEnabledHardwareTypes	Enabled OpenStack Bare Metal (ironic) hardware types. The default value is ['ipmi', 'redfish'] .
IroniEnabledInspectInterfaces	Enabled inspect interface implementations. Each hardware type must have at least one valid implementation enabled. The default value is ['no-inspect'] .
IroniEnabledManagementInterfaces	Enabled management interface implementations. Each hardware type must have at least one valid implementation enabled. The default value is ['ipmitool', 'noop', 'redfish'] .
IroniEnabledNetworkInterfaces	Enabled network interface implementations. Each hardware type must have at least one valid implementation enabled. The default value is ['flat', 'neutron'] .
IroniEnabledPowerInterfaces	Enabled power interface implementations. Each hardware type must have at least one valid implementation enabled. The default value is ['ipmitool', 'redfish'] .
IroniEnabledRaidInterfaces	Enabled RAID interface implementations. Each hardware type must have at least one valid implementation enabled. The default value is ['no-raid', 'agent'] .
IroniEnabledRescueInterfaces	Enabled rescue interface implementations. Each hardware type must have at least one valid implementation enabled. The default value is ['no-rescue', 'agent'] .
IroniEnabledStorageInterfaces	Enabled storage interface implementations. Each hardware type must have at least one valid implementation enabled. The default value is ['cinder', 'noop'] .
IroniEnabledVendorInterfaces	Enabled vendor interface implementations. Each hardware type must have at least one valid implementation enabled. The default value is ['ipmitool', 'no-vendor'] .

Parameter	Description
IroniForcePowerStateDuringSync	Whether to force power state during sync. The default value is True .
IroniIPXEEnabled	Whether to use iPXE instead of PXE for deployment. The default value is True .
IroniIPXEPort	Port to use for serving images when iPXE is used. The default value is 8088 .
IroniIPXETimeout	IPXE timeout in second. Set to 0 for infinite timeout. The default value is 60 .
IroniImageDownloadSource	Image delivery method for the "direct" deploy interface. Use "swift" for the Object Storage temporary URLs, use "http" for the local HTTP server (the same as for iPXE). The default value is swift .
IroniInspectorCollectors	Comma-separated list of IPA inspection collectors. The default value is default,logs .
IroniInspectorDiscoveryDefaultDriver	The default driver to use for newly discovered nodes (requires IroniInspectorEnableNodeDiscovery set to True). This driver is automatically added to enabled_drivers. The default value is ipmi .
IroniInspectorEnableNodeDiscovery	Makes ironic-inspector enroll any unknown node that PXE-boots introspection ramdisk in OpenStack Bare Metal (ironic). The default driver to use for new nodes is specified by the IroniInspectorDiscoveryDefaultDriver parameter. Introspection rules can also be used to specify it. The default value is False .
IroniInspectorExtraProcessingHooks	Comma-separated list of processing hooks to append to the default list. The default value is extra_hardware,lldp_basic,local_link_connection .
IroniInspectorIPXEEnabled	Whether to use iPXE for inspection. The default value is True .
IroniInspectorInterface	Network interface on which inspection dnsmasq will listen. The default value is br-ex .

Parameter	Description
IronicInspectorIpRange	Temporary IP range that will be given to nodes during the inspection process. This should not overlap with any range that OpenStack Networking (neutron) DHCP allocates, but it has to be routeable back to ironic-inspector . This option has no meaningful defaults, and thus is required.
IronicInspectorKernelArgs	Kernel args for the OpenStack Bare Metal (ironic) inspector. The default value is ipa-inspection-dhcp-all-interfaces=1 ipa-collect-lldp=1 ipa-debug=1 .
IronicInspectorSubnets	Temporary IP ranges that will be given to nodes during the inspection process. These ranges should not overlap with any range that OpenStack Networking (neutron) DHCP provides, but they need to be routeable back to the ironic-inspector API. This option has no meaningful defaults and is required.
IronicInspectorUseSwift	Whether to use Swift for storing introspection data. The default value is True .
IronicIpVersion	The IP version that will be used for PXE booting. The default value is 4 .
IronicPassword	The password for the Bare Metal service and database account.
IronicProvisioningNetwork	Name or UUID of the overcloud network used for provisioning of bare metal nodes if IronicDefaultNetworkInterface is set to neutron . Set to provisioning during the initial deployment (when no networks are created yet) and change to an actual UUID in a post-deployment stack update. The default value is provisioning .
IronicRescuingNetwork	Name or UUID of the overcloud network used for rescuing of bare metal nodes, if IronicDefaultRescueInterface is not set to "no-rescue". The default value of "provisioning" can be left during the initial deployment (when no networks are created yet) and should be changed to an actual UUID in a post-deployment stack update. The default value is provisioning .
IronicRpcTransport	The remote procedure call transport between conductor and API processes, such as a messaging broker or JSON RPC.

CHAPTER 12. IDENTITY (KEYSTONE) PARAMETERS

Parameter	Description
AdminEmail	The email for the OpenStack Identity (keystone) admin account. The default value is admin@example.com .
AdminPassword	The password for the OpenStack Identity (keystone) admin account.
AdminToken	The OpenStack Identity (keystone) secret and database password.
EnablePublicTLS	Whether to enable TLS on the public interface or not. The default value is True .
KeystoneAuthMethods	A list of methods used for authentication.
KeystoneChangePasswordUponFirstUse	Enabling this option requires users to change their password when the user is created, or upon administrative reset.
KeystoneCorsAllowedOrigin	Indicate whether this resource may be shared with the domain received in the request "origin" header.
KeystoneCredential0	The first OpenStack Identity (keystone) credential key. Must be a valid key.
KeystoneCredential1	The second OpenStack Identity (keystone) credential key. Must be a valid key.
KeystoneDisableUserAccountDaysInactive	The maximum number of days a user can go without authenticating before being considered "inactive" and automatically disabled (locked).
KeystoneEnableMember	Create the <i>member</i> role, useful for undercloud deployment. The default value is False .
KeystoneFederationEnable	Enable support for federated authentication. The default value is False .
KeystoneFernetKeys	Mapping containing OpenStack Identity (keystone) fernet keys and their paths.
KeystoneFernetMaxActiveKeys	The maximum active keys in the OpenStack Identity (keystone) fernet key repository. The default value is 5 .

Parameter	Description
KeystoneLDAPBackendConfigs	Hash containing the configurations for the LDAP backends configured in keystone.
KeystoneLDAPDomainEnable	Trigger to call ldap_backend puppet keystone define. The default value is False .
KeystoneLockoutDuration	The number of seconds a user account will be locked when the maximum number of failed authentication attempts (as specified by KeystoneLockoutFailureAttempts) is exceeded.
KeystoneLockoutFailureAttempts	The maximum number of times that a user can fail to authenticate before the user account is locked for the number of seconds specified by KeystoneLockoutDuration.
KeystoneMinimumPasswordAge	The number of days that a password must be used before the user can change it. This prevents users from changing their passwords immediately in order to wipe out their password history and reuse an old password.
KeystoneNotificationFormat	The OpenStack Identity (keystone) notification format. The default value is basic .
KeystoneNotificationTopics	OpenStack Identity (keystone) notification topics to enable.
KeystoneOpenIdcClientId	The client ID to use when handshaking with your OpenID Connect provider.
KeystoneOpenIdcClientSecret	The client secret to use when handshaking with your OpenID Connect provider.
KeystoneOpenIdcCryptoPassphrase	Passphrase to use when encrypting data for OpenID Connect handshake. The default value is openstack .
KeystoneOpenIdcEnable	Enable support for OpenIDC federation. The default value is False .
KeystoneOpenIdcEnableOAuth	Enable OAuth 2.0 integration. The default value is False .
KeystoneOpenIdcIdpName	The name associated with the IdP in OpenStack Identity (keystone).

Parameter	Description
KeystoneOpenIdcIntrospectionEndpoint	OAuth 2.0 introspection endpoint for mod_auth_openidc.
KeystoneOpenIdcProviderMetadataUrl	The url that points to your OpenID Connect provider metadata.
KeystoneOpenIdcRemoteldAttribute	Attribute to be used to obtain the entity ID of the Identity Provider from the environment. The default value is HTTP_OIDC_ISS .
KeystoneOpenIdcResponseType	Response type to be expected from the OpenID Connect provider. The default value is id_token .
KeystonePasswordExpiresDays	The number of days for which a password will be considered valid before requiring it to be changed.
KeystonePasswordRegex	The regular expression used to validate password strength requirements.
KeystonePasswordRegexDescription	Describe your password regular expression here in language for humans.
KeystoneSSLCertificate	OpenStack Identity (keystone) certificate for verifying token validity.
KeystoneSSLCertificateKey	OpenStack Identity (keystone) key for signing tokens.
KeystoneTokenProvider	The OpenStack Identity (keystone) token format. The default value is fernet .
KeystoneTrustedDashboards	A list of dashboard URLs trusted for single sign-on.
KeystoneUniqueLastPasswordCount	This controls the number of previous user password iterations to keep in history, in order to enforce that newly created passwords are unique.
KeystoneWorkers	Set the number of workers for the OpenStack Identity (keystone) service. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts. 0 sets to the OpenStack internal default, which is equal to the number of CPU cores on the node. The default value is equal to the number of vCPU cores on the physical node.

Parameter	Description
ManageKeystoneFernetKeys	Whether director should manage the OpenStack Identity (keystone) fernet keys or not. If set to True, the fernet keys will get the values from the saved keys repository in OpenStack Workflow (mistral) from the KeystoneFernetKeys variable. If set to false, only the stack creation initializes the keys, but subsequent updates will not touch them. The default value is True .
NotificationDriver	Driver or drivers to handle sending notifications. The default value is messagingv2 .
PublicSSLCertificateAutogenerated	Whether the public SSL certificate was autogenerated or not. The default value is False .
PublicTLSCAFile	Specifies the default CA cert to use if TLS is used for services in the public network.
SSLCertificate	The content of the SSL certificate (without Key) in PEM format.
TokenExpiration	Set a token expiration time in seconds. The default value is 3600 .

CHAPTER 13. KEY MANAGER (BARABICAN) PARAMETERS

Parameter	Description
ATOSVars	Hash of atos-hsm role variables used to install ATOS client software.
BarbicanDogtagStoreGlobalDefault	Whether this plugin is the global default plugin. The default value is False .
BarbicanDogtagStoreHost	Hostname of the Dogtag server.
BarbicanDogtagStoreNSSPassword	Password for the NSS DB.
BarbicanDogtagStorePEMPath	Path for the PEM file used to authenticate requests. The default value is /etc/barbican/kra_admin_cert.pem .
BarbicanDogtagStorePort	Port for the Dogtag server. The default value is 8443 .
BarbicanKmipStoreGlobalDefault	Whether this plugin is the global default plugin. The default value is False .
BarbicanKmipStoreHost	Host for KMIP device.
BarbicanKmipStorePassword	Password to connect to KMIP device.
BarbicanKmipStorePort	Port for KMIP device.
BarbicanKmipStoreUsername	Username to connect to KMIP device.
BarbicanPassword	The password for the OpenStack Key Manager (barbican) service account.
BarbicanPkcs11AlwaysSetCkaSensitive	Always set CKA_SENSITIVE=CK_TRUE. The default value is True .
BarbicanPkcs11CryptoAESGCMGenerateIV	Generate IVs for CKM_AES_GCM encryption mechanism. The default value is True .
BarbicanPkcs11CryptoATOSEnabled	Enable ATOS for PKCS11. The default value is False .
BarbicanPkcs11CryptoEnabled	Enable PKCS11. The default value is False .
BarbicanPkcs11CryptoEncryptionMechanism	Cryptoki Mechanism used for encryption. The default value is CKM_AES_CBC .

Parameter	Description
BarbicanPkcs11CryptoGlobalDefault	Whether this plugin is the global default plugin. The default value is False .
BarbicanPkcs11CryptoHMACKeyType	Cryptoki Key Type for Master HMAC key. The default value is CKK_AES .
BarbicanPkcs11CryptoHMACKeygenMechanism	Cryptoki Mechanism used to generate Master HMAC Key. The default value is CKM_AES_KEY_GEN .
BarbicanPkcs11CryptoHMACLabel	Label for the HMAC key.
BarbicanPkcs11CryptoLibraryPath	Path to vendor PKCS11 library.
BarbicanPkcs11CryptoLogin	Password to login to PKCS11 session.
BarbicanPkcs11CryptoLunasaEnabled	Enable Luna SA HSM for PKCS11. The default value is False .
BarbicanPkcs11CryptoMKEKLabel	Label for Master KEK.
BarbicanPkcs11CryptoMKEKLength	Length of Master KEK in bytes. The default value is 256 .
BarbicanPkcs11CryptoRewrapKeys	Cryptoki Mechanism used to generate Master HMAC Key. The default value is False .
BarbicanPkcs11CryptoSlotId	Slot Id for the HSM. The default value is 0 .
BarbicanPkcs11CryptoThalesEnabled	Enable Thales for PKCS11. The default value is False .
BarbicanSimpleCryptoGlobalDefault	Whether this plugin is the global default plugin. The default value is False .
BarbicanSimpleCryptoKek	KEK used to encrypt secrets.
BarbicanWorkers	Set the number of workers for barbican::wsgi::apache. The default value is %{::processorcount} .
LunasaClientIPNetwork	(Optional) When set OpenStack Key Manager (barbican) nodes will be registered with the HSMs using the IP from this network instead of the FQDN.
LunasaVars	Hash of lunasa-hsm role variables used to install Lunasa client software.

Parameter	Description
NotificationDriver	Driver or drivers to handle sending notifications. The default value is messagingv2 .
ThalesHSMNetworkName	The network that the HSM is listening on. The default value is internal_api .
ThalesVars	Hash of thales-hsm role variables used to install Thales client software.

CHAPTER 14. SHARED FILE SERVICE (MANILA) PARAMETERS

Parameter	Description
CephClusterName	The Ceph cluster name. The default value is ceph .
ManilaCephClientUserName	Ceph client username for manila integration. The default value is manila .
ManilaCephFSCephFSProtocolHelperType	Protocol type (<i>CEPHFS</i> or <i>NFS</i>) when cephfs back end is enabled. Set via manila cephfs environment files. The default value is CEPHFS .
ManilaIPv6	Set to True to enable IPv6 access in manila. The default value is False .
ManilaPassword	The password for the shared file service account.
ManilaWorkers	Set the number of workers for manila::wsgi::apache. The default value is equal to the number of vCPU cores on the physical node.
NotificationDriver	Driver or drivers to handle sending notifications. The default value is messagingv2 .

CHAPTER 15. MESSAGING PARAMETERS

Parameter	Description
RpcPassword	The password for messaging backend.
RpcPort	The network port for messaging backend. The default value is 5672 .
RpcUseSSL	Messaging client subscriber parameter to specify an SSL connection to the messaging host. The default value is False .
RpcUserName	The username for messaging backend. The default value is guest .

CHAPTER 16. NETWORKING (NEUTRON) PARAMETERS

Parameter	Description
DhcpAgentNotification	Enables DHCP agent notifications. The default value is True .
DockerAdditionalSockets	Additional domain sockets for the docker daemon to bind to (useful for mounting into containers that launch other containers). The default value is ['/var/lib/openstack/docker.sock'] .
EnableVLANTransparency	If True, then allow plugins that support it to create VLAN transparent networks. The default value is False .
NeutronAllowL3AgentFailover	Allow automatic l3-agent failover. The default value is True .
NeutronApiOptEnvVars	Hash of optional environment variables.
NeutronApiOptVolumes	List of optional volumes to be mounted.
NeutronBridgeMappings	The logical to physical bridge mappings to use. The default (datacentre:br-ex) maps br-ex (the external bridge on hosts) to a physical name datacentre , which provider networks can use (for example, the default floating network). If changing this, either use different post-install network scripts or be sure to keep datacentre as a mapping network name. The default value is datacentre:br-ex .
NeutronCorePlugin	The core plugin for networking. The value should be the entrypoint to be loaded from neutron.core_plugins namespace. The default value is ml2 .
NeutronDBSyncExtraParams	String of extra command line parameters to append to the neutron-db-manage upgrade head command.
NeutronDefaultAvailabilityZones	Comma-separated list of default network availability zones to be used by OpenStack Networking (neutron) if its resource is created without availability zone hints. If not set, no AZs will be configured for OpenStack Networking (neutron) network services.
NeutronDhcpAgentsPerNetwork	The number of DHCP agents to schedule per network. The default value is 0 .

Parameter	Description
NeutronDhcpLoadType	Additional to the availability zones aware network scheduler. The default value is networks .
NeutronDnsDomain	Domain to use for building the hostnames. The default value is openstacklocal .
NeutronEnableDVR	Enable Distributed Virtual Router.
NeutronEnableIcmpSnooping	Enable IGMP Snooping. The default value is False .
NeutronFirewallDriver	Firewall driver for realizing OpenStack Networking (neutron) security group function. The default value is iptables_hybrid .
NeutronFlatNetworks	Sets the flat network name to configure in plugins. The default value is datacentre .
NeutronGeneveMaxHeaderSize	Geneve encapsulation header size. The default value is 38 .
NeutronGlobalPhysnetMtu	MTU of the underlying physical network. OpenStack Networking (neutron) uses this value to calculate MTU for all virtual network components. For flat and VLAN networks, OpenStack Networking uses this value without modification. For overlay networks such as VXLAN, OpenStack Networking automatically subtracts the overlay protocol overhead from this value. The default value is 0 .
NeutronML2PhysicalNetworkMtus	A list of mappings of physical networks to MTU values. The format of the mapping is <physnet>: <mtu val> . This mapping allows you to specify a physical network MTU value that differs from the default segment_mtu value in ML2 plugin and overwrites values from global_physnet_mtu for the selected network.
NeutronMechanismDrivers	The mechanism drivers for the OpenStack Networking (neutron) tenant network. The default value is ovn .
NeutronMetadataProxySharedSecret	Shared secret to prevent spoofing.
NeutronNetworkSchedulerDriver	The network schedule driver to use for availability zones. The default value is neutron.scheduler.dhcp_agent_scheduler.AZ AwareWeightScheduler .

Parameter	Description
NeutronNetworkType	The tenant network type for OpenStack Networking (neutron). The default value is geneve .
NeutronNetworkVLANRanges	The OpenStack Networking (neutron) ML2 and Open vSwitch VLAN mapping range to support. Defaults to permitting any VLAN on the datacentre physical network (See NeutronBridgeMappings). The default value is datacentre:1:1000 .
NeutronOverlayIPVersion	IP version used for all overlay network endpoints. The default value is 4 .
NeutronOvsIntegrationBridge	Name of Open vSwitch bridge to use.
NeutronOvsVnicTypeBlacklist	Comma-separated list of VNIC types for which support in OpenStack Networking (neutron) is administratively prohibited by the OVS mechanism driver.
NeutronPassword	The password for the OpenStack Networking (neutron) service and database account.
NeutronPluginExtensions	Comma-separated list of enabled extension plugins. The default value is qos,port_security,dns .
NeutronPluginML2PuppetTags	Puppet resource tag names that are used to generate configuration files with puppet. The default value is neutron_plugin_ml2 .
NeutronPortQuota	Number of ports allowed per tenant, and minus means unlimited. The default value is 500 .
NeutronRouterSchedulerDriver	The router schedule driver to use for availability zones. The default value is neutron.scheduler.l3_agent_scheduler.AZLeastRoutersScheduler .
NeutronRpcWorkers	Sets the number of RPC workers for the OpenStack Networking (neutron) service. If not specified, it'll take the value of NeutronWorkers and if this is not specified either, the default value results in the configuration being left unset and a system-dependent default will be chosen (usually 1).

Parameter	Description
NeutronServicePlugins	Comma-separated list of service plugin endpoints. The default value is qos,ovn-router,trunk,segments .
NeutronSriovVnicTypeBlacklist	Comma-separated list of VNIC types for which support in OpenStack Networking (neutron) is administratively prohibited by the SR-IOV mechanism driver.
NeutronTunnelIdRanges	Comma-separated list of <tun_min>:<tun_max> tuples enumerating ranges of GRE tunnel IDs that are available for tenant network allocation. The default value is ['1:4094'] .
NeutronTypeDrivers	Comma-separated list of network type driver endpoints to be loaded. The default value is geneve,vlan,flat .
NeutronVhostuserSocketDir	The vhost-user socket directory for OVS.
NeutronVniRanges	Comma-separated list of <vni_min>:<vni_max> tuples enumerating ranges of VXLAN VNI IDs that are available for tenant network allocation. The default value is ['1:65536'] .
NeutronWorkers	Sets the number of API and RPC workers for the OpenStack Networking service. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts. 0 sets to the OpenStack internal default, which is equal to the number of CPU cores on the node.
NotificationDriver	Driver or drivers to handle sending notifications. The default value is messagingv2 .
OVNCMSOptions	The CMS options to configure in ovs db.
OVNDbConnectionTimeout	Timeout in seconds for the OVSDb connection transaction. The default value is 180 .
OVNDnsServers	List of servers to use as as dns forwarders.
OVNEnableHaproxyDockerWrapper	Generate a wrapper script so that haproxy is launched in a separate container. The default value is True .

Parameter	Description
OVNIntegrationBridge	Name of the OVS bridge to use as integration bridge by OVN Controller. The default value is br-int .
OVNMetadataEnabled	Whether Metadata Service has to be enabled. The default value is True .
OVNNeutronSyncMode	The synchronization mode of OVN with OpenStack Networking (neutron) DB. The default value is log .
OVNNorthboundServerPort	Port of the OVN Northbound DB server. The default value is 6641 .
OVNOpenflowProbeInterval	The inactivity probe interval of the OpenFlow connection to the OpenvSwitch integration bridge, in seconds. The default value is 60 .
OVNQosDriver	OVN notification driver for OpenStack Networking (neutron) QOS service plugin. The default value is ovn-qos .
OVNRemoteProbeInterval	Probe interval in ms. The default value is 60000 .
OVNSouthboundServerPort	Port of the OVN Southbound DB server. The default value is 6642 .
OVNVifType	Type of VIF to be used for ports. The default value is ovs .
OvsHwOffload	Enable OVS Hardware Offload. This feature supported from OVS 2.8.0. The default value is False .
TenantNetPhysnetMtu	MTU of the underlying physical network. OpenStack Networking (neutron) uses this value to calculate MTU for all virtual network components. For flat and VLAN networks, OpenStack Networking (neutron) uses this value without modification. For overlay networks such as VXLAN, OpenStack Networking (neutron) automatically subtracts the overlay protocol overhead from this value. (The mtu setting of the Tenant network in network_data.yaml control's this parameter.). The default value is 1500 .

CHAPTER 17. COMPUTE (NOVA) PARAMETERS

Parameter	Description
AdminPassword	The password for the keystone admin account, used for monitoring, querying OpenStack Networking (neutron) etc.
ContainerCpusetCpus	Limit the specific CPUs or cores a container can use. The default value is all .
ContainerNovaLibvirtPidsLimit	Tune nova_libvirt container PID limit (set to 0 for unlimited) (defaults to 65536). The default value is 65536 .
ContainerNovaLibvirtUlimit	Ulimit for OpenStack Compute (nova) Libvirt Container. The default value is ['nofile=131072', 'nproc=126960'] .
DockerInsecureRegistryAddress	Optional. The IP Address and Port of an insecure docker namespace that will be configured in /etc/sysconfig/docker. The value can be multiple addresses separated by commas.
DockerNovaComputeUlimit	Ulimit for OpenStack Compute (nova) Compute Container. The default value is ['nofile=131072', 'memlock=67108864'] .
DockerNovaMigrationSshdPort	Port that dockerized nova migration target sshd service binds to. The default value is 2022 .
EnableConfigPurge	Remove configuration that is not generated by the director. Used to avoid configuration remnants after upgrades. The default value is False .
EnableInstanceHA	Whether to enable an Instance Ha configurarion or not. This setup requires the Compute role to have the PacemakerRemote service added to it. The default value is False .
ExtractedPlacementEnabled	Set to True when deploying the extracted Placement service. The default value is False .
InstanceNameTemplate	Template string to be used to generate instance names. The default value is instance-%08x .
InternalTLSNbdCAFile	Specifies the CA cert to use for NBD TLS. The default value is /etc/pki/qemu/ca-cert.pem .

Parameter	Description
InternalTLSQemuCAFile	Specifies the CA cert to use for qemu. The default value is /etc/pki/CA/certs/qemu.pem .
InternalTLSVncCAFile	Specifies the CA cert to use for VNC TLS. The default value is /etc/pki/CA/certs/vnc.crt .
InternalTLSVncProxyCAFile	Specifies the CA cert to use for VNC TLS. The default value is /etc/pki/CA/certs/vnc.crt .
KernelArgs	Kernel Args to apply to the host.
LibvirtCACert	This specifies the CA certificate to use for TLS in libvirt. This file will be symlinked to the default CA path in libvirt, which is /etc/pki/CA/cacert.pem. Note that due to limitations GNU TLS, which is the TLS backend for libvirt, the file must be less than 65K (so we can't use the system's CA bundle). This parameter should be used if the default (which comes from the InternalTLSCAFile parameter) is not desired. The current default reflects TripleO's default CA, which is FreeIPA. It will only be used if internal TLS is enabled.
LibvirtEnabledPerfEvents	This is a performance event list which could be used as monitor. For example: cmt,mbml,mbmt . Make sure you are using Red Hat Enterprise Linux 7.4 as the base and libvirt version is 1.3.3 or above. Also ensure you have enabled the notifications and are using hardware with a CPU that supports the cmt flag.
LibvirtLogFilters	Defines a filter to select a different logging level for a given category log outputs, as specified in https://libvirt.org/logging.html . The default value is 1:libvirt 1:qemu 1:conf 1:security 3:event 3:json 3:file 3:object 1:util .
LibvirtNbdCACert	This specifies the CA certificate to use for NBD TLS. This file will be symlinked to the default CA path, which is /etc/pki/libvirt-nbd/ca-cert.pem. This parameter should be used if the default (which comes from the InternalTLSNbdCAFile parameter) is not desired. The current default reflects TripleO's default CA, which is FreeIPA. It will only be used if internal TLS is enabled.
LibvirtTLSPassword	The password for the libvirt service when TLS is enabled.

Parameter	Description
LibvirtTLSPriority	Override the compile time default TLS priority string. The default value is NORMAL:-VERS-SSL3.0:-VERS-TLS-ALL:+VERS-TLS1.2 .
LibvirtVncCACert	This specifies the CA certificate to use for VNC TLS. This file will be symlinked to the default CA path, which is /etc/pki/libvirt-vnc/ca-cert.pem. This parameter should be used if the default (which comes from the InternalTLSEncryptingCAFile parameter) is not desired. The current default reflects TripleO's default CA, which is FreeIPA. It will only be used if internal TLS is enabled.
MigrationSshKey	SSH key for migration. Expects a dictionary with keys <i>public_key</i> and <i>private_key</i> . Values should be identical to SSH public/private key files. The default value is {'public_key': '', 'private_key': ''} .
MigrationSshPort	Target port for migration over ssh. The default value is 2022 .
MultipathdEnable	Whether to enable the multipath daemon. The default value is False .
MysqIPv6	Enable IPv6 in MySQL. The default value is False .
NeutronMetadataProxySharedSecret	Shared secret to prevent spoofing.
NeutronPhysnetNUMANodesMapping	Map of physnet name as key and NUMA nodes as value. For example: NeutronPhysnetNUMANodesMapping: {'foo': [0, 1], 'bar': [1]} where foo and bar are physnet names and corresponding values are list of associated numa_nodes .
NeutronTunnelNUMANodes	Used to configure NUMA affinity for all tunneled networks.
NotificationDriver	Driver or drivers to handle sending notifications. The default value is messagingv2 .
NovaAdditionalCell	Whether this is an cell additional to the default cell. The default value is False .
NovaAutoDisabling	Max number of consecutive build failures before the nova-compute will disable itself. The default value is 10 .

Parameter	Description
NovaCPUAllocationRatio	Virtual CPU to physical CPU allocation ratio. The default value is 0.0 .
NovaComputeCpuDedicatedSet	A comma-separated list or range of physical host CPU numbers to which processes for pinned instance CPUs can be scheduled. For example, NovaComputeCpuDedicatedSet: [4-12,^8,15] reserves cores from 4-12 and 15, excluding 8. If setting this option, do not set the deprecated NovaVcpuPinSet parameter.
NovaComputeCpuSharedSet	If the deprecated NovaVcpuPinSet option is not set, then NovaComputeCpuSharedSet is set to a comma-separated list or range of physical host CPU numbers used to provide vCPU inventory, determine the host CPUs that unpinned instances can be scheduled to, and determine the host CPUs that instance emulator threads should be offloaded to for instances configured with the share emulator thread policy, hw:emulator_threads_policy=share . If the deprecated NovaVcpuPinSet is set, then NovaComputeCpuSharedSet is set to a list or range of host CPU cores used to determine the host CPUs that instance emulator threads should be offloaded to for instances configured with the share emulator thread policy (hw:emulator_threads_policy=share). In this case, NovaVcpuPinSet is used to provide vCPU inventory and to determine the host CPUs that both pinned and unpinned instances can be scheduled to. For example, NovaComputeCpuSharedSet: [4-12,^8,15] reserves cores from 4-12 and 15, excluding 8.
NovaComputeEnableKsm	Whether to enable KSM on compute nodes or not. Especially in NFV use case one wants to keep it disabled. The default value is False .
NovaComputeLibvirtType	Libvirt domain type. Defaults to <i>kvm</i> . The default value is kvm .
NovaComputeLibvirtVifDriver	Libvirt VIF driver configuration for the network.
NovaComputeOptEnvVars	List of optional environment variables.
NovaComputeOptVolumes	List of optional volumes.

Parameter	Description
NovaCronArchiveDeleteAllCells	Archive deleted instances from all cells. The default value is True .
NovaCronArchiveDeleteRowsAge	Cron to archive deleted instances - Age. This will define the retention policy when archiving the deleted instances entries in days. 0 means archive data older than today in shadow tables. The default value is 90 . The default value is 90 .
NovaCronArchiveDeleteRowsDestination	Cron to move deleted instances to another table - Log destination. The default value is /var/log/nova/nova-rowsflush.log .
NovaCronArchiveDeleteRowsHour	Cron to move deleted instances to another table - Hour. The default value is 0 .
NovaCronArchiveDeleteRowsMaxDelay	Cron to move deleted instances to another table - Max Delay. The default value is 3600 .
NovaCronArchiveDeleteRowsMaxRows	Cron to move deleted instances to another table - Max Rows. The default value is 1000 .
NovaCronArchiveDeleteRowsMinute	Cron to move deleted instances to another table - Minute. The default value is 1 .
NovaCronArchiveDeleteRowsMonth	Cron to move deleted instances to another table - Month. The default value is * .
NovaCronArchiveDeleteRowsMonthday	Cron to move deleted instances to another table - Month Day. The default value is * .
NovaCronArchiveDeleteRowsPurge	Purge shadow tables immediately after scheduled archiving. The default value is False .
NovaCronArchiveDeleteRowsUntilComplete	Cron to move deleted instances to another table - Until complete. The default value is True .
NovaCronArchiveDeleteRowsUser	Cron to move deleted instances to another table - User. The default value is nova .
NovaCronArchiveDeleteRowsWeekday	Cron to move deleted instances to another table - Week Day. The default value is * .
NovaCronPurgeShadowTablesAge	Cron to purge shadow tables - Age This will define the retention policy when purging the shadow tables in days. 0 means, purge data older than today in shadow tables. The default value is 14 .

Parameter	Description
NovaCronPurgeShadowTablesAllCells	Cron to purge shadow tables - All cells. The default value is True .
NovaCronPurgeShadowTablesDestination	Cron to purge shadow tables - Log destination. The default value is /var/log/nova/nova-rowspurge.log .
NovaCronPurgeShadowTablesHour	Cron to purge shadow tables - Hour. The default value is 5 .
NovaCronPurgeShadowTablesMaxDelay	Cron to purge shadow tables - Max Delay. The default value is 3600 .
NovaCronPurgeShadowTablesMinute	Cron to purge shadow tables - Minute. The default value is 0 .
NovaCronPurgeShadowTablesMonth	Cron to purge shadow tables - Month. The default value is * .
NovaCronPurgeShadowTablesMonthday	Cron to purge shadow tables - Month Day. The default value is * .
NovaCronPurgeShadowTablesUser	Cron to purge shadow tables - User. The default value is nova .
NovaCronPurgeShadowTablesVerbose	Cron to purge shadow tables - Verbose. The default value is False .
NovaCronPurgeShadowTablesWeekday	Cron to purge shadow tables - Week Day. The default value is * .
NovaCrossAZAttach	Whether instances can attach cinder volumes from a different availability zone. The default value is True .
NovaDbSyncTimeout	Timeout for OpenStack Compute (nova) database synchronization in seconds. The default value is 300 .
NovaDefaultFloatingPool	Default pool for floating IP addresses. The default value is public .
NovaDiskAllocationRatio	Virtual disk to physical disk allocation ratio. The default value is 0.0 .
NovaEnableDBArchive	Whether to create cron job for archiving soft deleted rows in OpenStack Compute (nova) database. The default value is True .

Parameter	Description
NovaEnableDBPurge	Whether to create cron job for purging soft deleted rows in OpenStack Compute (nova) database. The default value is True .
NovaEnableNUMALiveMigration	Whether to enable or not the live migration for NUMA topology instances. The default value is False .
NovaHWMachineType	To specify a default machine type per host architecture. The default value is x86_64=pc-i440fx-rhel7.6.0,aarch64=virt-rhel7.6.0,ppc64=pseries-rhel7.6.0,ppc64le=pseries-rhel7.6.0 .
NovalPv6	Enable IPv6 features for OpenStack Compute (nova). The default value is False .
NovalImageCacheTTL	Time in seconds that nova compute should continue caching an image once it is no longer used by any instances on the host. The default value is 86400 .
NovaLibvirtFileBackedMemory	Available capacity in MiB for file-backed memory. When configured, the NovaRAMAllocationRatio and NovaReservedHostMemory parameters must be set to 0. The default value is 0 .
NovaLibvirtMemStatsPeriodSeconds	A number of seconds to memory usage statistics period, zero or negative value mean to disable memory usage statistics. The default value is 10 .
NovaLibvirtNumPciePorts	Set num_pcie_ports to specify the number of PCIe ports an instance will get. Libvirt allows a custom number of PCIe ports (pcie-root-port controllers) a target instance will get. Some will be used by default, rest will be available for hotplug use. The default value is 16 .
NovaLibvirtRxQueueSize	Virtio-net RX queue size. Valid values are 256, 512, 1024. The default value is 512 .
NovaLibvirtTxQueueSize	Virtio-net TX queue size. Valid values are 256, 512, 1024. The default value is 512 .
NovaLibvirtVolumeUseMultipath	Whether to enable or not the multipath connection of the volumes. The default value is False .
NovaLiveMigrationWaitForVIFPlug	Whether to wait for network-vif-plugged events before starting guest transfer. The default value is True .

Parameter	Description
NovaLocalMetadataPerCell	Indicates that the nova-metadata API service has been deployed per-cell, so that we can have better performance and data isolation in a multi-cell deployment. Users should consider the use of this configuration depending on how OpenStack Networking (neutron) is setup. If networks span cells, you might need to run nova-metadata API service globally. If your networks are segmented along cell boundaries, then you can run nova-metadata API service per cell. When running nova-metadata API service per cell, you should also configure each OpenStack Networking (neutron) metadata-agent to point to the corresponding nova-metadata API service. The default value is False .
NovaNfsEnabled	Whether to enable or not the NFS backend for OpenStack Compute (nova). The default value is False .
NovaNfsOptions	NFS mount options for nova storage (when NovaNfsEnabled is true). The default value is context=system_u:object_r:nfs_t:s0 .
NovaNfsShare	NFS share to mount for nova storage (when NovaNfsEnabled is true).
NovaNfsVersion	NFS version used for nova storage (when NovaNfsEnabled is true). Since NFSv3 does not support full locking a NFSv4 version need to be used. To not break current installations the default is the previous hard coded version 4. The default value is 4 .
NovaOVSBridge	Name of integration bridge used by Open vSwitch. The default value is br-int .
NovaOVSDDBConnection	OVS DB connection string to used by OpenStack Compute (nova).
NovaPCIPassthrough	YAML list of PCI passthrough whitelist parameters.
NovaPMEMMappings	PMEM namespace mappings as backend for vPMEM feature. This parameter sets Nova's pmem_namespaces configuration options. PMEM namespaces needs to be create manually or with conjunction with NovaPMEMNamespaces parameter. Requires format: \$LABEL:\$NSNAME[\$NSNAME] [, \$LABEL:\$NSNAME[\$NSNAME]].

Parameter	Description
NovaPMEMNamespaces	Creates PMEM namespaces on the host server using ndctl tool through Ansible. Requires format: \$SIZE:\$NSNAME[\$SIZE:\$NSNAME...]. \$SIZE supports the suffixes "k" or "K" for KiB, "m" or "M" for MiB, "g" or "G" for GiB and "t" or "T" for TiB. NOTE: This requires properly configured NVDIMM regions and enough space for requested namespaces.
NovaPassword	The password for the OpenStack Compute (nova) service and database account.
NovaRAMAllocationRatio	Virtual RAM to physical RAM allocation ratio. The default value is 1.0 .
NovaReservedHostMemory	Reserved RAM for host processes. The default value is 4096 .
NovaReservedHugePages	A list of valid key=value which reflect NUMA node ID, page size (Default unit is KiB) and number of pages to be reserved. Example - NovaReservedHugePages: ["node:0,size:2048,count:64","node:1,size:1GB,count:1"] will reserve on NUMA node 0 64 pages of 2MiB and on NUMA node 1 1 page of 1GiB.
NovaResumeGuestsShutdownTimeout	Number of seconds we're willing to wait for a guest to shut down. If this is 0, then there is no time out (use with caution, as guests might not respond to a shutdown request). The default value is 300 seconds (5 minutes). The default value is 300 .
NovaResumeGuestsStateOnHostBoot	Whether to start running instance on compute host reboot. The default value is False .
NovaSchedulerAvailableFilters	List of available filters for OpenStack Compute (nova) to use to filter nodes.
NovaSchedulerDefaultFilters	An array of filters OpenStack Compute (nova) uses to filter a node. OpenStack Compute applies these filters in the order they are listed. Place your most restrictive filters first to make the filtering process more efficient.

Parameter	Description
NovaSchedulerDiscoverHostsInCellsInterval	This value controls how often (in seconds) the scheduler should attempt to discover new hosts that have been added to cells. The default value of -1 disables the periodic task completely. It is recommended to set this parameter for deployments using OpenStack Bare Metal (ironic). The default value is -1 .
NovaSchedulerEnableIsolatedAggregateFiltering	This setting allows the scheduler to restrict hosts in aggregates based on matching required traits in the aggregate metadata and the instance flavor/image. If an aggregate is configured with a property with key trait:\$TRAIT_NAME and value required, the instance flavor extra_specs and/or image metadata must also contain trait:\$TRAIT_NAME=required to be eligible to be scheduled to hosts in that aggregate. The default value is False .
NovaSchedulerLimitTenantsToPlacementAggregate	This value allows to have tenant isolation with placement. It ensures hosts in tenant-isolated host aggregate and availability zones will only be available to specific set of tenants. The default value is False .
NovaSchedulerMaxAttempts	Maximum number of attempts the scheduler will make when deploying the instance. You should keep it greater or equal to the number of bare metal nodes you expect to deploy at once to work around potential race conditions when scheduling. The default value is 3 .
NovaSchedulerPlacementAggregateRequiredForTenants	This setting, when NovaSchedulerLimitTenantsToPlacementAggregate is true, controls whether or not a tenant with no aggregate affinity will be allowed to schedule to any available node. If aggregates are used to limit some tenants but not all, then this should be False. If all tenants should be confined via aggregate, then this should be True. The default value is False .
NovaSchedulerQueryImageType	This setting causes the scheduler to ask placement only for compute hosts that support the disk_format of the image used in the request. The default value is True .
NovaSchedulerQueryPlacementForAvailabilityZone	This setting allows the scheduler to look up a host aggregate with metadata key of availability zone set to the value provided by incoming request, and request result from placement be limited to that aggregate. The default value is False .

Parameter	Description
NovaSchedulerWorkers	Number of workers for OpenStack Compute (nova) Scheduler services. The default value is 0 .
NovaSyncPowerStateInterval	Interval to sync power states between the database and the hypervisor. Set to -1 to disable. Setting this to 0 will run at the default rate. The default value is 0 .
NovaVcpuPinSet	(Deprecated) A list or range of physical CPU cores to reserve for virtual machine processes. For example, NovaVcpuPinSet: [4-12,^8] reserves cores from 4-12 excluding 8. This parameter has been deprecated. Use NovaComputeCpuDedicatedSet and NovaComputeCpuSharedSet instead.
NovaWorkers	Number of workers for the Compute's Conductor service. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. 0 sets to the OpenStack internal default, which is equal to the number of CPU cores on the node. The default value is 0 .
OvsDpdkSocketMemory	Sets the amount of hugepage memory to assign per NUMA node. It is recommended to use the socket closest to the PCIe slot used for the desired DPDK NIC. The format should be in "<socket 0 mem>, <socket 1 mem>, <socket n mem>", where the value is specified in MB. For example: "1024,0".
PlacementAPIInterface	Endpoint interface to be used for the placement API. The default value is internal .
PlacementPassword	The password for the Placement service and database account.
QemuCACert	This specifies the CA certificate to use for qemu. This file will be symlinked to the default CA path, which is /etc/pki/qemu/ca-cert.pem. This parameter should be used if the default (which comes from the InternalTLSQemuCAFile parameter) is not desired. The current default reflects TripleO's default CA, which is FreeIPA. It will only be used if internal TLS is enabled.
QemuMemoryBackingDir	Directory used for memoryBacking source if configured as file. NOTE: big files will be stored here.

Parameter	Description
StackUpdateType	Type of update, to differentiate between UPGRADE and UPDATE cases when StackAction is UPDATE (both are the same stack action).
UpgradeLevelNovaCompute	OpenStack Compute upgrade level.
UseTLSTransportForNbd	If set to true and if EnableInternalTLS is enabled, it will enable TLS transport for libvirt NBD and configure the relevant keys for libvirt. The default value is True .
UseTLSTransportForVnc	If set to true and if EnableInternalTLS is enabled, it will enable TLS transport for libvirt VNC and configure the relevant keys for libvirt. The default value is True .
VerifyGlanceSignatures	Whether to verify image signatures. The default value is False .
VhostuserSocketGroup	The vhost-user socket directory group name. Defaults to <i>qemu</i> . When vhostuser mode is <i>dpdkvhostuserclient</i> (which is the default mode), the vhost socket is created by qemu. The default value is qemu .

CHAPTER 18. OBJECT STORAGE (SWIFT) PARAMETERS

Parameter	Description
SwiftAccountWorkers	Number of workers for Swift account service. The default value is 0 .
SwiftCeilometerIgnoreProjects	Comma-separated list of project names to ignore. The default value is ['service'] .
SwiftCeilometerPipelineEnabled	Set to False to disable the object storage proxy ceilometer pipeline. The default value is False .
SwiftContainerSharderEnabled	Set to True to enable Swift container sharder service. The default value is False .
SwiftContainerWorkers	Number of workers for Swift account service. The default value is 0 .
SwiftCorsAllowedOrigin	Indicate whether this resource may be shared with the domain received in the request "origin" header.
SwiftEncryptionEnabled	Set to True to enable data-at-rest encryption in Swift. The default value is False .
SwiftHashSuffix	A random string to be used as a salt when hashing to determine mappings in the ring.
SwiftMinPartHours	The minimum time (in hours) before a partition in a ring can be moved following a rebalance. The default value is 1 .
SwiftMountCheck	Check if the devices are mounted to prevent accidentally writing to the root device. The default value is False .
SwiftObjectWorkers	Number of workers for Swift account service. The default value is 0 .
SwiftPartPower	Partition power to use when building object storage rings. The default value is 10 .
SwiftPassword	The password for the object storage service account.
SwiftProxyNodeTimeout	Timeout for requests going from swift-proxy to account, container, and object services. The default value is 60 .

Parameter	Description
SwiftRawDisks	Additional raw devices to use for the object storage backend. For example: {sdb: {}}
SwiftReplicas	Number of replicas to use in the object storage rings. The default value is 3 .
SwiftRingBuild	Whether to manage object storage rings or not. The default value is True .
SwiftRingGetTempurl	A temporary Swift URL to download rings from.
SwiftRingPutTempurl	A temporary Swift URL to upload rings to.
SwiftUseLocalDir	Use a local directory for object storage services when building rings. The default value is True .
SwiftWorkers	Number of workers for object storage service. Note that more workers creates a larger number of processes on systems, which results in excess memory consumption. It is recommended to choose a suitable non-default value on systems with high CPU core counts. 0 sets to the OpenStack internal default, which is equal to the number of CPU cores on the node. The default value is 0 .

CHAPTER 19. TIME PARAMETERS

Parameter	Description
ChronyAclRules	Access Control List of NTP clients. By default no clients are permitted. The default value is ['deny all'] .
ChronyGlobalPoolOptions	Default pool options for the configured NTP pools in chrony.conf. If this is specified, NtpIburstEnable, MaxPoll, and MinPoll are ignored.
ChronyGlobalServerOptions	Default server options for the configured NTP servers in chrony.conf. If this is specified, NtpIburstEnable, MaxPoll, and MinPoll are ignored.
EnablePackageInstall	Set to true to enable package installation at deploy time. The default value is false .
MaxPoll	Specify maximum poll interval of upstream servers for NTP messages, in seconds to the power of two. Allowed values are 4 to 17. The default value is 10 .
MinPoll	Specify minimum poll interval of upstream servers for NTP messages, in seconds to the power of two. The minimum poll interval defaults to 6 (64 s). Allowed values are 4 to 17. The default value is 6 .
NtpIburstEnable	Specifies whether to enable the iburst option for every NTP peer. If iburst is enabled, when the NTP server is unreachable NTP will send a burst of eight packages instead of one. This is designed to speed up the initial synchronization. The default value is True .
NtpPool	NTP pool list. Defaults to [], so only NtpServer is used by default.
NtpServer	NTP servers list. The default value is ['0.pool.ntp.org', '1.pool.ntp.org', '2.pool.ntp.org', '3.pool.ntp.org'] .
TimeZone	The timezone to be set on the overcloud. The default value is UTC .