

Network Working Group  
Request for Comments: 1747  
Category: Standards Track

J. Hilgeman, Chair  
Apertus Technologies, Inc.  
S. Nix  
Metaplex, Inc.  
A. Bartky  
Sync Research, Inc.  
W. Clark, Editor  
cisco Systems, Inc.  
January 1995

## Definitions of Managed Objects for SNA Data Link Control (SDLC) using SMIV2

### Status of this Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

### Abstract

This specification defines an extension to the Management Information Base (MIB) for use with SNMP-based network management. In particular, it defines objects for managing the configuration, monitoring and control of data link controls in an SNA environment. This draft identifies managed objects for SNA Synchronous Data Link Control (SDLC) links only.

### Table of Contents

1.	The SNMPv2 Network Management Framework .....	2
1.1	Object Definitions .....	2
2.	Overview .....	2
2.1	Tables Defined in the SNADLC SDLC MIB .....	3
2.2	Row Creation Mechanism .....	3
2.3	Relationship to the Interfaces Group .....	4
3.	Definitions .....	7
3.1	Port Administrative Table .....	9
3.2	Port Operational Table .....	14
3.3	Port Statistics Table .....	20
3.4	Link Station Administrative Table .....	26
3.5	Link Station Operational Table .....	35
3.6	Link Station Statistics Table .....	44
3.7	Trap Definitions .....	56
3.8	Compliance Statements .....	57

4.	Acknowledgments .....	65
5.	References .....	65
6.	Glossary .....	66
7.	Security Considerations .....	67
8.	Authors' Addresses .....	67

## 1. The SNMPv2 Network Management Framework

The SNMPv2 Network Management Framework consists of four major components. They are:

- o RFC 1441 which defines the SMI, the mechanisms used for describing and naming objects for the purpose of management.
- o STD 17, RFC 1213 defines MIB-II, the core set of managed objects for the Internet suite of protocols.
- o RFC 1445 which defines the administrative and other architectural aspects of the framework.
- o RFC 1448 which defines the protocol used for network access to managed objects.

The Framework permits new objects to be defined for the purpose of experimentation and evaluation.

### 1.1. Object Definitions

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. Objects in the MIB are defined using the subset of Abstract Syntax Notation One (ASN.1) defined in the SMI. In particular, each object type is named by an OBJECT IDENTIFIER, an administratively assigned name. The object type together with an object instance serves to uniquely identify a specific instantiation of the object. For human convenience, we often use a textual string, termed the descriptor, to refer to the object type.

## 2. Overview

This memo identifies the proposed set of objects for configuring, monitoring, and controlling SDLC ports and link stations.

## 2.1. Tables Defined in the SNADLC SDLC MIB

The SNADLC MIB is composed of two managed entities with three tables each. The two managed entities for SDLC are:

- o Ports: the physical connection, and
- o Link Stations: the logical connections on the Port.

The three management tables are:

- o Administration: objects used for configuring and controlling the operation of a Port or Link Station,
- o Operational: objects that reflect the run-time state of the Port or Link Station, and
- o Statistics: objects that reflect the operating metrics of the Port or Link Station.

Considering the above combinations, the following are the actual tables found in this MIB:

- 1) Port Administration Table,
- 2) Port Operation Table,
- 3) Port Statistics Table,
- 4) Link Station Administration Table,
- 5) Link Station Operation Table,
- 6) Link Station Statistics Table.

All variables in this MIB relate to SDLC ports and link stations only. Any variable relating to higher-layer entities in SNA such as Physical Units (PU) and Logical Units (LU) are found in the SNA NAU MIB [4].

## 2.2. Row Creation Mechanism

Row creation mechanism for the `sdclLSAdminTable` is based on the use of the `RowStatus` object. It follows the rules for the use in SNMPv1 context proposed in the memo "Row creation with SNMPv1" [5]. Before accepting the destroy value for an entry, an agent has to verify the operational state of the corresponding entry in the `sdclLSOperTable` entry.

### 2.3. Relationship to the Interfaces Group

This memo shall conform to the recommendations of [6].

The SDLC layer of each SDLC Port shall be modeled by a row in the ifTable with an ifType using the IANA assigned number for SDLC (17). Each SDLC port interface must comply with the following conformance groups in [6]:

- ifGeneralGroup
- ifStackGroup
- ifPacketGroup

An implementation may optionally comply with the ifTestGroup defined in that memo to execute vendor specific tests. An example of this would be to perform LPDA test functions.

The SDLC port's relation with its physical, or lower-layer interface (i.e., RS-232, V.35, etc.) shall be modeled by a row in the ifStackTable with the ifStackHigherLayer pointing to the SDLC port ifTable instance and the ifStackLowerLayer pointing to the physical media-specific ifTable instance. The media-specific objects of these lower-layer interfaces will, of course, be described in their respective MIBs (i.e., [1]).

The following table provides specific implementation guidelines for all the interface group objects listed in the conformance tables above.

Object	Use for an SDLC Port
ifIndex	Each SDLC port is represented by an ifEntry. All SDLC port tables shall be indexed by ifIndex.
ifDescr	Description of the SDLC port.
ifType	The IANA value reserved for SDLC - 17.
ifMtu	Refer to [6].
ifSpeed	This object shall reflect the value of the corresponding object in the ifEntry of the associated lower-layer interface.
ifPhysAddress	A string denoting the physical location of the SDLC port within its node. This shall have unique significance within each implementing node.

ifAdminStatus	This object shall reflect the value of the corresponding object in the ifEntry of the associated lower-layer interface.
ifOperStatus	This object shall reflect the value of the corresponding object in the ifEntry of the associated lower-layer interface.
ifLastChange	Refer to [6].
ifInOctets	Refer to [6].
ifInUcastPkts	This object shall count packets received from a specific SDLC poll address. Packets for the SDLC broadcast address of x'FF' are not counted.
ifInDiscards	Refer to [6].
ifInErrors	Refer to [6]. Specific counters for these errors are kept in the sdlcPortStatsTable.
ifInUnknownProtos	This counter shall return zero for SDLC ports.
ifOutOctets	Refer to [6].
ifOutUcastPkts	This object shall count packets transmitted to a specific SDLC poll address (not x'FF').
ifOutDiscards	Refer to [6].
ifOutErrors	Refer to [6]. Specific counters for these errors are kept in the sdlcPortStatsTable.
ifName	The textual name of the SDLC port or an octet string of zero length.
ifInMulticastPkts	The value is 0 (not applicable to the SDLC layer).
ifInBroadcastPkts	This object shall count packets received on this interface addressed to the SDLC broadcast address (x'FF'). Only point-to-point ports supporting a secondary switched station should return non-zero values.
ifOutMulticastPkts	The value is 0 (not applicable to the SDLC layer).
ifOutBroadcastPkts	This object shall count packets transmitted on this interface which were addressed to the SDLC broadcast

address (x'FF'). Only point-to-point ports supporting a primary switched station should return non-zero values.

ifHC*	Not part of the conformance group.
ifLinkUpDownTrapEnable	Refer to [6]. Default is disabled (2).
ifHighSpeed	Refer to [6].
ifPromiscuousMode	Should return false if this interface receives only packets addressed to its SDLC poll address(es). However, in certain implementations, the lower-layer interface shall present all frames to the SDLC port regardless of the poll address. Such frames may be the result of a misconfigured peer or the secondary end of a multipoint connection. Such implementations should return true for this object.
ifConnectorPresent	Set to 'false'.
ifStackHigherLayer	For each SDLC port there will be an ifStackEntry with this object's value referring to the ifIndex of the SDLC port's ifEntry for the SDLC layer.
ifStackLowerLayer	For each SDLC port there will be an ifStackEntry with this object's value referring to the ifIndex of the physical layer interface's ifEntry for that SDLC port.
ifStackStatus	Refer to [6].

### 3. Definitions

SNA-SDLC-MIB DEFINITIONS ::= BEGIN

#### IMPORTS

MODULE-IDENTITY, OBJECT-TYPE, NOTIFICATION-TYPE,  
Counter32, Integer32, TimeTicks  
FROM SNMPv2-SMI  
DisplayString, RowStatus, TimeInterval  
FROM SNMPv2-TC  
MODULE-COMPLIANCE, OBJECT-GROUP  
FROM SNMPv2-CONF  
mib-2, ifIndex, ifAdminStatus, ifOperStatus  
FROM RFC1213-MIB;

#### snaDLC MODULE-IDENTITY

LAST-UPDATED "9411150000Z"  
ORGANIZATION "IETF SNA DLC MIB Working Group"  
CONTACT-INFO  
" Wayne Clark

Postal: cisco Systems, Inc.  
3100 Smoketree Ct.  
Suite 1000  
Raleigh, NC 27604  
US

Tel: +1 919 878 6958

E-Mail: wclark@cisco.com"

#### DESCRIPTION

"This is the MIB module for objects used to  
manage SDLC devices."

::= { mib-2 41 }

--

-- The following data link controls are modelled in this MIB module:

--

-- 1. SDLC

--

sdlc OBJECT IDENTIFIER ::= { snaDLC 1 }

```
--
-- THE SDLC GROUP
-- =====
--
-- The following resources are modelled in the SDLC group of this
-- MIB module:
--
-- 1. PORTS
-- 2. LINK STATIONS
--
sdlcPortGroup OBJECT IDENTIFIER ::= { sdlc 1 } -- Physical Ports
sdlcLSGroup   OBJECT IDENTIFIER ::= { sdlc 2 } -- Logical Link Stations
--
-- THE SDLC PORT GROUP
-- =====
--
-- The following classes of information is modelled for each SDLC port:
--
-- 1. ADMINISTRATIVE ( read/write)
-- 2. OPERATIONAL    ( read-only)
-- 3. STATISTICS      ( read-only)
--
-- Information not found in this group is found in tables described in
-- the following RFCs:
--
-- 1. RFC1213 - MIB-II
--
--          TABLE                      INDEX
--          =====                      =====
--          a.  ifTable                  ifIndex
--
-- 2. RFC1659 - The RS232-like MIB
--
--          TABLE                      INDEX
--          =====                      =====
--          a.  rs232PortTable           rs232PortIndex
--          b.  rs232SyncPortTable       rs232SyncPortIndex
--          c.  rs232InSigTable          rs232InSigPortIndex,
--                                     rs232InSigName
--          d.  rs232OutSigTable         rs232OutSigPortIndex,
--                                     rs232OutSigName
--          ** e.  rs232AsyncPortTable    rs232AsyncPortIndex
--
--          ** rs232AsyncPortTable for ISO 3309.3 ( Start-Stop SDLC).
```



```
-- *****
-- *
-- *          THE SDLC PORT ADMINISTRATIVE TABLE
-- *
-- *****
```

**sdlcPortAdminTable** OBJECT-TYPE  
 SYNTAX SEQUENCE OF SdlcPortAdminEntry  
 MAX-ACCESS not-accessible  
 STATUS current  
 DESCRIPTION  
 "This table contains objects that can be changed to manage an SDLC port. Changing one of these parameters may take effect in the operating port immediately or may wait until the interface is restarted depending on the details of the implementation.

Most of the objects in this read-write table have corresponding read-only objects in the sdlcPortOperTable that return the current operating value.

The operating values may be different from these configured values if a configured parameter was changed after the interface was started."

::= { sdlcPortGroup 1 }

**sdlcPortAdminEntry** OBJECT-TYPE  
 SYNTAX SdlcPortAdminEntry  
 MAX-ACCESS not-accessible  
 STATUS current  
 DESCRIPTION  
 "A list of configured values for an SDLC port."  
 INDEX { ifIndex }  
 ::= { sdlcPortAdminTable 1 }

**SdlcPortAdminEntry** ::= SEQUENCE  
 {  
     sdlcPortAdminName DisplayString,  
     sdlcPortAdminRole INTEGER,  
     sdlcPortAdminType INTEGER,  
     sdlcPortAdminTopology INTEGER,  
     sdlcPortAdminISTATUS INTEGER,  
     sdlcPortAdminACTIVTO TimeInterval,  
     sdlcPortAdminPAUSE TimeInterval,  
     sdlcPortAdminSERVLIM Integer32,

```

        sdlcPortAdminSlowPollTimer TimeInterval
    }

sdlcPortAdminName    OBJECT-TYPE
    SYNTAX      DisplayString (SIZE (1..10))
    MAX-ACCESS   read-write
    STATUS      current
    DESCRIPTION
        "An octet string that defines the physical port
        to which this interface is assigned. It has
        implementation-specific significance. Its value
        shall be unique within the administered
        system. It must contain only ASCII printable
        characters. Should an implementation choose to
        accept a write operation for this object, it
        causes the logical port definition associated
        with the table instance to be moved to a
        different physical port. A write operation
        shall not take effect until the port is cycled
        inactive."
    ::= { sdlcPortAdminEntry 1 }

sdlcPortAdminRole    OBJECT-TYPE
    SYNTAX      INTEGER
    {
        primary(1),
        secondary(2),
        negotiable(3)
    }
    MAX-ACCESS   read-write
    STATUS      current
    DESCRIPTION
        "This object describes the role that the link
        station shall assume the next time a connection
        is established.

        Even though this is defined as a port object,
        it is a link station attribute in the sense
        that a role is per link station. However, it
        is not possible to vary link station roles on a
        particular port. For example, if an SDLC port
        is configured to primary, all link stations on
        that port must be primary."
    ::= { sdlcPortAdminEntry 2 }

sdlcPortAdminType    OBJECT-TYPE
    SYNTAX      INTEGER
    {

```

```

        leased(1),
        switched(2)
    }
    MAX-ACCESS    read-write
    STATUS        current
    DESCRIPTION
        "This parameter defines whether the SDLC port
        is to connect to a leased or switched line. A
        write operation to this administrative value
        shall not take effect until the SDLC port has
        been cycled inactive."
    DEFVAL { leased }
    ::= { sdlcPortAdminEntry 3 }

```

```

sdlcPortAdminTopology OBJECT-TYPE
    SYNTAX        INTEGER
    {
        pointToPoint(1),
        multipoint(2)
    }
    MAX-ACCESS    read-write
    STATUS        current
    DESCRIPTION
        "This parameter defines whether the SDLC port is
        capable of operating in either a point-to-point
        or multipoint topology.

        sdlcPortAdminTopology == multipoint implies the
        port can also operate in a point-to-point
        topology.  sdlcPortAdminTopology ==
        pointToPoint does not imply the port can
        operate in a multipoint topology.

        A write operation to this administrative value
        shall not take effect until the SDLC port has
        been cycled inactive."
    DEFVAL { pointToPoint }
    ::= { sdlcPortAdminEntry 4 }

```

```

sdlcPortAdminISTATUS OBJECT-TYPE
    SYNTAX        INTEGER
    {
        inactive(1),
        active(2)
    }
    MAX-ACCESS    read-write
    STATUS        current
    DESCRIPTION

```

"This parameter controls the initial value of the administrative status, ifAdminStatus, of this SDLC port at port start-up. Depending on the implementation, a write operation to this administrative object may not take effect until the SDLC port has been cycled inactive."

DEFVAL { active }  
 ::= { sdlcPortAdminEntry 5 }

## sdlcPortAdminACTIVT0

## OBJECT-TYPE

SYNTAX TimeInterval

MAX-ACCESS read-write

STATUS current

## DESCRIPTION

"This parameter defines the period of time (in 1/100ths of a second) that the port will allow a switched line to remain inactive before disconnecting. A switched line is considered to be inactive if there are no I-Frames being transferred. A value of zero indicates no timeout. Depending on the implementation, a write operation to this administered value may not take effect until the port is cycled inactive."

This object only has meaning for SDLC ports where sdlcPortAdminType == switched

The object descriptor contains the name of an NCP configuration parameter, ACTIVT0. Please note that the value of this object represents 1/100ths of a second while the NCP ACTIVT0 is represented in seconds."

DEFVAL { 0 }  
 ::= { sdlcPortAdminEntry 6 }

## sdlcPortAdminPAUSE

## OBJECT-TYPE

SYNTAX TimeInterval

MAX-ACCESS read-write

STATUS current

## DESCRIPTION

"This object defines the minimum elapsed time (in 1/100ths of a second) between any two traversals of the poll list for a primary SDLC port. Depending on the implementation, a write operation to this administered value may not take effect until the port is cycled inactive."

The object descriptor contains the name of an NCP configuration parameter, PAUSE. Please note that the value of this object represents 1/100ths of a second while the NCP PAUSE is represented in 1/10ths of a second.

This object only has meaning for SDLC ports where `sdlcPortAdminRole == primary` "

DEFVAL { 200 }

::= { `sdlcPortAdminEntry 7` }

#### `sdlcPortAdminSERVLIM` OBJECT-TYPE

SYNTAX Integer32  
MAX-ACCESS read-write  
STATUS current  
DESCRIPTION

"This object defines the number of times the active poll list will be traversed before polling a station on the slow poll list for a primary, multipoint SDLC port. Depending on the implementation, a write operation to this administered value may not take effect until the port is cycled inactive.

This object only has meaning for SDLC ports where

`sdlcPortAdminRole == primary`

and

`sdlcPortAdminTopology == multipoint` "

DEFVAL { 20 }

::= { `sdlcPortAdminEntry 8` }

#### `sdlcPortAdminSlowPollTimer` OBJECT-TYPE

SYNTAX TimeInterval  
MAX-ACCESS read-write  
STATUS current  
DESCRIPTION

"This object describes the elapsed time (in 1/100ths of a second) between polls for failed secondary link station addresses. Depending on the implementation, a write operation to this administered value may not take effect until the port is cycled inactive.

This object only has meaning for SDLC ports where

`sdlcPortAdminRole == primary`

and

```

                sdlcPortAdminTopology == multipoint "
DEFVAL { 2000 }
 ::= { sdlcPortAdminEntry 9 }

-- *****
-- *
-- *          THE SDLC PORT OPERATIONAL TABLE
-- *
-- *****

sdlcPortOperTable    OBJECT-TYPE
    SYNTAX      SEQUENCE OF SdlcPortOperEntry
    MAX-ACCESS   not-accessible
    STATUS      current
    DESCRIPTION
        "This table contains current SDLC port
        parameters. Many of these objects have
        corresponding objects in the sdlcPortAdminTable."
    ::= { sdlcPortGroup 2 }

sdlcPortOperEntry    OBJECT-TYPE
    SYNTAX      SdlcPortOperEntry
    MAX-ACCESS   not-accessible
    STATUS      current
    DESCRIPTION
        "Currently set parameters for a specific SDLC
        port."
    INDEX       { ifIndex }
    ::= { sdlcPortOperTable 1 }

SdlcPortOperEntry    ::= SEQUENCE
{
    sdlcPortOperName          DisplayString,
    sdlcPortOperRole          INTEGER,
    sdlcPortOperType          INTEGER,
    sdlcPortOperTopology      INTEGER,
    sdlcPortOperISTATUS       INTEGER,
    sdlcPortOperACTIVTO       TimeInterval,
    sdlcPortOperPAUSE         TimeInterval,
    sdlcPortOperSlowPollMethod INTEGER,
    sdlcPortOperSERVLIM       Integer32,
    sdlcPortOperSlowPollTimer TimeInterval,
    sdlcPortOperLastModifyTime TimeTicks,
    sdlcPortOperLastFailTime  TimeTicks,
    sdlcPortOperLastFailCause INTEGER
}

sdlcPortOperName      OBJECT-TYPE

```

SYNTAX        DisplayString (SIZE (1..8))  
 MAX-ACCESS   read-only  
 STATUS        current  
 DESCRIPTION  
     "An octet string that describes the physical  
     port to which this interface is currently  
     attached. It has implementation-specific  
     significance."  
 ::= { sdlcPortOperEntry 1 }

**sdlcPortOperRole**

OBJECT-TYPE  
 SYNTAX        INTEGER  
 {  
     primary(1),  
     secondary(2),  
     undefined(3)  
 }  
 MAX-ACCESS   read-only  
 STATUS        current  
 DESCRIPTION  
     "This object describes the role that the link  
     station has assumed on this connection.  
  
     Even though this is defined as a port object,  
     it is a link station attribute in the sense  
     that a role is per link station. However, it  
     is not possible to vary link station roles on a  
     particular port. For example, if an SDLC port  
     is configured to primary, all link stations on  
     that port must be primary.  
  
     The value of sdlcPortOperRole is undefined(3)  
     whenever the link station role has not yet been  
     established by the mode setting command."  
 ::= { sdlcPortOperEntry 2 }

**sdlcPortOperType**

OBJECT-TYPE  
 SYNTAX        INTEGER  
 {  
     leased(1),  
     switched(2)  
 }  
 MAX-ACCESS   read-only  
 STATUS        current  
 DESCRIPTION  
     "This parameter defines whether the SDLC port  
     is currently operating as though connected to a  
     leased or switched line."

```
 ::= { sdlcPortOperEntry 3 }
```

```
sdlcPortOperTopology OBJECT-TYPE
SYNTAX      INTEGER
{
    pointToPoint(1),
    multipoint(2)
}
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "This parameter defines whether the SDLC port is
    currently operating in a point-to-point or
    multipoint topology."
 ::= { sdlcPortOperEntry 4 }
```

```
sdlcPortOperISTATUS OBJECT-TYPE
SYNTAX      INTEGER
{
    inactive(1),
    active(2)
}
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "This parameter describes the initial value of
    the administrative status, ifAdminStatus, of
    this SDLC port at last port start-up."
 ::= { sdlcPortOperEntry 5 }
```

```
sdlcPortOperACTIVT0 OBJECT-TYPE
SYNTAX      TimeInterval
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "This parameter defines the period of time (in
    100ths of a second) that the port will allow a
    switched line to remain inactive before
    disconnecting. A switched line is considered
    to be inactive if there are no I-Frames being
    transferred.

    The object descriptor contains the name of an
    NCP configuration parameter, ACTIVT0. Please
    note that the value of this object represents
    1/100ths of a second while the NCP ACTIVT0 is
    represented in seconds."
```



A value of zero indicates no timeout."  
 ::= { sdlcPortOperEntry 6 }

**sdlcPortOperPAUSE** OBJECT-TYPE  
 SYNTAX TimeInterval  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
 "This object describes the current minimum elapsed time (in 1/100ths of a second) between any two traversals of the poll list for a primary SDLC port.  
  
 The object descriptor contains the name of an NCP configuration parameter, PAUSE. Please note that the value of this object represents 1/100ths of a second while the NCP PAUSE is represented in 1/10ths of a second.  
  
 This object only has meaning for SDLC ports where  
     sdlcPortAdminRole == primary "  
 ::= { sdlcPortOperEntry 7 }

**sdlcPortOperSlowPollMethod** OBJECT-TYPE  
 SYNTAX INTEGER  
 {  
     servlim(1),  
     pollpause(2),  
     other(3)  
 }  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
 "This object defines the exact method that is in effect for periodically polling failed secondary link station addresses.  
  
 If sdlcPortOperSlowPollMethod == servlim, then sdlcPortOperSERVLIM defines the actual polling characteristics.  
  
 If sdlcPortOperSlowPollMethod == pollpause, then sdlcPortOperSlowPollTimer defines the actual polling characteristics.  
  
 If sdlcPortOperSlowPollMethod == other, then the polling characteristics are modeled in

vendor-specific objects.

This object only has meaning for SDLC ports  
where

sdlcPortOperRole == primary

and

sdlcPortOperTopology == multipoint "

::= { sdlcPortOperEntry 8 }

sdlcPortOperSERVLIM OBJECT-TYPE

SYNTAX Integer32

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"This object describes the number of times the active poll list is currently being traversed before polling a station on the slow poll list for a primary, multipoint SDLC port.

This object only has meaning for SDLC ports  
where

sdlcPortOperRole == primary

and

sdlcPortOperTopology == multipoint "

::= { sdlcPortOperEntry 9 }

sdlcPortOperSlowPollTimer OBJECT-TYPE

SYNTAX TimeInterval

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"This object describes the elapsed time (in 1/100ths of a second) between polls for failed secondary link station addresses.

This object only has meaning for SDLC ports  
where

sdlcPortOperRole == primary

and

sdlcPortOperTopology == multipoint "

::= { sdlcPortOperEntry 10 }

sdlcPortOperLastModifyTime OBJECT-TYPE

SYNTAX TimeTicks

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"This object describes the value of sysUpTime

when this port definition was last modified.  
 If the port has not been modified, then this  
 value shall be zero."  
 ::= { sdlcPortOperEntry 11 }

sdlcPortOperLastFailTime OBJECT-TYPE  
 SYNTAX TimeTicks  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
 "This object describes the value of sysUpTime  
 when this SDLC port last failed. If the port  
 has not failed, then this value shall be zero."  
 ::= { sdlcPortOperEntry 12 }

sdlcPortOperLastFailCause OBJECT-TYPE  
 SYNTAX INTEGER  
 {  
 undefined(1),  
 physical(2)  
 }  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
 "This enumerated object describes the cause of  
 the last failure of this SDLC port. If the  
 port has not failed, then this object has a  
 value of undefined(1)."  
 DEFVAL { undefined }  
 ::= { sdlcPortOperEntry 13 }

```
-- *****
-- *
-- *          THE SDLC PORT STATISTICS TABLE
-- *
-- *****
```

```
sdlcPortStatsTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF SdlcPortStatsEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "Each entry in this table contains statistics
         for a specific SDLC port."
    ::= { sdlcPortGroup 3 }
```

```
sdlcPortStatsEntry OBJECT-TYPE
    SYNTAX      SdlcPortStatsEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "A list of statistics for an SDLC port."
    INDEX       { ifIndex }
    ::= { sdlcPortStatsTable 1 }
```

```
SdlcPortStatsEntry ::= SEQUENCE
{
    sdlcPortStatsPhysicalFailures Counter32,
    sdlcPortStatsInvalidAddresses Counter32,
    sdlcPortStatsDwarfFrames      Counter32,
    sdlcPortStatsPollsIn          Counter32,
    sdlcPortStatsPollsOut         Counter32,
    sdlcPortStatsPollRspsIn       Counter32,
    sdlcPortStatsPollRspsOut      Counter32,
    sdlcPortStatsLocalBusies      Counter32,
    sdlcPortStatsRemoteBusies     Counter32,
    sdlcPortStatsIFramesIn        Counter32,
    sdlcPortStatsIFramesOut       Counter32,
    sdlcPortStatsOoctetsIn        Counter32,
    sdlcPortStatsOoctetsOut       Counter32,
    sdlcPortStatsProtocolErrs     Counter32,
    sdlcPortStatsActivityT0s      Counter32,
    sdlcPortStatsRNRLIMITs        Counter32,
    sdlcPortStatsRetriesExps      Counter32,
    sdlcPortStatsRetransmitsIn    Counter32,
    sdlcPortStatsRetransmitsOut   Counter32
}
```

```
sdlcPortStatsPhysicalFailures OBJECT-TYPE
```

```
SYNTAX          Counter32
MAX-ACCESS      read-only
STATUS          current
DESCRIPTION
    "This object reflects the total number of times
    this port has failed due to its physical media
    since port startup. At port startup time,
    this object must be initialized to zero."
 ::= { sdlcPortStatsEntry 1 }
```

```
sdlcPortStatsInvalidAddresses OBJECT-TYPE
SYNTAX          Counter32
MAX-ACCESS      read-only
STATUS          current
DESCRIPTION
    "This object reflects the total number of
    frames received by this port with invalid link
    station addresses."
 ::= { sdlcPortStatsEntry 2 }
```

```
sdlcPortStatsDwarfFrames OBJECT-TYPE
SYNTAX          Counter32
MAX-ACCESS      read-only
STATUS          current
DESCRIPTION
    "This object reflects the total number of
    frames received by this port which were
    delivered intact by the physical layer but were
    too short to be legal.

    Ignoring the frame check sequence (FCS), a
    frame is considered to be too short if it
    is less than 2 bytes for sdlcLSOperMODULO of
    eight, or if it is less than 3 bytes for
    sdlcLSOperMODULO of onetwentyeight."

 ::= { sdlcPortStatsEntry 3 }
```

```
sdlcPortStatsPollsIn OBJECT-TYPE
SYNTAX          Counter32
MAX-ACCESS      read-only
STATUS          current
DESCRIPTION
    "This object reflects the total number of polls
    received by this port since the port was
    created."

 ::= { sdlcPortStatsEntry 4 }
```

**sdlcPortStatsPollsOut OBJECT-TYPE**

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"This object reflects the total number of polls sent by this port since the port was created."

::= { sdlcPortStatsEntry 5 }

**sdlcPortStatsPollRspIn OBJECT-TYPE**

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"This object reflects the total number of poll responses received by this port since the port was created."

::= { sdlcPortStatsEntry 6 }

**sdlcPortStatsPollRspOut OBJECT-TYPE**

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"This object reflects the total number of poll responses sent by this port since the port was created."

::= { sdlcPortStatsEntry 7 }

**sdlcPortStatsLocalBusies OBJECT-TYPE**

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"This object reflects the total number of times that the local SDLC link stations on this port have entered a busy state (RNR). This object is initialized to zero when the port is created."

::= { sdlcPortStatsEntry 8 }

**sdlcPortStatsRemoteBusies OBJECT-TYPE**

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

**DESCRIPTION**

"This object reflects the total number of times that the adjacent (i.e., remote) SDLC link stations on this port have entered a busy state (RNR). This object is initialized to zero when the port is created."

::= { sdlcPortStatsEntry 9 }

**sdlcPortStatsIFramesIn OBJECT-TYPE**

**SYNTAX** Counter32

**MAX-ACCESS** read-only

**STATUS** current

**DESCRIPTION**

"This object reflects the total number of I-Frames that have been received by SDLC link stations on this port. This object is initialized to zero when the port is created."

::= { sdlcPortStatsEntry 10 }

**sdlcPortStatsIFramesOut OBJECT-TYPE**

**SYNTAX** Counter32

**MAX-ACCESS** read-only

**STATUS** current

**DESCRIPTION**

"This object reflects the total number of I-Frames that have been transmitted by SDLC link stations on this port. This object is initialized to zero when the port is created."

::= { sdlcPortStatsEntry 11 }

**sdlcPortStatsOctetsIn OBJECT-TYPE**

**SYNTAX** Counter32

**MAX-ACCESS** read-only

**STATUS** current

**DESCRIPTION**

"This object reflects the total octets received from adjacent SDLC link stations on this port. This object covers the address, control, and information field of I-Frames only. This object is initialized to zero when the port is created."

::= { sdlcPortStatsEntry 12 }

**sdlcPortStatsOctetsOut OBJECT-TYPE**

**SYNTAX** Counter32

**MAX-ACCESS** read-only

**STATUS** current

**DESCRIPTION**

"This object reflects the total octets transmitted to adjacent SDLC link stations on this port. This object covers the address, control, and information field of I-Frames only. This object is initialized to zero when the port is created."  
 ::= { sdlcPortStatsEntry 13 }

#### sdlcPortStatsProtocolErrs OBJECT-TYPE

SYNTAX Counter32  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION

"This object reflects the total number of times that the SDLC link stations on this port have deactivated the link as a result of having received a protocol violation from the adjacent link station. This object is initialized to zero when the port is created."  
 ::= { sdlcPortStatsEntry 14 }

#### sdlcPortStatsActivityTOs OBJECT-TYPE

SYNTAX Counter32  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION

"This object reflects the total number of times that the SDLC link stations on this port have deactivated the link as a result of no activity on the link. This object is initialized to zero when the port is created."  
 ::= { sdlcPortStatsEntry 15 }

#### sdlcPortStatsRNRLIMITs OBJECT-TYPE

SYNTAX Counter32  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION

"This object reflects the total number of times that the SDLC link stations on this port have deactivated the link as a result of its RNRLIMIT timer expiring. This object is initialized to zero when the port is created."  
 ::= { sdlcPortStatsEntry 16 }

#### sdlcPortStatsRetriesExps OBJECT-TYPE

SYNTAX Counter32  
 MAX-ACCESS read-only



```
STATUS      current
DESCRIPTION
    "This object reflects the total number of
    times that the SDLC link stations on this port
    have deactivated the link as a result of a
    retry sequence being exhausted. This object
    is initialized to zero when the port is
    created."
 ::= { sdlcPortStatsEntry 17 }
```

```
sdlcPortStatsRetransmitsIn OBJECT-TYPE
SYNTAX      Counter32
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "This object reflects the total number of
    I-Frames retransmitted by remote link stations
    for all SDLC link stations on this port. This
    object is initialized to zero when the port is
    created."
 ::= { sdlcPortStatsEntry 18 }
```

```
sdlcPortStatsRetransmitsOut OBJECT-TYPE
SYNTAX      Counter32
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "This object reflects the total number of
    I-Frames retransmitted by all local SDLC link
    stations on this port. This object is
    initialized to zero when the port is created."
 ::= { sdlcPortStatsEntry 19 }
```

```

--
-- THE SDLC LINK STATION GROUP
-- =====
--
-- The following classes of information is modelled for each SDLC link
-- station:
--
-- 1. ADMINISTRATIVE ( read-write)
-- 2. OPERATIONAL    ( read-only)
-- 3. STATISTICS     ( read-only)
--
-- *****
-- *
-- * THE SDLC LINK STATION ADMINISTRATIVE TABLE *
-- *
-- *****

sdlcLSAdminTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF SdlcLSAdminEntry
    MAX-ACCESS  not-accessible
    STATUS      current
    DESCRIPTION
        "This table contains objects that can be
        changed to manage an SDLC link station.
        Changing one of these parameters may take
        effect in the operating link immediately or may
        wait until the link is restarted depending on
        the details of the implementation.

        The entries in sdlcLSAdminTable can be created
        either by an agent or a management station. The
        management station can create an entry in
        sdlcLSAdminTable by setting the appropriate
        value in sdlcLSAdminRowStatus.

        Most of the objects in this read-create table
        have corresponding read-only objects in the
        sdlcLSOperTable that reflect the current
        operating value.

        The operating values may be different from
        these configured values if changed by XID
        negotiation or if a configured parameter was
        changed after the link was started."
    ::= { sdlcLSGroup 1 }

sdlcLSAdminEntry OBJECT-TYPE

```

```

SYNTAX      SdlcLSAdminEntry
MAX-ACCESS  not-accessible
STATUS      current
DESCRIPTION
    "A list of configured values for an SDLC link
    station."
INDEX       { ifIndex, sdlcLSAddress }
 ::= { sdlcLSAdminTable 1 }

```

```

SdlcLSAdminEntry ::= SEQUENCE

```

```

{
    sdlcLSAddress      INTEGER,
    sdlcLSAdminName    DisplayString,
    sdlcLSAdminState   INTEGER,
    sdlcLSAdminISTATUS INTEGER,
    sdlcLSAdminMAXDATASend Integer32,
    sdlcLSAdminMAXDATARcv Integer32,
    sdlcLSAdminREPLYTO TimeInterval,
    sdlcLSAdminMAXIN   INTEGER,
    sdlcLSAdminMAXOUT  INTEGER,
    sdlcLSAdminMODULO  INTEGER,
    sdlcLSAdminRETRIESm INTEGER,
    sdlcLSAdminRETRIESt TimeInterval,
    sdlcLSAdminRETRIESn Integer32,
    sdlcLSAdminRNRLIMIT TimeInterval,
    sdlcLSAdminDATMODE INTEGER,
    sdlcLSAdminGPoll   INTEGER,
    sdlcLSAdminSimRim  INTEGER,
    sdlcLSAdminXmitRcvCap INTEGER,
    sdlcLSAdminRowStatus RowStatus
}

```

```

sdlcLSAddress      OBJECT-TYPE
SYNTAX      INTEGER (1..255)
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION
    "This value is the poll address of the
    secondary link station for this SDLC link.  It
    uniquely identifies the SDLC link station
    within a single SDLC port."
 ::= { sdlcLSAdminEntry 1 }

```

```

sdlcLSAdminName    OBJECT-TYPE
SYNTAX      DisplayString (SIZE (1..10))
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION

```

"An octet string that defines the local name of the SDLC link station. This field may be sent in the XID3 control vector 0x0E, type 0xF7."  
 ::= { sdlcLSAdminEntry 2 }

**sdlcLSAdminState** OBJECT-TYPE  
 SYNTAX INTEGER  
 {  
     inactive(1),  
     active(2)  
 }  
 MAX-ACCESS read-create  
 STATUS current  
 DESCRIPTION  
     "This object controls the desired state of the SDLC station. The managed system shall attempt to keep the operational state, sdlcLSOperState, consistent with this value."  
 DEFVAL { active }  
 ::= { sdlcLSAdminEntry 3 }

**sdlcLSAdminISTATUS** OBJECT-TYPE  
 SYNTAX INTEGER  
 {  
     inactive(1),  
     active(2)  
 }  
 MAX-ACCESS read-create  
 STATUS current  
 DESCRIPTION  
     "This parameter controls the desired state, sdlcLSAdminState, of the SDLC link station at link station start-up."  
 DEFVAL { active }  
 ::= { sdlcLSAdminEntry 4 }

**sdlcLSAdminMAXDATASend** OBJECT-TYPE  
 SYNTAX Integer32  
 MAX-ACCESS read-create  
 STATUS current  
 DESCRIPTION  
     "This object contains the maximum PDU size that the local link station thinks it can send to the adjacent link station before having received any XID from the ALS. After the maximum PDU size that the ALS can receive is known (via XID exchange) that value is reflected in sdlcLSOperMAXDATASend and takes

precedence over this object.

This value includes the Transmission Header (TH) and the Request Header (RH)."

::= { sdlcLSAdminEntry 5 }

sdlcLSAdminMAXDATARcv OBJECT-TYPE

SYNTAX Integer32  
MAX-ACCESS read-create  
STATUS current

DESCRIPTION

"This object contains the maximum PDU size that the local link station can receive from the adjacent link station. This value is sent in the XID to the ALS.

This value includes the Transmission Header (TH) and the Request Header (RH)."

::= { sdlcLSAdminEntry 6 }

sdlcLSAdminREPLYTO OBJECT-TYPE

SYNTAX TimeInterval  
MAX-ACCESS read-create  
STATUS current

DESCRIPTION

"This object controls the reply timeout (in 1/100ths of a second) for an SDLC link station. If the link station does not receive a response to a poll or message before the specified time expires then the appropriate error recovery shall be initiated.

The object descriptor contains the name of an NCP configuration parameter, REPLYTO. Please note that the value of this object represents 1/100ths of a second while the NCP REPLYTO is represented in 1/10ths of a second.

Depending on the implementation, a write operation to this administered value may not change the operational value, sdlcLSOperREPLYTO, until the link station is cycled inactive.

This object only has meaning for SDLC ports where sdlcPortAdminRole == primary "

DEFVAL { 100 }

::= { sdlcLSAdminEntry 7 }

**sdlcLSAdminMAXIN**      **OBJECT-TYPE**  
**SYNTAX**            **INTEGER (1..127)**  
**MAX-ACCESS**    **read-create**  
**STATUS**            **current**  
**DESCRIPTION**  
     "This object controls the maximum number of unacknowledged I-frames which an SDLC link station may receive. This should range from 1 to (sdlcLSAdminMODULO - 1). This value is sent in the XID to the ALS.

    A write operation to this administered value will not change the operational value, sdlcLSOperMAXIN, until the link station is cycled inactive."

**DEFVAL { 7 }**  
**::= { sdlcLSAdminEntry 8 }**

**sdlcLSAdminMAXOUT**      **OBJECT-TYPE**  
**SYNTAX**            **INTEGER (1..127)**  
**MAX-ACCESS**    **read-create**  
**STATUS**            **current**  
**DESCRIPTION**  
     "This object controls the maximum number of consecutive unacknowledged I-frames which an SDLC link station shall send without an acknowledgement. This shall range from 1 to (sdlcLSAdminMODULO - 1).

    For link stations on switched SDLC lines, certain implementations may choose to override this administered value with the value received in the XID exchange.

    Depending on the implementation, a write operation to this administered value may not change the operational value, sdlcLSOperMAXOUT, until the link station is cycled inactive.

    An implementation can support only modulo 8, only modulo 128, or both."

**DEFVAL { 1 }**  
**::= { sdlcLSAdminEntry 9 }**

**sdlcLSAdminMODULO**      **OBJECT-TYPE**  
**SYNTAX**            **INTEGER**  
**{**

```

        eight(8),
        onetwentyeight(128)
    }
    MAX-ACCESS    read-create
    STATUS        current
    DESCRIPTION
        "This object controls the modulus for an SDLC
        link station. This modulus determines the size
        of the rotating acknowledgement window used the
        SDLC link station pair.

        A write operation to this administered value
        will not change the operational value,
        sdlcLSOperMODULO, until the link station is
        cycled inactive.

        An implementation can support only modulo 8,
        only modulo 128, or both."
    DEFVAL { eight }
    ::= { sdlcLSAdminEntry 10 }

```

```

sdlcLSAdminRETRIESm OBJECT-TYPE
    SYNTAX        INTEGER (0..128)
    MAX-ACCESS    read-create
    STATUS        current
    DESCRIPTION
        "This object controls number of retries in a
        retry sequence for the local SDLC link
        station. A retry sequence is a series of
        retransmitted frames ( data or control) for
        which no positive acknowledgement is received.

        The number of times that the retry sequence is
        to be repeated is controlled by the object:
        sdlcLSAdminRETRIESn. The interval between retry
        sequences is controlled by the object:
        sdlcLSAdminRETRIESt.

        A value of zero indicates no retries. If the
        value of sdlcLSAdminRETRIESm is zero, then the
        values of sdlcLSAdminRETRIESt and
        sdlcLSAdminRETRIESn should also be zero.

        Depending on the implementation, a write
        operation to this administered value may not
        change the operational value,
        sdlcLSOperRETRIESm, until the link station is
        cycled inactive."

```

```
DEFVAL { 15 }
 ::= { sdLcLSAdminEntry 11 }
```

```
sdLcLSAdminRETRIESt OBJECT-TYPE
SYNTAX      TimeInterval
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION
    "This object controls the interval (in 1/100ths
    of a second) between retry sequences for the
    local SDLC link station if multiple retry
    sequences are specified . A retry sequence is
    a series of retransmitted frames ( data or
    control) for which no positive acknowledgement
    is received.
```

The number of repeated retries sequences is controlled by the object: sdLcLSAdminRETRIESn. The retries per sequence is controlled by the object: sdLcLSAdminRETRIESm.

The object descriptor contains the name of an NCP configuration parameter, RETRIEST. Please note that the value of this object represents 1/100ths of a second while the NCP RETRIEST is represented in seconds.

Depending on the implementation, a write operation to this administered value may not change the operational value, sdLcLSOperRETRIESt, until the link station is cycled inactive."

```
DEFVAL { 0 }
 ::= { sdLcLSAdminEntry 12 }
```

```
sdLcLSAdminRETRIESn OBJECT-TYPE
SYNTAX      Integer32
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION
    "This object controls the number of times that
    a retry sequence is repeated for the local SDLC
    link station. A retry sequence is a series of
    retransmitted frames ( data or control) for
    which no positive acknowledgement is received.
```

The interval between retry sequences is controlled by the object: sdLcLSAdminRETRIESn.



The retries per sequence is controlled by the object: `sdlcLSAdminRETRIESm`.

Depending on the implementation, a write operation to this administered value may not change the operational value, `sdlcLSOperRETRIESn`, until the link station is cycled inactive."

```
DEFVAL { 0 }
 ::= { sdlcLSAdminEntry 13 }
```

`sdlcLSAdminRNRLIMIT` OBJECT-TYPE

```
SYNTAX      TimeInterval
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION
```

"This object controls the length of time (in 1/100ths of a second) that an SDLC link station will allow its adjacent link station to remain in a busy (RNR) state before declaring it inoperative.

A value of `sdlcLSAdminRNRLIMIT == 0` means there is no limit.

The object descriptor contains the name of an NCP configuration parameter, `RNRLIMIT`. Please note that the value of this object represents 1/100ths of a second while the NCP `RNRLIMIT` is represented in minutes.

Depending on the implementation, a write operation to this administered value may not change the operational value, `sdlcLSOperRNRLIMIT`, until the link station is cycled inactive."

```
DEFVAL { 18000 }
 ::= { sdlcLSAdminEntry 14 }
```

`sdlcLSAdminDATMODE` OBJECT-TYPE

```
SYNTAX      INTEGER
{
    half(1),
    full(2)
}
MAX-ACCESS  read-create
STATUS      current
DESCRIPTION
```

"This object controls whether communications mode with the adjacent link station is two-way-alternate (half) or two-way-simultaneous (full).

A write operation to this administered value will not change the operational value, sdlcLSOperDATMODE, until the link station is cycled inactive."

DEFVAL { half }  
 ::= { sdlcLSAdminEntry 15 }

sdlcLSAdminGPoll

OBJECT-TYPE

SYNTAX INTEGER (0..254)

MAX-ACCESS read-create

STATUS current

DESCRIPTION

"This object describes the group poll address for this link station instance. If group poll is not in effect for this link station instance, the value for sdlcLSAdminGPoll should be zero.

Depending on the implementation, a write operation to this administered value may not change the operational value, sdlcLSOperGPoll, until the link station is cycled inactive."

::= { sdlcLSAdminEntry 16 }

sdlcLSAdminSimRim

OBJECT-TYPE

SYNTAX INTEGER

{  
     no(1),  
     yes(2)  
 }

MAX-ACCESS read-create

STATUS current

DESCRIPTION

"This object controls the support for transmission and receipt of SIM and RIM control frames for this link station. The value of this object controls the setting of the transmit-receive capability sent in the XID field."

DEFVAL { no }

::= { sdlcLSAdminEntry 17 }

sdlcLSAdminXmitRcvCap OBJECT-TYPE

```

SYNTAX          INTEGER
{
    twa(1),
    tws(2)
}
MAX-ACCESS      read-create
STATUS          current
DESCRIPTION
    "This object controls the transmit-receive
    capabilities for this SDLC link station.  The
    value of this object establishes the value of
    the transmit-receive capability indicator sent
    in the XID image to the adjacent link station."
DEFVAL { twa }
::= { sdclLSAdminEntry 18 }

```

```

sdclLSAdminRowStatus OBJECT-TYPE
SYNTAX          RowStatus
MAX-ACCESS      read-create
STATUS          current
DESCRIPTION
    "This object is used by a management station to
    create or delete the row entry in
    sdclLSAdminTable following the RowStatus
    textual convention.

    Upon successful creation of the row, an agent
    automatically creates a corresponding entry in
    the sdclLSOperTable with sdclLSOperState equal
    to 'discontacted (1)'."
::= { sdclLSAdminEntry 19 }

```

```

-- *****
-- *
-- *          THE SDLC LINK STATION OPERATIONAL TABLE
-- *
-- *****

```

```

sdclLSOperTable OBJECT-TYPE
SYNTAX          SEQUENCE OF SdclLSOperEntry
MAX-ACCESS      not-accessible
STATUS          current
DESCRIPTION
    "This table contains current SDLC link
    parameters.  Many of these objects have
    corresponding objects in the
    sdclLSAdminTable."
::= { sdclLSGroup 2 }

```

```

sdlcLS0perEntry      OBJECT-TYPE
    SYNTAX             SdlcLS0perEntry
    MAX-ACCESS          not-accessible
    STATUS              current
    DESCRIPTION
        "A list of status and control values for an
        SDLC link station."
    INDEX               { ifIndex, sdlcLSAddress }
    ::= { sdlcLS0perTable 1 }

SdlcLS0perEntry      ::= SEQUENCE
{
    sdlcLS0perName          DisplayString,
    sdlcLS0perRole          INTEGER,
    sdlcLS0perState         INTEGER,
    sdlcLS0perMAXDATASend   Integer32,
    sdlcLS0perREPLYT0       TimeInterval,
    sdlcLS0perMAXIN         INTEGER,
    sdlcLS0perMAXOUT        INTEGER,
    sdlcLS0perMODULO        INTEGER,
    sdlcLS0perRETRIESm      INTEGER,
    sdlcLS0perRETRIESt      TimeInterval,
    sdlcLS0perRETRIESn      INTEGER,
    sdlcLS0perRNRLIMIT      TimeInterval,
    sdlcLS0perDATMODE       INTEGER,
    sdlcLS0perLastModifyTime TimeTicks,
    sdlcLS0perLastFailTime  TimeTicks,
    sdlcLS0perLastFailCause INTEGER,
    sdlcLS0perLastFailCtrlIn OCTET STRING,
    sdlcLS0perLastFailCtrlOut OCTET STRING,
    sdlcLS0perLastFailFRMRInfo OCTET STRING,
    sdlcLS0perLastFailREPLYT0s Counter32,
    sdlcLS0perEcho          INTEGER,
    sdlcLS0perGPoll          INTEGER,
    sdlcLS0perSimRim         INTEGER,
    sdlcLS0perXmitRcvCap     INTEGER
}

sdlcLS0perName      OBJECT-TYPE
    SYNTAX             DisplayString (SIZE (1..10))
    MAX-ACCESS          read-only
    STATUS              current
    DESCRIPTION
        "An octet string that defines the name of the
        remote SDLC link station. This field is
        received in the XID3 control vector 0x0E, type
        0xF7."
    ::= { sdlcLS0perEntry 1 }

```

```

sdLcLSOperRole      OBJECT-TYPE
SYNTAX              INTEGER
{
    primary(1),
    secondary(2),
    undefined(3)
}
MAX-ACCESS          read-only
STATUS               current
DESCRIPTION
    "This object reflects the current role that the
    link station is assuming.

    The value of sdLcLSOperRole is undefined(3)
    whenever the link station role has not yet been
    established by the mode setting command."
 ::= { sdLcLSOperEntry 2 }

sdLcLSOperState      OBJECT-TYPE
SYNTAX              INTEGER
{
    discontacted(1),
    contactPending(2),
    contacted(3),
    discontactPending(4)
}
MAX-ACCESS          read-only
STATUS               current
DESCRIPTION
    "This object describes the operational state of
    the SDLC link station. The managed system
    shall attempt to keep this value consistent
    with the administered state, sdLcLSAdminState"
 ::= { sdLcLSOperEntry 3 }

sdLcLSOperMAXDATASend OBJECT-TYPE
SYNTAX              Integer32
MAX-ACCESS          read-only
STATUS               current
DESCRIPTION
    "This object contains the actual maximum PDU
    size that the local link station can send to
    the adjacent link station. This object is
    established from the value received in the XID
    from the adjacent link station. If no XID
    is received, then this value is implementation
    dependent (for instance, it could be the value
    of sdLcLSAdminMAXDATASend)."

```

This value includes the Transmission Header (TH) and the Request Header (RH)."  
 ::= { sdLcLSOperEntry 4 }

**sdLcLSOperREPLYTO** OBJECT-TYPE  
 SYNTAX TimeInterval  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
 "This object reflects the current reply timeout (in 1/100ths of a second) for an SDLC link station. If the link station does not receive a response to a poll or message before the specified time expires then the appropriate error recovery shall be initiated.  
  
 The object descriptor contains the name of an NCP configuration parameter, REPLYTO. Please note that the value of this object represents 1/100ths of a second while the NCP REPLYTO is represented in 1/10ths of a second.  
  
 This object only has meaning for SDLC ports where sdLcPortOperRole == primary "  
 ::= { sdLcLSOperEntry 5 }

**sdLcLSOperMAXIN** OBJECT-TYPE  
 SYNTAX INTEGER (1..127)  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
 "This object reflects the current maximum number of unacknowledged I-frames which an SDLC link station may receive. This shall range from 1 to (sdLcLSOperMODULO - 1)."  
 ::= { sdLcLSOperEntry 6 }

**sdLcLSOperMAXOUT** OBJECT-TYPE  
 SYNTAX INTEGER (1..127)  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
 "This object controls the maximum number of consecutive unacknowledged I-frames which an SDLC link station shall send without an acknowledgement. This shall range from 1 to (sdLcLSAdminMODULO - 1)."

This value may controlled by the administered MAXOUT, sdlcLSAdminMAXOUT, or by the MAXIN value received during the XID exchange."  
 ::= { sdlcLS0perEntry 7 }

**sdlcLS0perMODULO** OBJECT-TYPE  
 SYNTAX INTEGER  
 {  
     eight(8),  
     onetwentyeight(128)  
 }  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
     "This object reflects the current modulus for an SDLC link station. This modulus determines the size of rotating acknowledgement window used by the SDLC link station pair."  
 DEFVAL { eight }  
 ::= { sdlcLS0perEntry 8 }

**sdlcLS0perRETRIESm** OBJECT-TYPE  
 SYNTAX INTEGER (0..128)  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
     "This object controls number of retries in a retry sequence for an SDLC link station. A retry sequence is a series of retransmitted frames ( data or control) for which no positive acknowledgement is received.  
  
     The current number of times that the retry sequence is to be repeated is reflected by the object: sdlcLS0perRETRIESn. The current interval between retry sequences is reflected by the object: sdlcLS0perRETRIESt."  
 ::= { sdlcLS0perEntry 9 }

**sdlcLS0perRETRIESt** OBJECT-TYPE  
 SYNTAX TimeInterval  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
     "This object reflects the current interval (in 1/100ths of a second) between retry sequences for an SDLC link station if multiple retry sequences are specified. A retry sequence is a

series of retransmitted frames ( data or control) for which no positive acknowledgement is received.

The object descriptor contains the name of an NCP configuration parameter, RETRIEST. Please note that the value of this object represents 1/100ths of a second while the NCP RETRIEST is represented in seconds.

The current number of repeated retries sequences is reflected by the object: sdLcLS0perRETRIESn. The current retries per sequence is reflected by the object: sdLcLS0perRETRIESm."

::= { sdLcLS0perEntry 10 }

sdLcLS0perRETRIESn OBJECT-TYPE

SYNTAX INTEGER (0..127)

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"This object reflects the current number of times that a retry sequence is repeated for an SDLC link station. A retry sequence is a series of retransmitted frames ( data or control) for which no positive acknowledgement is received.

The current interval between retry sequences is reflected by the object: sdLcLS0perRETRIESn. The current retries per sequence is reflected by the object: sdLcLS0perRETRIESm."

::= { sdLcLS0perEntry 11 }

sdLcLS0perRNRLIMIT OBJECT-TYPE

SYNTAX TimeInterval

MAX-ACCESS read-only

STATUS current

DESCRIPTION

"This object reflects the current length of time (in 1/100ths of a second) that an SDLC link station will allow its adjacent link station to remain in a busy (RNR) state before declaring it inoperative.

The object descriptor contains the name of an NCP configuration parameter, RNRLIMIT. Please



note that the value of this object represents 1/100ths of a second while the NCP RNRLIMIT is represented in minutes.

A value of sdlcLSOperRNRLIMIT == 0 means there is no limit."

::= { sdlcLSOperEntry 12 }

**sdlcLSOperDATMODE**      OBJECT-TYPE  
 SYNTAX                  INTEGER  
 {  
     half(1),  
     full(2)  
 }  
 MAX-ACCESS      read-only  
 STATUS            current  
 DESCRIPTION  
     "This object reflects whether the current communications mode with the adjacent link station is two-way-alternate (half) or two-way-simultaneous (full)."  
 ::= { sdlcLSOperEntry 13 }

**sdlcLSOperLastModifyTime**      OBJECT-TYPE  
 SYNTAX                  TimeTicks  
 MAX-ACCESS      read-only  
 STATUS            current  
 DESCRIPTION  
     "This object describes the value of sysUpTime when this link station definition was last modified. If the link station has not been modified, then this value shall be zero."  
 ::= { sdlcLSOperEntry 14 }

**sdlcLSOperLastFailTime**      OBJECT-TYPE  
 SYNTAX                  TimeTicks  
 MAX-ACCESS      read-only  
 STATUS            current  
 DESCRIPTION  
     "This object describes the value of sysUpTime when this SDLC link station last failed. If the link station has not failed, then this value shall be zero."  
 ::= { sdlcLSOperEntry 15 }

**sdlcLSOperLastFailCause**      OBJECT-TYPE  
 SYNTAX                  INTEGER  
 {

```

        undefined(1),
        rxFRMR(2),
        txFRMR(3),
        noResponse(4),
        protocolErr(5),
        noActivity(6),
        rnrLimit(7),
        retriesExpired(8)
    }
    MAX-ACCESS    read-only
    STATUS        current
    DESCRIPTION
        "This enumerated object reflects the cause of
        the last failure of this SDLC link station.  If
        the link station has not failed, then this
        object will have a value of undefined(1)."
    DEFVAL { undefined }
    ::= { sdlcLSOperEntry 16 }

```

```

sdlcLSOperLastFailCtrlIn  OBJECT-TYPE
    SYNTAX          OCTET STRING (SIZE(1..2))
    MAX-ACCESS      read-only
    STATUS          current
    DESCRIPTION
        "This object reflects the last control octet or
        octets (depending on modulus) received by this
        SDLC link station at the time of the last
        failure.  If the link station has not failed,
        then this value has no meaning."
    ::= { sdlcLSOperEntry 17 }

```

```

sdlcLSOperLastFailCtrlOut OBJECT-TYPE
    SYNTAX          OCTET STRING (SIZE(1..2))
    MAX-ACCESS      read-only
    STATUS          current
    DESCRIPTION
        "This object reflects the last control octet or
        octets (depending on modulus) sent by this SDLC
        link station at the time of the last failure.
        If the link station has not failed, then this
        value has no meaning."
    ::= { sdlcLSOperEntry 18 }

```

```

sdlcLSOperLastFailFRMRInfo OBJECT-TYPE
    SYNTAX          OCTET STRING (SIZE(3))
    MAX-ACCESS      read-only
    STATUS          current
    DESCRIPTION

```

"This object reflects the information field of the FRMR frame if the last failure for this SDLC link station was as a result of an invalid frame. Otherwise, this field has no meaning."  
 ::= { sdLcLS0perEntry 19 }

**sdLcLS0perLastFailREPLYT0s** OBJECT-TYPE  
 SYNTAX Counter32  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
 "This object reflects the number of times that the REPLYT0 timer had expired for an SDLC link station at the time of the last failure. If the link station has not failed, then this value has no meaning."  
 ::= { sdLcLS0perEntry 20 }

**sdLcLS0perEcho** OBJECT-TYPE  
 SYNTAX INTEGER  
 {  
     no(1),  
     yes(2)  
 }  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
 "This object identifies whether the echo bit is in effect for this particular link station."  
 DEFVAL { no }  
 ::= { sdLcLS0perEntry 21 }

**sdLcLS0perGPoll** OBJECT-TYPE  
 SYNTAX INTEGER (0..254)  
 MAX-ACCESS read-only  
 STATUS current  
 DESCRIPTION  
 "This object describes the group poll address in effect for this link station instance."  
 DEFVAL { 0 }  
 ::= { sdLcLS0perEntry 22 }

**sdLcLS0perSimRim** OBJECT-TYPE  
 SYNTAX INTEGER  
 {  
     no(1),  
     yes(2)  
 }

```

MAX-ACCESS    read-only
STATUS        current
DESCRIPTION
    "This object reflects the support for
    transmission and receipt of SIM and RIM control
    frames for the adjacent link station.  The
    value of this object is set from the XID field
    received from the adjacent link station."
DEFVAL { no }
 ::= { sdlcLS0perEntry 23 }

```

```

sdlcLS0perXmitRcvCap OBJECT-TYPE
    SYNTAX      INTEGER
    {
        twa(1),
        tws(2)
    }
    MAX-ACCESS    read-only
    STATUS        current
    DESCRIPTION
        "This object reflects the transmit-receive
        capabilities for the adjacent SDLC link
        station.  The value of this object is the value
        of the transmit-receive capability indicator
        received in the XID image from the adjacent
        link station."
    DEFVAL { twa }
    ::= { sdlcLS0perEntry 24 }

```

```

-- *****
-- *
-- *          THE SDLC LINK STATION STATISTICS TABLE
-- *
-- *****

```

```

sdlcLSStatsTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF SdlcLSStatsEntry
    MAX-ACCESS    not-accessible
    STATUS        current
    DESCRIPTION
        "Each entry in this table contains statistics
        for a specific SDLC link station."
    ::= { sdlcLSGroup 3 }

```

```

sdlcLSStatsEntry OBJECT-TYPE
    SYNTAX      SdlcLSStatsEntry
    MAX-ACCESS    not-accessible

```

```

STATUS      current
DESCRIPTION
    "A list of statistics for an SDLC link station."
INDEX       { ifIndex, sdlcLSAddress }
 ::= { sdlcLSStatsTable 1 }

```

SdlcLSStatsEntry ::= SEQUENCE

```

{
    sdlcLSStatsBLUsIn           Counter32,
    sdlcLSStatsBLUsOut          Counter32,
    sdlcLSStatsOctetsIn          Counter32,
    sdlcLSStatsOctetsOut         Counter32,
    sdlcLSStatsPollsIn           Counter32,
    sdlcLSStatsPollsOut          Counter32,
    sdlcLSStatsPollRspIn          Counter32,
    sdlcLSStatsPollRspOut         Counter32,
    sdlcLSStatsLocalBusies        Counter32,
    sdlcLSStatsRemoteBusies       Counter32,
    sdlcLSStatsIFramesIn          Counter32,
    sdlcLSStatsIFramesOut         Counter32,
    sdlcLSStatsUIFramesIn          Counter32,
    sdlcLSStatsUIFramesOut         Counter32,
    sdlcLSStatsXIDsIn             Counter32,
    sdlcLSStatsXIDsOut            Counter32,
    sdlcLSStatsTESTsIn            Counter32,
    sdlcLSStatsTESTsOut           Counter32,
    sdlcLSStatsREJIn              Counter32,
    sdlcLSStatsREJOut             Counter32,
    sdlcLSStatsFRMRsIn            Counter32,
    sdlcLSStatsFRMRsOut           Counter32,
    sdlcLSStatsSIMsIn             Counter32,
    sdlcLSStatsSIMsOut            Counter32,
    sdlcLSStatsRIMsIn             Counter32,
    sdlcLSStatsRIMsOut            Counter32,
    sdlcLSStatsDISCIn             Counter32,
    sdlcLSStatsDISCOut            Counter32,
    sdlcLSStatsUAIIn              Counter32,
    sdlcLSStatsUAOut              Counter32,
    sdlcLSStatsDMIn               Counter32,
    sdlcLSStatsDMOut              Counter32,
    sdlcLSStatsSNRMIn             Counter32,
    sdlcLSStatsSNRMOut            Counter32,
    sdlcLSStatsProtocolErrs        Counter32,
    sdlcLSStatsActivityTos         Counter32,
    sdlcLSStatsRNRLIMITs          Counter32,
    sdlcLSStatsRetriesExps         Counter32,
    sdlcLSStatsRetransmitsIn       Counter32,
    sdlcLSStatsRetransmitsOut      Counter32
}

```

}

**sdLcLSStatsBLUsIn**      **OBJECT-TYPE**  
SYNTAX           Counter32  
MAX-ACCESS      read-only  
STATUS           current  
DESCRIPTION  
    "This object reflects the total basic link  
    units (BLUs; frames) received from an adjacent  
    SDLC link station since link station startup.  
    At link station startup time, this object must  
    be initialized to zero."  
 ::= { sdLcLSStatsEntry 1 }

**sdLcLSStatsBLUsOut**      **OBJECT-TYPE**  
SYNTAX           Counter32  
MAX-ACCESS      read-only  
STATUS           current  
DESCRIPTION  
    "This object reflects the total basic link  
    units (BLUs; frames), transmitted to an  
    adjacent SDLC link station since link station  
    startup. At link station startup time, this  
    object must be initialized to zero."  
 ::= { sdLcLSStatsEntry 2 }

**sdLcLSStatsOctetsIn** **OBJECT-TYPE**  
SYNTAX           Counter32  
MAX-ACCESS      read-only  
STATUS           current  
DESCRIPTION  
    "This object reflects the total octets received  
    from an adjacent SDLC link station since link  
    station startup. This object covers the  
    address, control, and information field of  
    I-Frames only. At link station startup time,  
    this object must be initialized to zero."  
 ::= { sdLcLSStatsEntry 3 }

**sdLcLSStatsOctetsOut** **OBJECT-TYPE**  
SYNTAX           Counter32  
MAX-ACCESS      read-only  
STATUS           current  
DESCRIPTION  
    "This object reflects the total octets  
    transmitted to an adjacent SDLC link station  
    since link station startup. This object covers  
    the address, control, and information field of

I-Frames only. At link station startup time, this object must be initialized to zero."  
 ::= { sdlcLSStatsEntry 4 }

**sdlcLSStatsPollsIn** OBJECT-TYPE  
SYNTAX Counter32  
MAX-ACCESS read-only  
STATUS current  
DESCRIPTION  
"This object reflects the total polls received from an adjacent SDLC link station since link station startup. At link station startup time, this object must be initialized to zero."  
 ::= { sdlcLSStatsEntry 5 }

**sdlcLSStatsPollsOut** OBJECT-TYPE  
SYNTAX Counter32  
MAX-ACCESS read-only  
STATUS current  
DESCRIPTION  
"This object reflects the total polls sent to an adjacent SDLC link station since link station startup. At link station startup time, this object must be initialized to zero."  
 ::= { sdlcLSStatsEntry 6 }

**sdlcLSStatsPollRspsOut** OBJECT-TYPE  
SYNTAX Counter32  
MAX-ACCESS read-only  
STATUS current  
DESCRIPTION  
"This object reflects the total number of poll responses sent to the adjacent SDLC link station since link station startup. This value includes I-frames that are sent in response to a poll.  
  
At link station startup time, this object must be initialized to zero."  
 ::= { sdlcLSStatsEntry 7 }

**sdlcLSStatsPollRspsIn** OBJECT-TYPE  
SYNTAX Counter32  
MAX-ACCESS read-only  
STATUS current  
DESCRIPTION  
"This object reflects the total number of poll responses received from the adjacent SDLC link

station since station startup. This value includes I-frames that are received in response to a poll.

At link station startup time, this object must be initialized to zero."

::= { sdlcLSStatsEntry 8 }

**sdlcLSStatsLocalBusies OBJECT-TYPE**

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

**DESCRIPTION**

"This object reflects the total number of times that the local SDLC link station has entered a busy state (RNR) since link station startup.

At link station startup time, this object must be initialized to zero."

::= { sdlcLSStatsEntry 9 }

**sdlcLSStatsRemoteBusies OBJECT-TYPE**

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

**DESCRIPTION**

"This object reflects the total number of times that an adjacent ( remote) SDLC link station has entered a busy state (RNR) since link station startup. At link station startup time, this object must be initialized to zero."

::= { sdlcLSStatsEntry 10 }

**sdlcLSStatsIFramesIn OBJECT-TYPE**

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

**DESCRIPTION**

"This object reflects the total I-frames received from an adjacent SDLC link station since link station startup. At link station startup time, this object must be initialized to zero."

::= { sdlcLSStatsEntry 11 }

**sdlcLSStatsIFramesOut OBJECT-TYPE**

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current



**DESCRIPTION**

"This object reflects the total I-frames transmitted to an adjacent SDLC link station since link station startup. At link station startup time, this object must be initialized to zero."

::= { sdlcLSStatsEntry 12 }

**sdlcLSStatsUIFramesIn OBJECT-TYPE**

**SYNTAX** Counter32

**MAX-ACCESS** read-only

**STATUS** current

**DESCRIPTION**

"This object reflects the total UI-frames received from an adjacent SDLC link station since link station startup."

::= { sdlcLSStatsEntry 13 }

**sdlcLSStatsUIFramesOut OBJECT-TYPE**

**SYNTAX** Counter32

**MAX-ACCESS** read-only

**STATUS** current

**DESCRIPTION**

"This object reflects the total UI-frames transmitted to an adjacent SDLC link station since link station startup."

::= { sdlcLSStatsEntry 14 }

**sdlcLSStatsXIDsIn****OBJECT-TYPE**

**SYNTAX** Counter32

**MAX-ACCESS** read-only

**STATUS** current

**DESCRIPTION**

"This object reflects the total XID frames received from an adjacent SDLC link station since link station startup."

::= { sdlcLSStatsEntry 15 }

**sdlcLSStatsXIDsOut****OBJECT-TYPE**

**SYNTAX** Counter32

**MAX-ACCESS** read-only

**STATUS** current

**DESCRIPTION**

"This object reflects the total XID frames transmitted to an adjacent SDLC link station since link station startup."

::= { sdlcLSStatsEntry 16 }

**sdLcLSStatsTESTsIn**    OBJECT-TYPE  
SYNTAX           Counter32  
MAX-ACCESS    read-only  
STATUS        current  
DESCRIPTION  
    "This object reflects the total TEST frames,  
    commands or responses, received from an  
    adjacent SDLC link station since link station  
    startup."  
 ::= { sdLcLSStatsEntry 17 }

**sdLcLSStatsTESTsOut**   OBJECT-TYPE  
SYNTAX           Counter32  
MAX-ACCESS    read-only  
STATUS        current  
DESCRIPTION  
    "This object reflects the total TEST frames,  
    commands or responses, transmitted to an  
    adjacent SDLC link station since link station  
    startup."  
 ::= { sdLcLSStatsEntry 18 }

**sdLcLSStatsREJsIn**     OBJECT-TYPE  
SYNTAX           Counter32  
MAX-ACCESS    read-only  
STATUS        current  
DESCRIPTION  
    "This object reflects the total REJ frames  
    received from an adjacent SDLC link station  
    since link station startup."  
 ::= { sdLcLSStatsEntry 19 }

**sdLcLSStatsREJsOut**    OBJECT-TYPE  
SYNTAX           Counter32  
MAX-ACCESS    read-only  
STATUS        current  
DESCRIPTION  
    "This object reflects the total REJ frames  
    transmitted to an adjacent SDLC link station  
    since link station startup."  
 ::= { sdLcLSStatsEntry 20 }

**sdLcLSStatsFRMRsIn**    OBJECT-TYPE  
SYNTAX           Counter32  
MAX-ACCESS    read-only  
STATUS        current  
DESCRIPTION  
    "This object reflects the total frame reject

(FRMR) frames received from an adjacent SDLC link station since link station startup."  
 ::= { sdLcLSStatsEntry 21 }

**sdLcLSStatsFRMRsOut**    OBJECT-TYPE  
    SYNTAX           Counter32  
    MAX-ACCESS    read-only  
    STATUS           current  
    DESCRIPTION  
       "This object reflects the total frame reject (FRMR) frames transmitted to an adjacent SDLC link station since link station startup."  
    ::= { sdLcLSStatsEntry 22 }

**sdLcLSStatsSIMsIn**    OBJECT-TYPE  
    SYNTAX           Counter32  
    MAX-ACCESS    read-only  
    STATUS           current  
    DESCRIPTION  
       "This object reflects the total set initialization mode (SIM) frames received from an adjacent SDLC link station since link station startup."  
    ::= { sdLcLSStatsEntry 23 }

**sdLcLSStatsSIMsOut**    OBJECT-TYPE  
    SYNTAX           Counter32  
    MAX-ACCESS    read-only  
    STATUS           current  
    DESCRIPTION  
       "This object reflects the total set initialization mode (SIM) frames transmitted to an adjacent SDLC link station since link station startup. At link station startup time, this object must be initialized to zero."  
    ::= { sdLcLSStatsEntry 24 }

**sdLcLSStatsRIMsIn**    OBJECT-TYPE  
    SYNTAX           Counter32  
    MAX-ACCESS    read-only  
    STATUS           current  
    DESCRIPTION  
       "This object reflects the total request initialization mode (RIM) frames received from an adjacent SDLC link station since link station startup. At link station startup time, this object must be initialized to zero."  
    ::= { sdLcLSStatsEntry 25 }

**sdLcLSStatsRIMsOut**    **OBJECT-TYPE**  
SYNTAX            Counter32  
MAX-ACCESS    read-only  
STATUS            current  
DESCRIPTION  
    "This object reflects the total request  
    initialization mode (RIM) frames transmitted to  
    an adjacent SDLC link station since link station  
    startup. At link station startup time, this  
    object must be initialized to zero."  
 ::= { sdLcLSStatsEntry 26 }

**sdLcLSStatsDISCIn**    **OBJECT-TYPE**  
SYNTAX            Counter32  
MAX-ACCESS    read-only  
STATUS            current  
DESCRIPTION  
    "This object reflects the total number of  
    disconnect (DISC) requests received from an  
    adjacent SDLC link station since link station  
    startup. At link station startup time, this  
    object must be initialized to zero."  
 ::= { sdLcLSStatsEntry 27 }

**sdLcLSStatsDISCOut**   **OBJECT-TYPE**  
SYNTAX            Counter32  
MAX-ACCESS    read-only  
STATUS            current  
DESCRIPTION  
    "This object reflects the total number of  
    disconnect (DISC) requests transmitted to an  
    adjacent SDLC link station since link station  
    startup. At link station startup time, this  
    object must be initialized to zero."  
 ::= { sdLcLSStatsEntry 28 }

**sdLcLSStatsUAIIn**    **OBJECT-TYPE**  
SYNTAX            Counter32  
MAX-ACCESS    read-only  
STATUS            current  
DESCRIPTION  
    "This object reflects the total number of  
    unnumbered acknowledgements (UA) requests  
    received from an adjacent SDLC link station  
    since link station startup. At link station  
    startup time, this object must be initialized  
    to zero."  
 ::= { sdLcLSStatsEntry 29 }

**sdLcLSStatsUAOut**      OBJECT-TYPE  
SYNTAX           Counter32  
MAX-ACCESS    read-only  
STATUS        current  
DESCRIPTION  
    "This object reflects the total number of unnumbered acknowledgements (UA) requests transmitted to an adjacent SDLC link station since link station startup. At link station startup time, this object must be initialized to zero."  
 ::= { sdLcLSStatsEntry 30 }

**sdLcLSStatsDMIn**      OBJECT-TYPE  
SYNTAX           Counter32  
MAX-ACCESS    read-only  
STATUS        current  
DESCRIPTION  
    "This object reflects the total number of disconnect mode (DM) requests received from an adjacent SDLC link station since link station startup. At link station startup time, this object must be initialized to zero."  
 ::= { sdLcLSStatsEntry 31 }

**sdLcLSStatsDMOut**    OBJECT-TYPE  
SYNTAX           Counter32  
MAX-ACCESS    read-only  
STATUS        current  
DESCRIPTION  
    "This object reflects the total number of disconnect mode (DM) requests transmitted to an adjacent SDLC link station since link station startup. At link station startup time, this object must be initialized to zero."  
 ::= { sdLcLSStatsEntry 32 }

**sdLcLSStatsSNRMIn**   OBJECT-TYPE  
SYNTAX           Counter32  
MAX-ACCESS    read-only  
STATUS        current  
DESCRIPTION  
    "This object reflects the total number of set normal response mode (SNRM/SNRME) requests received from an adjacent SDLC link station since link station startup. At link station startup time, this object must be initialized to zero."

```
 ::= { sdLcLSStatsEntry 33 }
```

```
sdLcLSStatsSNRMOut OBJECT-TYPE
SYNTAX      Counter32
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "This object reflects the total number of
    set normal response mode (SNRM/SNRME) requests
    transmitted to an adjacent SDLC link station
    since link station startup. At link station
    startup time, this object must be initialized
    to zero."
 ::= { sdLcLSStatsEntry 34 }
```

```
sdLcLSStatsProtocolErrs OBJECT-TYPE
SYNTAX      Counter32
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "This object reflects the total occurrences,
    since link station startup, where this SDLC
    link station has inactivated the link as a
    result of receiving a frame from its adjacent
    link station which was in violation of the
    protocol. At link station startup time, this
    object must be initialized to zero."
 ::= { sdLcLSStatsEntry 35 }
```

```
sdLcLSStatsActivityT0s OBJECT-TYPE
SYNTAX      Counter32
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "This object reflects the total occurrences,
    since startup, where this SDLC link station has
    inactivated the link as a result of no activity
    on the link. At link station startup time,
    this object must be initialized to zero."
 ::= { sdLcLSStatsEntry 36 }
```

```
sdLcLSStatsRNRLIMITs OBJECT-TYPE
SYNTAX      Counter32
MAX-ACCESS  read-only
STATUS      current
DESCRIPTION
    "This object reflects the total occurrences,
    since startup, where this SDLC link station has
```

inactivated the link as a result of its  
RNRLIMIT timer expiring. At link station  
startup time, this object must be initialized  
to zero."

::= { sdlcLSStatsEntry 37 }

#### sdlcLSStatsRetriesExps OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

##### DESCRIPTION

"This object reflects the total occurrences,  
since startup, where this SDLC link station has  
inactivated the link as a result of a retry  
sequence being exhausted. At link station  
startup time, this object must be initialized  
to zero."

::= { sdlcLSStatsEntry 38 }

#### sdlcLSStatsRetransmitsIn OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

##### DESCRIPTION

"This object reflects the total number of  
information frames retransmitted by the remote  
link station because the N(s) received from  
that link station indicated that one or more  
information frames sent by that station were  
lost. This event causes the first missing  
information frame of a window and all  
subsequent information frames to be  
retransmitted. At link station startup time,  
this object must be initialized to zero.

Management: If the value of  
sdlcLSStatsRetransmitsIn grows over time, then  
the quality of the serial line is in  
question. You might want to look at  
decreasing the value for  
sdlcLSAdminMAXDATASend to compensate for the  
lower quality line."

::= { sdlcLSStatsEntry 39 }

#### sdlcLSStatsRetransmitsOut OBJECT-TYPE

SYNTAX Counter32

MAX-ACCESS read-only

STATUS current

## DESCRIPTION

"This object reflects the total number of information frames retransmitted to a remote link station because the N(r) received from that link station indicated that one or more information frames sent to that station were lost. This event causes the first missing information frame of a window and all subsequent information frames to be retransmitted. At link station startup time, this object must be initialized to zero.

Management: If the value of `sdclSStatsRetransmitsOut` grows over time, then the quality of the serial line is in question. You might want to look at decreasing the value for `sdclSAdminMAXDATASend` to compensate for the lower quality line."

::= { `sdclSStatsEntry` 40 }

--  
-- TRAP DEFINITIONS  
--

--  
-- Notifications  
--

`sdclTraps` OBJECT IDENTIFIER ::= { `sdcl` 3 }

`sdclPortStatusChange` NOTIFICATION-TYPE  
 OBJECTS { `ifIndex`,  
           `ifAdminStatus`,  
           `ifOperStatus`,  
           `sdclPortOperLastFailTime`,  
           `sdclPortOperLastFailCause`  
           }  
 STATUS current  
 DESCRIPTION  
   "This trap indicates that the state of an SDLC  
   port has transitioned to active or inactive."  
 ::= { `sdclTraps` 1 }

`sdclLSStatusChange` NOTIFICATION-TYPE  
 OBJECTS { `ifIndex`,  
           `sdclLSAddress`,  
           `sdclLSOperState`,  
           `sdclLSAdminState`,



```

        sdlcLSOperLastFailTime,
        sdlcLSOperLastFailCause,
        sdlcLSOperLastFailFRMRInfo,
        sdlcLSOperLastFailCtrlIn,
        sdlcLSOperLastFailCtrlOut,
        sdlcLSOperLastFailREPLYTOs
    }
    STATUS current
    DESCRIPTION
        "This trap indicates that the state of an SDLC
        link station has transitioned to contacted or
        discontacted."
    ::= { sdlcTraps 2 }

```

```

--
-- Conformance Information
--

```

```

sdlcConformance OBJECT IDENTIFIER ::= { sdlc 4 }

```

```

sdlcCompliances OBJECT IDENTIFIER ::= { sdlcConformance 1 }
sdlcGroups      OBJECT IDENTIFIER ::= { sdlcConformance 2 }

```

```

--
-- Compliance Statements
--

```

```

sdlcCoreCompliance MODULE-COMPLIANCE
    STATUS current
    DESCRIPTION
        "The core compliance statement for all SDLC
        nodes."
    MODULE
        MANDATORY-GROUPS
        {
            sdlcCorePortAdminGroup,
            sdlcCorePortOperGroup,
            sdlcCorePortStatsGroup,
            sdlcCoreLSAdminGroup,
            sdlcCoreLSOperGroup,
            sdlcCoreLSStatsGroup
        }

    OBJECT      sdlcPortAdminName
    MIN-ACCESS  read-only
    DESCRIPTION
        "Write access is not required."

```

OBJECT           sdlcPortAdminRole  
MIN-ACCESS   read-only  
DESCRIPTION  
    "Write access is not required."

OBJECT           sdlcPortAdminType  
MIN-ACCESS   read-only  
DESCRIPTION  
    "Write access is not required."

OBJECT           sdlcPortAdminTopology  
MIN-ACCESS   read-only  
DESCRIPTION  
    "Write access is not required."

OBJECT           sdlcPortAdminISTATUS  
MIN-ACCESS   read-only  
DESCRIPTION  
    "Write access is not required."

OBJECT           sdlcLSAddress  
MIN-ACCESS   read-only  
DESCRIPTION  
    "Write access is not required."

OBJECT           sdlcLSAdminName  
MIN-ACCESS   read-only  
DESCRIPTION  
    "Write access is not required."

OBJECT           sdlcLSAdminState  
MIN-ACCESS   read-only  
DESCRIPTION  
    "Write access is not required."

OBJECT           sdlcLSAdminISTATUS  
MIN-ACCESS   read-only  
DESCRIPTION  
    "Write access is not required."

OBJECT           sdlcLSAdminMAXDATASend  
MIN-ACCESS   read-only  
DESCRIPTION  
    "Write access is not required."

OBJECT           sdlcLSAdminMAXDATARcv  
MIN-ACCESS   read-only  
DESCRIPTION

"Write access is not required."

OBJECT           sdlcLSAdminMAXIN  
MIN-ACCESS    read-only  
DESCRIPTION  
              "Write access is not required."

OBJECT           sdlcLSAdminMAXOUT  
MIN-ACCESS    read-only  
DESCRIPTION  
              "Write access is not required."

OBJECT           sdlcLSAdminMODULO  
MIN-ACCESS    read-only  
DESCRIPTION  
              "Write access is not required."

OBJECT           sdlcLSAdminRETRIESt  
MIN-ACCESS    read-only  
DESCRIPTION  
              "Write access is not required."

OBJECT           sdlcLSAdminRETRIESt  
MIN-ACCESS    read-only  
DESCRIPTION  
              "Write access is not required."

OBJECT           sdlcLSAdminRETRIESt  
MIN-ACCESS    read-only  
DESCRIPTION  
              "Write access is not required."

OBJECT           sdlcLSAdminRNRLIMIT  
MIN-ACCESS    read-only  
DESCRIPTION  
              "Write access is not required."

OBJECT           sdlcLSAdminDATMODE  
MIN-ACCESS    read-only  
DESCRIPTION  
              "Write access is not required."

OBJECT           sdlcLSAdminGPoll  
MIN-ACCESS    read-only  
DESCRIPTION  
              "Write access is not required."

OBJECT           sdlcLSAdminSimRim

```

MIN-ACCESS  read-only
DESCRIPTION
    "Write access is not required."

```

```

OBJECT      sdlcLSAdminRowStatus
MIN-ACCESS  read-only
DESCRIPTION
    "Write access is not required."

```

```
 ::= { sdlcCompliances 1 }
```

```

sdlcPrimaryCompliance  MODULE-COMPLIANCE
STATUS current
DESCRIPTION
    "The compliance statement for all nodes that
    are performing the role of a Primary link
    station."

```

```

MODULE
    MANDATORY-GROUPS { sdlcPrimaryGroup }

```

```

OBJECT      sdlcPortAdminPAUSE
MIN-ACCESS  read-only
DESCRIPTION
    "Write access is not required."

```

```

OBJECT      sdlcLSAdminREPLYTO
MIN-ACCESS  read-only
DESCRIPTION
    "Write access is not required."

```

```
 ::= { sdlcCompliances 2 }
```

```

sdlcPrimaryMultipointCompliance  MODULE-COMPLIANCE
STATUS current
DESCRIPTION
    "The compliance statement for all nodes that
    are performing the role of a primary link
    station on a multipoint line."

```

```

MODULE
    MANDATORY-GROUPS { sdlcPrimaryMultipointGroup }

```

```

OBJECT      sdlcPortAdminSERVLIM
MIN-ACCESS  read-only
DESCRIPTION
    "Write access is not required."

```

```

OBJECT      sdlcPortAdminSlowPollTimer
MIN-ACCESS  read-only

```

## DESCRIPTION

"Write access is not required."

::= { sdlcCompliances 3 }

--  
--  
--

Core Conformance Groups for All Link Stations

sdlcCoreGroups OBJECT IDENTIFIER ::= { sdlcGroups 1 }

sdlcCorePortAdminGroup OBJECT-GROUP  
OBJECTS

```
{
    sdlcPortAdminName,          sdlcPortAdminRole,
    sdlcPortAdminType,          sdlcPortAdminTopology,
    sdlcPortAdminISTATUS
}
```

STATUS current

## DESCRIPTION

"The sdlcCorePortAdminGroup defines objects which are common to the PortAdmin group of all compliant link stations."

::= { sdlcCoreGroups 1 }

sdlcCorePortOperGroup OBJECT-GROUP  
OBJECTS

```
{
    sdlcPortOperName,
    sdlcPortOperRole,
    sdlcPortOperType,
    sdlcPortOperTopology,
    sdlcPortOperISTATUS,
    sdlcPortOperACTIVT0,
    sdlcPortOperLastFailTime,
    sdlcPortOperLastFailCause
}
```

STATUS current

## DESCRIPTION

"The sdlcCorePortOperGroup defines objects which are common to the PortOper group of all compliant link stations."

::= { sdlcCoreGroups 2 }

sdlcCorePortStatsGroup OBJECT-GROUP  
OBJECTS

```

{
    sdlcPortStatsPhysicalFailures,
    sdlcPortStatsInvalidAddresses,
    sdlcPortStatsDwarfFrames
}
STATUS current
DESCRIPTION
    "The sdlcCorePortStatsGroup defines objects
    which are common to the PortStats group of all
    compliant link stations."
 ::= { sdlcCoreGroups 3 }

```

```

sdlcCoreLSAdminGroup OBJECT-GROUP
OBJECTS
{
    sdlcLSAddress,
    sdlcLSAdminName,
    sdlcLSAdminState,
    sdlcLSAdminISTATUS,
    sdlcLSAdminMAXDATASend,
    sdlcLSAdminMAXDATARcv,
    sdlcLSAdminMAXIN,
    sdlcLSAdminMAXOUT,
    sdlcLSAdminMODULO,
    sdlcLSAdminRETRIESt,
    sdlcLSAdminRETRIESt,
    sdlcLSAdminRETRIESt,
    sdlcLSAdminRNRLIMIT,
    sdlcLSAdminDATMODE,
    sdlcLSAdminGPoll,
    sdlcLSAdminSimRim,
    sdlcLSAdminRowStatus
}
STATUS current
DESCRIPTION
    "The sdlcCorePortAdminGroup defines objects
    which are common to the PortAdmin group of all
    compliant link stations."
 ::= { sdlcCoreGroups 4 }

```

```

sdlcCoreLSOperGroup OBJECT-GROUP
OBJECTS
{
    sdlcLSOperRole,
    sdlcLSOperState,
    sdlcLSOperMAXDATASend,
    sdlcLSOperMAXIN,

```

```

        sdLcLSOperMAXOUT,
        sdLcLSOperMODULO,
        sdLcLSOperRETRIESm,
        sdLcLSOperRETRIESt,
        sdLcLSOperRETRIESn,
        sdLcLSOperRNRLIMIT,
        sdLcLSOperDATMODE,
        sdLcLSOperLastFailTime,
        sdLcLSOperLastFailCause,
        sdLcLSOperLastFailCtrlIn,
        sdLcLSOperLastFailCtrlOut,
        sdLcLSOperLastFailFRMRInfo,
        sdLcLSOperLastFailREPLYTs,
        sdLcLSOperEcho,
        sdLcLSOperGPoll
    }
    STATUS current
    DESCRIPTION
        "The sdLcCorePortOperGroup defines objects
        which are common to the PortOper group of all
        compliant link stations."
    ::= { sdLcCoreGroups 5 }

```

```

sdLcCoreLSStatsGroup OBJECT-GROUP
OBJECTS
{
    sdLcLSStatsBLUsIn,
    sdLcLSStatsBLUsOut,
    sdLcLSStatsOctetsIn,
    sdLcLSStatsOctetsOut,
    sdLcLSStatsPollsIn,
    sdLcLSStatsPollsOut,
    sdLcLSStatsPollRspsIn,
    sdLcLSStatsPollRspsOut,
    sdLcLSStatsLocalBusies,
    sdLcLSStatsRemoteBusies,
    sdLcLSStatsIFramesIn,
    sdLcLSStatsIFramesOut,
    sdLcLSStatsRetransmitsIn,
    sdLcLSStatsRetransmitsOut,
    sdLcLSStatsUIFramesIn,
    sdLcLSStatsUIFramesOut,
    sdLcLSStatsXIDsIn,
    sdLcLSStatsXIDsOut,
    sdLcLSStatsTESTsIn,
    sdLcLSStatsTESTsOut,
    sdLcLSStatsREJsIn,

```

```

        sdLcLSStatsREJsOut,
        sdLcLSStatsFRMRsIn,
        sdLcLSStatsFRMRsOut,
        sdLcLSStatsSIMsIn,
        sdLcLSStatsSIMsOut,
        sdLcLSStatsRIMsIn,
        sdLcLSStatsRIMsOut,
        sdLcLSStatsProtocolErrs,
        sdLcLSStatsRNRLIMITs,
        sdLcLSStatsRetriesExps
    }
    STATUS current
    DESCRIPTION
        "The sdLcCorePortStatsGroup defines objects
        which are common to the PortStats group of all
        compliant link stations."
    ::= { sdLcCoreGroups 6 }

```

```

--
-- Conformance Groups for Primary Link Stations
--

```

```
sdLcPrimaryGroups OBJECT IDENTIFIER ::= { sdLcGroups 2 }
```

```

sdLcPrimaryGroup OBJECT-GROUP
    OBJECTS
    {
        sdLcPortAdminPAUSE,
        sdLcPortOperPAUSE,
        sdLcLSAdminREPLYTO,
        sdLcLSOperREPLYTO
    }
    STATUS current
    DESCRIPTION
        "The sdLcPrimaryGroup defines objects which
        are common to all compliant primary link
        stations."
    ::= { sdLcPrimaryGroups 1 }

```

```

sdLcPrimaryMultipointGroup OBJECT-GROUP
    OBJECTS
    {
        sdLcPortAdminSERVLIM,
        sdLcPortAdminSlowPollTimer,
        sdLcPortOperSlowPollMethod,
        sdLcPortOperSERVLIM,
        sdLcPortOperSlowPollTimer
    }

```



```
}  
STATUS current  
DESCRIPTION  
    "The sdlcPrimaryMultipointGroup defines objects  
    which are common to all compliant primary link  
    stations that are in a multipoint topology."  
 ::= { sdlcPrimaryGroups 2 }
```

END

#### 4. Acknowledgments

Thanks goes to the SNADLC MIB working group for reviewing this MIB and for their infinite patience through the editing process.

#### 5. References

- [1] Stewart, B., "Definitions of Managed Objects for RS-232-like Hardware Devices using SMIV2", RFC 1659, Xyplex, July 1994.
- [2] "Synchronous Data Link Control: Concepts", IBM Publication No. GA27-3093-04, 5th edition, May 1992.
- [3] "Vocabulary for Data Processing Telecommunications, and Office Systems", IBM Publication No. GC20-1699-6.
- [4] Kostick, D., Kielczewski, Z., and K. Shih, Editors, "Definitions of Managed Objects for SNA NAUs using SMIV2", RFC 1666, Eicon Technology Corporation, Bell Communications Research, Novell, August 1994.
- [5] Waldbusser, S., "Row Creation with SNMPv1", Work in Progress.
- [6] McCloghrie K., and F. Kastenholz, "Evolution of the Interfaces Group of MIB-II", RFC 1573, Hughes LAN Syst, FTP Software, January 1994.

## 6. Glossary

### link station

A link station comprises procedures and control information that coordinate the transfer of data between two nodes joined by a link connection. All traffic over the link connection is from the primary link station to one or more secondary link stations, or from a secondary link station to the primary link station.

### primary link station

The link station instance on a link connection that is responsible for the control of the data link. There must be only one primary link station on a link connection. The primary link station issues commands to one or more secondary link stations.

### secondary link station

The link station instance on a link connection that receives commands from the primary link station and issues responses to it.

### switched line

A telecommunications line in which the connection is established by dialing. For switched lines, the SDLC startup sequence typically begins with a null exchange identifier (null XID).

### leased line

A telecommunications line on which connections do not have to be established by dialing. For leased lines, the SDLC startup sequence may or may not begin with an exchange identifier (XID). While there are interface (e.g., RS.232) differences between leased and switched lines, those interface differences do not map one-to-one with differences in the SDLC startup protocol (i.e., the interface and the SDLC protocol are independent from one another).

### point-to-point link

A link that connects the single primary link station to single secondary link station. A point-to-point link may be either switched or leased.

### multipoint link

A link that connects the single primary link station to several secondary link stations. A multipoint link may be either switched or leased. Note: The physical interface signals for a multipoint link are different than for a point-to-point link.

Synonymous with multidrop line.

## 7. Security Considerations

Security issues are not discussed in this memo.

## 8. Authors' Addresses

Jeff Hilgeman (chair)  
Apertus Technologies, Inc.  
7275 Flying Cloud Dr.  
Eden Prairie, MN 55344

Phone: 1 612 828 0668  
EMail: jeffh@apertus.com

Shannon D. Nix  
Metaplex, Inc.  
7412 Wingfoot Dr.  
Raleigh, NC 27615

Phone: 1 919 878 0811  
EMail: snix@metaplex.com

Alan Bartky  
Sync Research, Inc.  
7 Studebaker  
Irvine, CA 92718

Phone: 1 714 588 2070  
EMail: alan@sync.com

Wayne Clark (editor)  
Cisco Systems, Inc.  
3100 Smoketree Ct.  
Suite 1000  
Raleigh, NC 27604

Phone: 1 919 878 6958  
EMail: wclark@cisco.com