

Oracle® Tuxedo Message Queue (OTMQ)

Administration Guide

12c Release 1 (12.1.1)

June 2012

Copyright © 2012 Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Oracle Tuxedo Message Queue Administration Guide

OTMQ and Oracle Tuxedo	1
OTMQ Based on Oracle Tuxedo	3
Using Oracle Tuxedo Domains	3
Oracle Tuxedo Configuration	4
UBBCONFIG	4
DMCONFIG	5
Using Oracle Tuxedo Workstation Component	5
Advanced Oracle Tuxedo features	5
Deploying OTMQ on OracleTuxedo Domain(s)	6
OTMQ on Oracle Tuxedo SHM Domain	6
OTMQ on Oracle Tuxedo MP Domain	7
OTMQ on Multiple Oracle Tuxedo Domains	8
OTMQ Workstation Client Support	9
Administrator Tasks	10
Interoperability	10
Interoperability with Traditional Oracle Tuxedo /Q client	11
Interoperability with Traditional Tuxedo /Q server	11
Interoperability with Oracle Message Queue (OMQ)	12
Cross-group connection with OMQ	12
Direct connection	12
Routing	12
Qspace and queue name	12
Buffer type	12
Interoperability with OMQ client	13
Interoperability with OMQ Naming	13
Interoperability with MQSeries Using MQAdapter	13

Configuring for OTMQ Application	14
Configuring OTMQ System Resources	14
Specifying the OTMQ Message Queue Manager Server Group	14
Specifying the OTMQ Message Queue Manager Server.	15
Specifying the OTMQ Offline Trade Driver Server	16
Specifying the OTMQ Event Broker	16
Specifying the OTMQ Naming Server	16
Creating OTMQ Queue Space and Queues.	17
Working with tmqadmin Commands	17
Creating an Entry in the Universal Device List: crdl.	17
Creating a Queue Space: qspacecreate.	18
Creating a Queue: qcreate	20
Configuration for Communication crossing OTMQ Queue Spaces	22
Configuration for Communication crossing OTMQ Queue Spaces in One Oracle Tuxedo Domain.	22
Configuration for Communication crossing OTMQ Queue Spaces in Multiple Oracle Tuxedo Domains	23
Configuration for /WS Clients	24
Configuration for Communication with Oracle Tuxedo /Q	24
Upgrade from Oracle Tuxedo /Q	24
Communication with Oracle Tuxedo /Q client	25
Configuration for Communication with Oracle Message Queue	25
Link Driver Server	25
Create Link Table and Routing Table in Queue Space.	26
Configure Environment	26
Configuration File.	26
%XGROUP Section	27
%ROUTE	28

Client Library Server	28
See Also	28

Oracle Tuxedo Message Queue Administration Guide

This chapter contains the following topics:

- [OTMQ and Oracle Tuxedo](#)
- [Administrator Tasks](#)
- [Interoperability](#)
- [Configuring for OTMQ Application](#)
- [Creating OTMQ Queue Space and Queues](#)
- [Configuration for Communication crossing OTMQ Queue Spaces](#)
- [Configuration for /WS Clients](#)
- [Configuration for Communication with Oracle Tuxedo /Q](#)
- [Configuration for Communication with Oracle Message Queue](#)

OTMQ and Oracle Tuxedo

Note: This section provides a high-level overview of how OTMQ works with Oracle Tuxedo. If you are already familiar with how these products work with each other, you can skip this section.


OTMQ is implemented based on the Oracle Tuxedo infrastructure, which is a typical client-server mode. The basic queuing features are provided by the central OTMQ server `TuxMsgQ(5)`. For more information, see the Oracle Tuxedo Message Queue Reference Guide.

As the foundation and physical storage of OTMQ, the QSpace is the actual physical device that the messages reside in. The QSpace contains one or more message queues. A message is stored in a message queue.

When a client calls the queuing service to enqueue/dequeue messages to/from one message queue, the request will be handled by the TuxMsgQ server. The server will write or retrieve messages from the queue defines in the specific QSpace as the client request.

User processes cannot access the QSpace directly. All requests to operating the QSpace should go through the OTMQ server. [Figure 1](#) show the OTMQ and Tuxedo Architecture.

Figure 1 OTMQ and Oracle Tuxedo Architecture.



There are several more components that enrich the queuing features of OTMQ, such as naming server TMQ_NA, etc. For more detail description about these components, please refer to the OTMQ E-doc "OTMQ system components".

This section contains the following topics:

- [OTMQ Based on Oracle Tuxedo](#)
- [Using Oracle Tuxedo Domains](#)
- [Oracle Tuxedo Configuration](#)
- [Using Oracle Tuxedo Workstation Component](#)
- [Deploying OTMQ on OracleTuxedo Domain\(s\)](#)

OTMQ Based on Oracle Tuxedo

As the foundation of OTMQ, Oracle Tuxedo provides the framework for building scalable multi-tier client-to-server applications in heterogeneous, distributed environment.

First, some important concept for Oracle Tuxedo:

An Oracle Tuxedo domain, also known as an Oracle Tuxedo application, is a set of Tuxedo system, client, and server processes administered as a single unit from a single Tuxedo configuration file. An Oracle Tuxedo domain consists of many system processes, one or more application client processes, one or more application server processes, and one or more computer machines connected over a network.

For one Oracle Tuxedo domain, the architecture can be a single machine (SHM) or multiple machines (MP) connected through networks.

- SHM

A SHM domain is a single node Oracle Tuxedo domain where all Oracle Tuxedo processes have access to the same share memory.

- MP

A MP domain is a clustered environment where the application can be spread across multiple machines/nodes, but all these nodes of the cluster are managed as a single entity.

- Multiple Domains

An Oracle Tuxedo application can consist with multiple domains. Each domain is a separately administered unit. Oracle Tuxedo allows the application to separate into multiple domains and still allow applications in one domain to access services in other domains

Using Oracle Tuxedo Domains

As a company's business grows, application engineers may need to organize the business information management into distinct applications, each having administrative autonomy, based on functionality, geographical location, or confidentiality. These distinct business applications, can be configured as several domains. The Oracle Tuxedo Domains component provides the infrastructure for interoperability among the domains of a business, thereby extending the Oracle Tuxedo client/server model to multiple domains.

The inter-domain communication between Oracle Tuxedo domains is using the domain gateway. Domain gateway is highly asynchronous, multitasking server processes that handle outgoing and

incoming services requests to or from remote domains. They make access to services across domains transparent to both the application programmer and the application user.

For more information, see "[Using the Oracle Tuxedo Domains Component](#)."

Oracle Tuxedo Configuration

Oracle Tuxedo configuration files are used to describe the Oracle Tuxedo applications. The configuration file is a repository that contains all the information necessary to boot and run an application, such as specifications for application resources, machines, machine groups, servers, available services, interfaces, and so on.

For SHM/MP domains, the UBBCONFIG is the configuration file. It is a text version of the configuration file, which can be created and edited with any text editor. Before booting the application using the configuration file, a binary version of the configuration file TUXCONFIG should be created from the text version by `tmloadcf(1)` command.

For applications consist of multiple domains, additional configuration file for domain connections. Like UBBCONFIG, configuration file DMCONFIG is the text version, which describe how multiple domains are connected and which services they make accessible to each other. Use the `dmloadcf(1)` utility to get the binary version of domain configuration file BDMCONFIG.

For more information, see "[About the Configuration File](#)" and "[Creating the Configuration File](#)."

UBBCONFIG

A UBBCONFIG file is made up of nine possible specification sections:

*RESOURCES, *MACHINES, *GROUPS, *SERVERS, *SERVICES, *INTERFACES, *NETWORK, *NETGROUPS, *ROUTING.

The *RESOURCES section defines parameters that control the application as a whole and server as system-wise defaults.

The *MACHINES section defines parameters for each machine in an application.

The *GROUPS section designate logically grouped sets of servers. At least one server group for a machine should be defined.

The *SERVERS section contains information specific to a server process. Each entry in this section represents a server process to be booted in the application.

The *SERVICES section provides information on services that advertised by server processes.

For more information, see UBBCONFIG(5) in [“Section 5 - File Formats, Data Descriptions, MIBs, and System Processes Reference”](#) in the Oracle Tuxedo Reference Guide.

DMCONFIG

The domains configuration file DMCNFIG defines the local/remote domain access points, and local/remote available services through each access point. Application clients can access services through these access points. Also it map the local access points and remote access points to specific domain gateway groups and network address defined in the UBBCONFIG.

The DMCNFIG file is made up of the following specification sections: *DM_LOCAL, *DM_REMOTE, *DM_EXPORT, *DM_IMPORT, *DM_RESOURCES, *DM_ROUTING, *DM_ACCESS_CONTROL, *DM_TDOMAIN.

The *DM_LOCAL section defines one or more local domain access point identifiers and their associated gateway groups. Correspondingly, the *DM_REMOTE section defines one or more remote domain access point identifiers and their characteristics.

The *DM_EXPORT section provides information on the services exported by each individual local domain access point. And the *DM_IMPORT section provides information on services imported and available to the local domain through remote domain access points defined in the *DM_REMOTE section.

For more information, see DMCNFIG(5) in [“Section 5 - File Formats, Data Descriptions, MIBs, and System Processes Reference”](#) in the Oracle Tuxedo Reference Guide.

Using Oracle Tuxedo Workstation Component

The Workstation component of the Oracle Tuxedo system allows application clients to reside on a machine that does not have a full server-side installation, that is, a machine that does not support any administration or application servers. All communication between a Workstation client-an application client running on a Workstation component-and the server application takes place over the network. For more information, see [Using The Oracle Tuxedo ATMI Workstation Component](#) .

Advanced Oracle Tuxedo features

Besides being the basic framework for client-to-server applications, Oracle Tuxedo can also provide a series of advanced features, such as:

- Scalability

Application built on Oracle Tuxedo can support a single client on a single server, or they can support tens of thousands of clients and thousands of servers without changing application code. As an application scales, the Oracle Tuxedo system continues to provide end users with consistently high performance and good responsiveness.

- High availability and fault management

In a distributed client-to-server environment with thousands of independent processors and processes, Oracle Tuxedo can ensure no single point of failure by providing replicated server groups, and restores the running application to good condition after failures occur.

- Security

Oracle Tuxedo security includes authentication, authorization, and encryption to ensure data privacy when deploying Oracle Tuxedo application across networks. Network level and application level encryption are supported.

Deploying OTMQ on OracleTuxedo Domain(s)

OTMQ can utilize the flexible and scalable Oracle Tuxedo domain configurations, to deploy the QSpace and queues according to the requirements of the application.


To deploy and run a basic OTMQ application, you must do the following steps:

1. Create QSpace and queues on disk (refer to OTMQ E-doc "Creating OTMQ Queue Space and Queues").
2. Create Oracle Tuxedo UBBCONFIG (and DMCONFIG if using multiple domains) to configure TuxMsgQ server(s) that associate with the QSpaces.
3. Create application that calls OTMQ API `tpenqplus/tpdeqplus` for queuing.
4. Build the application.
5. Boot Oracle Tuxedo and run the application.

OTMQ on Oracle Tuxedo SHM Domain

OTMQ application on an Oracle Tuxedo SHM domain can create one or multiple QSpace. Each QSpace maps to a service provided by OTMQ server TuxMsgQ. Application clients calls OTMQ API `tpqattach()` first to attach to a queue to get access to specific QSpace, then calls `tpenqplus()` to enqueue message, or dequeue message from attached queue.

Also the client can enqueue message to the queue that belongs to another QSpace that it does not attached to, as shown in [Figure 2](#).


Figure 2 OTMQ Application on Oracle Tuxedo SHM Domain

OTMQ on Oracle Tuxedo MP Domain

OTMQ application on an Oracle Tuxedo MP domain can create one or multiple QSpace on its master and slave node respectively. Each QSpace maps to a service provided by OTMQ server TuxMsgQ. Application clients on master or slave node can call OTMQ API `tpqattach()` first to attach to a queue to get access to specific QSpace on its own node, then calls `tpenqplus()` to enqueue message, or dequeue message from attached queue.

Also the client on node B can enqueue message to the queue that belongs to another QSpace on node A that it doesn't attached to, as shown in [Figure 3](#).


Figure 3 OTMQ Application on Oracle Tuxedo MP Domain



OTMQ on Multiple Oracle Tuxedo Domains

OTMQ application can be deployed across multiple Oracle Tuxedo domains. Each domain can have one or multiple QSpace. Each QSpace maps to a service provided by OTMQ server TuxMsgQ. Application clients of one domain A can call OTMQ API `tpqattach(3c)` first to attach to a queue to get access to specific QSpace in its domain, then calls `tpenqplus(3c)` to enqueue message to queues that belong to the attached QSpace, or dequeue message from attached queue.


Also the client of domain B can also enqueue message to the queue that belongs to the QSpace of domain A as long as domain A has exported its service for its own QSpace, as shown in [Figure 4](#).

Figure 4 OTMQ Application on Multiple Oracle Tuxedo Domains

OTMQ Workstation Client Support

OTMQ application can also have workstation clients by utilizing Oracle Tuxedo workstation component, as shown in [Figure 5](#).

Figure 5 OTMQ Application Workstation Client Support



Administrator Tasks

The Oracle Tuxedo administrator is responsible for defining servers and creating queue spaces and queues for the Oracle Tuxedo Message Queue (OTMQ) component.

The administrator must define at least one queue server group with TMS_TMQM as the transaction manager server for the group.

The administrator also must create a queue space using the queue administration program, `tmqadmin(1)`, or the `OTMQ_MIB()` Management Information Base (MIB) that includes extended classes for OTMQ. There is a one-to-one mapping of queue space to queue server group since each queue space is a resource manager (RM) instance and only a single RM can exist in a group.

The administrator can define a single server group in the application configuration for the queue space by specifying the group in `UBBCONFIG` or by using `tmconfig` to add the group dynamically.

Part of the task of defining a queue is specifying the order for messages on the queue. Queue ordering can be determined by message availability time, expiration time, priority, FIFO and LIFO. Refer to `qcreate` sub-command of `tmqadmin(1)` for detail information.

Interoperability

- [Interoperability with Traditional Oracle Tuxedo /Q client](#)


- Interoperability with Traditional Tuxedo /Q server
- Interoperability with Oracle Message Queue (OMQ)
- Interoperability with MQSeries Using MQAdapter

Interoperability with Traditional Oracle Tuxedo /Q client

Traditional Oracle Tuxedo /Q clients can communicate with OTMQ with only configuration change, as shown in [Figure 6](#)

Of course, to take advantage of the new features introduced in OTMQ, application code need be changed. Traditional Tuxedo /Q `tpenqueue(3c)/tpdequeue(3c)` functions need be replaced with OTMQ counterparts `tpenqplus(3c)/tpdeqplus(3c)`. Traditional Tuxedo /Q clients including APPQ_MIB classes (`T_APPQ`, `T_APPQMSG`, `T_APPQSPACE` and `T_APPQTRANS`) need replace them with corresponding OTMQ_MIB(5) classes (`T_OTMQ`, `T_OTMQMSG`, `T_OTMQSPACE` and `T_OTMQTRANS`).

Figure 6 Interoperability with Traditional Oracle Tuxedo /Q client



Interoperability with Traditional Tuxedo /Q server

Tuxedo /Q server cannot boot on the new OTMQ QSpace, and cannot process queuing requests from the new OTMQ clients.

Interoperability with Oracle Message Queue (OMQ)

- [Cross-group connection with OMQ](#)
- [Interoperability with OMQ client](#)
- [Interoperability with OMQ Naming](#)

Cross-group connection with OTMQ

To support cross-group connection with OMQ, OTMQ provides Link Driver Server `TuxMsgQLD(5)`, as shown in [Figure 7](#). With this server deployed, OTMQ and OMQ can have message-level compatibilities, with following limitations:

Direct connection

Only support DISC and RTS UMA.

Routing

Only support AK and NN modes.

Only support DISC UMA.

Only support MEM, DEQ and ACK DIPs when protocol exchange is involved more than once, such as sending message from OMQ to OMQ through OTMQ or from OTMQ to OTMQ through OMQ.

Qspace and queue name


In OTMQ, Qspace and queue name are string characters. In OMQ, the counterparts group and queue number are integer numbers. So, to communicate with OMQ, OTMQ must have numerical Qspace and queue name.

Message Based Service

OTMQ does not support Message Based Service (MBS).

Buffer type

OMQ only supports CARRAY and FML32 buffer types.

Figure 7 Interoperability with Oracle Message Queue (OMQ)

Interoperability with OMQ client

To support interoperability between OMQ client application and OTMQ, OTMQ provides Client Library Server `TuxCls(5)`. With this server deployed, OTMQ and OMQ client can have message-level compatibilities. The traditional OMQ client can work with OTMQ server without any code change, compile and link, and any configuration change, except for below limitations:.

- OMQ security is not supported.
- OMQ UMA `PDEL_UMA_DISCL` is not supported.

Interoperability with OMQ Naming

To integrate the OTMQ global naming service with OMQ naming, the global naming file, which indicated by environment variables `DMQNS_DEFAULTPATH` and `DMQNS_DEVICE`, should have the read and write permissions for OTMQ and OMQ naming services.

Interoperability with MQSeries Using MQAdapter

To integrate with MQSeries, OTMQ can still utilize MQ Adapter. must do as follow:

- Using `tpenqueue/tpdequeue` or `tpenqplus/tpdeqplus`.

- If using `tpenqplus/tpdeqplus`, need add `tpqattach` before invoking `tpenqplus/tpdeqplus`, and the attached `qspace/qname` is a OTMQ's `qspace/qname` .
- Using `buildqclient` to re-compile codes.

Note: OTMQ server can only booted on an OTMQ formatted QSPACE, it cannot booted on a /Q formatted QSAPCE.

Configuring for OTMQ Application

The configuration and the queue attributes must reflect the requirements of the application.

Configuring OTMQ System Resources

Core servers `TMS_TMQM(5)`, `TuxMsgQ(5)`, `TuxMQFWD(5)` and `TMQEVNT(5)` are provided by the OTMQ. `TMS_TMQM(5)` manages global transactions for the queued message facility. It must be defined in the `*GROUPS` section of the configuration file. `TuxMsgQ(5)` and `TuxMQFWD(5)` provide message queuing services to users. They must be defined in the `*SERVERS` section of the configuration file. `TMQEVNT(5)` provides publish/subscribe services to users. It must be defined in `*SERVERS` section of the configuration file.

Supplemental servers `TMQ_NA(5)`, `TuxMsgQLD(5)` and `TuxCls(5)` can be configured at machine level for one or more OTMQ queue space.

Specifying the OTMQ Message Queue Manager Server Group

In addition to the standard requirements of a group name tag and a value for `GRPNO`, there must be a server group defined for each OTMQ queue space the application will use. The `TMSNAME` and `OPENINFO` parameters need to be set. Here are examples:

```
TMSNAME= TMS_TMQM
```

and

```
OPENINFO=" TUXEDO/TMQM:<device_name>:<queue_space_name>"
```

`TMS_TMQM` is the name for the transaction manager server for OTMQ. In `OPENINFO` parameter, `TUXEDO/TMQM` is the literal name for the resource manager as it appears in `$TUXDIR/udataobj/RM`. The values for `<device_name>` and `<queue_space_name>` are instance-specific and must be set to the pathname for the universal device list and the name associated with the queue space, respectively. These values are specified by the administrator using `tmqadmin(1)`.

Note: The chronological order of these specifications is not critical. The configuration file can be created either before or after the queue space is defined. The important thing is that the configuration must be defined and queue space and queues created before the facility can be used.

There can be only one queue space per *GROUPS section entry. The CLOSEINFO parameter is not used.

The following example shows the configuration of server group for OTMQ.

Listing 1 OTMQ Server Group Configuration

```
*GROUPS
QGRP1 GRPNO=1 TMSNAME=TMS_TMQM
      OPENINFO="TUXEDO/TMQM:/dev/device1: queuespace1"
QGRP2 GRPNO=2 TMSNAME=TMS_TMQM
      OPENINFO="TUXEDO/TMQM:/dev/device2: queuespace2"
```

Specifying the OTMQ Message Queue Manager Server

The `TuxMsgQ(5)` takes the same CLOPT as TMQUEUE server of Oracle Tuxedo /Q. The `TuxMsgQ(5)` reference page gives a full description of the SERVERS section of the configuration file. But still the `TuxMsgQ(5)` has several unique properties can be specified:

- Attach Timeout

Attach is the mandatory operation for an OTMQ application to access the OTMQ queue space. The attach operation can be configured with a default timeout value per queue space. To configure the default attach timeout for the queue space, add a service named `TuxMQATH<qspace_name>` in the SERVICES section, and set the BLOCKTIME property of this service as the default attach timeout value.

- Sanity Check Interval

`TuxMsgQ(5)` provides the sanity check function to remove invalid queue owners. To configure the sanity check interval for the `TuxMsgQ(5)` server, set "`-i <interval>`" in CLOPT. The `<interval>` value means the `TuxMsgQ(5)` server will do sanity check per receiving this number of messages.

Specifying the OTMQ Offline Trade Driver Server

OTMQ Offline Trade Driver Server `TuxMQFWD(5)` is part of the OTMQ Reliable Message Delivery feature. It is responsible for resending the recoverable messages to the target if the OTMQ Message Queue Manager Server `TuxMsgQ(5)` fails to deliver the message to target at the first time.

Refer to the `TuxMQFWD(5)` reference page for a full description of the `*SERVERS` section of the configuration file for this server.

Any improper configuration that prevents the `TuxMQFWD(5)` server from dequeuing or forwarding messages will cause the server booting failure. Some important items should be emphasized:

- `*SRVGRP` of `TuxMQFWD(5)` server must have `TMSNAME` set to `TMS_TMQM`, and the `OPENINFO` must be set to associate with the proper device and queue space.
- The entry of `TuxMQFWD(5)` server in `*SERVERS` section should not be part of an `MSSQ` set.
- `REPLYQ` of `TuxMQFWD(5)` server should be set to `N`.
- `TuxMQFWD(5)` server does not advertise any service.
- Only one `TuxMQFWD(5)` server process can be configured for one OTMQ queue space.

Specifying the OTMQ Event Broker

OTMQ Event Broker `TMQEVNT(5)` is required for publish/subscribe feature. It is responsible for notifying subscribers when topics are published. It must be configured in a separate server group from `TuxMsgQ(5)` and `TuxMQFWD(5)`.

Refer to the `TMQEVNT(5)` reference page for a full description of the `*SERVERS` section of the configuration file for this server.

Specifying the OTMQ Naming Server

OTMQ Naming Server `TMQ_NA(5)` can be configured to provide the naming feature. It allows the application to bind the queue alias to an actual queue name, and also supports lookup the actual queue name through provided queue alias.

Refer to the reference page of `TMQ_NA(5)` for a full description of the `*SERVERS` section of the configuration file for this server.

One limitation for the naming server is only one `TMQ_NA(5)` server process can be configured for one OTMQ queue space.

The `TMQ_NA(5)` may boot with a pre-defined name space file, which is specified when creating or updating the queue space. The following example shows the content of one static name space file, which defines the association between the user defined queue alias and the actual queue name.

Table 1 Static Name Space File Content

# Queue Alias	Queue Name	Name Scope
Queue_Alias_1	queue1	L
Queue_Alias_2	queue1	G
MyQueue	queue2	L

Refer to `qspacecreate` or `qspacechange` command of `tmqadmin(1)` for specifying the static name space file.

Creating OTMQ Queue Space and Queues

OTMQ command `tmqadmin(1)` is used to establish the resources of the OTMQ. The OTMQ_MIB Management Information Base also provides an alternative method of administering OTMQ programmatically. See the Using MIB for more information on the MIB operation.

Working with `tmqadmin` Commands

Most of the key commands of `tmqadmin` have positional parameters. If the positional parameters (those not specified with a dash (-) preceding the option) are not specified on the command line when the command is invoked, `tmqadmin` prompts you for the required information.

Creating an Entry in the Universal Device List: `crdl`

The universal device list (UDL) is a VTOC file under the control of the Oracle Tuxedo system. It maps the physical storage space on a machine where the Oracle Tuxedo system is run. An entry in the UDL points to the disk space where the queues and messages of a queue space are stored; the Oracle Tuxedo system manages the input and output for that space. If the queued message

facility is installed as part of a new Oracle Tuxedo installation, the UDL is created by `tmloadcf(1)` when the configuration file is first loaded.

Before you create a queue space, you must create an entry for it in the UDL. The following is an example of the commands:

```
# First invoke the OTMQ administrative interface, tmqadmin
# The QMCONFIG variable points to an existing device where the UDL
# either resides or will reside.
```

```
QMCONFIG=/dev/QUE_TMQ
```

```
# Next create the device list entry
```

```
crdl /dev/QUE_TMQ 0 5000
```

```
# The above command sets aside 5000 physical pages beginning at block number 0
```

If you are going to add an entry to an existing Oracle Tuxedo UDL, the value for the `QMCONFIG` variable must be the same pathname specified in `TUXCONFIG`. Once you have invoked `tmqadmin(1)`, it is recommend that you run a `lidl` command to see where space is available before creating your new entry.

Creating a Queue Space: `qspacecreate`

A queue space makes use of IPC resources; when you define a queue space you are allocating a shared memory segment and a semaphore. As noted above, the easiest way to use the command is to let it prompt you. (You can also use the `T_OTMQSPACE` class of the `OTMQ_MIB` to create a queue space.) The sequence looks like this:

Listing 2 `qspacecreate`

```
> qspacecreate
Queue space name: 1
IPC Key for queue space: 123567
Size of queue space in disk pages: 2048
Number of queues in queue space: 15
Number of concurrent transactions in queue space: 100
Number of concurrent processes in queue space: 100
Number of messages in queue space: 100
Error queue name: errque
```



```

Initialize extents (y, n [default=n]): y
Blocking factor [default=16]:
Create SAF and DQF queue by default: (y, n [default=y]):
Enables PCJ journaling by default: (y, n [default=n]): y
Enable Dead Letter Journal by default: (y, n [default=y]): y

```

The program does not prompt you to specify the size of the area to reserve in shared memory for storing non-persistent messages for all queues in the queue space. When you require non-persistent (memory-based) messages, you must specify the size of the memory area on the `qspacecreate` command line with the `-n` option.

The value for the IPC key should be picked so as not to conflict with your other requirements for IPC resources. It should be a value greater than 32,768 and less than 262,143.

The size of the queue space, the number of queues, and the number of messages that can be queued at one time all depend on the needs of your application. Of course, you cannot specify a size greater than the number of pages specified in your UDL entry. In connection with these parameters, you also need to look ahead to the queue capacity parameters for an individual queue within the queue space. Those parameters allow you to (a) set a limit on the number of messages that can be put on a queue, and (b) name a command to be executed when the number of enqueued messages on the queue reaches the threshold. If you specify a low number of concurrent messages for the queue space, you may create a situation where your threshold on a queue will never be reached.

To calculate the number of concurrent transactions, count each of the following as one transaction:

- Each TMS_TMQM server in the group that uses this queue space
- Each TuxMsgQ or TuxMQFWD server in the group that uses this queue space
- `tmqadmin`

If your client programs begin transactions before they join the OTMQ queue space, increase the count by the number of clients that might access the queue space concurrently. The worst case is that all clients access the queue space at the same time.

For the number of concurrent processes count one for each TMS_TMQM, TuxMsgQ or TuxMQFWD server in the group that uses this queue space and one for a fudge factor.

Most of these prompts are the same as the `qspacecreate` of `qmadmin` command of Oracle Tuxedo /Q component. The last three prompts are specific for OTMQ.

If SAF and DQF queues are created by default, the recoverable delivery feature using SAF and DQF are enabled. Otherwise they cannot be used until the user create these two queues manually by `qcreate` command and enable them by OTMQ_MIB.

PCJ and DLJ are created by default as permanent active queues. If they are not enabled by default, they cannot be used until the user enables them by OTMQ_MIB.

You can choose to initialize the queue space as you use the `qspacecreate` command, or you can let it be done by the `qopen` command when you first open the queue space.

Creating a Queue: `qcreate`

Each queue that you intend to use must be created with the `tmqadmin(1) qcreate` command. First you have to open the queue space with the `qopen` command. If you do not provides a queue space name, `qopen` will prompt for it. (You can also use the T_OTMQ class of the OTMQ_MIB to create a queue.)

The prompt sequence for `qcreate` looks like the following:

Listing 3 `qcreate` Prompt Sequence

```
> qcreate -t PQ -a Y
Queue name: my_que
Queue order (priority, time, expiration, fifo, lifo): fifo
Out-of-ordering enqueueing (top, msgid, [default=none]):
Retries [default=0]: 0
Retry delay in seconds [default=0]: 30
High limit for queue capacity warning (b for bytes used, B for blocks used,
% for percent used, m for messages [default=100%]):
Default high threshold: 100%
Reset (low) limit for queue capacity warning [default=0%]:
Default low threshold: 0%
Queue capacity command:
No default queue capacity command
Queue 'my_que' created
```

The program does not prompt you for a default delivery policy and memory threshold options. The default delivery policy option allows you to specify whether messages with no specified delivery mode are delivered to persistent (disk-based) or non-persistent (memory-based) storage. The memory threshold option allows you to specify values used to trigger command execution when a non-persistent memory threshold is reached. To use these options, you must specify them on the `qcreate` command line with `-d` and `-n`, respectively. When the delivery policy is specified as persistent, using `-q` option can specify the storage threshold.

Most of these prompts and options are the same as the `qcreate` or `qmadmin` command of Oracle Tuxedo /Q component. Still OTMQ provides more specific options:

- Specifying queue type

```
-t [qtype]
```

OTMQ queue can has following types: PQ (Primary Queue), SQ (Secondary Queue), MRQ (Multi-Reader Queue), and UNLIMITQ (Unlimited Queue). When not specified, the default type is UNLIMITQ.

- Specifying queue owner

```
-o [queue_name]
```

If the queue type is specified as "SQ", you can define the controlling queue of this SQ using the option "-o". Only the PQ can be defined as the owner of one SQ. When not specified, there is no owner by default.

- Specifying queue active property

```
-a [active]
```

The queue can be specified as permanent active or temporary active. A permanent active queue can always receive and store messages even there is no application attaching to it, while a temporary active queue can only receive and store messages when it is attached by application. Setting the value of the option "-a" to "Y" or "N" to specify the active property. When not specified, the default property is temporary active.

- Specifying the confirm style

```
-c [confirm_style]
```

The confirm style of the queue determines the behavior of how the recoverable messages are confirmed by the receiving application that attaches to this queue. Using option "-c" to specify. The allowed values of this option are: EO (Explicit, out-of-order confirmations); EI (Explicit, in-order confirmations); II (Implicit, in-order confirmations). When not specified, the default confirm style is EO.

Configuration for Communication crossing OTMQ Queue Spaces

Applications that belong to different OTMQ queue spaces can communicate with each other, which is called the cross queue space communication. The most common scenario is the sender application that attaches to one OTMQ queue space A can enqueue messages to a remote receiver application that attaches to another OTMQ queue space B.

These OTMQ queue spaces can reside in the same Oracle Tuxedo domain or in different Oracle Tuxedo domains.

Configuration for Communication crossing OTMQ Queue Spaces in One Oracle Tuxedo Domain

Multiple OTMQ queue spaces can be configured in one Oracle Tuxedo Domain. Different OTMQ queue spaces should belong to different server groups in the UBBCONFIG. Accordingly the TMS and OPENINFO should be defined for each OTMQ queue space.

The following example shows the configuration of two OTMQ queue spaces that reside in the same Oracle Tuxedo Domain.

Listing 4 Two OTMQ Queue Spaces in Same Oracle Tuxedo Domain

```
*GROUPS

QGRP1   GRPNO=1  TMSNAME=TMS_TMQM
        OPENINFO="TUXEDO/TMQM:/dev/device1: queuespace1"

QGRP2   GRPNO=2  TMSNAME=TMS_TMQM
        OPENINFO="TUXEDO/TMQM:/dev/device2: queuespace2"

*SERVERS

TuxMsgQ
        SRVGRP=QGRP1  SRVID=11  RESTART=Y  CONV=N  MAXGEN=10
        CLOPT = "-s queuespace1:TuxMsgQ -- -i 60 "

TuxMsgQ
        SRVGRP=QGRP2  SRVID=12  RESTART=Y  CONV=N  MAXGEN=10
        CLOPT = "-s queuespace2:TuxMsgQ -- -i 30 "
```

Configuration for Communication crossing OTMQ Queue Spaces in Multiple Oracle Tuxedo Domains

OTMQ queue spaces can be configured on different Oracle Tuxedo Domains. Applications belong to these queue spaces can communicate with each other once the DMCONFIG is configured properly.

Just like the normal DMCONFIG configuration for Oracle Tuxedo cross domain service invoking, to enable one application to access the OTMQ queue space on a remote domain, the OTMQ queue space should export itself to the peers as a service. The local domain should import this service accordingly for local OTMQ applications.

The following example shows the configuration of two OTMQ queue spaces that reside in the different Oracle Tuxedo Domains.

- Configure OTMQ queue space "QS1" in UBBCONFIG for Domain "DomA":

```
*GROUPS
QGRP1  GRPNO=1  TMSNAME=TMS_TMQM
        OPENINFO="TUXEDO/TMQM:/dev/device1: QS1"

*SERVERS
TuxMsgQ
        SRVGRP=QGRP1  SRVID=11  RESTART=Y  CONV=N  MAXGEN=10
        CLOPT = "-s QS1:TuxMsgQ -- -i 60 "
```

- Configure OTMQ queue space "QS2" in UBBCONFIG for Domain "DomB"

```
*GROUPS
QGRP1  GRPNO=1  TMSNAME=TMS_TMQM
        OPENINFO="TUXEDO/TMQM:/dev/device2: QS2"

*SERVERS
TuxMsgQ
        SRVGRP=QGRP1  SRVID=11  RESTART=Y  CONV=N  MAXGEN=10
        CLOPT = "-s QS2:TuxMsgQ -- -i 30 "
```

- Export OTMQ queue space "QS2" of "DomB " to remote domain "DomA" in DMCONFIG of "DomB"

```
*DM_EXPORT
QS2  LDOM=DomB  RDOM=DomA
```

- Import OTMQ queue space "QS2" of "DomB" in DMCONFIG of "DomA"

```
*DM_IMPORT
QS2  LDOM=DomA  RDOM=DomB
```

After properly configuration, an application that attaches to the queue space QS1 then can directly enqueue messages, via standard enqueue APIs to a remote queue of queue space QS2 that resides in a remote domain.

Configuration for /WS Clients

This section describes how to configure the OTMQ WS Client. OTMQ WS client must set some environments to take advantage of WS SAF feature. The following configuration options can be set using script, WSENVFILE or default value. WSENVFILE is name of a file containing environment variable settings to be set in the client's environment. The description of its format can be seen on TUXEDO edoc.

WSC_JOURNAL_ENABLE: If set to 1, WS SAF is enabled. If set to 0, WS SAF is disabled. The default value is 0.

WSC_JOURNAL_PATH: Specifies the journal file path. The default value is `"/"` on UNIX and `"\\\\"` on Windows.

WSC_JOURNAL_SIZE: Initial size of the journal file. The default value is 49150.

WSC_JOURNAL_CYCLE_BLOCKS: the journal cycles (reuses) disk blocks when full and overwrites previous messages. The default value is 0.

WSC_JOURNAL_FIXED_SIZE: Determines if the journal size is fixed or allowed to grow. The default value is 0.

WSC_JOURNAL_PREALLOC: the journal file disk blocks are pre-allocated when the journal is initially opened. The default value is 1.

WSC_JOURNAL_MSG_BLOCK_SIZE: Defines the file I/O block size, in bytes. The default value is 0.

Configuration for Communication with Oracle Tuxedo /Q

Upgrade from Oracle Tuxedo /Q

OTMQ provides a utility `ConvertQSPACE()` to upgrade Oracle Tuxedo /Q Qspace to OTMQ Qspace, so that the customers who already deployed Oracle Tuxedo /Q applications can benefit from OTMQ new features without data lost.

Refer to the `ConvertQSPACE(1)` reference page for a full description of usage.

You must do the following steps::

1. Shutdown existed /Q servers and applications.
2. ipcrm /Q Qspace ipckey.
3. Make sure the QMCONFIG environment variable is configured as /Q device.
4. Run the utility with a) OTMQ device name, b) Qspace to be migrated and c) OTMQ Qspace ipckey:
`ConvertQSPACE -d [Q++ device name] -s [Qspace name] -i [Q++ ipckey]`
5. ipcrm OTMQ Qspace ipckey.
6. Configure the OTMQ servers in Tuxedo UBB according to OTMQ device and Qspace name.
7. Boot up the OTMQ servers.

Communication with Oracle Tuxedo /Q client

After Tuxedo /Q Qspace is upgraded to OTMQ Qspace, and OTMQ servers are booted, Tuxedo /Q clients can communicate with OTMQ without any change. Alternatively Tuxedo /Q clients can be re-compiled and re-linked with OTMQ libraries to use /Q compatible APIs `tpenqueue(3c)` and `tpdequeue(3c)` provided by OTMQ. To take advantage of OTMQ new features, application code need be changed with OTMQ APIs. In one application or applications communicating with each other, /Q compatible APIs `tpenqueue()` / `tpdequeue()` should not be mixed with other OTMQ APIs such as `tpengplus()` / `tpdeqplus()` / `tpqconfirmmsg()`, otherwise the result is undefined.

Configuration for Communication with Oracle Message Queue

Link Driver Server

OTMQ provides Link Driver Server `TuxMsgQLD(5)` as counterpart of OMQ Link Driver to achieve message level compatibilities for cross-group communication between OTMQ and OMQ applications.

Also `TuxMsgQLD(5)` provides the routing functionality like traditional OMQ Link Driver but with limitations. For more information, see [Interoperability](#)

Create Link Table and Routing Table in Queue Space

TuxMsgQLD(5) requires pre-created link table and routing table in corresponding OTMQ Qspace. Link table consists of entries that each stands for one remote OMQ group. Routing table consists of entries that each stands for one combination of target group and routing through group. Link table and routing table are created by `tmqadmin(1) qspacecreate` command. The default size of link table is 200, or a different size can be specified with `-L` option. The default size of routing table is 200, or a different size can be specified with `-R` option.

Refer to `qspacecreate` command of `tmqadmin(1)` for specifying link table and routing table size.

Configure Environment

To notify remote OMQ that we are in the same bus, environment variable `DMQ_BUS_ID` should be defined before booting up TuxMsgQLD(5).

Configuration File

TuxMsgQLD(5) requires a configuration file placed under `APPDIR`. The configuration file name is specified by `CLOPT-f` parameter. Refer to the TuxMsgQLD(5) reference page for a full description of the `SERVERS` section of the configuration file for this server.

Following is an example of the Link Driver Server's configuration file:

Listing 5 Link Driver Server Configuration File

```
# Define cross-group connections with remote OMQ,
# only the remove OMQ group info should be list here
%XGROUP
#Group  Group  Node/  Init-  Thresh  Buffer  Recon-  Window  Trans-  End-
#Name   Number Host    iate   old     Pool   nect   Delay  Size(Kb) port  point
GRP_11  11    host1.abc.com Y      -       -       30    10    250    TCPIP 10001
GRP_12  12    host2.abc.com Y      -       -       30    10    250    TCPIP 10002
%EOS

%ROUTE
#-----
# Target      Route-through
# Group       Group
#-----
```



```

2          11
3          12
%EOS
%END

```

%XGROUP Section

Following attributes are mandatory for OTMQ to setup XGROUP connection to the remote OMQ group:

- Group Name -- Remote OMQ group name by which the remote OMQ group is known to the local OTMQ Qspace
- Group Number -- Remote OMQ group number
- Node/Host -- Network name of remote OMQ group
- Endpoint -- The internet port number of the remote OMQ link listener process

Following attributes are optional. If not set, default values will be used:

- Initiate -- "Y", "N" or "D". Indicating whether connections to this node should be initiated (connect when local group startup) or whether connections to this node is enabled. Default is "N".
- Reconnect -- Interval in seconds, between reconnect attempts when this cross-group link is not connected. Default is 60.
- Window Delay -- Delay in seconds, that a sender must wait before using a new window when the receiver is congested. Default is 10.
- Windows Size -- Maximum number of messages a group can send to another group before requesting permission to send more. Default is 250.
- Transport: Network protocol stack used. Only "TCPIP" is supported.

Following attributes are not supported by OTMQ Link Driver Server, just to keep align with traditional OMQ XGROUP settings:

- Buffer Pool -- Not supported by OTMQ for now.
- Threshold -- Not supported by OTMQ for now.

%ROUTE

Following attributes are mandatory for OTMQ to setup ROUTE info for the remote OMQ/OTMQ groups that can't be connected directly:

- Target Group -- OMQ/OTMQ group for which traffic is being routed to.
- Route-through Group -- OMQ group to which traffic for the target group will be routed through.

Notes:

- Route-through Groups should be the directly connected OMQ groups defined in the %XGROUP section
- Cannot define multiple routing entries for the same Target Group.

Client Library Server

OTMQ provides Client Library Server `TuxCls(5)` as counterpart of OMQ Client Library Server to achieve message-level compatibilities with OMQ workstation clients. With `TuxCls(5)` deployed, OMQ workstation clients can work with OTMQ servers without any change.

`TuxCls(5)` works as proxy of OTMQ clients, so the max count of supported OMQ clients is configured by `MIN` and `MAX` parameters of `TuxCls(5)` in the `UBBCONFIG *SERVERS` section.

On windows, `MIN` must be set to 1 or not configured, `MAX` must be set in the range 2-512. The max OMQ clients count connected to OTMQ is limited to 511.

On UNIX, `MIN` must be set to 1 or not configured, `MAX` has no limitation. The max OMQ clients count connected to OTMQ depends on the operating system and Oracle Tuxedo limitations.

See Also

- [Oracle Tuxedo Message Queue Reference Guide](#)