

Fast Error-Bounded HPC Data Compressor (sz-1.4)

User Guide (Version 1.4.9)

Mathematics and Computer Science (MCS)

Argonne National Laboratory

Contact: Sheng Di (sdi1@anl.gov)

Feb, 2017

Table of Contents

Table of Contents	1
1. Brief description.....	1
2. How to install SZ	2
3. Quick Start	3
3.1 Compression	3
3.2 Decompression	4
4. Application Programming Interface (API)	5
4.1 Compression/Decompression by C Interfaces.....	5
4.2 Compression/Decompression by Fortran Interfaces.....	8
5 Test cases.....	11
6. Initialization of SZ environment	11
7. Compression Modes.....	12
8. Version history	12
8. Q&A and Trouble shooting.....	14

1. Brief description

- **SZ** (short for **Squeeze**) is an **error-bounded** HPC in-situ data compressor for significantly reducing the data sizes, which can be leveraged to improve the checkpoint/restart performance and post-processing efficiency for HPC executions.
- SZ can be used to compress different types of data (single-precision and double-precision) and any shapes of the array. Current version supports up to five dimensions. Higher dimensions can also be extended easily.
- SZ is very easy to use. It supports three programming languages: Fortran, C and Java.
- SZ supports many different architectures, including x86_32bits (denoted by linux_x86 in the Makefile), x86_64bits (denoted by linux_x64 in the Makefile), ARM (denoted by linux_arm), SOLARIS (denoted by solaris), IBM BlueGene series (denoted by pps).

- SZ allows setting the compression error bound based on *absolute error bound* and/or *relative error bound*, or *point-wise relative error bound*, by using sz.config (which can be found in the directory *example*) or by passing arguments through programming interfaces.
 - **Absolute error bound** (namely *absErrBound* in the configuration file sz.config): It is to limit the (de)compression errors to be within an absolute error. For example, `absErrBound=0.0001` means the decompressed value must be in $[V-0.0001, V+0.0001]$, where V is the original true value.
 - **Relative error bound** (called *relBoundRatio* in the configuration file sz.config): It is to limit the (de)compression errors by considering the **global data value range size** (i.e., taking into account the range size (`max_value - min_value`)). For example, suppose `relBoundRatio` is set to 0.01, and the data set is {100,101,102,103,104,...,110}. That is, the maximum value is 110 and minimum value is 100. So, the global value range size is $110-100=10$, and the error bound will actually be $10*0.01=0.1$, from the perspective of "relBoundRatio".
 - **Point-wise relative error bound**: It is to control the compression errors based on a relative error ratio in comparison with each data point's value. For example, given point-wise relative error bound = 0.01, then the real compression error bound for each data point will be equal to $0.01*\{\text{the current data value}\}$. SZ will adopt the point-wise relative error bound mode when setting `errBoundMode` to **PW_REL**.
- Users can set the real compression error bound based on only `absErrorBound`, `relBoundRatio`, or a kind of combination of them. Two types of combinations are provided: **AND, OR**. **ABS_AND_REL** means that both of the two bounds (`absErrorBound` and `relBoundRatio`) will be considered in the compression. **ABS_OR_REL** means that the compression error is satisfied as long as one type of bound is met. Current version doesn't support combination of **PW_REL** and other types of bounds.
- If there are many variables to be compressed, we recommend to compress them using batch-compression way. Specifically, there are two steps in the batch-compression: (1) register/add variables, and (2) perform the compression. Please reference the description of `SZ_batchAddVar()` and `SZ_batch_compress()`. An example code (`testfloat_batch_compress.c`) can also be found in `example/` directory.
- Users are allowed to set the endian type of the data in the sz.config. Please check the comments of this file in the `example/` directory.

2. How to install SZ

The SZ software can be downloaded from <http://collab.mcs.anl.gov/display/ESR/SZ>

Perform the following three simple steps to finish the installation:

```
configure --prefix=[INSTALL_DIR]
```

```
make
```

make install

You'll find all the executables in [INSTALL_DIR]/bin and .a and .so libraries in [INSTALL_DIR]/lib

(**Note:** If you want to enable fortran compilation, please use --enable-fortran option when running the "configure --prefix=[]" command. The default compilation is without fortran.)

3. Quick Start

The testing cases can be found in [SZ_Package]/example

You can use "make clean;make" to recompile all the example codes, or compile them by the customized Makefile.bk as follows:

```
make -f Makefile.bk
```

(Makefile.bk allows you to compile your customized source codes.)

For simplicity, you can use [SZ_Package]/example/test.sh to test all examples.

3.1 Compression

Testing commands:

Run **"/testdouble_compress sz.config testdata/x86/testdouble_8_8_128.dat 8 8 128"** to compress the data testdouble_8_8_128.dat.

Run **"/testdouble_compress sz.config testdata/x86/testdouble_8_8_8_128.dat 8 8 8 128"** to compress the data testdouble_8_8_8_128.dat.

Run **"/testfloat_compress sz.config testdata/x86/testfloat_8_8_128.dat 8 8 128"** to compress the data testfloat_8_8_128.dat

Remark:

testdouble_8_8_128.dat and testdouble_8_8_8_128.dat are two binary testing files, which contain a 3d array (128X8X8) and a 4d array (128X8X8X8) respectively. Their data values are shown in the two plain text files, testdouble_8_8_128.txt and testdouble_8_8_8_128.txt. These two data files are from FLASH_Blast2 and FLASH_MacLaurin respectively (the two test data are both extracted at time step 100). The compressed data files to be generated are named testdouble_8_8_128.dat.sz and testdouble_8_8_8_128.dat.sz respectively.

./testfloat_compress.c is an example to show how to compress single-precision data. Use testfloat_8_8_128.dat as the input when testing the compression of single-precision data.

sz.config is the configuration file. The key settings are *errorBoundMode*, *absErrBound*, and *relBoundRatio*, which are described below.

- **absErrBound** refers to the absolute error bound, which is to limit the (de)compression

errors to be within an absolute error. For example, `absErrBound=0.0001` means the decompressed value must be in $[V-0.0001, V+0.0001]$, where V is the original true value.

- **relBoundRatio** refers to value-range based relative bound ratio, which is to limit the (de)compression errors by considering the global data value range size (i.e., taking into account the range size (`max_value - min_value`)). For example, suppose `relBoundRatio` is set to 0.01, and the data set is `{100,101,102,103,104,...,110}`. In this case, the maximum value is 110 and the minimum is 100. So, the global value range size is $110-100=10$, and the error bound will be $10*0.01=0.1$, from the perspective of "relBoundRatio".
- **errorBoundMode** is to define a combination of the above two types of error bounds. There are four types of values: **ABS**, **REL**, **ABS_AND_REL**, **ABS_OR_REL**.
 - **ABS** takes only "absolute error bound" into account. That is, relative bound ratio will be ignored.
 - **REL** takes only "relative bound ratio" into account. That is, absolute error bound will be ignored.
 - **ABS_AND_REL** takes both of the two bounds into account. The compression errors will be limited using both `absErrBound` and `relBoundRatio*rangeSize`. That is, the two bounds must be both met.
 - **ABS_OR_REL** takes both of the two bounds into account. The compression errors will be limited using either `absErrBound` or `relBoundRatio*rangeSize`. That is, only one bound is required to be met.
 - **PW_REL** takes "point-wise relative error bound". Please read the comment in `sz.config` for details.

sz.config is the configuration file used to set the compression environment. Please read the comment in the file to understand the parameters.

3.2 Decompression

Testing commands:

```
./testdouble_decompress sz.config testdata/x86/testdouble_8_8_128.dat.sz 8 8 128
```

```
./testdouble_decompress sz.config testdata/x86/testdouble_8_8_8_128.dat.sz 8 8 8 128
```

```
./testfloat_decompress sz.config testdata/x86/testfloat_8_8_128.dat.sz 8 8 128
```

Remark:

- Unlike the compression step, you don't have to provide the error bound information (such as `errBoundMode`, `absErrBound`, and `relBoundRatio`), when performing the data decompression, because such information is stored in the compressed data stream.
- The output files of the `test_decompress.c` are `.out` files, i.e., `testdouble_8_8_128.dat.sz.out` and `testdouble_8_8_8_128.dat.sz.out` respectively. You can compare `.txt` file and `.out` file for checking the compression errors for each data

point. For instance, compare testdouble_8_8_8_128.txt and
testdouble_8_8_8_128.dat.sz.out.

4. Application Programming Interface (API)

Programming interfaces are provided in two programming languages – C and Fortran (SZ-0.x versions also provided Java interfaces). The usage methods of the interfaces are quite similar across different programming languages, with only a few differences. For example, In C interface, a *dataType* (either SZ_FLOAT or SZ_DOUBLE) is required, while Fortran interface doesn't require this argument because of the function overloading feature.

4.1 Compression/Decompression by C Interfaces

There are three key interfaces for compression/decompression in C.

- (1) Initialize the compressor by calling SZ_Init();
- (2) Compress the data (a floating-point array) by SZ_compress(), or decompress the data by SZ_decompress();
- (3) Finalize the compressor by SZ_Finalize() if the compressor won't be used any more.

Interfaces:

(a) SZ_Init and SZ_Init_Params

Initialize the SZ compressor. SZ_Init() just needs to be called only **once** before performing multiple compressions for different variables (data arrays).

Synopsis: `void SZ_Init(char *configFilePath);`

Input:

`configFilePath` the configuration file path (such as example/sz.config)

Return: none.

Synopsis: `void SZ_Init_Params(sz_params * params);`

Input: `params` the configuration variable that contains the initialization information.

Return: none.

sz_params data structure:

`typedef struct sz_params`

`{`

`unsigned int quantization_intervals; //default value: 0`

`int dataEndianType; //what is the endian type of the original data set?`

`int sysEndianType; //sysEndianType can be ignored, because it can be detected automatically by our compressor based on the system architectures.`

`int sol_ID; //default value: #define SZ 101`

`int layers; //default value: 1`

```

int sampleDistance; //default value: 50
float preThreshold; //default value: 0.97
int offset; //default value: 0
int szMode; //default value: #define SZ_BEST_COMPRESSION 1
int gzipMode; //default value: Gzip_BEST_SPEED
int errorBoundMode; //4 options: ABS, REL, ABS_AND_REL, ABS_OR_REL
double absErrBound; //example: 0.0001
double relBoundRatio; //example: 0.001

```

} **sz_params**;

(Detailed description of the above parameters can be found in the sz.config)

(b) **SZ_compress**

Compress the floating-point data array. Two types of interfaces are provided, as shown below. For the first one, the three important control parameters (errBoundMode, absErrBound, and relBoundRatio) will be given by the configuration file sz.config. For the second one, the three control parameters will be passed using arguments, so in this case, the parameter settings in the sz.config will be ignored.

There are three compression interfaces with different arguments, as listed below. The user just needs to choose one of them in compressing data.

Synopsis:

```

char *SZ_compress(int dataType, void *data, int *outSize, int r5, int r4, int r3, int r2,
int r1);

```

```

char *SZ_compress_args(int dataType, void *data, int *outSize,
int errBoundMode, double absErrBound, double relBoundRatio,
int r5, int r4, int r3, int r2, int r1);

```

```

int SZ_compress_args2(int dataType, void *data, char* compressed_bytes,
int *outSize,
int errBoundMode, double absErrBound, double relBoundRatio,
int r5, int r4, int r3, int r2, int r1);

```

Input:

dataType	the indicator that indicates the data type (two options: either <i>SZ_FLOAT</i> or <i>SZ_DOUBLE</i>)
data	the variable that contains the data to be compressed. (Current version only supports “double precision” data)
compressed_bytes	the address that contains the compressed bytes
outSize	the data stream size (in bytes) after compression.
r5	size of dimension 5
r4	size of dimension 4
r3	size of dimension 3
r2	size of dimension 2
r1	size of dimension 1

Return: Compressed data stream (in the form of bytes)

Usage tips: The dimension of the variable is determined based on the five dimension parameters (r5, r4, r3, r2, and r1). For instance, if the variable is a 2D array (M X N),

then $r5=0$, $r4=0$, $r3=0$, $r2=M$, and $r1=N$. If the variable to protect is a 4D array, then only $r5$ is set to 0. (See `test_compress.c` for details).

(c) **SZ_decompress**

Decompress/recover the data. Two options, as listed below.

Synopsis:

```
void *SZ_decompress(int dataType, char *bytes, int byteLength,
                    int r5, int r4, int r3, int r2, int r1);
int SZ_decompress_args(int dataType, char *bytes, int byteLength,
                        void* decompressed_array,
                        int r5, int r4, int r3, int r2, int r1);
```

Input:

dataType	the indicator to indicate the data type (either <i>SZ_FLOAT</i> or <i>SZ_DOUBLE</i>)
bytes	the compressed data stream to be decompressed
byteLength	length of the compressed data stream
decompressed_array	the address to store decompressed data
r5	size of dimension 5
r4	size of dimension 4
r3	size of dimension 3
r2	size of dimension 2
r1	size of dimension 1

Return: the recovered data array decompressed from the compressed bytes.

(d) **SZ_batchAddVar**

Register/add a variable (denoted by *var*) to be compressed with other variables together in a batch way.

Synopsis:

```
void SZ_batchAddVar(char* varName, int dataType, void* var,
                    int r5, int r4, int r3, int r2, int r1,
                    int errBoundMode, double absErrBound, double relBoundRatio);
```

(e) **SZ_batchDelVar**

Deregister/delete a variable (denoted by *var*) from the list of registered variables, that are to be compressed with other variables together in a batch way.

Synopsis:

```
int SZ_batchDelVar(char* varName);
```

Input:

varName	the name of variable used in the registration.
----------------	--

Return: 0: success or 1: no corresponding variable is found based on *varName*.

(f) **SZ_batch_compress**

Compress the data in a batch way: all of the registered variable data will be compressed together (The benefit is improvement of compression factor).

Synopsis:

```
char* SZ_batch_compress(int *outSize);
```

Input:

outSize the data stream size (in bytes) after compression.

Return: the compressed stream.

(g) SZ_batch_decompress

Decompress the batch-compressed stream.

Synopsis:

SZ_VarSet* **SZ_batch_decompress** (**char*** compressedStream,
int compressedLength);

Input:

compressedStream the compressed stream

compressedLength the length of the compressed stream (in byte)

Return: The data structure containing the decompressed data with multiple variables. See VarSet.h for more details. The global SZ_VarSet is defined in sz.h: SZ_VarSet* sz_varset.

(h) SZ_Finalize

Release the memory and compression environment.

Synopsis: **int** **SZ_Finalize**();

Input: none.

Return: none.

4.2 Compression/Decompression by Fortran Interfaces

Interfaces:

(a) SZ_Init

Initialize the SZ compressor. SZ_Init() just needs to be called only **once** before performing multiple compressions for different variables (data arrays).

Synopsis: **SZ_Init**(configFilePath, ierr);

Input:

configFilePath configuration file path (e.g., sz.config)

CHARACTER(len=32) :: configFilePath

Output:

ierr successful (0) or failed (1)

INTEGER(Kind=4) :: ierr

(b) SZ_Compress

Compress the floating-point data array. Two types of interfaces are provided, as shown below. For the first one, the three important control parameters (errBoundMode, absErrBound, and relBoundRatio) will be given by the configuration file sz.config. For the second one, the three control parameters will be passed using arguments, so in this case, the parameter settings in the sz.config will be ignored.

Synopsis A:

SZ_compress(data, bytes, outSize);

Input:

data the data array to be compressed

(the data here is a floating-point data array with up to 5 dimensions. For example, "REAL(KIND=8), DIMENSION(:, :, :) :: *data*" indicates a 3D double-precision array, where *data* refers to the array variable.)

Output:

bytes the byte stream generated after the compression
INTEGER(kind=1), DIMENSION(:), allocatable :: bytes

outsize the size (in bytes) of the byte stream
INTEGER(kind=4) :: OutSize

Synopsis B:

SZ_Compress (data, bytes, outSize,
errBoundMode, absErrBound, relBoundRatio);

Input:

data the data array to be compressed
(the data here is a floating-point data array with up to 5 dimensions. For example, "REAL(KIND=8), DIMENSION(:, :, :) :: *data*" indicates a 3D double-precision array, where *data* refers to the array variable.)

errBoundMode the error bound mode.
Four options: ABS, REL, ABS_AND_REL, ABS_OR_REL
INTEGER(kind=4) :: ErrBoundMode

absErrBound absolute error bound
REAL(kind=4 or 8) :: absErrBound

relBoundRatio relative bound ratio
REAL(kind=4 or 8) :: relBoundRatio
(Details about error bound mode, absolute error bound, and relative bound ratio can be found in Section 3.1)

Output:

bytes the byte stream generated after the compression
INTEGER(kind=1), DIMENSION(:), allocatable :: bytes

outsize the size (in bytes) of the byte stream
INTEGER(kind=4) :: OutSize

(c) SZ-Decompress

Decompress/recover the data

Synopsis:

SZ-Decompress(bytes, data, [r1,r2,...])

Input:

bytes the compressed data stream to be decompressed
INTEGER(kind=1), DIMENSION(:) :: Bytes

data length of the compressed data stream
REAL(KIND=4 or 8), DIMENSION(:, :, ..., :), allocatable :: data

r1 size of dimension 1

r2	size of dimension 2
r3	size of dimension 3
r4	size of dimension 4
r5	size of dimension 5

INTEGER(kind=4) :: r1[, r2, r3, r4, r5]

Usage tips: SZ_Decompress supports the decompression of the array with at most 5 dimensions. The dimension sizes (such as r1, r2,) are supposed to be provided. For example, in order to decompress a binary stream whose original data is a 3D array (r3=10,r2=8,r1=8), the function is like "SZ_Decompress(bytes, data, 8, 8, 10).

(d) SZ_BatchAddVar

Register/add a data variable (denoted by *var*) to be compressed with other variables together in a batch way.

Synopsis:

```
void SZ_batchAddVar(varName, var,
                    errBoundMode, absErrBound, relBoundRatio);
```

varName	the name of the variable to be registered/added CHARACTER(len=128) :: varName
var	the variable/data to be registered/added
errBoundMode	the error bound mode. Four options: ABS, REL, ABS_AND_REL, ABS_OR_REL INTEGER(kind=4) :: ErrBoundMode
absErrBound	absolute error bound REAL(kind=4 or 8) :: absErrBound
relBoundRatio	relative bound ratio REAL(kind=4 or 8) :: relBoundRatio (Details about error bound mode, absolute error bound, and relative bound ratio can be found in Section 3.1.

(e) SZ_BatchDelVar

Deregister/delete a variable (denoted by *var*) from the list of registered variables, that are to be compressed with other variables together in a batch way.

Synopsis:

```
void SZ_batchDelVar(varName, ierr);
```

Input:

varName	the name of variable used in the registration. CHARACTER(len=128) :: varName
----------------	--

Output:

ierr	the output status (0: success or 1: no variable found) INTEGER(kind=4) :: ErrBoundMode
-------------	--

Return: 0: success or 1: no corresponding variable is found based on varName.

(f) SZ_Batch_Compress

Compress the data in a batch way: all of the registered variable data will be compressed together (The benefit is improvement of compression factor).

Synopsis:

void SZ_Batch_Compress(bytes, outSize)

Output:

bytes the byte stream generated after the compression
 INTEGER(kind=1), DIMENSION(:), allocatable :: bytes
outsize the size (in bytes) of the byte stream

(g) SZ_Batch-Decompress

Decompress the batch-compressed stream.

Synopsis:

void SZ_Batch-Decompress(bytes, outSize)

Output:

bytes the compressed data stream to be decompressed
 INTEGER(kind=1), DIMENSION(:) :: Bytes
outsize the size of the decompressed data stream
 INTEGER(kind=4) :: OutSize

(h) SZ_Finalize

Release the memory and compression environment

Synopsis: **SZ_Finalize();**

Input: none.

Return: none.

5 Test cases

example/testdouble_compress.c
 example/testdouble_decompress.c
 example/testfloat_compress.c
 example/testfloat_decompress.c
 example/testfloat_batch_compress.c
 example/testdouble_batch_compress.c
 example/testdouble_compress.f90
 example/testdouble/decompress.f90

6. Initialization of SZ environment

As you can see in the test cases, the SZ requires loading some parameters beforehand for compressing the floating-point data sets. This parameter loading step is performed by `SZ_Init(configFilePath)` or `SZ_Init_Params(params)` function, and it just needs to be called once in order to compress multiple data sets stored in different variables.

- `SZ_Init(configFilePath)` loads the parameters by reading a configuration file (named `sz.config`), which can be found in the `./example` directory.
- `SZ_Init_Params(params)` initialize the compression environment by passing the

parameter data structure. Its definition can be found in the sz.h.

7. Compression Modes

SZ provides three different modes, including SZ_BEST_SPEED, SZ_DEFAULT_COMPRESSION, and SZ_BEST_COMPRESSION respectively.

- **SZ_BEST_SPEED:** SZ will compress the data sets as fast as possible, by ignoring the Gzip step.
- **SZ_DEFAULT_COMPRESSION:** SZ will compress the data sets with a good tradeoff between the compression speed and compression factor.
- **SZ_BEST_COMPRESSION:** SZ will try to compress the data sets with a high compression factor.

Basically, SZ_BEST_SPEED will lead to a much faster compression than the other two modes (by 30+%) in our evaluation. The compression factor of SZ_DEFAULT_COMPRESSION is close to that of SZ_BEST_COMPRESSION, while the compression speed may be faster than SZ_BEST_COMPRESSION by 10%.

8. Version history

The latest version (**version 1.4.9**) is the recommended one.

Version New features

SZ 0.2-0.4 Compression ratio is the same as SZ 0.5. The key difference is different implementation ways, such that SZ 0.5 is much faster than SZ 0.2-0.4.

SZ 0.5.1 Support version checking

SZ 0.5.2 finer compression granularity for unpredictable data, and also remove redundant Java storage bytes

SZ 0.5.3 Integrate with the dynamic segmentation support

SZ 0.5.4 Gzip_mode: default --> fast_mode ; Support reserved value

SZ 0.5.5 runtime memory is shrinked (by changing int xxx to byte xxx in the codes)

The bug that writing decompressed data may encounter exceptions is fixed.

Memory leaking bug for ppc architecture is fixed.

SZ 0.5.6 improve compression ratio for some cases (when the values in some segmentation are always the same, this segment will be merged forward)

SZ 0.5.7 improve the decompression speed for some cases

SZ 0.5.8 Refine the leading-zero granularity (change it from byte to bits based on the distribution). For example, in SZ0.5.7, the leading-zero is always in bytes, 0, 1, 2, or 3. In

SZ0.5.8 The leading-zero part could be xxxx xxxx xx xx xx xxxx xxxx (where each x means a bit in the leading-zero part)

SZ 0.5.9 optimize the offset by using simple right-shifting method. Experiments show that

this cannot improve compression ratio actually, because simple right-shifting actually make each data be multiplied by 2^k , where k is # right-shifting bits. The pros is to save bits because of more leading-zero bytes, but the cons is much more required bits to save. A good solution is SZ 0.5.10!

SZ 0.5.10 optimize the offset by using the optimized formula of computing the median_value based on optimized right-shifting method. Anyway, SZ0.5.10 improves compression ratio a lot for hard-to-compress datasets. (Hard-to-compress datasets refer to the cases whose compression ratios are usually very limited)

SZ 0.5.11 In a very few cases, SZ 0.5.10 cannot guarantee the error-bounds to a certain user-specified level. For example, when absolute error bound = $1E-6$, the maximum decompression error may be $0.01(>>1E-6)$ because of the huge value range even in the optimized segments such that the normalized data cannot reach the required precision even stoaring all of the 64 or 32 mantissa bits. SZ 0.5.11 fixed the problem well, with degraded compression ratio less than 1%.

SZ 0.5.12 A parameter setting called "offset" is added to the configuration file sz.config. The value of offset is an integer in [1,7]. Generally, we recommend offset=2 or 3, while we also find that some other settings (such as offset=7) may lead to better compression ratios in some cases. How to automize/optimize the selection of offset value would be the future work. In addition, the compression speed is improved, by replacing java List by array implementation in the code.

SZ 0.5.13 Compression performance is improved, by replacing some class instances in the source code by primitive data type implementation.

SZ 0.5.14 fixed a design bug, which improves the compression ratio further.

SZ 0.5.15 improved the compression ratio for single-precision data compression, by tuning the offset.

The version 0.x were all coded in Java, and C/Fortran interfaces were provided by using JNI and C/Fortran wrapper. SZ 1.0 is coded in C purely.

SZ 1.0 Pure C version. In this version, the users don't need to install JDK and make the relative configurations any more. It provides dataEndienType in the sz.config file, so it can be used to compress the data file which was generated on different endian-type systems.

SZ 1.1 batch_compression function is added to this version. Compression performance is improved slightly due to for(;;) being replaced by memcpy() somewhere.

SZ 1.2 The compression ratio is improved by 30%-50% in most of datasets (especially for relatively-hard-to-compress ones), and the compression time is reduced by about 10%, compared to SZ1.1.

SZ 1.3 The compression ratio and speed are improved further compared with SZ1.2, by using 256 quantization intervals and multi-dimensional prediction.

SZ 1.4 The compression ratio and speed are further improved than SZ 1.3, by optimizing the number of quantization intervals. This version also provides different compression modes, including SZ_BEST_SPEED, SZ_DEFAULT_SPEED, and SZ_BEST_COMPRESSION.

8. Q&A and Trouble shooting

1. Why would the maximum decompression error be slightly larger than the specified error bound in some cases?

Answer: This is due to the machine representation of the floating-point data. Here is one example. Suppose the error bound is set to 1E-5 and the original data value is 128.178314, and the decompressed value would be 128.178324 according to our compression method, which satisfies the error bound 1E-5. However, 128.178324 and 128.178329 has exactly the same IEEE 754 representation: 01000011 00000000 00101101 10100111. So, the decompressed value may be represented as 128.178329 instead of 128.178324. In this situation, the decompression error is 1.5E-5, which is larger than the error bound 1E-5.

2. Do I need to call SZ_init() every time I compress a variable in the program?

Answer: No. In the progress, SZ_init() is to initialize the compression, and it just needs to be called once, and thereafter you can always compress different variables using the compression/decompression functions on demand, until SZ_finalize() is called. There are two ways to initialize the compression environment, please read Section 6 for details.

3. If I want to use SZ_compress_args() function and specify the errorBoundMode and bounds at run time instead of using the sz.config, do I need to call SZ_init()?

Answer: It depends. In fact, sz.config has some important parameter settings, e.g., data_endian_type (little or big). You can also set these parameters manually in your code or use the default setting or using sz_params data structure. Please check sz.h and conf.c for details.

4. How to deal with “Error: The input file or data stream is not in SZ format!”?

Answer: This error is because the input file or data stream used to be decompressed is probably not the byte stream compressed/generated by the SZ. Please use the compressed file (such as data.sz) in the decompression.

5. How to switch on/off the Fortran compilation?

Answer:

Do the following steps to switch on the compilation for Fortran users.

```
./configure --prefix=[install_dir] --enable-fortran
```

(The compilation without the option “--enable-fortran” is without Fortran compile by default)

6. Do I need to initialize the environment by SZ_Init() for decompression?

Answer:

No. SZ_Init() is only required by compression step.

<END>