


Kentico provides a flexible security model that allows you to configure granular access permissions for pages and applications in the administration interface.

The security model consists of:

- [Users](#) (shared among websites)
- [Roles](#) (defined for websites or globally for all sites in the system)
- [Memberships](#) (collections of roles that can be assigned to users)
- [Module permissions](#) (permissions for specific features in Kentico)
- [Page permissions](#) (ACLs, content and page type permissions)
- [UI personalization](#) (hiding components of the user interface)

## Relationships between users, roles and permissions

The following figure shows how users are assigned to roles and how permissions for pages and applications are granted to users and roles:



**Users** can be members of any number of roles. Permissions for particular pages can be granted to users directly. If you want to grant module permissions to a user, you need to make the user a member of a role, and grant the permissions to the role.



Each user has a [privilege level](#) that controls access to the administration interface, and can override permission requirements (for administrator levels).

**Roles** in Kentico are fully customizable. You are not limited to a predefined set of roles. Instead, you can define your own roles with custom sets of permissions.

If a user is a member of multiple roles, their **permissions for modules** are calculated as a sum of all permissions granted to all roles.

If **permissions for pages** in Kentico repository are granted to both a user and their roles, page permissions are calculated as a sum of all permissions granted to the user and to all roles. If you **deny a page permission** for a user or one of their roles, then the result is always "denied" for the given permission, even if some of the roles are allowed to perform the action.