

How config MSYS2 MinGW32_MinGW64 GCC C_C++ compiler into CodeBlocks

Name of tutorial : How config MSYS2 MinGW32/MinGW64 GCC C/C++ compiler into Code::Blocks on Windows 11 64 bits.

Code::Blocks : the best and great free IDE for Windows, Linux and ... Mac OS

During first run of CB on Windows, this IDE detect automatically some compilers, or present one list of them pre-configured.

It's very good functionality, but, sometimes, you must "force" these configurations proposed by default to run correctly.

This tuto describe how configure compilers GCC included in MSYS2 MinGW32/MinGW64 environment on Windows.

MinGW : A native Windows port of the GNU Compiler Collection (GCC), with freely distributable import libraries and header

files for building native Windows applications; includes extensions to the MSVC runtime to support C99 functionality.

All of MinGW's software will execute on the 64bit Windows platforms.

MSYS2 : It's a portage of MSYS to actualised all packages included in MinGW32 and MinGW64 with latest versions of software.

How to install MSYS2 MinGW32/MinGW64 on Windows 11 64 bits ?

By example, you can install MSYS2 available on this site <https://www.msys2.org/>, last version dated july 2024 :

"msys2-x86_64-20240507.exe"

On Windows 11 system, 64 bits, MSYS2 is installed by default on directory : C:\msys64.

After first install, you must add all needed software by use of tool "pacman" in console MSYS2 by open this in list

of installed software on Windows 11 : clic in task bar on "windows" icon, then choose "all" on the rigth of the new

screen and select application "MSYS2" and submenu "MSYS2 MSYS".

Open this console (or command file) and type next commands ("-toolchain" because install many useful complements) :

```
pacman -S mingw-w64-i686-toolchain
pacman -S mingw-w64-x86_64-toolchain
pacman -S mingw-w64-ucrt-x86_64-toolchain
pacman -S mingw-w64-x86_64-doxygen, grep, sed, bash, mingw-w64-x86_64-ninja,
msys/make mingw32/mingw-w64-i686-clang,
mingw-w64-x86_64-clang
```

So, with MSYS2, you can use multiple development environment, 32 or 64 bits (ARM64 not mandatory on X32/X64 architecture) :

Name	Directory	Compiler	Architecture	RT	C	base	Default lib	C++
------	-----------	----------	--------------	----	---	------	-------------	-----

MSYS	/usr	gcc	x86_64	cygwin			libstdc++	
UCRT64	/ucrt64	gcc	x86_64	ucrt			libstdc++	
CLANG64	/clang64	llvm/clang	x86_64	ucrt			libc++	
CLANGARM64	/clangarm64	llvm/clang	aarch64	ucrt			libc++	
CLANG32	/clang32	llvm/clang	i686	ucrt			libc++	
MINGW64	/mingw64	gcc	x86_64	msvcrt			libstdc++	
MINGW32	/mingw32	gcc	i686	msvcrt			libstdc++	

You must configure this new compiler into CB by selecting main menu "Settings" then submenu "Compiler..." into IDE interface,
then, choose "GNU GCC Compiler (default)" and rename this like "MSYS2 MinGW32 32bit" by example.

Then, you choose tab "Toolchain executable" to position good environment like this

Toolchain executable :

C:\msys64\mingw32 (subdirectory \bin will be searched automatically to access to binaries listed after)

compilateur C : gcc.exe

compilateur C++ : g++.exe

linker for dynamic lib : g++.exe

linker for static lib : gcc-ar.exe

debugger : gdb.exe

resource compiler : windres.exe

make program : mingw32-make.exe

Then, you choose tab "Search directories" to position good environment like this :

```
to compiler :          C:\msys64\mingw32\i686-w64-mingw32\include and
C:\msys64\mingw32\include
to linker :            C:\msys64\mingw32\i686-w64-mingw32\lib      and
C:\msys64\mingw32\lib
to resource compiler : C:\msys64\mingw32\i686-w64-mingw32\include and
C:\msys64\mingw32\include
```

Then, you can type this into command console Windows : "C:\msys64\mingw32\bin\g++.exe --version"; result here :

g++.exe (Rev1, Built by MSYS2 project) 14.2.0

Copyright (C) 2024 Free Software Foundation, Inc.

This is free software; see the source for copying conditions. There is NO warranty; not even for MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.

And, with simply source "helloworld.c", you can test generation of program into IDE CB, choosing "create new project" in main windows of CB, and choose "console application" with no source proposed by default, because named "main.c" is proposed by default, and choose compiler "MSYS2 MinGW32 32bit".

You can select good directory/source with option "add file" after first creation of project into CB.

One time project created, you can generate it with selecting main menu "Build" and choose submenu "Rebuild..." (or CTRL-F11).

If, you apply all of precedent instructions, compile and link of your program with this new compiler must be succeeded.

To terminate, you must reiterate last instructions to configure MinGW64 included in MSYS2 environment :

You must configure this new compiler into CB by selecting main menu "Settings" then submenu "Compiler..." into IDE interface, then, choose "GNU GCC Compiler (default)" and rename this like "MSYS2 MinGW64 64bit" by example.

After, choose tab "Toolchain executable" to position good environment like this

Toolchain executable :

C:\msys64\mingw64 (subdirectory \bin will be searched automatically to access to binaries listed after)

compilateur C : gcc.exe

compilateur C++ : g++.exe

linker for dynamic lib : g++.exe

linker for static lib : gcc-ar.exe

debugger : gdb.exe

resource compiler : windres.exe

make program : mingw32-make.exe

Then, you choose tab "Search directories" to position good environment like this :

```
to compiler : C:\msys64\mingw64\x86_64-w64-mingw32\include
and C:\msys64\mingw64\include
to linker : C:\msys64\mingw64\x86_64-w64-mingw32\lib
and C:\msys64\mingw64\lib
to resource compiler : C:\msys64\mingw64\x86_64-w64-mingw32\include and
C:\msys64\mingw64\include
```

To verify, you can repeat instruction with "very simply" code "helloworld.c" like with MinGW32, only choose good compiler to generate program.

Warning : To update with latest versions of software after first install, you must reactivate "pacman" in console MSYS2 MSYS

like this : "pacman -Syuu". It's suffisant to update all packages and softwares installed on your configuration. Simply.

Pleasure of programming is open for you, your imagination is illimited, at your keyboard ! Enjoy !

PS : source file "helloworld.c" :

/ Basic example in language C : helloworld.c /

```
#include <stdio.h>

int main(int argc, char argv[]) {
/ printf() displays the string inside quotation */
printf("Hello, World!");
return 0;
}
```

PS2 : You can also use compiler GCC of MinGW64 include in MSYS2 in command console on Windows (CMD.EXE) with next instructions :

```

set PATHSAV=%PATH%
set PATH=C:\msys64\mingw64\bin;%PATH%
REM Next instructions are not mandatory, but you can set var if you want.
REM set CLANG=C:\RedPanda-Cpp\MinGW64\x86_64-w64-
mingw32\includeC:\msys64\mingw64\include
REM set LIBRARY_PATH=C:\msys64\mingw64\x86_64-w64-
mingw32\lib,C:\msys64\mingw64\include

```

```

REM Generate console application in one pass
gcc helloworld.c -o helloworld.exe
REM Generate console application in two pass
gcc -c helloworld.c -o helloworld.obj
gcc helloworld.obj -o helloworld.exe -Wl,--subsystem console

```

Continue with use of GCC, and don't forgive, at the end of your work, to return to initial state :

```

set PATH=%PATHSAV%

```

And, with precedent example, you can also use version GCC 32 bits of MSYS2.

But, it's much easy to use GCC of MinGW64 included in MSYS2 directly into CB IDE especially with complex C program
(many C sources and many subdirectories ...) -)

PS3 : Command "gcc" present a very "verbose" list of options, but to resume principal and useful options, you can use

by example :

"-m16" Generate i386 16 bits object or executable.

"-m32" Generate i386 32 bits object or executable.

"-m64" Generate x64 64 bits object or executable.

"-c" Compile and assemble, but do not link.

"-D var[=value]" Define variable to be use by preprocessor, and optionnally affect an value at this variable.

"-o " Place the output into .

"-I " Add directory to search include files.

"-L " Add directory to search library files.

"-shared" Create a shared library.

"-llibrary" Give name of library used by linker.

"-pthread" Link with the POSIX threads library.

"-Wl," Pass comma-separated on to the linker. Example of options :

-t trace all input files used by linker

--kill-at not add the function name decorations at-sign and number for stdcall functions

- add-stdcall-alias export functions with the stdcall decoration suffix (@nn) and also without this suffix
- dll create DLL on Win32 systems
- export-all-symbols all global symbols in the objects used to build a DLL will be exported by the DLL
- output-def file create a def file of all exported symbols
- out-implib file create a import library in parallel of creation of shared library
- subsystem ident create target based on "ident" that can be valued by "native, windows, console, posix, or xbox"

You can consult an summary of these options on site :

<https://gcc.gnu.org/onlinedocs/gcc/Option-Summary.html>

And for "ld" (linker of gcc), you can consult too : <http://sourceware.org/binutils/docs-2.16/ld/Options.html>