



Moving a metadata volume in MetroCluster configurations

ONTAP MetroCluster

netapp-ivanad, ntap-bmegan
April 12, 2021

Table of Contents

Moving a metadata volume in MetroCluster configurations 1

Moving a metadata volume in MetroCluster configurations

You can move a metadata volume from one aggregate to another aggregate in a MetroCluster configuration. You might want to move a metadata volume when the source aggregate is decommissioned or unmirrored, or for other reasons that make the aggregate ineligible.

- You must have cluster administrator privileges to perform this task.
- The target aggregate must be mirrored and should not be in the degraded state.
- The available space in the target aggregate must be larger than the metadata volume that you are moving.

Steps

1. Set the privilege level to advanced:

```
set -privilege advanced
```

2. Identify the metadata volume that should be moved:

```
volume show MDV_CRS*
```

```

Cluster_A::*> volume show MDV_CRS*
Vserver    Volume                Aggregate      State      Type      Size
Available  Used%
-----
Cluster_A
MDV_CRS_14c00d4ac9f311e7922800a0984395f1_A
Node_A_1_aggr1
online     RW        10GB
9.50GB     5%
Cluster_A
MDV_CRS_14c00d4ac9f311e7922800a0984395f1_B
Node_A_2_aggr1
online     RW        10GB
9.50GB     5%
Cluster_A
MDV_CRS_15035e66c9f311e7902700a098439625_A
Node_B_1_aggr1
-          RW        -
-          -
Cluster_A
MDV_CRS_15035e66c9f311e7902700a098439625_B
Node_B_2_aggr1
-          RW        -
-          -
4 entries were displayed.

Cluster_A::>

```

3. Identify an eligible target aggregate:

metrocluster check config-replication show-aggregate-eligibility

The following command identifies the aggregates in cluster_A that are eligible to host metadata volumes:

```
Cluster_A::*> metrocluster check config-replication show-aggregate-eligibility
```

```
Aggregate Hosted Config Replication Vols Host Addl Vols Comments
-----
Node_A_1_aggr0 - false Root Aggregate
Node_A_2_aggr0 - false Root Aggregate
Node_A_1_aggr1 MDV_CRS_1bc7134a5ddf11e3b63f123478563412_A true -
Node_A_2_aggr1 MDV_CRS_1bc7134a5ddf11e3b63f123478563412_B true -
Node_A_1_aggr2 - true
Node_A_2_aggr2 - true
Node_A_1_Aggr3 - false Unable to determine available space of aggregate
Node_A_1_aggr5 - false Unable to determine mirror configuration
Node_A_2_aggr6 - false Mirror configuration does not match requirement
Node_B_1_aggr4 - false NonLocal Aggregate
```



In the previous example, Node_A_1_aggr2 and Node_A_2_aggr2 are eligible.

4. Start the volume move operation:

```
volume move start -vserver svm_name -volume metadata_volume_name -destination  
-aggregate destination_aggregate_name
```

The following command moves metadata volume MDV_CRS_14c00d4ac9f311e7922800a0984395f1 from aggregate Node_A_1_aggr1 to aggregate Node_A_1_aggr2:

```
Cluster_A::*> volume move start -vserver svm_cluster_A -volume  
MDV_CRS_14c00d4ac9f311e7922800a0984395f1  
-destination-aggregate aggr_cluster_A_02_01  
  
Warning: You are about to modify the system volume  
"MDV_CRS_9da04864ca6011e7b82e0050568be9fe_A". This may cause  
severe  
performance or stability problems. Do not proceed unless  
directed to  
do so by support. Do you want to proceed? {y|n}: y  
[Job 109] Job is queued: Move  
"MDV_CRS_9da04864ca6011e7b82e0050568be9fe_A" in Vserver  
"svm_cluster_A" to aggregate "aggr_cluster_A_02_01".  
Use the "volume move show -vserver svm_cluster_A -volume  
MDV_CRS_9da04864ca6011e7b82e0050568be9fe_A" command to view the status  
of this operation.
```

5. Verify the state of the volume move operation:

```
volume move show -volume vol_constituent_name
```

6. Return to the admin privilege level:

```
set -privilege admin
```

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.