

z/OS
2.5

MVS Installation Exits



Note

Before using this information and the product it supports, read the information in [“Notices” on page 379](#).

This edition applies to Version 2 Release 5 of z/OS® (5650-ZOS) and to all subsequent releases and modifications until otherwise indicated in new editions.

Last updated: 2022-06-28

© **Copyright International Business Machines Corporation 1988, 2022.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Figures.....	ix
Tables.....	xi
About this document.....	xiii
Who should use this document.....	xiii
How to use this document.....	xiii
How each exit is organized.....	xiii
Where to find more information.....	xiv
How to send your comments to IBM.....	xv
If you have a technical problem.....	xv
Summary of changes.....	xvii
Summary of changes for z/OS MVS Installation Exits for Version 2 Release 5 (V2R5).....	xvii
Summary of changes for z/OS Version 2 Release 4 (V2R4).....	xviii
Summary of changes for z/OS Version 2 Release 3.....	xix
Part 1. Introduction.....	1
Chapter 1. All About Exit Routines.....	3
Assembling Installation Exit Routines.....	3
Link editing an Installation Exit Routine into a Library.....	3
Programming Considerations for Installation Exit Routines.....	4
Dynamic Exits Facility.....	4
Link editing a Dynamic Exit Routine into a Library.....	5
Replacing a Dynamic Exit Routine.....	6
Providing Security for Dynamic Exits.....	6
Part 2. The Exits.....	9
Chapter 2. ASREXIT — SYMREC Authorization Exit.....	11
Chapter 3. CNZ_MSGTOSYSLOG — Message To Syslog Exit.....	15
Chapter 4. CNZ_MSIEXIT — Master Scheduler Initialization Dynamic Exit.....	21
Chapter 5. CNZ_WTOMDBEXIT — WTO Message Data Block Exit.....	23
Chapter 6. CSVLLIX1 — LLA Module Fetch Exit.....	29
Chapter 7. CSVLLIX2 — LLA Module Staging Exit.....	33
Chapter 8. DLF Connect / Disconnect Exit.....	39
Installing the Exit Routine.....	40
Exit Routine Environment.....	40
Exit Routine Functions.....	41
Exit Routine Processing.....	42
Programming Considerations.....	42

Entry Specifications.....	43
Return Specifications.....	43
Coded example of the exit routine.....	44
Chapter 9. HIS.SERVSTAT— HISSERV Service Exit.....	45
Chapter 10. ICHRTX00 — MVS Router Exit.....	49
Chapter 11. IEALIMIT — User Region Size Limit Exit.....	55
Chapter 12. IEAVADFM — Format SNAP, SYSABEND, and SYSUDUMP Dumps.....	59
Chapter 13. IEAVADUS — Select and Format Dump Data Exit.....	65
Chapter 14. IEAVMXIT — Installation-Specified MPF Exits.....	69
Chapter 15. IEAVTABX — Change Options / Suppress Dump Exit.....	79
Chapter 16. IEAVTABX_EXIT — ABDUMP Change Options / Suppress Dump Exit.....	85
Chapter 17. IEAVTSEL — Post Dump Exit Name List Exit.....	89
Chapter 18. IEF_ALLC_OFFLN — Allocated or Offline Device Installation Exit.....	97
Chapter 19. IEF_ALLC_EVENT — Allocation Event Installation Exit.....	107
Chapter 20. IEF_ALLC_MOD — Allocation Modify DDname Installation Exit.....	111
Chapter 21. IEF_ALLC_UNLOAD — Allocation Event Installation Exit.....	115
Chapter 22. IEF_SPEC_WAIT — Specific Waits Installation Exit.....	119
Chapter 23. IEF_VOLUME_ENQ — Volume ENQ Installation Exit.....	125
Chapter 24. IEF_VOLUME_MNT — Volume Mount Installation Exit.....	129
Chapter 25. IEFACTRT — SMF Job and Job Step Termination Exits.....	133
Chapter 26. IEFDB401 — Dynamic Allocation Input Validation Routine Exit.....	147
Chapter 27. IEFDOIXT — Edit / Check A Caller's Dynamic Output Text Units Exit.....	155
Chapter 28. IEFJFRQ — Subsystem Function Request Exit.....	161
Chapter 29. IEFUAV — User Account Validation Exit.....	167
Chapter 30. IEFUJI — Job Initiation Exit.....	175
Chapter 31. IEFUJP — Job Purge Exit.....	181
Chapter 32. IEFUJV — Job Validation Exit.....	185
Chapter 33. IEFUSI — Step Initiation Exit.....	193
Chapter 34. IEFUSO — SYSOUT Limit Exit.....	205
Chapter 35. IEFUTL — Time Limit Exit.....	209

Chapter 36. IEFU29 — SMF Dump Exit.....	215
Chapter 37. IEFU29L — SMF Log Stream Dump Exit.....	219
Chapter 38. IEFU83 — SMF Record Exit.....	223
Chapter 39. IEFU84 — SMF Record Exit.....	227
Chapter 40. IEFU85 — SMF Record Exit.....	233
Chapter 41. IEFU86 — SMF record exit.....	239
Chapter 42. IFASMF DL and IFASMF DP — SMF Dump Program Exits.....	245
Chapter 43. Global Resource Serialization Exits.....	247
System Programmer or Authorized Exits.....	247
ISGNQXITFAST — Fast ISGENQ / ENQ / DEQ Installation Exit	247
ISGNQXIT — ISGENQ / ENQ / DEQ Installation Exit.....	250
ISGCNFXITSYSTEM — Filter Global Resource Serialization Contention Notification, SYSTEM Scope.....	252
ISGCNFXITSYSPLEX — Filter Global Resource Serialization Contention Notification, SYSTEMS Scope.....	254
Authorized Exits.....	256
ISGDGRSRES — Display Global Resource Serialization Resource Exit.....	256
Authorized Exits for Alternate Serialization Products.....	258
ISGNQXITPREBATCH — ISGENQ / ENQ / DEQ Batch Preprocessing Exit.....	258
ISGNQXITBATCH— ISGENQ / ENQ / DEQ Batched Exit ISGNQXITBATCHCND — ISGENQ / ENQ / DEQ Conditional Batch Processing Exit.....	260
ISGNQXITQUEUED1 — ISGENQ / ENQ / DEQ First Queued Exit.....	264
ISGNQXITQUEUED2 — ISGENQ / ENQ / DEQ Second Queued Exit.....	266
ISGENDOFLQCB — End of Local QCB Exit.....	268
Chapter 44. IXC_ELEM_RESTART — Element Restart Exit.....	271
Chapter 45. IXC_WORK_RESTART — Workload Restart Exit.....	277
Chapter 46. Log Stream Subsystem Exit (IXGSEXIT, For Example).....	285
Chapter 47. MVS Commands Installation Exit.....	295
Chapter 48. MVS Message Service (MMS) Exits.....	305
Part 3. Installation Exit Directory.....	313
Chapter 49. BCP Exits.....	315
Chapter 50. DFSMS Exits.....	317
Chapter 51. IPCS Exits.....	319
Chapter 52. JES2 Exits.....	321
Chapter 53. JES3 Exits.....	323
Chapter 54. RACF Exits.....	325

Chapter 55. RMF Exits.....	327
Chapter 56. TSO/E Exits.....	329
Chapter 57. VTAM® Exits.....	333
Part 4. MVS Converter / Interpreter Text Processing.....	335
Chapter 58. Issuing Messages through JES Installation Exits.....	337
Chapter 59. Converter / Interpreter (C/I) Text Strings.....	339
Prefix Information.....	339
Keyword Information.....	339
End-of-text Information.....	339
Chapter 60. Converter / Interpreter Text String Formats.....	341
Prefix Format.....	341
JOB String Prefix.....	341
EXEC String Prefix.....	342
DD String Prefix.....	343
JDT String Prefix.....	343
Extended Statement Type String Prefix.....	344
Positional Format.....	344
JOB String Positional Parameters.....	344
EXEC String Positional Parameters.....	345
DD String Positional Parameters.....	345
Text Format for JDT-defined JCL.....	345
Extended Statement Type String Positional Parameters.....	347
Key Entry Format Examples.....	348
Referral Type Data.....	348
Data Set Name with Member Name.....	348
Overrides of Parameters.....	349
End-of-text Format.....	349
Examples of MVS/CI Text Strings.....	350
User References.....	350
Chapter 61. Modifying Converter / Interpreter Text.....	351
Part 5. Testing SMF Exit Routines.....	353
Chapter 62. TESTEXIT Exit Routine Requirements.....	355
Obtaining TESTEXIT from SYS1.SAMPLIB.....	356
Modifying the TESTEXIT Procedure.....	356
Part 6. SMF Exit — System Interface Diagrams.....	361
Appendix A. Accessibility.....	377
Notices.....	379
Terms and conditions for product documentation.....	380
IBM Online Privacy Statement.....	381
Policy for unsupported hardware.....	381
Minimum supported hardware.....	381
Programming Interface Information.....	382
Trademarks.....	382

Index.....	383
-------------------	------------

Figures

1. Example: Link editing an installation exit routine.....	3
2. CNZ_WTOMDBEXIT input parameter structure.....	25
3. RACROUTE macro invokes the MVS router.....	50
4. Example: IEALIMIT exit routine.....	58
5. Writing Job Log Messages from IEFACTRT.....	136
6. Example: make an IEFACTRT installation exit routine available.....	136
7. IEFACTRT Input Parameter Structure.....	140
8. Examples of Accounting Information.....	143
9. Example.....	144
10. Example.....	144
11. Example.....	144
12. IEFDB401 Input Parameter Structure.....	150
13. IEFDOIXT Input Parameter Structure.....	158
14. IEFUAV Input Parameter Structure.....	172
15. IEFUJI Input Parameter Structure.....	178
16. IEFUJP Input Parameter Structure.....	183
17. IEFUJV Input Parameter Structure.....	191
18. IEFUSI Input Parameter Structure.....	201
19. IEFUSO Input Parameter Structure.....	207
20. IEFUTL Input Parameter Structure.....	213
21. IEFU29 Input Parameter Structure.....	217
22. IEFU29L Input Parameter Structure.....	221
23. IEFU83 Input Parameter Structure.....	226

24. IEFU84 Input Parameter Structure.....	230
25. IEFU85 Input Parameter Structure.....	236
26. TESTEXIT Input/Output and Control Flow.....	353
27. SMFWTM Macro Definition Required for Using TESTEXIT.....	355
28. Sample JCL for Entering User-Written Exit Routines into EXITLIB.....	356
29. Sample JCL for Obtaining a Punched Deck of TESTEXIT.....	356
30. IEFUJV — Job Validation Exit (Converter).....	362
31. IEFUJV — Job Validation Exit (Interpreter).....	363
32. IEFUJI — Job Initiation Exit and IEFUSI — Step Initiation Exit.....	364
33. IEFUTL — Time Limit Exit.....	365
34. IEFUSO — JES2 SYSOUT Limit Exit.....	366
35. IEFUSO — JES3 SYSOUT Limit Exit.....	367
36. IEFU83 — SMF Record Exit.....	368
37. IEFU84 — SMF Record Exit.....	369
38. IEFU85 — SMF Record Exit.....	370
39. IEFU86 — SMF Record Exit.....	371
40. IEFACTRT — Termination Exit Part 1 of 2.....	372
41. IEFACTRT — Termination Exit Part 2 of 2.....	373
42. IEFUJP — JES2 Job Purge Exit.....	374
43. IEFUJP — JES3 Job Purge Exit.....	375

Tables

1. IEALIMIT Default Values.....	56
2. Values Passed to ADPLESRV.....	67
3. Common Exit Parameter Area.....	141
4. Format of Accounting Information.....	142
5. IEFU86 input parameter structure.....	242
6. IEFU86 work area.....	242
7. Environmental factors for the log stream subsystem exit routine.....	287
8. Setting Up the Common Data Area.....	299
9. IFASMF DL and IFASMF DP SMF Log stream and data set dump programs exits (USERx).....	315
10. BCP Exit (authorized assembler).....	315
11. BCP Exits (JES common coupling services).....	315
12. DFSMS Exits.....	317
13. IPCS Exits.....	319
14. JES2 Exits.....	321
15. JES3 Exits.....	323
16. RACF Exits.....	325
17. RACF Exit.....	325
18. RMF Exits.....	327
19. TSO/E Exits.....	329
20. VTAM Exits.....	333
21. Text Format for Long Parameters: Example 1.....	346
22. Text Format for Long Parameters: Example 2.....	346
23. Parameters and DD Statements for Executing TESTEXIT.....	359

About this document

This document supports z/OS (5650-ZOS). This document identifies and describes the installation exits that you can use to modify your MVS™ system.

Who should use this document

This document is intended for a systems programmer who wants to modify the processing of an MVS system. The document assumes that the reader can code in assembler language and read assembler, loader, and linkage editor output.

Although the documentation for the exits in this document follows a standard format, each exit has unique features and requirements that you need to know about. In general, the introductory section to each exit describes the exit's functions and the possible uses for the exit. The remaining sections point out specific considerations for coding the exit.

How to use this document

Because all of the exits perform the general function of modifying the existing code, you may find it helpful to read Section 1 to develop a general idea of what an exit is and how it functions as a part of the MVS system.

Once you have determined the type of modification you want to make to your system, you might follow these general steps when using the document:

- Use the table of contents to locate the exit that might fit your needs.
- Turn to the description of the exit and use the introductory section, which provides a description of the exit routine and its possible uses, to determine if the exit routine can meet your needs.
- Use the detailed information to design, code, and install your installation exit routine.

How each exit is organized

The exit routines in this document follow a format to allow you to locate information about the exit routine you are coding. The list that follows describes how each exit can be organized. However, some of these topics may not apply to every exit, such as I/O restrictions. A topic that does not apply to the exit is not discussed for that exit.

- Exit routine name and description.
- Introductory material, which describes the function of the exit routine and lists possible uses for the routine.
- Installing the exit.
- Exit routine environment, which contains specific environmental considerations that you need to know, such as the address space that the exit runs in, the AMODE and RMODE for the exit, and locks or ENQs that the exit routine might hold when it gets control.
- Exit recovery environment, which describes the type of recovery environment for the exit routine.
- Processing.
- Programming considerations.
- Macro instructions and restrictions, which contain specific macro requirements or restrictions that you must keep in mind when coding the exit routine.
- I/O restrictions.
- Entry specifications, which includes a list of the register contents when the exit routine receives control and, when applicable, describes any related parameter lists for the exit routine.

- Return specifications, which lists the register contents expected when the exit routine returns control to the calling program.
- Coded example of the exit.

Where to find more information

Where necessary, this document references information in other documents, using shortened versions of the document title. For complete titles and order numbers of the documents for all products that are part of z/OS, see [*z/OS Information Roadmap*](#).

How to send your comments to IBM

We invite you to submit comments about the z/OS product documentation. Your valuable feedback helps to ensure accurate and high-quality information.

Important: If your comment regards a technical question or problem, see instead [“If you have a technical problem”](#) on page xv.

Submit your feedback by using the appropriate method for your type of comment or question:

Feedback on z/OS function

If your comment or question is about z/OS itself, submit a request through the [IBM RFE Community](#) (www.ibm.com/developerworks/rfe/).

Feedback on IBM® Documentation function

If your comment or question is about the IBM Documentation functionality, for example search capabilities or how to arrange the browser view, send a detailed email to IBM Documentation Support at ibmdocs@us.ibm.com.

Feedback on the z/OS product documentation and content

If your comment is about the information that is provided in the z/OS product documentation library, send a detailed email to mhvrcfs@us.ibm.com. We welcome any feedback that you have, including comments on the clarity, accuracy, or completeness of the information.

To help us better process your submission, include the following information:

- Your name, company/university/institution name, and email address
- The following deliverable title and order number: z/OS MVS Installation Exits, SA23-1381-50
- The section title of the specific information to which your comment relates
- The text of your comment.

When you send comments to IBM, you grant IBM a nonexclusive authority to use or distribute the comments in any way appropriate without incurring any obligation to you.

IBM or any other organizations use the personal information that you supply to contact you only about the issues that you submit.

If you have a technical problem

If you have a technical problem or question, do not use the feedback methods that are provided for sending documentation comments. Instead, take one or more of the following actions:

- Go to the [IBM Support Portal](#) (support.ibm.com).
- Contact your IBM service representative.
- Call IBM technical support.

Summary of changes

This information includes terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations for the current edition are indicated by a vertical line to the left of the change.

Note: IBM z/OS policy for the integration of service information into the z/OS product documentation library is documented on the z/OS Internet Library under [IBM z/OS Product Documentation Update Policy \(www-01.ibm.com/servers/resourcelink/svc00100.nsf/pages/ibm-zos-doc-update-policy?OpenDocument\)](http://www-01.ibm.com/servers/resourcelink/svc00100.nsf/pages/ibm-zos-doc-update-policy?OpenDocument).

Summary of changes for z/OS MVS Installation Exits for Version 2 Release 5 (V2R5)

The following content is new, changed, or no longer included in V2R5.

New

The following content is new.

April 2022 refresh

- For APAR OA61850, Chapter 50, “DFSMS Exits,” on page 317 IFG_CLOSE_START, IFG_OPEN_START and IGG_STOW_START are added.

Prior to April 2022 refresh

- None

Changed

The following content is changed.

June 2022 refresh

- The entry specifications have been updated for the IEFU86 exit routine. See [“Entry specifications” on page 241](#).

April 2022 refresh

- RACF® Exits ICHFRX01 and ICHFRX02 have been renamed to ICHRFX01 and ICHRFX01. See [Chapter 54, “RACF Exits,” on page 325](#).
- In the "Controlling the Exit Routine Through the Dynamic Exits Facility" topic for several exits, the statement, "The exit should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAM keyword when defining the exit in PROGxx, as the system will not be able to load the exit when restarting SMF," has been updated to "The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAM keyword when adding the exit routine in PROGxx."

November 2021 refresh

- Information about exit recovery and recovery considerations is updated for clarity in [Chapter 41, “IEFU86 — SMF record exit,” on page 239](#).

Prior to November 2021 refresh

- None

Deleted

The following content was deleted.

- None

Summary of changes for z/OS Version 2 Release 4 (V2R4)

New

The following content is new:

June 2020 refresh

- IFASMF DL and IFASMF DP — SMF Dump Program Exits are new. For more information, see [Chapter 42, “IFASMF DL and IFASMF DP — SMF Dump Program Exits,”](#) on page 245.

Changed

The following content is changed:

May 2021 refresh

- IEFU29 exit example has been updated for clarity. For more information see, [“Coded Example of the Exit Routine”](#) on page 218.

April 2021 refresh

- The Exit routine environment section for the IEFU86 - SMF record exit is updated. For more information see, [“Exit routine environment”](#) on page 240.

December 2020 refresh

- Updates are made to the description of parameter word 5 of the IEFUSI exit. See [“Entry Specifications”](#) on page 196.
- Updates are made to the description of sub-word 4 of parameter word 7 of the IEFUSI exit. See [“Entry Specifications”](#) on page 196.

June 2020 refresh

- For BCP Exits, [Table 9 on page 315](#) is updated.
- The IEFUSI installation exit is updated in the parameter word 7, sub-word 3, for default and maximum values. For more information, see [Chapter 33, “IEFUSI — Step Initiation Exit,”](#) on page 193.

Prior to June 2020 refresh

- The IEFACTRT installation exit is updated to add the parameter word 14. For more information, see [Chapter 25, “IEFACTRT — SMF Job and Job Step Termination Exits,”](#) on page 133.

Deleted

The following content is deleted:

May 2021 refresh

- Removed erroneous text reference to IEFU29L SYS1.SAMPLIB example exit because IBM does not currently provide this sample exit. For more information see, [“Coded Example of the Exit Routine”](#) on page 222.

June 2020 refresh

- Note removed from sub-word 4 of IEFUSI Word 7 due to MVS no longer using ESQA to manage 31-bit shared storage.

Summary of changes for z/OS Version 2 Release 3

The following information is new, changed, or deleted in z/OS Version 2 Release 3 (V2R3).

New

The following information has been added:

- For APAR OA54790, information about the LOGON command is added in [“Programming Considerations” on page 298](#) in [Chapter 47, “MVS Commands Installation Exit,” on page 295](#).
- For APAR OA51174, information on the log stream subsystem exit is added in [“Installing the Exit Routine” on page 286](#).
- Information is updated in [Chapter 25, “IEFACTRT — SMF Job and Job Step Termination Exits,” on page 133](#).
- This statement is added to several exits: "The exit should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNNAME keyword when defining the exit in PROGxx, as the system will not be able to load the exit when restarting SMF." The exits updated include:
 - IEFACTRT
 - IEFUAV
 - IEFUJI
 - IEFUJP
 - IEFUJV
 - IEFUSI
 - IEFUSO
 - IEFUTL
 - IEFU29
 - IEFU29L
 - IEFU84
 - IEFU85
 - IEFU86
- New SMF IEFU86 record exit section added labeled [Chapter 41, “IEFU86 — SMF record exit,” on page 239](#).
- New sub-section added for selecting an eligible tape library device based on device priority. See [Chapter 18, “IEF_ALLC_OFFLN — Allocated or Offline Device Installation Exit,” on page 97](#) for more information.

Part 1. Introduction

In certain areas of processing, your installation might need to customize its MVS system to an extent not available through standard options, such as initialization parameters and operator commands. IBM provides installation exit points for this purpose.

There are installation exit points located throughout the MVS system code. When an exit is invoked, the system passes control to an IBM-supplied routine that might or might not perform actual processing. When you provide an exit routine, control passes to that routine, which does its special processing. At the end of the user routine, control returns to a specified point in the system code.

Chapter 1. All About Exit Routines

The following section contain introductory information about installation exit routines. To start, it is helpful to review the following terminology.

- **Installation Exit Point.** An installation exit point is a specific point in component processing at which control passes to an installation exit routine. The macro that calls the user routine uses parameter values from keywords supplied at the initialization of the component. In most cases, the initialization statement defaults are set to cause the exit point to be ignored. However, you can modify macro processing by specifying parameters supplied with operator commands.
- **Replaceable Module.** A replaceable module is a load module that the user installation can update, alter, or completely replace. Some replaceable modules are IBM-supplied code that performs a specific function, while others simply branch directly back to the calling program without any additional processing. When you write your exit routine, you replace the IBM-supplied routine with your own. Both the name of the routine and its library location are predefined.
- **Installation Exit Name List.** An installation exit name list is similar to an installation exit point. However, rather than directly calling the installation exit routine, the macro addresses a CSECT that contains a list of installation exit routine names. The installation exit routines are then invoked sequentially as they appear in the name list. This processing ends in one of two ways:
 - One of the installation exit routines issues a terminating return code.
 - The end of the name list is reached.

Your installation provides the routine names by updating, reassembling, and again link editing the name list CSECT. (It is possible to update the CSECT temporarily using SPZAP. See [z/OS MVS Diagnosis: Tools and Service Aids](#) for more information on SPZAP.)

If you provide no exit routines, the name list contains blank entries.

In both the installation exit point and installation exit name list methods, the installation defines the installation exit routine names.

- **Dynamic Exit.** A user-written or system exit that has been defined to the dynamic exits facility. See [“Dynamic Exits Facility” on page 4](#) for more information.

Assembling Installation Exit Routines

To ensure all necessary macros are resolved during assembly of your exit routines, use the same SYSLIB concatenation as your SMP procedure or SYSLIB DDDEF statement.

Link editing an Installation Exit Routine into a Library

For information about link editing a dynamic exit routine, see [“Link editing a Dynamic Exit Routine into a Library” on page 5](#).

The example in [Figure 1 on page 3](#) shows how to make an installation exit routine available to the system by link editing it into a system library.

```
//LKUSRPGM      JOB      MSGLEVEL=(1,1)
//              EXEC      PGM=IEWL,PARM='XREF,LET,LIST,NCAL'
//SYSPRINT      DD      SYSOUT=A
//SYSUT1        DD      UNIT=SYSDA,SPACE=(TRK,10)
//SYSLMOD       DD      DSN=SYS1.LINKLIB,DISP=SHR
//SYSLIN        DD      *
               object deck
               NAME      EXITNAME(R)
/*
```

Figure 1. Example: Link editing an installation exit routine

EXEC Statement: invokes the linkage editor and requests maximum diagnostic listing. For a description of module attributes that you can assign to your routine, see [z/OS MVS Program Management: Advanced Facilities](#).

SYSPRINT DD Statement: defines the message data set.

SYSLMOD DD Statement: defines the output data set, in this case the link library, SYS1.LINKLIB. The output data set can also be a permanent library to be referenced by a JOBLIB or STEPLIB DD statement; in that case, the SYSLMOD DD statement could be coded as follows:

```
//SYSLMOD DD DSN=MYLIB,UNIT=3380,VOL=SER=666666,  
// DISP=(NEW,KEEP),SPACE=(1024,(20,2,1))
```

SYSLIN DD Statement: defines the input data set, in this example the object code for the user program.

NAME Control Statement: specifies the member name, and thus the program name, to be assigned to the user program. In this example, the member name is EXITNAME.

Programming Considerations for Installation Exit Routines

Each MVS component has individual programming conventions. Components that have similar functions have similar requirements. Most requirements, however, are unique. Because of these differences among component requirements, we cannot provide universal rules for coding installation exit routines. The specific guidelines we can give are:

- Whenever a macro is provided to perform a service, use the macro.
- Upon entry to your exit routine, save all register contents and restore them before returning to your calling routine. An exception to this guideline is the use of return and reason codes. In many cases, you must insert a return code in register 15, and reason codes in registers 0 and 1 before returning to the calling program.
- Under no circumstances should you assume an interface (such as contents of a register) that is not specifically documented.
- **Exits That Use a z/OS UNIX Callable Service:** Any exit that uses a z/OS UNIX callable service needs to be written based on the current environment. If the task is not dubbed on entry to the exit (STCBOTCB=0), the exit must undub (perform a CALL BPX1MPC) at completion if the exit has called any other z/OS UNIX callable service. If the task is already dubbed (STCBOTCB does not equal 0), the exit should leave the environment as it was on entry, which would require closing any files that it opens and leaving signal states unchanged.

Dynamic Exits Facility

The dynamic exits facility is a set of services that you can use through any of the following methods:

- The EXIT statement of the PROGxx parmlib member. The EXIT statement allows an installation to add exit routines to an exit, change the state of an exit routine, delete an exit routine for an exit, undefine an implicitly defined exit, and change the attributes of an exit.

The PROGxx EXIT statement interacts with the PROG=xx parameter of IEASYSxx and the SET PROG=xx command. At IPL, operators can use PROG=xx to specify the particular PROGxx parmlib member the system is to use. During normal processing, operators can use the SET PROG=xx command to set a current PROGxx parmlib member. See [z/OS MVS Initialization and Tuning Reference](#) for information about the PROGxx parmlib member.

- The SETPROG EXIT operator command. This command performs the same functions as the EXIT statement of the PROGxx parmlib member. See [z/OS MVS System Commands](#) for information about the SETPROG EXIT command.
- The CSVDYNEX macro. The CSVDYNEX macro can be used to define exits to the dynamic exits facility, control their use within a program, and associate one or more exit routines with those exits. It can also be used to associate exit routines with the existing SMF and allocation exits, which have been defined to the dynamic exits facility. The CSVDYNEX macro provides a superset of the functions available through

the SETPROG EXIT operator command and the EXIT statement of the PROGxx parmlib member. See *z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN* for information about the CSVDYNEX macro.

An installation can use any of these methods to control dynamic exits. For example, an exit routine can be associated with an exit using the CSVDYNEX ADD request, the SETPROG EXIT,ADD operator command, or the EXIT statement of PROGxx.

The following exits have been defined to the dynamic exits facility:

- ABDUMP exit:
 - IEAVTABX_EXIT - ABDUMP Change Options / | Suppress Dump Exit
- Allocation exits:
 - IEF_ALLC_OFFLN— Allocated/Offline Device Installation Exit
 - IEFDB401— Allocation Input Validation Routine
 - IEF_SPEC_WAIT— Specific Waits Installation Exit
 - IEF_VOLUME_ENQ— Volume ENQ Installation Exit
 - IEF_VOLUME_MNT— Volume Mount Installation Exit
- Automatic restart management exits:
 - IXC_ELEM_RESTART— Element Restart Exit
 - IXC_WORK_RESTART— Workload Restart Exit
- SMF exits:
 - IEFACTRT— SMF Job/Job Step Termination Exit
 - IEFUAV— User Account Validation Exit
 - IEFUJI— Job Initiation Exit
 - IEFUJP— Job Purge Exit
 - IEFUJV— Job Validation Exit
 - IEFUSI— Step Initiation Exit
 - IEFUSO— SYSOUT Limit Exit
 - IEFUTL— Time Limit Exit
 - IEFU29— SMF Dump Exit
 - IEFU83— SMF Record Exit
 - IEFU84— SMF Record Exit
 - IEFU85— SMF Record Exit
- Subsystem interface (SSI) exit:
 - IEFJFRQ— Subsystem Function Request Exit
- SVC dump (SDUMP) exits:
 - [IEASDUMP.QUERY](#)
 - [IEASDUMP.GLOBAL](#) and [IEASDUMP.LOCAL](#)
 - [IEASDUMP.SERVER](#)

Link editing a Dynamic Exit Routine into a Library

You can link edit a dynamic exit routine into a library by:

- Link editing it into a data set that is made part of the PLPA, MLPA, or FLPA at IPL-time
- Link editing it into a data set that is part of the LNKLIST concatenation
- Link editing it into IEANUC0x

- Link editing it into any PDS/PDSE and naming that data set using the DSNNAME option of:
 - The SETPROG EXIT command
 - The EXIT ADD statement of a PROGxx parmlib member
 - The ADD request of the CSVDYNEX macro.

Replacing a Dynamic Exit Routine

There are two ways to replace a dynamic exit routine:

1. You can delete the current exit routine and add a replacement routine that uses either the same or another name, or
2. You can change the state of the current routine to "inactive" and then later change it back to "active."

You can use any of the following methods to accomplish the replacement:

- Use the CSVDYNEX macro.
- Use the SETPROG EXIT command.
- Use the SET PROG= command with new or modified EXIT statements in a PROGxx parmlib member.
- Use the PROG= system parameter with new or modified EXIT statements in a PROGxx parmlib member when you re-IPL.

You will make the most efficient use of storage if an exit routine that is associated with more than one exit resides in the LPA. However, it is easier to replace a dynamic exit routine that does not reside in the LPA.

If you are replacing an exit routine that *is* in the LPA, observe these two cautions so that the system does not find and use the original (unchanged) copy of the module in the LPA:

1. Use the DSNNAME parameter of the ADD statement to specify the library into which you have placed the modified load module.
2. Do not use the method that changes the state of the exit routine to inactive and then back to active, unless you use the dynamic LPA function to add or replace the modified exit module to the system.

Providing Security for Dynamic Exits

An installation can control access to programs that create and call dynamic exits by authorizing specific users or groups of users to issue the various CSVDYNEX requests.

The exit services tables contain lists of exits with associated exit routines. To protect the exit services tables, set up RACF FACILITY resource class profiles that protect the following entities:

- CSVDYNEX.exitname.DEFINE
- CSVDYNEX.exitname.modname
- CSVDYNEX.exitname.UNDEFINE
- CSVDYNEX.exitname.ATTRIB
- CSVDYNEX.LIST
- CSVDYNEX.exitname.CALL
- CSVDYNEX.exitname.RECOVER
- Grant UPDATE authority to CSVDYNEX.exitname.DEFINE to users who are authorized to define dynamic exits (CSVDYNEX DEFINE request).
- Grant UPDATE authority to CSVDYNEX.exitname.modname to users who are authorized to add, delete, or modify exit routines for dynamic exits (CSVDYNEX ADD, REPLACE, MODIFY, and DELETE requests).
- Grant UPDATE authority to CSVDYNEX.exitname.UNDEFINE to users who are authorized to remove the definition of a dynamic exit (CSVDYNEX UNDEFINE request).
- Grant UPDATE authority to CSVDYNEX.exitname.ATTRIB to users who are authorized to change the attributes of dynamic exits (CSVDYNEX ATTRIB request).

- Grant READ authority to CSVDYNEX.LIST to users who are authorized to list information about dynamic exits (CSVDYNEX LIST request).
- Grant READ authority to CSVDYNEX.exitname.CALL to users who are authorized to call exit routines for dynamic exits (CSVDYNEX CALL FASTPATH=NO request).
- Grant READ authority to CSVDYNEX.exitname.RECOVER to users who are authorized to provide recovery for exit routines associated with dynamic exits (CSVDYNEX RECOVER request).

The SET PROG= and SETPROG commands are restricted to consoles with SYS authority. The DISPLAY PROG command can be issued on any console with INFO or higher authority. You can prevent operators from issuing particular requests by setting up the RACF profiles listed above for the ADD, MODIFY, DELETE, and ATTRIB requests.

Part 2. The Exits

The installation exits described in this section of the document are functions supported in the MVS base control program (BCP) code. The remaining installation exit functions found in various MVS components and related products are listed in [Part 3, “Installation Exit Directory,” on page 313](#).

Chapter 2. ASREXIT – SYMREC Authorization Exit

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routine” on page 11](#)
- [“Exit Routine Environment” on page 11](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 12](#)
- [“Programming Considerations” on page 13](#)
- [“Entry Specifications” on page 13](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 13](#)
 - Registers at Exit
- [“Coded Examples of the Exit Routine” on page 14](#)

To allow unauthorized programs to write symptom records to the logrec data set (or to a job log or to both) through the use of the SYMREC macro, the SYMREC authorization exit, ASREXIT, must be in effect.

IBM provides the following sample ASREXIT routines for your installation's use:

- ASREXT0 allows all unauthorized programs to write symptom records to the logrec recording medium.
- ASREXT1 allows only unauthorized programs *that reside in APF-authorized libraries* to write symptom records to the logrec recording medium.

If one of these IBM-supplied routines serves the needs of your installation, use it instead of coding your own routine (see [“Coded Examples of the Exit Routine” on page 14](#)). If you plan to code your own routine, ASREXT0 and ASREXT1 appear in SYS1.SAMPLIB. You can refer to them as examples when coding your routine.

You can use the ASREXIT interface to:

- Allow all or only particular unauthorized programs to write symptom records to the logrec recording medium.
- Cause unauthorized programs to write symptom records to a job log instead of, or in addition to, the logrec recording medium.

If you do not install the ASREXIT routine, MVS will not allow unauthorized programs to write symptom records to the logrec recording medium.

For information on the SYMREC macro, see [z/OS MVS Programming: Assembler Services Guide](#).

Installing the Exit Routine

The exit must be linkedited with the name ASREXIT into SYS1.LINKLIB or any library in the LNKLIST concatenation. To activate the exit routine, refresh LLA through the F LLA,REFRESH command.

For general instructions on installing an exit routine, see [“Link editing an Installation Exit Routine into a Library” on page 3](#).

Exit Routine Environment

ASREXIT receives control running under the unit of work that invoked the SYMREC service, in the following environment:

- In supervisor state with PSW key 0
- Enabled or disabled for interrupts
- AMODE 31 and RMODE ANY
- Primary=home address space of the unit of work that issues the SYMREC request.
- SRB or task mode. PSATOLD=0 means SRB mode, and nonzero means task mode.

Note: Whether the exit routine receives control in task or SRB mode is dependent on the unit of work that issues the SYMREC request.

Exit Recovery: ASREXIT should provide its own recovery.

If ASREXIT does not provide a recovery routine, or if an exit routine error percolates beyond the exit's recovery, the system's ESTAEX recovery routine will get control. The ESTAEX will record information in the SDWA and request an SDUMP.

If ASREXIT abends, the system will not allow the symptom record to be written to the logrec recording medium. The exit will be invoked for the next unauthorized program that attempts to write symptom records.

Exit Routine Processing

When you install ASREXIT, the system will invoke the exit routine whenever an unauthorized program issues the SYMREC macro to write symptom records to the logrec recording medium. The system passes to the exit in register 1 the address of fullword, which contains an address of the SYMREC authorization exit parameter list (mapped by ASREPL). The SYMREC authorization exit parameter list contains the following:

- A program name
- The job step name
- The address of the symptom record
- An indication of whether the program originated from an APF-authorized library.

ASREXIT runs under an RB that issues a SYMREC request. The values of the program name and the APF-authorized library indication in the SYMREC authorization exit parameter list are not necessarily those of the RB that issued the SYMREC request. The system obtains the program name and the APF-authorized library indication from the MAJOR CDE pointed to by the oldest RB on the TCB RB chain. See *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for information on the CDE data area. Based on the program name and the authorized library indication, ASREXIT indicates (by placing a value in the EPLRETC field of the exit parameter list) whether to reject the request or allow the program to write the symptom record to:

- The logrec recording medium
- The job log
- Both the logrec recording medium and the job log.

If you code an ASREXIT routine, instead of installing one of the two IBM-supplied routines, you will probably use the routine to allow only **specific** unauthorized programs to write symptom records, or to cause unauthorized programs to write symptom records to their job log instead of, or in addition to, the logrec recording medium.

Using the Job Log: If you intend to restrict unauthorized programs from writing symptom records to the logrec recording medium, but still want to collect symptom records from unauthorized programs for debugging purposes, code the ASREXIT routine to cause unauthorized programs' symptom records to be written to their job log (by issuing WTOs with routing code 11). Application programmers can then view symptom records in the job log directly, rather than having the system programmer search the logrec recording medium for the symptom records.

If you do not install an ASREXIT routine, unauthorized programs cannot write symptom records to a job log.

Programming Considerations

Code the ASREXIT exit routine to be reentrant. A new copy of ASREXIT is loaded into storage from SYS1.LINKLIB for every request to write a SYMREC.

Entry Specifications

The system passes the address of the exit parameter list to ASREXIT.

Registers at Entry: The contents of the registers on entry to ASREXIT are as follows.

Register Contents

0	Not applicable
1	Pointer to the address of the exit parameter list
2-12	Not applicable
13	Register save area
14	Return address
15	Entry point address of the exit

Parameter List Contents: Register 1 contains a pointer to the address of the exit parameter list, the EPL. The EPL contains the program name, job step name, address of the symptom record, and an indication of whether the program resides in an APF-authorized library.

The EPL is mapped by the ASREPL macro (data area ASREPL), which resides in SYS1.MODGEN. See *z/OS MVS Data Areas* in the z/OS Internet library (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for a mapping of the ASREPL data area.

Return Specifications

ASREXIT indicates to the system whether to cancel the request or allow the symptom record to be written by placing one of the following values in the EPLRETC field of the EPL:

Value

Explanation

X'00'

Write the symptom record to the logrec recording medium

X'04'

Write the symptom record to **both** the logrec recording medium and to the job log

X'08'

Write the symptom record to the job log only

X'0C'

Do not write the symptom record. The system returns to the caller both a system return code (X'0C') and reason code (X'F1C') indicating that request was rejected for either of the following reasons:

- The exit routine rejected the request.
- The exit routine was not installed.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0,1

Not relevant

2-14

Restored to contents at entry

15

Not relevant

Coded Examples of the Exit Routine

IBM provides two SYMREC authorization exit routines for your installation's use, ASREXT0 and ASREXT1.

Use ASREXT0 to allow **all** unauthorized programs to write symptom records to the logrec recording medium. This exit routine always returns a value of X'00' (grant the request).

Use ASREXT1 to allow only unauthorized programs (that is, programs that were not linked with authorization code AC=1), that you have installed in an APF-authorized library to write symptom records to the logrec recording medium. When it is invoked, ASREXT1 checks to see whether the calling program resides in an APF-authorized library (the system sets the EPLAPFL bit to 1). If EPLAPFL is set to 1, ASREXT1 returns a value of X'00' (grant the request). Otherwise, ASREXT1 returns a value of X'0C' (reject the request).

ASREXT0 and ASREXT1 are provided in SYS1.SAMPLIB. To install either exit routine, you must link it with the name ASREXIT into SYS1.LINKLIB or any library in the LNKSTxx concatenation.

When you assemble ASREXT0 and ASREXT1, ensure SYS1.MODGEN is included in Assembler SYSLIB concatenation.

For more information on APF-authorized libraries, see [z/OS MVS Programming: Assembler Services Guide](#).

Chapter 3. CNZ_MSGTOSYSLOG – Message To Syslog Exit

Topics for This Exit Appear as Follows:

- [“Controlling the Exit Routine Through the Dynamic Exits Facilities” on page 15](#)
- [“Exit Routine Environment” on page 15](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 16](#)
- [“Programming Considerations” on page 16](#)
- [“Performance Considerations” on page 16](#)
- [“Entry Specifications” on page 17](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 17](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 17](#)

CNZ_MSGTOSYSLOG receives control from the system when a message is sent to the SYSLOG. Every message line that is sent to syslog will be passed to the exit routines active at the exit point. Multi-line messages will be presented as major line first, then major and each minor (one at a time). For example, a multi-line message with 1 major and 3 minor lines will result in the exit routines receiving control 4 times:

- 1st Time - For the major line
- 2nd Time - For the first minor line
- 3rd Time - For the second minor line
- 4th Time - For the last minor line

Code a CNZ_MSGTOSYSLOG exit routine when you want to view all messages being sent to the SYSLOG.

Controlling the Exit Routine Through the Dynamic Exits Facilities

IBM has defined the CNZ_MSGTOSYSLOG exit to the dynamic exits facility. You can refer to the exit by the name CNZ_MSGTOSYSLOG. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

1. The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error.
2. The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system disables the exit routine after one abend.

Exit Routine Environment

The exit receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 31.
- With no locks or ENQs held.
- In the CONSOLE address space.

Exit Recovery: The exit routine should NOT provide its own recovery. If recovery is necessary, set up an EUT functional recovery routine (FRR) instead of an ESTAE-type recovery routine. This will improve system performance by shortening the path length of the exit routine.

If the exit routine abnormally terminates, and the exit routine does not provide its own recovery, or the error percolates beyond the exit's recovery routine, a system recovery routine will get control.

Whether or not the exit routine continues to be invoked depends on theabend processing of the dynamic exits facility.

Exit Routine Processing

MVS invokes the CNZ_MSGTOSYSLOG exit routine every time a message is sent to the SYSLOG. If any CNZ_MSGTOSYSLOG routines are specified to the dynamic exits facility, a parameter list (mapped by macro CNZMYM2S) is passed that contains the following information about the message:

- Whether the message is a MLWTO
- Whether the message is for a minor line WQE
- Whether the message is the last line of a MLWTO
- Pointer to the single or major line WQE (Mapped by macro IHAWQE, data area WQE for single WQE and data area WMJM for major line WQE)
- Pointer to the current minor line WQE (or zero) (Mapped by macro IHAWQE, data area WMNM)

Note: Exactly one minor line is passed to the exit routine.

- Pointer to a 4K workarea that can be used by the exit (Each exit routine will share the same 4K workarea. It is up to the exit routine to initialize the workarea.)

Programming Considerations

Observe the following conventions when coding the CNZ_MSGTOSYSLOG exit routine:

- Code the exit routine to be reentrant.
- Do not code the exit routine to issue messages to the SYSLOG.

Performance Considerations

Message to syslog processing may impact performance; therefore, consider the following recommendations so that system performance is not degraded:

- Exit routines installed at the CNZ_MSGTOSYSLOG exit point should not perform operations that might degrade system performance, such as issuing WAIT requests, issuing requests for large amounts of dynamic storage, or issuing I/O requests. To reduce the need for storage requests, the system provides a 4K workarea that your exit routine can use for dynamic storage. The M2SL_WorkArea@ field in the CNZMYM2S parameter mapping points to the 4K workarea. The exit routine must clear the workarea before using it, because all exit routines installed at the CNZ_MSGTOSYSLOG exit point use the same workarea.
- The exit routine should NOT provide its own recovery. If recovery is necessary, set up an EUT functional recovery routine (FRR) instead of an ESTAE-type recovery routine. This will improve system performance by shortening the path length of the exit routine.

Entry Specifications

The system passes the address of the exit parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of a pointer to the exit parameter list

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of the exit

Parameter Descriptions: Register 1 contains the address of a pointer to the exit parameter list, the M2SL, which is mapped by macro CNZMYM2S.

Return Specifications

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-15

Restored to contents at entry

Coded Example of the Exit Routine

The following is an example of an CNZ_MSGTOSYSLOG exit:

```

      TITLE 'M2SLEXIT - SAMPLE MESSAGE TO SYSLOG EXIT'
***START OF SPECIFICATIONS*****
*
* MODULE NAME           = M2SLEXIT
*
* DESCRIPTIVE NAME      = SAMPLE MESSAGE TO SYSLOG EXIT.
*
* FUNCTION              = THIS EXIT WILL DEMONSTRATE HOW TO
*                        = PROCESS THE DATA IN THE PARAMETER
*                        = LIST.
*
* OPERATION             = IDENTIFIES THE MESSAGE LINE PASSED IN
*                        = THE PARAMETER LIST AND BRANCHES TO
*                        = THE APPROPRIATE SECTION TO PERFORM
*                        = PROCESSING BASED ON THE MESSAGE LINE.
*
* ENTRY POINT           = M2SLEXIT
*
* PURPOSE               = DEMONSTRATE HOW TO USE THIS EXIT.
*
* LINKAGE               = BALR
*
* INPUT DATA           = REG1  ADDRESS OF THE PARAMETER LIST
*                        = REG13 ADDRESS OF STANDARD SAVE AREA
*                        = REG14 RETURN ADDRESS
*                        = REG15 ENTRY POINT ADDRESS
*
* REGISTERS SAVED       = REG0 - REG15
*

```

CNZ_MSGTOSYSLOG – Message To Syslog Exit

```

* REGISTER USAGE      = REG0 - USED FOR BASING          *
*                     REG1 - PARAMETER REGISTER        *
*                     REG2 - WORK REGISTER              *
*                     REG3 - WORK REGISTER              *
*                     REG4 - WORK REGISTER              *
*                     REG5 - WORK REGISTER              *
*                     REG6 - POINTER TO PARAMETER LIST  *
*                     REG7 - NOT USED                   *
*                     REG8 - NOT USED                   *
*                     REG9 - NOT USED                   *
*                     REG10 - NOT USED                  *
*                     REG11 - POINTER TO 4K WORK AREA   *
*                     REG12 - MODULE BASE REGISTER     *
*                     REG13 - POINTER TO STANDARD SAVE AREA *
*                     REG14 - RETURN POINT              *
*                     REG15 - NOT USED                  *
*
* REGISTERS RESTORED = REG0 - REG14                    *
*
* CONTROL BLOCKS     =                                *
*   NAME      MAPPING MACRO   REASON USED             USAGE      *
*   ----      - - - - -      - - - - -      - - - - -      *
*   M2SL      CNZMYM2S        EXIT PARAMETER LIST     R          *
*   WQE       IHAWQE          WTO QUEUE ELEMENT       R          *
*
* KEY = R-READ, W-WRITE, C-CREATE, D-DELETE           *
*
* TABLES          = NONE                             *
*
* MACROS            = NONE                             *
*
* MESSAGES          = NONE                             *
*
* MODULE TYPE       = CSECT                             *
*
* ATTRIBUTES        = REENTRANT, REUSABLE, AMODE 31,    *
*                     RMODE ANY                          *
*
*****
EJECT
M2SLEXIT CSECT
M2SLEXIT AMODE 31          31-BIT ADDRESSING MODE
M2SLEXIT RMODE ANY        31-BIT RESIDENCE
SPACE 1
*****
*
* REGISTER ASSIGNMENTS
*
*****
REG0 EQU 0      REGISTER 0
REG1 EQU 1      REGISTER 1
REG2 EQU 2      REGISTER 2
REG3 EQU 3      REGISTER 3
REG4 EQU 4      REGISTER 4
REG5 EQU 5      REGISTER 5
M2SLPTR EQU 6   REGISTER 6 - PTR TO M2SL
REG6 EQU 6      REGISTER 6
REG7 EQU 7      REGISTER 7
REG8 EQU 8      REGISTER 8
REG9 EQU 9      REGISTER 9
REG10 EQU 10    REGISTER 10
REG11 EQU 11    REGISTER 11
DATAREG EQU 11  REGISTER 11 - WORKAREA
REG12 EQU 12    REGISTER 12
BASEREG EQU 12  REGISTER 12 - MOD BASE
REG13 EQU 13    REGISTER 13
REG14 EQU 14    REGISTER 14
REG15 EQU 15    REGISTER 15
*****
*
* STANDARD ENTRY LINKAGE
*
*****
SAVE (14,12)      SAVE REGISTERS
BASR BASEREG,REG0 ESTABLISH MODULE BASE
USING *,BASEREG    ESTABLISH ADDRESSABILITY
LR M2SLPTR,REG1    ESTABLISH ADDRESSABILITY
USING M2SL,M2SLPTR TO THE PARAMETER LIST
*****
*
* SET ADDRESSABILITY AND INITIALIZE 4K WORKAREA
*

```

```

*****
L    DATAREG,M2SL_WORKAREA@  ESTABLISH ADDRESSABILITY
USING DATAAREA,DATAREG      TO 4K WORKAREA
LR   REG2,DATAREG             ADDRESS OF 4K WORKAREA
L    REG3,LEN4K               SIZE OF WORKAREA
LR   REG4,REG2                ADDRESS OF 4K WORKAREA
SR   REG5,REG5                CLEAR PADDING BYTE
MVCL REG2,REG4                INITIALIZE WORKAREA
*****
*
*    CHECK WHAT THE PARAMETER LIST PASSED US.
*
*****
SPACE 1
TM   M2SL_FLAGS,M2SL_MLWTO    MESSAGE IS MLWTO?
BZ   SINGLINE                 NO, SINGLE LINE...
TM   M2SL_FLAGS,M2SL_MINORLINE MINOR LINE?
BZ   MAJRLINE                 NO, MAJOR LINE...
*****
*
*    PROCESSING A MINOR WQE LINE.
*
*****
MINRLINE EQU *
L    REG3,M2SL_WQE@           ESTABLISH ADDRESSABILITY
USING WMJM,REG3               TO THE MAJOR WQE
L    REG4,M2SL_WNMN@          ESTABLISH ADDRESSABILITY
USING WMNM,REG4               TO THE MINOR WQE
*
*    DO STUFF NOW THAT WE KNOW THIS IS A MINOR WQE LINE.
*
MVC  DYNAMTXT,WMNMTXT1        COPY MESSAGE TEXT
DROP REG3                     DROP ADDRESSABILITY
DROP REG4                     DROP ADDRESSABILITY
TM   M2SL_FLAGS,M2SL_LASTLINE LAST LINE?
BNZ  COMPLETE                 YES, MLWTO IS COMPLETE
B    FINISHED                 PROCESSED MINOR, QUIT
*****
*
*    PROCESSING A MAJOR WQE LINE.
*
*****
MAJRLINE EQU *
L    REG3,M2SL_WQE@           ESTABLISH ADDRESSABILITY
USING WMJM,REG3               TO THE MAJOR LINE
*
*    DO STUFF NOW THAT WE KNOW THIS IS A MAJOR WQE LINE.
*
MVC  DYNAMTXT,WMJMTXT         COPY MESSAGE TEXT
DROP REG3                     DROP ADDRESSABILITY
TM   M2SL_FLAGS,M2SL_LASTLINE LAST LINE?
BNZ  COMPLETE                 YES, MLWTO IS COMPLETE
B    FINISHED                 PROCESSED MAJOR, QUIT
*****
*
*    PROCESSING A SINGLE WQE LINE.
*
*****
SINGLINE EQU *
L    REG3,M2SL_WQE@           ESTABLISH ADDRESSABILITY
USING WQE,REG3                TO THE SINGLE WQE
*
*    DO STUFF NOW THAT WE KNOW THIS IS A SINGLE WQE LINE.
*
MVC  DYNAMTXT,WQETXT          COPY MESSAGE TEXT
DROP REG3                     DROP ADDRESSABILITY
B    COMPLETE                 MESSAGE IS COMPLETE
*****
*
*    WE HAVE PROCESSED A COMPLETE MESSAGE.
*
*****
COMPLETE EQU *
*
*    DO STUFF NOW THAT WE KNOW THE MESSAGE IS COMPLETE.
*
B    FINISHED                 DONE PROCESSING, QUIT
*****
*
*    EXIT FROM THIS MODULE
*
*****

```

```

FINISHED EQU *
          RETURN (14,12)          RESTORE REGISTERS
          EJECT
*****
*
*      4K WORKAREA DEFINITIONS
*      NOTE: THIS SAMPLE ONLY USES 128 BYTES OF THE WORKAREA
*
*****
LEN4K     DC      F'4096'
DATAAREA  DSECT
          DS       0H
DYNAMTXT  DS       CL128          MESSAGE TEXT AREA
DATAAVAL  DS       CL3968        AVAILABLE WORKAREA
          DS       0H
          ORG
DATAEND   EQU      *-DATAAREA
          SPACE 2
*****
*
*      PARAMETER LIST MAPPING
*
*****
          IHAQEQ FORMAT=NEW        WTO QUEUE ELEMENT
          CNZMYM2S                M2SL PARAMETER LIST
          EJECT
          END      M2SLEXIT

```


Chapter 4. CNZ_MSIEXIT — Master Scheduler Initialization Dynamic Exit

Topics for This Exit Appear as Follows:

- [“Controlling the Exit Routine Through the Dynamic Exits Facilities” on page 21](#)
- [“Exit Routine Environment” on page 21](#)
- [“Exit Routine Processing” on page 21](#)
- [“Programming Considerations” on page 21](#)
- [“Performance Considerations” on page 22](#)
- [“Entry Specifications” on page 22](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 22](#)
 - Registers at Exit

Controlling the Exit Routine Through the Dynamic Exits Facilities

IBM has defined the CNZ_MSIEXIT exit to the dynamic exits facility. You can refer to the exit by the name CNZ_MSIEXIT. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

By default, the system disables the exit routine after one abend.

Exit Routine Environment

The exit routine receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 31.
- With no locks or ENQs held.
- In the MASTER address space.

The exit receives control during Master Scheduler Initialization before the IEFSSNxx parmlib member is processed.

Exit Routine Processing

The exit routine is defined via the PROGxx parmlib member. Dynamic allocation is not available at this point in the IPL, so the exit routine must be defined in LPA, LNKLIST or the NUCLEUS. The DSNAME parameter of the EXIT ADD statement in PROGxx should not be used for this exit routine. If it is used, the exit routine does not get control. For example, the PROGxx statement can be EXIT ADD EXITNAME(CNZ_MSIEXIT) MODNAME(MYMSIEXT).

Programming Considerations

You may code your CNZ_MSIEXIT to be reentrant or non-reentrant because the exit is invoked only once for the IPL.

Performance Considerations

While your CNZ_MSIEXIT has control, the IPL of the system does not continue. Therefore, keep the exit processing to a minimum.

Entry Specifications

No parameters will be passed by the exit point to the exit routine, while the 1-8 character parameter PARAM will be passed into the exit routine through Access Registers AR0 and AR1. The value of PARAM parameter is specified in the EXIT statement of the PROGxx parmlib member and in the SETPROG EXIT command.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

0-12

Not applicable

13

Address of a 72 byte save area

14

Return address

15

Entry point address of the exit

Parameter Descriptions: Register 13 contains the address of a 72 byte save area on entry to the exit routine.

Access Registers AR0 and AR1 contain the data for the 1-8 character parameter PARAM, the value of which is specified in the EXIT statement of the PROGxx parmlib member and in the SETPROG EXIT command. AR0 contains the first 4 bytes, and AR1 contains the second 4 bytes. To get the full 8 bytes of PARAM data, the contents of AR0 and AR1 need to be concatenated.

Return Specifications

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0-15

Restored to contents at entry

Chapter 5. CNZ_WTOMDBEXIT – WTO Message Data Block Exit

Topics for This Exit Appear as Follows:

- [“Controlling the Exit Routine Through the Dynamic Exits Facilities” on page 23](#)
- [“Exit Routine Environment” on page 23](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 24](#)
- [“Programming Considerations” on page 24](#)
- [“Performance Considerations” on page 24](#)
- [“Entry Specifications” on page 25](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 25](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 26](#)

Code a CNZ_WTOMDBEXIT exit routine when you want to view all messages being sent by WTO or WTOR. Information in the message is **readonly**; you can not modify the message contents.

CNZ_WTOMDBEXIT receives control from the system when a message is sent by a single-line WTO, a multi-line WTO, or a WTOR. Every single-line message that is sent by WTO or WTOR will be passed to the exit routines active at the exit point. Multi-line messages will be presented only when all lines have been completed. For example, a multi-line message with 1 major and 3 minor lines will result in the exit routine receiving control one time.

Controlling the Exit Routine Through the Dynamic Exits Facilities

IBM has defined the CNZ_WTOMDBEXIT exit to the dynamic exits facility. You can refer to the exit by the name CNZ_WTOMDBEXIT. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

1. The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error.
2. The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system disables the exit routine after one abend.

Exit Routine Environment

The exit receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.

- In AMODE 31.
- With no locks or ENQs held.
- In the address space of the WTO or WTOR issuer, unless the message was a branch-entry message or was a multi-line message that timed out. In both of those cases, the exit receives control in the CONSOLE address space.

Exit Recovery: If the exit routine abnormally terminates, and the exit routine does not provide its own recovery, or the error percolates beyond the exit's recovery routine, a system recovery routine will get control.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

MVS invokes the CNZ_WTOMDBEXIT exit routine every time a WTO or WTOR single-line or completed multi-line message is sent. If any CNZ_WTOMDBEXIT routines are specified to the dynamic exits facility, a parameter list (mapped by macro CNZMYWMX) is passed that contains information about the message, such as:

- Whether the message is a single-line WTO
- Whether the message is a multi-line WTO
- Whether the message is a branch-entry WTO
- Whether the message is a WTOR
- First line of the message text, where the first 12 characters are typically the message identifier.
- Pointer to the message data block (MDB), mapped by macro IEAVM105

Also passed to CNZ_WTOMDBEXIT is the address of a 4K workarea for use by the exit routine.

Programming Considerations

1. All received messages are "completed" messages, in that control is received after the subsystem interface.
2. The exit routine will not affect the content of the message itself. The original message text and attributes (for example, routing and descriptor codes) remain intact. This exit routine cannot suppress a message.
3. Do not code an exit routine that receives control for a message that the exit issues; this causes an endless loop. The exit must be coded so that when it receives control for that message, it does not issue the message again.
4. If an exit routine needs to issue a message it should issue it as a branch entry message. Similarly, if an exit routine needs to DOM a message it should issue the DOM as branch entered.
5. Code the exit routine to be re-entrant.

Performance Considerations

WTO message processing can impact performance; therefore, consider the following recommendations so that system performance is not degraded:

1. Do not code an exit routine that contains an explicit or implicit WAIT or other processing of potentially long duration, for example, issuing requests for large amounts of dynamic storage, or issuing I/O requests. Exits that do this can adversely affect both application and overall system performance.
2. To reduce the need for storage requests, the system provides a 4K workarea that your exit routine can use for dynamic storage. The second word of the input parameter list points to the 4K workarea. The exit routine should clear what they put in the workarea before exiting, because all exit routines installed at the CNZ_WTOMDBEXIT exit point use the same workarea. Use this workarea for your

program's working storage (for example, variables) and avoid doing a GETMAIN or STORAGE OBTAIN in the exit routine.

3. If recovery is necessary, set up an EUT functional recovery routine (FRR) instead of an ESTAE-type recovery routine for shortened path length of the exit routine. If it is not possible to use FRR recovery, then IEAARR should be used because it has the best set/delete performance for Estae-type recovery routines.

Entry Specifications

The system passes the address of the exit parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.


Register Contents

- 0** Not applicable
- 1** Address of a pointer to the exit parameter list
- 2-12** Not applicable
- 13** Register save area
- 14** Return address
- 15** Entry point address of the exit

Parameter Descriptions: Register 1 points to the following:

Word 1
Address of the WMDX, mapped by macro CNZMYWMX

Word 2
Address of a 4K work area



Return Specifications

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

- 0-15** Restored to contents at entry

Coded Example of the Exit Routine

The following is an example of an CNZ_WTOMDBEXIT exit:

```

      TITLE 'WMXEXIT - SAMPLE WTO MDB EXIT'
***START OF SPECIFICATIONS*****
*
* MODULE NAME           =   WMXEXIT
*
* DESCRIPTIVE NAME      =   SAMPLE WTO MDB EXIT (FOR ACTIVATION
*                           ON CNZ_WTOMDBEXIT).
*
* FUNCTION              =   THIS EXIT DEMONSTRATES HOW TO
*                           USE THE DATA IN THE WMDX PARAMETER
*                           LIST TO IDENTIFY DIFFERENT TYPES OF
*                           MESSAGES.
*
* OPERATION = THIS SAMPLE EXIT DETERMINES IF THE MESSAGE
*               DESCRIBED BY THE WMDX IS FOR A SPECIFIC
*               MESSAGE ID, A WTOR, SINGLE LINE MESSAGE, OR
*               MULTIPLE LINE MESSAGE AND PUTS TEXT IN THE
*               WMDX USER WORKAREA INDICATING WHAT IT FOUND.
*
* NOTE1: THE WMDX PARAMETER LIST PROVIDES THE FIRST LINE OF
* MESSAGE TEXT. IN ORDER TO OBTAIN SUBSEQUENT TEXT LINES
* OF A MULTI-LINE MESSAGE USE THE MDB POINTER (IN THE
* WMDX) TO ACCESS THE MESSAGE DATA BLOCK (MDB), WHICH
* CONTAINS DATA DESCRIBING THE MESSAGE, AND ALLOWS YOU
* TO ACCESS THE SUBSEQUENT LINES. SEE "RECEIVING
* MESSAGES AND COMMAND RESPONSES" IN "Z/OS MVS
* ASSEMBLER SERVICES GUIDE", SA22-7608-08 FOR
* INFORMATION ABOUT USING THE MDB. A GOOD EXAMPLE
* PROGRAM USING THE MDB IS IEAEXMCS IN SAMPLIB.
*
* ENTRY POINT          =   WMXEXIT
*
* PURPOSE              =   DEMONSTRATE HOW TO USE THIS EXIT.
*
* LINKAGE = REGISTER 1 CONTAINS THE ADDRESS OF A PARAMETER
* LIST, WHICH CONTAINS (1) THE ADDRESS THE WMDX
* (MAPPED BY CNZMYWMX), AND (2) THE ADDRESS OF A
* 4K WORKAREA.
*
* NOTE2: THERE IS ONLY ONE COPY OF THE WMDX AND WORKAREA
* PER MESSAGE FOR ALL USERS OF CNZ_WTOMDBEXIT. CARE
* MUST BE TAKEN TO MAKE SURE THE WMDX DATA IS NOT
* MODIFIED. THE WORKAREA IS NOT CLEARED BEFORE IT IS
* PASSED TO SUBSEQUENT EXITS SO THE USER MUST CLEAR
* IT IF IT CONTAINS SENSITIVE DATA.
*
* INPUT DATA          =   REG1 ADDRESS OF THE PARAMETER LIST
*                           REG13 ADDRESS OF STANDARD SAVE AREA
*                           REG14 RETURN ADDRESS
*                           REG15 ENTRY POINT ADDRESS
*
* REGISTERS SAVED      =   REG0 - REG15
*
* REGISTER USAGE       =   REG0 - USED FOR BASING
*                           REG1 - PARAMETER REGISTER
*                           REG2 - WORK REGISTER
*                           REG3 - WORK REGISTER
*                           REG4 - WORK REGISTER
*                           REG5 - WORK REGISTER
*                           REG6 - POINTER TO PARAMETER LIST
*                           REG7 - POINTER TO WMDX
*                           REG8 - NOT USED
*                           REG9 - NOT USED
*                           REG10 - NOT USED
*                           REG11 - POINTER TO 4K WORK AREA
*                           REG12 - MODULE BASE REGISTER
*                           REG14 - RETURN POINT
*                           REG15 - NOT USED
*
* REGISTERS RESTORED = REG0 - REG14
*
* CONTROL BLOCKS      =
* NAME      MAPPING MACRO  REASON USED      USAGE
* ----      -
* WMDX      CNZMYWMX      EXIT PARAMETER LIST  R
* WORKAREA  NOT MAPPED    FOR USER            W

```

```

*   KEY = R-READ, W-WRITE, C-CREATE, D-DELETE
*
*   TABLES          = NONE
*
*   MACROS           = NONE
*
*   MESSAGES         = NONE
*
*   MODULE TYPE      = CSECT
*
*   ATTRIBUTES       = REENTRANT, REUSABLE, AMODE 31,
*                     RMODE ANY
*
*01* DISCLAIMER =
*
* THIS SAMPLE PROGRAM IS PROVIDED FOR TUTORIAL PURPOSES ONLY.
* A COMPLETE HANDLING OF ERROR CONDITIONS HAS NOT BEEN SHOWN
* OR ATTEMPTED, AND THIS SOURCE HAS NOT BEEN SUBMITTED TO
* FORMAL IBM TESTING. THIS SOURCE IS DISTRIBUTED ON AN
* 'AS IS' BASIS WITHOUT ANY WARRANTIES EITHER EXPRESSED OR
* IMPLIED.
*
*****
      EJECT
WMXEXIT CSECT
WMXEXIT AMODE 31          31-BIT ADDRESSING MODE
WMXEXIT RMODE ANY       31-BIT RESIDENCE
      SPACE 1
*****
*
*       REGISTER ASSIGNMENTS
*
*****
REG0    EQU    0          REGISTER 0
REG1    EQU    1          REGISTER 1
REG2    EQU    2          REGISTER 2
REG3    EQU    3          REGISTER 3
REG4    EQU    4          REGISTER 4
REG5    EQU    5          REGISTER 5
REG6    EQU    6          REGISTER 6
WMDXPPTR EQU    6          REGISTER 6 - PLIST
REG7    EQU    7          REGISTER 7
WMDXPTR EQU    7          REGISTER 6 - WMDX ADDRESS
REG8    EQU    8          REGISTER 8
REG9    EQU    9          REGISTER 9
REG10   EQU   10          REGISTER 10
REG11   EQU   11          REGISTER 11
DATAREG EQU   11          REGISTER 11 - 4K WORKAREA ADDR
REG12   EQU   12          REGISTER 12
BASEREG EQU   12          REGISTER 12 - MOD BASE
REG13   EQU   13          REGISTER 13
REG14   EQU   14          REGISTER 14
REG15   EQU   15          REGISTER 15
*****
*
*       STANDARD ENTRY LINKAGE
*
*****
      SAVE (14,12)          SAVE REGISTERS
      BASR BASEREG,REG0      ESTABLISH MODULE BASE
      USING *,BASEREG
      LR  WMDXPPTR,REG1      PARAMETER LIST
      SPACE 1
*****
*
*       ESTABLISH ADDRESABILITY
*
*****
      L      WMDXPTR,0(,WMDXPPTR)  GET ADDRESSABILITY
      USING WMDX,WMDXPTR          TO WMDX
      L      DATAREG,4(,WMDXPPTR)  GET ADDRESSABILITY
      USING WORKAREA,DATAREG      TO 4K WORKAREA
      SPACE 1
*****
*
*       CHECK FOR A SPECIFIC MESSAGE. IN THIS EXAMPLE,
*       CNZ4015I (RESPONSE TO D A,L COMMAND) IS USED.
*
*****
      CLC  WMDX_MSGTEXT(8),=C'CNZ4015I' IS THIS CORRECT MSG
      BNE  CHKWTOR              NO, CONTINUE
*

```

```

*      DO STUFF NOW THAT WE KNOW THE MESSAGE IS CORRECT MSG
*
      MVC   WORKATXT(L'WORKATXT),=C'MESSAGE IS CNZ4015I.
      B     FINISHED          DONE
      SPACE 1
*****
*
*      CHECK FOR A WTOR
*
*****
CHKWTOR EQU *
      TM    WMDX_FLAGS,WMDX_WTOR      IS MESSAGE A WTOR
      BNO   CHKSLWTO                  NO, CONTINUE
*
*      DO STUFF NOW THAT WE KNOW THE MESSAGE IS A WTOR
*
      MVC   WORKATXT(L'WORKATXT),=C'MESSAGE IS A WTOR.
      B     FINISHED          DONE
      SPACE 1
*****
*
*      CHECK FOR A SINGLE LINE MESSAGE
*
*****
CHKSLWTO EQU *
      TM    WMDX_FLAGS,WMDX_SLWTO     IS MESSAGE A SLWTO
      BNO   MULTLINE                 NO, MSG IS A MULTILINE
*
*      DO STUFF NOW THAT WE KNOW THE MESSAGE IS A SINGLE LINE
*
      MVC   WORKATXT(L'WORKATXT),=C'MESSAGE IS A SINGLE LINE.
      B     FINISHED          DONE
      SPACE 1
MULTLINE EQU *
*****
*
*      PERFORM MULTIPLE LINE MESSAGE PROCESSING.
*      NOTE THAT WMDX_MLWTO COULD HAVE BEEN USED TO
*      DETERMINE IF MESSAGE IS A MULTI-LINE.
*
*****
*
*      DO STUFF NOW THAT WE KNOW THE MESSAGE IS A MULTILINE
*
*      SEE NOTE ABOVE ON HOW TO LOCATE THE REMAINING LINES IN
*      THE MDB.
*
      MVC   WORKATXT(L'WORKATXT),=C'MESSAGE IS A MULTI-LINE.
      B     FINISHED          DONE
      SPACE 1
*****
*
*      EXIT FROM THIS MODULE
*
*****
FINISHED EQU *
      RETURN (14,12)          RESTORE REGISTERS
      EJECT
*****
*
*      4K WORKAREA DEFINITIONS
*      NOTE: THIS SAMPLE ONLY USES 25 BYTES OF THE WORKAREA
*
*****
WORKAREA DSECT
      DS    0H
WORKATXT DS    CL25          MESSAGE TEXT AREA
WORKREST DS    CL4071       AVAILABLE WORKAREA
      DS    0H
      ORG
WORKAEND EQU *-WORKAREA
      EJECT
*****
*
*      PARAMETER LIST MAPPING
*
*****
      CNZMYWMX              WMDX PARAMETER LIST
      SPACE 2
      END    WMXEXIT

```


Chapter 6. CSVLLIX1 — LLA Module Fetch Exit

Topics for This Exit Appear as Follows:

- [“Controlling The Exit Routine Through the Dynamic Exits Facility” on page 29](#)
- [“Exit Routine Environment” on page 30](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 30](#)
- [“Programming Considerations” on page 31](#)
 - Macro Instructions and Restrictions
 - I/O Restrictions
- [“Entry Specifications” on page 31](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 32](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 32](#)

Library lookaside (LLA) improves the performance of fetching modules from both LNKST and non-LNKST data sets, and is a control point in managing updates to these data sets on DASD. For each module that is fetched, LLA dynamically accumulates statistics such as the fetch rate and the fetch durations. Using these and other statistics, LLA periodically triggers LLA module staging analysis to evaluate the cost of fetching each module. Based on projected savings, LLA module staging analysis places copies of the most frequently used modules into a virtual lookaside facility (VLF) data space. LLA can then fetch these modules from virtual storage without I/O and with a reduced number of processor instructions.

LLA module fetch keeps track of the number of modules fetched from the LLA libraries. When a default threshold of 2000 module fetches from a library is reached, or after the initial 10 fetches of a single module from DASD, LLA module fetch triggers the LLA module staging analysis function.

Each time LLA fetches a module from an LLA library, it logs statistics and then calls the installation exit CSVLLIX1. LLA fetch passes to CSVLLIX1 the address of a parameter list containing fetch statistics, the address of a user work area, and a copy of the module's BLDL format PDS directory entry.

You can use CSVLLIX1 to:

- Monitor and collect fetch statistics.
- Control the 2000 fetch default limit.
- Cause staging analysis to begin regardless of the statistics for one module or all modules.
- Modify statistics to influence the triggering of staging analysis.

Controlling The Exit Routine Through the Dynamic Exits Facility

IBM has defined the CSVLLIX1 installation exit to the dynamic exits facility. You can refer to the exit by the name CSVLLIX1. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and the exit routines of the exit.

When you start LLA, if the EXIT1(OFF) statement is not present in the CSVLLAxx parmlib member being used by LLA, the system attempts to add exit routine CSVLLIX1 in the following situations:

- no exit routines have been associated with CSVLLIX1 by PROGxx
- no exits have been associated using SETPROG
- there are no exit routines from a previous LLA start

If you have associated exit routines with CSVLLIX1 the system does not use the default exit routine. In this case, if you require an exit routine of the default name, you must explicitly add the default exit routine to PROGxx.

A change from EXIT1(ON) to EXIT1(OFF) has no effect. If you want to deactivate the CSVLLIX1 exit routine (or any other exit routine for the CSVLLIX1 exit), you can use the PROGxx EXIT statement with SET PROG=xx or you can use SETPROG EXIT.

To limit the number of times the exit routine ends with an abend, before the exit routine becomes inactive, you can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro, or the ABENDNUM parameter of the SETPROG EXIT operator command. The system disables the exit routine if the exit routine ends with an abend on two successive calls. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error.
- The system allows a retry (the recovery routine is entered with bit SDWACLUP off).

The system disables the exit routine if the exit routine ends with an abend, as defined above, on two successive calls.

Exit Routine Environment

CSVLLIX1 receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0 and in primary ASC mode with the primary ASID equal to the home ASID.
- In AMODE 31 and RMODE ANY.
- Under a content supervisor's SVRB within the user's address space.
- With no locks or ENQs held.
- Under any task that might issue a LINK, LOAD, XCTL, or ATTACH macro.

Exit Recovery: The LLA recovery routine protects the exit routines of CSVLLIX1. The recovery routine records diagnostic information in the system diagnostic work area (SDWA), requests recording of the error in the logrec data set, and takes an SVC dump. LLA then retries to a point within LLA module fetch to call the next exit routine.

Exit Routine Processing

When a caller issues a LINK, LOAD, XCTL, or ATTACH macro, the system must fetch the module if it doesn't already reside in virtual storage. If the module is in a data set that LLA is managing, then an LLA fetch occurs. If the module has already been staged, then LLA fetch obtains the module from a VLF data space to avoid program fetch I/O. If the module has not been staged, LLA fetch obtains the module from DASD. LLA first logs statistics about the fetch and then passes control to CSVLLIX1. The exit routine examines the parameters and returns a code indicating whether LLA should trigger module staging analysis.

The LLP1USER field in LLP1, the exit parameter list, contains a 31-bit address that points to a 4-byte user data area in the CSA. The user data area is aligned on a fullword boundary and is initialized to 0. The user data area is also pointed to by the LLP2X1US field in the CSVLLIX2 (LLA module staging exit) parameter list. An installation can use the user data area as a means of allowing CSVLLIX1 and CSVLLIX2 to share information. For example, CSVLLIX1 or CSVLLIX2 can acquire storage in the CSA (by issuing a GETMAIN or STORAGE macro) and place the address of this storage in the 4-byte user data area. CSVLLIX1 could write records to the common storage area during fetch time and CSVLLIX2, when it gets control, could

then write the records to DASD. This action could reduce the time CSVLLIX1 needs for processing and thus shorten LLA's path length for fetching a module.

CSVLLIX1 can also use the LLP1USER field to pass information (such as a parameter or the address of a parameter) to itself during subsequent invocations of the exit routine.

If your installation plans to have both CSVLLIX1 and CSVLLIX2 access the 4-byte user data area (pointed to by LLP1USER and LLP2X1US), both exits must manage the serialization of the area. If only CSVLLIX1 is going to use the area then CSVLLIX1 must manage the serialization of the user data area. Compare-and-swap (CS) is a potential serialization method. The 4-byte user data area is initialized to 0. If LLA is restarted, the user data area is not reset to 0. It will contain the last value stored in it by either CSVLLIX1 or CSVLLIX2. When using this field as a counter, you must reset it when the condition you are testing for is met.

Programming Considerations

Code CSVLLIX1 to be reentrant.

CSVLLIX1 is called each time a program fetch occurs for LLA managed members. When coding a modification to the exit, you should be aware that an increased path length will increase processor utilization. If your installation wants to limit its use of CSVLLIX1, perhaps to improve performance by shortening path length, you can deactivate the exit.

Note: Be aware while coding the exit routine, that because the exit is called for every module fetch request, an increased path length increases processor utilization which can degrade system performance.

Macro Instructions and Restrictions: While CSVLLIX1 has control, it cannot issue (or cause another program to issue) a LOAD, LINK, XCTL, or ATTACH macro that might require LLA to fetch a module from a data set that LLA is managing. This would result in recursive calls to the exit routine. See [z/OS MVS Initialization and Tuning Guide](#) for information on managing a data set.

Note: Do not code the exit routine to issue the WAIT macro or call a service, such as WTOR, that issues a WAIT. Do not code the exit routine to call a service that suspends processing for a period of time, like STIMER(M), which will also have a severely negative impact upon system performance.

I/O Restrictions: Some functions that are needed to perform I/O, such as dynamic allocation, must be initialized.

Entry Specifications

LLA passes to CSVLLIX1 the address of the LLP1 parameter list.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

0	Zero
1	Address of the LLA module fetch exit parameter list (LLP1)
2-12	Not applicable
13	Register save area
14	Return address
15	Entry point address of CSVLLIX1

Parameter List Contents: Register 1 contains the address of LLP1, the LLA fetch exit parameter list. The macro IHALLP1 maps LLP1. The LLP1 mapping is described in *z/OS MVS Data Areas* in the [z/OS Internet library](http://www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

CSVLLIX1 passes back to LLA both a return code and a reason code to indicate whether LLA should trigger module staging analysis.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0

One of the following reason codes:

Reason Code

Explanation

0

Use the default threshold to trigger LLA module staging analysis.

1

Indicates that LLA module staging analysis should begin.

2

Indicates that LLA module staging analysis should not begin.

1-14

Restored to contents at entry

15

One of the following return codes:

Return Code

Explanation

0

Indicates that the default threshold should be used to trigger LLA module staging analysis. The reason code in register 0 should be zero.

4

Indicates that the exit has determined whether to trigger LLA module staging analysis. The reason code in register 0 provides additional information.

Coded Example of the Exit Routine

A sample CSVLLIX1 exit routine is provided in SYS1.SAMPLIB for your reference. This routine contains the code for entry to the exit routine (a standard BR14 branch).

Chapter 7. CSVLLIX2 – LLA Module Staging Exit

Topics for This Exit Appear as Follows:

- [“Controlling The Exit Routine Through the Dynamic Exits Facility” on page 33](#)
- [“Exit Routine Environment” on page 34](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 34](#)
- [“Programming Considerations” on page 35](#)
- [“Entry Specifications” on page 37](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 37](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 38](#)

Library lookaside (LLA) improves the performance of fetching modules from both LNKLIST and non-LNKLIST data sets, and is a control point in managing updates to these modules on DASD. LLA collects statistics such as fetch rates and fetch durations to allow LLA module staging to determine the value of staging each module. LLA module staging runs periodically to perform this evaluation and stages, or places, copies of the most frequently used modules into a virtual lookaside facility (VLF) data space. LLA can then fetch these selected modules from virtual storage without I/O and with a reduced number of processor instructions.

LLA combines four independent components of staging value to determine the net value of staging a module into processor storage (see [“Exit Routine Processing” on page 34](#)). LLA multiplies each component of staging value by its weighting factor, adds the products, and determines the net LLA staging value for the module. LLA stages modules that have the highest LLA staging value. Modules with a low LLA value are provided to users through program fetch from DASD.

Before applying the weighting factors to determine whether a module should be staged, LLA calls CSVLLIX2 and passes it the address of a parameter list that contains the weighting factors. CSVLLIX2 can modify the weighting factor values or specify an installation-defined value and thus determine which modules are staged.

You can use CSVLLIX2 to:

- Analyze fetch statistics provided in the LLA module staging parameter list (LLP2).
- Influence the calculation of the LLA value (which determines if a module should be staged) by altering the weighting factors in the LLP2 parameter list.
- Force LLA to stage the module by setting the appropriate return and reason codes.

Controlling The Exit Routine Through the Dynamic Exits Facility

IBM has defined the CSVLLIX2 installation exit to the dynamic exits facility. You can refer to the exit by the name CSVLLIX2. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and the exit routines of the exit.

When you start LLA, if the EXIT2(OFF) statement is not present in the CSVLLAxx parmlib member being used by LLA, the system attempts to add exit routine CSVLLIX2 in the following situations:

- no exit routines have been associated with CSVLLIX2 by PROGxx

- no exits have been associated using SETPROG
- there are no exit routines from a previous LLA start

If you have associated exit routines with CSVLLIX2 the system does not use the default exit routine. In this case, if you require an exit routine of the default name, you must explicitly add the default exit routine to PROGxx.

A change from EXIT2(ON) to EXIT2(OFF) has no effect. If you want to deactivate the CSVLLIX2 exit routine (or any other exit routine for the CSVLLIX2 exit), you can use the PROGxx EXIT statement with SET PROG=xx or you can use SETPROG EXIT.

To limit the number of times the exit routine ends with an abend, before the exit routine becomes inactive, you can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro, or the ABENDNUM parameter of the SETPROG EXIT operator command. The system disables the exit routine if the exit routine ends with an abend on two successive calls. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error.
- The system allows a retry (the recovery routine is entered with bit SDWACLUP off).

The system disables the exit routine if the exit routine ends with an abend, as defined above, on two successive calls.

Exit Routine Environment

CSVLLIX2 receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0 and in primary ASC mode with the primary ASID equal to the home ASID.
- In AMODE 31 and RMODE ANY.
- With no locks or ENQs held.
- In task mode under a non-jobstep TCB attached by LLA's jobstep program in LLA's address space.
- With TCB and PSW keys of zero.

Exit Recovery: The LLA recovery routine protects the exit routines of CSVLLIX2. The recovery routine records diagnostic information in the system diagnostic work area (SDWA), requests recording of the error in the logrec data set, and takes an SVC dump. LLA then retries to a point within LLA staging to call the next exit routine.

Exit Routine Processing

CSVLLIX2 receives control from the LLA staging function before it applies the weighting factors to determine a module's total staged value. LLA staging combines 4 independent staging values to determine the net value of staging a module into processor storage. The 4 values, which are contained in field LLP2VALU of the parameter list, relate to response time, processor storage, contention, and an optional, installation-defined cost. Each staging value is in the range -10,000 to +10,000 and indicates the relative value to the system of LLA staging the module. Each value has a corresponding weighting factor (LLP2WGTS) in the range 0 to 100, used to indicate the relative importance of the value. LLA staging multiplies each factor of staging value by its weighting factor, adds the products, and determines the net LLA staging value for the module.

CSVLLIX2 receives control from LLA staging before it applies the weighting factors to determine whether a module should be staged. CSVLLIX2 can influence the calculation of the module's LLA staging value by altering the appropriate weighting factors. For example, if response time is more important to your installation than processor storage use, you can use CSVLLIX2 to set the response time weighting factor to a high value (70-100) and set the processor storage weighting factor to a low value (0-30).

CSVLLIX2 can introduce its own installation-defined value (LLP2VUSR). The value must be in the specific range (-10,000 to +10,000), and the corresponding weighting factor must be changed from its initial value of zero.

CSVLLIX2 can also force a module to be staged by setting the appropriate return and reason codes. This is a less desirable solution because LLA can then change the staging only at the direction of CSVLLIX2; for example, it could never deactivate the staged module even if it was so infrequently used that it was stolen to auxiliary storage.

The LLP2X1US field in LLP2, the exit parameter list, contains a 31-bit address that points to a 4-byte user data area in the CSA. The user data area is aligned on a fullword boundary and is initialized to 0. The user data area is also pointed to by the LLP1USER field in the CSVLLIX1 (LLA module fetch exit) parameter list. An installation can use the user data area as a means of allowing CSVLLIX1 and CSVLLIX2 to share information. For example, CSVLLIX1 or CSVLLIX2 can acquire storage in the CSA (by issuing a GETMAIN or STORAGE macro) and place the address of this storage in the 4-byte user data area. CSVLLIX1 could then write records to this common storage area during fetch time and CSVLLIX2, when it gets control, could then write the records to DASD. This action could reduce the time CSVLLIX1 needs for processing and thus shorten LLA's path length for fetching a module.

If your installation plans to have both CSVLLIX1 and CSVLLIX2 access the 4-byte user data area (pointed to by LLP1USER and LLP2X1US), both exits must manage the serialization of the area. If only CSVLLIX1 is going to use the area, then CSVLLIX1 must manage the serialization of the user data area. Compare-and-swap (CS) is a potential serialization method. The 4-byte user data area is initialized to 0. If LLA is restarted, the user data area is not reset to 0. It will contain the last value stored in it by either CSVLLIX1 or CSVLLIX2. When using this field as a counter, you must reset it when the condition you are testing for is met.

The LLP2USER field in LLP2, the exit parameter list, points to a 4-byte user data area that is aligned on a fullword boundary and is reserved for CSVLLIX2 to use. CSVLLIX2 can use the 4-byte user data area as a work area to pass information to itself during subsequent invocations. The 4-byte user data area is initialized to zero and subsequently contains any value stored in it by CSVLLIX2. When using this field as a counter, you must reset it when the condition you are testing for is met.

In most cases LLA does apply the same algorithm to program objects, however in a few situations LLA finds staging in VLF unacceptable due to certain attributes of program objects. For example, if LLA discovers that the number of deferred classes in the header of the program object is not 0 or the program object is a split RMODE module, then LLA cancels the staging algorithm, making a particular program object ineligible for staging.

Programming Considerations

Code the exit routine to be reentrant. There are no restrictions on external routines that CSVLLIX2 can invoke while it has control.

If your installation wants to limit its use of CSVLLIX2, perhaps to improve performance by shortening path length, you can deactivate the exit. CSVLLIX2 is ON by default.

Changing Weighting Factors: The default weighting factors that CSVLLIX2 can change are set to response time=75, contention=50, storage=25, and installation=0. You should not need to change these settings. However, if an adjustment is necessary, consider the following:

- Response time (LLP2WRSP)

Keep this weighting factor higher than the others if you have sufficient central storage to hold all the staged modules. Decrease this slightly relative to the storage weighting factor if LLA quickly fills the VLF data space and the data space cannot be enlarged. (To enlarge the data space, increase the value specified by the MAXVIRT keyword for class CSVLLA in the COFVLFxx parmlib member.) Processor time might increase if many staged modules age out to expanded storage because of central storage contention. In general, for the modules that remain backed by central storage, LLA uses slightly less processor time than program fetch for all module sizes.

- Contention (LLP2WCTN)

Increase this factor relative to response time if data sets that LLA is managing incur I/O activity that causes disruptive contention. Such data sets are likely to be on volumes shared between systems or on volumes that contain other performance-sensitive data sets. You can use storage isolation to control contention for LLA's VLF data space.

- Storage (LLP2WSTO)

Increase this factor if you do not have enough processor storage to hold all the modules. The storage value should always be weighted lower than the response time value because the storage value usually is negative.

The values that LLA calculates using these weighting factors are derived as follows:

- Response time (LLP2VRSP)

This value is defined as the time that would be saved per sample if the module were to be fetched from VLF divided by the total time that would have been saved during the previous sample if all modules had been fetched from VLF.

- Contention time (LLP2VCTN)

This value is defined as the average difference between the minimum fetch for the module from LLA or DASD, and the duration of the fetch. The average LLA difference is then subtracted from the average DASD difference. The result is multiplied by the number of fetches, and is normalized by dividing by the sum of all the contention deltas from the previous sample.

Contention value helps LLA to compensate dynamically for unbalanced storage and I/O resources in a system.

- Storage (LLP2VSTO)

This value is defined as the number of processor storage bytes that would be saved minus the number of bytes that would be spent if the module were to be kept in VLF, normalized by dividing the sum of all the storage deltas accumulated in the previous sample. Storage is saved because users occupy storage for less time while they wait for fetches. Storage is spent because the staged module requires processor storage to back it in the VLF data space. With the exception of some very small and highly used modules, storage value is a negative number.

Changing the Staging Threshold: If your installation has a steady state workload, you should notice a consistency in the modules being staged and in the ranking of the modules. If the same modules are not being staged, or if the ranking of the modules staged fluctuates often, the reason could be that your installation has a large number of modules in its working set and therefore, LLA needs to have a larger sampling of modules on which to base its staging decisions.

Increase the staging threshold (the default is 2000) to provide LLA with a more meaningful sampling on which to base its decisions, so that LLA will consistently stage the most often used modules. It is suggested that the staging threshold be at least 3 times the total number of modules in your installation's working set.

Using the Exit to Influence Module Staging: If you use CSVLLIX2 to force LLA to stage a particular module, the change applies only to the current staging analysis of the module. That is, LLA does not maintain the changed staging status of the module across subsequent exit invocations. In addition, if the exit is deactivated or the code of the exit routine changed, the outcome of staging analysis might be affected.

Depending on your installation's workload, the staging analysis for a given module might be different each time CSVLLIX2 is invoked. If you use CSVLLIX2 to determine whether a particular module should be staged, the exit routine should continue to check the module's staging statistics during subsequent invocations.

If you plan to use CSVLLIX2 to force LLA to stage a particular module regardless of the module's staging statistics, the exit routine should maintain this status each time the exit is invoked. Do this by setting the appropriate return and reason codes. Otherwise, excessive LLA overhead can occur.

For example, avoid using program logic that indicates that a module, if not staged, should be staged, but fails to indicate an action if the module is already staged. In this case, when the exit fails to indicate

an action, LLA staging analysis will make its own determination and might deactivate staging for the module. The next invocation of the exit for this module would cause LLA to restage the module, and so on. Excessive LLA overhead results as LLA alternately stages and deactivates the same module repeatedly.

Entry Specifications

LLA passes to CSVLLIX2 the address of the LLP2 parameter list.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

- 0**
Zero
- 1**
Address of the LLA staging installation exit parameter list (LLP2)
- 2-12**
Not applicable
- 13**
Register save area
- 14**
Return address
- 15**
Entry point address of CSVLLIX2

Parameter List Contents: Register 1 contains the address of LLP2, the LLA staging exit parameter list. The macro IHALLP2 maps data area LLP2. See *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for a mapping of the LLP2 data area.

Return Specifications

CSVLLIX2 passes back to LLA both a return code and a reason code to determine the need for LLA module staging.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

- 0**
One of the following reason codes (the reason code in register 0 is dependent upon the return code in register 15):

Reason Code	Explanation
0	Indicates that LLA should use the weighting factors to determine whether the module should be staged. (Set register 15 to 0.)
1	Indicates that LLA is to stage this module. If the module is already staged, it remains staged. (Set register 15 to 4.)
2	Indicates that LLA is not to stage this module. If the module is already staged, LLA stops using the staged copy of the module. (Set register 15 to 4.)
- 1-14**
Restored to contents at entry

15

One of the following return codes:

Return Code	Explanation
--------------------	--------------------

0	Indicates that LLA module staging should use the weighting factors to determine whether the module should be staged.
4	Indicates that LLA module staging should not use the weighting factors. The decision to stage or not stage the module is specified by the reason code in register 0.

Coded Example of the Exit Routine

IBM provides a sample CSVLLIX2 exit routine in SAMPLIB for your reference. This routine contains the code for entry to the exit routine (a standard BR14 branch).

Chapter 8. DLF Connect / Disconnect Exit

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routine” on page 40](#)
- [“Exit Routine Environment” on page 40](#)
 - Exit Recovery
- [“Exit Routine Functions” on page 41](#)
 - Initialization
 - Query
 - Connect
 - Disconnect
- [“Exit Routine Processing” on page 42](#)
- [“Programming Considerations” on page 42](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 43](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 43](#)
 - Registers at Exit
- [“Coded example of the exit routine” on page 44](#)

This exit provides the control information that hiperbatch and the data lookaside facility (DLF) need.

Hiperbatch is a performance enhancement that can significantly reduce the execution time of certain batch job streams or multi-step batch jobs that access the same VSAM or QSAM data sets. Hiperbatch works with DLF to allow batch jobs to share access to a DLF object. A DLF object is a set of hiperspaces created by DLF that contains QSAM or VSAM data managed by hiperbatch. Storing data into, and retrieving data from, DLF objects is done transparently by the access method; an installation does not need to rewrite its application programs or the JCL needed to run them. The installation does, however, need to provide control information to DLF.

If your system includes RACF 1.9 or higher, you can define RACF profiles in the DLFCLASS general resource class instead of using this exit routine. However, you must still code the exit; its decisions can override the information in the RACF profiles.

If your system *does not* include RACF 1.9 or higher, you must code a DLF Connect / Disconnect installation exit routine to provide the needed control information.

You can use the DLF Connect / Disconnect exit to:

- Decide whether a job is eligible to connect to a DLF object. (The object will be created if this is the first connection.)
- Specify whether or not to retain a DLF object even when no jobs are connected to it. The default is to delete the DLF object when there are no longer any connections to it.
- Determine whether a particular data set is eligible for DLF processing, so that if the data set is updated while DLF is not running, DLF will process the updated form of the data set. (See [“Query” on page 41.](#))

To make these decisions, the exit must have access to the DLF control information:

- The names of all data sets that you want the system to process as DLF objects

- The names of all DLF objects that are to be retained
- The users and/or job names that are allowed to access each DLF object

You can store this control information in a data set or code the information in the exit routine. If you have a great deal of control information, or if you plan to update it often, you should consider storing the information in a data set.

Installing the Exit Routine

Before starting the Data Lookaside Facility:

1. You must include the exit in an authorized library in the LNKLIST concatenation.
2. You must specify the exit name on the CONEXIT keyword in the COFDLFxx parmlib member.

If your installation runs jobs that perform random updates of VSAM or QSAM data sets while other jobs read the data sets, you must name your exit COFXDLF1. Hiperbatch calls this name when DLF is not running to request the exit to query VSAM or QSAM data sets. If your installation does not access VSAM or QSAM data sets when DLF is not running, you may choose any name for the exit. (See [“Query” on page 41.](#))

If you name the exit routine COFXDLF1—specify CONEXIT(COFXDLF1) in the COFDLFxx member in the parmlib—the DLF initialization code will look for that routine in the LPA. If it is not there, it will load the exit routine into the CSA from the LNKLIST. Then, as long as the DLF is active, the system will call the exit via a branch to the LPA or CSA address, avoiding a LINK or LOAD.

Note: If you haven't named your exit routine on the CONEXIT keyword in the COFDLFxx parmlib member, the system does a BLDL to the LNKLIST for the exit; when BLDL finds the routine, the system issues a LINK with DE= without first searching the LPA. To avoid this overhead where your installation makes infrequent accesses to the same VSAM or QSAM data sets and thus does not need to use hiperbatch, simply don't start the DLF.

You cannot replace the exit while the DLF is active. The exit that is requested when the DLF is started remains in effect for the duration of the DLF address space. To replace the exit, you must stop the DLF, replace the exit (or change the parmlib CONEXIT parameter to point to a different exit), and then start the DLF again.

For general instructions on installing an exit routine, see [“Link editing an Installation Exit Routine into a Library” on page 3.](#) For information on how to start the DLF, see [z/OS MVS System Commands.](#)

Exit Routine Environment

The DLF exit receives control in the following environment:

- Resides in an APF-authorized library in the LNKLIST concatenation
- Enabled for interrupts
- In primary ASC mode
- In AMODE 31 and RMODE ANY
- In supervisor state with PSW key 0
- When called to perform the initialization function, the exit is invoked in the DLF address space. On subsequent calls, in which the routine performs the query, connect, and disconnect functions, the exit routine runs in the address space of the task that issues the request

Exit Recovery

DLF recovery protects the exit.

If the exit abnormally terminates during DLF initialization, the DLF initialization is terminated.

If the exit abnormally terminates during a query call, DLF determines that the data set is not eligible for DLF processing. OPEN processing continues and the job reads the data set from DASD, instead of from a DLF object, and updates the data set on DASD.

If the exit abnormally terminates during a user's attempt to connect to a DLF object, the request is terminated and the user is not connected to the DLF object. OPEN processing continues and the job reads the data set from DASD, instead of from the DLF object.

If the exit abnormally terminates during a user's attempt to disconnect from the DLF object, the user is disconnected from the DLF object.

Exit Routine Functions

The exit is called to perform these functions: initialization, query, connect, and disconnect.

Initialization

When the DLF is started, the exit is invoked with a request from the DLF to perform initialization: the CXTFUN field in the CXT (the exit routine parameter list) is set to 0. If your installation places control information in a data set, use the initialization call to access the data set. On subsequent calls, the exit routine uses the control information in the data set to perform the query, connect, and disconnect functions.

In the CXT, the CXTUDAB field points to a 16-byte area in the CSA. The exit routine can acquire storage in the CSA (for example, by issuing a GETMAIN or STORAGE macro) and place the address of this storage in the first word of a 16-byte area pointed to by CXTUDAB. The exit can then open the data set that contains the DLF control information and read it into the CSA area. DLF passes the pointer to the address of the control information to the exit (in CXTUDAB) every time it is called. The exit now has access to the control information it will need on subsequent calls.

The exit must manage serialization of the 16-byte area in the CSA to prevent the address of the control information from being reset by the exit on a DLF restart while the area is being accessed for a query. An installation can serialize the 16-byte area by, for example, using the third word of the area as a serialization field and using compare-and-swap (CS) as a serialization method. If DLF is restarted, the 16-byte area is not reset to zero. It will contain the last values stored by the exit.

You do not need to code the exit to perform initialization if you code the control information within the exit routine itself. If you code the control information within the exit routine, your exit needs only to return control to DLF on an initialization call. The exit return code is ignored on an initialization call.

Query

If your installation runs jobs that perform random updates of VSAM or QSAM data sets while other jobs read the data sets, you must:

- Code your exit routine to perform the query function.
- Name your exit COFXDLF1.

If you do not code the exit routine to perform the query function, you can choose any name for the exit.

Hiperbatch calls the exit with a query request (the CXTFUN field in the CXT is set to 1) to determine whether or not a particular VSAM or QSAM data set that is being opened for update or output could be processed as a DLF object. The exit routine searches the installation's control information (its address is pointed to by CXTUDAB) for the name of the data set (in CXTDSN) and, optionally, its volume serial (in CXTVOL). If the data set is listed in the control information, the exit routine sets return code 0 to indicate that the data set is eligible for DLF processing. If the data set is not listed in the control information, the exit routine sets return code 8 to indicate that the data set is not eligible for DLF processing.

If the data set is listed in the control information, hiperbatch records the name of the data set to ensure that if a data set is opened while DLF is down, and DLF is started before the data set has been closed, subsequent jobs that open the data set will connect to its updated form.

It is strongly recommended that you start DLF before starting JES. This action is necessary to ensure that readers of VSAM and QSAM data sets read the latest level of the data sets.

Connect

DLF calls the exit when a job opens a VSAM or QSAM data set (the CXTFUN field in the CXT is set to 2). At this time, the exit routine must determine whether the user or job requesting the connection is eligible to connect to the DLF object. The exit also must specify whether the DLF object is to be retained. (If RACF profiles exist for the DLF objects, the exit routine might not need to make these decisions, but it can override the RACF information.) The exit sets a return code that indicates whether the connection is to be permitted, or whether RACF information is to be used to make the decision.

If DLF is not active, connect processing always invokes exit COFXDLF1.

Disconnect

DLF calls the exit when it disconnects a user from a DLF object (the CXTFUN field in the CXT is set to 3). The exit return code is ignored on a disconnect call.

Exit Routine Processing

When a user attempts to open a VSAM or QSAM data set, and DLF is active, the system tries to connect the user to the DLF object corresponding to the data set.

The exit is only called after RACF or another security product has already granted the user access to the VSAM or QSAM data set. Then, on a system with RACF 1.9 or higher, DLF will check the job or user's eligibility to connect to the DLF object. If RACF approves the request, DLF updates CXTSFLGS in the CXT, the exit parameter list, with the connect information. Then DLF passes the CXT to the exit routine, which can override the RACF decision to connect to a DLF object.

On a system without RACF 1.9, the CXTSFLGS bits are set to zero, and the exit routine must determine whether the application is eligible to connect to a particular DLF object.

After exit routine processing, the exit returns a code specifying whether or not the user is allowed to connect to the DLF data object. The exit routine can override the eligibility of the DLF data object and inform DLF not to connect the DLF object to the user. The exit also sets bit CXTRTAIN in CXTUDATA to '1'B if the DLF object is to be retained when no jobs are connected to it. CXTRTAIN will be honored only if the data set is being opened for update (QSAM) or load (VSAM) mode.

For more information on the return codes the exit routine can set, see [“Registers at Exit” on page 44](#).

Programming Considerations

If your installation does not include RACF 1.9 or higher (or if you are using the exit to override RACF decisions), the exit must determine which connections will be permitted. The exit must have access to the following:

- The names of all data sets that you want the system to process as DLF objects
- The names of all DLF objects that are to be retained
- The users and/or job names that are allowed to connect to each DLF object.

The exit routine must be reentrant and must reside in an APF-authorized library in the LNKLIST concatenation.

If your installation runs jobs that perform random updates of VSAM or QSAM data sets while other jobs read the data sets, you must name your exit COFXDLF1. Hiperbatch calls this name when DLF is not running to request the exit to query VSAM or QSAM data sets. If your installation does not access VSAM or QSAM data sets when DLF is not running, you may choose any name for the exit (see [“Query” on page 41](#)). However, you must specify the name in the COFDLFxx parmlib member with the keyword CONEXIT, so that it is known to DLF.

The installation determines the maximum number of VSAM/QSAM data sets for which DLF objects may exist, based on available extended storage, and places the value in the CXTDSMAX field. (The default is 50.) This value is read only on the first query or connect call to the exit. It is recommended that you code the exit to store the proper value in CXTDSMAX on all query and connect calls to the exit.

When the DLF is active, the exit is called for every OPEN (connect) and every CLOSE (disconnect) issued by a VSAM or QSAM application. If you plan to have the exit routine search very long lists of names, you should consider using a more efficient search technique than sequential (for example, a binary search).

Macro Instructions and Restrictions

With one exception, the exit routine cannot issue (or cause another program to issue) the OPEN macro, because the exit is already running under OPEN processing. The exception is the initialization function; during this call, the exit routine can issue the OPEN macro.

Entry Specifications

DLF passes to the exit the address of a fullword that points to the CXT, the exit parameter list.

Registers at Entry

The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of a fullword that points to the CXT, which is mapped by COFZCXIT

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of the exit routine

Parameter List Contents

Register 1 contains the pointer to the fullword that contains the address of the CXT, the exit parameter list. The CXT is described in *z/OS MVS Data Areas* in the [z/OS Internet library \(www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary\)](http://www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

There is no field in the CXT that indicates whether or not a particular connection is allowed. The exit must set a return code on the connect exit call to communicate this information to DLF.

Note:

1. The exit routine indicates whether or not an object is to be retained by setting the CXTRTAIN bit on the connect exit call.
2. To include the CXT mapping in your exit routine, you must code 'COPY COFZCXIT' in the routine.

Return Specifications

A return code from the exit indicates whether the DLF object is eligible to be connected to the user (query), or whether the DLF object should be connected to the user (connect).

The exit routine indicates whether or not an object is to be retained by setting the CXTRTAIN bit on the connect exit call.

Registers at Exit

Upon return from the exit processing, the register contents must be as follows.

Register Contents

0-1

Irrelevant

2-14

Same as at entry

15

One of the following return codes:

Query Return Code

Explanation

0

The data set is eligible for DLF processing.

4

DLF is to use information from the security product (e.g., RACF) to determine whether the data set is eligible for DLF processing.

8

The data set is not eligible for DLF processing.

Connect Return Code

Explanation

0

DLF is to permit the user to connect to the DLF object.

4

DLF is to use information from the security product (e.g., RACF) to determine whether the user is authorized to connect to the DLF object. If RACF 1.9 or higher is not included in the system, DLF is not to permit the user to connect to the DLF object.

8

DLF is not to permit the user to connect to the object.

Coded example of the exit routine

IBM Systems Centers produce IBM Redbooks® publications that can be helpful in setting up and using z/OS. See [IBM Redbooks \(www.ibm.com/redbooks\)](http://www.ibm.com/redbooks) for more information.

Chapter 9. HIS.SERVSTAT— HISSESV Service Exit

Topics for This Exit Appear as Follows:

- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 45](#)
- [“Replacing the Exit Routine” on page 45](#)
- [“Exit Routine Environment” on page 45](#)
- [“Exit Recovery” on page 46](#)
- [“Exit Routine Processing” on page 46](#)
- [“Programming Considerations” on page 46](#)
- [“Entry Specifications” on page 46](#)
- [“Return Specifications” on page 47](#)
- [“Coded Example of the Exit Routine” on page 47](#)

The HIS.SERVSTAT exit will be defined by IBM. Any authorized program that wants to know the state of the HISSESV service can register with the HIS.SERVSTAT dynamic exit. For example, an exit can provide a bootstrap process for potential exploiters of the HISSESV service, as a mechanism to know when a program is able to begin exploiting the service. Exit routines are called for the following reasons:

- The HISSESV service has been enabled.
- The HISSESV service has started instrumentation data collection.
- The HISSESV service has stopped instrumentation data collection.
- The HISSESV service had been disabled.

The HISYEXIT macro maps the storage passed to a HIS exit routine that is monitoring the service.

Controlling the Exit Routine Through the Dynamic Exits Facility

The exit routine is defined by registering an exit routine with the HIS.SERVSTAT dynamic exit. Note exit routines registered with the HIS.SERVSTAT dynamic exit do not have the ability to receive instrumentation data, only monitor the state of the service. You can use the CSVDYNEX macro to control the HIS.SERVSTAT dynamic exit and its exit routines.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error.
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system will disable the exit routine after 3 consecutive abends.

Replacing the Exit Routine

For information about replacing a dynamic exit routine, see [“Replacing a Dynamic Exit Routine” on page 6](#).

Exit Routine Environment

The exit routine receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0 and must return control in same state and key with no locks held.

- In AMODE as defined by linkedit of exit routine module and RMODE=ABOVE.
- In the HIS address space as H=P=S for any of the events, or in *MASTER* (ASID 1) with H=P=S for the "service has been disabled" call only.
- With no locks held in TCB mode.

Exit Recovery

The exit routine should provide its own recovery. If the exit routine abnormally terminates, its recovery routine will get control.

If the exit routine abnormally terminates, and the exit routine does not provide its own recovery, or the error percolates beyond the exit's recovery routine, a system recovery routine will get control. If this occurs 3 consecutive times, the exit routine will be disabled.

Exit Routine Processing

The system invokes the HIS.SERVSTAT exit routine or routines, if they are registered to the dynamic exits facility, anytime the HISSERV service has enabled, started, stopped, or has disabled.

Using the Information in the Parameter List: The system passes the address of a list of parameters to the exit routine. The parameters contain the following information:

- Version of this parameter area.
- The function code, which indicates why the exit routine was called. For this exit, it would be that the status of the service has changed.
- The reason code describing how the HISSERV service has changed.
 - (1) - The service has been enabled.
 - (2) - The service has been disabled.
 - (3) - The service has started profiling the system.
 - (4) - The service has stopped profiling the system.

See macro HISYEXIT in *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for more details on the interface.

Programming Considerations

Observe the following conventions when coding the HIS.SERVSTAT Exit routine:

- The exit routine is allowed to obtain and release any locks it desires in order to handle the exit, however performance degradation should be a concern.
- Code the exit routine to be reentrant.
- The exit is called whenever an event begins or ends. Therefore, when coding the exit routine, you should be aware that an increased path length will increase processor utilization and may degrade performance.
- Make sure that the exit routine does not get affected when new function code support is added.

Macro Instructions and Restrictions: The exit is not allowed to issue a HISSERV REQUEST=PROFILE request, or wait on a resource held by another work unit which might issue a HISSERV REQUEST=PROFILE request.

Be aware that the exit can create performance degradation. Do not perform unnecessary tasks.

Do not code the exit routine to invoke dynamic allocation.

Entry Specifications

The system passes the address of the exit parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

**Register
Contents**

0	Not applicable
1	Address of the exit parameter list
2-12	Not applicable
13	Address to a 216 byte save area
14	Return address
15	Entry point address of the exit routine

Parameter Descriptions: Register 1 contains the address of the exit parameter list, which is mapped by macro HISYEXIT in *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

The interface does not provide any field for a response; the exit does not need to return a valid value.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

**Register
Contents**

0-1	Does not need to be preserved
2-13	Restored to contents at entry
14-15	Does not need to be preserved

Coded Example of the Exit Routine

There is no coded example of this exit routine in SYS1.SAMPLIB.

Chapter 10. ICHRTX00 — MVS Router Exit

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routine” on page 50](#)
- [“Exit Routine Environment” on page 50](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 50](#)
- [“Programming Considerations” on page 51](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 51](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 52](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 53](#)

The system authorization facility (SAF) provides an installation with centralized control over system security processing through a system service called the MVS router. The MVS router provides a focal point for all products that provide resource management. The resource management components and subsystems call the MVS router as part of security decision-making functions in their processing, such as access control checking and authorization-related checking. These functions are called “control points”. SAF supports the use of common control points across products and across systems.

To use the MVS router, a resource management component or subsystem issues the RACROUTE macro. The RACROUTE macro accepts all valid parameters for any of the independent RACF system macros (RACDEF, RACINIT, RACHECK, RACLIST, RACXTRT, and FRACHECK). RACROUTE verifies that only valid parameters have been coded and then passes the parameters to the MVS router.

For more information on the RACROUTE macro and programming requirements for the ICHRTX00 exit, see *z/OS Security Server RACROUTE Macro Reference*.

The RACROUTE macro invokes the MVS router. When it is invoked, the MVS router first calls an optional installation exit routine. If an external security product (such as RACF) is active and installed on the system, the MVS router calls it next. This process is shown in [Figure 3 on page 50](#).




Figure 3. RACROUTE macro invokes the MVS router

If an external security product is not available, you can use the MVS router exit as an installation-written security processing (or routing) routine. If an external security product is available, you can use the MVS router exit as a preprocessing exit routine for the security product. The MVS router exit routine is ICHRTX00.

After MVS system initialization is complete, ICHRTX00 receives control for all subsequent requests for the duration of the IPL. See [“Programming Considerations” on page 51](#) for information on coding ICHRTX00.

Installing the Exit Routine

To install ICHRTX00, name the exit ICHRTX00 and load it into the link pack area (LPA). For general instructions on installing an exit routine, see [“Link editing an Installation Exit Routine into a Library” on page 3](#).

Exit Routine Environment

ICHRTX00 receives control in the following environment:

- Is entered via a branch and link macro. Therefore, the exit routine runs in the same key and state as the issuer of the RACROUTE macro.
- Enabled for interrupts.
- Must be linkedited with AMODE(ANY) and RMODE(24).
- Can be invoked with the local lock held.
- Caller's address space.
- Can be invoked in SRB mode. If the routine is invoked in SRB mode, the exit routine must follow SRB conventions.
- Can be invoked in cross-memory mode. If the routine is invoked in cross-memory mode, system services that invoke SVC routines cannot be used.

Exit Recovery: An installation must provide its own recovery routine for ICHRTX00. If the exit routine terminates abnormally, the recovery routine will get control first.

Exit Routine Processing

Normally, a caller invokes the MVS router and passes it class, requestor, and subsystem parameters via the RACROUTE parameter list. Using those parameters, the MVS router invokes ICHRTX00. ICHRTX00 returns to the MVS router with a return code that indicates whether further security processing is to occur.

If the return code is 0, the MVS router invokes the external security product by calling its router, ICHFR00. ICHFR00 will then invoke the other external security product processing and will report

the results of that invocation to the MVS router by placing a return code in register 15 and the detailed RACF-compatible return and reason codes in the first and second words (respectively) of the RACROUTE parameter list. For more information on the return codes the exit routine can set, see the description of registers at exit in [“Return Specifications” on page 52](#).

Simulating a Call to RACF: Instead of invoking the external security product, your installation may choose to have ICHRTX00 respond to the caller's request. In that case, you must still provide the caller with the RACF-compatible return and reason codes that it expects to receive. To do so, set the exit routine return code so that the external security product is not invoked (as described in [“Return Specifications” on page 52](#)). However, you must simulate the results of an external security product invocation by coding ICHRTX00 so it places the RACF-compatible return and reason codes in the RACROUTE parameter list.

RACF return and reason codes are documented in [z/OS Security Server RACROUTE Macro Reference](#).

Programming Considerations

ICHRTX00 must be reentrant.

In addition to the address of the RACROUTE parameter list, ICHRTX00 also receives the address of a 152-byte work area.

SAF performs functions other than being a router, such as creating security tokens for certain RACROUTE request types, propagating userids, and creating default control blocks (ACEEs) when an external security product is not available to the system. IBM recommends that, in coding ICHRTX00, you do not bypass these SAF functions. SAF creates and returns control blocks (tokens or ACEEs) whenever the RACROUTE request types are issued:

- REQUEST=VERIFYX
- REQUEST=TOKENMAP
- REQUEST=TOKENXTR
- REQUEST=TOKENBLD

SAF also creates default ACEEs for REQUEST=VERIFY when an external security product is not available on the system. System code, such as JES, requires these control blocks. Therefore, if your ICHRTX00 exit routine bypasses SAF security functions, your installation must construct and return the control blocks that SAF would have created. If you do not provide the required control blocks, problems can result. The token fields are mapped by macro ICHRUTKN (data area RUTKN). For a mapping of the RUTKN data area, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Macro Instructions and Restrictions: Do not install an exit routine that issues the WAIT macro or calls a service that issues a WAIT, such as WTOR. WAITs and implied WAITs can cause the system console or JES to stop functioning.

Entry Specifications

The MVS router passes to the exit routine (in Register 1), the address of a doubleword area that contains the addresses of:

- The RACROUTE parameter list and
- A work area that the exit routine can use.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

0

Not applicable

1

Address of the following area:

Offset	Length	Description
0	4	Parameter list address: points to the RACROUTE parameter list
4	4	Work area address: points to a 152-byte work area that ICHRTX00 can use.

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of the exit

Parameter Descriptions: The RACROUTE parameter list (SAFP) is mapped by macro ICHSAFP (data area SAFP). If an ICHRTX00 exit routine exists, the MVS router passes the SAFP to the exit. See *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for a mapping of the SAFP data area.

Return Specifications

A return code from the exit routine indicates whether the external security product is to be given control or further security processing is to be bypassed.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register
Contents
0-14

Restored to contents at entry.

15

One of the following return codes:

Hex/Dec
Explanation
X'0' (0)

The exit has completed successfully. Control proceeds to the external security product router (ICHRFR00) for further security processing and an invocation of the external security product.

X'C8' (200)

The exit routine has completed successfully. The MVS router translates this return code to an MVS router return code of 0 and returns control to the issuer of the RACROUTE macro, bypassing further SAF and any external security product processing. (See note.)

X'CC' (204)

The exit routine has completed successfully. The MVS router translates this return code to an MVS router return code of 4 and returns control to the issuer of the RACROUTE macro, bypassing further SAF and any external security product processing. (See note.)

X'D0' (208)

The exit routine has completed processing. The MVS router translates this return code to an MVS router return code of 8 and returns control to the issuer of the RACROUTE macro, bypassing further SAF and any external security product processing. (See note.)

Other

If the exit routine sets any other return code, the MVS router returns control directly to the issuer of the RACROUTE macro and passes the untranslated code as the MVS router return code. Further SAF and any external security product processing is bypassed.

Note: The installation is responsible for putting RACF-compatible return and reason codes in the first 2 fullwords, respectively, of the RACROUTE parameter list (SAFP). If the exit routine does not issue a specific reason code, it should issue a zero reason code.

Coded Example of the Exit Routine

A copy of a sample ICHRTX00 exit routine is provided in SYS1.SAMPLIB (in member RACINSTL).

Chapter 11. IEALIMIT — User Region Size Limit Exit

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routine” on page 55](#)
- [“Exit Routine Environment” on page 55](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 56](#)
 - IEALIMIT Default Values
- [“Programming Considerations” on page 57](#)
- [“Entry Specifications” on page 57](#)
 - Registers at Entry
- [“Return Specifications” on page 58](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 58](#)

An installation can limit application programs' access to nonextended private area storage (subpools 0-127, 129-132, 244, 251 and 252) by writing IEALIMIT. This exit routine is invoked before each job step is started. IEALIMIT can be used under MVS to set nonextended region size and nonextended region limit only. The values set by IEALIMIT should be less than the size of the nonextended private area. If they are not, the control program uses the size of the nonextended private area.

Use of the IEALIMIT exit may only reduce the amount of storage requested, not increase it.

The values set by IEALIMIT have no effect on establishing the extended region size and extended region limit. It is recommended that the exit routine IEFUSI be used in place of IEALIMIT when possible, especially when jobs are expected to specify a region value greater than 16 megabytes. IEFUSI can include region limit processing for the private area for both less than and greater than 16 megabytes. See Chapter 33, “IEFUSI — Step Initiation Exit,” on page 193 for a comparison of these two exit routines.

Limiting Region Size Consideration: If you want to use the IEALIMIT exit to control region size, and you have the IEFUSI exit available, ensure that the flag to bypass the IEALIMIT exit is not set in the IEFUSI parameter list.

The SMFLIMxx parmlib member provides the ability to set the REGION and reserve storage for system key storage obtains without writing an IEALIMIT or IEFUSI exit. For details, see:

- [z/OS MVS Initialization and Tuning Reference](#)
- [z/OS MVS Initialization and Tuning Guide](#)

Installing the Exit Routine

The IBM-supplied IEALIMIT exit routine is linkedited with the nucleus. To replace the IBM-supplied routine with your own IEALIMIT, you must linkedit your own version into the nucleus prior to an initial program load.

For general instructions on installing an exit routine, see [“Link editing an Installation Exit Routine into a Library” on page 3](#).

Exit Routine Environment

IEALIMIT receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 24 and RMODE 24.
- In any address space.
- Holds a local lock.
- Under the initiator's task.

Exit Recovery: The exit routine runs under an ESTAE. The VSM recovery routine that gets control should an error occur in the IEALIMIT exit will (1) fill in the SDWA (with IEALIMIT as the module name) and take an SVC dump, and then (2) either (a) retry the operation (including another call to the IEALIMIT exit) or (b) percolate, which could eventually result in an ABEND.

Because IEALIMIT is an authorized routine that runs in key 0, it can provide its own recovery routine, which would have the same capabilities as the IEALIMIT routine itself. The recovery routine would be subject to the limitations on all recovery routines, which are documented in the topic "Providing Recovery" of *z/OS MVS Programming: Authorized Assembler Services Guide*.

Exit Routine Processing

IEALIMIT gets control after an existing region has been freed, and before a new region is initialized. On entry, the IEALIMIT routine receives in register 0 the number of bytes requested by the application program for its region, as specified through the JCL REGION parameter. If this REGION value is less than 16 megabytes, the value in register 0 is the same as the REGION value. If this REGION value is greater than 16 megabytes, the value in register 0 is equal to the size of the nonextended private area minus 64K. Register 1 contains the same value as register 0.

If the JCL REGION parameter value is zero or if the parameter is absent, then the installation JES default value is used. If the JES default is zero, the IEALIMIT routine receives a zero in register 1.

After processing, the IEALIMIT routine returns values in both registers 0 and 1. Register 0 contains the number of bytes to be used as the region size which should be less than the size of the nonextended private area. Register 1 contains the number of bytes to be used as the region limit. Both registers 0 and 1 should be rounded to a multiple of 4K. These values in registers 0 and 1 determine how much space is allocated in the user's region, in response to GETMAIN and STORAGE requests.

IEALIMIT Default Values: If your installation does not supply an IEFUSI exit routine to control region size, and does not override the default values in the IBM-supplied IEALIMIT exit routine, users obtain the results shown in [Table 1 on page 56](#) when specifying various values for the region size on the REGION parameter.

Table 1. IEALIMIT Default Values		
JCL Region parameter	Results-below 16 Mb	Results-above 16 Mb
OK or OM	The job step is allocated all the storage available below 16 megabytes. The resulting size of the region below 16 megabytes is 16 megabytes minus the amount of virtual storage allocated to MVS.	The job step is allocated all the storage available above 16 megabytes. The resulting size of the region above 16 megabytes is 2 gigabytes minus the amount of virtual storage allocated to MVS, minus 16 megabytes.
> OK or OM and <= 16384K or 16M	Establishes the size of the private area below 16 megabytes. If the region size specified is not available below 16 megabytes, the job (or job step, if coded on the EXEC statement) abnormally terminates with an ABEND 822.	The extended region size is the default value of 32 megabytes

Table 1. IEALIMIT Default Values (continued)		
JCL Region parameter	Results-below 16 Mb	Results-above 16 Mb
> 16384K or 16M and <= 32768K or 32M	The job (or job step) is allocated all the storage available below 16 megabytes. The resulting size of the region below 16 megabytes is 16 megabytes minus the amount of virtual storage allocated to MVS.	The extended region size is the default value of 32 megabytes.
> 32768K or 32M and <= 2096128K or 2047M	The job (or job step) is allocated all the storage available below 16 megabytes. The resulting size of the region below 16 megabytes is 16 megabytes minus the amount of virtual storage allocated to MVS.	The extended region size is the specified value. If the region specified is not available above 16 megabytes, the job step receives whatever storage that is available above 16 megabytes, up to the requested amount. The resulting size of the region above 16 megabytes depends on system options and on what system software is installed.

Note that for the REGIONX keyword, the value passed to IEALIMIT will either be 0M (if the REGIONX second parameter is 0M) or the larger of the two specified REGIONX values. In that case, the "results-below 16MB" will be the amount specified in the first parameter or all storage available if 0M was specified for the first parameter. The "Results-Above 16 MB" will be the amount specified in the second parameter or all storage available if 0M was specified for the second parameter. Note that the extended region will not be less than 32MB.

See [z/OS MVS Initialization and Tuning Guide](#) for further information on the effect of the region limit and region size on requests for storage.

Programming Considerations

Code IEALIMIT to be reentrant. If this exit routine uses dynamic storage, use subpool 229, 230, or 249 for that storage. Do not use 0-127, as this will determine the key of the subpool for the duration of the jobstep. Common storage and LSQA are not recommended.

When using IEALIMIT to limit region size, the region size should be less than the region limit. This provides protection against programs that issue variable length GETMAINS with very large maximums and then do not immediately free part of that space, or free such a small amount that a subsequent GETMAIN (possibly issued by a system service) fails.

Entry Specifications

Either the value specified by the REGION parameter on the JOB or EXEC statement or the value of the JES default is passed to the IEALIMIT routine so that the exit can determine whether it is acceptable.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

0

If the application program requests a region that is less than 16 megabytes, then register 0 contains the size of the region requested by the application program.

If the application program requests a region that is greater than 16 megabytes, then register 0 contains a value equal to the size of the available private area minus 64K.

Note: An application program explicitly requests a region that is less than 16 megabytes by specifying 'REGION=xxM' on the JOB or EXEC JCL statements and making 'xx' less than or equal to 16.

An application program explicitly requests a region that is greater than 16 megabytes by specifying 'REGION=xxM' on the JOB or EXEC JCL statements and making 'xx' larger than 16.

An application program requests a default region by omitting the REGION parameter from both the JOB and EXEC JCL statements. The value that is passed in register 0 is controlled by JES.

1

The contents are the same as register 0.

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of IEALIMIT

Return Specifications

The IEALIMIT routine returns a region size and region limit.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0

The number of bytes to be used as the region size. This number should be less than the value in register 1.

1

The number of bytes to be used as the region limit. This value should be less than the size of the nonextended private area.

2-15

Restored to contents at entry

Coded Example of the Exit Routine

Figure 4 on page 58 is a coded example of the IEALIMIT exit routine.

```
* Save caller's registers and establish addressability.
      STM 14,15,12(13)
      STM 2,12,28(13)
      BALR 9,0
* If this is not a request for an unlimited
* region, then increase the region limit by 64K.
* The region size is not changed.
      LTR 1,1
      BZ EXIT
      AL 1,INCRMENT
* Restore caller's registers and return to caller.
EXIT   LM 14,15,12(13)
      LM 2,12,28(13)
      BR 14
INCRMENT DC F'65536'
```

Figure 4. Example: IEALIMIT exit routine

The IBM-supplied IEALIMIT routine as described in this topic does the following processing:

- If register 1 contains a nonzero value, the IEALIMIT routine adds 64K to its contents and returns to the caller. This value in register 1 is used to limit the allocation of storage from subpools 0-127, 129-132, 244, 251, and 252. The content of register 0 is unchanged.
- If register 1 contains a zero, the IEALIMIT routine returns a zero in register 1 to the caller. This indicates that no limit is assigned to the job, started program, or TSO/E user.

Chapter 12. IEAVADFM — Format SNAP, SYSABEND, and SYSUDUMP Dumps

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routine” on page 59](#)
- [“Defining Dump Formatting Exits to IEAVADFM” on page 60](#)
 - Adding and Deleting Exit Names in IEAVADFM
- [“Exit Routine Environment” on page 62](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 62](#)
- [“Programming Considerations” on page 62](#)
- [“Entry Specifications” on page 63](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 63](#)
 - Registers at Exit

IEAVADFM is a dump facility installation exit routine name list. It contains a list of installation exit routine names to be given control during the formatting of a SNAP or ABEND dump. An installation can use these exit routines to:

- Gather information to be included in a SNAP/ABEND dump and
- Format the information to be written to a data set described by a SYSABEND, SYSUDUMP, or installation-defined JCL DD statement.

The installation exit routines listed in IEAVADFM are invoked during the control block formatting phase of every SNAP or ABEND dump for which the CB option was specified. The system provides to the exit routines:

- A buffer in which the routines can build a print line
- The address of an IBM-supplied print routine to which the exit routines can pass the line for printing.

The difference between IEAVADFM and IEAVADUS is that IEAVADFM is an **installation exit name list** while IEAVADUS is a **single exit routine**. The routine names listed in IEAVADFM are invoked sequentially and maintain control until the end of the list of routines is reached or until a routine within the list returns a terminating code. IEAVADUS receives control once for each SNAP dump or ABEND dump and then returns control to the calling program.

Installing the Exit Routine

To install a dump formatting installation exit routine in your system, you need to do the following :

- Linkedit the dump formatting exit routine into SYS1.LPALIB, SYS1.LINKLIB, or a data set in the LNKLIB concatenation.
- Define the dump formatting exit routine to MVS by adding its load module name to the exit name list in IEAVADFM.

Defining Dump Formatting Exits to IEAVADFM

You can specify dump formatting exits in any of the blank entries in the IEAVADFM exit name list. During the formatting of a SNAP or ABEND dump, the system invokes the routines in the order you specified them. That is, the exit routine specified in entry 1 gets control first, followed by the exit routine specified in entry 2, and so on.

IEAVADFM is a CSECT in load module IGC0805A (which resides in SYS1.LPALIB). The IBM-supplied version of IEAVADFM contains the following entries:

- Four 8-byte entries that contain hexadecimal zeroes, and are intended for customer use, followed by
- A final 4-byte entry that contains hexadecimal zeroes to indicate the end of the exit name list (the end-of-table marker).

You can add as many dump formatting exit routine load modules to IEAVADFM as you want. IBM recommends that you use the existing blank entries in IEAVADFM before creating new ones. Ensure that the last entry contains 4 bytes of hexadecimal zeroes.

Contents of Entries: The first four 8-byte entries contain the exit load module name. These entries contain hexadecimal zeroes, and are available for customer use.

This is how the first, second, and last entries in IEAVADFM appear:

IEAVADFM		
HEX LOCATION:	CONTENTS:	
0000	00000000 00000000	ENTRY 1
0008	00000000 00000000	ENTRY 2
.	.	.
.	.	.
0040	00000000	END OF LIST

To insert a dump formatting exit load module name in the list, select an available entry (one that is set to hexadecimal zeroes) and substitute the exit load module name in place of the hexadecimal zeroes. Exit names can be one to eight characters, padded to the right with blanks.

Examples of changing entries in IEAVADFM are shown in the sections that follow .

Adding and Deleting Exit Names in IEAVADFM: To add or delete exit names in the exit name list, you must modify the IEAVADFM object code in SYS1.LPALIB through the use of the SPZAP program, or through SMP/E. For more information, refer to [“Using SPZAP or SMP/E to Add or Delete Name”](#) on page 60.

Using SPZAP or SMP/E to Add or Delete Name

Adding Exit Names: When using SPZAP or SMP/E, take the following steps:

- Use SPZAP to produce a dump of IEAVADFM. Sample JCL follows:

```
//DUMPJCL JOB MSGLEVEL=(1,1)
//STEP EXEC PGM=AMASPZAP
//SYSPRINT DD SYSOUT=*
//SYSLIB DD DSNAME=SYS1.LPALIB,DISP=OLD
//SYSIN DD *
NAME IEAVADFM
DUMP IEAVADFM
/*
```

- Use the dump produced to select an available entry in IEAVADFM.
- Write the name of the dump formatting exit module in the entry. (See Example 1 if you are using SPZAP or Example 1A if you are using SMP/E.)

The changes will take affect on the next IPL.

Example 1 - Using SPZAP to Add Exit Names: The following job adds EXITRTN1 to the first entry in IEAVADFM, and EXITRTN2 to the second entry in IEAVADFM. The job then dumps IEAVADFM to verify the changes.

```
//EXAMPLE1 JOB MSGLEVEL=(1,1)
//STEP      EXEC PGM=AMASPZAP
//SYSPRINT  DD SYSOUT=*
//SYSLIB    DD DSN=SYS1.LPALIB,DISP=OLD
//SYSIN     DD *
NAME IEAVADFM
VER 0000 0000,0000,0000,0000    FIRST UNUSED ENTRY
REP 0000 C5E7,C9E3,D9E3,D5F1    SET TO EXITRTN1
VER 0008 0000,0000,0000,0000    SECOND UNUSED ENTRY
REP 0008 C5E7,C9E3,D9E3,D5F2    SET TO EXITRTN2
DUMP IEAVADFM
/*
```

Example 1A - Using SMP/E to Add Exit Names: The following job adds EXITRTN1 to the first entry in IEAVADFM, and EXITRTN2 to the second entry in IEAVADFM.

```
++USERMOD(USRM0D2).
++VER(Z038) FMID(HBB4410). /* CHANGE THE FMID AS NEEDED */
++ZAP(IEAVADFM).
NAME IEAVADFM IEAVADFM
VER 0000 0000,0000,0000,0000    FIRST UNUSED ENTRY
REP 0000 C5E7,C9E3,D9E3,D5F1    SET TO EXITRTN1
VER 0008 0000,0000,0000,0000    SECOND UNUSED ENTRY
REP 0008 C5E7,C9E3,D9E3,D5F2    SET TO EXITRTN2
```

Deleting Exit Names: When using SPZAP or SMP/E, take the following steps:

- Use SPZAP to dump IEAVADFM (as shown earlier in the sample JCL code under [“Using SPZAP or SMP/E to Add or Delete Name”](#) on page 60).
- Write X'40' (blanks) in place of the dump formatting exit module name. (See Example 2 if you are using SPZAP or Example 2A if you are using SMP/E.)

The changes will take effect on the next IPL.

If all entries are in use, you can replace module IEAVADFM, or expand it. Ensure that the last entry contains 4 bytes of hexadecimal zeroes.

Example 2 - Using SPZAP to Delete Exit Names: The following job deletes EXITRTN1 from the dump formatting exit list. The job then dumps IEAVADFM to verify the changes.

```
//EXAMPLE2 JOB MSGLEVEL=(1,1)
//STEP      EXEC PGM=AMASPZAP
//SYSPRINT  DD SYSOUT=*
//SYSLIB    DD DSN=SYS1.LPALIB,DISP=OLD
//SYSIN     DD *
NAME IEAVADFM
VER 0000 C5E7,C9E3,D9E3,D5F1    EXITRTN1
REP 0000 4040,4040,4040,4040    RESTORE ENTRY 1
DUMP IEAVADFM
/*
```

Example 2A - Using SMP/E to Delete Exit Names: The following job deletes EXITRTN1 from the dump formatting exit list.

```
++USERMOD(USRM0D3).
++VER(Z038) FMID(HBB4410). /* CHANGE THE FMID AS NEEDED */
++ZAP(IEAVADFM).
NAME IEAVADFM IEAVADFM
VER 0000 C5E7,C9E3,D9E3,D5F1    EXITRTN1
REP 0000 4040,4040,4040,4040    REPLACE WITH BLANKS
```

For additional information on the use of:

- SPZAP, see [z/OS MVS Diagnosis: Tools and Service Aids](#).
- SMP, see [z/OS SMP/E User's Guide](#).
- Expand, see [z/OS MVS Program Management: User's Guide and Reference](#).

Exit Routine Environment

Each routine in IEAVADFM receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In the AMODE and RMODE specified in the routine or in the linkedit.
- In the address space of the task taking the dump.
- With no locks held.
- Under the task associated with the request block that requested the dump. Each routine runs under the SVRB of SNAP/ABDUMP.

Exit Recovery: An ESTAE routine provides recovery for SNAP. Each user formatting routine listed in IEAVADFM should, however, also set up its own recovery to handle any ABENDs encountered during the formatting process. Each recovery routine should either recover and continue, or recover and return to SNAP with a zero return code. A nonzero return code is interpreted as a GETMAIN failure, causing the following message in the dump data set:

```
USER/PP CONTROL BLOCKS UNAVAILABLE
```

The dump is truncated because of lack of storage. The recovery routine should not continue formatting if a X'37' ABEND occurs, because no space remains in the dump data set. Before the recovery routine returns to SNAP, it should free all the storage that it has obtained.

If the user formatting routine does not establish recovery, or if the recovery exit specifies continue-with-termination after an ABEND, SNAP terminates this control block formatter entirely and continues with the next portion of the dump, if any.

Exit Routine Processing

The installation exit routines listed in IEAVADFM receive control automatically during the control block formatting phase of every SNAP or ABEND dump for which the CB option was requested.

The routines build one print line at a time in the buffer provided and use BALR to branch to the IBM-supplied print routine, which in turn prints the line to the dump data set. Offsets are recommended for all formatted control blocks that are longer than one output line. (One line generally formats 20 hexadecimal characters). The print routine saves registers, prints the line, blanks the buffer, restores the registers, and returns control to the user's routine via register 14.

Programming Considerations

Code each routine in the IEAVADFM name list to be reentrant.

In order to avoid an abnormal termination later in the SNAP/ABEND routine, the user's routines must not free either the entry parameter list or the print buffer.

IEAVADFM works through the IBM-supplied print routine, so the formatting exit does not have any direct access to the carriage controls. Therefore, in order to cause a skipped line in the dump output, you must pass a blank buffer to the print routine. The print routine handles page ejects. The installation exit routine can use format patterns to format data in the output buffer, by using the IBM-supplied format service routine. The service routine can also convert data to printable hexadecimal. This service routine is the same routine that is provided by the IPCS service aid; see [z/OS MVS IPCS Customization](#). No registers are necessary as input to this service routine.

IBM-Supplied Print Routine: The installation exit routines listed in IEAVADFM can use the IBM-supplied print routine to format data to the dump data set. The print routine is pointed to by the ADPLPRNT field in the exit parameter list and is mapped by macro BLSABDPL (data area BLSABDPL). For a mapping of the BLSABDPL data area, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

The interface to the print routine is:

- *Entry:* via BALR 14,15 for each line to be written.
- *Environment:* PSW key 0, supervisor state, no locks held.

Entry Specifications

The ABDUMP calling routine passes to each installation exit routine in IEAVADFM the address of a parameter list useful for formatting the dump data.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of the parameter list (mapped by IHAABDPL) for the user formatting routine.

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of the installation exit routine listed in IEAVADFM

Parameter List Contents: Register 1 points to a parameter list that provides the addresses of subroutines and data that the user-written format routines will use. This is the same parameter list used by exit routine IEAVADUS.

This parameter list is mapped by the BLSABDPL mapping macro (data area BLSABDPL). The mapping list includes all the fields of the IPCS service aid's parameter list so user formatting routines can be invoked by either SNAP/ABEND or IPCS.

The BLSABDPL mapping is documented in *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

The installation exit routine returns a code indicating whether processing should continue.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-14

Restored to contents at entry

15

One of the following return codes:

Return Code

Explanation

- 0** Continue processing.
- 4** Request is not valid.
- 12** Suppress the remainder of the SNAP/ABEND dump. If the same installation exit routine is executed under the IPCS service aid, print dump does not suppress the remainder of the dump.

Chapter 13. IEAVADUS — Select and Format Dump Data Exit

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routine” on page 65](#)
- [“Exit Routine Environment” on page 65](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 66](#)
- [“Programming Considerations” on page 66](#)
- [“Entry Specifications” on page 67](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 68](#)
 - Registers at Exit

You can use the IEAVADUS installation exit to select and format data to be included in an ABDUMP (SNAP/ABEND dump). The selected data is written to a data set described by a SYSABEND, SYSUDUMP, or installation-defined JCL DD statement. The system provides an area in which IEAVADUS builds a print line and also provides the address of an IBM-supplied print routine to which the installation exit routine passes the line for printing.

The difference between IEAVADUS and IEAVADFM is that the exit routine IEAVADUS is a **single exit routine** while IEAVADFM is an **installation exit name list**. IEAVADUS receives control once for each SNAP dump or ABEND dump. Your IEAVADUS installation exit routine replaces one already supplied with your system. In contrast, the routine names in IEAVADFM are invoked sequentially when IEAVADFM receives control. IEAVADFM maintains control until the end of the list of routines is reached or until a routine within the list returns a terminating code.

Installing the Exit Routine

To use IEAVADUS, you must linkedit the exit routine into SYS1.LPALIB with the load module name of IGC0905A, replacing the IBM-supplied routine IEAVADUS.

To remove the installation exit routine from the system, linkedit a copy of module IEFBR14 into SYS1.LPALIB with the name IGC0905A.

Exit Routine Environment

IEAVADUS receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In the AMODE and RMODE specified in the routine or in the linkedit.
- In the address space of the task taking the dump.
- With no locks held.
- Under the task associated with the request block that requested the dump. The routine runs under the SVRB of SNAP/ABEND.

Exit Recovery: An ESTAE routine provides recovery for SNAP. IEAVADUS should, however, also set up its own recovery to handle any ABENDs encountered during the formatting process. The routine should either recover and continue, or recover and return to SNAP with a zero return code. A nonzero return code is interpreted as a GETMAIN failure, causing the following message in the dump data set:

```
USER/PP CONTROL BLOCKS UNAVAILABLE
```

The dump is truncated because of lack of storage. The recovery routine should not continue formatting if a X'37' ABEND occurs, because no space remains in the dump data set. Before the recovery routine returns to SNAP, it should free all the storage that it has obtained.

If the IEAVADUS routine does not establish recovery, or if the recovery exit specifies continue-with-termination after an ABEND, SNAP terminates this control block formatter entirely and continues with the next portion of the dump, if any.

Exit Routine Processing

IEAVADUS receives control automatically during the control block formatting phase of every SNAP and ABEND dump for which the CB option was requested.

IEAVADUS builds one print line at a time in the buffer whose address is in the exit parameter list (in the ADPLBUF field). To print the line on the dump data set, IEAVADUS invokes the IBM-supplied print routine (via BALR or CALL). Offsets are recommended for all formatted control blocks that are longer than one output line. (One line generally formats 20 hexadecimal characters.) The print routine saves registers, prints the line, blanks the buffer, restores the registers, and returns control to IEAVADUS via register 14.

When all lines have been selected and printed, IEAVADUS restores the entry registers and returns to SNAP/ABDUMP.

Note: IEAVADUS can format and print an entire control block in one invocation of the IPCS control block formatter service. See "Writing IPCS Exit Routines" in *z/OS MVS IPCS Customization* for information on how to define a control block model to SNAP/ABDUMP.

Programming Considerations

Code your IEAVADUS routine to be reentrant.

Return from IEAVADUS to SNAP/ABDUMP must be made in protection key 0, supervisor state, with no locks held (the same state as when IEAVADUS was entered).

In order to avoid an abnormal termination later in the SNAP/ABEND routine, the user's routines must not free either the entry parameter list or the print buffer.

Because IEAVADUS works through the IBM-supplied print routine, IEAVADUS has no direct access to the carriage controls. Therefore, to cause a skipped line in the dump output, you must code IEAVADUS to pass a blank buffer to the print routine.

The print routine handles page ejects.

IEAVADUS can use format patterns to format data in the output buffer by using the IBM-supplied format service routine. The service routine can also convert data to printable hexadecimal. This service routine is the same routine that is provided by the IPCS service aid; see *z/OS MVS IPCS Customization*.

IEAVADUS can use the subpool indicated in ADPLSBPL for all working storage.

The IPCS Control Block Formatter Service: Before invoking the IPCS control block formatter service, IEAVADUS initializes several fields in the exit parameter list (in the ADPLPFMT area) as follows:

Field

IEAVADUS Sets to:

ADPLPBLC

Number of blank lines the formatter will skip

ADPLPCHA

Control block acronym (for example, "TCBnnnn")

ADPLBAS

0

ADPLPBLs

0

ADPLPBAV

The virtual address of the control block

ADPLPVCL

The view control; IEAVADUS sets this field to select the individual fields to be printed in the dump

Invoking the Service: Code IEAVADUS to take the following steps to invoke the IPCS control block formatter service:

1. Create and pass a 3-word parameter list to the control block formatter routine, ADPLESRV. Before passing the 3-word parameter list, IEAVADUS places the values shown in [Table 2 on page 67](#) in the parameter list.

Table 2. Values Passed to ADPLESRV	
Field	Description
Word 1	Address of the ABDPL
Word 2	Address of the control block service code (ADPLSCBF)
Word 3	Address of the control block formatter service parameter list (ADPLPFMT)

2. Set register to the address of the 3-word parameter list
3. Call the exit services router (its address is in the ADPLSERV field of the exit parameter list). The remaining fields needed by the control block formatter service have already been initialized by SNAP/ABDUMP.

See “Using the IBM-supplied Exit Service Routines” in [z/OS MVS IPCS Customization](#) for more information about the IPCS control block formatter service.

The IBM-Supplied Print Routine: IEAVADUS can use the IBM-supplied print routine to format data to the dump data set. The print routine is pointed to by the ADPLPRNT field in the exit parameter list and is mapped by macro BLSABDPL (data area BLSABDPL). For a mapping of the BLSABDPL data area, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

The interface to the print routine is:

- *Entry:* via BALR 14, 15 for each line to be written.
- *Environment:* PSW key 0, supervisor state, no locks held.

Entry Specifications

The ABDUMP calling routine passes to IEAVADUS the address of a parameter list that contains information the exit routine can use to format the dump data.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register**Contents**

0

Not applicable

1

Address of a parameter list (mapped by IHAABDPL) for the user formatting routine

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of IEAVADUS

Parameter List Contents: Register 1 points to a parameter list that provides the addresses of subroutines and data that the user written format routines will use.

This parameter list is mapped by the BLSABDPL mapping macro (data area BLSABDPL). The mapping list includes all the fields of the IPCS service aid's parameter list so user formatting routines can be invoked by either SNAP/ABEND or IPCS.

The BLSABDPL mapping is documented in *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

A return code from IEAVADUS indicates whether the exit routine is to continue processing or to suppress the remainder of the dump.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0-14

Restored to contents at entry

15

One of the following return codes:

Return Code	Explanation
-------------	-------------

0	Continue processing.
4	Request is not valid.
12	Suppress the remainder of the ABEND dump. If the same exit routine is executed under the IPCS service aid, print dump does not suppress the remainder of the dump.

Chapter 14. IEAVMXIT — Installation-Specified MPF Exits

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routine” on page 70](#)
 - Replacing the Exit Routine Without a Re-IPL
- [“Exit Routine Environment” on page 71](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 72](#)
 - Message Processing Considerations
- [“Programming Considerations” on page 73](#)
 - Macro Instructions and Restrictions
 - Security Consideration
- [“Entry Specifications” on page 76](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 76](#)
 - Registers at Exit
- [“Coded Examples of MPF Exit Routines” on page 77](#)

The IEAVMXIT installation exit or an MPF installation exit (one that you specify on the USEREXIT parameter in an MPFLSTxx member of SYS1.PARMLIB) allows you to modify message processing in a system or sysplex. IEAVMXIT is the general-purpose exit routine that does processing that is common to many messages (WTOs). An MPF exit routine does processing that is specific to a certain type of message or a particular message ID.

For information on the MPFLSTxx member of SYS1.PARMLIB, see [z/OS MVS Initialization and Tuning Reference](#).

You can use IEAVMXIT or an MPF exit routine to:

- Modify the presentation of messages by:
 - Changing the text and descriptor codes of selected messages.

Changing the descriptor code can alter the retention of the message on a console screen and in the Action Message Retention Facility (AMRF). It can also affect the color of a message when it is displayed on a console with color capabilities.
 - Changing the color, intensity, and highlighting of messages.
- Modify the routing of messages by:
 - Changing the routing codes of selected messages.
 - Changing either the console name or the console ID to which the message is queued.
 - Selectively routing messages to a specific console.
 - Queuing messages to a particular active console.
 - Queuing messages by routing codes.
 - Directing messages to hardcopy only.

- Indicating whether or not to broadcast a message to active consoles.
- Reducing message traffic at specific consoles by redirecting some traffic.
- Indicating whether or not the message should be routed to the consoles that requested to see the message as the result of a MONITOR command.
- Reduce operator workload through message suppression or automation by:
 - *Selectively* suppressing (filtering) occurrences of messages. (MPF suppresses *all* occurrences of a particular message.)
 - Performing error thresholding.
 - Indicating whether or not the action message retention facility (AMRF) is to retain an action message.
 - Overriding message processing facility (MPF) suppression.
 - Handling the common requests (WTORs) from the system.
 - Altering the automation token specified in the MFPLSTxx member of SYS1.PARMLIB.
 - Indicating whether to consider a message for automation.
 - Deleting a message

If an IEAVMXIT message exit already exists in the installation and you require that the installation uses message flood automation, you can either integrate the existing IEAVMXIT with message flood automation, or call message flood automation from IEAVMXIT. For more details about customizing the IEAVMXIT, see [z/OS MVS Planning: Operations](#).

Installing the Exit Routine

IEAVMXIT: The IEAVMXIT exit routine is an installation-coded module. When you install this exit routine you must name it IEAVMXIT.

Specify whether you want to have IEAVMXIT active or not active at IPL by specifying either (Y) or (N) on the UEXIT keyword on the INIT statement of the CONSOLxx parmlib member. If you do not specify the UEXIT keyword, the system assumes the default, which is UEXIT(Y), and activates IEAVMXIT if it is installed.

You must provide your own IEAVMXIT routine if you specify UEXIT with the (Y) option or expect the system to default to (Y).

If your IEAVMXIT routine is active at IPL, it will be invoked for all of the messages that were issued during IPL and NIP. This invocation is done after NIP is over, when the messages are re-issued to be recorded in the hardcopy log.

Operators can use the CONTROL M command to change the online status of IEAVMXIT.

You can insert your IEAVMXIT exit routine into the control program by:

- Linkediting it into the LNKLST. Use 31-bit addresses in the routine and assemble it with AMODE 31 and RMODE ANY.
- Activating it with the CONTROL M, UEXIT=Y command.

MPF Exit Routine: When an MPF exit routine is installed, its address is located during the processing of the SET MPF command (and the associated processing of the specified MPFLSTxx member of SYS1.PARMLIB). When the MPF exit routine is to be invoked, its address is passed to the installation exit interface, and the exit routine is invoked via standard linkage.

Do not use the name IEAVMXIT as the name of an MPF exit that you specify in the MPFLSTxx parmlib member.

Operators can use the SET MPF command to change the online status of MPF exit routines.

You can insert MPF exit routines into the control program by following these steps:

1. Link-edit them into an APF-authorized library that is part of the LNKLST concatenation. Use 31-bit addresses in the routines and assemble them with AMODE 31 and RMODE ANY.

2. Put the name of each MPF exit routine you write into the MPFLSTxx parmlib member. Specify the name of the exit routine on the USEREXIT parameter of the message ID entry for each message the exit routine is to process.
3. Activate the MPFLSTxx member with a SET MPF=xx command.

Replacing the Exit Routine Without a Re-IPL:

There may be times when you need to replace IEAVMXIT or an MPF exit routine, either because you want to add functions to the routine or because the routine abended when it was processing a particular message. Depending on whether the routine is IEAVMXIT or an installation-specified MPF exit routine, the procedures are as follows:

IEAVMXIT: To replace your IEAVMXIT exit routine with a fresh copy, take the following steps:

- Linkedit the new copy of IEAVMXIT into the LNKLST.
- Refresh LLA with the MODIFY LLA,REFRESH command.

If you make the message exit available by changing the libraries referred to in the LINKLIST concatenation, you must issue the

```
SETPROG LNKLST, UPDATE, JOB=CONSOLE
```

command to cause the Console address space to use the new LINKLIST concatenation. The K M command runs in the Console address space.

- Reload and reactivate the exit routine using the K M, UEXIT=Y command.

MPF Exit Routine: To replace an MPF exit routine with a fresh copy, take the following steps:

- Link-edit the new copy of the exit routine into an APF-authorized library that is part of the LNKLST concatenation.
- Refresh LLA with the MODIFY LLA,REFRESH command.

If you make the message exit available by changing the libraries referred to in the LINKLIST concatenation, you must issue the

```
SETPROG LNKLST, UPDATE, JOB=*MASTER*
```

command to cause the Master Schedule address space to use the new LINKLIST concatenation. The SET MPF command runs in the Master Schedule address space.

- Reload and reactivate the exit routine using the SET MPF=xx command.

Exit Routine Environment

The IEAVMXIT and MPF exit routines receive control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 31 and RMODE ANY.
- With no locks held; they MUST return control with no locks held.
- Address space of the WTO issuer.

Exit Recovery: The IEAVMXIT and MPF exit routines must provide their own level of recovery because, with one exception, the system does not continue to pass control to an exit routine after it abnormally terminates.

The exception is when an exit routine is to be deactivated (via the CONTROL M command for IEAVMXIT, and the SET MPF command for MPF exit routines) and the contents of the exit routine's individual data area are nonzero. In this case, the routine is given control before it is deactivated, so that it can clean up any work areas it may have created.

For information on how to reactivate the exit routine if it abnormally terminates, see [“Replacing the Exit Routine Without a Re-IPL:”](#) on page 71.

For information on the individual data area, see [“Programming Considerations”](#) on page 73.

Exit Routine Processing

The IEAVMXIT and MPF exit routines get control during MPF processing. The IEAVMXIT and MPF exit routines are mutually exclusive. For a particular message ID, if you have not named an MPF exit routine to do specific processing, IEAVMXIT, the general-purpose exit routine, receives control.

The control program calls IEAVMXIT or an MPF exit routine for all single-line messages. For a multiple-line message, the program calls the exit routine only for the first line of the message, unless the routine requests minor-line processing. When the exit routine requests minor-line processing, all minor lines will be processed. The default is to bypass minor-line processing.

Message Processing Considerations: Your exit will receive all of the parameters of the message in a parameter list that is known as the CTXT. The CTXT is mapped by macro IEZVX100 that is found in the SYS1.MODGEN system library. When planning to write the IEAVMXIT or an MPF exit routine, you should consider carefully the steps that are necessary to process the message. One step might be sufficient to obtain your desired result; other cases might require several steps.

Request Processing: Your exit can examine all of the attributes of a message and can alter almost all of them. To alter an attribute of a message, you must alter the attribute in the CTXT parameter list and indicate through a "request flag" that the alteration is to be made in the actual message. You can only alter fields that have request flags associated with them. Alterations to fields that do not have request flags associated with them will be ignored.

Although you can alter many of the attributes of a message, you cannot convert a single-line message into a multi-line message or a multi-line message into a single-line message. You cannot convert a single-line message into a Write To Operator with Reply (WTOR) message or a WTOR message into a single-line message.

The following are two examples of the planning that is necessary before you code your exit routine to process a message:

- To request queuing of a message to a particular console and to eliminate queuing by routing codes, the steps are:
 1. Request queuing to a particular console
 2. Request a change to the console ID or console name
 3. Specify the desired console ID or console name
 4. Request a change to the routing codes
 5. Change the routing codes to all zeroes
- To request queuing a message by routing codes only and also change the text of the message, the steps are:
 1. Request queuing by routing codes only
 2. Change the routing code to whatever is desired
 3. Request a change in the message text
 4. Specify the new length of the text
 5. Supply the new text

Incompatible Requests: The system handles incompatible requests in one of two ways. If IEAVMXIT or an MPF exit makes conflicting requests, the message is either (1) processed in its original state or (2) processed according to the request that is least detrimental to the message.

Incompatible request errors are signaled in the "MPF request flag" field in the SYSLOG.

The following incompatible requests cause the message to be processed in its original state:

- A request to delete a message (CTXTRDTM) and a request in the request flags in CTXTRFLG that specifies processing other than a request to affect the automation (CTXTRAYS or CTXTRANO) of the message. Any requests in the extended request flags (CTXTERFS) may be specified with the request to delete a message, including the request to suppress the message from JOBLOG (CTXTESJL)
- A request to queue via routing codes only (CTXTRQRC) and a request to:
 - Queue to a particular active console (CTXTRQPC)
 - Queue to hardcopy only (CTXTRHCO)
 - Change the message type (CTXTRCMF)
- A request to queue a message to hardcopy only (CTXTRHCO) and a request to broadcast the message to active consoles (CTXTRBCA)
- A request to retain a message (CTXTRRET) and a request not to retain a message (CTXTRNRT)
- A request to automate a message (CTXTRAYS) and a request not to automate a message (CTXTRANO)
- A request to allow the primary subsystem to alter message routing (CTXTEMRM) and a request not to allow the primary subsystem to alter message routing (CTXTEMRN)

The following incompatible requests cause the message to be processed according to the request that is least detrimental to the message:

- A request to change both the name (CTXTRCNM) and the ID of the console (CTXTRCFC) to which a message is queued causes only the console name to change. If the specified console name is not valid, no change occurs, regardless of whether the specified console ID is valid.
- A request to send a message to hardcopy (CTXTRFHC) and a request to not send a message to hardcopy (CTXTRNHC) results in a hardcopy of the message.
- A request to send a message to hardcopy while allowing display at a console (CTXTRFHC) and a request to send a message only to hardcopy (CTXTRHCO) causes the message to be sent to hardcopy as well as displayed at any console to which it might be queued.
- A request to send a message to only hardcopy (CTXTRHCO) and a request not to send a message to hardcopy (CTXTRNHC) results in only sending a message to hardcopy.
- A request to broadcast a message (CTXTRBCA) and a request to not broadcast a message (CTXTRBCN) results in not broadcasting the message.

Previous Requests: In a JES3 complex, messages pass through MPF twice - once on the LOCAL processor, and once on the GLOBAL processor. If your exit is running on the GLOBAL processor, you can determine what was altered by an MPF exit on the LOCAL processor by looking at the previous request flags pointed to by CTXTPREQ.

You can observe the alterations that your exit has made to a message by examining the message in the SYSLOG. Each record in the SYSLOG is mapped by macro IHAHCLOG which is found in the SYS1.MODGEN system library. The HCLREQFL User Exit/MPF Request Flags field in each SYSLOG record indicates the actions taken against the message by MPF, an MPF exit, or by a subsystem on the Subsystem Interface (SSI). If you requested that a message be deleted, it will not be present in the SYSLOG.

If your exit made an incompatible request, this is also indicated in the HCLREQFL field.

Programming Considerations

When you code an IEAVMXIT routine or an MPF exit routine, observe the following conventions:

- Code the routine to be reentrant and serially reusable.
- Code the routine to use 31-bit addresses with AMODE 31 and allow residency above the 16 MB line with RMODE ANY.
- Do not code an installation exit that receives control for a message that the exit issues; this causes an endless loop. The exit must be coded so that when it receives control for that message, it does not issue the message again.

- Do not use services (ENQ) or perform actions (I/O) that can result in a WAIT since this might delay or even hang the message issuer and z/OS console support.
- Do not use message intensity fields when coding an MPF exit and using a multicolor screen. Message highlighting is best achieved by requesting a color change for specified message.
- If you specify message text or a message text length value that exceeds the maximum length allowed for that type of message, the system truncates the message.
- When suppressing write-to-programmer (WTP) messages, either change the routing code so that routing code 11 is not specified (CTXTRCRC is ON and CTXTR11 is OFF), or set bit CTXTNWTP ("do not do WTP processing") ON.
- Some messages are issued using the MSGTYP parameter on the WTO macro, causing the message to be routed to the consoles that requested to see the message as the result of a MONITOR command. To queue these messages by any other queueing attribute (for example, by console ID or route codes), it is necessary to zero the message type bytes. To determine if an IBM message is routed to consoles as a result of the MONITOR command, please refer to the CTXTMTYP field.
- To prevent almost all further processing of a message, set these bits ON:

Bit**Description****CTXTRDTM**

"Delete the message." The message will not be displayed on consoles or logged in hardcopy.

CTXTRANO

"Automation is not required for this message." The message will not be sent to EMCS consoles receiving automation messages.

CTXTESJL

"Suppress from joblog." The message will not go into the JES job log.

CTXTNWTP

"Do not do WTP processing." The message will not be sent to a TSO user's terminal or to the system message data set of a batch job.

Setting those four bits ON will prevent almost all of the usual message processing. However, the message is still shown on the message SSI. Use extreme caution when doing this to a message because there will be no record of it in the system.

- Messages can be queued exclusively to EMCS consoles that are receiving automation messages. To do this, use the CTXTRDTM, CTXTESJL, and CTXTNWTP bits. Then either use CTXTRAYS or specify AUTO(YES) in the MPFLSTxx member for a particular message.
- Do **not** add routing code 11 to message IEF170I, as this causes an endless loop.
- You must explicitly request processing for subsequent lines of a multiple-line WTO, by setting the CTXTRPML bit in the CTXT to 1.
- When processing minor lines of a multiple-line WTO, the installation exit can change only the message text of the current minor line.
- On entry, the CTXT indicates (in the CTXTSYSN field) which system sent the message.
- If the WTO/R is a branch-entry WTO/R, the CTXTNBEW bit is set to 1. This is for informational purposes only.
- IEAVMXIT and MPF exit routines will **not** be invoked during the initial processing of synchronous WTOs or WTORs. The exit routine will be invoked when the message is later issued (via SVC) to the hardcopy log.
- Some messages (such as \$HASP373) have their text completed when WTO calls the subsystem interface. This call occurs after the exit routine completes its processing.
- When replying to a WTOR, you should note the following restrictions:
 - An exit routine should reply to a suppressed WTOR (using the MGCRE macro); otherwise, the WTOR remains outstanding but will not be displayed unless the operator issues a DISPLAY R command.

- An installation exit should not request deletion of a WTOR; a request for deletion results in suppression of the WTOR. The operator will not be aware of the WTOR unless the operator issues the DISPLAY R command.
- A WTOR may not be displayed on an MCS console when the reply is processed before the message can be displayed. A WTOR that is replied to with an exit routine can be seen in the hard-copy log.
- IEAVMXIT or the MPF exit routine uses the following fields in the CTXT to determine the WTOR message for which it has been invoked:

Field**Description****CTXTRPYB**

Binary representation of the message reply ID

CTXTRPYL

Length of the reply ID (halfword)

CTXTRPYI

The reply id, in EBCDIC (8 bytes, left-justified, and padded with blanks)

- A reply issued by an MPF exit to a WTOR will appear twice on the JES job log of the job that issued the WTOR. This is because the system displays the reply once on the job log of the job that issued the WTOR and once on the job log of the job that issued the reply to that WTOR. An MPF exit replying to a WTOR runs in the address space of the job that issued the WTOR, so in this case the two jobs are the same.

Common Data Area: IEAVMXIT and all MPF exit routines receive the address of a 12-byte common data area (pointed to by CTXTCWKP in the CTXT). The common data area allows the exit routines to share data (in common work areas) across invocations.

Sharing Data With Other Exit Routines: You can code IEAVMXIT or an MPF exit routine to create work areas in the extended common storage area (ECSA), by issuing a GETMAIN or STORAGE macro, and then placing the address of these work areas in the common data area. Whenever IEAVMXIT or the MPF exit routines are invoked, the exit routines can access the common data area to obtain the work area addresses. If the exits require 12 bytes or less of data, you can place the data itself in the common data area instead of creating work areas.

The system initializes the common data area to zero; thereafter, the common data area contains whatever values the exit routines place in it.

IEAVMXIT and the MPF exit routines must manage serialization of the common data area.

Individual Data Area: In addition to the common data area, IEAVMXIT and all MPF exit routines receive the address of an 8-byte individual data area (pointed to by CTXTIWKP in the CTXT) whenever they are invoked. Each exit routine can use its individual data area to pass data (or the address of a work area) to itself across invocations.

Passing data to itself: To enable an exit routine to pass data to itself across invocations, code the routine to:

1. Create a work area in the ECSA by issuing a GETMAIN or STORAGE macro
2. Place the address of the work area in the individual data area.

During subsequent invocations, the exit routine can obtain the address of the work area by accessing its individual data area. As with the common data area, the system initializes each individual data area to zero; thereafter, the individual data area contains whatever values the exit routine places in it.

If the data required by the exit is 8 bytes or less, you can place the data itself within the individual data area instead of using a work area.

IEAVMXIT and the MPF exit routines must manage serialization of the individual data area.

Cleaning Up Work Areas: When IEAVMXIT or an MPF exit routine is to be deactivated (via CONTROL M or SET MPF), and the contents of its individual data area are nonzero, the exit routine is invoked before it is deactivated, so that it can clean up any work areas it may have created.

Individual work area should be cleaned up when the exit that owns them terminates. Common work areas should be cleaned up when the last exit using them terminates.

The exit routine determines whether it has been called for deactivation by checking the CTXTCIDA bit in the CTXT. The CTXTCIDA bit is set to 1 to indicate deactivation.

When the exit routine is reactivated, its individual data area is reset to zero by the system.

Macro Instructions and Restrictions: IEAVMXIT and MPF exit routines can issue system macros, but you should be aware of the following restrictions:

- Do not install an exit routine that issues the WAIT macro or calls a service that issues a WAIT. WAITs and implied WAITs can terminate console communications.
- Do not use macros with expansions that store information into an inline parameter list.
- Do not issue a GETMAIN or STORAGE macro for subpools that represent space within a region (0 — 127, 240, or 250 — 252). Because the exit routine executes as a part of the control program, it can use subpools such as 229, 230, and 249.

Security Consideration: It is the responsibility of your installation to provide any required security for an exit routine that issues the MGCRE macro. For example, the routine can issue the RACROUTE REQUEST=TOKENBLD macro to obtain the user token for a user ID that is authorized to the command and then append the security token to the MGCRE parameter list.

Entry Specifications

On entry, register 1 points to the address of the exit parameter list, the CTXT.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of the pointer to the CTXT

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of the exit routine

Parameter List Contents: Register 1 contains the address of a pointer to the exit parameter list (the CTXT), which is mapped by macro IEZVX100 (data area CTXT). The IEZVX100 mapping is described in *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

IEAVMXIT or an MPF exit routine returns to the calling module by using a branch and return via register 14.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-15

Restored to contents at entry

Coded Examples of MPF Exit Routines

IBM provides the following examples of MPF exit routines in SYS1.SAMPLIB, which can be used to modify message processing:

- IEACWAIT — used to cancel jobs that are waiting for volumes
- IEAOCANC — used to cancel jobs that are waiting for data sets
- IEAKTRCK — used to route status messages, for critical jobs, to a particular console
- IEAJTRCK — used to track JES2 jobs that are started during a given period.

Chapter 15. IEAVTABX – Change Options / Suppress Dump Exit

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routine” on page 79](#)
- [“Defining Dumping Services Exits to IEAVTABX” on page 79](#)
 - Adding and Deleting Exit Names in IEAVTABX
- [“Exit Routine Environment” on page 81](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 82](#)
- [“Programming Considerations” on page 82](#)
- [“Entry Specifications” on page 82](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 83](#)
 - Registers at Exit

IEAVTABX is a SYSUDUMP/SYSABEND/SYSMDUMP dumping services installation exit routine name list. It contains a list of installation exit routine names to be given control before the dump actually is taken. These installation exit routines allow an installation to change the dump options in effect or to suppress the dump that would be generated by an abending task.

You can use IEAVTABX to:

- Change dump options or suppress a dump based on job name, abend code, or other information in the SDWA.
- Tailor dumps for specific problems before the dump is taken.

Installing the Exit Routine

To install a dumping services installation exit routine in your system, you need to take the following steps:

- Linkedit the dumping services exit routine into SYS1.LPALIB, SYS1.LINKLIB, or a data set in the LNKLIB concatenation.
- Define the dumping services exit to MVS by adding its load module name to the exit name list in IEAVTABX.

Defining Dumping Services Exits to IEAVTABX

You can specify dumping services exits in any of the blank entries in the IEAVTABX exit name list. At the completion of each SVC DUMP or SYSMDUMP, the system invokes the routines in the order you specified them. That is, the exit routine specified in entry 1 gets control first, followed by the exit routine specified in entry 2, and so on.

IEAVTABX is a CSECT in load module IEAVTABX (which resides in SYS1.LPALIB). The IBM-supplied version of IEAVTABX contains the following entries:

- A 4-byte count field that contains hexadecimal zeroes, followed by
- Ten 8-byte entries that contain EBCDIC blanks, and are intended for customer use, followed by

- An 8-byte entry that contains eight character zeroes (X'F0') to indicate the end of the exit name list (the end-of-table marker).

You can add as many dumping services exit routine load modules to IEAVTABX as you want. IBM recommends that you use the existing blank entries in IEAVTABX before creating new ones. Ensure that the last entry is an 8-byte field that contains eight character zeroes (X'F0').

Contents of Entries: The first 4-byte entry contains the count field, which indicates the number of exit routine names in the table. Each 8-byte entry after the count field contains the exit load module name.

This is how the first, second, third and end-of-table marker fields in the IEAVTABX supplied by IBM appear:

IEAVTABX			
HEX LOCATION:	CONTENTS:		COUNT
0000	00000000		ENTRY 1
0004	40404040 40404040		ENTRY 2
000C	40404040 40404040		
.	.	.	
.	.	.	
.	.	.	
0054	F0F0F0F0 F0F0F0F0		END OF LIST

To insert a dumping services exit load module name in the list, select an available entry (one that is set to blanks) and substitute the exit load module name in place of the blanks. Exit names can be one to eight characters.

Examples of changing entries in IEAVTABX are shown in the sections that follow .

Adding and Deleting Exit Names in IEAVTABX: To add or delete exit names in the exit name list, you must modify the IEAVTABX object code in SYS1.LPALIB through the use of the SPZAP program, or through SMP/E. For more information, refer to [“Using SPZAP or SMP/E to Add or Delete Name” on page 80](#).

Using SPZAP or SMP/E to Add or Delete Name

Adding Exit Names: When using SPZAP or SMP/E, take the following steps:

- Use SPZAP to produce a dump of IEAVTABX. Sample JCL follows:

```
//DUMPJCL JOB MSGLEVEL=(1,1)
//STEP EXEC PGM=AMASPZAP
//SYSPRINT DD SYSOUT=*
//SYSLIB DD DSNAME=SYS1.LPALIB,DISP=OLD
//SYSIN DD *
NAME IEAVTABX
DUMP IEAVTABX
/*
```

- Use the dump produced to select an available entry in IEAVTABX.
- Write the EBCDIC name of the dumping services exit module in the entry. (See Example 1 if you are using SPZAP or Example 1A if you are using SMP/E.)

The changes will take affect on the next IPL.

Example 1 - Using SPZAP to Add Exit Names: The following job adds EXITRTN1 to the first entry in IEAVTABX, and EXITRTN2 to the second entry in IEAVTABX. The job then dumps IEAVTABX to verify the changes.

```
//EXAMPLE1 JOB MSGLEVEL=(1,1)
//STEP EXEC PGM=AMASPZAP
//SYSPRINT DD SYSOUT=*
//SYSLIB DD DSNAME=SYS1.LPALIB,DISP=OLD
//SYSIN DD *
NAME IEAVTABX
VER 0000 0000,0000 COUNT FIELD
REP 0000 0000,0002 SET COUNT FIELD
VER 0004 4040,4040,4040,4040 FIRST UNUSED ENTRY
REP 0004 C5E7,C9E3,D9E3,D5F1 SET TO EXITRTN1
VER 000C 4040,4040,4040,4040 SECOND UNUSED ENTRY
```

```

REP 000C C5E7,C9E3,D9E3,D5F2    SET TO EXITRTN2
DUMP IEAVTABX
/*

```

Example 1A - Using SMP/E to Add Exit Names: The following job adds EXITRTN1 to the first entry in IEAVTABX, and EXITRTN2 to the second entry in IEAVTABX.

```

++USERMOD(USRM0D2).
++VER(Z038) FMID(HBB4410). /* CHANGE THE FMID AS NEEDED */
++ZAP(IEAVTABX).
NAME IEAVTABX IEAVTABX
VER 0000 0000,0000          COUNT FIELD
REP 0000 0000,0002          SET COUNT FIELD
VER 0004 4040,4040,4040,4040 FIRST UNUSED ENTRY
REP 0004 C5E7,C9E3,D9E3,D5F1 SET TO EXITRTN1
VER 000C 4040,4040,4040,4040 SECOND UNUSED ENTRY
REP 000C C5E7,C9E3,D9E3,D5F2 SET TO EXITRTN2

```

Deleting Exit Names: When using SPZAP or SMP/E, take the following steps:

- Use SPZAP to dump IEAVTABX (as shown earlier in the sample JCL code under [“Using SPZAP or SMP/E to Add or Delete Name”](#) on page 80).
- Write EBCDIC blanks in place of the dump processing exit module name. (See Example 2 if you are using SPZAP or Example 2A if you are using SMP/E.)

The changes will take effect on the next IPL.

If all entries are in use, you can replace module IEAVTABX, or expand it. Ensure that the last entry contains 8 bytes of hexadecimal zeroes.

Example 2 - Using SPZAP to Delete Exit Names: The following job deletes EXITRTN1 from the dump processing exit list. The job then dumps IEAVTABX to verify the changes.

```

//EXAMPLE2 JOB MSGLEVEL=(1,1)
//STEP EXEC PGM=AMASPZAP
//SYSPRINT DD SYSOUT=*
//SYSLIB DD DSN=SYS1.LPALIB,DISP=OLD
//SYSIN DD *
NAME IEAVTABX
VER 0000 0000,0002          COUNT FIELD
REP 0000 0000,0001          SET COUNT FIELD
VER 0004 C5E7,C9E3,D9E3,D5F1 EXITRTN1
REP 0004 4040,4040,4040,4040 RESTORE ENTRY 1
DUMP IEAVTABX
/*

```

Example 2A - Using SMP/E to Delete Exit Names: The following job deletes EXITRTN1 from the dump processing exit list.

```

++USERMOD(USRM0D3).
++VER(Z038) FMID(HBB4410). /* CHANGE THE FMID AS NEEDED */
++ZAP(IEAVTABX).
NAME IEAVTABX
VER 0000 0000,0002          COUNT FIELD
REP 0000 0000,0001          SET COUNT FIELD
VER 0004 C5E7,C9E3,D9E3,D5F1 EXITRTN1
REP 0004 4040,4040,4040,4040 REPLACE WITH BLANKS

```

See the following references for more information on the use of:

- SPZAP, see [z/OS MVS Diagnosis: Tools and Service Aids](#).
- SMP, see [z/OS SMP/E User's Guide](#).
- Expand, see [z/OS MVS Program Management: User's Guide and Reference](#).

Exit Routine Environment

Each routine in IEAVTABX must reside in (E)PLPA, and receives control in the following environment:

- Enabled for interrupts
- In supervisor state with PSW key 0
- In AMODE 31
- Holding no locks
- Under the abending task and in the home address space
- Under the SVRB of ABDUMP
- Holding either or both of the following ENQs: QNAME SYSZTIOT and SYSIEA01.

Exit Recovery: Each exit routine must establish an ESTAE and request a tailored dump. Before each exit routine returns control to ABDUMP it must delete the ESTAE, and it must free all storage it obtained.

Note: A request for an ABDUMP from the ESTAE will cause recursion, and no dump will be produced for the installation exit routine error. It is suggested that you take an SDUMP and issue a SETRP DUMP=NO. These actions cause a retry attempt to a return point that prevents ABDUMP's recovery routine from getting control.

Exit Routine Processing

The installation exit routines receive control sequentially prior to taking the dump. At entry, each routine has addressability to a parameter list that is the major communication area among the installation exit routines. The input parameter list is mapped by the macro IHAABEPL (data area ABEP) and contains a copy of the following types of information for each dump:

- Job name
- System completion code
- Address of the SDWA
- Module name
- Options in effect (SNAP parameter list)
- Parameter list level indicator
- Return code from the previous installation exit routine

The SNAP parameter list, mapped by IHASNAPX (data area SNAPX), contains the current dump options in effect. You can change these options in your exit routine based on other information in the ABEPL and the SDWA.

The exit routine get control prior to taking the dump. If one of the exit routines suppresses the dump, the system issues message IEA848I, indicating that dump suppression has taken place.

Programming Considerations

The installation exit routines in IEAVTABX must be reentrant. Their load module names must be eight bytes padded to the right with blanks.

The exits must obtain storage from specific subpools requested in the tailored dump. Before returning, each exit routine must free all the storage it obtained.

The installation exit routine must not free the entry parameter list.

Entry Specifications

The ABDUMP calling routine passes to each installation exit routine in IEAVTABX the address of a parameter list used for communication between the routines.

Registers at Entry: The contents of the registers on entry to an installation exit routine specified in IEAVTABX are:

**Register
Contents****0**

Not applicable

1

Address of IHAABEPL parameter list

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of the installation exit routine in IEAVTABX

Parameter List Contents: Register 1 points to the exit routine parameter list, which is mapped by the IHAABEPL macro (data area ABEP). For a mapping of the ABEP data area, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

Each installation exit routine returns a code indicating whether processing should continue.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

**Register
Contents****0-14**

Restored to contents at entry

15

One of the following return codes:

**Return Code
Explanation****0**

Continue processing with the current options.

4

Change options as indicated in IHAABEPL.

8

Suppress the dump.

Chapter 16. IEAVTABX_EXIT — ABDUMP Change Options / Suppress Dump Exit

Topics for This Exit Appear as Follows:

- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 85](#)
- [“Replacing the Exit Routine” on page 85](#)
- [“Exit Routine Environment” on page 85](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 86](#)
- [“Programming Considerations” on page 86](#)
- [“Entry Specifications” on page 86](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 87](#)
 - Registers at Exit

As with the exit routines that receive control under the IEAVTABX interface, described in Chapter 15, [“IEAVTABX — Change Options / Suppress Dump Exit,” on page 79](#), you can use an IEAVTABX_EXIT dynamic exit routine to change the current dump options or suppress the dump that could be generated by an abending task. The job name and abend code are examples of the data that is provided for the current dump request.

Unlike the IEAVTABX interface, the dynamic exit routines are called before ABDUMP setup processing begins. At this point in processing, no suppression determination has been made, no ENQs are established, and the type of ABDUMP has not yet been determined. Also, all of the associated exit routines are called, regardless of the return code that is returned by any one of them.

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEAVTABX_EXIT installation exit to the dynamic exits facility. You can control the exit and its exit routines by using the EXIT statement of a PROGxx PARMLIB member, the SETPROG EXIT operator command, or the CSVDYNEX macro.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- Exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error.
- System allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system disables the exit routine after two consecutive abends.

Replacing the Exit Routine

For information about replacing a dynamic exit routine, see [“Replacing a Dynamic Exit Routine” on page 6](#).

Exit Routine Environment

The IEAVTABX_EXIT exit routine receives control in the following environment:

- Enabled for I/O and External interrupts.

- In supervisor state with PSW key 0.
- In AMODE 31.
- With no locks or ABDUMP obtained ENQs held.
- Cross memory environment is PASN=HASN=SASN.
- Under the abending task.

Exit Recovery: The exit routine should provide its own recovery routine. If the IEAVTABX_EXIT exit routine ends abnormally, its recovery routine gets control first. If that recovery routine percolates, or there is no recovery routine, IEAVTABX_EXIT processing proceeds as though the exit routine had returned a zero return code. Resource clean up processing remains the responsibility of the exit routine.

Note: If the exit routine recovery requires a dump, it is suggested that you use the IEATDUMP or SDUMPX interfaces and specify SETRP DUMP=NO. A user dump could result in undesirable behavior.

Exit Routine Processing

The IEAVTABX_EXIT exit routines receive control when:

- An ABDUMP was requested for the original abend, or was requested by a recovery routine (SETRP DUMP=YES) and no FRR retried the abend
- No subsequent recovery routine indicated that an ABDUMP should not be taken (SETRP DUMP=NO)
- TCBPDUMP was not turned on in the jobstep task TCB
- No dump was suppressed by a previous exit routine.

The IEAVTABX_EXIT exit routines receive control regardless of whether:

- An ABDUMP DD statement was specified in the job steps
- An ABDUMP will be taken.

Every exit routine receives control sequentially before the dump is taken. At entry, register 1 contains the address of the input parameter list.

Only one version of the two following informational messages is issued, with the suppression version superseding the other. When any exit routine changes the dump options, the system issues message IEA848I, indicating the name of the last exit routine that made the modification. When any exit routine suppresses the dump, the system issues message IEA848I, indicating the name of the last exit routine that suppressed the dump.

When an IEAVTABX_EXIT exit routine ends abnormally, or returns a return code of 0, no data is added. When an exit routine returns a return code of 4, data is added. When any exit routine returns a code of 8, no data is added and the dump is suppressed.

Programming Considerations

Code the exit routine to be reentrant.

Entry Specifications

Registers at Entry: The contents of the registers on entry to an installation exit routine specified in IEAVTABX are:

Register

Contents

0

Not applicable

1

Address of IHAABEPL parameter list

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of the installation exit routine in IEAVTABX_EXIT

Parameter List Contents: Register 1 points to the exit routine parameter list, which is mapped by the IHAABEPL macro (data area ABEP), and contains the following data for each dump. For a mapping of the ABEP data area, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

The SNAPX parameter list, mapped by IHASNAPX (data area SNAPX) contains the current dump options in effect. These options can be changed by the exit routine. For details about data area fields, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

Each installation exit routine returns a code indicating whether processing should continue.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-1

Not applicable

2-13

Restored to contents at entry

14

Return address

15

One of the following return codes:

Return Code

Explanation

0

Continue processing with the current options.

4

Change options as indicated in IHAABEPL.

8

Suppress the dump.

Chapter 17. IEAVTSEL — Post Dump Exit Name List Exit

Topics for This Exit Appear as Follows:

- [“Installing Post-Dump Exit Routines” on page 89](#)
- [“Defining Post-Dump Exits to IEAVTSEL” on page 90](#)
 - Methods of Adding and Deleting Exit Names in IEAVTSEL
- [“Exit Routine Environment” on page 93](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 93](#)
- [“Programming Considerations” on page 93](#)
- [“Entry Specifications” on page 94](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 95](#)
 - Registers at Exit.

IEAVTSEL is the SVC, IEATDUMP, and SYSMDUMP post-dump exit names list. In IEAVTSEL, you list the names of installation exit routines that the system is to invoke after each SVC dump and SYSMDUMP. You can also set a flag bit for each exit routine to indicate whether the system is to invoke the routine for any dump that dump analysis and elimination (DAE) has suppressed.

Each routine receives control in the order it is listed in IEAVTSEL. However, to prevent endless recursion processing loops, the system does not invoke any of the exit routines in IEAVTSEL if an SVC dump request is issued by a post-dump exit routine or its recovery routine.

You can use post-dump exit routines to:

- Extract certain information from the header record, such as the dump title, ERRORID, time of dump, ABEND code, and failing module name. This information can be written to a log data set (using DISP=MOD to append the new entries at the end).
- Offload the dump from SYS1.DUMPnn to a DASD or tape data set for later processing and log the information in a log data set.
- Start an IPCS job that would print a small portion of the dump (such as log data, summary, and/or SUMDUMP).

Installing Post-Dump Exit Routines

To install a post-dump installation exit routine in your system, you need to take both of the following steps:

- Linkedit the post-dump exit routine into SYS1.LPALIB, SYS1.LINKLIB, or a data set in the LNKLST concatenation. The library containing the exit routine must be APF-authorized.
- Define the post-dump exit to MVS by adding its load module name to the exit name list in IEAVTSEL.

Defining Post-Dump Exits to IEAVTSEL

You can specify post-dump exits in any of the blank entries in the IEAVTSEL exit name list. At the completion of each SVC dump, IEATDUMP, or SYSMDUMP, the system invokes the routines in the order you specified them. That is, the exit routine specified in entry 1 gets control first, followed by the exit routine specified in entry 2, and so on.

IEAVTSEL is a CSECT in load module IEAVTSEL (which resides in SYS1.LINKLIB). The IBM-supplied version of IEAVTSEL contains the following 12-byte entries:

- Nine entries that contain EBCDIC blanks, and are intended for customer use, followed by
- A number of entries that are reserved for use by IBM, followed by
- A final entry that contains hexadecimal zeroes to indicate the end of the exit name list (the end-of-table marker).

You can add as many post-dump exit routine load modules to IEAVTSEL as you want. IBM recommends that you use the existing blank entries in IEAVTSEL before creating new ones. Ensure that you do not delete any entries in use by MVS, and that the last entry contains 12 bytes of hexadecimal zeroes.

Contents of Entries: The first 8 bytes of each entry contain the exit load module name, and the last 4 bytes of each entry contain a flag bit you would set under certain conditions (explained in [“The Flag Bit”](#) on page 90). Entries that have 8 bytes of X'40' (blanks) for the exit load module name are available for customer use.

This is how the first, second, and last entries in IEAVTSEL appear:

IEAVTSEL			
HEX LOCATION:	CONTENTS:		
0000	40404040 40404040 00000000	ENTRY 1	
000C	40404040 40404040 00000000	ENTRY 2	
.	.	.	
.	.	.	
0078	00000000 00000000 00000000	END OF LIST	

To insert a post-dump exit load module name in the list, select an available entry (one that is set to blanks) and substitute the exit load module name in place of the blanks. Exit names can be one to eight characters. Also, set the flag bit if appropriate.

For examples of changing entries in IEAVTSEL, see [“Methods of Adding and Deleting Exit Names in IEAVTSEL”](#) on page 90.

The Flag Bit

You can set the high-order bit of the 4-byte flag field to indicate whether the corresponding exit routine is invoked for dumps that are suppressed through dump analysis and elimination (DAE).

- If the bit is off (X'00000000'), the exit routine gets control when dump processing ends, if DAE has **not** suppressed the dump.
- If the bit is on (X'80000000'), the exit routine gets control when dump processing ends, even if DAE has suppressed the dump.

Methods of Adding and Deleting Exit Names in IEAVTSEL

There are two ways to add or delete exit names in the exit name list. You can use either of the following methods:

- **Method 1:** Modify the IEAVTSEL source code through the use of the DUMPEXIT macro. Note that DUMPEXIT is defined within the IEAVTSEL module. To use DUMPEXIT, you need the source code for IEAVTSEL. You can obtain the source code for IEAVTSEL from the optional machine-readable material provided by IBM. For additional information on this optional material, contact your IBM Marketing representative.

- **Method 2:** Modify the IEAVTSEL object code in SYS1.LINKLIB through the use of the SPZAP program, or through SMP/E.

Both methods are explained in greater detail in the sections that follow .

Method 1 — Using DUMPEXIT to Add Names: When using the DUMPEXIT macro, take the following steps:

- Select an available entry in IEAVTSEL, which appears in IEAVTSEL as:

```
DUMPEXIT NAME=,ATTR=00000000
```

- On the NAME parameter of DUMPEXIT, specify the load module name of the exit routine to be added and set the flag field if desired (on the ATTR parameter). In this example:

```
DUMPEXIT      NAME=EXITRTN,ATTR=xxxxxxxx
```

'EXITRTN' is the load module name of the post-dump exit routine to be added, and 'xxxxxxxx' is either X'00000000' or X'80000000', depending on whether you want the exit routine to receive control for dumps that are suppressed through DAE.

Ensure that you do not delete any entries in use by MVS, and that the last entry contains 12 bytes of hexadecimal zeroes.

- Assemble and linkedit the IEAVTSEL exit again.

The changes will take effect on the next IPL.

You can add as many post-dump exit routine load modules to IEAVTSEL as you want. Additional DUMPEXIT macro invocations can be added to the post-dump exit routine load module anywhere **before** the end of the table marker:

```
DC      XL12X'000000000000000000000000'
```

Method 1 — Using DUMPEXIT to Delete Names: When using the DUMPEXIT macro, take the following steps:

- Replace the entry to be deleted with:

```
DUMPEXIT NAME=,ATTR=00000000
```

- Assemble and linkedit IEAVTSEL again.

The changes will take effect on the next IPL.

Method 2 — Using SPZAP or SMP/E to Add Names: When using SPZAP or SMP/E, take the following steps:

- Use SPZAP to produce a dump of IEAVTSEL. The sample JCL code follows:

```
//DUMPJCL JOB MSGLEVEL=(1,1)
//STEP   EXEC PGM=AMASPZAP
//SYSPRINT DD SYSOUT=*
//SYSLIB  DD DSN=SYS1.LINKLIB,DISP=OLD
//SYSIN   DD *
          NAME IEAVTSEL
          DUMP IEAVTSEL
/*
```

- Use the dump produced to select an available entry in IEAVTSEL.
- Write the EBCDIC name of the post-dump exit module in the entry and set the appropriate flag setting. (See Example 1 if you are using SPZAP or Example 1A if you are using SMP/E.)

The changes will take affect on the next IPL.

Example 1 - Using SPZAP to Add Exit Names: The following job adds EXITRTN1 to the first entry in IEAVTSEL and sets the flag to indicate that EXITRTN1 should get control even if the dump is suppressed

by DAE. The job also adds EXITRTN2 to IEAVTSEL and sets the flag to indicate that EXITRTN2 should get control only when a dump is not suppressed by DAE. The job then dumps IEAVTSEL to verify the changes.

```
//EXAMPLE1 JOB MSGLEVEL=(1,1)
//STEP      EXEC PGM=AMASPZAP
//SYSPRINT  DD SYSOUT=*
//SYSLIB    DD DSN=SYS1.LINKLIB,DISP=OLD
//SYSIN     DD *
NAME IEAVTSEL
VER 0000 4040,4040,4040,4040,0000,0000    FIRST UNUSED ENTRY
REP 0000 C5E7,C9E3,D9E3,D5F1,8000,0000    SET TO EXITRTN1
VER 000C 4040,4040,4040,4040,0000,0000    SECOND UNUSED ENTRY
REP 000C C5E7,C9E3,D9E3,D5F2,0000,0000    SET TO EXITRTN2
DUMP IEAVTSEL
/*
```

Example 1A - Using SMP/E to Add Exit Names: The following job adds EXITRTN1 to the first entry in IEAVTSEL and sets the flag to indicate that EXITRTN1 should get control even if the dump is suppressed by DAE. The job also adds EXITRTN2 to IEAVTSEL and sets the flag to indicate that EXITRTN2 should get control only when a dump is not suppressed by DAE.

```
++USERMOD(USRM02).
++VER(Z038) FMID(HBB4410). /* CHANGE THE FMID AS NEEDED */
++ZAP(IEAVTSEL).
NAME IEAVTSEL IEAVTSEL
VER 0000 4040,4040,4040,4040,0000,0000    FIRST UNUSED ENTRY
REP 0000 C5E7,C9E3,D9E3,D5F1,8000,0000    SET TO EXITRTN1
VER 000C 4040,4040,4040,4040,0000,0000    SECOND UNUSED ENTRY
REP 000C C5E7,C9E3,D9E3,D5F2,0000,0000    SET TO EXITRTN2
```

Method 2 — Using SPZAP or SMP/E to Delete Name: When using SPZAP or SMP/E, take the following steps:

- Use SPZAP to dump IEAVTSEL. Sample JCL code for using SPZAP or SMP/E to add or delete names is shown in [“Methods of Adding and Deleting Exit Names in IEAVTSEL”](#) on page 90.
- Write EBCDIC blanks in place of the post-dump exit module name and set the flag bit off. (See Example 2 if you are using SPZAP or Example 2A if you are using SMP/E.)

The changes will take effect on the next IPL.

If all entries are in use, you can replace module IEAVTSEL, or expand it. Ensure that you do not delete any entries in use by MVS, and that the last entry contains 12 bytes of hexadecimal zeroes.

Example 2 - Using SPZAP to Delete Exit Names: The following job deletes EXITRTN1 from the post-dump exit list. The job then dumps IEAVTSEL to verify the changes.

```
//EXAMPLE2 JOB MSGLEVEL=(1,1)
//STEP      EXEC PGM=AMASPZAP
//SYSPRINT  DD SYSOUT=*
//SYSLIB    DD DSN=SYS1.LINKLIB,DISP=OLD
//SYSIN     DD *
NAME IEAVTSEL
VER 0000 C5E7,C9E3,D9E3,D5F1,8000,0000    EXITRTN1
REP 0000 4040,4040,4040,4040,0000,0000    RESTORE ENTRY 1
DUMP IEAVTSEL
/*
```

Example 2A - Using SMP/E to Delete Exit Names: The following job deletes EXITRTN1 from the post-dump exit list.

```
++USERMOD(USRM03).
++VER(Z038) FMID(HBB4410). /* CHANGE THE FMID AS NEEDED */
++ZAP(IEAVTSEL).
NAME IEAVTSEL IEAVTSEL
VER 0000 C5E7,C9E3,D9E3,D5F1,8000,0000    EXITRTN1
REP 0000 4040,4040,4040,4040,0000,0000    REPLACE WITH BLANKS
```

For more information on the following topics, use these references:

- SPZAP, see *z/OS MVS Diagnosis: Tools and Service Aids*.
- SMP, see *z/OS SMP/E User's Guide*.
- Expand, see *z/OS MVS Program Management: User's Guide and Reference*.

Exit Routine Environment

Each routine in IEAVTSEL receives control in the following environment:

- Enabled for interrupts.
- In supervisor state, PSW key 0.
- In AMODE 24 or 31 and RMODE ANY.
- In task mode in the DUMPSRV (dumping services) address space.
- With no locks held.

Exit Recovery: SVC dump establishes its own ESTAE before calling the IEAVTSEL exit routines. Each exit routine must establish its own recovery.

Exit Routine Processing

The installation exit routines listed in IEAVTSEL receive control with the completion of the dump.

Each exit routine in IEAVTSEL accesses a common parameter list (SDEPL) containing data and an interface area that the routines can use to pass information to succeeding routines. The SDEPL is mapped by macro IHASDEPL.

Exit Status Flags: A post-dump exit routine listed in IEAVTSEL can determine whether the exit routine that immediately preceded it completed successfully or not by checking the SDEPLEXE flag bit in the SDEPL. The system sets this bit on if the preceding exit routine returned a nonzero return code (in register 15).

A post-dump exit routine can determine whether **any** of the preceding exit routines failed to complete successfully by checking the SDEPLERR flag bit in the SDEPL. Like SDEPLEXE, this bit is set to '1' if a post-dump exit returns a nonzero return code. However, once set on, SDEPLERR is not reset when a subsequent exit routine returns a zero return code.

Programming Considerations

Parameter List: The SDUMP exit parameter list (SDEPL) is passed to each post-dump exit routine listed in IEAVTSEL. In addition to other useful information, the SDEPL contains the addresses of both an exit interface area and a 200-byte exit work area:

- The exit interface area (pointed to by SDEPLEXT) enables a post-dump exit routine to pass information to successive post-dump exit routines. This area is set to zeroes before the call to the first post-dump exit routine. Thereafter, the exit interface area contains whatever values the post-dump exit routines place in it. If an installation chooses, it can use this area as a work area
- The exit work area (pointed to by SDEPLWA) is a general work area for the installation exit routine. This area is reset to zeroes between calls to each exit named in IEAVTSEL

Dump Header Record: The SDEPLHD field in the parameter list (SDEPL) points to a copy of the dump header record. The AMDDATA mapping macro maps the dump header record, and the description of AMDDATA contains information about fields in the header record. For details, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

The DAE section of the dump header record, which is located in the second 2K of the header record, contains information about the dump that DAE has gathered. Some fields in the DAE section of the header record that contain useful diagnostic information are:

ADSSDAE

Start of the DAE section of the header record.

DAESSMVS

Symptom string used for matching.

DAECRIT

Criteria for unique symptom string generated by DAE.

DAESTAT

DAE status flags mapped by ADYDSTAT.

DAEERID

ERROR-ID from the original occurrence of the dump.

DAEDCNT

The number of occurrences of the dump.

If DAE has not suppressed the dump, the first 2K of the dump header record also contains information that a post-dump exit routine can use. To determine whether DAE has suppressed the dump, the exit routine can test the PRDID field in the header record. If the PRDID field contains X'000000', DAE has suppressed the dump, and the first 2K of the header record does not contain useful information. If PRDID is non-zero, DAE has not suppressed the dump, and the first 2K of the dump header record contains valid information about the dump. Some fields in this part of the header record that contain useful diagnostic information are:

PRDDUMPT

PRDDUMPT Dump type that tells whether the dump is a stand alone dump, an SVC dump, a SYSMDUMP, or an SVC dump for a SLIP request.

PRDDSNAM

Dump data set name to which dump was taken.

PRDERRID

Error ID from this dump.

PRDSDWA

A copy of the SDWA of the caller of SDUMP. From this SDWA you can obtain the failing module name, the ABEND code, and any other diagnostic data. See mapping macro SDWA in *z/OS MVS Data Areas* in the z/OS Internet library (www.ibm.com/servers/resourceLink/svc00100.nsf/pages/zosInternetLibrary) for available fields.

The SDWA is not present on SLIP dumps.

Other Considerations:

- Dump data sets are allocated with the following attributes:

- RECFM = FBS
- LRECL = 4160
- BLKSIZE = whatever is optimum size per track

Therefore, have your exit routines specify these attributes when defining DCBs to use to open SYS1.DUMPnn data sets.

- If an installation does not want to have the installation exit routine run in supervisor state or key 0, the exit routine must issue a MODESET macro to obtain the desired state.

Entry Specifications

Each exit routine in IEAVTSEL receives control sequentially and receives a common parameter list.

Registers at Entry: The contents of the registers on entry to an installation exit routine in IEAVTSEL are as follows.

Register**Contents**

0

Not applicable

- 1**
Address of the address of the parameter list mapped by IHASDEPL
- 2-12**
Not applicable
- 13**
Register save area
- 14**
Return address
- 15**
Entry point address of the installation exit routine in IEAVTSEL

Parameter List Contents: Register 1 points to address of the SDUMP exit parameter list (SDEPL) mapped by macro IHASDEPL (data area SDEPL). For a mapping of the SDEPL data area, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

The installation exit routine returns a code indicating whether the exit was successful.

Registers at Exit: Upon return from an installation exit routine in IEAVTSEL, the register contents must be as follows.

Register Contents

- 0-14**
Restored to contents at entry
- 15**
One of the following return codes

Return Code Explanation

- 0**
The exit was successful.
- nonzero**
The exit was unsuccessful.

The system sets exit status flags SDEPLEXE and SDEPERR based on the return code in register 15. See [“Exit Routine Processing” on page 93](#).

Chapter 18. IEF_ALLC_OFFLN – Allocated or Offline Device Installation Exit

Topics for This Exit Appear as Follows:

- “Controlling the Exit Routine”
- “Replacing the Exit Routine” on page 98
- “Exit Routine Environment” on page 98
- “Exit Recovery” on page 98
- “Exit Routine Processing” on page 99
 - Bringing a Device Online
 - The Offline Device Table
 - Letting the Job Wait for the Device
 - Using the Exit with Your Installation's Default Policy
- “Programming Considerations” on page 103
 - Macro Instructions and Restrictions
- “Entry Specifications” on page 104
 - Registers at Entry
 - Parameter Descriptions
- “Return Specifications” on page 105
 - Registers at Exit
- “Coded Example of the Exit Routine” on page 105

When a job must wait because a device it requested is offline or allocated to another job, MVS issues WTORs that instruct the system operator to take one of the following actions:

- Cancel the waiting job
- Bring the device online
- Allow the job to wait for the device to become available.

You can automate your installation's responses to allocation requests for offline, pending offline, or allocated devices, and reduce the need for operator intervention by:

- Defining an installation default policy for handling the **majority** of potential allocation requests for offline, pending offline, or allocated devices. Specify the default policy in the ALLOCxx member of SYS1.PARMLIB.
- Coding the Allocated or Offline Device exit routine to make exceptions, if any, to the installation default policy for certain jobs and devices. You can specify the exit in the EXITxx or PROGxx member of SYS1.PARMLIB; however, IBM recommends that you use PROGxx.

For a list of the allocation messages you can automate or suppress, see [“Message Processing” on page 103](#).

Using the information that it receives about the job and the required device(s), the exit routine can:

- Cancel the job
- Cause offline devices to be brought online to satisfy the job's request
- Cause a pending offline device to be considered for allocation

- Allow the job to wait while:
 - holding resources
 - not holding resources
- Allow the installation's default policy to determine which action to take.
- Allow the WTOR to be issued so that the system operator can decide how to handle the job. If the WTOR is to be issued, the exit routine can determine which device numbers are displayed on the WTOR.

Note: The exit routine can only exclude device numbers from the WTOR. It cannot exclude the actual list of devices eligible for allocation.

For more information about the ALLOCxx, EXITxx, and PROGxx parmlib members, see [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM defines the Allocated or Offline installation exit to the dynamic exits facility. You can refer to the exit by the name IEF_ALLC_OFFLN. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes disabled. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Replacing the Exit Routine

For information about replacing a dynamic exit routine, see [“Replacing a Dynamic Exit Routine” on page 6](#).

Exit Routine Environment

The exit routine receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 1.
- In AMODE 31 and RMODE ANY.
- With no locks held. (However, it might hold an exclusive ENQ on major name SYSZTIOT for the address space in which the allocation occurs.)

Exit Recovery

The exit routine should provide its own recovery. If the exit routine abnormally ends, its recovery routine gets control.

If the exit routine abnormally ends, and the exit routine does not provide its own recovery, or the error percolates beyond the exit's recovery routine, a system recovery routine gets control and fail the allocation request.

Whether the exit routine continues to be started depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

MVS starts the allocated or offline device exit routine or routines, if any are specified to the dynamic exits facility, every time a job must wait for a device. This is because all devices that can satisfy the job's request are either offline, pending offline, or allocated to other jobs. This exit is only started for tape requests and non-SMS-managed DASD requests. It is not started for SMS-managed DASD requests.

MVS starts the exit routine before it issues WTORs that:

- Identify the job that is waiting
- List the devices that are unavailable
- Request operator action.

These messages are listed in [“Message Processing”](#) on page 103.

Using the Information in the Parameter List: MVS passes the address of a list of parameters to the exit routine. The parameters contain the following information:

- Job name
- Step name
- Name of the DD statement that requires the resource
- Name of the data set that requires the resource
- If specific volumes are needed, the serial numbers of the volumes
- The number of nonspecific scratch volumes
- The number of nonspecific private volumes
- A list of the eligible devices that can be brought online

Note: The list might include pending offline devices. You can use this exit to indicate whether these devices are eligible for allocation. If a pending offline device is permanently resident DASD or has a reserved volume mounted, its entry in the list contains the mounted volume serial number.

- An indication of whether the job can wait
- An indication of whether the job can bring devices online
- An indication of whether it is a repeated call to the exit
- Action to be taken in response to WTOR (this field, ACTION, is completed by the exit routine).
- The number of 'wait without holding resources' decisions that the system allows to be made for a particular device request (in the WAITNOHC field). This number includes decisions that are made by both the exit routine and the installation default. This number does not restrict the number of 'wait without holding resources' decisions that can be made by the system operator.
- An indication of whether the system-managed tape library is online.
- An indication of whether the system-managed tape library is offline.
- An indication of whether the system-managed tape library is pending offline.
- For a system-managed tape library request, the name of the library.
- The relative concatenation number of the DD.
- An indication of the device class of the DD; one of the following:
 - Tape device
 - Communications device
 - Direct access device
 - Graphics display device
 - Unit record device
 - Character reader device

If the request is for an esoteric group name that includes both tape and direct access devices, both the tape and direct access indicators are set.

Using the information in the parameter list, the exit routine determines how the system should respond to the allocation request. The exit routine indicates its decision to the system by placing a value in the ACTION field of the parameter list.

See [“Return Specifications” on page 105](#) for the specific values the exit routine can return.

Bringing a Device Online

The system indicates to the exit routine that the job can bring devices online by setting the OKONLINE bit to 1 (in the exit parameter list).

If the exit routine attempts to bring a device online when the OKONLINE bit is not set to 1, the system ignores the exit routine's decision and use the installation default policy (specified in the ALLOCxx parmlib member) to determine how to respond to the allocation request. If your installation does not define a default policy for handling allocated or offline device requests, or if no ALLOCxx parmlib member is defined, the system issues WTORS. That way, the system operator must respond to the job's allocation request.

The exit routine brings device(s) online by:

- Setting the ACTION field to X'08'.
- Selecting the device(s) from the offline device table (as described in [“The Offline Device Table” on page 101](#)).

Selecting an Offline Device to Bring Online: If you plan to use the exit routine to cause devices to be brought online, code the routine to check the input bits in the UXSTATUS field of the offline device table. Before selecting the device(s), check:

- The UXOFFLNE bit indicates whether the device has been varied offline (for maintenance, for example). If a device has been varied offline, the system sets the UXOFFLNE bit to 1.
- The UXNOTACC bit indicates whether the device is accessible to the exit routine. If the device is not accessible (not physically defined in the system), the system sets the UXNOTACC bit to 1.

The exit routine can cause only accessible devices to be brought online.

- The UXPENDNG bit indicates whether the device is pending offline. If a device is pending offline it cannot be brought online by the exit. However, it can be selected for allocation consideration. See [“Selecting a Pending-Offline Device for Allocation Consideration” on page 101](#).
- The UXVCOFFL bit indicates whether the device was varied offline by a configuration manager (for example, ESCON Manager). If the exit routine attempts to bring the device online, the device is brought online.
- The UXVLOFFL bit indicates whether the device is offline because it exists in an offline system-managed tape library. If the system-managed tape library is offline, the system sets the UXVLOFFL bit to 1.

The exit routine brings the device online by setting the UXONLINE bit in the UXSTATUS field to 1.

Be aware that if the chosen devices cannot be successfully brought online, Allocation retries the allocation request anyway. If the allocation request still cannot be satisfied, the exit routine might be driven again. The parameter list does not indicate that the device was not able to be brought online previously. The exit routine should consider this when it chooses devices, and should be aware that it can cause a loop if it repeatedly chooses devices that cannot be brought online.

Selecting an Eligible System-Managed Tape Library Device

The system indicates whether a request is a system-managed tape library request by setting the LBREQIND bit to one in the exit parameter list. For system-managed tape library requests, the exit or installation default policy determines whether:

- The exit is to select an eligible system-managed tape library device. The exit varies the device online only when the named library is already online.
- The operator is to select an eligible system-managed tape library device. To vary the device online, the operator must first ensure that the named library is online by issuing the DISPLAY SMS,LIBRARY command (described in *z/OS MVS System Commands*). If the library is offline or pending offline, the operator must vary the library online before it varies the device online by issuing the VARY SMS,LIBRARY command (described in *z/OS MVS System Commands*).

An eligible device in a system-managed tape library might be offline for one of the following reasons:

- The device exists in a system-managed tape library that is offline or pending offline
- There are no paths to the device
- A reason other than a VARY LIBRARY offline command; for example, because the operator varied the tape device offline

Selecting an eligible tape library device based on device priority

The device priority value (UXDEVPRI) is available at z/OS 2.3 and above. It is also available for prior releases when the fix for APAR OA49373 is installed. UXDEVPRI is used in a system-managed tape environment to reflect device preference information:

- The priority value is a number from 0-255, where 255 is the best or preferred value, and 0 is the worst value.
- The priority value isn't unique, which means that multiple devices might have the same value.
- Not all of the priority values are necessarily used. So for a given request, the best device the exit sees might have a priority value of 250 (instead of 255), or the best device might be 255 and the next best device might be 245, for example.
- Some allocation requests might not be prioritized - for those requests, the priority value is 0.

Bit flag UXPRVALD indicates whether the devices in the offline device list have been assigned priority values.

Priority values are returned in the following cases:

- The Device Allocation Assist (DAA) function is being used in the TS7700 Virtualization Engine to prioritize which clusters (or distributed libraries) are preferred on a specific mount request.
- When multiple libraries are eligible for a scratch request, some libraries might be above or below scratch threshold. Devices in libraries above scratch threshold receive a priority value of 255 and devices in libraries below scratch threshold receive a priority value of 254.

Selecting a Pending-Offline Device for Allocation Consideration

The exit can be used to indicate whether a specific pending-offline device is considered for allocation. A pending-offline device is allocated only if no other online device becomes available. The device remains in pending offline status.

The Offline Device Table

The offline device table (pointed to in the exit parameter list) contains the device numbers of all offline or pending offline devices that match the device type that the job specified in the allocation request.

The system sets the first 4 bytes of the offline device table to the number of entries (devices) in the table. The 4-byte field is followed by one 12-byte entry for each offline device:

Bytes

Contents

1-4

contain the device number (in EBCDIC).

5

the UXSTATUS field contains information about the offline status of the device.

6

reserved.

7-12

contain the VOLSER of the pending offline permanently resident DASD or reserved device is a volume is mounted.

The format of the offline device table follows:

Number of Entries	(4 bytes)			
Device Number	(4 bytes)	Status (1 byte)	Priority (1 byte)	Pending-offline Volser (6 bytes)
Device Number	(4 bytes)	Status (1 byte)	Priority (1 byte)	Pending-offline Volser (6 bytes)
⋮		⋮		
⋮		⋮		
⋮		⋮		
Device Number	(4 bytes)	Status (1 byte)	Priority (1 byte)	Pending-offline Volser (6 bytes)

Letting the Job Wait for the Device

The system indicates to the exit routine (in the OKTOWAIT bit of the exit parameter list) whether the job is allowed to wait. If OKTOWAIT is set to 1, the exit routine can cause the job to wait by setting the ACTION field to indicate one of the following:

- The job waits holding any resources that it might have obtained
- The job waits without holding any resources that it might have obtained.

If the exit routine attempts to cause the job to wait when OKTOWAIT is set to 0, the system ignores the exit routine's decision and use the installation default policy (specified in the ALLOCxx parmlib member) to determine how to respond to the allocation request. If your installation does not define a default policy for handling allocated or offline device requests, or if no ALLOCxx parmlib member is defined, the system issues messages (listed in [“Message Processing” on page 103](#)) so that the system operator must respond to the job's allocation request.

If the exit routine allows the job to wait, the system issues an eventual action message (IEF289E) to inform the operator that the job is waiting for a device.

Using the Exit with Your Installation's Default Policy

If you code the exit, use it with your installation default policy for jobs that must wait for allocated or offline devices. Define your installation's default policy by specifying one of the following parameters on the POLICY keyword of the ALLC_OFFLN statement:

Parameter

Action

WTOR

Allow the messages to be issued so that the system operator must decide whether to cancel the job or let the job wait.

Note: In a sysplex environment, you want to reduce the number of WTORs; this exit might be a candidate for that consideration.

WAITHOLD

Allow jobs to wait for devices while it holds obtained resources.

WAITNOH

Allow jobs to wait for devices without holding obtained resources.

CANCEL

Cancel jobs that must wait for allocated or offline devices.

When you have chosen a default policy to handle most of possible requests for allocation of pending offline, offline, or already-allocated devices use the exit routine to make exceptions, if any, for certain jobs and devices. The exit routine's decisions override the installation's default policy.

If you do not code the exit routine, MVS uses your installation's default policy (specified in the ALLOCxx parmlib member) to determine how to respond to **all** allocation requests for allocated pending offline, or offline devices. If your installation does not define a default policy, the system always issues the WTORs.

Programming Considerations

Observe the following conventions when you code the Allocated or Offline Device Exit routine:

- Code the exit routine to be reentrant.
- Do not code the exit routine to issue dynamic allocation calls.
- Do not code an allocated or offline device exit routine if the decision of the exit routine is always the same regardless of which devices are needed. Instead, allow your installation's default policy to determine how to handle the allocation request.
- The exit is called every time that a job requires a device that is either offline, pending offline or allocated to another job. Therefore, when you code the exit routine, you should be aware that an increased path length increases processor usage and might degrade performance.
- When the exit routine determines that the system should issue WTORs (by setting the ACTION field to X'40'), the routine can modify the list of device numbers that are displayed, via WTOR, to the system operator. The exit routine can exclude certain device numbers from the WTOR by setting the UXEXCLUD bit of the UXSTATUS field for the device (in the offline device table) to 1.
- When you use system-managed tape libraries, it is possible to loop between offline recovery and the exit. In this situation, offline recovery calls the exit, which selects a tape device that is offline because it is in an offline system-managed tape library. However, offline recovery cannot bring the selected device online until the operator brings the library online. Therefore, the device is not removed from the table of offline eligible devices, and offline recovery again calls the exit. This looping occurs up to the number of times specified by the MAXNWAIT parameter of the ALLOCxx parmlib member. Then, the system uses the installation-defined default action.
- Before you use the UXOFLPTR pointer field in the input parameters, check the field's value to see whether there are offline devices eligible to be allocated. A UXOFLPTR value of zero indicates that no offline devices are eligible for this request, and only already allocated devices are eligible.
- Use the exit routine, with the installation default policy, to automate your installation's responses to the following WTORs:
 - IEF157E
 - IEF238D
 - IEF244I
 - IEF433D
 - IEF434D
 - IEF490I.
- When the exit routine requests to bring one or more devices online by setting the ACTION field to X'08' the system attempts to bring the requested device(s) online, and then retry the allocation. The system retries the allocation regardless of whether the devices can be brought online, and it might result in calling the exit routine again for the same allocation request. If the exit routine chooses the same devices to bring online, a loop results where Allocation repeatedly calls the exit routine to attempt to satisfy the request, and the exit routine takes an action that is unsuccessful and so the request can never be satisfied.

Message Processing

Use the exit routine, with the installation default policy, to suppress or automate your installation's responses to the following message:

- IEF238D - Reply [device name] [,] ['wait'] or 'cancel'

Note: In a sysplex environment, determine which, if any, devices require job-level support; for these devices, code the exit to mark the REPLY with the device number. For all other devices (most), determine whether this message should set UXONLINE to 1 to allow offline devices to be brought online and to allow a pending offline device to be considered for allocation.

- IEF244I - Unable to allocate <nnn> unit(s). At least <nnn> allocated or offline units are needed
- IEF433D - Wait requested — reply hold or nohold.

In addition, you might also avoid getting one or more of the following messages, which the system issues in response to invalid replies to the preceding messages:

- IEF434D - Invalid reply (to message IEF433D). Reply hold or nohold.
- IEF490I - Invalid reply (to message IEF238D) for one of the following reasons:
 - Device is not accessible
 - Required system managed volume is not available
 - Required volume is not available
 - Replied device is not eligible
 - Device might not be found in the configuration.
 - Device found in an offline library.
- IEF877E - jjobname NEEDS xxx UNIT(S) FOR stepname ddname FOR VOLUME(S): ser, ...,ser SCRTCH nn PRIVAT nn | LIBRARY: LIBNAME LIBRARY STATUS: STATUS state1 dev ...dev state2
- IEF878I - END OF IEF877E FOR stepname ddname

Macro Instructions and Restrictions

Do not code the exit routine to issue the WAIT macro or call a service that issues a WAIT, such as WTOR.

Entry Specifications

The system passes the address of the exit parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are:

Register

Contents

0

Not applicable

1

Address of a pointer to the exit parameter list

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of the exit routine

Parameter Descriptions: Register 1 contains the address of a pointer to the exit parameter list, the UXPARMD, which is mapped by macro IEFZB481 (data area UXPARMD). For a mapping of the UXPARMD data area, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

The exit routine indicates its decision to the system by setting the ACTION field (in the UXPARMD) to one of the following values:

Value

Meaning

X'80'

Cancel the job

X'40'

Issue the WTOR so that the operator can determine what to do

X'20'

Let the job wait without holding resources

X'10'

Let the job wait while holding resources

X'08'

Bring the device online or, if pending offline, allow the device to be considered for allocation

X'00'

Let the installation default policy determine what to do

If the exit routine does not return a valid value in the ACTION field, the system ignores the exit, issue a message, and use the installation default policy to make the decision.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-14

Restored to contents at entry

15

0

Coded Example of the Exit Routine

For your reference, IBM provides a coded example of this exit routine in SYS1.SAMPLIB. The member is named IEFOFLNE.

Chapter 19. IEF_ALLC_EVENT – Allocation Event Installation Exit

Topics for This Exit Appear as Follows:

- “Controlling the Exit Routine”
- “Replacing the Exit Routine” on page 107
- “Exit Routine Environment” on page 107
- “Exit Recovery” on page 108
- “Exit Routine Processing” on page 108
- “Programming Considerations” on page 109
 - Macro Instructions and Restrictions
- “Entry Specifications” on page 109
 - Registers at Entry
 - Parameter Descriptions
- “Return Specifications” on page 109
 - Registers at Exit
- “Coded Example of the Exit Routine” on page 110

The IEF_ALLC_EVENT exit is driven at various points in the allocation process, for example, at the start and end of batch allocation or dynamic allocation. Parameters describing the function are passed to the exit. These parameters are mapped by the IEFALCXT mapping macro.

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the Allocation Event installation exit to the dynamic exits facility. You can refer to the exit by the name IEF_ALLC_EVENT. You can use the CSVDYNEX macro to control this exit and its exit routines.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error.
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Replacing the Exit Routine

For information about replacing a dynamic exit routine, see [“Replacing a Dynamic Exit Routine” on page 6](#).

Exit Routine Environment

The exit routine receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 1.
- In AMODE 31 and RMODE ANY.

- With no locks held.

Exit Recovery

The exit routine should provide its own recovery. If the exit routine abnormally terminates, its recovery routine will get control.

If the exit routine abnormally terminates, and the exit routine does not provide its own recovery, or the error percolates beyond the exit's recovery routine, a system recovery routine will get control and fail the allocation request.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

MVS invokes the Allocation Event exit routine or routines, if any are specified to the dynamic exits facility, whenever an event takes place.

Using the Information in the Parameter List: MVS passes the address of a list of parameters to the exit routine. The parameters contain the following information:

- Eye-Catcher ALCXT
- Version ID
- Length of the parameter list
- Job name
- Step name
- Name of the step in the procedure
- One of the following functions indicating the nature of the event:
 - Beginning of batch allocation – 01
 - End of batch allocation -- 02
 - Beginning of dynamic allocation – 03
 - End of dynamic allocation – 04
 - Abend in allocation -- 05
 - Concatenate DD function -- 06
 - Deconcatenate DD function -- 07
 - Unallocation (batch) -- 08
 - Unallocation (Dynamic) -- 09
 - Beginning of Recovery Allocation Wait -- 0A
 - End of Recovery Allocation Wait -- 0B
- Pointer to an area, which contains function related data
 - End of batch allocation
Return code (0 for Success and 4 for Failure)
 - Beginning of dynamic allocation request
DDNAME
 - End of dynamic allocation request
DDNAME
Return code (0 for Success and 4 for Failure)

The exit routine can use the information in the parameter list. Because there is no action to be taken, the exit routine does not need to provide any response. MVS does not expect any response from the Allocation Event Exit.

Programming Considerations

Observe the following conventions when coding the IEF_ALLC_EVENT Exit routine:

- Code the exit routine to be reentrant.
- Do not code the exit routine to issue dynamic allocation calls.
- Do not code the exit routine if you do not need to be notified of an Allocation event.
- The exit is called every time a step allocation begins or ends. Therefore, when coding the exit routine, you should be aware that an increased path length will increase processor utilization and may degrade performance.
- Make sure that the exit routine does not get affected when new function code support is added.

Macro Instructions and Restrictions: Do not code the exit routine to invoke dynamic allocation.

Entry Specifications

The system passes the address of the exit parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of a pointer to the exit parameter list

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of the exit routine

Parameter Descriptions: Register 1 contains the address of a pointer to the exit parameter list, which is mapped by macro IEFALCXT.

Return Specifications

MVS does not provide any field for a response; the exit does not return a valid value.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-14

Restored to contents at entry

15

0

Coded Example of the Exit Routine

There is no coded example of this exit routine in SYS1.SAMPLIB.

Chapter 20. IEF_ALLC_MOD – Allocation Modify DDname Installation Exit

Topics for This Exit Appear as Follows:

- “Controlling the Exit Routine”
- “Replacing the Exit Routine” on page 111
- “Exit Routine Environment” on page 111
- “Exit Recovery” on page 112
- “Exit Routine Processing” on page 112
- “Programming Considerations” on page 112
 - Macro Instructions and Restrictions
- “Entry Specifications” on page 112
 - Registers at Entry
 - Parameter Descriptions
- “Return Specifications” on page 113
 - Registers at Exit
- “Coded Example of the Exit Routine” on page 113

The IEF_ALLC_MOD exit is driven when the service routine IEFDDSRV requests to modify a DDNAME. Parameters describing the modification are passed to the exit. These parameters are mapped by the IEFDISXT mapping macro.

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the Allocation Modify DDname installation exit to the dynamic exits facility. You can refer to the exit by the name IEF_ALLC_MOD. You can use the CSVDYNEX macro to control this exit and its exit routines.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error.
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Replacing the Exit Routine

For information about replacing a dynamic exit routine, see [“Replacing a Dynamic Exit Routine” on page 6](#).

Exit Routine Environment

The exit routine receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 1.
- In AMODE 31 and RMODE ANY.

- With no locks held.

Exit Recovery

The exit routine should provide its own recovery. If the exit routine abnormally terminates, its recovery routine will get control.

If the exit routine abnormally terminates, and the exit routine does not provide its own recovery, or the error percolates beyond the exit's recovery routine, a system recovery routine will get control and fail the allocation request.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

MVS invokes the Allocation Modify exit routine or routines, if any are specified to the dynamic exits facility, every time it modifies DDname for an IEFDDSRV service request.

Using the Information in the Parameter List: MVS passes the address of a list of parameters to the exit routine. The parameters contain the following information:

- Eye-catcher (IEFDISXT)
- Version ID
- Length of the parameter list
- Modify function
 - Modify DDNAME – 01
- Job name
- Step name
- Name of step in the procedure
- Modify Parameters
 - Address of the DSAB modified
 - DDNAME before Modification
 - DDNAME after Modification

The exit routine can use the information in the parameter list. Because there is no action to be taken, the exit routine does not need to provide any response. MVS will not expect any response from the Modify Exit.

Programming Considerations

Observe the following conventions when coding the IEF_ALLC_MOD Exit routine:

- Code the exit routine to be reentrant.
- Do not code the exit routine to issue dynamic allocation calls.
- Do not code the exit routine if you do not need to be notified of a DDname Modification by the IEFDDSRV request.
- The exit is called every time a DDname is modified by IEFDDSRV. Therefore, when coding the exit routine, you should be aware that an increased path length will increase processor utilization and may degrade performance.

Macro Instructions and Restrictions: Do not code the exit routine to invoke dynamic allocation.

Entry Specifications

The system passes the address of the exit parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

**Register
Contents**

0	Not applicable
1	Address of a pointer to the exit parameter list
2-12	Not applicable
13	Register save area
14	Return address
15	Entry point address of the exit routine

Parameter Descriptions: Register 1 contains the address of a pointer to the exit parameter list, which is mapped by macro IEFDISXT.

Return Specifications

MVS does not provide any field for a response; the exit does not return a valid value.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

**Register
Contents**

0-14	Restored to contents at entry
15	0

Coded Example of the Exit Routine

There is no coded example of this exit routine in SYS1.SAMPLIB.

Chapter 21. IEF_ALLC_UNLOAD – Allocation Event Installation Exit

Topics for This Exit Appear as Follows:

- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 115](#)
- [“Replacing the Exit Routine” on page 115](#)
- [“Exit Routine Environment” on page 115](#)
- [“Exit Recovery” on page 116](#)
- [“Exit Routine Processing” on page 116](#)
- [“Programming Considerations” on page 117](#)
- [“Entry Specifications” on page 117](#)
- [“Return Specifications” on page 117](#)
- [“Coded Example of the Exit Routine” on page 118](#)

The IEF_ALLC_UNLOAD exit is driven when a device is unloaded by Device Allocation outside of normal end-of-job or end-of-step device unload processing. It is invoked during processing such as VARY OFFLINE or UNLOAD commands.

This exit is called before the unload event starts and after the unload is complete. It is intended for programs that need to perform pre-processing or post-processing for an unload event. If your program only needs to be notified of an unload occurring and does not need to perform pre- or post-processing, then ENF function code 25 should be used instead.

Parameters describing the function are passed to the exit. These parameters are mapped by the IEFUNLXT mapping macro.

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the Allocation Event installation exit to the dynamic exits facility. You can refer to the exit by the name IEF_ALLC_UNLOAD. You can use the CSVDYNEX macro to control this exit and its exit routines.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error.
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Replacing the Exit Routine

For information about replacing a dynamic exit routine, see [“Replacing a Dynamic Exit Routine” on page 6](#).

Exit Routine Environment

The exit routine receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 1.

- In AMODE 31 and RMODE ANY.
- With no locks held.
- May be invoked with any of the following ENQs held:

SYSIEFSD.Q4

SYSIEFSD.VARYDEV

SYSIEFSD.CHNGDEVS

The parameter list contains information indicating which of the ENQs are obtained by another task on behalf of the unload process.

Exit Recovery

The exit routine should provide its own recovery. If the exit routine abnormally terminates, its recovery routine will get control.

If the exit routine abnormally terminates, and the exit routine does not provide its own recovery, or the error percolates beyond the exit's recovery routine, a system recovery routine will get control and fail the allocation request.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

MVS invokes the Unload Event exit routine or routines, if any are specified to the dynamic exits facility, whenever an unload event takes place.

Using the Information in the Parameter List: MVS passes the address of a list of parameters to the exit routine. The parameters contain the following information:

- Eye-catcher (UNLXT)
- Version ID
- Length of the parameter list
- One of the following functions indicating the nature of the event:
 - Beginning of Unload event - 01
 - End of Unload event - 02
 - ABEND occurred during unload - 03
- Flags indicating which of the following ENQs are held by the caller:
 - SYSIEFSD.CHNGDEVS
 - SYSIEFSD.VARYDEV
 - SYSIEFSD.Q4
- One of the following source values that indicates the reason the exit is invoked:
 - Unload is on behalf of the VARY OFFLINE command or comparable IEEVARYD request - 01
 - Unload is on behalf of the UNLOAD command - 02
 - Unload is on behalf of a non-Allocation requestor - 03

Beginning in z/OS V2R3, the source information is always available in the parameter list. For z/OS V1R13, z/OS V2R1, and z/OS V2R2 systems, the source information is only available when APAR OA49722 is installed. When OA49722 is not installed, the corresponding location in the parameter list will always contain zero. When OA49722 is installed, the field will always contain a non-zero value.

- Address of the UCB of the device being unloaded. The system does not pin the UCB before calling the exit.

The exit routine can use the information in the parameter list. Because there is no action to be taken, the exit routine does not need to provide any response from the Unload Event exit.

Programming Considerations

Observe the following conventions when coding the IEF_ALLC_UNLOAD Exit routine:

- Code the exit routine to be reentrant.
- Do not code the exit routine to issue dynamic allocation calls.
- Do not code the exit routine if you do not need to be notified of an Unload event.
- The exit is called whenever an unload event begins or ends. Therefore, when coding the exit routine, you should be aware that an increased path length will increase processor utilization and may degrade performance. This includes issuing WAITs or invoking routines that may issue WAITs. Also, because of the serialization environment, other system processes may be delayed until the exit routine completes if the exit was invoked with any ENQs held.
- Make sure that the exit routine does not get affected when new function code support is added or new exit source values are added.

Macro Instructions and Restrictions: Do not code the exit routine to invoke dynamic allocation.

Entry Specifications

The system passes the address of the exit parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of the exit parameter list

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of the exit routine

Parameter Descriptions: Register 1 contains the address of the exit parameter list, which is mapped by macro IEFUNLXT.

Return Specifications

MVS does not provide any field for a response; the exit does not return a valid value.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-14

Restored to contents at entry

15

0

Coded Example of the Exit Routine

There is no coded example of this exit routine in SYS1.SAMPLIB.

Chapter 22. IEF_SPEC_WAIT – Specific Waits Installation Exit

Topics for This Exit Appear as Follows:

- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 120](#)
- [“Replacing the Exit Routine” on page 120](#)
- [“Exit Routine Environment” on page 120](#)
- [“Exit Recovery” on page 120](#)
- [“Exit Routine Processing” on page 120](#)
- [“Programming Considerations” on page 122](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 122](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 123](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 123](#)

When a job must wait for a **specific** volume or device to become available, MVS issues a WTOR that requests the system operator to cancel the job or let the job wait for the volume or device. You can automate your installation's responses to specific waits allocation requests and reduce the need for system operator intervention by:

- Defining an installation default policy for handling a **majority** of the specific waits allocation requests that are likely to occur. Specify the default policy in the ALLOCxx member of SYS1.PARMLIB.
- Coding the specific waits exit routine to make exceptions (for certain jobs and/or volumes) to the installation default policy. You can specify the exit in the EXITxx or PROGxx member of SYS1.PARMLIB, but IBM recommends that you use PROGxx.

Using the information it receives about the job, the specific waits exit routine can:

- Cancel the job
- Allow the job to wait while:
 - holding resources
 - not holding resources
- Allow the installation default policy to determine the action to take.
- Allow the WTORs to be issued so that the system operator can determine the action to take.

For a list of the allocation messages you can automate or suppress, see the [“Programming Considerations” on page 122](#).

For more information on the ALLOCxx, EXITxx and PROGxx members of SYS1.PARMLIB, see [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the specific waits installation exit to the dynamic exits facility. You can refer to the exit by the name IEF_SPEC_WAIT. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Replacing the Exit Routine

For information about replacing a dynamic exit routine, see [“Replacing a Dynamic Exit Routine”](#) on page 6.

Exit Routine Environment

The exit routine receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 1.
- In AMODE 31 and RMODE ANY.
- With no locks held. (However, it may hold an exclusive ENQ on major name SYSZTIOT for the address space in which the allocation occurs.)

Exit Recovery

The exit routine should provide its own recovery. If the exit routine abnormally terminates, its recovery routine will get control.

If the exit routine abnormally terminates, and the exit routine does not provide its own recovery, or the error percolates beyond the exit's recovery routine, a system recovery routine will get control. The system will fail the allocation request.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

MVS invokes the specific waits exit routine or routines every time a job must wait for a **specific** volume or a **specific** device to become available.

Example of a Wait for a Specific Volume: In the following example, JOB1 acquires a shareable ENQ on volume 3350A0. JOB2 attempts to acquire an exclusive ENQ on the same volume:

```
//JOB1      JOB
//DD        ... ,UNIT=12A0 ,VOL=SER=3350A0...

//JOB2      JOB
//DD        ... ,UNIT=12A1 ,VOL=SER=3350A0...
```

Because JOB2 must have exclusive access to the volume, JOB2 must wait for JOB1 to DEQ from the volume. MVS invokes the specific waits exit for JOB2's allocation request because JOB2 must wait for a specific volume.

Example of a Wait for a Specific Device: In the following example, JOB1 and JOB2 acquire ENQs on different specific volumes, 3350A2 and 3350B2. JOB2 specifies the same device, 2A0, that JOB1 controls.

```
//JOB1      JOB
//DD        ... ,UNIT=12A0 ,VOL=SER=3350A2...

//JOB2      JOB
//DD        ... ,UNIT=12A0 ,VOL=SER=3350B2...
```

MVS invokes the specific waits exit for JOB2's allocation request because JOB2 must wait for a specific device.

Using Information in the Exit Parameter List: Before issuing WTORs that identify the volume(s) that are unavailable and request operator action, MVS invokes the specific waits exit routine, if one is specified, and passes it a set of parameters that contains the following information about the allocation request:

- Job name
- Step name
- Name of the DD statement that requires the specific volume or device
- Name of the data set that requires the specific volume or device
- Serial number of the specific volume (if one is required)
- Device number of the device that is required
- An indication of whether the job is waiting for both a specific volume and a device, or for a specific device only.
- The number of 'wait without holding resources' decisions that the system will allow both the exit routine and the installation default to make for a particular device allocation request. This number (in the WAITNOHC field of the exit parameter list) does not limit the number of 'wait without holding resources' decisions that can be made by the system operator.
- Action to be taken in response to WTOR (this field, ACTION, is filled in by the exit routine).

Using the information in the parameter list, the exit routine determines how the system should respond to the allocation request. The exit routine indicates its decision to the system by placing a value in the ACTION field of the exit parameter list.

See [“Return Specifications” on page 123](#) for the specific values the exit routine can return.

Using the Exit with Your Installation's Default Policy: If you code the exit, use it in conjunction with your installation default policy for jobs that must wait for specific volumes. Determine your installation's default policy by specifying one of the following parameters on the POLICY parameter of the SPEC_WAIT statement:

Parameter Action

WTOR

Allow the specific wait messages to be issued so that the system operator must decide whether to cancel the job or let the job wait. (For a list of these messages, see [“Programming Considerations” on page 122.](#))

WAITHOLD

Allow jobs to wait for devices while holding obtained resources.

WAITNOH

Allow jobs to wait for devices without holding obtained resources.

CANCEL

Cancel jobs that must wait for a volume to be released.

When you have chosen a default policy to handle the majority of specific wait WTORs that can occur, use the specific waits exit routine to make exceptions, if any, for certain jobs and/or volumes. The exit routine's decisions will override the installation's default policy.

If you do not code the specific waits exit routine, MVS will use your installation's default policy (specified in the ALLOCxx member) to determine how to respond to **all** specific waits allocation requests. If your installation does not define a default policy, the system will always issue the specific wait WTOR.

Programming Considerations

Observe the following conventions when coding the specific waits exit routine:

- Code the exit routine so that it is reentrant.
- Do not code the exit routine to issue dynamic allocation calls.
- Do not code the exit routine if its decision will always be the same regardless of which jobs are waiting or which volumes are needed. Instead, allow your installation's default policy to make the decision.
- The exit is called every time a job requires a specific volume. Therefore, when coding the exit routine, you should be aware that an increased path length will increase processor utilization and may degrade performance.

Message Processing: Use the exit routine, in conjunction with the installation default policy, to suppress and automate your installation's responses to the following messages:

- IEF238D - Reply [device name] [,] ['wait'] or 'cancel'
- IEF244I - Unable to allocate <nnn> units(s). At least <nnn> allocated or offline units are needed.
- IEF433D - Wait requested — reply hold or nohold
- IEF488I - Must wait for a unit, or volume on unit.

In addition, you might also avoid getting one or more of the following messages which the system issues in response to an invalid reply to the preceding messages:

- IEF434D - Invalid reply (to message IEF433D). Reply hold or nohold.
- IEF490I - Invalid reply (to message IEF238D) for one of the following reasons:
 - Device is not accessible
 - Required system-managed volume is not available
 - Required volume is not available
 - Replied device is not eligible
 - Device could not be found in the configuration.

Macro Instructions and Restrictions: Do not code the exit routine to issue the WAIT macro or call a service that issues a WAIT, such as WTOR.

Entry Specifications

The system passes the address of the exit parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of a pointer to the exit parameter list

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of the exit routine

Parameter Descriptions: Register 1 contains the address of a pointer to the exit parameter list, the UXPARMC, which is mapped by macro IEFZB480 (data area UXPARMC). For a mapping of the UXPARMC data area, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

The exit routine indicates its decision to the system by setting the ACTION field (in the UXPARMC) to one of the following values:

Value**Meaning****X'80'**

Cancel the job

X'40'

Issue the WTOR so that the operator can determine what to do

X'20'

Let the job wait without holding resources

X'10'

Let the job wait while holding resources

X'00'

Let the installation default policy determine what to do

If the exit routine does not return a valid value, the system will ignore the exit and use the installation default policy to make the decision.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register**Contents****0-14**

Restored to contents at entry

15

0

Coded Example of the Exit Routine

For your reference, IBM provides a coded example of this exit routine in SYS1.SAMPLIB. The routine is named IEFSWAIT.

Chapter 23. IEF_VOLUME_ENQ – Volume ENQ Installation Exit

Topics for This Exit Appear as Follows:

- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 126](#)
- [“Replacing the Exit Routine” on page 126](#)
- [“Exit Routine Environment” on page 126](#)
- [“Exit Recovery” on page 126](#)
- [“Exit Routine Processing” on page 126](#)
- [“Programming Considerations” on page 127](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 127](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 128](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 128](#)

When a job must wait to enqueue on a volume or a series of volumes, MVS issues a WTOR that requests the system operator to cancel the job or let the job wait. You can automate your installation's responses to volume ENQ WTORs and reduce the need for operator intervention by:

- Defining an installation default policy for handling a **majority** of the volume ENQ allocation requests that are likely to occur. Specify the default policy on the VOL_ENQ statement in the ALLOCxx member of SYS1.PARMLIB.
- Coding the volume ENQ exit routine to make exceptions, if any, to the installation default policy for certain jobs and/or volumes. You can specify the exit in the EXITxx or PROGxx member of SYS1.PARMLIB; however, IBM recommends that you use PROGxx.

Using the information it receives about the job, the volume ENQ exit routine determines whether to:

- Cancel the job and suppress the WTOR
- Allow the job to wait
- Allow the WTOR to be issued so that the system operator must decide whether to cancel the job or let the job wait
- Allow the installation default policy to determine whether to cancel the job or issue the WTOR.

For a list of the allocation messages you can automate or suppress, see [“Programming Considerations” on page 127](#).

For more information on the ALLOCxx, EXITxx, and PROGxx parmlib members, see [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the volume ENQ installation exit to the dynamic exits facility. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Replacing the Exit Routine

For information about replacing a dynamic exit routine, see [“Replacing a Dynamic Exit Routine” on page 6](#).

Exit Routine Environment

The exit routine receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 1.
- In AMODE 31 and RMODE ANY.
- With no locks held. (However, it may hold an exclusive ENQ on major name SYSZTIOT for the address space in which the allocation occurs.)

Exit Recovery

The exit routine should provide its own recovery. If the exit routine abnormally terminates, its recovery routine will get control.

If the exit routine abnormally terminates, and the exit routine does not provide its own recovery, or the error percolates beyond the exit's recovery routine, a system recovery routine will get control. The system will fail the allocation request.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

MVS invokes the volume ENQ exit routine or routines every time a job must wait to enqueue on a volume. Before issuing messages (listed in [“Programming Considerations” on page 127](#)) that identify the volume(s) and request operator action, MVS invokes the volume ENQ exit routine or routines, if any are specified to the dynamic exits facility, and passes a list of parameters that contains the following information about the allocation request:

- Job name
- Step name
- A table containing the serial numbers of the volumes that the job requires
- Action to be taken in response to WTOR (this field, ACTION, is filled in by the exit routine).

Using the information in the parameter list, the exit routine indicates to the system (in the ACTION field of the parameter list) whether the system should:

- Cancel the job and suppress the WTORs

- Allow the job to wait for the volume(s)
- Allow the WTORs to be issued so that the system operator must make the decision
- Allow the installation's default policy to make the decision.

See “Return Specifications” on page 128 for the specific values the exit routine can return.

Using the Exit with Your Installation's Default Policy: If you code the exit, use it in conjunction with your installation default policy for jobs that must wait to enqueue on volumes. Determine your installation's default policy by specifying one of the following parameters on the POLICY parameter of the VOLUME_ENQ statement:

**Parameter
Action**

CANCEL

Cancel jobs that must wait for a volume to be released

WTOR

Allow the volume ENQ messages to be issued so that the system operator must decide whether to cancel the job or let the job wait.

WAIT

Allow jobs to wait for volumes to be released.



Attention: When WAIT is used as the default, deadlocks with other jobs in the system might arise for tape volumes.

When you have chosen a default policy to handle the majority of volume ENQ WTORs that can occur, use the volume ENQ exit routine to make exceptions, if any, for certain jobs and/or volumes. The exit routine's decisions will override the installation's default policy.

If you do not code the volume ENQ exit routine, MVS will use your installation's default policy (specified in the ALLOCxx member) to determine how to respond to **all** volume ENQ allocation requests. If your installation does not define a default policy, the system will always issue the volume ENQ WTORs.

Programming Considerations

Observe the following conventions when coding the volume ENQ exit routine:

- Code the exit routine so that it is reentrant.
- Do not code the exit routine to issue dynamic allocation calls.
- Do not code the exit routine if its decision will always be the same regardless of which jobs are waiting or which volumes are needed. Instead, allow your installation's default policy to make the decision.
- The exit is called every time a job requires a volume to be released. Therefore, when coding the exit routine, you should be aware that an increased path length will increase processor utilization and may degrade performance.

Message Processing: Use the exit routine, in conjunction with the installation default policy, to suppress and automate your installation's responses to the following messages:

- IEF690I - The following volumes are unavailable to <jobname>...
- IEF235D - <jobname> is waiting for volumes. To cancel wait, reply no.

In addition, you might avoid getting message IEF369D (invalid reply), which the system issues in response to an invalid reply to IEF235D.

Macro Instructions and Restrictions: Do not code the exit routine to issue the WAIT macro or call a service that issues a WAIT, such as WTOR.

Entry Specifications

The system passes the address of the exit parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

0	Not applicable
1	Address of a pointer to the exit parameter list
2-12	Not applicable
13	Register save area
14	Return address
15	Entry point address of the exit routine

Parameter Descriptions: Register 1 contains the address of a pointer to the exit parameter list, the UXPARMA, which is mapped by macro IEFZB478 (data area UXPARMA). For a mapping of the UXPARMA data area, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

The volume ENQ exit indicates its decision to the system by placing one of the following values in the 1-byte ACTION field of the exit parameter list (the UXPARMA):

Value Explanation

X'80'	Cancel the job and suppress the WTOR
X'40'	Issue the WTOR so that the system operator can make the decision
X'08'	Let the job wait for the volume(s)
X'00'	Let the installation default policy make the decision

If the exit routine does not return a valid value in the ACTION field, the system will ignore the exit and use the installation default policy to make the decision.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0-14	Restored to contents at entry
15	0

Coded Example of the Exit Routine

For your reference, IBM provides a coded example of this exit routine in SYS1.SAMPLIB. The routine is named IEFVENQS.

Chapter 24. IEF_VOLUME_MNT – Volume Mount Installation Exit

Topics for This Exit Appear as Follows:

- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 129](#)
- [“Replacing the Exit Routine” on page 130](#)
- [“Exit Routine Environment” on page 130](#)
- [“Exit Recovery” on page 130](#)
- [“Exit Routine Processing” on page 130](#)
- [“Programming Considerations” on page 131](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 131](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 132](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 132](#)

When a job's allocation request requires a volume to be mounted, MVS issues a WTOR that requests the system operator to mount the volume or cancel the job. You can automate your installation's responses to volume mount WTORs, and reduce the need for operator intervention, by defining an installation default policy for volume mount allocation requests in the ALLOCxx member of SYS1.PARMLIB. The policy you specify will handle the majority of volume mount allocation requests that can occur.

Code a volume mount exit routine when you want to make exceptions to your installation default policy for certain jobs and/or volumes. Using the information it receives about the job, the exit routine determines whether to:

- Cancel the job and suppress the WTOR
- Allow the WTOR to be issued so that the system operator must decide whether to cancel the job or mount the volume
- Allow your installation's default policy to determine whether to cancel the job or issue the WTOR.

For a list of the allocation messages you can automate or suppress, see [“Programming Considerations” on page 131](#).

For more information on the ALLOCxx and EXITxx members of SYS1.PARMLIB, see [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the volume mount exit to the dynamic exits facility. You can refer to the exit by the name IEF_VOLUME_MNT. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Replacing the Exit Routine

For information about replacing a dynamic exit routine, see [“Replacing a Dynamic Exit Routine” on page 6](#).

Exit Routine Environment

The exit receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 1.
- In AMODE 31 and RMODE ANY.
- With no locks held. (However, it may hold an exclusive ENQ on major name SYSZTIOT for the address space in which the allocation occurs.)
- Can reside in (E)PLPA, (E)MLPA, or (E)FLPA.

Exit Recovery

The exit routine should provide its own recovery. If the exit routine abnormally terminates, its recovery routine will get control.

If the exit routine abnormally terminates, and the exit routine does not provide its own recovery, or the error percolates beyond the exit's recovery routine, a system recovery routine will get control. The system will fail the allocation request.

Whether or not the exit routine continues to be invoked depends on theabend processing of the dynamic exits facility. However, the exit routine will continue to be invoked for all other volume mount allocation requests.

Exit Routine Processing

MVS invokes the volume mount exit routine or routines every time a job must wait for a volume to be mounted. Before issuing WTORs that identify the volume(s) to be mounted and request operator action, MVS invokes the volume mount exit routine or routines, if any are specified to the dynamic exits facility, and passes a set of parameters that contains the following information about the allocation request:

- Job name
- Step name
- DD name of the data set that requires the volume to be mounted
- Data set name
- Volume serial number
- Device number of the device on which the volume is to be mounted
- Flags indicating the type of label on the volume, if any
- Action to be taken in response to WTOR (this field is filled in by the exit routine).

Using the information in the parameter list, the exit routine indicates to the system (by placing a value in the ACTION field of the parameter list) whether the system should:

- Cancel the job
- Allow the WTORs to be issued so that the system operator must make the decision
- Allow the installation's default policy to make the decision.

See “Return Specifications” on page 132 for the specific values the exit routine can return.

Using the Exit with Your Installation's Default Policy: If you code the exit, use it in conjunction with your installation's default policy for jobs that require volumes to be mounted. Determine your installation's default policy by specifying one of the following parameters on the POLICY parameter of the VOLUME_MNT statement:

Parameter

Action

CANCEL

Cancel jobs that must wait for a volume to be mounted.

WTOR

Allow the volume mount messages to be issued so that the system operator must decide whether to cancel the job or mount the volume.

When you have chosen a default policy to handle the majority of volume mount WTORs that can occur, use the volume mount exit routine to make exceptions, if any, for certain jobs and/or volumes. The exit routine's decisions will override the installation's default policy.

If you do not code the volume mount exit routine, MVS will use your installation's default policy (specified on the ALLOCxx parmlib member) to determine how to respond to **all** allocation volume mount requests (either cancelling all jobs that must wait for a volume to be mounted, or always allowing the WTOR to be issued). If your installation does not define a default policy, the system will always issue the volume mount WTOR.

Programming Considerations

Observe the following conventions when coding the volume mount exit routine:

- Code the exit routine to be reentrant.
- Do not code the exit routine to issue dynamic allocation calls.
- Do not code the exit routine if its decision will always be the same regardless of which volumes are needed. Instead, allow your installation's default policy to make the decision.
- The exit is called every time a job requires a volume to be mounted. Therefore, when coding the exit routine, you should be aware that an increased path length will increase processor utilization and may degrade performance.

Message Processing: Use the exit routine, in conjunction with the installation default policy, to suppress and automate your installation's responses to the following messages:

- IEF233A - Mount volume <ser>
- IEF233D - Mount volume <ser> or respond to IEF455D message
- IEF455D - Mount <ser> on <device> for <jobname> or reply no.

In addition, you might avoid getting message IEF369D (invalid reply), which the system issues in response to an invalid reply to IEF455D.

Macro Instructions and Restrictions: Do not code the exit routine to issue the WAIT macro or call a service that issues a WAIT, such as WTOR.

Entry Specifications

The system passes the address of the exit parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

- 1**
Address of a pointer to the exit parameter list
- 2-12**
Not applicable
- 13**
Register save area
- 14**
Return address
- 15**
Entry point address of the exit

Parameter Descriptions: Register 1 contains the address of a pointer to the exit parameter list, the UXPARMB, which is mapped by macro IEFZB479 (data area UXPARMB). For a mapping of the UXPARMB data area, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

The volume mount exit indicates its decision to the system by placing one of the following values in the 1-byte ACTION field of the exit parameter list:

Value

Explanation

X'80'

Cancel the job and suppress the WTOR

X'40'

Issue the WTOR so that the system operator can make the decision

X'00'

Let the installation default policy make the decision

If the exit routine does not return a valid value, the system will ignore the exit and use the installation default policy to make the decision.

If you associate multiple exit routines with IEF_VOLUME_MNT, you can specify how the return information is to be handled using the ATTRIB KEEPRLC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEPRLC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRLC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-14

Restored to contents at entry

15

0

Coded Example of the Exit Routine

For your reference, IBM provides a coded example of this exit routine in SYS1.SAMPLIB. The routine is named IEFVOLMT.

Chapter 25. IEFACTRT — SMF Job and Job Step Termination Exits

Topics for This Exit Appear as Follows:

- [“Defining the Exit in SMFPRMxx” on page 134](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 134](#)
- [“Exit Routine Environment” on page 134](#)
- [“Exit Recovery” on page 135](#)
- [“Exit Routine Processing” on page 135](#)
- [“Programming Considerations” on page 136](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 137](#)
 - Registers at Entry
 - Parameter Descriptions
 - Common Exit Parameter Area
- [“Return Specifications” on page 143](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 145](#)

IEFACTRT receives control from the system when a job or job step terminates, either normally or abnormally. A return code from IEFACTRT (in register 15) indicates whether the job is to continue or terminate. Another return code (in register 1) indicates whether or not SMF is to write the termination records to the SMF data set.

The system invokes IEFACTRT only when the installation is collecting SMF record types 4, 5, 30, 32, 34, or 35. IEFACTRT is invoked for:

- Record types 4, 5, and 30 for background jobs and started tasks.
- Record types 30, 32, 34, and 35 for TSO/E users.
- Record type 30 (subtypes 4 and 5) for work initiated by the IBM-supplied APPC/MVS transaction scheduler (ASCH).

When the data for an SMF record exceeds 32,756 bytes in length, the system constructs one or more "continuation" or "additional" records to ensure that no individual record exceeds that length. The system invokes IEFACTRT once for the original record and once for each continuation record.

The system invokes IEFACTRT for these types of records even when an installation uses the SYS(NOTYPE) parameter in SMFPRMxx to suppress a particular subtype of these record types. Only when the installation suppresses an entire record type through SMFPRMxx will the system not pass the record to IEFACTRT.

The system does not invoke IEFACTRT for any other record types.

You can use IEFACTRT to:

- Write selected job or job step records to an installation-defined data set for further analysis.
- Displacement from PointerInclude additional information in the SMF job/job step termination records.

- Write messages to a job log to provide additional information about the job or job step. For example, if the operator has cancelled a job, you can issue a WTOR to learn why the job was cancelled and then write the reason as a message to the job log.
- Write an estimated job or job step cost to the job log.
- Update tables that describe the amount of resources certain users consume. For example, you can keep a total of the processor time for specific users, then flag their account numbers if they exceed an allowed time limit.

Defining the Exit in SMFPRMxx

In the SMF parmlib member (SMFPRMxx), specify IEFACTRT on the EXITS option of the SYS or SUBSYS parameters, depending on the scope of work (system-wide or subsystem-wide) the exit is to affect.

If you use the SUBSYS option, the system invokes the IEFACTRT routine only for work running under the subsystems you specify on SUBSYS. If you use the SYS option, the system invokes the IEFACTRT routine for work running under any SMF-defined subsystem, such as JES2, JES3, STC, ASCH, OMVS, or TSO.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFACTRT installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFACTRT or SYSyyy.IEFACTRT. See the description of the SMFPRMxx parmlib member in [z/OS MVS Initialization and Tuning Reference](#) for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

To define IEFACTRT to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for IEFACTRT, you need only define this exit in SMFPRMxx.

The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFACTRT in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFACTRT).

If you associate exit routines with IEFACTRT in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Exit Routine Environment

IEFACTRT receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 31.
- In the address space of the task that is currently running.

- With no locks or ENQs held.

Exit Recovery

IBM strongly recommends that you set up an ESTAEX recovery routine to handle errors that might occur during the execution of IEFACRT.

An ESTAE-type recovery routine is set up by the module that calls IEFACRT; the recovery routine, if it gets control, will allow the job to continue processing if the exit routine abnormally ends.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

SMF constructs several types of termination records. An installation can use the IEFACRT exit routine to include additional information in the termination record and to determine whether to write the termination record to the SMF data set. The specific SMF termination records that IEFACRT references are:

Dec (Hex)	Description
-----------	-------------

4 (X'04')	The step termination record is constructed and written at the normal or abnormal termination of a job or job step for a background job, or when a job step is flushed during or after job initiation.
------------------	---

5 (X'05')	The job termination record is constructed and written at the normal or abnormal termination of a background job.
------------------	--

30 (X'1E')	The common address space work record is written at the normal or abnormal termination of a batch job or step, a TSO/E session, a started task, or work initiated by the IBM-supplied APPC/MVS transaction scheduler and at the expiration of a specified interval. The type 30 record consolidates data that also is found in record types 4, 5, 20, 34, 35, and 40. Record subtypes are used within the type 30 record to help limit the amount of data stored in SMF data sets.
-------------------	---

32 (X'20')	The TSO/E user work accounting record is written when a TSO/E session terminates (normally or abnormally) and when a TSO/E accounting interval expires.
-------------------	---

34 (X'22')	The TSO-step termination record is constructed and written when the TSO/E logoff function processes a job step termination.
-------------------	---

35 (X'23')	The logoff record is constructed and written when a logoff process is completed.
-------------------	--

At job or job step termination, use the termination indicators in record types 4, 5 and 30 to determine whether or not IEFACRT cancelled the job.

The length of the type 30 record is variable. If the data exceeds 32,756 bytes, the system constructs "continuation" (or "additional") type 30 records. Each such record always contains these three sections:

- Header section
- Subsystem section
- Identification section

In addition, each continuation record contains one or more of the following sections:

- Execute channel program (EXCP) section
- Usage section

- Automatic restart management section
- z/OS UNIX process section

For the subtype 4 (step termination) record passed by the record, expect:

- The field at offset +06'x (SMF30TME) will contain '00000000'x.
- The field at offset +0A'x (SMF30DTE) will contain '0000000F'x.

For the subtype 5 (job termination) record passed by the record, expect:

- The field at offset +06'x (SMF30TME) will contain '00000000'x.
- The field at offset +0A'x (SMF30DTE) will contain '00000000'x.

Your exit routine should be aware of these added type 30 continuation records, because they are passed to IEFACTRT. See the CAUTION bullet in the next section, "Programming Considerations," if the exit routine suppresses some of these records. See *z/OS MVS System Management Facilities (SMF)* for more information concerning type 30 records.

IEFACTRT is the only SMF exit routine that can write to a job log, but only by passing the message to module IEFYS. When IEFYS receives control, register 13 must contain the address of an 18-word save area and register 12 must be used to pass message information. Figure 5 on page 136 shows the procedure for writing JOBLOG messages from IEFACTRT. The maximum number of characters that can appear in a message is 132.

MVC	36(4,12),MSGADDR	MOVE MESSAGE ADDRESS AND
MVC	42(2,12),MSGLEN	LENGTH TO SYSTEM TABLE
L	REG15,VIEFYS	BRANCH AND LINK TO MESSAGE
BALR	REG14,REG15	ROUTINE
MSGADDR	DC A(MSG)	
MSG	DC C'message text'	
MSGLEN	DC H'xx'	MESSAGE LENGTH
VIEFYS	DC V(IEFYS)	

Figure 5. Writing Job Log Messages from IEFACTRT

To resolve the VCON for IEFYS correctly, be sure to follow the example in Figure 6 on page 136 which shows how to make an IEFACTRT installation exit routine available to the system by link editing it into a system library.

```
//LKUSRPGM    JOB      MSGLEVEL=(1,1)
//            EXEC     PGM=IEWL,PARM='XREF,LET,LIST'
//SYSPRINT    DD      SYSOUT=A
//SYSUT1      DD      UNIT=SYSDA,SPACE=(TRK,10)
//SYSLMOD     DD      DSN=SYS1.LINKLIB,DISP=OLD
//SYSLIB      DD      DSN=SYS1.AOSB3,DISP=SHR
//SYSLIN      DD      *
               object deck
               INCLUDE  SYSLIB(IEFTB724)
               NAME     EXITNAME(R)
/*
```

Figure 6. Example: make an IEFACTRT installation exit routine available

Programming Considerations

SMF provides a replaceable module for an unused exit. If an installation includes IEFACTRT, it must follow certain programming standards.

- The exit routine must follow standard linkage conventions. For example, upon exit, register 15 must contain the return code. (But see the note in the topic "Registers at Exit" later in this chapter.)
- Code the exit routine to be reentrant.
- IEFACTRT can perform dynamic allocations and write to installation-defined data sets. In foreground jobs, data sets are allocated dynamically. However, for background jobs, you can either allocate data

sets dynamically or you can pre-define (pre-allocate) a data set with a DD statement in the initiator cataloged procedure.

- IEFACTRT cannot access ISAM data sets.
- Do not use a WTO with a routing code of 11 to send a message to the JESYSMSG data set for started tasks or TSO users.
- To provide a consistent environment for accessing and allocating data sets across calls to SMF exits for the duration of a job or task, IEFACTRT receives control with the initiator's JSCB active.
- When there are multiple data records, the IEFACTRT exit routine receives control once for each record.
- **CAUTION:** If the IEFACTRT installation exit elects to suppress one or more BUT NOT ALL of the SMF type 30 continuation records, then follow-on batch jobs that process SMF records might encounter unexpected and invalid conditions, such as:
 - "Continuation" type 30 records without the initial type 30 record
 - An initial type 30 record indicating that more type 30 records follow, but some or all of those continuation records are not present.

Macro Instructions and Restrictions: Your IEFACTRT exit routine can issue MVS system macros. Observe the following restrictions:

- Do not code your IEFACTRT exit routine to issue the WAIT macro, or call a service that issues WAIT. Doing so in IEFACTRT can adversely affect the system's allocation and unallocation functions.
- Do not use a WTO with a routing code of 11 to send a message to the JES joblog for started tasks or TSO users.

The following SMF macros are available to SMF installation exit routines:

- IFASMFR — to address SMF record fields
- SMFWTM — to write records to the SMF data set
- SMFEWTM — to write records to the SMF data set
- SMFRTEST — to test record recording
- SMFEXIT — to branch to the SMF exits
- SMFINTVL — to determine interval time
- SMFDETAL — to test detail recording
- SMFSUBP — to determine subsystem parameters
- SMFCHSUB — to change subsystem parameters.

For information on how to use these macros, see [z/OS MVS System Management Facilities \(SMF\)](#).

Entry Specifications

SMF passes to IEFACTRT a code to define the reason for calling the exit routine and a list of parameter addresses that the routine can use.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

One of the following hexadecimal codes that indicate why SMF has invoked the exit:

Code

Explanation

X'0C'

Indicates job step termination. Word 10 in the parameter list is the address of the record descriptor word (RDW) for a type 4 or type 34 record.

X'10'

Indicates job termination. Word 10 in the parameter list is the address of the RDW for a type 5 or type 35 record.

X'14'

Indicates job or step termination. Word 10 in the parameter list is the address of the RDW for a type 30 record. The subtype field in the type 30 record determines if it is a job or a step termination record.

X'18'

Indicates TSO/E session or accounting interval termination. Word 10 in the parameter list is the address of the RDW for a type 32 record.

1

Address of the parameter list

2-11

Not applicable

12

Address of a message information area, which can be used to interface to IEFYS.

13

Register save area

14

Return address

15

Entry point address of IEFACTRT

Parameter Descriptions: Register 1 points to the following list of addresses:

Word 1

Address of the common exit parameter area. For details, see [“Common Exit Parameter Area” on page 140](#).

Word 2

Address of an 8-byte area containing the job step name (in EBCDIC). This area is aligned left and padded with blanks if necessary. At job termination, the field is zero.

Note: It is possible that some address spaces will be associated with IEESYSAS. For that case, JMRJOB will contain IEESYSAS.

Word 3

Address of a 20-byte area containing the programmer's name (in EBCDIC). This area is aligned left and padded with blanks if necessary.

Word 4

Address of a 4-byte area. The first 3 bytes contain the job processor time (which includes time under TCBs, enclave time, preemptable class SRB time, and client SRB time), in hundredths of a second (in binary). The last byte contains the number of accounting fields in the JOB statement. At job termination, the field is zero.

Note: Since this job processor time is only 3 bytes it is limited to 46 hours. If the job accumulates more than this amount of processor time, this field will become invalid. You can avoid this situation by having your exit get the processor time from the parameter at word 11.

Word 5

Address of a variable length area that contains accounting fields from the JOB statement. For details, see [Table 4 on page 142](#).

Word 6

Address of a 4-byte area. The first 3 bytes contain the step processor time (which includes time under TCBs, enclave time, preemptable class SRB time, and client SRB time), in hundredths of a second (in binary). The last byte contains the number of accounting fields in the EXEC statement (in binary). At job termination, the field is zero.

Note: Since this step processor time is only 3 bytes it is limited to 46 hours. If the step accumulates more than this amount of processor time, this field will become invalid. You can avoid this situation by having your exit get the processor time from the parameter at word 12.

Word 7

Address of a variable length area that contains accounting fields from the EXEC statement. For details, see [Table 4 on page 142](#).

Word 8

Address of a 2-byte area. The first byte is a binary indicator; if bit 7 (low-order bit) is set to 1 when the exit routine is entered, the job has been cancelled. If the exit routine sets bit 7 to 1, the job will be cancelled. The second byte contains the number of the job step currently being processed. At job termination, the second byte contains the number of steps in the job.

Word 9

Address of a 2-byte area containing the termination status (condition or completion code) for the job or job step. For information on the job or job step termination status, see the description of the following fields in [z/OS MVS System Management Facilities \(SMF\)](#):

- Record Type 4 — field SMF4SCC
- Record Type 5 — field SMF5JCC
- Record Type 30 — field SMF30SCC

Note: X'0D' abends may result in a value of 0000.

- Record Type 34 — field TIVSTAT

Word 10

Address of an area containing a 4-byte record descriptor word (RDW). One of the following records immediately follows the RDW:

- The job step termination record (type 4 or type 34)
- The job termination record (type 5 or type 35)
- The common address space work record (type 30)
- The TSO/E command accounting record (type 32)

Word 11

Address of a 4-byte area containing the job processor time, which includes time under TCBs, enclave time, preemptable class SRB time, and client SRB time, in hundredths of a secondary (in binary).

Word 12

Address of a 4-byte area containing the step processor time, which includes time under TCBs, enclave time, preemptable class SRB time, and client SRB time, in hundredths of a second (in binary). At job termination, the field is zero.

Word 13

Address of a 4-character area that contains the name of the subsystem for the job being processed. Examples:

- ASCH, JES2, or JES3 - indicates the name of the subsystem that selected the job
- OMVS - indicates a forked or spawned address space
- STC - indicates a started task
- TSO - indicates a time sharing option task
- The jobname - used if it is four or fewer characters and none of the above apply

Word 14

Address of a 12-byte area that describes TIOT usage for this address space.

The first word of this area contains the length of this structure. The second word of this area contains the size of the TIOT that is usable for TIOT entries in bytes. This does not include the space reserved by the system for the TIOT Prefix, Header, and Trailer. The third word of this area contains the high water mark in bytes of the space used for TIOT entries for the current job.

Word 14 may contain zero (or only have the end of list indicator bit set with zeros in the rest of the word) if there is no TIOT usage information. The exit should check for a zero address before referencing the new area. There will be no TIOT usage information at job end, so the address will always be zero. At step end, TIOT usage information may not be available for some steps in specific job restart scenarios so the address can be zero.

Note: The high-order bit is set in the address of the last parameter to indicate the end of the parameter list.




Figure 7. IEFACTRT Input Parameter Structure

Common Exit Parameter Area

The common exit parameter area is a 56-byte area that contains information an SMF installation exit routine might need. It is a copy of the first 56 bytes of the job management record (JMR), of which the first 36 bytes are usable by the exit. In addition, byte 56 is a version indicator, which indicates whether additional information is available. When byte 56 is '01'x, an additional area is provided at offset 76, mapped by the JMRE DSECT within the JMR and contains an 8 character jobclass and a 64-byte job correlator, if provided by the primary JES subsystem.

The address of the common exit parameter area is passed to all SMF installation exits except IEFU29, IEFU83, IEFU84, and IEFU85. The common exit parameter area is mapped by macro IEFJMR, as part of the JMR, except for the indicator of the SMF option selected by the user field. This field is mapped by the SMCAOPT field in the SMCA data area. See Table 3 on page 141 for a description of the area, and “Accounting Information” on page 142 for a description of the accounting information. See z/OS

MVS Data Areas in the z/OS Internet library (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the complete mapping of the JMR and the complete mapping of the SMCA.

Table 3. Common Exit Parameter Area			
Displacement from Pointer	Field Size	Data Format	Description
0	8	EBCDIC	Job name
8	4	binary	Time, in hundredths of a second, when the reader recognized the JOB statement for this job
12	4	packed	Date when the reader recognized the JOB statement for the job, in the form OCYYDDDF where F is the sign and C is X '1' if the year is greater than 1999
16	4	EBCDIC	System identification (taken from SID parameter)
20	8	EBCDIC	User identification. SMF places this data in all subsequent records for this job. This field is initialized to EBCDIC blanks when each job is read. Note: This field is not related to the USER parameter on the JOB statement.
28	1	binary	Number of the step being processed
29	1	binary	Indicator of the SMF options selected by the user. (The following bit settings are mapped by the SMCAOPT field in the SMCA data area. See <i>z/OS MVS Data Areas</i> in the z/OS Internet library (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for a mapping of the SMCA data area.) Bit Meaning When Set 0 Reserved 1 Reserved 2 Reserved 3 Data set accounting. ¹ 4 Volume accounting. Record type 19 selected 5 Usage data collection services 6 Type 17 records will be written for temporary data sets (REC(ALL)) 7 If 0, background job. If 1, foreground job. Note: TSO sessions, APPC/MVS transactions, and OMVS (z/OS UNIX System Services) forked and spawned jobs are indicated as foreground jobs.

Table 3. Common Exit Parameter Area (continued)			
Displacement from Pointer	Field Size	Data Format	Description
30	1	binary	Restart indicator Bit Meaning When Set 0 Automatic step restart 1 Automatic checkpoint/restart 2 Continue restart 3 Reserved 4 Warm start 5-7 Reserved
31	1	EBCDIC	Job class
32	4	binary	The user-communication field. This field is intended for communication among user-written exit routines within a unique job. The field is initialized to zeroes when a job begins execution. For APPC/MVS transactions, this field remains zeros.
36	19	binary	Information not usable to the exit
55	1	binary	Version of JMR
56	20	binary	Information not usable to the exit
76	8	EBCDIC	Job class
84	64	EBCDIC	Job correlator, if provided by primary Job subsystem
Note: ¹ This bit is set on when any of the following record types is selected: 14, 15, 17, 18, 62, 63, 64, 67, or 68.			

Accounting Information

Accounting Information: These SMF installation exits receive accounting information for the job or job step:

- IEFACRT
- IEFUAV
- IEFUJI
- IEFUSI

The accounting information is presented to IEFACRT differently than to IEFUAV, IEFUJI, and IEFUSI. IEFACRT receives both the number of accounting fields and a pointer to the accounting fields in the input parameter list. See the parameter descriptions in “Entry Specifications” on page 137 for more details. For the other exits, the input parameter list contains a pointer to all the accounting information as described in Table 4 on page 142.

Table 4. Format of Accounting Information			
Offset	Length	Format	Description
0	1-Byte	Binary	Number of accounting fields.

Table 4. Format of Accounting Information (continued)

Offset	Length	Format	Description
1	Variable	EBCDIC	Accounting fields. Each accounting field contains the length of the field (one byte, binary) followed by accounting information (variable length, EBCDIC). A zero in the length field indicates an omitted field.

Figure 8 on page 143 provides examples of accounting information. Note that these fields are contiguous and are only spaced in Figure 8 on page 143 for clarity. These examples show different forms of accounting information you can specify in JCL, and the resulting representation (hexadecimal) that will be passed to the SMF exits listed earlier.

In the examples in Figure 8 on page 143:

- 'MYJOB' represents the job name.
- 'PROGNAM' represents the programmer name.
- '#FIELDS' represents the number of accounting fields.
- 'LEN1', 'LEN2', and 'LEN3' represent the length of the respective accounting field.
- 'DATA1', 'DATA2', and 'DATA3' represent data in the respective accounting field.

JCLAccounting Information.....						
Accounting Fields.....						
	#FIELDS	LEN1	DATA1	LEN2	DATA2	LEN3	DATA3
//MYJOB JOB ,PROGNAM	-> 01	00					
//MYJOB JOB 9,PROGNAM	-> 01	01	F9				
//MYJOB JOB (9,8),PROGNAM	-> 02	01	F9	01	F8		
//MYJOB JOB (9,8,77),PROGNAM	-> 03	01	F9	01	F8	02	F7F7
//MYJOB JOB '9',PROGNAM	-> 01	01	F9				
//MYJOB JOB '9,8',PROGNAM	-> 01	03	F96BE8				
//MYJOB JOB ('9','8'),PROGNAM	-> 02	01	F9	01	F8		
//MYJOB JOB ('9,8'),PROGNAM	-> 01	03	F96BF8				
//MYJOB JOB (9,8),PROGNAM	-> 03	01	F9	00		01	F8
//MYJOB JOB (9,'8'),PROGNAM	-> 03	01	F9	00		01	F8
//MYJOB JOB ((9)),PROGNAM	-> 01	01	F9				

Figure 8. Examples of Accounting Information

Return Specifications

A return code from IEFACTRT (in register 15) indicates whether the job is to continue or terminate. Another return code (in register 1) indicates whether or not SMF is to write the termination records to the SMF data set.

If you associate multiple exit routines with IEFACTRT, you can use any of these criteria methods to specify how the system is to handle the return information:

- The ATTRIB KEEPRC function of the SETPROG EXIT command,
- The ATTRIB KEEPRC parameter of the EXIT statement of PROGxx, or
- The RCFROM/RCCOMPARE parameters of the CSVDYNEX services.

The criterion is based on the contents of register 15. If multiple exit routines match the defined criterion, the system returns information from the exit routine called first.

The defined criterion is EXIT ATTRIB KEEPRC(GE,4).

If Exit A returns with R1 = 4 and R15 = 0,
and Exit B returns with R1 = 0 and R15 = 8,
and Exit C returns with R1 = 0 and R15 = 4,
and Exit D returns with R1 = 4 and R15 = 4,

the final results are R1 = 0 and R15 = 8.

The system derives the return information from the first exit called that matches the defined criteria. Here, R15 is greater or equal to 4, which is Exit B.

The job continues (because R15 is not 4) and the system writes the termination records to the SMF data set (because R1 for Exit B is not 4).

Figure 9. Example

If you do not specify a criteria method, the system returns the information from the first exit routine that returns a value of four in register 15, and cancels the remaining job steps. If that exit routine also returns a value of four in register 1, the system does not write the termination records to the SMF data set. For any other value in register 1 the system does write the termination records.

There are no defined criteria.

If Exit A returns with R1 = 4 and R15 = 0,
and Exit B returns with R1 = 0 and R15 = 8,
and Exit C returns with R1 = 0 and R15 = 4,
and Exit D returns with R1 = 4 and R15 = 4,

the final results are R1 = 0 and R15 = 4.

The system derives the return information from the first exit called that returns a value of 4 in R15, which is Exit C.

The job terminates (because R15 is 4) and the system writes the termination records to the SMF data set (because R1 for Exit C is not 4).

Figure 10. Example

If no exit routine returns a value of four in register 15, the system returns the information from the exit routine that is called first, and the job continues. Again, if that exit routine returns a value of four in register 1, the system does not write the termination records to the SMF data set, while for any other value in register 1 from that exit routine, the system does write the termination records to the SMF data set.

There are no defined criteria.

If Exit A returns with R1 = 4 and R15 = 0,
and Exit B returns with R1 = 0 and R15 = 8,
and Exit C returns with R1 = 0 and R15 = 0,

the final results are R1 = 4 and R15 = 0.

Because no exit set R15 to 4, the system derives the return information from the first exit called, which is Exit A.

The job continues (because R15 is not 4) and the system does not write the termination records to the SMF data set (because R1 for Exit A is 4).

Figure 11. Example

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0

Restored to contents at entry

1

One of the following return codes:

Return Code
Explanation

Value of 4

SMF is not to write the termination record to the SMF data set.

Other than 4

SMF is to write the termination record to the SMF data set.

2-14

Restored to contents at entry

15

One of the following return codes:

Return Code
Explanation

Value of 4

The remaining job steps are to be cancelled.

Other than 4

Job processing is to continue.

Note: The system may fail a step or job even if the return code is zero. This could happen, for example, as a result of specifying CATLG_ERR FAILJOB(YES) and incurring that type of post execution error. (A return code is generated by the application program and is never changed by the operating system.) A user can deduce that a step failed due to a "post execution error" if bit SMF30SYE in the two-byte SMF30STI field in the SMF30 subtype 4 record is on.

Coded Example of the Exit Routine

Sample IEFACTRT exit routines are provided in SYS1.SAMPLIB in members SMFEXITS and IEEEACTRT. The sample in SMFEXITS changes the SMF job termination (types 5 and 35) and job step termination (types 4 and 34) records to user records, and attempts to write them to an SMF data set. If the data set is full, the routine writes a message to the console indicating that SMF records are being lost. At job termination, the routine writes a record containing the job name, programmer's name, and account number to the JOBLOG data set.

The IEEEACTRT exit routine puts a summary of the step on each JES2 job log using WTO with ROUTCODE=14. The summary includes both step and job information.

Chapter 26. IEFDB401 — Dynamic Allocation Input Validation Routine Exit

Topics for This Exit Appear as Follows:

- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 147](#)
- [“Exit Routine Environment” on page 148](#)
- [“Exit Recovery” on page 148](#)
- [“Exit Routine Processing” on page 148](#)
- [“Programming Considerations” on page 148](#)
- [“Entry Specifications” on page 148](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 150](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 151](#)

The IEFDB401 installation exit from the allocation control routine allows an exit routine to either validate or alter any dynamic allocation request. Control passes to IEFDB401 for all system and user dynamic allocation requests. See *z/OS MVS Programming: Authorized Assembler Services Guide* for more information about dynamic allocation.

The user validation routine tests and can modify the dynamic allocation request, and it indicates through a return code whether or not processing of the request is to continue. You can use IEFDB401 to:

- Control the amount of direct access space requested.
- Check for authorization to use specified units.
- Check for authorization to use certain data sets.
- Check for authorization to hold certain resources for reuse.

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFDB401 installation exit to the dynamic exits facility. You can refer to the exit by the name IEFDB401. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

If you do not associate any exit routines with exit IEFDB401 in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFDB401).

If you associate exit routines with IEFDB401 in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Exit Routine Environment

IEFDB401 receives control in the following environment:

- In supervisor state and under the scheduler's PSW key (key 1).
- In AMODE 31 and RMODE ANY.

Exit Recovery

An ESTAE routine that is established in the calling module provides recovery from errors encountered in IEFDB401.

Whether or not the exit routine continues to be invoked depends on theabend processing of the dynamic exits facility.

Exit Routine Processing

The dynamic allocation facility passes control to IEFDB401 before doing any processing on behalf of a dynamic allocation request. It is entered for all requests, foreground and background. IEFDB401 can test and modify the dynamic allocation input, and indicate with a return code whether processing is to continue or if the request is to be terminated. The exit receives control after System Allocation has completed validation of the passed parameters.

The IBM-supplied version of IEFDB401 that your routine can replace does no testing and allows all requests to continue processing.

Programming Considerations

- When IEFDB401 receives control, a parameter list is passed via register 1. Among the parameters are the dynamic allocation request block and a work area for the addition or modification of text units. This work area immediately follows the text unit pointer list and is usually in nonfetch-protected scheduler key storage (subpool 230). It is in fetch-protected scheduler key storage (subpool 229) only when the request has a password specification text unit. If text unit pointers are to be added to the pointer list, they must be added to the end of the list in the work area. The end-of-list indicator also must be adjusted. To delete a text unit pointer, zero the text unit pointer or the text unit key.
- Code the exit routine so that it is reentrant.

Entry Specifications

IEFDB401 receives control from dynamic allocation.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of the parameter list

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of IEFDB401

Parameter List Contents: Register 1 points to the following parameters:

Word 1

Address of a copy of the dynamic allocation input parameter list in scheduler-key storage (mapped by macro IEFZB4D0). See the chapter on dynamic allocation in *z/OS MVS Programming: Authorized Assembler Services Guide*. See S99PARMS in *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the structure of IEFZB4D0.

Word 2

Pointer to the address of a work area that the exit routine can use. This area is contiguous with the text unit pointer list so that you can use it to extend the list and provide additional text units.

Word 3

Address of a fullword that contains the length of the work area (500 bytes).

Word 4

Address of the 8-character job name.

Word 5

Address of the 20-character programmer name.

Word 6

Address of an area that contains accounting information from the JOB statement. The first byte of this area contains the number of accounting fields; the accounting fields follow this byte. Each entry for an accounting field contains the length of the field (one byte, hexadecimal), followed by the field itself. The entry for a null field contains a length of zero.

Word 7

Address of the 8-character step name.

Word 8

Address of the 8-character program name.

Word 9

Address of an area containing accounting information from the EXEC statement. The first byte of this area contains the number of accounting fields (zero for no fields); the accounting fields follow this byte. Each entry for an accounting field contains the length of the field (one byte, hexadecimal), followed by the field itself. The entry for a null field contains a length of zero.




Figure 12. IEFDB401 Input Parameter Structure

Return Specifications

A return code from IEFDB401 indicates whether processing of the dynamic allocation request should continue.

If you associate multiple exit routines with IEFDB401, you can specify how the return information is to be handled using the ATTRIB KEEPRC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register
Contents

0-14
Restored to contents at entry

15
One of the following return codes:

Return Code
Explanation

0
Dynamic allocation request processing continues.

nonzero
Dynamic allocation request processing is terminated.

Coded Example of the Exit Routine

This sample exit routine first checks for an allocation verb code. If one is present, the routine loops through the text unit pointers to find the end of the text unit list. A return code is set to cancel the request if the unit description key is set to '3380'.

```

      TITLE 'DYNAMIC ALLOCATION INSTALLATION EXIT EXAMPLE'
IEFDB401 AMODE 31
IEFDB401 RMODE ANY
*****
*
*   $MOD(IEFDB401)
*
*   DESCRIPTIVE NAME - DYNAMIC ALLOCATION
*                       INSTALLATION EXIT EXAMPLE
*
*   COPYRIGHT = 5665-291
*               THIS MODULE IS "RESTRICTED MATERIALS OF IBM"
*               (C) COPYRIGHT IBM CORP. 1987
*               LICENSED MATERIALS - PROPERTY OF IBM.
*               REFER TO COPYRIGHT INSTRUCTIONS
*               FORM NUMBER G120-2083
*
*   STATUS = HBB3310
*
*   FUNCTION - THE DYNAMIC ALLOCATION FACILITY OF THE CONTROL
*               PROGRAM EXITS TO THIS 'EXIT ROUTINE' BEFORE
*               DOING ANY PROCESSING ON BEHALF OF A DYNAMIC
*               ALLOCATION REQUEST. IT IS ENTERED FOR ALL
*               REQUESTS, FOREGROUND AND BACKGROUND. THIS
*               ROUTINE MAY TEST AND MODIFY THE DYNAMIC
*               ALLOCATION INPUT, AND INDICATE THROUGH A
*               RETURN CODE WHETHER PROCESSING IS TO CONTINUE
*               OR IF THE REQUEST IS TO BE TERMINATED.
*
*               THE ROUTINE MAY DELETE A TEXT UNIT BY ZEROING
*               THE TEXT UNIT POINTER OR TEXT UNIT KEY.
*               A WORK AREA IS PROVIDED TO FACILITATE THE
*               ADDITION OR MODIFICATION OF TEXT UNITS AND
*               IMMEDIATELY FOLLOWS THE TEXT UNIT POINTER
*               LIST. POINTERS TO ITS ADDRESS AND LENGTH
*               ARE PASSED AS PARAMETERS. THIS AREA IS IN
*
*
*               FETCH-PROTECTED SCHEDULER-KEY CORE. IF TEXT
*               UNIT POINTERS ARE TO BE ADDED TO THE POINTER
*               LIST, THEY MUST BE ADDED TO THE END OF THE
*               LIST, (IN THE WORK AREA DESCRIBED ABOVE) AND
*               THE END-OF-LIST INDICATOR MUST BE ADJUSTED.
*
*   DEPENDENCIES - THIS MODULE RECEIVES CONTROL IN SCHEDULER
*                   KEY FROM A PREVIOUS MODULE OF DYNAMIC
*                   ALLOCATION.
*
*   MODULE TYPE - PROCEDURE
*
*   PROCESSOR - ASSEMBLER H
*
*   ATTRIBUTES - REFRESHABLE, SCHEDULER KEY, EXTENDED PLPA,
*                 SUPERVISOR STATE, AMODE(31), RMODE(ANY)
*
*   ENTRY POINT - IEFDB401
*
*   LINKAGE - STANDARD ENTRY AND EXIT LINKAGE
*
*   INPUT - REGISTERS - REG0    - IRRELEVANT
*                       REG1    - PARAMETER LIST ADDRESS
*                       REG2-12 - IRRELEVANT
*                       REG13   - SAVE AREA ADDRESS
*                       REG14   - RETURN ADDRESS
*                       REG15   - ENTRY ADDRESS
*
*   - DATA - UPON ENTRY REG1 POINTS TO A LIST OF
*               ADDRESSES FOR THE FOLLOWING ITEMS:
*
*               1. THE DYNAMIC ALLOCATION REQUEST BLOCK
*                   IN SCHEDULER-KEY, FETCH-PROTECTED
*                   CORE.

```

```

*          2.  A POINTER TO THE WORK AREA THAT          *
*          FOLLOWS THE TEXT UNIT POINTER LIST.          *
*          3.  LENGTH OF THE WORK AREA                  *
*          4.  8-CHARACTER JOB NAME                     *
*          5.  20-BYTE PROGRAMMER NAME                   *
*          6.  JOB ACCOUNTING INFORMATION - IN THE      *
*          STANDARD FORMAT PASSED TO SMF EXITS.          *
*          7.  8-CHARACTER STEP NAME                    *
*          8.  8-CHARACTER PROGRAM NAME                  *
*          9.  STEP ACCOUNTING INFORMATION - IN THE     *
*          STANDARD FORMAT PASSED TO SMF EXITS.          *
*
*          EXITS - REGISTERS - REG0-13 - RESTORED        *
*                      REG14  - RETURN ADDRESS           *
*                      REG15  - RETURN CODE              *
*
*          - RETURN CODE - 0      - CONTINUE SVC 99 PROCESSING *
*                      non-0 - TERMINATE SVC 99 PROCESSING *
*
*          - DATA - POSSIBLE CHANGES IN THE DYNAMIC ALLOCATION *
*                      REQUEST BLOCK, THE TEXT POINTERS, OR THE *
*                      TEXT UNITS.                          *
*
*****

```

```

          TITLE 'DYNAMIC ALLOCATION (SVC 99) PARM LIST'
          IEFZB4D0
          TITLE 'DYNAMIC ALLOCATION KEY TABLE'
          IEFZB4D2
          TITLE 'DYNAMIC ALLOCATION INSTALLATION EXIT EXAMPLE'
IEFDB401 CSECT
          SPACE 1
*****
*          STANDARD REGISTER EQUATES                      *
*****
          SPACE 1
R0      EQU 0
R1      EQU 1
R2      EQU 2
R3      EQU 3
R4      EQU 4
R5      EQU 5
R6      EQU 6
R7      EQU 7
R8      EQU 8
R9      EQU 9
R10     EQU 10
R11     EQU 11
R12     EQU 12
R13     EQU 13
R14     EQU 14
R15     EQU 15
          SPACE 1
*****
*          STANDARD INPUT LINKAGE                          *
*****
          SPACE 1
          STM  R14,R12,12(R13)    SAVE CALLER'S REGISTERS
          BALR R12,R0             ESTABLISH ADDRESSABILITY
          USING *,R12            TO CSECT
          EJECT

*****
*  INITIALIZE RETURN CODE, GET POINTER TO THE PARAMETER LIST *
*  AND ESTABLISH ADDRESSABILITY TO THE SVC 99 REQUEST BLOCK. *
*****
          SPACE 1
          XR   R15,R15            INITIALIZE RETURN CODE
          L    R9,0(R1)          ESTABLISH ADDRESSABILITY TO
          USING S99RB,R9         THE SVC 99 REQUEST BLOCK
          SPACE 1
*****
*  CHECK FOR AN 'ALLOCATION' VERB CODE, (X'01'), AND IF NOT *
*  BRANCH TO CONTINUE THE REQUEST UNCHANGED. ELSE ESTABLISH *
*  ADDRESSABILITY TO THE TEXT UNIT POINTER LIST AND CHECK *
*  FOR A VALID TEXT UNIT POINTER,non-0,AND THEN CHECK FOR THE *
*  END OF THE TEXT UNIT LIST. IF NEITHER OF THE CHECKS PASS, *
*  THEN ADJUST THE TEXT UNIT POINTER AND LOOP UNTIL ONE DOES. *
*****

```

```

SPACE 1
CLI S99VERB,S99VRBAL IS THIS AN ALLOCATION VERB CODE?
BNE DB401D BIN TO CONTINUE REQUEST UNCHANGED
L R8,S99TXTPP ESTABLISH ADDRESSABILITY TO
USING S99TUPL,R8 THE TEXT UNIT POINTER LIST
DB401A DS 0H
CLC S99TUPTR,BLANKPTR IS THIS A BLANK/-LAST TEXT UNIT PTR?

```

```

BE DB401B BIY TO CHECK THE NEXT TEXT UNIT PTR
CLC S99TUPTR,LSTBLKPT IS THIS A BLANK/LAST TEXT UNIT PTR?
BE DB401D BIY TO EXIT THE EXIT ROUTINE
B DB401C GO CHECK THE TEXT UNIT CONTENTS
DB401B DS 0H
LA R8,4(,R8) POINT TO NEXT TEXT UNIT POINTER
B DB401A GO CHECK THE NEXT TEXT UNIT POINTER
SPACE 1

```

```

*****
* ESTABLISH ADDRESSABILITY TO THE SVC 99 TEXT UNIT AND CHECK *
* FOR A 'UNIT DESCRIPTION SPECIFICATION' KEY, (X'0015'), AND *
* IF MATCHED CHECK FOR A '3380' PARAMETER. IT THIS MATCHES, *
* SET THE RETURN CODE TO CANCEL THE REQUEST, (X'04'), AND *
* RETURN TO CALLER. IF EITHER OF THESE CHECKS FAIL THEN *
* BRANCH BACK TO CONTINUE THE LOOP OF TEXT UNIT POINTERS. *
*****

```

```

SPACE 1
DB401BB DS 0H
TM S99TUPTR,LSTVALPT IS THIS A VALID LAST TEXT UNIT PTR?
BO DB401D BIY TO EXIT THE EXIT ROUTINE
B DB401B GO GET NEXT TEXT UNIT POINTER
DB401C DS 0H
L R7,S99TUPTR ESTABLISH ADDRESSABILITY TO
USING S99TUNIT,R7 THE SVC 99 TEXT UNIT
CLC S99TUKEY,UNDESKEY IS THIS A UNIT DESCRIPTION KEY?
BNE DB401BB BIN TO CHECK IF LAST TEXT UNIT PTR
CLC PARM3380,S99TUPAR IS THIS A 3380 PARAMETER?
BNE DB401BB BIN TO CHECK IF LAST TEXT UNIT PTR
LA R15,4(,R15) SET RETURN CODE TO CANCEL REQUEST
DB401D DS 0H
EJECT

```

```

*****
* STANDARD EXIT LINKAGE *
*****

```

```

SPACE 1
L R14,12(R13) RESTORE CALLER'S REGISTERS
LM R0,R12,20(R13) EXCEPT REGISTER 15
BR R14 RETURN TO CALLER
DROP R7,R8,R9,R12
SPACE 1

```

```

*****
* DECLARATIONS AND CONSTANTS *
*****

```

```

SPACE 1
PARM3380 DC C'3380' 3380 PARAMETER
BLANKPTR DC F'0' CHECKS FOR A BLANK TEXT UNIT PTR
LSTBLKPT DC X'80000000'
UNDESKEY DC H'21'
LSTVALPT EQU X'80'
END

```


Chapter 27. IEFDOIXT — Edit / Check A Caller's Dynamic Output Text Units Exit

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routine” on page 155](#)
- [“Exit Routine Environment” on page 155](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 156](#)
- [“Programming Considerations” on page 157](#)
- [“Entry Specifications” on page 158](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 159](#)
 - Registers at Exit

Dynamic output is a system service that users can invoke by issuing the OUTADD or OUTDEL macro. Dynamic output allows an installation to specify the output characteristics of a sysout data set dynamically as an alternative to specifying these characteristics on the OUTPUT JCL statement. For more detailed information about using dynamic output, see [z/OS MVS Programming: Authorized Assembler Services Guide](#).

IEFDOIXT is the dynamic output installation exit. You can use IEFDOIXT to:

- Edit the text units. For example, you can use this exit to limit requests for COPIES to be less than or equal to 50.
- Detect requests for unsupported devices or features.
- Correct requests for unsupported devices or features by issuing installation-defined reason codes. These reason codes help the invoker of dynamic output diagnose problems that the exit detected.

Installing the Exit Routine

The IBM-supplied version of IEFDOIXT resides in SYS1.LINKLIB. You can replace IEFDOIXT in SYS1.LINKLIB with your own version or place your version of IEFDOIXT in an authorized library somewhere else in the search order prior to SYS1.LINKLIB. For more details on the search order for load modules, see [z/OS MVS Programming: Assembler Services Guide](#).

For general instructions on installing an exit routine, see [“Link editing an Installation Exit Routine into a Library” on page 3](#).

Exit Routine Environment

IEFDOIXT receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 1 and must return control in the same state and key.
- In AMODE 31 and RMODE ANY.
- In the caller's address space.
- With no locks or resources held (other than storage obtained via GETMAIN and an ESTAE) when it calls IEFDOIXT.

- Under a type 3 SVC. See *z/OS MVS Programming: Authorized Assembler Services Guide* for a description of the restrictions in this environment.

Exit Recovery: IEFDOIXT runs under dynamic output's recovery environment. If recovery for dynamic output gets control during exit routine processing, dynamic output returns to its invoker and sets return and reason codes to indicate that the exit abnormally terminated.

Exit Routine Processing

Each time that you invoke dynamic output via the OUTADD or OUTDEL macro, it links to the IEFDOIXT installation exit. When IEFDOIXT completes its processing, it returns control to dynamic output. If no errors are detected, dynamic output then creates or deletes the output descriptor.

Dynamic output passes the exit a copy of the input from the caller of dynamic output. Before calling the exit, dynamic output performs the following verification of the caller's input data:

- Dynamic output references the input data in the key of the caller that issued the OUTADD or OUTDEL macro. If a protection exception (OC4 ABEND) occurs when the data is referenced, dynamic output passes control back to the caller, and the installation exit does not get control.
- Dynamic output verifies the text units. If the text units are not valid, dynamic output reports the problem as being that the parameter list is not valid. In general, dynamic output does not differentiate between text unit errors that the caller causes and those that the exit causes. In addition, because the exit works on a copy of the caller's parameter list, the caller can not recognize the changes that the exit has made to the text units. For this reason, the exit must ensure that text units are updated correctly.

If dynamic output determines that there is an error in the caller's input data, the installation exit does not receive control. If dynamic output verifies the caller's input data, the installation exit receives a copy of the data. This input data includes the fixed parameter list (DOCNP), the text units and a text unit pointer list with pointers to the copied text units. The exit also receives 500 bytes of storage so that it can update the caller's text unit pointers and text units.

In the exit routine, you can read or make valid alterations to the data passed to the exit. You can omit text units by zeroing their text unit pointers. You can add text units, as well as the text unit pointers for the new text units, in the work area provided. Concatenate the new text unit pointers to the end of the passed text unit pointer list, which is contiguous with the work area. If you add new text unit pointers, reset the high-order bit that indicates the last text unit pointer.

The exit should set the values of registers 0, 1 and 15 on return to dynamic output. The value of register 15 indicates whether dynamic output is to cancel or proceed with the request. Registers 1 and 0 are used for the exit to optionally pass diagnostic information to the dynamic output caller. For specification of the registers on return from the exit, see *“Return Specifications”* on page 159, and *z/OS MVS Programming: Assembler Services Guide*.

Upon return from the exit, dynamic output performs the following verification of the registers returned by the exit and the data areas passed to the exit:

- Dynamic output verifies the contents of registers 0, 1, and 15. If the register contents are not valid, or if the return code in register 15 is an 8, dynamic output denies the user's request and returns a reason code that identifies the problem.
- Dynamic output verifies the fixed parameter list (DOCNP) and reports any problems with the parameter list by setting the appropriate return and reason codes. Because dynamic output also verifies DOCNP before linking to the exit routine, unique error return and reason codes are issued to help differentiate between errors in DOCNP which the caller causes, and errors that the exit routine causes.
- Dynamic output verifies the text units. If the text units are not valid, dynamic output reports the problem as being that the parameter list is not valid. Dynamic output does not differentiate between text unit errors that the caller causes and those that the exit causes. In addition, because the exit works on a copy of the caller's parameter list, the caller can not recognize the changes that the exit has made to the text units. For this reason, the exit should make changes to the text units very carefully.

When the exit alters the text units to contain negative values in the number of parameters field or in the length of parameter field, the results are unpredictable. Dynamic output only checks these fields before

calling the exit routine. It is the exit's responsibility to make sure that it does not pass negative values in these fields. It also is essential that the exit does not cause an OUTADD request to contain no text units.

If no errors are detected, the output descriptor is created or deleted.

Programming Considerations

Code the IEFDOIXT routine to be reentrant.

The copy of the caller's input data, the text unit pointers and the 500-byte work area that are passed to the exit are in key 1 storage, subpool 229. This storage is pageable and fetch protected.

The IBM-supplied exit routine only zeroes the contents of registers 0, 1, and 15. It restores the other registers and returns control to dynamic output.

The exit is an authorized exit, so you must follow standard security and integrity procedures.

Dynamic output links to IEFDOIXT. The LINK macro does not restore the register contents, so you must be sure that you restore the contents of registers 2-13 before returning to dynamic output.

Tracing IEFDOIXT's Input and Output

You can use the generalized trace facility (GTF) to trace IEFDOIXT's input and output, when the GTF identifier for dynamic output is active. The GTF identifier for dynamic output is user event F62.

Each GTF trace record is prefixed with a 24-byte field that uniquely identifies the creator of the trace record and the trace record's sequence number. The format of the 24-byte field is as follows:

(Hex)

Contents

X'00'

'TCB ' (EBCDIC representation)

X'04'

TCB address of the task that invoked the SVC

X'08'

'SVRB' (EBCDIC representation)

X'0C'

SVRB address for this invocation of the SVC

X'10'

'SEQ#' (EBCDIC representation)

X'14'

Sequence number of trace record. That is, **1** indicates the **first** trace record of the input to IEFDOIXT, **2** indicates the **second** trace record, and so on.

Each GTF trace record can have a maximum length of 256 bytes. The following is a description of the GTF trace records for IEFDOIXT:

- The first trace record contains a character string header (starting at offset X'18') that indicates whether the data being traced is IEFDOIXT's input or output.
- The second trace record contains the following information:

(Hex)

Contents

X'18'

'DOCNP->'

X'20'

Pointer to copy of DOCNP

X'24'

'WORKAREA START->'

X'38'

Pointer to the start of IEFDOIXT's workarea

X'3C'

'WORKAREA END->'

X'4C'

Pointer to the end of IEFDOIXT's workarea

- The third record through the second-to-last record contains the data area that was passed to IEFDOIXT. This includes the copy of the SVC caller's parameters and the installation workarea. More than one trace record is issued if the data area exceeds the maximum length of one trace record (256 bytes).
- The last record contains a character string that indicates the end of the trace data.

See [z/OS MVS Diagnosis: Tools and Service Aids](#) for information on using GTF.

Entry Specifications

Dynamic output passes three address parameters to the installation exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of three consecutive fullwords. Each fullword is a pointer; the first fullword points to the parameter list (DOCNP), the second fullword points to the beginning (first byte) of the 500-byte work area that the exit can use, and the third fullword points to the end (last byte) of the work area. [Figure 13 on page 158](#) shows the parameter structure.

2-12

Not applicable

13

Not applicable

14

Return address

15

Not applicable




Figure 13. IEFDOIXT Input Parameter Structure

Parameter Descriptions: Register 1 contains the address of a pointer list that consists of three contiguous fullwords in storage. The first fullword points to the address of the fixed parameter list, the DOCNP, which is mapped by macro IEFDOCNP (data area DOCNP). For a mapping of the DOCNP data area, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

IEFDOIXT returns control to dynamic output and passes back a return code, a reason code and, optionally, a key in error.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0

The contents of register 0 depend on the return code that the exit routine places in register 15.

- If the return code is zero, register 0 must contain a zero.
- If the return code is 8, register 0 may contain a zero or an installation-defined reason code with a value between X'6000' and X'7FFF'.

1

The contents of register 1 depend on the return code that the exit places in register 15.

- If the return code is zero, set register 1 to zero.
- If the return code is 8, register 1 can contain either an erroneous text unit key in the two low-order bytes, or zero. The two high-order bytes must always contain zeroes.

2-13

Restored to contents at entry

14

Return address

15

Contains one of the following return codes:

Return Code Description

0

The request is to be processed.

8

The request is to be denied. The values in register 0 and 1 are set accordingly and returned to the dynamic output caller in those registers.

Chapter 28. IEFJFRQ — Subsystem Function Request Exit

Topics for This Exit Appear as Follows:

- [“Controlling the Exit Routine through the Dynamic Exits Facility” on page 162](#)
- [“Exit Routine Environment” on page 162](#)
- [“Exit Recovery” on page 162](#)
- [“Exit Routine Processing” on page 163](#)
- [“Programming Considerations” on page 163](#)
- [“Entry Specifications” on page 164](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 165](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 166](#)

You can use the IEFJFRQ exit to tailor the subsystem interface (SSI) processing of subsystem function requests. See [z/OS MVS Using the Subsystem Interface](#) for more information on subsystem function requests.

IEFJFRQ receives control at two different points in SSI function request processing:

- Prerequisite — before the SSI routes either a directed or broadcast subsystem function request to the target subsystem(s). For broadcast requests, IEFJFRQ is called once for each subsystem defined to the SSI.
- Postrequest — after the SSI has routed either a directed or broadcast subsystem function request to all appropriate subsystems.

At the prerequisite point, you can use IEFJFRQ to modify or suppress processing for any subsystem, or for any subsystem function request. (See [z/OS MVS Using the Subsystem Interface](#) for a list of subsystem function requests.) For example, you can:

- Suppress commands or WTOs.
- Prevent calls to a specific subsystem, for example, a subsystem that is failing repeatedly.
- Route directed requests to a different subsystem.
- Interrupt a broadcast request, that is, cause the SSI to discontinue routing the broadcast request to the subsystems that have not yet processed the request.
- Maintain records of subsystem invocation.
- Enforce installation policies for subsystem invocation.
- Modify the return code that the caller of the SSI receives.

At the postrequest point, you can use IEFJFRQ to:

- Update records to reflect the results of function requests acted on by multiple exit routines during the prerequisite processing.
- Modify the return code that the caller of the SSI receives.

Applications using the IEFJFRQ installation exit can determine whether it is available by testing the JESFRQEX flag in the JESFLG field of the JESCT data area.

Controlling the Exit Routine through the Dynamic Exits Facility

IBM has defined the IEFJFRQ exit to the dynamic exits facility. You can refer to the exit by the name IEFJFRQ. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

You may install more than one exit routine at the IEFJFRQ exit point. Each exit routine can examine and modify the control blocks that represent the subsystem function request. The control blocks passed to the target subsystem reflect the modifications made by all installed exit routines.

You can control the order that exit routines receive control by using the FIRST or LAST parameter on one of the following services:

- The CSVDYNEX REQUEST=ADD macro
- The SETPROG EXIT,ADD command
- The EXIT ADD statement of the PROGxx parmlib member.

You can use the ADDABENDNUM parameter on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. See [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#) for more information on the CSVDYNEX macro, and [z/OS MVS System Commands](#) for more information on the SETPROG EXIT operator command. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine provides recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine. Note that IEFJFRQ cannot take advantage of consecutive abend processing, since IEFJFRQ supports fastpath calls in any PSW key,

You can use the DELETE parameter on the CSVDYNEX macro, or the SETPROG EXIT,DELETE command to delete exit routines from IEFJFRQ. If the delete request does not specify FORCE=YES, the system will not free the exit routine's storage, since the IEFJFRQ exit supports callers in any PSW key. See [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#) for more information on the FORCE parameter on the CSVDYNEX macro, and [z/OS MVS System Commands](#) for more information on the FORCE parameter on the SETPROG command.

Exit Routine Environment

IEFJFRQ receives control in the following environment:

- Enabled for interrupts
- In the state and key of the caller of the SSI (issuer of the IEFSSREQ service that produced the subsystem function request that drives this exit)
- In AMODE 31
- With any locks held by the caller of the SSI
- In primary ASC mode
- In the dispatch mode (task or SRB) of the caller of the SSI
- In the cross-memory mode of the caller of the SSI.

Exit Recovery

You should consider the resources accessed by your exit routine and the impact on system performance, when evaluating whether your exit routine should provide its own recovery. IBM recommends that you establish your own recovery only if you access system resources, and only for subsystem function requests that concern your exit routine.

A system recovery routine will get control if:

- The exit routine abnormally ends and the exit routine does not provide its own recovery
- The error percolates beyond the exit routine's recovery routine

The system does not route the function request to any other exit routines associated with the exit, or to the target subsystem. If the error occurs while the SSI is processing a broadcast request, the SSI continues routing the request to any remaining subsystems. The abend processing of the dynamic exits facility determines whether the exit routine continues to be invoked.

Exit Routine Processing

When IEFJFRQ receives control, the SSI has:

- Validated the SSOB and SSIB control blocks to ensure that these control blocks are addressable and have the correct eyecatchers and lengths. Note that an SSOB may have more than one acceptable length.
- Set the SSOBSSIB field in the SSOB control block to point to the life-of-job SSIB, if the original subsystem function request did not specify an SSIB control block. See [z/OS MVS Using the Subsystem Interface](#) for more information on the life-of-job SSIB.

IEFJFRQ may be called multiple times for each subsystem function request. The process for calling IEFJFRQ differs depending on whether the request is directed or broadcast as follows:

- For directed requests, IEFJFRQ is called:
 - Once before the target subsystem receives control
 - Once after the target subsystem receives control

Note that the postrequest instance is called even if the prerequest instance caused the SSI to bypass the call to the target subsystem.

- For broadcast requests, IEFJFRQ is called:
 - Once when the MSTR subsystem is invoked to initiate the broadcast processing
 - Once for each target subsystem
 - Once after broadcast processing is complete and the request has been routed to all appropriate subsystems.

Note that the postrequest instance is called even if the prerequest instance caused the SSI to bypass all broadcast processing.

Prerequest processing:

IEFJFRQ receives control at the prerequest processing exit point before the SSI routes either a directed or broadcast subsystem function request to the target subsystem(s). Note that IEFJFRQ is invoked once for each subsystem receiving the request.

Postrequest processing:

IEFJFRQ receives control at the postrequest processing point after the SSI has routed either a directed or broadcast subsystem function request to all appropriate subsystems. Its primary purpose is to inform exit routines of the actions the SSI has taken with respect to the current subsystem function request.

Programming Considerations

IEFJFRQ exit routines must be reentrant.

Exit routines receive a pointer to the control blocks that represent the subsystem function request, which include the SSOB, SSIB, SSOB extension, and any areas pointed to from these control blocks. Exit routines should be careful when modifying any of these control blocks.

IEFJFRQ exit routines should not take actions that result in a call to the SSI, such as issuing a system command or dynamic allocation request. Actions that result in a call to the SSI could result in infinitely recursive calls to the IEFJFRQ exit. For example, an exit routine cannot issue an SVC WTO when processing a WTO/WTOR function request (SSI function code 9).

The SSI provides a 12-byte correlation token, named `FRQP_CORRELATION_TOKEN`, in the `IEFJFRQP` parameter mapping to assist exit routines in correlating calls resulting from a single subsystem function request. The correlation token has the following characteristics:

- The token is not valid if the system clock is not operating
- The first 8 bytes of the token are unique over the life of an IPL on a single system
- The 8-byte single system token concatenated with the 4-byte system ID in the parameter mapping form a 12-byte token that is unique across a sysplex.

Performance Considerations:

SSI processing, specifically the routing of subsystem function requests, may impact performance; therefore, consider the following recommendations so that system performance is not degraded:

- Exit routines installed at the `IEFJFRQ` exit point should not perform operations that may degrade system performance, such as; issuing `WAIT` requests, issuing requests for large amounts of dynamic storage, or issuing I/O requests. To reduce the need for storage requests, the system provides an area that your exit routine can use for dynamic storage. The `FRQP_DYNSIZE` constant in the `IEFJFRQP` parameter mapping defines the size of the dynamic storage area. The exit routine must clear the dynamic storage area before using it, because all exit routines installed at the `IEFJFRQ` exit point use the same work area.
- Exit routines should quickly determine whether the current subsystem function request is of interest, and return to the system immediately if not. Time consuming operations, such as obtaining storage, should be deferred until after this check. You can delay the establishment of recovery to perform this check, as long as the check references only information identified by the input control blocks, that is, the `IEFJFRQP` parameter area, the `SSOB`, and the `SSIB`.

Entry Specifications

The `IEFJFRQP` macro maps the input to the `IEFJFRQ` exit, and contains the following information:

- The address of the `SSOB` control block representing the subsystem function request
- Flags that indicate:
 - Which instance (prerequisite or postrequest) of the exit is being called
 - Whether the subsystem function request is a broadcast request
 - Whether the `SSIB` is a copy of the life-of-job `SSIB` or was provided by the SSI's caller.
- The current value of the return code that is passed back to the caller of the SSI, if `IEFJFRQ` does not change this value.
- A token that you can use to correlate exit calls resulting from a single subsystem function request.

For directed requests, the current return code value is always zero for the prerequisite instance of the exit.

Every broadcast request begins as a subsystem function request directed to the `MSTR` subsystem. The SSI cannot determine if the request represents a broadcast request until the `MSTR` subsystem processes this request. Therefore, the broadcast indicator is not set when the SSI calls the prerequisite instance of `IEFJFRQ` for a request directed to the `MSTR` subsystem, even if the request will eventually be a broadcast request.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

0

Does not contain any information for use by the exit routine

1

Address of a list of pointers

2-12

Does not contain any information for use by the exit routine

13

Register save area

14

Return address

15

Entry point address of IEFJFRQ exit routine

Parameter List Contents: Register 1 points to the following list of addresses, which are mapped by the FRQP_PLIST_AREA field of the IEFJFRQP macro:

- The address of the IEFJFRQP parameter area
- The address of the working storage that the system provides for use by the exit routine.

Note: The high-order bit is set in the address of the last parameter to indicate the end of the parameter list.

Return Specifications

The exit routine must specify the following return codes:

- A return code passed in register 15 that controls the system's processing of the subsystem function request
- A return code in register 0 that is passed to the caller of the SSI.

For the prerequest instance of the IEFJFRQ exit, the return code passed in register 0 for the caller of the SSI is used only if the return code passed in register 15 indicates that the SSI should not pass the subsystem function request to the target subsystem.

For the postrequest instance of IEFJFRQ, the return code passed in register 0 is passed back to the caller of the SSI. You can preserve the return code that would be returned by the SSI by copying FRQP CURRENT SSI RETCODE in register 0. Register 0 must contain one of the return code values defined in the IEFSSOBH mapping macro.

If you associate multiple exit routines with IEFJFRQ, you can specify how the return information is handled by using the ATTRIB KEEPRC function on one of the following:

- The SETPROG EXIT command
- The EXIT statement of the PROGxx parmlib member
- The CSVDYNEX macro services.

If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

Note that the KEEPRC function specifies tests to be performed on the return code set in register 15 on exit from the IEFJFRQ exit routine. The results of the tests control the information that is returned to the SSI, that is, both the exit's return code in register 15 and the SSI caller's return code in register 0.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine with the largest return code value. If multiple exit routines return with the same value, the value in the exit routine that finished first will be returned.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0

Return code to be provided to the caller of the SSI

1

The exit routine does not have to place any information in this register, and does not have to restore its contents to what they were when the exit routine received control.

2-14

Restored to contents on entry

15

One of the following return codes:

Return Code	Explanation
-------------	-------------

0	Route the subsystem function request to the target subsystem
4	Do not route the subsystem function request to the target subsystem
8	Do not route the subsystem function request to the target subsystem, or for broadcast requests, do not route the subsystem function request to any remaining subsystem that has not yet processed the request.
24	Do not route the subsystem function request to the target subsystem, or for broadcast requests, do not route the subsystem function request to any remaining subsystem that has not yet processed the request. Do not call any remaining IEFJFRQ exit routines.

The IEFJFRQP macro provides mnemonic names for the return code values.

Coded Example of the Exit Routine

A sample IEFJFRQ exit routine is provided in SYS1.SAMPLIB (in member IEFJSXIT).

Chapter 29. IEFUAV – User Account Validation Exit

Topics for This Exit Appear as Follows:

- [“Defining the Exit in SMFPRMxx” on page 168](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 168](#)
- [“Exit Routine Environment” on page 168](#)
- [“Exit Recovery” on page 168](#)
- [“Exit Routine Processing” on page 169](#)
- [“Programming Considerations” on page 170](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 170](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 172](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 173](#)

You can use the IEFUAV installation exit routine to validate the accounting information of users of APPC/MVS transaction programs (TPs).

IEFUAV is invoked:

- When the IBM-supplied APPC/MVS transaction scheduler (ASCH) selects a TP for execution and
- At the points in TP processing where APPC/MVS could have tailored the accounting information for the TP user. For example, IEFUAV is invoked when APPC/MVS tailors the account number to which resources are charged for that instance of the TP.
- The Workload Manager (WLM) component of the base control program is used to create forked/spawned address spaces. In addition to APPC/MVS TPs, the IEFUAV exit now receives control for forked/spawned address spaces.

When the IEFUAV exit receives control for a forked/spawned address space, the TP flag value indicator is set to 1. The jobname in the ASCB is BPXAS, which is the name of the procedure used to start the MVS initiator associated with forked/spawned address spaces.

Based on whether the TP user's accounting information is valid, IEFUAV sets a return code to indicate that either:

- Processing should continue for the unit of work or
- The unit of work is to be cancelled.

IEFUAV also allows you to place a message into a user's APPC/MVS job log. With the message you can provide information to supplement the return code.

For APPC/MVS TPs, IEFUAV is the only exit that allows you to validate accounting information for specific users **at execution time**. Therefore, it is recommended that you use IEFUAV, instead of IEFUJV (or another exit, such as IEFUJI or IEFUSI), to validate the accounting information of APPC/MVS TPs. Even though IEFUJV is invoked (as part of C/I text processing) during the reading of a TP profile, the user of the TP is not known at that time.

Defining the Exit in SMFPRMxx

To allow the system to invoke IEFUAV, define the exit in the SMF parmlib member (SMFPRMxx). Specify IEFUAV on the EXITS option of the SUBSYS parameter for the ASCH subsystem. If your installation chooses not to define a SUBSYS parameter for ASCH, you can specify IEFUAV on the EXITS option of the SYS parameter.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFUAV installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFUAV or SYSyyy.IEFUAV. See the description of the SMFPRMxx parmlib member in [z/OS MVS Initialization and Tuning Reference](#) for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

To define IEFUAV to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for IEFUAV, you need only define this exit in SMFPRMxx.

The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFUAV in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFUAV).

If you associate exit routines with IEFUAV in PROGxx, the system does not use the default exit routine. If you need this exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Exit Routine Environment

IEFUAV receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 1.
- In AMODE 31 and runs RMODE ANY.
- In the address space of the unit of work being started
- With no locks or ENQs held.

Exit Recovery

IBM strongly recommends that you set up an ESTAEX recovery routine to handle errors that might occur during the execution of IEFUAV.

If you do not provide recovery for IEFUAV, or if the exit routine's error percolates beyond its recovery routine, a system recovery routine will get control.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

The system invokes the IEFUAV exit routine during the processing of an APPC/MVS TP at the points in which the accounting information might have been altered. At these points, an installation can validate the user's accounting information before processing the transaction further. For example, IEFUAV is invoked when a TP issues `Get_Transaction` because this service allows APPC to tailor the accounting information for the unit of work, such as the account number to which a resource is charged.

When IEFUAV Is Invoked: IEFUAV will get control only for APPC/MVS TPs whose profiles specify `TAILOR_ACCOUNT(YES)`. IEFUAV is invoked once for standard TPs and multiple times for multi-trans TPs, as follows:

- For both standard and multi-trans TPs, IEFUAV is invoked when the APPC/MVS transaction scheduler (ASCH) selects a TP for execution. In this case, IEFUAV receives the generic accounting information that is specified in the TP user's RACF profile.
- For multi-trans TPs only, IEFUAV is invoked when the TPs issue calls to the following services:
 - `Get_Transaction`, to obtain the next transaction. IEFUAV receives accounting information derived from the TP user's RACF profile.
 - `Return_Transaction`, to restore the generic "shell" environment that was established when the TP was initialized. IEFUAV receives generic accounting information from the TP user's RACF profile.

For information on creating a TP profile, see [z/OS MVS Planning: APPC/MVS Management](#).

The circumstances under which IEFUAV receives control might impose restrictions on exit routine processing; see macros and restrictions in [“Programming Considerations” on page 170](#) for more details.

Using IEFUAV to Validate Account Numbers

Code your IEFUAV routine to check the user's account number against a list of valid installation account numbers.

Using the Exit Function Code: IEFUAV determines why it was invoked by checking the exit function code in Word 3 of the parameter list (pointed to by Register 1). An installation would probably want IEFUAV to perform validation when Word 3 is set to a value of either 1 (generic account number) or 2 (possible account number alteration).

For exit function code 3, IEFUAV can simply return to the caller, as this code indicates the generic account number that IEFUAV already validated during TP initialization (exit function code 1).

See parameter descriptions in [“Entry Specifications” on page 170](#) for more information on the exit function codes.

Validating the User's Account Number: IEFUAV receives, as parameters, the accounting information specified on the JOB statement in the TP user's RACF profile. The accounting information appears in a formatted list, and follows the order in which the accounting parameters were specified on the JOB statement. [Table 4 on page 142](#) shows the format of the accounting information.

After locating the account number field, IEFUAV would typically do these checks:

- Is the account number present? A value of 0 in the first byte of the account number field indicates the account number was omitted.
- Does the account number have the correct length? A nonzero value in the first byte indicates the length of the account number.
- Is the account number valid? IEFUAV can determine this by comparing the account number to a list of valid account numbers.

At the end of its processing, IEFUAV sets a return code that indicates whether processing for this user should continue or be cancelled.

Placing a Message into a User's APPC/MVS Job Log: IEFUAV allows you to place a message into a user's APPC/MVS job log. Through the message, you can provide information to supplement the return code from IEFUAV. On entry, word 5 of the input parameter list points to a two-word area representing a message area. Place the length of the message in the first word. If the length exceeds zero, then the system issues the message that the second word points to regardless of the value returned in register 15. The maximum allowed length is 80.

The second word is the address of an 80-byte buffer; in that buffer, place the message to be issued to the APPC/MVS job log.

Programming Considerations

SMF provides a replaceable module for an unused exit.

If an installation includes an IEFUAV exit routine, the following programming standards must be observed:

- IEFUAV must follow standard linkage conventions.
- IEFUAV must be reentrant.
- IEFUAV cannot access ISAM data sets.

Macro Instructions and Restrictions are as follows.

- If you want to issue a WTOR macro from IEFUAV, also issue the WAIT macro with LONG=YES.
- You can issue any macros from IEFUAV, including the OPEN and DYNALLOC macros. The circumstances under which IEFUAV receives control, however, determine the results of OPEN and DYNALLOC processing:
 - When IEFUAV gets control because the APPC initiator started a standard or multi-trans TP, IEFUAV can open only those data sets specified in the APPC initiator's procedure. If IEFUAV needs access to other data sets, it may dynamically allocate them, which adds those data sets to the APPC initiator's environment. Those data sets will remain available to the APPC initiator unless IEFUAV unallocates them before completing its processing.
 - When IEFUAV gets control because a multi-trans TP issued either Get_Transaction or Return_Transaction, IEFUAV can open only those data sets that are specified in the TP's profile. If IEFUAV needs access to other data sets, it may dynamically allocate them, which adds those data sets to the TP's environment. Those data sets will remain available to the TP unless IEFUAV unallocates them before completing its processing.

Entry Specifications

IEFUAV is passed a list of parameter addresses (pointed to in register 1).

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of parameter list

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point of IEFUAV

Parameter Descriptions: Register 1 points to a list of addresses. The list is specified in VL format (that is, the last address has its leftmost bit set to 1). The following describes the list of parameters:

Word 1

Address of the common exit parameter area. For details, see [“Common Exit Parameter Area” on page 140.](#)

Word 2

Address of a 20-byte area containing the programmer's name (in EBCDIC). This area is aligned left and padded with blanks if necessary.

Word 3

Address of a 1-byte area that contains a value (binary). The value indicates one of the following conditions:

**Exit Function Code
Condition**

0

This code is reserved, and no action is taken.

1

For both standard and multi-trans TPs, this code indicates that IEFUAV has received control during the initialization of a TP. The exit receives generic, installation-supplied accounting information from the TP user's RACF profile (in the area pointed to by Word 4).

2

For multi-trans TPs, this code indicates that accounting information might have been altered. The exit receives accounting information from the TP user's RACF profile (in the area pointed to by Word 4).

3

For multi-trans TPs, this code indicates a return to processing on behalf of the multi-trans "shell". The exit receives generic, installation-supplied accounting information from the TP user's RACF profile (in the area pointed to by Word 4).

4-255

These codes are reserved, and no action is taken.

Word 4

Address of an area containing accounting information. (See [“Accounting Information” on page 142.](#))

Word 5

Address of a two-word area representing a message area. The first word contains a message length of zero on entry. The second word contains the address of an 80-byte message buffer. In that buffer, the exit routine can place a message to be issued to the APPC/MVS job log.

Note: The high-order bit is set in the address of the last parameter to indicate the end of the parameter list.




Figure 14. IEFUAV Input Parameter Structure

Return Specifications

A return code from IEFUAV indicates whether processing is to continue.

If you associate multiple exit routines with IEFUAV, you can specify how the return information is to be handled using the ATTRIB KEEPRC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

If you associate multiple exit routines with exit IEFUAV, and any of those exit routines return with a value of 8, the system will cancel the unit of work.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

- 0 Not applicable
- 1 Address of input parameter list

Words 1-4
Not applicable

Word 5
Points to a two-word area representing a message to be written to the APPC/MVS job log. The first word contains the length of the message. The second word is the address of an 80-byte buffer; the buffer contains the text of the message.

2-14
Not applicable

- 15 One of the following return codes:

Return Code Explanation

- 0 Processing is to continue.

8

This unit of work should be cancelled.

Coded Example of the Exit Routine

IBM provides a sample IEFUAV exit routine in SYS1.SAMPLIB (member SMFEXITS). The sample routine validates the account number of the current user.

If this routine meets the needs of your installation, use it instead of coding your own routine (you will need to make minor modifications to the sample). If you plan to code your own routine, you might want to refer to this routine as an example.

Chapter 30. IEFUJI — Job Initiation Exit

Topics for This Exit Appear as Follows:

- [“Defining the Exit in SMFPRMxx” on page 175](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 175](#)
- [“Exit Routine Environment” on page 176](#)
- [“Exit Recovery” on page 176](#)
- [“Exit Routine Processing” on page 176](#)
- [“Programming Considerations” on page 176](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 177](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 178](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 179](#)

IEFUJI receives control before the system selects a job on the input queue for initiation. A return code from IEFUJI indicates whether job processing is to continue or be cancelled.

You can use IEFUJI to:

- Validate job accounting information.
- Determine how long a job was on the input job queue before it was selected.
- Write particular information to an installation data set.

Defining the Exit in SMFPRMxx

In the SMF parmlib member (SMFPRMxx), specify IEFUJI on the EXITS option of either the SYS or SUBSYS parameters, depending on the scope of work (system-wide or subsystem-wide) the exit is to affect.

If you use the SUBSYS option, the system invokes the IEFUJI routine only for work running under the subsystems you specify on SUBSYS. If you use the SYS option, the system invokes the IEFUJI routine for work running under any SMF-defined subsystem, such as JES2, JES3, STC, ASCH, OMVS, or TSO.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFUJI installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFUJI or SYSyyy.IEFUJI. See the description of the SMFPRMxx parmlib member in [z/OS MVS Initialization and Tuning Reference](#) for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its routines.

To define IEFUJI to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for this exit, you need only define IEFUJI in SMFPRMxx.

The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFUJI in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFUJI).

If you associate exit routines with IEFUJI in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Exit Routine Environment

IEFUJI receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 31.
- In the address space of the job that is being started.
- With no locks or ENQs held.

Exit Recovery

IBM strongly recommends that you set up an ESTAE recovery routine to handle errors that might occur during the execution of IEFUJI.

An ESTAE-type recovery routine is set up by the module that calls IEFUJI; the recovery routine, if it gets control, will allow the job to continue processing if the exit routine abnormally ends.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

IEFUJI receives control from the system whenever a job on the input queue is selected for initiation. If the system availability manager (SAM) function is active and operational, the SAM job/step initialization exit routine executes before IEFUJI is called.

IEFUJI has information from the JOB statement available as parameters. The accounting information is in a formatted list, so that, for account number processing, IEFUJI is easier to use than exit IEFUJV. [Table 4 on page 142](#) shows the format of the JOB statement accounting information.

At the end of its processing, IEFUJI sets a return code to indicate whether job processing is to continue or not.

Programming Considerations

SMF automatically provides a replaceable module for IEFUJI. If an installation includes IEFUJI, it must follow certain programming standards:

- The exit routine must follow standard linkage conventions.

- Code the exit routine reenterable and refreshable.
- IEFUJI can perform dynamic allocations and write to installation-defined data sets. In foreground jobs, data sets are allocated dynamically. However, for background jobs, you can either allocate data sets dynamically or you can pre-define (pre-allocate) a data set with a DD statement in the initiator cataloged procedure.
- IEFUJI cannot access ISAM data sets.
- Do not use a WTO with a routing code of 11 to send a message to the JESYSMSG data set for started tasks or TSO users.
- Do not use subpool 240 or 250 when obtaining storage for this exit. Using these subpools may result in errors when the exit receives control for address spaces that are created with the KEEPGRN attribute.
- To provide a consistent environment for accessing and allocating data sets across calls to SMF exits for the duration of a job or task, IEFUJI receives control with the initiator's JSCB active.

At job or job step termination, use the termination indicators in SMF record types 4, 5, 30, 34, and 35 to indicate that IEFUJI cancelled the job.

Macro Instructions and Restrictions: When issuing a WTOR macro, specify LONG=YES on the WAIT macro. Do not use a WTO with a routing code of 11 to send a message to the JESYSMSG data set for started tasks or TSO users.

Entry Specifications

The system provides a list of parameter addresses that IEFUJI can use.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of the parameter list

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of IEFUJI

Parameter Descriptions: Register 1 points to the following list of addresses:

Word 1

Address of the common exit parameter area. For details on the parameter area, see [Table 3 on page 141](#).

Word 2

Address of a 20-byte area containing the programmer's name (in EBCDIC) from the JOB statement. This area is aligned left and padded with blanks if necessary.

Word 3

Address of a one-byte area indicating (in binary) the requested job selection priority. The value of this field equals the user-assigned priority of 0 to 14 (taken from the PRTY parameter on the JOB statement).

Word 4

Address of an area containing the accounting information from the JOB statement. (See [“Accounting Information” on page 142](#).)

Word 5

Address of a 4-character area that contains the name of the subsystem for the job being processed.
Examples:

- ASCH, JES2, or JES3 – indicates the name of the subsystem that selected the job
- OMVS – indicates a forked or spawned address space
- STC – indicates a started task
- TSO – indicates a time sharing option task
- The jobname – used if it is four or fewer characters and none of the above apply

Note: The high-order bit is set in the address of the last parameter to indicate the end of the parameter list.




Figure 15. IEFUJI Input Parameter Structure

Return Specifications

A return code from IEFUJI indicates whether job processing is to continue.

If you associate multiple exit routines with IEFUJI, you can specify how the return information is to be handled using the ATTRIB KEEPRC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

If you associate multiple exit routines with exit IEFUJI, and any of those exit routines return with a value of 4, job processing will not continue.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

**Register
Contents**

0-14
Not applicable

15
One of the following return codes:

**Return Code
Explanation**

Value of 4

Job processing is to be cancelled.

Value other than 4

Job processing is to continue.

Coded Example of the Exit Routine

A sample IEFUJI exit routine is provided in SYS1.SAMPLIB (in member SMFEXITS). This routine determines how long a job has been on the input job queue before it is initiated. It then writes this value and the job priority to the SMF data set as a user record.

Chapter 31. IEFUJP – Job Purge Exit

Topics for This Exit Appear as Follows:

- [“Defining the Exit in SMFPRMxx” on page 181](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 181](#)
- [“Exit Routine Environment” on page 182](#)
- [“Exit Recovery” on page 182](#)
- [“Exit Routine Processing” on page 182](#)
- [“Programming Considerations” on page 182](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 182](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 183](#)
 - Registers at Exit

IEFUJP receives control from the job entry subsystem (JES2 or JES3) when a job is ready to be purged from the system, meaning that the job terminated and the system has written all SYSOUT output pertaining to the job. A return code from IEFUJP indicates whether the SMF job purge record (type 26) is to be written to the SMF data set.

Defining the Exit in SMFPRMxx

To allow the system to invoke IEFUJP, define the exit in the SMF parmlib member (SMFPRMxx). Specify IEFUJP on the EXITS option of the SUBSYS parameter for the STC subsystem. If your installation chooses not to define a SUBSYS parameter for STC, you can specify IEFUJP on the EXITS option of the SYS parameter.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFUJP installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFUJP or SYSyyy.IEFUJP. See the description of the SMFPRMxx parmlib member in [z/OS MVS Initialization and Tuning Reference](#) for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

To define IEFUJP to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for this exit, you need only define IEFUJP in SMFPRMxx.

The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFUJP in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFUJP).

If you associate exit routines with this exit in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Exit Routine Environment

IEFUJP receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 1.
- In AMODE 31.

Exit Recovery

IBM strongly recommends that you set up an ESTAEX recovery routine to handle errors that might occur during the execution of IEFUJP.

An ESTAE-type recovery routine is set up by the module that calls IEFUJP; the recovery routine, if it gets control, will allow the job to continue processing if the exit routine abnormally ends.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

IEFUJP receives control from the job entry subsystem SMF writer. The addresses of the SMF common exit parameter list and the type 26 SMF record (SMF job purge record) are parameters that the exit routine can use to determine whether or not to write the SMF record.

At the end of its processing, IEFUJP sets a return code to indicate to the JES SMF writer whether to write the SMF record.

Programming Considerations

SMF automatically provides a replaceable module for an unused exit. If an installation includes IEFUJP, certain programming conventions must be followed:

- The exit routine must follow standard linkage conventions.
- Code the exit routine to be reentrant and refreshable.
- If you use installation-defined data sets with IEFUJP, you must define them with a DD statement in the job entry subsystem cataloged procedure.

Macro Instructions and Restrictions: When issuing a WTOR macro, specify LONG=YES on the WAIT macro. Do not use a WTO with a routing code of 11 to send a message to the JESYSMSG data set for started tasks or TSO users.

Entry Specifications

The job entry subsystem provides the addresses of the SMF record and the common exit parameter area for the exit routine to use.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

- 0** Not applicable
- 1** Contains address of parameter list
- 2-12** Not applicable
- 13** Register save area
- 14** Return address
- 15** Entry point address of IEFUJP

Parameter Descriptions: Register 1 points to the following list of addresses:

Word 1

The address of the common exit parameter area. (See [Table 3 on page 141.](#))

Word 2

The address of an area containing the SMF job purge record (type 26) to be written to the SMF data set.




Figure 16. IEFUJP Input Parameter Structure

Return Specifications

A return code from IEFUJP indicates whether the SMF type 26 record is to be written.

If you associate multiple exit routines with IEFUJP, you can specify how the return information is to be handled using the ATTRIB KEEPRC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

If you associate multiple exit routines with exit IEFUJP, and any of those exit routines return with a value of 4, the system will not write the SMF type 60 record.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

- 0-14** Restored to contents at entry
- 15** One of the following return codes:

Return Code

Explanation

Value of 4

Job purge record is not to be written to the SMF data set.
--

Value other than 4

Job purge record is to be written to the SMF data set.
--

Chapter 32. IEFUJV – Job Validation Exit

Topics for This Exit Appear as Follows:

- [“Defining the Exit in SMFPRMxx” on page 186](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 186](#)
- [“Exit Routine Environment” on page 186](#)
- [“Exit Recovery” on page 187](#)
- [“Exit Routine Processing” on page 187](#)
- [“Programming Considerations” on page 188](#)
- [“Entry Specifications” on page 189](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 191](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 192](#)

IEFUJV receives control at three different points in the converter/interpreter (C/I) processing of an input stream. They are:

1. Preconversion — before each job control statement (or cataloged procedure) in the input stream is converted.
2. Postconversion — after all job control statements for a job have been converted.
3. Postinterpretation — after all job control statements for a job have been interpreted.

For z/OS UNIX System Services, this exit is called only once when each BPXAS initiator is started. It is not called for forked/spawned requests and can not be used to validate them.

A return code from this exit indicates whether job processing is to continue.

At the preconversion point, you might use IEFUJV to:

- Validate any accounting fields included in the JOB and EXEC statements (except symbolic parameters) by comparing them to a standard list.
- Validate or assign the REGION request.
- Validate or assign job TIME and job step TIME parameters.
- Control output stream data by using the OUTLIM or SPACE parameters.
- Check for authorization to use restricted data sets.
- Create user-written records.
- Assign the user identification to be included in both the SMF job/step termination record and the SMF job purge record.
- Limit the size of temporary data sets handled by VIO.
- Require checkpoint/restart for jobs requesting a large amount of processor time.
- Enforce installation standards on usage of the ADDRSPC parameter.
- Override certain JES initialization parameters (such as designation of where SWA blocks are to be obtained) that are passed to converter routines.

At the postconversion point, you might use IEFUJV to:

- Create user-written records.

- Assign the user identification to be included in both the SMF job/step termination record and the SMF job purge record.
- Override certain JES initialization parameters (such as designation of where SWA blocks are to be obtained) that are passed to converter routines.

At the postinterpretation point, you might use IEFUJV to:

- Create user-written records.
- Assign the user identification to be included in both the SMF job/step termination record and the SMF job purge record.

Defining the Exit in SMFPRMxx

In the SMF parmlib member (SMFPRMxx), specify IEFUJV on the EXITS option of either the SYS or SUBSYS parameters, depending on the scope of work (system-wide or subsystem-wide) the exit is to affect.

If you use the SUBSYS option, the system invokes the IEFUJV routine only for work running under the subsystems you specify on SUBSYS. If you use the SYS option, the system invokes the IEFUJV routine for work running under any SMF-defined subsystem, such as JES2, JES3, STC, ASCH, OMVS, or TSO.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFUJV installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFUJV or SYSyyy.IEFUJV. See the description of the SMFPRMxx parmlib member in [z/OS MVS Initialization and Tuning Reference](#) for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines. However, you cannot use the JOBNAME parameter of the SETPROG EXIT command to restrict exit IEFUJV processing to a particular job.

To define IEFUJV to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for this exit, you need only define IEFUJV in SMFPRMxx.

The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFUJV in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFUJV).

If you associate exit routines with this exit in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Exit Routine Environment

IEFUJV receives control in the following environment:

- Enabled for interrupts.

- In supervisor state with PSW key 0 or 1 (based on the caller's key). When the entry code (contained in word 3 of the input parameter list) is 32, the key is 0.
- In AMODE 31.

In a JES2 environment, conversion might take place on one processor and interpretation of the same job on another. Therefore, the IEFUJV exits could receive control on different processors for the same job. In that case, timing comparisons of the job flow would not be valid.

For an interpreter call in a JES2 environment, a security environment must be established if the exit is to obtain access to any protected resources. For example, if a command is to be issued with RACF OPERCMDS active, pass a user security token (UTOKEN) on the MGCRE macro to establish authority for the user requesting access to the command. See *z/OS MVS Programming: Authorized Assembler Services Reference LLA-SDU* for information about the MGCRE macro.

Exit Recovery

IBM strongly recommends that you set up an ESTAEX recovery routine to handle errors that might occur during the execution of IEFUJV.

An ESTAE-type recovery routine is set up by the module that calls IEFUJV; the recovery routine, if it gets control, will allow the job to continue processing if the exit routine abnormally ends.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

There are two data formats related to JCL statements. The first data format is the JCL "card image." A JCL card image is an 80-character EBCDIC string that represents either an entire JCL statement or a portion of a JCL statement that is continued. The second data format is the C/I text string representation of the JCL statement. The C/I text format consists of an established pattern of hexadecimal codes, or keys, assigned to each parameter or subparameter. See Part 4, "MVS Converter / Interpreter Text Processing," on page 335 for more details about C/I text strings and the appropriate processing exit points.

JES provides several exit points related to JCL card image processing. See *z/OS JES2 Installation Exits* and *z/OS JES3 Customization* for additional information about this processing.

Note that IEFUJV receives control following the JES exits related to card image processing. Your installation is responsible for coordinating the processing between IEFUJV and the JES exits.

Note further that if you use the IEFUJV exit to change certain parameters on the JOB statement, the result might be that the internal representation of the JCL card image would reflect the changes while the job itself continues to be processed according to the original JOB statement. For example, if you change the CLASS parameter as part of the exit routine, the job will still run in its original specified class. This applies to both the JES2 and JES3 environments. These other JOB statement parameters have the same restriction: GROUP, MSGCLASS, NOTIFY, PASSWORD, PRTY, SECLABEL, TYPRUN, and USER.

Preconversion processing: IEFUJV receives control at the preconversion processing exit point before each JCL statement card image is converted. The input parameter list provides an indication of the type of JCL statement being processed.

The exit will be invoked multiple times for a continued JCL statement (once per card image). The JCL statement type indicator is the same for each card image of the continued JCL statement.

When modifying a JCL statement, the updated JCL statement must adhere to the JCL syntax as defined in *z/OS MVS JCL Reference*. The following updates are not permitted at the preconversion processing point:

- Do not include additional JCL statements
- Do not add continuation card images.
- Do not change the operation field on a JCL statement.
- Do not change the identifier field on a JCL statement.

If a procedure is used, it is expanded before the IEFUJV exit routine receives control. For example, for a cataloged procedure, the sequence of statements are:

```
//UJV      JOB
//STEP1    EXEC   PROC=MYPROC
XXMYPROC   PROC
XXSTEP2    EXEC   PGM=...
```

followed by the other statements of the procedure. Note that the resolved values for symbolic parameters are not passed to the IEFUJV exit routine.

Using IEFUJV for Job Accounting: You might want to use an IEFUJV exit routine for job accounting. If so, consider the following:

- For APPC/MVS transaction programs (TPs), IBM recommends that you use IEFUAV instead of IEFUJV to validate accounting information. IEFUAV is the only exit that allows you to validate the accounting information of a TP user **at execution time**. Even though IEFUJV is invoked when a TP profile is created (specifically, when the profile's JCL statements are processed by the converter/interpreter), the TP user is not known at that time. Therefore, when you need to validate the TP user's accounting information (such as the job name or account number), use the IEFUAV exit routine. See [Chapter 29, “IEFUAV — User Account Validation Exit,”](#) on page 167 for more information.
- Depending upon the processing to be performed, it may be more efficient to check JOB and EXEC statement accounting fields in the IEFUJI exit routine and the first IEFUSI exit routine, respectively. The accounting fields are passed as parameters to IEFUJI and IEFUSI, making a statement scan routine unnecessary. Either of these exit routines can assign user identification, and the IEFACTRT exit routine can write messages to JOBLLOG.
- When running JES2, you can use Exit 03, the job statement accounting field scan exit (HASPRSCN), as well as the IEFUJV exit. Because Exit 03 receives control before the IEFUJV exit, do not use the IEFUJV exit to change the following fields of the JOB statement: CLASS, MSGCLASS, NOTIFY, PRTY, PASSWORD and TYPRUN.
- If an installation checks JOB statement accounting in the IEFUJV exit for all tasks, the IEFUJV exit should not be taken, unless modified, for started tasks. Started tasks do not have any JOB statement accounting and might be cancelled by the installation exit.

For jobs cancelled by IEFUJV from the converter, only SMF record types 6 and 26 are generated.

Preconversion input limitations: The following information is not made available to this exit routine:

- Resolved values for JCL symbolic parameters
- JCL COMMAND, Command, and Comment statements
- JCL Null statement (//)
- JES2 control statements
- JES3 control statements

Postconversion processing: IEFUJV receives control at the postconversion processing point once per job to indicate that the conversion processing for the job has completed.

Postinterpretation processing: IEFUJV receives control at the postinterpretation processing point once per job to indicate that the interpretation processing for the job has completed.

When running JES3, a JES3 user can use JES3 installation exits, in addition to the IEFUJV exit, to write programs to examine and change the results of interpreter processing and allow the job to proceed or to flush the job from the system. For more information about the JES3 installation exits, see [z/OS JES3 Customization](#).

Programming Considerations

When issuing a WTOR macro, specify LONG=YES on the WAIT macro. Do not use a WTO with a routing code of 11 to send a message to the JESYSMSG data set for started tasks or TSO users.

IEFUJV must be reenterable and refreshable because PLPA pages are stolen. That is, they can be paged in but not paged out, and subsequent page-ins overlay any code changes.

To use installation-defined data sets with this exit routine, you must define them with a DD statement in the job entry subsystem cataloged procedure. When running JES2, you must also define the data sets with a DD statement in the initiator cataloged procedure.

IEFUJV cannot access ISAM data sets.

Exit IEFUJV is called multiple times for a job. When you change the exit routine after it has been called at least once, but before all the calls for the job have been made, the job might be rejected because of incorrect JCL. When you rerun the job it will run successfully.

Entry Specifications

The converter/interpreter passes to IEFUJV a list of parameter addresses (in register 1).

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of the parameter list

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of IEFUJV

Parameter Descriptions: Register one points to the following list of addresses:

Word 1

The address of the common exit parameter area. (See [Table 3 on page 141.](#))

Word 2

When the value pointed to by Word 3 is neither 16 nor 32, Word 2 is the address of the JCL statement card image.

This word is 0 when the value pointed to by word 3 is 16 or 32.

Word 3

The address of a 1-byte area that indicates the specific exit processing point. For preconversion, it also indicates the type of JCL statement being passed to the exit. See [“Exit Routine Processing” on page 187](#) for more information. The indicator is one of the following binary values:

Value

Meaning

0

indicates the preconversion exit point; null statement card image.

1

indicates the preconversion exit point; JOB statement card image.

2

indicates the preconversion exit point; EXEC statement card image.

4

indicates the preconversion exit point; DD statement card image.

8

indicates the preconversion exit point; PROC statement card image from cataloged procedure.

16

indicates the postconversion exit point; all JCL has been converted.

32

indicates the postinterpretation exit point; all JCL has been interpreted.

64

indicates the preconversion exit point; JCL definition table defined (JDT) statement card image.

128

indicates the preconversion exit point; extended JCL statement type card image. Extended JCL statement type refers to any new JCL statements defined as of MVS/ESA Version 4. (For possible exceptions see [“Exit Routine Processing”](#) on page 187.)

Word 4

This word is 0 when the value pointed to by word 3 is 32.

When the value pointed to by word 3 is not 32, word 4 is the address of the JES initialization parameters that are passed to the converter routine. The address points to the first converter parameter field, which is a 1-byte bit-map defined as follows for bits that are set on:

.....1

Programmer name required.

.....1.

Account number required.

.....1..

Indicates that a job is enabled to run with the SWA located in virtual storage above 16 megabytes.

Note: IEFUJV may turn any of these bits on or off at any time except when the value pointed to by word 3 is 32. If a bit is turned on or off more than one time, the final setting of the bit is the one which will be honored.

Note: The account number must not be required in the exit for started task JOB statements because there is no way to put an account number on a started task JOB statement. An accounting number can be required on an EXEC statement in SYS1.PROCLIB.

Word 5

The address of a 4-character area that contains the name of the subsystem for the job being processed. Examples:

- ASCH, JES2, JES3 or OMVS - indicates the name of the subsystem that selected the job (For OMVS, see Guideline below.)
- STC - indicates a started task
- TSO - indicates a time sharing option task
- The jobname - used if it is four or fewer characters and none of the above apply

Guideline: The first time after an IPL that a z/OS UNIX fork or spawn occurs, z/OS UNIX creates JCL for a job named BPXYOEJS using a default JOB statement and passes that JCL to the MVS Converter and Interpreter (C/I). For this one job, C/I calls IEFUJV under SUBSYS = OMVS. Job BPXYOEJS does not actually execute. Instead the Interpreter creates SWA blocks for this job and passes them back to z/OS UNIX, which stores them for later use. These SWA blocks will be used by all subsequent forked or spawned address spaces. This means that whatever version of IEFUJV is active when the first fork or spawn occurs will be the only IEFUJV entered for forked or spawned address spaces, even if a new version of IEFUJV is later dynamically activated (through the SETPROG EXIT command). The BPXAS initiators in which the forked or spawned processes run, do go through IEFUJV, but with SUBSYS = STC exit.

Word 6

The address of a 4-byte area that contains the environment indicator associated with the subsystem specified in word 5.

The value that applies to all subsystems is 0.

Value
Meaning

0
Default - “no meaning”

The values that apply to ASCH (APPC Scheduler) are 1, 2, and 3.

Value
Meaning

1
APPC Scheduler Utility TP Add call

2
APPC Scheduler Utility TP Retrieve call

3
APPC Scheduler Utility TP Reconvert call

Note: The high-order bit is set in the address of the last parameter to indicate the end of the parameter list.




Figure 17. IEFUJV Input Parameter Structure

Return Specifications

A return code from IEFUJV indicates whether job processing will continue or be terminated.

If you associate multiple exit routines with IEFUJV, you can specify how the return information is to be handled using the ATTRIB KEEPRC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

If you associate multiple exit routines with exit IEFUJV, and any of those exit routines return with a value of 4, job processing will be terminated.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

**Register
Contents****0-14**

Restored to contents at entry

15

One of the following return codes:

Return Code**Explanation****Value of 0**

Job processing is to continue.

Value of 4

Job processing is to be cancelled.

Coded Example of the Exit Routine

Sample IEFUJV exit routines are provided in SYS1.SAMPLIB in members SMFEXITS and IEEUJV. The routine in SMFEXITS checks the validity of a continued JOB statement and of values supplied for the REGION, PRTY, TIME, and accounting parameters in the JOB statement. The routine uses characters from the account number to index a table that contains allowable values for these parameters. If any value is not valid, the sample IEFUJV routine terminates the job.

The sample in IEEUJV changes the SYSOUT class to SYSOUT=* for jobs in specified JOB classes and for specified SYSOUT classes. Assembled into the exit routine is a list of eligible job classes and a list of eligible SYSOUT classes. Thus, if a job enters the system in one of the specified job classes and contains a DD statement specifying SYSOUT=class, where class is one of the specified SYSOUT classes, then the SYSOUT class will be changed to '*'.

Chapter 33. IEFUSI – Step Initiation Exit

Topics for This Exit Appear as Follows:

- [“Comparing IEFUSI with IEALIMIT when Limiting Region Size” on page 194](#)
- [“Defining the Exit in SMFPRMxx” on page 195](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 195](#)
- [“Exit Routine Environment” on page 195](#)
- [“Exit Recovery” on page 195](#)
- [“Exit Routine Processing” on page 196](#)
- [“Programming Considerations” on page 196](#)
- [“Entry Specifications” on page 196](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 201](#)
 - Registers at Exit
- [“Examples” on page 202](#)
 - Example of Using IEFUSI to Limit Region Size
 - Examples of Storage Allocations Based on Values Set by IEFUSI

IEFUSI receives control before each job step is started (prior to allocation). A return code from this exit indicates whether the job step is to be started or the job should be cancelled.

You can use IEFUSI to:

- Validate job step accounting information.
- Write to a user data set.
- For long-running jobs, create and write a user step-initiation SMF record in case of system failure.
- Set the region size and region limit for all programs that run under this job step. For more information about controlling region size and region limit, see [z/OS MVS Initialization and Tuning Guide](#).

Note: For programs with the NOHONORIEFUSIREGION Program Property Table (PPT) attribute specified, region and MEMLIMIT values and limits set by the IEFUSI exit are not honored. See the [z/OS MVS Initialization and Tuning Reference](#) and the [z/OS MVS Initialization and Tuning Guide](#) for more information about this PPT attribute and how it affects the IEFUSI-altered region and MEMLIIT settings.

- Set limits on the use of data spaces and hiperspaces created by application programs with storage key 8 - F.
- Limit the number of pages that can be shared at one time through the use of the IARVSRV macro.
- Set the default size of data spaces and hiperspaces.
- Limit the use of the 16 exabyte address space above two gigabytes.
- Reduce the values of LDAELIM, LDAEVVRG, LDALIMIT, and LDAVVRG. Initially, these fields contain the maximum amount of storage available to the user. Specifically:

```
LDAELIM = LDAEVVRG = 32Mb
```

and

```
LDALIMIT = LDAVVRG = LDASIZA - 64K
```

Note: For programs with the NOHONORIEFUSIREGION Program Property Table (PPT) attribute specified, these region values are not changed by the IEFUSI exit. See the *z/OS MVS Initialization and Tuning Reference* and the *z/OS MVS Initialization and Tuning Guide* for more information about this PPT setting and how it affects the IEFUSI-altered region and MEMLIMIT values and limits.

Use of the IEFUSI exit may only reduce the amount of storage requested, not increase it.

If an installation uses major and minor account numbers with several fields, IEFUSI is easier to use than IEFUJV for account number processing because the accounting fields are placed in a formatted list. See Table 4 on page 142 for the format of the accounting information.

Limiting Region Size: There are several factors to consider in using IEFUSI to limit region size:

- Consider using the SMFLIMxx parmlib member, which provides the ability to set the REGION and reserve storage for system key storage obtains without writing an IEALIMIT or IEFUSI exit.
- If IEFUSI is not available, or IEFUSI is not used to set up the region size, the system will use IEALIMIT.
- To use IEFUSI for region size control, you must tell the system to bypass the IEALIMIT exit by setting a flag in the IEFUSI parameter list.
- When writing the installation exit, the region size should be made less than the region limit. This is to protect against programs that issue variable requests for storage with very large upper bounds and then do not immediately free part of that space, or free such a small amount that a subsequent request for storage (possibly issued by a system service) causes the job to fail. See *z/OS MVS Initialization and Tuning Guide* for a discussion on the relationship between region size and region limit and how the system uses these values.
- For programs with the NOHONORIEFUSIREGION Program Property Table (PPT) attribute specified, IEFUSI-altered region and MEMLIMIT values and limits are not honored. The NOHONORIEFUSIREGION PPT attribute can be specified in the SCHEDxx member of SYS1.PARMLIB, or as an IBM supplied PPT default. This PPT attribute is used to bypass IEFUSI region controls for programs that require more region space to successfully execute. See the *z/OS MVS Initialization and Tuning Reference* and the *z/OS MVS Initialization and Tuning Guide* for more information on this PPT setting and how it affects the IEFUSI-altered region and MEMLIMIT values and limits.

Although you can use the IEFUSI exit to modify the region size of an address space, IBM strongly recommends that you do not alter the region size of address spaces in the OMVS subsystem category.

Note: A default IEFUSI module is included in SYS1.LPALIB. This default module does not do any processing, but just returns to the caller. It will be picked up first by the system at IPL time, unless you code your exit specifically in the PROGxx parmlib member using the EXIT ADD statement.

Comparing IEFUSI with IEALIMIT when Limiting Region Size

Historically, users could limit program storage below 16 megabytes in virtual storage by using IEALIMIT. IEALIMIT can still be used to limit program storage in the nonextended region; however, IEFUSI is the preferred exit routine, and has the following advantages over IEALIMIT:

- IEFUSI is a separate load module in the link pack area. You must supply a routine named IEFUSI and linkedit it into LPALIB or an LPALSTxx member of SYS1.PARMLIB. IEALIMIT must reside in the nucleus, so you must linkedit the nucleus every time you replace IEALIMIT with a new version. You must linkedit your routine again into the nucleus each time you IPL a different version of the nucleus, as all versions of the nucleus initially contain the IBM-supplied IEALIMIT routine.
- IEFUSI users can obtain information required to set a region size and region limit. IEALIMIT scans system control blocks to gather that information; thus IEFUSI is easier to write and less susceptible to system changes.
- IEALIMIT requires that the local lock be held and therefore cannot issue SVCs. IEFUSI has neither of these restrictions.
- IEFUSI can control the region size and region limit of both the area above and the area below 16 megabytes in virtual storage. IEALIMIT can set values for only the area below 16 megabytes, leaving values for the extended private area above 16 megabytes to be determined by the system.

- Previously, if the region requested by a job was greater than 16 megabytes, MVS allowed a minimum of 32 megabytes in the extended region; IEFUSI can override this 32-megabyte minimum value.

Defining the Exit in SMFPRMxx

In the SMF parmlib member (SMFPRMxx), specify IEFUSI on the EXITS option of either the SYS or SUBSYS parameters, depending on the scope of work (system-wide or subsystem-wide) the exit is to affect.

If you use the SUBSYS option, the system invokes the IEFUSI routine only for work running under the subsystems you specify on SUBSYS. If you use the SYS option, the system invokes the IEFUSI routine for work running under any SMF-defined subsystem, such as JES2, JES3, STC, ASCH, OMVS, or TSO.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFUSI installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFUSI or SYSyyy.IEFUSI. See the description of the SMFPRMxx parmlib member in [z/OS MVS Initialization and Tuning Reference](#) for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its routines.

To define IEFUSI to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for IEFUSI, you need only define this exit in SMFPRMxx.

The exit routine should reside in LPA, the LNKLST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFUSI in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFUSI).

If you associate exit routines with IEFUSI in PROGxx, the system does not use the default exit routine. If you need the default exit routine, add it explicitly to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Exit Routine Environment

IEFUSI receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 31.

Exit Recovery

IBM strongly recommends that you set up an ESTAEX recovery routine to handle errors that might occur during the execution of IEFUSI.

An ESTAE-type recovery routine is set up by the module that calls IEFUSI; the recovery routine, if it gets control, will allow the job to continue processing if the exit routine abnormally ends.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

IEFUSI exit routines receive control before the initiator checks to determine whether the job step will actually execute. That is, IEFUSI receives control before the system performs testing for COND and IF/THEN/ELSE/ENDIF, including ABENDs. This means that IEFUSI will always be called, regardless of whether the step will execute.

Using IEFUSI to Limit Data Space and Hipspace Use: Your IEFUSI exit routine can communicate the values you want to use to limit data space and hipspace use for programs with storage key 8 - F. Code your routine to place these values in word 7 of the SMF parameter list before returning control. (See the parameter descriptions in [“Entry Specifications”](#) on page 196 for a description of word 7.)

Your IEFUSI exit routine can include region processing for the private area, both less than and greater than 16 megabytes. The exit checks the region requested on the JOB or EXEC JCL statement, and determines whether it is acceptable. You can then communicate the values you want to use to limit access to private area storage. Your IEFUSI routine places these values in the appropriate fullwords in the SMF parameter list before returning control to the initiator.

For more information on data spaces and hipspaces, see [z/OS MVS Programming: Extended Addressability Guide](#).

Programming Considerations

When coding an IEFUSI exit routine, observe the following conventions:

- When issuing a WTOR macro, specify LONG=YES on the WAIT macro. Do not use a WTO with a routing code of 11 to send a message to the JESYSMSG data set for started tasks or TSO users.
- Do not use subpool 240 or 250 when obtaining storage for this exit. Using these subpools may result in errors when the exit receives control for address spaces that are created with the KEEPRGN attribute.
- To provide a consistent environment for accessing and allocating data sets across calls to SMF exits for the duration of a job or task, IEFUSI receives control with the initiator's JSCB active.
- IEFUSI must be reenterable and refreshable because PLPA pages are stolen. That is, they can be paged in but not paged out, and subsequent page-in operations will overlay any code changes.
- IEFUSI can perform dynamic allocations and write to installation-defined data sets. In foreground jobs, data sets are allocated dynamically. However, for background jobs, you can either allocate data sets dynamically or you can pre-define (pre-allocate) a data set with a DD statement in the initiator-cataloged procedure.
- IEFUSI cannot access ISAM data sets.

Additional Considerations for z/OS UNIX Applications: When running z/OS UNIX applications you need to consider that fork and spawn are issued to create new address spaces. The default processing on fork and spawn is for the z/OS UNIX kernel to propagate the region size from the parent to the child. Because the region size in the parent process has already passed through IEFUSI and has an approved region size, IBM recommends that you bypass normal IEFUSI processing when the subsystem (Word 8) is OMVS.

At the time of IEFUSI processing, the kernel has not yet propagated the parent's region size to the child, so IEFUSI has nothing to work with. If IEFUSI modifies the region size of the child process, the kernel will honor that region size and not propagate the region size from parent to child. This can result in failure of a fork if the region size is insufficient in the child to capture the parent's storage.

Entry Specifications

The system passes a list of parameter addresses to IEFUSI.

Registers at entry: The contents of the registers on entry to the exit are as follows.

**Register
Contents**

- 0**
Not applicable
- 1**
Address of the parameter list
- 2 - 12**
Not applicable
- 13**
Register save area
- 14**
Return address
- 15**
Entry point address of IEFUSI

Parameter descriptions: Register 1 points to the following list of addresses:

Word 1

The address of the common exit parameter area. (See [Table 3 on page 141.](#))

Word 2

The address of an 8-byte area containing the job step name (in EBCDIC) from the EXEC statement. This area is aligned left and padded with blanks if necessary.

For a forked/spawned address space, this will be STEP1 when the address space is first started and will be *OMVSEX, after an exec().

Note: It is possible that some address spaces will be associated with IEESYSAS. For that case, JMRJOB will contain IEESYSAS.

Word 3

The address of an 8-byte area containing the program name (in EBCDIC) from the EXEC statement. This area is aligned left and padded with blanks if necessary. If you refer back, the area contains **pgm=*.DD**. For a forked/spawned address space, this will be BPXPRFC; after an exec() call, it will be BPXPREFC.

Word 4

The address of an area containing the accounting information from the EXEC statement. (See [“Accounting Information” on page 142.](#))

Word 5

The address of an 8-word area that IEFUSI can use to communicate with MVS. This area primarily consists of region size and region limit information. The information consists of the following sub-words:

Sub-word 1

Flag word to specify that IEFUSI, rather than IEALIMIT, is to provide the information on how to control access to private area storage.

The flag word is initialized to zero. Your routine sets the flag bits to mean the following:

Bit	Value	Meaning
0	0	IEALIMIT is supplying information on how to control access to private area storage.
	1	IEFUSI is supplying information on how to control access to private area storage.
1	0	Check if the requested below-16-megabyte-region size is available. If the size is not available an 822 abend occurs.
	1	Do not check if the requested below-16-megabyte-region size is available. If the size is not available, a less-predictable abend than 822 might occur.

Bit	Value	Meaning
2	0	Do not check if the requested above-16-megabyte-region size is available. If the size is not available, a less-predictable abend than 822 might occur.
	1	Check if the requested above-16-megabyte-region size is available. If the size is not available, an 822 abend occurs.
3	0	REGIONX keyword was not used. Note that this bit cannot be altered.
	1	REGIONX keyword was used with sub-word 7 holding the REGIONX first parameter (non-extended region size requested) and sub-word 8 holding the REGIONX second parameter (extended region size requested).
4	0	The SMFLIMxx parmlib settings, if applicable, can override the exit's output.
	1	The SMFLIMxx parmlib settings must not override the exit's settings. This applies to all SMFLIMxx settings, not just region size and region limit information.
5 - 31		Reserved.

Note: The settings for bits 1 and 2 have opposite meanings. You must turn on bit 2 when the amount of contiguous free space requested is critical for the step to be executed.

Sub-word 2

Region size request on the JOB or EXEC JCL statement. For a forked address space, this shows as 54M.

Sub-word 3

Region limit below 16 megabytes.

Sub-word 4

Region size below 16 megabytes.

Sub-word 5

Region limit above 16 megabytes.

Sub-word 6

Region size above 16 megabytes.

Sub-word 7

The REGIONX first parameter (non-extended region size requested).

Sub-word 8

REGIONX second parameter (extended region size requested).

On every entry to IEFUSI, sub-words 3 through 6 in the region size information list are set to X'FFFFFFFF'.

There is no lower bound on the region limit and region size that IEFUSI can request. If the JCL specifies REGION=0 with no MEMLIMIT coded, and the IEFUSI exit changes the REGION size but does not set the MEMLIMIT, the MEMLIMIT value is set to the REGION size above 16MB.

Word 6

The address of a word containing a flag indicating a V=R job.

Word 7

The address of a 4-word area containing IBM-supplied default values for data spaces, hiperspaces, and data sharing (through the IARVSERV macro). These defaults apply only for programs running in problem state with user keys. The number of sharing pages, address spaces, data spaces and hiperspaces can be limited only for jobs running in user keys and in problem state. Jobs running in system key (0 - 7) or in supervisor state may use unlimited sharing pages, data spaces and hiperspaces. The words are defined as follows:

Sub-word

Contents

1

Default data space and hiperspace size. It is specified in blocks of 4K bytes and must be in the range of 1 - X'00080000'. The IBM-supplied default is 956K (X'000000EF' × 4K).

2

Maximum combined size for all user key data spaces and hiperspaces that are created by application programs owned within an address space (in megabytes). The IBM-supplied default and the maximum that can be specified is $(2^{24} - 1)$ megabytes.

3

Maximum number of user-key data spaces and hiperspaces created by application programs that can exist at any given time for an address space. The IBM-supplied default is 4096. The maximum number that can be specified is 4,294,967,295, or $(2^{32} - 1)$.

4

Maximum number of source and target shared pages that can be used at one time by problem state callers using the IARV SERV SHARE services. The IBM-supplied default is 32 (which allows at most 16 pages to be shared with 16 other pages; the number of pages include source plus target). The maximum you can specify is $(2^{31} - 1)$.

Note: If you change the default, make sure you balance this with other uses of real storage. You can calculate the number of real 4K frames that are required, as follows:

$$(number\ of\ share\ groups + number\ of\ shared\ views + 252) \div 127$$

Ignore any remainder after dividing by 127.

Word 8

The address of a 4-character area that contains the name of the subsystem for the job being processed. Examples:

- ASCH, JES2, or JES3 — indicates the name of the subsystem that selected the job.
- OMVS — indicates a forked or spawned address space
- STC — indicates a started task
- TSO — indicates a time sharing option task
- The jobname — used if it is four or fewer characters and none of the above apply

Word 9

The address of an area consisting of three 64-bit fields used to specify MVS MEMLIMIT value. The MEMLIMIT information consists of:

Sub-parm 1

A 64-bit flag word. The first 8 bits indicate whether the source of the MEMLIMIT is from JCL, or the SMF-supplied system default. The remaining 56 bits are not used.

Your routine can set the flag bits to the following possible values:

Hex value of first 8 bits	Meaning
01 ('00000001'b)	MEMLIMIT is from SMF
02 ('00000010'b)	MEMLIMIT is from JCL
03 ('00000011'b)	MEMLIMIT was set to NOLIMIT because JCL specified REGION=0
FF ('11111111'b)	MEMLIMIT is from SMF (indicative of internal processing errors)

Note: When you initialize a child address space in the UNIX System Services environment, the source MEMLIMIT value can be set using definitions other than those provided through the IEFUSI exit. For additional information, see

- [System limits and process limits in z/OS UNIX System Services Planning.](#)
- In [z/OS UNIX System Services Programming: Assembler Callable Services Reference](#):
 - [setrlimit \(BPX1SRL, BPX4SRL\)](#) — Set resource limits.
 - [spawn \(BPX1SPN, BPX4SPN\)](#) — Spawn a process.

Sub-parm 2

The 64-bit MEMLIMIT originally requested by the source that is specified in the flagword. This value is specified in megabytes.

Sub-parm 3

The 64-bit MEMLIMIT requested by the IEFUSI exit. The initial value is X'FFFFFFFFFFFFFFF' to indicate that no value was set by the exit. This value is specified in megabytes.

Notes:

1. A MEMLIMIT of NOLIMIT is equivalent to X'0000FFFFFFFF000'.
2. Critical address spaces are exempt from the IEFUSI imposed limit on above the bar virtual memory, so as not to affect system availability.

For a complete description of MEMLIMIT, and the ways to define it, see [*z/OS MVS Programming: Extended Addressability Guide*](#).

Note: The high-order bit is set in the address of the last parameter to indicate the end of the parameter list.




Figure 18. IEFUSI Input Parameter Structure

Note: These fields are only valid when bit 3 in the "Flag word" is set.

Return Specifications

A return code from IEFUSI indicates whether job processing should continue or be cancelled.

If you associate multiple exit routines with IEFUSI, you can specify how the return information is to be handled using the ATTRIB KEEPRC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

If you associate multiple exit routines with exit IEFUSI, and any of those exit routines return with a value of 4, job processing will be cancelled.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0 - 14

Restored to contents at entry

15

One of the following return codes:

Return Code Explanation

4

Job processing should be cancelled.

Other than 4

Job processing should continue.

Examples

The examples that follow illustrate actual allocations based on region size and limit values set by IEFUSI.

Example of using IEFUSI to Limit Region Size: Suppose you want to limit all jobs in a given step-accounting category to a user region of 4 megabytes below and 4 megabytes above 16 megabytes. You also want to set a GETMAIN limit of 6 megabytes below 16 megabytes and 48 megabytes above 16 megabytes.

The system applies the following limits when allocating space for the program whose values you set in IEFUSI:

(Assume that the user's private area below 16 megabytes is 8 megabytes, and that the extended private area, above 16 megabytes, is approximately 1975 megabytes.)

Limit Value below 16Mb = 6Mb

(Less than 8Mb)

Limit Value above 16Mb = 48Mb

(The value from IEFUSI is greater than 32Mb, but less than the extended private area)

Region Size below 16Mb = 4Mb

(Less than limit value)

Region Size above 16Mb = 4Mb

(Less than extended limit value)

Examples of Storage Allocations Based on Values Set by IEFUSI: Assume that application program A has the following characteristics:

Limit value	150K
REGION size value	100K
Space currently allocated	80K

Program A issues the following variable length GETMAIN requests, in the order indicated (note that the GETMAIN requests are **cumulative**):

1. Request 5K–10K: 10K is allocated, making the currently allocated space 90K.

Because the amount still unallocated (20K, relative to the region size of 100K), was greater than the maximum amount requested, the maximum amount was allocated.

2. Request 5K—100K: 10K is allocated, making the currently allocated space 100K.

Because the amount still unallocated (10K, relative to the region size) was between the minimum and maximum requested, the unallocated space was allocated.

3. Request 40K—100K: 40K is allocated, making currently allocated space 140K.

Although the amount still unallocated (0K, relative to the region size) was less than the minimum amount requested (40K), the minimum amount requested would not increase the currently allocated space beyond the limit value, so the minimum amount was allocated.

4. Request 15K—50K: the GETMAIN fails.

The amount still unallocated (0K, relative to the region size) was less than the minimum amount requested (15K), AND the minimum requested would increase the currently-allocated space to 155K, which exceeds the GETMAIN limit value of 150K.

The region size value is usually set up to be less than the limit value. This will protect against programs that issue variable length GETMAINS with very large maximums and then do not immediately free part of that space, or free such a small amount that a subsequent GETMAIN (possibly issued by a system service) causes the job to fail.

As an example, suppose that the region size value equals the limit value, and a program issues a variable length GETMAIN with a maximum of (2 gigabytes – 1). If the GETMAIN is satisfied, all the space in the region up to the limit value will be allocated, and any subsequent GETMAIN that cannot be satisfied from free space in an existing subpool will cause the job to fail.

If, however, the region size value is less than the limit value, only space up to the region size value is allocated for the GETMAIN. Thus, an amount of space equal to the limit value minus the region size value remains for subsequent GETMAINS.

Note: For V=R jobs, the REGION parameter is more significant as a limiting value than are the limits set by IEFUSI. You can use the two factors together to control the region size for applications that must run V=R:

- Set the region size value where you want it, via IEFUSI.
- If a REGION parameter specification for a V=R job exceeds the region size value you have set, the job will not be initiated.

Coded Example of the Exit Routine

A sample IEFUSI exit routine is provided in SYS1.SAMPLIB in member IEEUSI. It sets the flag in the VSM parameter list indicating that it is controlling region sizes and limits instead of IEALIMIT. It is designed to perform the same processing as IEALIMIT in the control of region size and limit above and below the 16Mb line.

Chapter 34. IEFUSO – SYSOUT Limit Exit

Topics for This Exit Appear as Follows:

- [“Defining the Exit in SMFPRMxx” on page 205](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 205](#)
- [“Exit Routine Environment” on page 206](#)
- [“Exit Recovery” on page 206](#)
- [“Exit Routine Processing” on page 206](#)
- [“Programming Considerations” on page 206](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 207](#)
 - Registers at Entry
- [“Return Specifications” on page 207](#)
 - Registers at Exit

IEFUSO receives control from the job entry subsystem when the number of records written to an output data set exceeds the output limit for that data set. If the output limit is exceeded and your installation does not supply an IEFUSO exit routine, the job entry subsystem cancels the job. A return code from this exit indicates that the job is to be terminated or that the job should continue processing with a new output limit.

You can use IEFUSO to:

- Allow the job step to abend when a data set has exceeded its output limit.
- Inform the operator when a job exceeds its output limit for a data set and let the job continue processing.
- Extend output limits at the data set level for selected jobs.
- Keep a record of jobs that exceed output limits.
- Vary the handling of exceeding the output limit for different types of data sets or different types of jobs, such as teleprocessing, test, or production jobs.

Defining the Exit in SMFPRMxx

To allow the system to invoke IEFUSO, define the exit in the SMF parmlib member (SMFPRMxx). Specify IEFUSO on the EXITS option of the SUBSYS parameter for the STC subsystem. If your installation chooses not to define a SUBSYS parameter for STC, you can specify IEFUSO on the EXITS option of the SYS parameter.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFUSO installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFUSO or SYSyyy.IEFUSO. See the description of the SMFPRMxx parmlib member in [z/OS MVS Initialization and Tuning Reference](#) for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

To define IEFUSO to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for this exit, you need only define IEFUSO in SMFPRMxx.

The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFUSO in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFUSO).

If you associate exit routines with this exit in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Exit Routine Environment

IEFUSO receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 1 from JES3 and key 0 from JES2.
- In AMODE 31 (JES2) and in AMODE 24 or 31 (JES3). For the valid combinations of AMODE and RMODE, see [z/OS MVS Programming: Assembler Services Guide](#).

Exit Recovery

IBM strongly recommends that you set up an ESTAEX recovery routine to handle errors that might occur during the execution of IEFUSO.

An ESTAE-type recovery routine is set up by the module that calls IEFUSO; the recovery routine, if it gets control, will allow the job to continue processing if the exit routine abnormally ends.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

IEFUSO receives control from the job entry subsystem when the output limit for a data set is exceeded. The output limit is specified by the OUTLIM parameter on the DD statement defining the output data set. Note that the OUTLIM parameter limits output only to spooled data sets. See [z/OS MVS JCL User's Guide](#) and [z/OS MVS JCL Reference](#) for a description of this parameter.

IEFUSO has the information in the SMF common exit parameter area available to it. When the exit routine completes its processing, it sets a return code in register 15. This value indicates whether the job entry subsystem (JES) is to cancel the job or allow it to continue processing with an increased output limit specified by the exit routine. The value for the increment to be applied to the output limit is placed in register 1.

Programming Considerations

SMF provides a replaceable module for each SMF exit routine. If an installation includes IEFUSO, certain programming standards must be followed:

- The exit routine must follow standard linkage conventions.
- Code the exit routine reenterable and refreshable.
- If IEFUSO is entered for a foreground job, it cannot access installation-defined data sets. If the exit routine is entered for a background job, it cannot write to installation-defined data sets.

IEFUSO sets a return code in register 15 to indicate whether or not processing is to continue with a new output limit. The value of the increment to the output limit is placed in register 1. If you specify with the return code that the limit is to be increased (register 15=4), but you do not increase the limit (register 1=0), then IEFUSO will receive control again when the next record is written to the output data set.

Note: For information about changing output limits at the job level for started tasks, refer to the following:

- For JES2, Exit 9 - Job Output Overflow, see [z/OS JES2 Installation Exits](#).
- For JES3, Exit 29 - Examine the Accounting Information, see [z/OS JES3 Customization](#).

Macro Instructions and Restrictions: When issuing a WTOR macro, specify LONG=YES on the WAIT macro. Do not use a WTO with a routing code of 11 to send a message to the JESYSMSG data set for started tasks or TSO users.

Entry Specifications

The job entry subsystem provides IEFUSO with addressability to the SMF common exit parameter area.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Contains the address of the parameter list (See [Table 3 on page 141](#))

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of IEFUSO

Parameter Descriptions: Register 1 points to the following address:

Word 1

The address of the common exit parameter area (see [“Common Exit Parameter Area” on page 140](#)).



Figure 19. IEFUSO Input Parameter Structure

Return Specifications

A return code from IEFUSO indicates whether or not job processing is to continue.

If you associate multiple exit routines with IEFUSO, you can specify how the return information is to be handled using the ATTRIB KEEPRLC function of the SETPROG EXIT command, the EXIT statement of

PROGxx, or CSVODYNEX services. If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

If you associate multiple exit routines with exit IEFUSO, and any of those exit routines return with a value other than 4, job processing will not continue.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

**Register
Contents**

0

Restored to contents at entry

1

One of the following values:

- If R15=4, R1 contains the increment to the output limit.
- If R15 not=4, R1 restored to contents at entry.

2-14

Restored to contents at entry

15

One of the following return codes:

**Return Code
Explanation**

Value of 4

Continue processing the job. Increase the output limit by the value in register 1.

Value other than 4

Cancel the job.

Chapter 35. IEFUTL – Time Limit Exit

Topics for This Exit Appear as Follows:

- [“Defining the Exit in SMFPRMxx” on page 209](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 210](#)
- [“Exit Routine Environment” on page 210](#)
- [“Exit Recovery” on page 210](#)
- [“Exit Routine Processing” on page 211](#)
- [“Programming Considerations” on page 212](#)
- [“Entry Specifications” on page 212](#)
 - Registers at Entry
- [“Return Specifications” on page 213](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 214](#)

IEFUTL receives control from the system when one of the following time limits expires:

- Job processor time limit (from the JOB statement)
- Step processor time limit (from the EXEC statement or the default from the job entry subsystem)
- Continuous wait time limit for the job (from the SMFPRMxx JWT parameter). "Continuous wait time" is defined as time spent waiting while the application program is in control. For example, the time required to recall a data set from HSM Migration Levels 1 or 2 and/or the time required to mount a tape is counted towards the job's continuous wait time if the allocation of the data set is dynamic (that is, issued while the application program is running) while the time required for those activities is not counted toward the job's continuous wait time if the allocation is static (that is, for a DD statement). This is because static allocations occur under the initiator rather than under the application program.

If one of the above time limits is exceeded and your installation does not supply an IEFUTL exit routine, the system cancels the job. A return code from this exit indicates whether the job step is to be terminated or processing should continue with a new time limit.

You can use IEFUTL to:

- Allow the job step to abend.
- Inform the operator that a job has exceeded its continuous-wait-time limits.
- Extend processor time limits for selected jobs.
- Extend the wait time limit within a job.
- Keep a record of time limit expirations.
- Vary the handling of time limit expirations for different types of jobs, such as teleprocessing, test, or production jobs.

Defining the Exit in SMFPRMxx

In the SMF parmlib member (SMFPRMxx), specify IEFUTL on the EXITS option of either the SYS or SUBSYS parameters, depending on the scope of work (system-wide or subsystem-wide) the exit is to affect.

If you use the SUBSYS option, the system invokes the IEFUTL routine only for work running under the subsystems you specify on SUBSYS. If you use the SYS option, the system invokes the IEFUTL routine for work running under any SMF-defined subsystem, such as JES2, JES3, STC, ASCH, OMVS, or TSO.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFUTL installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFUTL or SYSyyy.IEFUTL. See the description of the SMFPRMxx parmlib member in [z/OS MVS Initialization and Tuning Reference](#) for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

To define IEFUTL to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for IEFUTL, you need only define this exit in SMFPRMxx.

The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFUTL in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFUTL).

If you associate exit routines with this exit in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Exit Routine Environment

IEFUTL receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 24 or 31. For the valid combinations of AMODE and RMODE, see [z/OS MVS Programming: Assembler Services Guide](#).
- In IRB mode as an asynchronous exit.

Exit Recovery

IBM strongly recommends that you set up an ESTAEX recovery routine to handle errors that might occur during the execution of IEFUTL.

An ESTAE-type recovery routine is set up by the module that calls IEFUTL. The recovery routine, if it gets control, will allow the job to continue processing if the exit routine abnormally ends.

Because the purpose of IEFUTL is to decide whether a step that has exceeded its allotted processor time or wait time should be abnormally terminated (the system default) or allowed to continue, be aware that the job WILL abend with the S322 or S522 it would have received if the exit routine had never gotten control.

Exit Routine Processing

Processor time is collected in two categories: execution under TCBs and execution under SRBs. The limiting function of IEFUTL applies only to such time under TCBs.

IEFUTL receives control when a time limit has expired. While IEFUTL is running, the application program continues to execute. (Note that this represents a change from MVS/XA and MVS/ESA up through release 4, wherein the system would suspend execution of an application program while IEFUTL was running.) This means, for example, that if IEFUTL issues a WTOR asking the operator whether to allow a job to continue executing or to cancel it, the job will, in fact, continue to execute while IEFUTL is waiting for the answer to the WTOR.

Depending on whether the expired time limit is a job, step, or continuous wait time limit, you can use the information in the SMF common exit parameter area to determine if processing should continue. The value of the time limit extension is either in seconds or in timer units, where 1 second = 38400 timer units. The smallest time extension granted is 2^{20} microseconds or 1.048576 seconds.

The time limit for the execution of a job step is specified by the job entry subsystem or by parameters on job control statements.

- If a job time limit is not specified on the JOB statement, the time limit for each job step is the value specified for the TIME=parameter on the EXEC statement, or the default value from the job entry subsystem.
- If a job time limit is specified on the JOB statement, the time limit for each job step is the remaining job time or the job step time limit (from the TIME=parameter or the job entry subsystem default), whichever is smaller.

You can extend execution time and wait time only within a step. Each extension resets the limit for the entire step to the extension value you specify.

The step execution and the wait time limits are re-initialized to the system default values at the beginning of each job step. Thus, unused extended execution time from one job step is not carried over for the next step.

An installation-written IEFUTL exit routine should control the number of extensions for a given step to prevent looping. It can record the expiration in the SMF data set or write a message to the console; however, in doing so, a system interlock could occur. (See [“Programming Considerations”](#) on page 212.)

z/OS UNIX MVS Address Space Processing: The following applies to address spaces that are z/OS UNIX MVS processes:

- If the time expiration is for a job or step time limit and IEFUTL exit processing indicates that the job step should be terminated, the system takes the following action:
 1. The system sends a SIGXCPU signal to the z/OS UNIX MVS process, and grants a small time extension to allow for SIGXCPU processing to occur. Applications can catch SIGXCPU signals and perform an orderly cleanup of the job or reset the CPU limit to a larger value.

Note: Processes can use the z/OS UNIX MVS **setrlimit** callable service to control CPU resource consumption. For information about z/OS UNIX MVS signals and the **setrlimit** callable service, see *z/OS UNIX System Services Programming: Assembler Callable Services Reference*.
 2. If the time extension for SIGXCPU processing expires, the system sends a SIGKILL signal to the z/OS UNIX MVS process and grants a small time extension to allow SIGKILL processing to occur. Applications cannot catch or ignore SIGKILL signals. SIGKILL signals provide for a more orderly shutdown of the application than an abend of the job step.
 3. If the time extension for SIGKILL processing expires, the system abends the job step.
- If the time expiration is for a job or step time limit and IEFUTL exit processing indicates that a time extension should be granted, the system grants the time extension.
- If the time expiration is for a continuous wait time limit and IEFUTL exit processing indicates that the job step should be terminated, the system abends the job step.

- If the time expiration is for a continuous wait time limit and IEFUTL exit processing indicates that a time extension should be granted, the system grants the time extension.

Programming Considerations

IEFUTL must be reenterable and refreshable, because PLPA pages are stolen. That is, they can be paged in but not paged out, and subsequent page-ins overlay any code changes.

IEFUTL can perform dynamic allocations and write to installation-defined data sets. In foreground jobs, data sets are allocated dynamically. For background jobs, you can either allocate data sets dynamically or you can pre-define (pre-allocate) a data set with a DD statement in the initiator cataloged procedure.

When issuing a WTOR macro, specify LONG=YES on the WAIT macro. Do not use a WTO with a routing code of 11 to send a message to the JESYSMSG data set for started tasks or TSO users. To provide a consistent environment for accessing and allocating data sets across calls to SMF exits for the duration of a job or task, IEFUTL receives control with the initiator's JSCB active.

If IEFUTL enqueues on any resource that the job task or any of its subtasks is enqueued on, the initiator ends abnormally. IEFUTL can, however, determine if a particular resource is held before issuing an ENQ (or invoking an SVC that issues an ENQ) by issuing an ENQ macro with RET=TEST. The macro must also specify the major and minor resource names in the QNAME and RNAME parameters. For example:

```
ENQ(QNAME,RNAME,E,3,SYSTEM),RET=TEST
```

Because SMF exits must be reentrant, be sure to use the execute form of the macro.

For more information on the ENQ macro, see [z/OS MVS Programming: Assembler Services Guide](#) and [z/OS MVS Programming: Assembler Services Reference ABE-HSP](#).

Entry Specifications

IEFUTL is passed the address of the SMF common exit parameter area and the type of time limit that expired to determine whether processing should continue.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

A binary code to indicate why the exit is taking control:

Binary Code

Explanation

0

The processor time limit for the job expired

4

The processor time limit for the step expired

8

The continuous wait time limit for the job expired

1

Address of the parameter list

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of IEFUTL

Parameter Descriptions: Register 1 points to the following list of addresses:

Word 1

The address of the common exit parameter area (see [“Common Exit Parameter Area”](#) on page 140).

Word 2

The address of a 4-character area that contains the name of the subsystem for the job being processed. Examples:

- ASCH, JES2, or JES3 - indicates the name of the subsystem that selected the job
- OMVS - indicates a forked or spawned address space
- STC - indicates a started task
- TSO - indicates a time sharing option task
- The jobname - used if it is four or fewer characters and none of the above apply

Note: The high-order bit is set in the address of the last parameter to indicate the end of the parameter list.




Figure 20. IEFUTL Input Parameter Structure

Return Specifications

If IEFUTL returns a code that indicates that processing should continue, then the time extension to be applied is returned in register 1.

If you associate multiple exit routines with IEFUTL, you can specify how the return information is to be handled using the ATTRIB KEEPRC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

If you associate multiple exit routines with exit IEFUTL, and any of those exit routines return with a value other than 4 or 8, job processing is cancelled.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0

Not applicable

1

Contains one of the following time extensions:

- If R15=4, R1 contains a time extension in timer units.
- If R15=8, R1 contains a time extension in seconds.

2-14

Not applicable

15

One of the following return codes:

Return Code**Explanation****4**

Job processing should be continued with a time extension in timer units.

8

Job processing should be continued with a time extension in seconds.

Other value

Job processing should be cancelled.

Coded Example of the Exit Routine

Sample IEFUTL exit routines are provided in SYS1.SAMPLIB in members SMFEXITS and IEEUTL. This routine terminates a job if either the job processor time limit or the job step processor time limit has been exceeded. If the continuous wait time limit for the job has been exceeded, the routine extends the limit twice; on the third entry for exceeding the continuous wait time limit, the routine cancels the job.

The continuous wait time limit is not an accumulation of all the time the task spends waiting, but rather a single continuous wait period that exceeds the specified limit.

Each time the routine is invoked for exceeding the continuous wait time limit, the routine writes a record to the SMF data set describing the action taken.

The IEEUTL exit routine is the SMF time limit exit. Since TSO sessions are handled like batch jobs, the SMF job wait limit and CPU time limits are enforced. This routine checks to see if the address space is a TSO session, and, if the CPU time is exceeded, issues a warning message to the terminal and grants a one-minute extension before the session is cancelled.

Chapter 36. IEFU29 – SMF Dump Exit

Topics for This Exit Appear as Follows:

- [“Defining the Exit in SMFPRMxx” on page 215](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 215](#)
- [“Exit Routine Environment” on page 216](#)
- [“Exit Recovery” on page 216](#)
- [“Exit Routine Processing” on page 216](#)
- [“Programming Considerations” on page 216](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 217](#)
 - Registers at Entry
- [“Return Specifications” on page 217](#)
 - Registers at Exit

The SMF dump exit IEFU29 is invoked when the current recording data set cannot hold any more records, since the SMF writer routine automatically switches recording from the active SMF data set to an empty SMF data set. This exit is also invoked when the writer switches recording data sets as a result of the SWITCH SMF command. A return code from this exit routine indicates whether a message that the SMF data set requires dumping should be suppressed or not.

You can use IEFU29 to:

- Issue the WTO macro to request that the operator start the dump program.
- Initiate the dump program by submitting a job request to an internal reader.

IEFU29 will also be invoked during SMF initialization for alternate data sets that are not empty.

Defining the Exit in SMFPRMxx

To allow the system to invoke IEFU29, define the exit in the SMF parmlib member (SMFPRMxx). Specify IEFU29 on the EXITS option of the SUBSYS parameter for the STC subsystem. If your installation chooses not to define a SUBSYS parameter for STC, you can specify IEFU29 on the EXITS option of the SYS parameter.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFU29 installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFU29 or SYSyyy.IEFU29. See the description of the SMFPRMxx parmlib member in [z/OS MVS Initialization and Tuning Reference](#) for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

To define IEFU29 to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for this exit, you need only define IEFU29 in SMFPRMxx.

The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFU29 in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFU29).

If you associate exit routines with this exit in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system does not disable the exit routine.

Exit Routine Environment

IEFU29 receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 24 or 31: When the SMF data set name is in the SYS1.MANx format.
- In AMODE 31: When the SMF data set name is in a format other than SYS1.MANx.
- In the SMF address space.

Exit Recovery

IBM strongly recommends that you set up an ESTAEX recovery routine to handle errors that might occur during the execution of IEFU29.

An ESTAE-type recovery routine is set up by the module that calls IEFU29; the recovery routine, if it gets control, will prevent SMF from ending if the exit routine abnormally ends.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

While the SMF writer records on one data set, the others can be written out (or cleared). As long as one inactive data set is empty when the active data set becomes full, the SMF writer continues to record. If none is available, no further recording takes place.

The SMF dump exit receives control from the SMF writer when an SMF data set becomes full. IEFU29 returns a code specifying that the control program either issue or suppress the dump message (IEE362A, IEE362I, IEE391A or IEE392I).

Programming Considerations

IEFU29 must be reenterable and refreshable because PLPA pages are stolen. That is, they can be paged in but not paged out, and subsequent page-ins overlay any code changes.

Note: IEFU29 runs in the SMF address space which runs under the MSTR subsystem rather than JES. Therefore, jobs submitted to the internal reader from IEFU29 will run under MSTR rather than JES. To have a job run under JES, you must request that the job run on JES rather than the MSTR subsystem. For more information on submitting a job request to an internal reader, see [*z/OS MVS Using the Subsystem Interface*](#).

Macro Instructions and Restrictions: IEFU29 can issue the WTOR macro (for example, to request the operator to start the dump program). When issuing the WTOR macro, specify LONG=YES on the WAIT macro.

IEFU29 cannot use the SMFWTM or SMFEWTM macro to write records to the SMF data set.

Entry Specifications

SMF passes to IEFU29 the address of the name of the SMF data set that requires dumping; see [Figure 21](#) on page 217.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

0	Not applicable
1	Address of the name of the SMF data set
2-12	Not applicable
13	Register save area
14	Return address
15	Entry point address of IEFU29

Parameter Descriptions: Register 1 points to the following address:

Word 1

The address of the 44-character field that contains the name of the SMF data set that requires dumping. This field is left-justified and padded on the right with blanks.




Figure 21. IEFU29 Input Parameter Structure

Return Specifications

A return code from IEFU29 indicates whether the dump message (IEE362A, IEE362I, IEE391A or IEE392I) is to be issued.

If you associate multiple exit routines with IEFU29, you can specify how the return information is to be handled using the ATTRIB KEEPRC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

If you associate multiple exit routines with exit IEFU29, and any of those exit routines return with a value of 4, the dump message (IEE362A, IEE362I, IEE391A or IEE392I) is not issued.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0-14

Not applicable

15

One of the following return codes:

Return Code

Explanation

4

Indicates that the dump message (IEE362A, IEE362I, IEE391A or IEE392I) is not to be issued.

Other than 4

The message is to be written.

Coded Example of the Exit Routine

A sample IEFU29 exit is provided in the IEEU29 member of SYS1.SAMPLIB. The sample exit issues an SVC34 to start DUMPXY, and it issues a WTO to inform the operator that the command has been issued. To run this exit, the DUMPXY procedure must be provided by the installation. For more information, see [Using IFASMFDP - the SMF data set dump program in z/OS MVS System Management Facilities \(SMF\)](#).

Chapter 37. IEFU29L — SMF Log Stream Dump Exit

Topics for This Exit Appear as Follows:

- [“Defining the Exit in SMFPRMxx” on page 219](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 219](#)
- [“Exit Routine Environment” on page 220](#)
- [“Exit Recovery” on page 220](#)
- [“Exit Routine Processing” on page 220](#)
- [“Programming Considerations” on page 220](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 221](#)
 - Registers at Entry
- [“Return Specifications” on page 221](#)
 - Registers at Exit

The SMF dump exit IEFU29L allows you to initiate the archiving of SMF data from a log stream. IEFU29L is invoked using the SWITCH SMF command.

Note that you can use the system logger to manage how long you retain the SMF log stream data and to automatically offload the log stream data to VSAM linear DASD data sets, so you might not need to use IEFU29L to drive the archiving of the SMF log stream data. See [Managing log data: How much? For how long?](#) in *z/OS MVS Setting Up a Sysplex*.

Use IEFU29L to perform the following tasks:

- Issue the WTO macro to request that the operator start the SMF log stream dump program, IFASMF DL.
- Initiate the dump program by submitting a job request to an internal reader.

Defining the Exit in SMFPRMxx

To allow the system to invoke IEFU29L, define the exit in the SMF parmlib member (SMFPRMxx). Specify IEFU29L on the EXITS option of the SUBSYS parameter for the STC subsystem. If your installation chooses not to define a SUBSYS parameter for STC, you can specify IEFU29L on the EXITS option of the SYS parameter.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFU29L installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFU29L or SYSyyy.IEFU29L. See the description of the SMFPRMxx parmlib member in *z/OS MVS Initialization and Tuning Reference* for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

To define IEFU29L to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for this exit, you only need to define IEFU29L in SMFPRMxx.

The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFU29L in PROGxx, by default, the system uses the exit routine name that matches the exit name (IEFU29L).

If you associate exit routines with this exit in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times that the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error.
- The system allows a retry, that is, the recovery routine is entered with the bit SDWACLUP off.

By default, the system does not disable the exit routine.

Exit Routine Environment

IEFU29L receives control in the following environment:

- Enabled for interruptions.
- In supervisor state with PSW key 0.
- In AMODE 24 or 31.
- In the SMF address space.

Exit Recovery

IBM suggests that you set up an ESTAEX recovery routine to handle errors that might occur during the execution of IEFU29L.

An ESTAE-type recovery routine is set up by the module that calls IEFU29L; if the recovery routine gets control, it prevents SMF from ending when the exit routine ends abnormally.

Whether the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

The SMF dump exit receives control from the SMF writer when the SWITCH SMF command is issued to dump data from an SMF log stream.

Programming Considerations

IEFU29L must be reenterable and refreshable because PLPA pages are stolen. That is, they can be paged in but not paged out, and subsequent page-ins overlay any code changes.

Note: IEFU29L runs in the SMF address space that runs under the MSTR subsystem rather than JES. Therefore, jobs submitted to the internal reader from IEFU29L runs under MSTR rather than JES. To have a job run under JES, you must request that the job run on JES rather than the MSTR subsystem. For more information about submitting a job request to an internal reader, see [z/OS MVS Using the Subsystem Interface](#).

Macro Instructions and Restrictions: IEFU29L can issue the WTOR macro (for example, to request the operator to start the dump program). When you issue the WTOR macro, specify LONG=YES on the WAIT macro.

IEFU29L cannot use the SMFWTM or SMFEWTM macro to write records to the SMF log stream.

Entry Specifications

SMF passes to IEFU29L a parameter list mapped by IEFU29LM, which contains the name of the log stream.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of a pointer to a parameter list of IEFU29L, mapped by the IFAU29LM control block

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of IEFU29L

Parameter Descriptions: When IEFU29L is driven, control block IEFU29LM receives Register 1, which points to the following address. [Figure 22 on page 221](#) shows an example of input parameter structure.

Word 1

An array of pointers, each of which point to U29L_PARM mapped in IFAU29LM. The high order bit of the pointer signifies that it is the last one.




Figure 22. IEFU29L Input Parameter Structure

Return Specifications

No return information is expected.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-15

Not applicable

Coded Example of the Exit Routine

The SMF Logstream Mode: Optimizing the New Paradigm (www.redbooks.ibm.com/abstracts/sg247919.html) publication provides an example for this exit in Appendix E. Because IBM currently does not provide a sample IEFU29L exit, it is included in this book. The sample exit consists of an Assembler stub that calls a REXX program, passing the names of the log streams as parameters. The sample REXX program simply returns the log stream names to the console, but you can modify it as you require. Example E-6 shows a sample of the output.

Chapter 38. IEFU83 – SMF Record Exit

Topics for This Exit Appear as Follows:

- [“Defining the Exit in SMFPRMxx” on page 223](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 224](#)
- [“Exit Routine Environment” on page 224](#)
- [“Exit Recovery” on page 224](#)
- [“Exit Routine Processing” on page 225](#)
- [“Programming Considerations” on page 225](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 225](#)
 - Registers at Entry
- [“Return Specifications” on page 226](#)
 - Registers at Exit

The IEFU83 exit receives control only when SMF is processing a record that contains a standard header. It does not receive control when SMF is processing a record that contains an extended header. See the *Standard and Extended SMF record headers* section in [z/OS MVS System Management Facilities \(SMF\)](#) for details.

The SMF record exit IEFU83 receives control when the caller invokes either:

- The SMFWTM macro.
- The SMFEWTM macro and specifies BRANCH=NO.

After exit routine processing, IEFU83 returns a code that specifies whether SMF is to write the SMF record to the SMF data set. IEFU83 does not receive control for records whose writing has been suppressed either because of a system failure or because of options selected at IPL time or via the SET SMF command.

You can use IEFU83 to:

- Select or suppress those records to be written to the SMF data set. For example, an installation with a large TSO/E account might want to suppress the SMF dynamic DD records (type 40).
- Check resource use during a specific interval. For example, select records during the peak workload period.

Defining the Exit in SMFPRMxx

In the SMF parmlib member (SMFPRMxx), specify IEFU83 on the EXITS option of either the SYS or SUBSYS parameters, depending on the scope of work (system-wide or subsystem-wide) the exit is to affect.

If you use the SUBSYS option, the system invokes the IEFU83 routine only for work running under the subsystems you specify on SUBSYS. If you use the SYS option, the system invokes the IEFU83 routine for work running under any SMF-defined subsystem, such as JES2, JES3, STC, ASCH, OMVS, or TSO.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFU83 installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFU83 or SYSyyy.IEFU83. See the description of the SMFPRMxx parmlib member in *z/OS MVS Initialization and Tuning Reference* for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

To define IEFU83 to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for this exit, you need only define IEFU83 in SMFPRMxx.

If you do not associate any exit routines with exit IEFU83 in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFU83).

If you associate exit routines with this exit in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system disables the exit routine after two consecutive abends.

Exit Routine Environment

IEFU83 receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 31.

Exit Recovery

If IEFU83 abnormally terminates, SMF, in most cases, does not terminate. SMF deactivates the exit and then issues message CSV430I to the operator. If the exit performs a critical function, the operator can issue a SET SMF or SETSMF command to terminate recording. Otherwise, SMF recording continues but bypasses the installation exit routine.

IBM strongly recommends that you set up an ESTAE recovery routine to handle errors that might occur during the execution of your exit routine.

An ESTAE-type recovery routine is set up by the module that calls IEFU83; the recovery routine, if it gets control, will prevent SMF from ending if the exit routine abnormally ends. If this recovery routine gets control on two consecutive invocations of the exit, SMF requests that the exit routine be marked inactive, preventing any further invocations of that exit routine. The system issues message CSV430I, naming the exit and the exit routine.

If the exit performs a critical function, the operator can issue a SET PROG or SETPROG MODIFY command to change the status of the exit to active. This should be done only if you have corrected the program, or if you know the error conditions are transient.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

Each SMF record is passed to an installation exit (either IEFU83, IEFU84, or IEFU85) before it is written to the SMF data set. If you use the SMFWTM macro, or if you specify BRANCH=NO on the SMFEWTM macro, SMF invokes installation exit IEFU83. If you use the SMFEWTM macro and specify BRANCH=YES, SMF invokes installation exit IEFU84.

IEFU83 places a return code in register 15 before returning control; the code indicates whether the record should be written to the SMF data set.

Programming Considerations

IEFU83 must be reenterable and refreshable, because PLPA pages are stolen. That is, they can be paged in but not paged out, and subsequent page-ins overlay any code changes.

If IEFU83 is entered for a foreground job, it cannot access installation-defined data sets. If the exit is entered for a background job, it cannot write to installation-defined data sets.

The addresses of the user communication and user identification fields of the common exit parameter area (a copy of the first 36 bytes of the JMR) are not passed to the IEFU83 exit routine. To obtain these addresses, the exit routine can follow pointers from the PSA to the TCB to the JMR. In the PSA, the PSATOLD points to the TCB. In the TCB, the TCBTCT field points to the TCT. In the TCT, the TCTJMR field points to the JMR. The JMR and the PSA are mapped by macro IEFJMR and IHAPSA, respectively. See *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the mapping of the JMR and the mappings of the TCB and the TCT.

APPC/MVS Consideration: You might want your exit routine to perform specific processing for work initiated by the APPC/MVS transaction scheduler. To enable your exit routine to determine when it has been invoked during this type of processing, have the routine check the OUCBSUBN field in the OUCB control block. For APPC/MVS TPs, this field is set to 'ASCH' (EBCDIC).

The exit routine can access OUCBSUBN by chaining through pointers from the PSA to the ASCB to the OUCB. In the PSA, the PSAAOLD points to the ASCB. In the ASCB, the ASCBOUCB field points to the OUCB.

The ASCB, OUCB, and the PSA are mapped by macros IHAASCB, IRAOUCB, and IHAPSA, respectively. The mappings are described in *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Macro Instructions and Restrictions: When issuing a WTOR macro, specify LONG=YES on the WAIT macro.

IEFU83 cannot use the SMFWTM or SMFEWTM macro to write to the SMF data set.

Entry Specifications

SMF passes to IEFU83 the address of a fullword that points to the SMF record.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

0

Not applicable

1

Address of the parameter list.

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of IEFU83

Parameter Descriptions: Register 1 points to the following address:**Word 1**

The address of the record that SMF is to write. The first four bytes of this record are the record descriptor word (RDW). See [z/OS MVS System Management Facilities \(SMF\)](#) for a description of the RDW.




Figure 23. IEFU83 Input Parameter Structure

Return Specifications

A return code from IEFU83 indicates whether the current SMF record is to be suppressed.

If you associate multiple exit routines with IEFU83, you can specify how the return information is to be handled using the ATTRIB KEEP RC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEP RC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEP RC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

If you associate multiple exit routines with exit IEFU83, and any of those exit routines return with a value of 4, the current SMF record is suppressed.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

1

Not applicable

2-14

Not applicable

15

One of the following return codes:

Return Code Explanation

4

SMF is not to write the record to the SMF data set.

Other than 4

SMF is to write the record to the SMF data set.

Chapter 39. IEFU84 – SMF Record Exit

Topics for This Exit Appear as Follows:

- [“Defining the Exit in SMFPRMxx” on page 227](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 227](#)
- [“Exit Routine Environment” on page 228](#)
- [“Exit Recovery” on page 228](#)
- [“Exit Routine Processing” on page 229](#)
- [“Programming Considerations” on page 229](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 229](#)
 - Registers at Entry
- [“Return Specifications” on page 230](#)
 - Registers at Exit

The IEFU84 exit receives control only when SMF is processing a record that contains a standard header. It does not receive control when SMF is processing a record that contains an extended header. See the *Standard and Extended SMF record headers* section in [z/OS MVS System Management Facilities \(SMF\)](#) for details.

The SMF record exit IEFU84 receives control when the caller invokes the SMFEWTM macro, specifying BRANCH=YES. After exit routine processing, IEFU84 returns a code that specifies whether the SMF record should be written to the SMF data set. The SMFEWTM macro allows the issuer to branch directly to the SVC routine without issuing the SVC. IEFU84 does not receive control for records suppressed because of options selected at IPL time or via the SET SMF command.

You can use IEFU84 to:

- Select or suppress those records to be written to the SMF data set. For example, an installation with a large TSO/E account might want to suppress SMF records for all but a few selected TSO/E users.
- Check resource use during a specific interval. For example, select records during the peak workload period.
- Suppress some of the record type 30 subtypes.

Defining the Exit in SMFPRMxx

In the SMF parmlib member (SMFPRMxx), specify IEFU84 on the EXITS option of either the SYS or SUBSYS parameters, depending on the scope of work (system-wide or subsystem-wide) the exit is to affect.

If you use the SUBSYS option, the system invokes the IEFU84 routine only for work running under the subsystems you specify on SUBSYS. If you use the SYS option, the system invokes the IEFU84 routine for work running under any SMF-defined subsystem, such as JES2, JES3, STC, ASCH, OMVS, or TSO.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFU84 installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFU84 or SYSyyy.IEFU84. See the description of the SMFPRMxx parmlib member in [z/OS MVS](#)

Initialization and Tuning Reference for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

To define IEFU84 to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for this exit, you need only define IEFU84 in SMFPRMxx.

The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFU84 in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFU84).

If you associate exit routines with this exit in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system disables the exit routine after two consecutive abends.

Exit Routine Environment

IEFU84 receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 31.
- In the address space of the task that issues the SMFEWTM BRANCH=YES macro.
- Can be locked or in SRB mode.

Exit Recovery

If IEFU84 abnormally terminates, SMF, in most cases, does not terminate. SMF marks the exit as not valid and issues message IEE952I to the operator. If the exit performs a critical function, the operator can issue a SET SMF or SETSMF command to terminate recording. Otherwise, SMF recording continues but bypasses the installation exit routine.

IBM strongly recommends that you set up an FRR recovery routine to handle errors that might occur during the execution of your exit routine. The FRR should use the EUT=YES option to handle errors that occur when the exit is called in unlocked task mode.

An FRR is set up by the module that calls IEFU84; the recovery routine, if it gets control, will prevent SMF from ending if the exit routine abnormally ends. If this recovery routine gets control on two consecutive invocations of the exit, SMF requests that the exit routine be marked inactive, preventing any further invocations of that exit routine. The system issues message CSV430I, naming the exit and the exit routine.

If the exit performs a critical function, the operator can issue a SET PROG or SETPROG MODIFY command to change the status of the exit to active. This should be done only if you have corrected the program, or if you know the error conditions are transient.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

Each SMF record is passed to an installation exit (either IEFU83, IEFU84 or IEFU85) before it is written to the SMF data set. If you use the SMFEWMT macro and specify BRANCH=YES, SMF invokes installation exit IEFU84. If you use the SMFWMT macro or if you specify BRANCH=NO on the SMFEWMT macro, SMF invokes installation exit IEFU83.

The SMFEWMT macro verifies that SMF recording is active and allows the issuer to branch directly to the SVC routine without issuing the SVC. BRANCH=YES causes the macro to generate a call to the subroutine that moves the data to the SMF buffer.

IEFU84 places a return code in register 15 before returning control; the code indicates whether the record is to be written to the SMF data set.

Programming Considerations

IEFU84 must be reenterable and refreshable, because PLPA pages are stolen. That is, they can be paged in but not paged out, and subsequent page-ins overlay any code changes.

IEFU84 cannot access installation-defined data sets.

The addresses of the user communication and user identification fields of the common exit parameter area (a copy of the first 36 bytes of the JMR) are not passed to the IEFU84 exit routine. To obtain these addresses, the exit routine can follow pointers from the ASXB to the TCB to the JMR. In the ASXB, the ASXBLTCB points to a chain of TCBs. The ASXB can be found from the field ASCBASXB in the ASCB which in turn can be found from the PSAAOLD in the PSA.

In the TCB, the TCBTCT field points to the TCT. In the TCT, the TCTJMR field points to the JMR. The JMR and the PSA are mapped by macros IEFJMR and IHAPSA, respectively. See *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the mapping of the JMR, and *z/OS MVS Data Areas, Vol 5 (SSAG-XTLST)* for the mappings of the TCB and the TCT.

Note: If you use the ASXBLTCB, this would only be the LAST TCB that was attached in the address space, and would not necessarily be running, or even dispatchable. You would have determine that by looking at the dispatchability bits in the TCB. Or you could start with the ASXBFTCB, which will point to the Region Control Task's TCB, and chain down from that using the TCBTCB field.

APPC/MVS Consideration: You might want your exit routine to perform specific processing for work initiated by the APPC/MVS transaction scheduler. To enable your exit routine to determine when it has been invoked during this type of processing, have the routine check the OUCBSUBN field in the OUCB control block. For APPC/MVS TPs, this field is set to 'ASCH' (EBCDIC).

The exit routine can access OUCBSUBN by chaining through pointers from the PSA to the ASCB to the OUCB. In the PSA, the PSAAOLD points to the ASCB. In the ASCB, the ASCBOUCB field points to the OUCB.

The ASCB, OUCB, and the PSA are mapped by macros IHAASCB, IRAOUCB, and IHAPSA, respectively. The mappings are described in *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Macro Instructions and Restrictions: When issuing a WTOR macro, specify LONG=YES on the WAIT macro.

IEFU84 cannot use the SMFWMT or SMFEWMT macro to write to the SMF data set.

Because IEFU84 might be locked or in SRB mode, the exit routine cannot issue any SVCs. IEFU83 may be given the alias name IEFU84, if IEFU83 can run locked or SRB mode.

Entry Specifications

SMF passes to IEFU84 the address of a fullword that points to the SMF record.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

**Register
Contents**

- 0**
Not applicable
- 1**
Address of the parameter list
- 2-12**
Not applicable
- 13**
Register save area
- 14**
Return address
- 15**
Entry point address of IEFU84

Parameter Descriptions: Register 1 points to the following address:

Word 1

The address of the record that SMF is to write. The first four bytes of this record are the record descriptor word (RDW). See *z/OS MVS System Management Facilities (SMF)* for a description of the RDW.




Figure 24. IEFU84 Input Parameter Structure

Return Specifications

A return code from IEFU84 indicates whether the current SMF record is to be suppressed.

If you associate multiple exit routines with IEFU84, you can specify how the return information is to be handled using the ATTRIB KEEPRC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

If you associate multiple exit routines with exit IEFU84, and any of those exit routines return with a value of 4, the system does not write the record to the SMF data set.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

**Register
Contents**

- 0-14**
Same as at entry
- 15**
One of the following return codes:

**Return Code
Explanation**
Value of 4

SMF is not to write the record to the SMF data set.

Other than 4

SMF is to write the record to the SMF data set.

Chapter 40. IEFU85 – SMF Record Exit

Topics for This Exit Appear as Follows:

- [“Defining the Exit in SMFPRMxx” on page 233](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 234](#)
- [“Exit Routine Environment” on page 234](#)
- [“Exit Recovery” on page 234](#)
- [“Exit Routine Processing” on page 235](#)
- [“Programming Considerations” on page 235](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 235](#)
 - Registers at Entry
- [“Return Specifications” on page 236](#)
 - Registers at Exit

The IEFU85 exit receives control only when SMF is processing a record that contains a standard header. It does not receive control when SMF is processing a record that contains an extended header. See the *Standard and Extended SMF record headers* section in [z/OS MVS System Management Facilities \(SMF\)](#) for details.

The SMF record exit IEFU85 is used for a caller who is running in cross memory mode. The exit routine receives control when the caller invokes the SMFEWMTM macro, specifying BRANCH=YES and MODE=XMEM and when ASCB does not equal PSAAOLD (the home primary ASID). After exit routine processing, IEFU85 returns a code that specifies whether the SMF record should be written to the SMF data set. The SMFEWMTM macro allows the issuer to branch directly to the SVC routine without issuing the SVC. IEFU85 does not receive control for records that are suppressed because of options selected at IPL time or via the SET SMF command.

You can use IEFU85 to:

- Select or suppress those records to be written to the SMF data set. For example, an installation with a large TSO/E account might want to suppress SMF records for all but a few selected TSO/E users.
- Check resource use during a specific interval. For example, select records during the peak workload period.

Defining the Exit in SMFPRMxx

In the SMF parmlib member (SMFPRMxx), specify IEFU85 on the EXITS option of either the SYS or SUBSYS parameters, depending on the scope of work (system-wide or subsystem-wide) the exit is to affect.

If you use the SUBSYS option, the system invokes the IEFU85 routine only for work running under the subsystems you specify on SUBSYS. If you use the SYS option, the system invokes the IEFU85 routine for work running under any SMF-defined subsystem, such as JES2, JES3, STC, ASCH, OMVS, or TSO.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

IBM has defined the IEFU85 installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFU85 or SYSyyy.IEFU85. See the description of the SMFPRMxx parmlib member in *z/OS MVS Initialization and Tuning Reference* for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

To define IEFU85 to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for this exit, you need only define IEFU85 in SMFPRMxx.

The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFU85 in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFU85).

If you associate exit routines with this exit in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

You can use the ADDABENDNUM and ABENDCONSEC parameters on the CSVDYNEX REQUEST=ADD macro or the ABENDNUM parameter of the SETPROG EXIT operator command to limit the number of times the exit routine abnormally ends before it becomes inactive. An abend is counted when both of the following conditions exist:

- The exit routine does not provide recovery, or the exit routine does provide recovery but percolates the error
- The system allows a retry; that is, the recovery routine is entered with bit SDWACLUP off.

By default, the system disables the exit routine after two consecutive abends.

Exit Routine Environment

IEFU85 receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 31.
- In the address space of the task that issues the SMFEWMTM BRANCH=YES MODE=XMEM macro.
- May be locked.
- In cross memory mode.

Exit Recovery

If IEFU85 abnormally terminates, SMF, in most cases, does not terminate. SMF marks the exit as not valid and issues message IEE952I to the operator. If the exit performs a critical function, the operator can issue a SET SMF or SETSMF command to terminate recording. Otherwise, SMF recording continues but bypasses the installation exit routine.

A functional recovery routine (FRR) is set up by IEEMB830 (the SVC 83 routine) because the caller is in cross memory mode.

IBM strongly recommends that you set up an FRR recovery routine to handle errors that might occur during the execution of your exit routine.

An FRR is set up by the module that calls IEFU85; the recovery routine, if it gets control, will prevent SMF from ending if the exit routine abnormally ends. If this recovery routine gets control on two consecutive invocations of the exit, SMF requests that the exit routine be marked inactive, preventing any further invocations of that exit routine. The system issues message CSV430I, naming the exit and the exit routine.

If the exit performs a critical function, the operator can issue a SET PROG or SETPROG MODIFY command to change the status of the exit to active. This should be done only if you have corrected the program, or if you know the error conditions are transient.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit Routine Processing

Each SMF record is passed to an installation exit (either IEFU83, IEFU84, or IEFU85) before it is written to the SMF data set. If you use the SMFEWMT macro and specify BRANCH=YES MODE=XMEM, SMF invokes installation exit IEFU85.

The SMFEWMT macro verifies that SMF recording is active and allows the issuer to branch directly to the SVC routine without issuing the SVC. BRANCH=YES causes the macro to generate a call to the subroutine that moves the data to the SMF buffer.

IEFU85 places a return code in register 15 before returning control; the code indicates whether the record is to be written to the SMF data set.

Programming Considerations

IEFU85 must be reenterable and refreshable, because PLPA pages are stolen. That is, PLPA pages can be paged in but not paged out, and subsequent page-ins overlay any code changes.

IEFU85 cannot access installation-defined data sets.

Because IEFU85 is running in cross-memory mode, the exit routine cannot issue any SVCs.

The addresses of the user communication and user identification fields of the common exit parameter area (a copy of the first 36 bytes of the JMR) are not passed to the IEFU85 exit routine. To obtain these addresses, the exit routine can follow pointers from the PSA to the TCB to the JMR. In the PSA, the PSATOLD points to TCB. In the TCB, the TCBTCT field points to the TCT. In the TCT, the TCTJMR field points to the JMR. The JMR and the PSA are mapped by macros IEFJMR and IHAPSA, respectively. See *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the mapping of the JMR, and *z/OS MVS Data Areas, Vol 5 (SSAG-XTLST)* for the mappings of the TCB and the TCT.

APPC/MVS Consideration: You might want your exit routine to perform specific processing for work initiated by the APPC/MVS transaction scheduler. To enable your exit routine to determine when it has been invoked during this type of processing, have the routine check the OUCBSUBN field in the OUCB control block. For APPC/MVS TPs, this field is set to 'ASCH' (EBCDIC).

The exit routine can access OUCBSUBN by chaining through pointers from the PSA to the ASCB to the OUCB. In the PSA, the PSAAOLD points to the ASCB. In the ASCB, the ASCBOUCB field points to the OUCB.

The ASCB, OUCB, and the PSA are mapped by macros IHAASCB, IRAOUCB, and IHAPSA, respectively. The mappings are described in *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Macro Instructions and Restrictions: IEFU85 can issue only macros that can run in cross-memory mode. See the macro summary in *z/OS MVS Programming: Assembler Services Reference ABE-HSP* for information on macros that can run in cross-memory mode.

IEFU85 cannot use the SMFWMT or SMFEWMT macro to write to the SMF data set.

Entry Specifications

SMF passes to IEFU85 the address of a fullword that points to the SMF record.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

**Register
Contents**

- 0**
Not applicable
- 1**
Address of the parameter list.
- 2-12**
Not applicable
- 13**
Register save area
- 14**
Return address
- 15**
Entry point address of IEFU85

Parameter Descriptions: Register 1 points to the following address:

Word 1

The address of the record that SMF is to write. The first four bytes of this record are the record descriptor word (RDW). See *z/OS MVS System Management Facilities (SMF)* for a description of the RDW.




Figure 25. IEFU85 Input Parameter Structure

Return Specifications

A return code from IEFU85 indicates whether the current SMF record is to be suppressed.

If you associate multiple exit routines with IEFU85, you can specify how the return information is to be handled using the ATTRIB KEEPRC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first will be returned.

If you associate multiple exit routines with exit IEFU85, and any of those exit routines return with a value of 4, the current SMF record is suppressed.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

**Register
Contents**

- 0-14**
Same as at entry
- 15**
One of the following return codes:

**Return Code
Explanation**
Value of 4

SMF is not to write the record to the SMF data set.

Other than 4

SMF is to write the record to the SMF data set.

Chapter 41. IEFU86 – SMF record exit

Topics for this exit appear as follows:

- [Defining the Exit in SMFPRMxx](#)
- [Controlling the Exit Routine Through the Dynamic Exits Facility](#)
- [Exit Recovery](#)
- [Exit Routine Environment](#)
- [Exit Routine Processing](#)
- [Programming Considerations](#)
- [Entry Specifications](#)
 - [Registers at Entry](#)
- [Parameter Descriptions](#)
 - [Input Parameter Structure](#)
 - [Work Area](#)
- [Return Specifications](#)
 - [Registers at Exit](#)
- [Recovery Considerations](#)

The IEFU86 exit receives control for SMF records with either standard or extended headers. See the *Standard and Extended SMF record headers* section in [z/OS MVS System Management Facilities \(SMF\)](#) for details.

IEFU86 receives control when the caller invokes the SMFWTM or SMFEWTM macros. Unlike the IEFU83, IEFU84, and IEFU85 exits, IEFU86 receives control regardless of the mode of the caller or the SMFWTM or SMFEWTM invocation parameters.

After exit routine processing, IEFU86 returns a code that specifies whether SMF is to write the SMF record to the SMF data set. IEFU86 does not receive control for records whose writing has been suppressed either because of a system failure or because of SMFPRMxx options selected at IPL time or through the SET SMF command.

You can use IEFU86 to:

- Select or suppress those records to be written to the SMF data set or log stream. For example, an installation with a large TSO/E account might want to suppress the SMF dynamic DD records (type 40).
- Check resource use during a specific interval. For example, select records during the peak workload period.

Defining the exit in SMFPRMxx

In the SMF parmlib member (SMFPRMxx), specify IEFU86 on the EXITS option of either the SYS or SUBSYS parameters, depending on the scope of work (system-wide or subsystem-wide) the exit is to affect.

If you use the SUBSYS option, the system invokes the IEFU86 routine only for work running under the subsystems you specify on SUBSYS. If you use the SYS option, the system invokes the IEFU86 routine for work running under any SMF-defined subsystem, such as JES2, JES3, STC, ASCH, OMVS, or TSO.

For more information about coding the EXITS option, see the description of SMFPRMxx in [z/OS MVS Initialization and Tuning Reference](#).

Controlling the exit routine through the dynamic exits facility

IBM has defined the IEFU86 installation exit to the dynamic exits facility. You can refer to the exit by the name SYS.IEFU86 or SYSyyy.IEFU86. See the description of the SMFPRMxx parmlib member in *z/OS MVS Initialization and Tuning Reference* for an explanation of the naming conventions for SMF exit routines. You can use the EXIT statement of the PROGxx parmlib member, the SETPROG EXIT operator command, or the CSVDYNEX macro to control this exit and its exit routines.

To define IEFU86 to the dynamic exits facility, you must specify the exit in both PROGxx and SMFPRMxx. The system does not call the exit if it is defined in PROGxx only. If you do not plan to use the dynamic exits facility for this exit, you need only define IEFU86 in SMFPRMxx.

The exit routine should reside in LPA, the LNKST concatenation, or the nucleus. Do not use the DSNAME keyword when adding the exit routine in PROGxx.

If you do not associate any exit routines with exit IEFU86 in PROGxx, the system defaults to using the exit routine name that matches the exit name (IEFU86).

If you associate exit routines with this exit in PROGxx, the system does not use the default exit routine. If you need the default exit routine, you should explicitly add it to PROGxx.

Exit recovery

If IEFU86 abnormally terminates, SMF, in most cases, does not terminate. SMF marks the exit as not valid and issues message IEE952I to the operator. If the exit performs a critical function, the operator can issue a SET SMF or SETSMF command to terminate recording. Otherwise, SMF recording continues but bypasses the installation exit routine.

The caller of the exit will establish recovery. If it gets control, it will prevent SMF from ending if the exit routine abnormally ends. If this recovery routine gets control on two consecutive invocations of the exit, SMF requests that the exit routine be marked inactive, preventing any further invocations of that exit routine. In the case that an exit is marked as inactive, the system issues message CSV430I, naming the exit and the exit routine.

IBM strongly recommends that you set up a recovery routine to handle errors that might occur during the execution of your exit routine. The recovery routine should be appropriate for the environment in which the exit is invoked. The environment is described in the IFAEXITP parameter list that is provided to the exit:

- When the SMXP_IEFU86_SVC bit is set in the IFAEXITP parameter list, SMF establishes ESTAE-type recovery prior to calling the exit. In this case, it is sufficient for the exit to establish ESTAE-type recovery, although an FRR using the EUT=YES option may also be used.
- When the SMXP_IEFU86_BR_XMEM bit is set, SMF establishes FRR-type recovery. In this case, the exit should also establish FRR-type recovery using the EUT=YES option.
- When the SMXP_IEFU86_BR_NXMEM bit is set, SMF also establishes FRR-type recovery prior to calling the exit. In this case, the exit should also establish FRR-type recovery. The EUT=YES option can be used but is not necessary.

If the exit is marked inactive and it performs a critical function, the operator can issue a SET PROG or SETPROG MODIFY command to change the status of the exit to active. This should be done only if you have corrected the program or if you know that the error conditions are transient.

Whether or not the exit routine continues to be invoked depends on the abend processing of the dynamic exits facility.

Exit routine environment

IEFU86 receives control in the address space of the program that called the SMFWTM or SMFEWTM service. Following is a description of the environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.

- In AMODE 31.
- Task or SRB mode.
- Can be invoked in cross memory mode.
- Can be holding the local lock.

See the IFAEXITP parameter list map for more information about how the exit was called.

Exit routine processing

Each SMF record is passed to IEFU86 before it is written to the SMF data set or log stream. The exit receives control for SMF records with either standard or extended headers. The exit receives control regardless of whether SMFWTM or SMFEWTM was used to write the record, and regardless of the parameters used on the calls.

IEFU86 places a return code in register 15 before returning control; the code indicates whether the record is to be written to the SMF data set or log stream.

Programming considerations

APPC/MVS consideration:

You might want your exit routine to perform specific processing for work initiated by the APPC/MVS transaction scheduler. To enable your exit routine to determine when it has been invoked during this type of processing, have the routine check the OUCBSUBN field in the OUCB control block. For APPC/MVS TPs, this field is set to 'ASCH' (EBCDIC).

The exit routine can access OUCBSUBN by chaining through pointers from the PSA to the ASCB to the OUCB. In the PSA, the PSAAOLD points to the ASCB. In the ASCB, the ASCBOUCB field points to the OUCB.

The ASCB, OUCB, and the PSA are mapped by macros IHAASCB, IRAOUCB, and IHAPSA, respectively. The mappings are described in *z/OS MVS Data Areas* under *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Entry specifications

SMF passes to IEFU86 a parameter area that is mapped by the IFAEXITP mapping macro.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable.

1

Address of the parameter area. See [Parameter Descriptions](#) for more details.

2-12

Not applicable.

13

Register save area

14

Return address.

15

Entry point address of IEFU86.

Parameter descriptions

Input parameter structure mapped by IFAEXITP:

Table 5. IEFU86 input parameter structure

Offset	Length	Type	Description
0	4	Character	Eye catcher - 'SMXP'
4	2	Binary	Length of this structure
6	1	Binary	Version - 1
7	1	Binary	Bit Meaning when set 0 Set by IBM. Indicates that the SMF writer routine was entered through an SVC call. 1 Set by IBM. Indicates that the SMF writer routine was branch-entered and not entered in cross-memory mode. 2 Set by IBM. Indicates that the SMF writer routine was branch-entered and entered in cross-memory mode. 3 - 15 Reserved. Do not set or use.
8	4	Binary	Pointer to the SMF record
C	2	Binary	Offset to the work area
E	2	Binary	Length of the work area

Work area described in IFAEXITP

Table 6. IEFU86 work area

Offset	Length	Type	Description
0	See Description in this table.	Character	Work area that is located past the parameter list at an offset value at + X'C' into the parameter list. The length value of the work area is at + X'E' into the parameter list.

Return specifications

A return code from IEFU86 indicates whether the current SMF record is to be suppressed.

If you associate multiple exit routines with IEFU86, you can specify how the return information is to be handled using the ATTRIB KEEPRC function of the SETPROG EXIT command, the EXIT statement of PROGxx, or CSVDYNEX services. If multiple exit routines match the ATTRIB KEEPRC criteria, the system returns information from the exit routine that finished first.

If you do not specify the ATTRIB KEEPRC function, the system returns the information from the exit routine whose return value was the greatest. If multiple exit routines return with the same highest value, the return information from the exit routine that finished first is returned.

If you associate multiple exit routines with exit IEFU86, and any of those exit routines return with a value of 4, the current SMF record is suppressed.

Registers at exit: Upon return from the exit processing, the register contents must be as follows:

Register Contents

0 - 1

Not applicable.

2

Deleted by exit call processing.

3 -14

Not applicable.

15

Note: If multiple IEFU86 exits are called, or if any of the IEFU83, IEFU84, or IEFU85 exits are called, SMF accepts any of the exits that set a return code of 4.

One of the following return codes:

Return code Explanation

Value of 0

SMF is to write the record.

Value of 4

SMF is to not write the record.

Other Value

SMF is to write the record.

Recovery considerations

If IEFU86 abnormally terminates, SMF, in most cases, does not terminate. SMF deactivates the exit and then issues message CSV430I to the operator. If the exit performs a critical function, the operator can issue a SET SMF or SETSMF command to terminate recording. Otherwise, SMF recording continues but bypasses the installation exit routine.

IBM strongly recommends that you set up a recovery routine to handle errors that might occur during the execution of your exit routine. See [“Exit recovery” on page 240](#) for more information regarding recovery processing in the exit.

The caller of the exit will establish recovery. If it gets control, it will prevent SMF from ending if the exit routine abnormally ends. If this recovery routine gets control on two consecutive invocations of the exit, SMF requests that the exit routine be marked inactive, preventing any further invocations of that exit routine. In the case that an exit is marked as inactive, the system issues message CSV430I, naming the exit and the exit routine.

Chapter 42. IFASMFDL and IFASMFDL — SMF Dump Program Exits

Topics for This Exit Appear as Follows:

- [“Defining the Exits” on page 245](#)
- [“Controlling the Exit Routine Through the Dynamic Exits Facility” on page 245](#)
- [“Exit Routine Environment” on page 245](#)
- [“Exit Routine Processing” on page 246](#)
- [“Programming Considerations” on page 246](#)
- [“Entry and Return Specifications” on page 246](#)

The USER1, USER2, USER3, USER4 and USER5 exits are called at various times during processing by each of the SMF dump programs IFASMFDL and IFASMFDL. These exits are also referred to here as the USERx exits. For more information about each of these exits, refer to the [z/OS MVS System Management Facilities \(SMF\)](#) manual.

Defining the Exits

When invoking the SMF log stream or data set dump programs, IFASMFDL or IFASMFDL, specify the USER1, USER2, USER3, USER4, and/or USER5 parameters to identify the exit names to the programs. Additionally, it may be required that for each USERx exit, the SMFPRMxx parmlib member contains an SMFDLEXIT and/or SMFDPEXIT keyword option to identify the valid exit names to the system.

For more information about coding the SMFDLEXIT and SMFDPEXIT parameter options, see the SMFPRMxx section in the [z/OS MVS Initialization and Tuning Reference](#).

Controlling the Exit Routine Through the Dynamic Exits Facility

Dynamic Exit support is not provided for the IFASMFDL and IFASMFDL USERx exits.

Exit Routine Environment

When called from IFASMFDL, the USERx exits receive control in the following environment:

- In the authorization state and key of the SMF dump program
- Enabled for interrupts
- With no locks held
- In the address space of the SMF dump program
- In Primary ASC mode
- In AMODE 31

When called from IFASMFDL, the USERx exits receive control in the following environment:

- Enabled for interrupts
- With no locks held
- In the address space of the SMF dump program
- In Primary ASC mode
- In AMODE 24 for USER1, USER2 and USER3
- In AMODE 31 for USER4 and USER5

Exit Recovery: If recovery processing is not established by the USERx exit, the USERx exits run under the recovery of IFASMFDL or IFASMFDL.

Exit Routine Processing

See the MVS System Management Facilities (SMF) manual for information about exit routine processing for each of the USERx exits.

Programming Considerations

None

Entry and Return Specifications

For information about entry and return specifications for each of the USERx exits refer to the [*z/OS MVS System Management Facilities \(SMF\)*](#).

Chapter 43. Global Resource Serialization Exits

Topics for The GRS Exits Appear as Follows:

- “System Programmer or Authorized Exits” on page 247
 - ISGNQXITFAST – Fast ISGENQ / ENQ / DEQ Installation Exit
 - ISGNQXIT – ISGENQ / ENQ / DEQ Installation Exit
 - ISGCNFXITSYSTEM – Filter Global Resource Serialization Contention Notification, SYSTEM Scope
 - ISGCNFXITSYSPLEX – Filter Global Resource Serialization Contention Notification, SYSTEMS Scope
- “Authorized Exits” on page 256
 - ISGDGRSRES – Display Global Resource Serialization Resource Exit
- “Authorized Exits for Alternate Serialization Products” on page 258
 - ISGNQXITPREBATCH – ISGENQ / ENQ / DEQ Batch Preprocessing Exit
 - ISGNQXITBATCH – ISGENQ / ENQ / DEQ Batched Exit
 - ISGNQXITBATCHCND – ISGENQ / ENQ / DEQ Conditional Batch Processing Exit
 - ISGNQXITQUEUED1 – ISGENQ / ENQ / DEQ First Queued Exit
 - ISGNQXITQUEUED2 – ISGENQ / ENQ / DEQ Second Queued Exit
 - ISGENDOFLQCB – End of Local QCB Exit

System Programmer or Authorized Exits

ISGNQXITFAST — Fast ISGENQ / ENQ / DEQ Installation Exit

ISGNXITFAST is the IBM recommended replacement for ISGNQXIT and should be used except where restrictions apply.

For each ENQ/DEQ/RESERVE request with SCOPE=SYSTEM or SCOPE=SYSTEMS, the system invokes the Fast ENQ/DEQ Installation Exit, ISGNQXITFAST. The exit routine can modify attributes of the request prior to Resource Name List (RNL) processing. See *z/OS MVS Planning: Global Resource Serialization* for the installation flow through ENQ/DEQ exits.

By altering the ISGNXITFAST exit parameter list, the exit can:

- Alter the resource name (QNAME and/or RNAME).
- Alter the resource scope. See restrictions below .
- Alter the UCB address (for a RESERVE). See restrictions below .
- Convert a RESERVE to an ENQ by setting the UCB to zero. See restrictions below .
- Convert an ENQ to a RESERVE by adding a UCB specification. See restrictions below .
- Indicate to bypass the RNL processing.

Note: The exit routine cannot change the scope nor UCB address of a request when the program issues the ENQ or ISGENQ macro with RNL=NO. The Nqxp_SF1_RnEqNo bit passed in the parameter list indicates if RNL=NO was specified.

This exit is invoked under the caller's unit of work on the system where the caller is running. For global resource requests, the exit is invoked only on the system where the request is made.

Note:

1. This exit is intended to replace ISGNQXIT. Although it is possible to run with both the ISGNQXIT and ISGNQXITFAST exits on a system, it is not recommended as path length and processing time are increased.
2. If both the ISGNQXIT and ISGNQXITFAST exits are installed, because ISGNQXIT is called second, any changes requested by the ISGNQXIT exits will override any changes made by the ISGNQXITFAST exits.
3. Any changes made by ISGNQXITFAST are not honored for an ISGENQ CHANGE or RELEASE request. Instead, the original changes made by ISGNQXITFAST on the OBTAIN are used.

Replacing the Exit Routine

Unlike RNL changes, GRS does not know how an exit alters the resource identity of a request. Therefore, to maintain data integrity, do not make an exit change that alters the resource identity of any outstanding or in-flight ENQ or DEQ requests. The resource identity consists of the QNAME, RNAME, SCOPE, and hardware reserve status. When you make exit changes, first stop the programs that are currently using the resource, and do not resume the programs until all the exit changes in the GRS complex have completed.

For information regarding dynamic exit routine replacement, see [“Replacing a Dynamic Exit Routine” on page 6](#).

Exit Routine Environment

ISGNQXITFAST receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In primary mode with H not= P not= S or H=P=S.
- In AMODE 31 and RMODE ANY.
- With no locks held or with the local and CMSEQDQ locks held.
- An FRR held when locks are held, otherwise an ARR is in effect.

Exit Recovery is as follows.

- If an error occurs, ISGNQXITFAST provides its own recovery routine.
- If no recovery exists, or the recovery continues with termination, GRS fails the request and continues processing. CSVDYNEX rules for the exit are used to determine whether the exit should be removed.

The unplanned removal of an exit can result in serialization changes. Therefore, it is important to provide recovery and to understand how CSVDYNEX determines when to remove an abend exit.

For more information about CSVDYNEX, see [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#).

Exit Routine Processing

The ISGNQXITFAST exit routine is invoked for every ISGENQ/ENQ/DEQ/RESERVE request issued for a resource. If any exit routines are defined to the dynamic exits facility, those routines are invoked before Resource Names List processing. If any ISGNQXIT exit routines are defined, these are run after the ISGNQXITFAST exit routines are run.

By updating and using information in the parameter list, the exit routine alters the following characteristics of the request:

- Resource major name (QNAME).
- Resource minor name (RNAME).
- Resource scope. If the requestor specified RNL=NO, changes to this parameter are not honored.
- Device UCB address (for RESERVE or DEQ with UCB requests). If the requestor specified RNL=NO, changes to this parameter are not honored. A UCB address can be deleted from a RESERVE request,

converting the request from a RESERVE to an ENQ or a UCB address can be added to an ENQ, converting the request to a RESERVE.

The exit routine can also indicate that RNL processing can be bypassed.

Programming Considerations

Observe the following conventions when coding a Fast ISGENQ/ENQ/DEQ exit routine:

- Every exit routine must be reentrant.
- Because the exit is called for every ENQ, RESERVE, and DEQ request, an increased path length increases processor utilization and can degrade performance.
- Do not code the exit routine to issue the WAIT macro or call a service, such as WTOR, that issues a WAIT.
- Do not code the exit routine to issue another ISGENQ, ENQ, RESERVE, or DEQ macro.

Entry Specifications

The system passes a NQXP parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

0	Not applicable
1	Address of the exit parameter list (ISGYNQXP)
2-12	Not applicable
13	Address of a 72-byte save area
14	Return address
15	Entry point address of ISGNQXITFAST

Parameter List Contents: Register 1 contains the address of the exit parameter (NQXP) that is mapped by macro ISGYNQXP. Refer to *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the mapping of the ISGYNQXP data area.

Return Specifications

The ISGNQXITFAST installation exit sets the appropriate request flag and alters the value in the parameter list. For example, to change the major name, the exit sets Nqxp_RFI_ChangeQName to B'1' and Nqxp_CP_QNAME to the new major name.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0-14	Restored to contents on entry
15	0

ISGNQXIT – ISGENQ / ENQ / DEQ Installation Exit

For the best performance, IBM recommends that the installation use the ISGNQXITFAST rather than ISGNQXIT. The ISGNQXIT exit should only be used if the ISGNQXITFAST exit cannot be used. In no case should both exits be used because both will be called on every ENQ resulting in degraded system performance.

For each ISGENQ/ENQ/DEQ/RESERVE request with SCOPE=SYSTEM or SCOPE=SYSTEMS, the system invokes the ENQ/DEQ Installation Exit point, ISGNQXIT. The exit routines can modify attributes of the request prior to Resource Names List (RNL) processing. See *z/OS MVS Planning: Global Resource Serialization* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the installation flow through ENQ/DEQ exits.

By altering the exit parameter list, the exit can:

- Alter the resource name (QNAME and/or RNAME).
- Alter the resource scope. See restrictions below .
- Alter the UCB address (for a RESERVE). See restrictions below .
- Convert a RESERVE to an ENQ by setting the UCB to zero. See restrictions below .
- Convert an ENQ to a RESERVE by adding a UCB specification. See restrictions below .
- Indicate to bypass the RNL processing.

Note: The exit routine cannot change the scope nor UCB address of a request when the program issues the ENQ or ISGENQ macro with RNL=NO. The Nqxp_SF1_RnLEqNo bit passed in the parameter list indicates if RNL=NO was specified.

This exit is invoked under the caller's unit of work on the system where the caller is running. For global resource requests, the exit is invoked only on the system where the request is made.

Note:

1. Any changes made by ISGNQXIT are not honored for an ISGENQ CHANGE or RELEASE request. Instead, the original changes made by ISGNQXIT on the OBTAIN are used.
2. This exit replaces the ISGGREX0 exit interface, which was removed in z/OS V1R2; ISGGSIX, ISGGSEEX, and ISGGRCEX are no longer used. Message ISG351I is issued and the exit is not invoked if any of these exits are installed.

Replacing the Exit Routine

Unlike RNL changes, GRS does not know how an exit alters the resource identity of a request. Therefore, to maintain data integrity, do not make an exit change that alters the resource identity of any outstanding or in-flight ENQ or DEQ requests. The resource identity consists of the QNAME, RNAME, SCOPE, and hardware reserve status. When you make exit changes, first stop the programs that are currently using the resource, and do not resume the programs until all the exit changes in the GRS complex have completed.

Any changes the exit makes must be taken into consideration. For information regarding dynamic exit routine replacement, see [“Replacing a Dynamic Exit Routine”](#) on page 6.

Exit Routine Environment

ISGNQXIT receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In primary mode with H = P = S = requestor's address space.
- In AMODE 31 and RMODE ANY.
- With no locks held.

Exit Recovery is as follows.

- If an error occurs, ISGNQXIT provides its own recovery routine.
- If no recovery exists, or the recovery continues with termination, GRS fails the request and continues processing. CSVDYNEX rules for the exit are used to determine whether the exit should be removed.

The unplanned removal of an exit can result in serialization changes. Such changes might cause data integrity errors. Therefore, it is important to provide recovery and to understand how CSVDYNEX determines when to remove an abend exit. For more information about CSVDYNEX, see [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#).

Exit Routine Processing

The ISGNQXIT exit routine is invoked for every ENQ/DEQ/RESERVE/ISGENQ SCOPE=SYSTEM or SCOPE=SYSTEMS request issued for a resource. If any exit routines are defined to the dynamic exits facility, those routines are invoked before Resource Names List (RNL) processing.

By updating and using information in the parameter list, the exit routine alters the following characteristics of the request:

- Resource major name (QNAME).
- Resource minor name (RNAME).
- Resource scope. If the requester specified RNL=NO, changes to this parameter are not honored.
- Device UCB address (for RESERVE or DEQ with UCB requests). If the requester specified RNL=NO, changes to this parameter are not honored. A UCB address can be deleted from a RESERVE request, converting the request from a RESERVE to an ENQ or a UCB address can be added to an ENQ, converting the request to a RESERVE.

The exit routine can also indicate that RNL processing can be bypassed.

Programming Considerations

Observe the following conventions when coding an ISGENQ, ENQ, DEQ and RESERVE exit routine:

- Every exit routine must be reentrant.
- Because the exit is called for every ISGENQ, ENQ, DEQ, and RESERVE request, an increased path length increases processor utilization and can degrade performance.
- Do not code the exit routine to issue the WAIT macro or call a service, such as WTOR, that issues a WAIT.
- Do not code the exit routine to issue another ISGENQ, ENQ, RESERVE, or DEQ macro.
- The QNAME, RNAME, SCOPE, and UCB must match both the ENQ and the DEQ.
- Issuing the GETMAIN or STORAGE OBTAIN macro can slow down performance.

Entry Specifications

The ISGENQ/ENQ/DEQ/RESERVE mainline routine passes the address of the ENQ exit parameter list (ISGYNQXP).

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

0	Not applicable
1	Address of the exit parameter list (ISGYNQXP).
2-12	Not applicable

13

Address of a 72-byte save area

14

Return address

15

Entry point address of ISGNQXIT

Parameter List Contents: Register 1 contains the address of the exit parameter (NQXP) that is mapped by macro ISGYNQXP. Refer to *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the mapping of the ISGYNQXP data area.

Return Specifications

The ISGENQ/ENQ/DEQ installation exit sets the appropriate request flag and alters the value in the parameter list. For example, to change the major name, the exit sets Nqxp_RFI_ChangeQName to '1'b and Nqxp_CP_QNAME to the new major name.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-14

Restored to contents on entry

15

0

ISGCNFXITSYSTEM – Filter Global Resource Serialization Contention Notification, SYSTEM Scope

ISGCNFXITSYSTEM provides a way for your installation to suppress the ENF 51 signal that global resource serialization issues to notify programs of contention for a scope=SYSTEM resource. When at least one exit routine has been added to the ISGCNFXITSYSTEM exit, it will receive control for every resource of system scope that Global Resource Serialization finds in contention. Depending on what your installation specified in the exit routine, the exit can suppress the ENF 51 signal for the resource in contention. This allows the installation to suppress ENF signals for resources known to be frequently in contention, with the trade-off of providing less data to any monitoring tools that listen for those signals.

Replacing the Exit Routine

For information regarding dynamic exit routine replacement, see [“Replacing a Dynamic Exit Routine”](#) on page 6.

Exit Routine Environment

ISGCNFXITSYSTEM receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In primary ASC mode with H=S=requestor's address space, and P=Global Resource Serialization's address space.
- In task mode.
- In AMODE 31 and RMODE ANY.
- With no locks held, a local lock held, or both a local lock and the CMSEQDQ lock held..

Exit Recovery is as follows.

- If an error occurs, ISGCNFXITSYSTEM provides with its own recovery routine.

- If no recovery exists, or the recovery continues with termination, GRS fails the request and continues processing. CSVDYNEX rules for the exit are used to determine whether the exit should be removed.

The unplanned removal of an exit can result in serialization changes. Such changes might cause data integrity errors. Therefore, it is important to provide recovery and to understand how CSVDYNEX determines when to remove an abend exit. For more information about CSVDYNEX, see [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#).

Exit Routine Processing

The ISGCNFXITSYSTEM exit point allows an exit routine to suppress the ENF 51 signal when global resource serialization detects contention on a system scope resource. The exit routine is passed a parameter list, CNFP (mapped by CNFP), which contains information about the request. The exit routine can check the QNAME, RNAME, and Rnamelen of the resource and filter the ENF 51 signal.

Programming Considerations

Observe the following considerations when coding an exit routine to filter global resource serialization contention notification on a system scope:

- Every exit routine must be reentrant.
- While coding the exit routine, be aware that you will have an increased path length for ENQ/DEQ requests because the exit is called for every system scope resource in contention.
- Depending on the locks held upon entry to the exit routine, failing to return control promptly can cause significant delays in global resource serialization processing.
- Make sure that your exit routine takes into account the parameter list version, CNFP_VERSION, in case of future interface changes for the exit point.
- Do not code the exit routine to change any variables in the parameter list except for the filter flag. The exit does not make a copy of the resource identifying parameters passed, such as QNAME, RNAME, and Rnamelen.
- If you want to write an exit routine that covers both system (ISGCNFXITSYSTEM) and systems (ISGCNFXITSYSPLX) scope resource contention, then use the CNFP_SYSTEM flag in the CNFP parameter list to differentiate between them.
- The resource described in the parameter list via CNFP_QNAME@, CNFP_RNAME@, CNFP_RLEN, and CNFP_SYSTEM reflects any changes made from other exits or RNL processing.

Entry Specifications

The system passes a parameter list (CNFP) to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of the exit parameter list (ISGYCNFP)

2-12

Not applicable

13

Address of a 72-byte save area

14

Return address

15

Entry point of ISGCNFXITSYSTEM

Parameter List Contents: Register 1 contains the address of the exit parameter (CNFP) that is mapped by macro ISGYCNFP. The parameter list contains the QNAME, RNAME, and Rnamelen of the resource, the filter flag, and a 4K work area. You should not use this work area to communicate among multiple exit routines because the work area may not be cleared upon entry. In addition, in certain recovery scenarios the work area may not be the same for all routines.

Return Specifications

At the completion of ISGCNFXITSYSTEM processing, ISGYCNFP can indicate that the ENF 51 signal be suppressed by setting the CNFP_FILTER flag.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0-14

Restored to contents on entry

15

0

Coded Example of the Exit Routine

IBM provides coded examples of the ISGCNFXITSYSTEM and ISGCNFXITSYSPLEX exit routines in member ISGCNFXR of SYS1.SAMPLIB.

ISGCNFXITSYSPLEX – Filter Global Resource Serialization Contention Notification, SYSTEMS Scope

ISGCNFXITSYSPLEX provides a way for your installation to suppress the ENF 51 signal that global resource serialization issues to notify programs of contention for a scope=SYSTEMS resource. When at least one exit routine has been added to the ISGCNFXITSYSPLEX exit, it will receive control for every resource of systems scope that global resource serialization finds in contention. Depending on what your installation specified in the exit routine, the exit can suppress the ENF 51 signal for the resource in contention. This allows the installation to suppress ENF signals for resources known to be frequently in contention, with the trade-off of providing less data to any monitoring tools that listen for those signals.

Replacing the Exit Routine

For information regarding dynamic exit routine replacement, see [“Replacing a Dynamic Exit Routine” on page 6](#).

Exit Routine Environment

ISGCNFXITSYSPLEX receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In primary ASC mode with P=H=S=Global Resource Serialization's address space
- In task mode.
- In AMODE 31 and RMODE ANY.
- With no locks held, a local lock held, or both a local lock and the CMSEQDQ lock held..

Exit Recovery is as follows.

- If an error occurs, ISGCNFXITSYSPLEX provides with its own recovery routine.
- If no recovery exists, or the recovery continues with termination, GRS fails the request and continues processing. CSVDYNEX rules for the exit are used to determine whether the exit should be removed.

The unplanned removal of an exit can result in serialization changes. Such changes might cause data integrity errors. Therefore, it is important to provide recovery and to understand how CSVDYNEX determines when to remove an abend exit. For more information about CSVDYNEX, see [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#).

Exit Routine Processing

The ISGCNFXITSYSplex exit point allows an exit routine to suppress the ENF 51 signal when global resource serialization detects contention on a systems scope resource. The exit routine is passed a parameter list, CNFP (mapped by CNFP), which contains information about the request. The exit routine can check the QNAME, RNAME, and Rnamelen of the resource and filter the ENF 51 signal.

Programming Considerations

Observe the following considerations when coding an exit routine to filter global resource serialization contention notification on a systems scope:

- Every exit routine must be reentrant.
- While coding the exit routine, be aware that you will have an increased path length for ENQ/DEQ requests because the exit is called for every system scope resource in contention.
- Depending on the locks held upon entry to the exit routine, failing to return control promptly can cause significant delays in global resource serialization processing.
- Make sure that your exit routine takes into account the parameter list version, CNFP_VERSION, in case of future interface changes for the exit point.
- Do not code the exit routine to change any variables in the parameter list except for the filter flag. The exit does not make a copy of the resource identifying parameters passed, such as QNAME, RNAME, and Rnamelen.
- If you want to write an exit routine that covers both system (ISGCNFXITSYSTEM) and systems (ISGCNFXITSYSplex) scope resource contention, then use the CNFP_SYSTEM flag in the CNFP parameter list to differentiate between them.
- The resource described in the parameter list via CNFP_QNAME@, CNFP_RNAME@, CNFP_RLEN, and CNFP_SYSTEM reflects any changes made from other exits or RNL processing.

Entry Specifications

The system passes a parameter list (CNFP) to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of the exit parameter list (ISGYCNFP)

2-12

Not applicable

13

Address of a 72-byte save area

14

Return address

15

Entry point of ISGCNFXITSYSplex

Parameter List Contents: Register 1 contains the address of the exit parameter (CNFP) that is mapped by macro ISGYCNFP. The parameter list contains the QNAME, RNAME, and Rnamelen of the resource, the

filter flag, and a 4K work area. You should not use this work area to communicate among multiple exit routines because the work area may not be cleared upon entry. In addition, in certain recovery scenarios the work area may not be the same for all routines.

Return Specifications

At the completion of ISGCNFXITSYSplex processing, ISGYCNFP can indicate that the ENF 51 signal be suppressed by setting the CNFP_FILTER flag.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0-14

Restored to contents on entry

15

0

Coded Example of the Exit Routine

IBM provides coded examples of the ISGCNFXITSYSplex and ISGCNFXITSYSTEM exit routines in member ISGCNFXR of SYS1.SAMPLIB.

Authorized Exits

ISGDGRSRES — Display Global Resource Serialization Resource Exit

ISGDGRSRES is called for each ENQ resource displayed in a DISPLAY GRS,RES= or CONTENTION command. It allows an application to provide additional information describing the meaning of the ENQ resource name.

The parameter list passed to ISGDGRSRES is mapped by ISGYDSPX (DSPX). The parameter list describes an ENQ resource name.

Replacing the Exit Routine

For information regarding dynamic exit routine replacement, see [“Replacing a Dynamic Exit Routine”](#) on page 6.

Exit Routine Environment

ISGDGRSRES receives control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In primary mode with H = P = S = requestor's address space.
- In AMODE 31 and RMODE ANY.
- With no locks held.
- An EUT FRR is held when the exit routine is called.

Exit Recovery is as follows.

- If an error occurs, ISGDGRSRES provides with its own recovery routine.
- If no recovery exists, or the recovery continues with termination, GRS fails the request and continues processing. CSVDYNEX rules for the exit are used to determine whether the exit should be removed.

The unplanned removal of an exit can result in serialization changes. Such changes might cause data integrity errors. Therefore, it is important to provide recovery and to understand how CSVDYNEX

determines when to remove an abend exit. For more information about CSVDYNEX, see [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#).

Exit Routine Processing

The exit routine should interrogate the QNAME and RNAME information that will be displayed. If the exit routine can add information about the meaning of the QNAME and RNAME for the resource, it can place:

- An identifier (16 EBCDIC characters padded with EBCDIC blanks on the right, if needed) in the DspX_ResourceIdentifier field (for example, a subsystem or product name).
- Descriptive information (up to 70 EBCDIC characters padded with EBCDIC blanks on the right, if needed) in the DspX_ResourceInformation field.

For an example, see [Providing ENQ resource information on DISPLAY GRS command in z/OS MVS Programming: Authorized Assembler Services Guide](#).

Programming Considerations

Observe the following conventions when coding a display global resource serialization exit routine:

- Every exit routine must be reentrant.
- Be aware while coding the exit routine that because the exit is called for every resource displayed in a DISPLAY GRS command response, excessive path length could degrade system performance.
- Do not code the exit routine to issue the WAIT macro or call a service, such as WTOR, that issues a WAIT.
- Do not code the exit routine to issue another ENQ, RESERVE, or DEQ macro.

Entry Specifications

The system passes a ISGYDSPX parameter list (DSPX) to the exit routine. The DSPX contains the QNAME, RNAME, and scope of the resource being displayed. The exit routine can update the resource identifier and information fields for display.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of the exit parameter list (ISGYDSPX)

2-12

Not applicable

13

Address of a 72-byte save area

14

Return address

15

Entry point address of ISGDGRSRES

Parameter List Contents: Register 1 contains the address of the exit parameter (DSPX) that is mapped by macro ISGYDSPX. Refer to *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the mapping of the ISGYDSPX data area.

Return Specifications

The information displayed in the command output will be that from the last exit routine to update the DSPX parameter list.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-14

Restored to contents on entry

15

0

Authorized Exits for Alternate Serialization Products

ISGNQXITPREBATCH — ISGENQ / ENQ / DEQ Batch Preprocessing Exit

ISGNQXITPREBATCH provides the ability to reduce CPU consumption for ENQ, DEQ, ISGENQ or RESERVE requests that need to be processed by the ISGNQXITBATCH and ISGNQXITQUEUED1 exit points. The system calls the ISGNQXITPREBATCH exit point once for each ENQ, DEQ, ISGENQ or RESERVE resource with SCOPE=SYSTEM or SCOPE=SYSTEMS. If any of the ISGNQXITPREBATCH exit routines indicate that the resource should be processed by the ISGNQXITBATCHCND exit, then all of the resources in the current request will be presented to the ISGNQXITBATCHCND exit. Any ENQ or RESERVE request presented to the ISGNQXITBATCHCND exit will also be processed by the ISGNQXITQUEUED1 exit. See [Request processing sequence in z/OS MVS Planning: Global Resource Serialization](#) for the installation flow through ENQ/DEQ exits.

The ISGNQXITPREBATCH exit point also provides the ability to control future calls to this exit point. If the set of ISGNQXITPREBATCH exit routines indicates that this exit should no longer be called for a particular resource QNAME and scope, an entry for that QNAME is added to the GRS Exit Cache. Before calling the ISGNQXITPREBATCH exit point, GRS queries the GRS Exit Cache. If a matching entry is found and the entry indicates to NOT call the ISGNQXITPREBATCH exit point, this exit can be bypassed. Filtering the GRS Exit Cache is based on the QNAME, the original scope, the final scope, the original RESERVE state, and the final RESERVE state.

To restore processing of a resource through the ISGNQXITPREBATCH exit, the GRS Exit Cache must be cleared. For more information, see ISGGCECR, ClearCache call in [z/OS MVS Programming: Callable Services for High-Level Languages](#).

This exit is invoked under the caller's unit of work on the system where the caller is running. For global resource requests, the exit is invoked only on the system where the request is made.

Note:

1. The ISGNQXITBATCH exit is not affected by the ISGNQXITPREBATCH exit.
2. After a call to ISGGCECR, the ISGNQXITPREBATCH exit can be called again for all resources.
3. If an error occurs in the GRS Exit Cache, the cache will be disabled and all resources will again be processed by the ISGNQXITPREBATCH. You must do the IPL again to restore cache processing.

Note:

Replacing the Exit Routine

Unlike RNL changes, GRS does not know how an exit alters the resource identity of a request. Therefore, to maintain data integrity, do not make an exit change that alters the resource identity of any outstanding or in-flight ENQ or DEQ requests. The resource identity consists of the QNAME, RNAME, SCOPE, and hardware reserve status. When you make exit changes, first stop the programs that are currently using the resource, and do not resume the programs until all the exit changes in the GRS complex have completed.

For information regarding dynamic exit routine replacement, see [“Replacing a Dynamic Exit Routine”](#) on page 6.

Exit Routine Environment

ISGNQXITPREBATCH receives control in the following environment:

- Task mode (running under the requester's task).
- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In primary ASC mode.
- In cross-memory mode with H=Caller's home address space, S=Any space, and P=Global Resource Serialization's address space.
- In AMODE 31 and RMODE ANY.
- With no locks held or with the local and CMSEQDQ locks held.
- An FRR is held when locks are held, otherwise an ARR is in effect.

The routine can be invoked with an FRR established that must remain in effect. Therefore, system services or instructions that do not allow FRRs to be active or cause FRRs to be removed cannot be used. This includes the SVC instruction.

Exit Recovery is as follows.

- If an error occurs, the ISGNQXITPREBATCH exit routine should provide its own recovery routine.
- Exclusive use of EUT FRR recovery is the suggested recovery to be used because it can be used in all possible entry environments. ESTAE-like recovery is a worse performer and can be used only when locks are not held on entry. ESTAE-like recovery can be established but it does not receive control because an EUT FRR is established on entry.
- If no recovery exists, or the recovery continues with termination, GRS fails the request and continues processing. CSVDYNEX rules for the exit are used to determine whether the exit should be removed.

The unplanned removal of an exit can result in serialization changes. Therefore, it is important to provide recovery and to understand how CSVDYNEX determines when to remove an abend exit.

For more information about CSVDYNEX, see [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#).

Exit Routine Processing

The ISGNQXITPREBATCH exit routine is invoked for every ENQ, DEQ, ISGENQ or RESERVE SCOPE=SYSTEM or SCOPE=SYSTEMS request issued for a resource. If any exit routines are defined to the dynamic exits facility, those routines are invoked after Resource Names List (RNL) processing.

By updating and using information in the parameter list, the exit routine indicates whether the ISGNQXITBATCHCND exit needs to be invoked or if the ISGNQXITPREBATCH exit will be called again for a resource.

Programming Considerations

Observe the following conventions when coding a Batch Preprocessing exit routine:

- Every exit routine must be reentrant.
- You should be aware while coding the exit routine, that because the exit is called for every ENQ, DEQ, ISGENQ and RESERVE request, an increased path length increases processor utilization and can degrade performance.
- Do not code the exit routine to issue the WAIT macro or call a service, such as WTOR, that issues a WAIT.
- Do not code the exit routine to issue another ENQ, DEQ, ISGENQ or RESERVE macro.

Entry Specifications

The system passes the NQPB parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of the exit parameter list (NQPB)

2-12

Not applicable

13

Address of a 72-byte save area

14

Return address

15

Entry point address of ISGNQXITPREBATCH

Parameter List Contents: Register 1 contains the address of the exit parameter (NQPB) that is mapped by macro ISGYNQPB. Refer to *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the mapping of the ISGYNQPB data area.

Return Specifications

The pre-batch installation exit sets the appropriate request flag in the parameter list to indicate:

- That ISGNQXITBATCHCND should be called
- That the scope of the ENQ should be considered to be global. This indication will be reported through ISGQUERY and ISGENQ TEST for API users to determine the overall scope of their ENQ request.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-14

Restored to contents on entry

15

0

ISGNQXITBATCH— ISGENQ / ENQ / DEQ Batched Exit ISGNQXITBATCHCND — ISGENQ / ENQ / DEQ Conditional Batch Processing Exit

Both the ISGNQXITBATCH exit and the ISGNQXITBATCHCND exit can interrogate and alter an entire ENQ, DEQ, ISGENQ, or RESERVE request. In most cases, the ISGNQXITBATCH exit and the ISGNQXITBATCHCND exit can be used interchangeably.

The ISGNQXITBATCH or ISGNQXITBATCHCND exit is invoked after all of the resources in the request have been passed to the ISGNQXIT exit point, and the RNLs have been processed for each resource in the request. Only SCOPE=SYSTEM and SCOPE=SYSTEMS resources are passed to the ISGNQXITBATCH or ISGNQXITBATCHCND exit; STEP requests are not passed to the ISGNQXITBATCH or ISGNQXITBATCHCND exit. See *Request processing sequence* in *z/OS MVS Planning: Global Resource Serialization* for the installation flow through ENQ/DEQ exits.

The ISGNQXITATCH and ISGNQXITBATCHCND exits can:

- Set a return code for each resource in a conditional request. For example, make the request not happen.

- Convert a RESERVE to an ENQ.
- Set an ABEND for the request. For example, make the entire request not happen.

The parameter list passed to ISGNQXITBATCH (or ISGNQXITBATCHCND) exit is mapped by ISGYNQBP (NQBP). See ISGYNQBP macro in *z/OS MVS Data Areas* in the [z/OS Internet library \(www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary\)](http://www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for more information.

An ISGNQXITBATCH (or ISGNQXITBATCHCND) exit routine can set its own non-zero return code for each resource in the request, overriding ENQ or RESERVE functionality, for all:

- ENQ requests that specify a RET value or an ECB value
- Conditional ISGENQ requests

In addition, the ISGNQXITBATCH (or the ISGNQXITBATCHCND) exit routine can optionally set its own non-zero reason code that accompanies the non-zero return code for conditional ISGENQ requests.

For all requests (ENQ, DEQ, ISGENQ, and RESERVE), an ISGNQXITBATCH (or ISGNQXITBATCHCND) exit routine can set a one-byte ABEND code and a half-word reason code for the request. The one-byte ABEND code is used to generate the ABEND code. For example, if the exit routine sets the ABEND code to 5 for an ENQ request, a 'X'538' ABEND will be generated by ENQ processing.

When you use the ISGNQXITBATCH and ISGNQXITBATCHCND exits, be aware of the following notes.

Note:

1. ISGNQXITBATCH and ISGNQXITBATCHCND exits are only used to interrogate and alter an entire ENQ, DEQ, ISGENQ, or RESERVE request. For any other changes, you must use the ISGNQXIT exit or the ISGNQXITFAST exit.
2. If your installation is using an OEM serialization product to replace global resource serialization, do not specify that the exit is to be called last, either with the LAST parameter of the SETPROG command or the POS=LAST parameter of the CSVDYNEX macro, when installing the exit.
3. If all ENQ, DEQ, ISGENQ, and RESERVE requests need to be processed, use the ISGNQXITBATCH exit; if only a subset of requests need to be processed, use the combination of the ISGNQXITPREBATCH and ISGNQXITBATCHCND exit for better performance. See [“ISGNQXITPREBATCH — ISGENQ / ENQ / DEQ Batch Preprocessing Exit”](#) on page 258 for more information on the usage of ISGNQXITPREBATCH and ISGNQXITBATCHCND.
4. When both the ISGNQXITBATCH and ISGNQXITBATCHCND exits are installed, ISGNQXITBATCHCND is called second. Therefore, any actions requested by the ISGNQXITBATCHCND exits override any requests made by the ISGNQXITBATCH exits.

Replacing the Exit Routine

Unlike RNL changes, GRS does not know how an exit alters the resource identity of a request. Therefore, to maintain data integrity, do not make an exit change that alters the resource identity of any outstanding or in-flight ENQ or DEQ requests. The resource identity consists of the QNAME, RNAME, SCOPE, and hardware reserve status. When you make exit changes, first stop the programs that are currently using the resource, and do not resume the programs until all the exit changes in the GRS complex have completed.

For information regarding dynamic exit routine replacement, see [“Replacing a Dynamic Exit Routine”](#) on page 6.

Exit Routine Environment

ISGNQXITBATCH (or ISGNQXITBATCHCND) exit receives control in the following environment:

- Task mode (running under the requester's task).
- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In primary ASC mode.

- In cross-memory mode with H=Caller's home address space, S=Any space, and P=Global Resource Serialization's address space.
- In AMODE 31 and RMODE ANY.
- With no locks held.
- An EUT FRR is held when the exit routine is called.

The routine can be invoked in the cross-memory mode with an EUT FRR established that must remain in effect. Therefore, system services or instructions that do not allow FRRs to be active or cause FRRs to be removed cannot be used. This includes the SVC instruction.

Exit Recovery is as follows.

- If an error occurs, the ISGNQXITBATCH (or ISGNQXITBATCHCND) exit should provide its own EUT FRR recovery routine.
- An EUT FRR recovery is the only recovery type that can be used. ESTAE-like recovery can be established but it does not receive control because an EUT FRR is established on entry.
- If no recovery exists, or the recovery continues with termination, GRS fails the request and continues processing. CSVDYNEX rules for the exit are used to determine whether the exit should be removed.

The unplanned removal of an exit can result in serialization changes. Therefore, it is important to provide recovery and to understand how CSVDYNEX determines when to remove an abend exit.

For more information about CSVDYNEX, see [*z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN*](#).

Exit Routine Processing

The ISGNQXITBATCH (or ISGNQXITBATCHCND) exit point allows an exit routine to interrogate an ENQ, DEQ, ISGENQ, or RESERVE request as a single unit, rather than on an individual resource basis, as ISGNQXIT. The exit routine is passed a NQBP (mapped by ISGYNQBP) which contains information about the request.

The exit routine can affect processing in the following ways:

1. Set an ABEND code for the entire request. The requestor is ABENDED with this ABEND code, prepended to the appropriate SVC number. For example, if the exit indicated to use ABEND code 5 on an ENQ request, the caller would get ABENDED with a S538 ABEND code.
2. Set the return code for a conditional request. If the request specified RET=TEST, RET=HAVE, USE, CHNG, or ISGENQ COND=YES the exit routine can prevent normal ENQ/DEQ processing by indicating the return code to pass back to the caller. If this return code is set, the system will do no further processing on that resource. The list of acceptable return codes is as follows:

ENQ/RESERVE:

- RET=TEST RC=X'00',X'04',X'08',X'14',X'20'
- RET=USE RC=X'00',X'04',X'08',X'14',X'18'
- RET=CHNG RC=X'00',X'04',X'08',X'14'
- RET=HAVE RC=X'00',X'08',X'14',X'18',X'28',X'44'
- RET=ECB RC=X'00',X'08',X'14',X'18',X'28',X'44'

DEQ:

- RET=HAVE RC=X'00',X'04',X'08'

ISGENQ:

- RC=4 RSN=0402,0404,0405,0406,0407,0409,040A,040B
- RC=8 RSN=0815
- RC=C RSN=0C05
- RC=10 RSN=FFyy where yy are diagnostic bits set by the exit

Failure to use an acceptable return code may result in unexpected results for the request. Example of failure case:

On an ENQ RET=HAVE, when an exit sets a resource return code to X'20' GRS will not process the request. Instead GRS will pass the X'20' back to the ENQ caller. The ENQ caller will assume they have control of the resource because the return code X'20' indicates so. But GRS did not process the request so when the corresponding DEQ is issued for the resource, GRS will not find the resource on its queues, and therefore issue an ABEND130.

3. If the ISGNQXITBATCH (or ISGNQXITBATCHCND) exit is driven by an ISGENQ COND=YES request, and ISGNQXITBATCH (or ISGNQXITBATCHCND) specifies a return AND reason code, only the lower two bytes of the reason code will be set; the upper two bytes are reserved for system use.
4. Convert a RESERVE to an ENQ.

Programming Considerations

Observe the following conventions when you code a Batch ENQ exit routine. If you do not want to get control for all request instances but only for particular requests, the combined use of the ISGNQXITPREBATCH and ISGNQXITBATCHCND provides better performance over the ISGNQXITBATCH exit. See “ISGNQXITPREBATCH — ISGENQ / ENQ / DEQ Batch Preprocessing Exit” on page 258 for more information.

- Every exit routine must be reentrant.
- Because the exit is called for every ENQ, DEQ, ISGENQ, and RESERVE request, an increased path length increases processor utilization and can degrade performance.
- Do not code the exit routine to issue the WAIT macro or call a service, such as WTOR, that issues a WAIT.
- Do not code the exit routine to issue another ENQ, DEQ, ISGENQ, or RESERVE macro.

Entry Specifications

The system passes a Batch Exit parameter list (NQBP) to the exit routine. The NQBP contains a header section describing the request and an entry (NQBPSC) for each resource in the request.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

0	Not applicable
1	Address of the exit parameter list (ISGYNQBP)
2-12	Not applicable
13	Address of a 72-byte save area
14	Return address
15	Entry point address of ISGNQXITBATCH (or ISGNQXITBATCHCND)

Parameter List Contents: Register 1 contains the address of the exit parameter (NQBP) that is mapped by macro ISGYNQBP. Refer to *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the mapping of the ISGYNQBP data area.

Return Specifications

At the completion of ISGNQXITBATCH (or ISGNQXITBATCHCND) processing, ISGYNQBP can indicate that an ABEND code or return code has been set, or that a RESERVE has been converted to an ENQ.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-14

Restored to contents on entry

15

0

ISGNQXITQUEUED1 — ISGENQ / ENQ / DEQ First Queued Exit

ISGNQXITQUEUED1 is called when all the elements of an ENQ (not DEQ) request have completed local processing or have been queued to the global processor. The exit is called just prior to waiting (for unconditional requests that have not been granted) or returning to the ENQ requester. ISGNQXITQUEUED1 is called for both successful and unsuccessful cases. However it is not called at all if neither the batch nor batch conditional exits were called. See [Request processing sequence in z/OS MVS Planning: Global Resource Serialization](#) for the installation flow through ENQ/DEQ exits.

The parameter list passed to ISGNQXITQUEUED1 is mapped by ISGYNQQP (NQQP). The request data presented to ISGNQXITQUEUED1 are read only. Information contained in NQQP includes return codes that have been set for the local resources, the ABEND code if the request failed, and whether the request needs to be suspended for RNL processing.

Note:

1. This exit is intended for use by OEM serialization products.
2. If your installation is using an OEM serialization product to replace global resource serialization, you should NOT specify that any installation provided exits are to be called first (either with the FIRST parameter of the SETPROG command or the POS=FIRST parameter of the CSVDYNEX macro) when installing this exit.

Replacing the Exit Routine

Unlike RNL changes, GRS does not know how an exit alters the resource identity of a request. Therefore, to maintain data integrity, do not make an exit change that alters the resource identity of any outstanding or in-flight ENQ or DEQ requests. The resource identity consists of the QNAME, RNAME, SCOPE, and hardware reserve status. When you make exit changes, first stop the programs that are currently using the resource, and do not resume the programs until all the exit changes in the GRS complex have completed.

For information regarding dynamic exit routine replacement, see [“Replacing a Dynamic Exit Routine” on page 6](#).

Exit Routine Environment

ISGNQXITQUEUED1 receives control in the following environment:

- Task mode (running under the requester's task).
- Enabled for interrupts.
- Supervisor state with PSW key 0.
- Cross-memory mode with H=S=Requester's address space and P=Global Resource Serialization's address space.
- AMODE 31 and primary ASC mode.
- With no locks held.
- An EUT FRR might be held when the exit routine is called.

The routine can be invoked in the cross-memory mode with an EUT FRR established that must remain in effect. Therefore, system services or instructions that do not allow FRRs to be active or cause FRRs to be removed cannot be used. This includes the SVC instruction.

Exit Recovery is as follows.

- If an error occurs, the ISGNQXITQUEUED1 exit should provide its own EUT FRR recovery routine.
- An EUT FRR recovery is the only recovery type that can be used. ESTAE-like recovery can be established but it does not receive control because an EUT FRR is established on entry.
- If no recovery exists, or the recovery continues with termination, GRS fails the request and continues processing. CSVDYNEX rules for the exit are used to determine whether the exit should be removed.

The unplanned removal of an exit can result in serialization changes. Therefore, it is important to provide recovery and to understand how CSVDYNEX determines when to remove an abend exit.

For more information about CSVDYNEX, see [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#).

Exit Routine Processing

The ISGNQXITQUEUED1 exit point is called after the local resources in an ENQ/RESERVE request have been completed and the global resources have been queued to the global resource serialization address space for global processing. DEQ requests are not passed to ISGNQXITQUEUED1 exit routines. The exit routine is passed a NQQP (mapped by ISGYNQQP) which contains information about the request. If the request is going to ABEND, the ABEND code is indicated. An indicator is set if the request will be redriven due to a dynamic RNL change processing. Only SCOPE=SYSTEM and SYSTEMS resources are passed to the exit (STEP requests are not passed to the exit).

The NQQP is followed by one NQQPRSC entry for each resource in the request. Each NQQPRSC entry indicates the result for each local ENQ resource, or the fact that the request has been queued, for each global resource.

Programming Considerations

Most of the exits that are driven for a request are provided with a unique "request token". This token allows the exits to correlate any required user information between exit callers. For example, the Nqqp_RD_RequestToken will be the same as the Nqxp_RequestToken if both the ISGNQXITQUEUED1 and ISGNQXITFAST exits are driven for the same request.

Observe the following conventions when coding an ENQ/DEQ First Queued exit routine:

- Every exit routine must be reentrant.
- You should be aware while coding the exit routine, that because the exit is called for every ENQ and RESERVE request, an increased path length increases processor utilization and can degrade performance.
- Do not code the exit routine to issue the WAIT macro or call a service, such as WTOR, that issues a WAIT.
- Do not code the exit routine to issue another ENQ, RESERVE, or DEQ macro.
- The ISGNQXITQUEUED1 exit point is called for all ENQ/RESERVE requests only when either the ISGNQXITBATCH or ISGNQXITBATCHCND exits are called. In other words, only if a batch exit is called, the queued exit is called.

Entry Specifications

The system passes a NQQP parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register
Contents

ISGNQXITQUEUED1 – ENQ/DEQ First Queued Exit

0	Not applicable
1	Address of the exit parameter list (ISGYNQQP)
2-12	Not applicable
13	Address of a 72-byte save area
14	Return address
15	Entry point address of ISGNQXITQUEUED1

Parameter List Contents: Register 1 contains the address of the exit parameter (NQQP) that is mapped by macro ISGYNQQP. Refer to *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the mapping of the ISGYNQQP data area.

Return Specifications

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register	Contents
----------	----------

0-14	Restored to contents on entry
15	0

ISGNQXITQUEUED2 – ISGENQ / ENQ / DEQ Second Queued Exit

ISGNQXITQUEUED2 is called when all the elements of an ENQ (not DEQ) request have completed both local and global processing. The exit is called before waiting (for unconditional requests that have not been granted) or returning to the ENQ requester. This exit is called only if either the ISGNQXITBATCH or ISGNQXITBATCHCND exits have been called previously for the same request.

See ENQ/DEQ Exits Installation in *z/OS MVS Planning: Global Resource Serialization* for the installation flow through ENQ/DEQ exits.

ISGYNQQP (NQQP) maps the parameter list that is passed to ISGNQXITQUEUED2. The request data presented to ISGNQXITQUEUED2 are read only. The following information is contained in NQQP:

- Return codes that have been set for both local and global resources.
- The ABEND code if the request failed.
- Information about whether the request needs to be suspended for RNL processing.

Note:

1. This exit is intended for use by OEM serialization products.
2. If your installation is using an OEM serialization product to replace global resource serialization, do not specify that any installation-provided exits are to be called first (either with the FIRST parameter of the SETPROG command or with the POS=FIRST parameter of the CSVDYNEX macro) when installing this exit.

Replacing the Exit Routine

For information about the replacement of the dynamic exit routine, see [“Replacing a Dynamic Exit Routine”](#) on page 6.

Exit Routine Environment

ISGNQXITQUEUEU2 receives control in the following environment:

- Task mode (running under the requester's task).
- Enabled for interrupts.
- Supervisor state with PSW key 0.
- Cross-memory mode with H=S=Requester's address space and P=Global Resource Serialization's address space.
- AMODE 31 and primary ASC mode.
- With no locks held.
- An EUT FRR might be held when the exit routine is called.

The routine can be invoked in the cross-memory mode with an EUT FRR established that must remain in effect. Therefore, system services or instructions that do not allow FRRs to be active or that cause FRRs to be removed cannot be used. This includes the SVC instruction.

Exit Recovery is as follows.

- To recover from errors, the ISGNQXITQUEUEU2 routine must provide its own recovery routine.
- If no recovery exists, or the recovery terminates, GRS fails the request and continues processing. CSVDYNEX rules for the exit are used to determine whether the exit needs to be removed.

An unplanned removal of an exit can result in loss of the function it provides. Ensure that you provide recovery and understand how CSVDYNEX determines when to remove an exit that ends abnormally. For more information about CSVDYNEX, see [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#).

Exit Routine Processing

The ISGNQXITQUEUEU2 exit point is called after all local and global resources in an ENQ/RESERVE request have been processed. DEQ requests are not passed to ISGNQXITQUEUEU2 exit routines. The exit routine is passed by an NQQP (mapped by ISGYNQQP) that contains information about the request. If the request ends abnormally, an abend code is indicated. Only SCOPE=SYSTEM and SYSTEMS resources are passed to the exit (STEP requests are not passed to the exit).

The NQQP is followed by one NQQPRSC entry for each resource in the request. Each NQQPRSC entry indicates the result for each local and global ENQ resource.

Programming Considerations

Most of the exits that are driven for a request are provided with a unique request token. This token enables the exits to correlate any required user information between exit callers. For example, the Nqqp_RD_RequestToken is the same as the Nqxp_RequestToken if both the ISGNQXITQUEUEU2 and ISGNQXITFAST exits are driven for the same request.

Observe the following conventions when coding an ISGNQXITQUEUEU2 exit routine:

- Every exit routine must be re-entrant.
- When you are coding the exit routine, an increased path length increases processor utilization and can degrade performance, because the exit is called for every ENQ, RESERVE and ISGENQ OBTAIN/CHANGE request.
- Do not code the exit routine to issue another ENQ, RESERVE, DEQ or ISGENQ macro or to call another service that might issue those macros.
- The ISGNQXITQUEUEU2 exit point is called for all ENQ/RESERVE requests only when either the ISGNQXITBATCH or ISGNQXITBATCHCND exits are called. In other words, only if a batch exit is called, the queued exit is called.

Entry Specifications

The system passes a NQQP parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Not applicable

1

Address of the exit parameter list (ISGYNQQP)

2-12

Not applicable

13

Address of a 72-byte save area

14

Return address

15

Entry point address of ISGNQXITQUEUED2

The contents of the registers on entry to ISGNQXITQUEUED2 are as follows: Access Register contents are not predictable.

Parameter List Contents: Register 1 contains the address of the exit parameter (NQQP) that is mapped by macro ISGYNQQP. See *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the mapping of the ISGYNQQP data area.

Return Specifications

No return information is expected.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-14

Restored to contents on entry

15

Zero

ISGENDOFLQCB — End of Local QCB Exit

ISGENDOFLQCB is called when the last requester for a LOCAL resource (SCOPE=SYSTEM or RNL excluded SCOPE=SYSTEMS, but not SCOPE=STEP) is DEQed. The ISGENDOFLQCB exit is also called for SCOPE=SYSTEMS resources in a GRS=NONE environment. See *Request processing sequence* in *z/OS MVS Planning: Global Resource Serialization* for the installation flow through ENQ/DEQ exits.

The ISGENDOFLQCB exit point provides the ability to control future calls to this exit point. If the set of ISGENDOFLQCB exit routines indicates that this exit no longer needs to be called for a particular resource QNAME, an entry for that QNAME is added to the GRS Exit Cache. Prior to calling the ISGENDOFLQCB exit point, GRS queries the GRS Exit Cache. If a matching entry is found, and this entry indicates to NOT call the ISGENDOFLQCB exit point, then this exit may be bypassed. To restore processing of a resource through the ISGENDOFLQCB exit, the GRS Exit Cache must be cleared. See, ISGGCECR, ClearCache call in *z/OS MVS Programming: Callable Services for High-Level Languages*.

The parameter list passed to ISGENDOFLQCB is mapped by ISGYQCBP (QCBP). The parameter list describes a resource for which the last requester on this system has been DEQed.

Note:

1. This exit is intended for use by OEM serialization products.
2. If your installation is using an OEM serialization product to replace Global Resource Serialization, you should NOT specify that the exit is to be called last (either with the LAST parameter of the SETPROG command or the POS=LAST parameter of the CSVDYNEX macro) when installing this exit.
3. After a call to ISGGCECR, the ISGENDOFLQCB exit can be called again for all resources.
4. If an error occurs in the GRS Exit Cache, the cache is disabled and all resources will again be processed by the ISGENDOFLQCB exit. Re-IPL to restore cache processing.

Replacing the Exit Routine

Unlike RNL changes, GRS does not know how an exit alters the resource identity of a request. Therefore, to maintain data integrity, do not make an exit change that alters the resource identity of any outstanding or in-flight ENQ or DEQ requests. The resource identity consists of the QNAME, RNAME, SCOPE, and hardware reserve status. When you make exit changes, first stop the programs that are currently using the resource, and do not resume the programs until all the exit changes in the GRS complex have completed.

For information regarding dynamic exit routine replacement, see [“Replacing a Dynamic Exit Routine” on page 6](#).

Exit Routine Environment

ISGENDOFLQCB receives control in the following environment:

- Task mode.
- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In primary ASC mode.
- Might be invoked in the cross-memory mode.
- In AMODE 31 and RMODE ANY.
- No locks held or local and CMSEQDQ locks held.
- An EUT FRR might be held when the exit routine is called.

The routine can be invoked in the cross-memory mode with an EUT FRR established that must remain in effect. Therefore, system services or instructions that do not allow FRRs to be active or cause FRRs to be removed cannot be used. This includes the SVC instruction.

Exit Recovery is as follows.

- If an error occurs, the ISGENDOFLQCB exit should provide its own EUT FRR recovery routine.
- An EUT FRR recovery is the only recovery type that can be used. ESTAE-like recovery can be established, but it does not receive control because an EUT FRR might be established on entry.
- If no recovery exists, or the recovery continues with termination, GRS fails the request and continues processing. CSVDYNEX rules for the exit are used to determine whether the exit should be removed.

The unplanned removal of an exit can result in serialization changes. Therefore, it is important to provide recovery and to understand how CSVDYNEX determines when to remove an abend exit.

For more information about CSVDYNEX, see [z/OS MVS Programming: Authorized Assembler Services Reference ALE-DYN](#).

Exit Routine Processing

The ISGENDOFLQCB exit point is called after the last requester for a local resource (SCOPE=SYSTEM, only) DEQs from that resource. The exit routine is passed a QCBP (mapped by ISGYQCBP) which describes the resource that is being deleted.

Programming Considerations

Observe the following conventions when coding an End of Local QCB exit routine:

- Every exit routine must be reentrant.
- You should be aware while coding the exit routine, that because the exit is called for every ENQ, RESERVE, and DEQ request, an increased path length increases processor utilization and can degrade performance.
- Do not code the exit routine to issue the WAIT macro or call a service, such as WTOR, that issues a WAIT.
- Do not code the exit routine to issue another ENQ, RESERVE, or DEQ macro.
- Do not code the exit such that the Local or CMSEQDQ locks are freed.

Entry Specifications

The system passes an QCBP parameter list to the exit routine.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register Contents

0	Not applicable
1	Address of the exit parameter list (ISGYQCBP)
2-12	Not applicable
13	Address of a 72-byte save area
14	Return address
15	Entry point address of ISGENDOFLQCB

Parameter List Contents: Register 1 contains the address of the exit parameter (QCBP) that is mapped by macro ISGYQCBP. Refer to *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the mapping of the ISGYQCBP data area.

Return Specifications

The ISGENDOFLQCB installation exit sets the appropriate request flag in the parameter list to indicate if ISGENDOFLQCB exit routine will be called again.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register Contents

0-14	Restored to contents on entry
15	0

Chapter 44. IXC_ELEM_RESTART — Element Restart Exit

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routine” on page 271](#)
- [“Exit Routine Environment” on page 271](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 272](#)
- [“Programming Considerations” on page 272](#)
- [“Entry Specifications” on page 272](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 273](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 274](#)

Through the IXC_ELEM_RESTART exit, your installation can modify or cancel the automatic restart management-initiated restart of an element. Your installation may use this exit to coordinate the restart of an element with other automation routines, and to make decisions about how, or if, it will be restarted. Automatic restart management (ARM) invokes this exit once for each element that is to be restarted, on the system where it will be restarted.

Installing the Exit Routine

IXC_ELEM_RESTART must be a load module in LPA or in an APF-authorized library in the LNKST concatenation on all the systems in the sysplex that are, or may be, connected to the ARM couple data set. This exit must be linkedited as reentrant.

For general instructions on installing a dynamic exit routine, see [“Link editing a Dynamic Exit Routine into a Library” on page 5](#).

Exit Routine Environment

The element restart exit receives control on the system where the element is to be restarted, in the following environment:

- Task mode
- Supervisor state with PSW key 0
- 31-bit addressing mode
- Primary ASC mode
- Enabled for interrupts
- No locks held

Exit Recovery: Your installation must provide recovery for this exit, if it is critical for the exit to successfully complete its processing. If you do not provide recovery and the exit ends abnormally, MVS restarts proceed without modification.

Exit Routine Processing

MVS invokes the IXC_ELEM_RESTART exit on the system on which the element is to be restarted, just before restarting the element. When MVS is restarting a group of elements from a failing system in the sysplex, MVS first invokes the IXC_WORK_RESTART exit once, so the installation can prepare the new system for additional work, and then invokes the IXC_ELEM_RESTART exit once **for each element** to be restarted.

When the exit routine receives control, MVS passes a parameter list (mapped by the IXCYERE macro) that contains such information as the name of the element to be restarted, the reason for the restart, and the restart method. Based on your knowledge of the installation, the systems in its sysplex, its automation packages and production controllers, and the elements registered with the automatic restart manager, you can design the element restart exit to use the parameter list information to do one of the following:

- Allow MVS to proceed without changes by setting a return code of 0.
- Select a different restart method; for example, request that MVS use a START command instead of persistent JCL.
 1. Check to see what restart methods are available in the EREFLAGS field.
 2. Update the EREJCLDATASET with the name of the data set that contains the JCL that should be used, or update ERESTARTTXT with the new START text that should be used.
 3. Indicate the change in the ERERESTARTTYPE field.
 4. Set a return code of 4.
- Modify the current restart method.
 1. Modify the START command text in ERESTARTTXT, or the JCL in EREJCLDATASET, whichever is appropriate.
 2. Set a return code of 4.
- Cancel the restart of the element.
 1. Indicate in the ERERESTARTTYPE field that the element should not be restarted.
 2. Set a return code of 4.

Programming Considerations

- Code IXC_ELEM_RESTART to be reentrant.
- If you provide new restart text (either a JCL data set name or a started task command), and you use any symbolic substitution parameters (such as &SYSCONE.), they will be resolved using the values from the system on which the element initially registered. If you use symbolic substitution parameters, retrieve the replication ID of the system the element initially registered on, the system the element was previously running on, or the system the element is to be restarted on from the EREHOMESYSTEM field, the EREFROMSYSTEM field, or the ERETOSYSTEM field in IXCYERE.
- Do not code the IXC_ELEM_RESTART exit to perform the restart itself, because the element might not be able to reregister. Use this exit to notify automatic restart management that it should not restart the element. Use a separate program to restart the element, after it has been deregistered. To indicate that this element should not be restarted by automatic restart management, code the following in the IXC_ELEM_RESTART exit:
 - Set ERERESTARTTYPE to X'01' to indicate that automatic restart management should not restart the element.
 - Set a return code of X'4' in register 15.

From another program, use the ENFREQ macro to listen for the deregister ENF signal for the element. Restart the element.

Entry Specifications

MVS passes to IXC_ELEM_RESTART the address of the parameter list mapped by IXCYERE.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

**Register
Contents**

- 0**
Does not contain any information for use by the exit
- 1**
Address of the IXCYERE parameter list
- 2-12**
Does not contain any information for use by the exit
- 13**
Register save area
- 14**
Return address
- 15**
Entry point address of IXC_ELEM_RESTART

Parameter List Contents: Register 1 contains the address of the element restart exit parameter list, which is mapped by the IXCYERE mapping macro. The parameter list contains:

- The job name, element name, and element type.
- An indication of whether the element registered with the ELEMBIND=CURSYS option.
- START command text, persistent JCL, or the data set name containing the JCL that MVS will use to restart the element.
- An indication of how MVS will restart the element (START command, persistent JCL, or JCL in a data set).
- The name of the system where the element will be restarted.
- The name of the system the element was running on when the failure occurred.
- An indication of whether persistent restart text is available or is not available for this element. Persistent restart text is either the JCL or the started task command that was used to previously start this element.
- An indication of whether the exit must supply restart text or the restart will fail and the element will be deregistered.

The IXCYERE mapping is described in *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

MVS expects the exit to return a return code of 0 if no changes to the restart method were requested, or a return code of 4 if a change to the restart method was requested in the ERERESTARTTYPE field of IXCYERE. ERERESTARTTYPE may also be used to indicate that the automatic restart manager should not restart an element.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

**Register
Contents**

- 0-14**
The exit does not have to place any information in these registers, and does not have to restore their contents to what they were when the exit received control.
- 15**
Return code
 - 0**
No changes to the restart method

4

The automatic restart manager should change the restart method as indicated in the IXCYERE parameter list.

Coded Example of the Exit Routine

The following is an example of an IXC_ELEM_RESTART exit.

```
TITLE 'ELEMEXIT - SAMPLE AUTOMATIC RESTART MANAGER ELEMENT RESTART EXIT'
***START OF SPECIFICATIONS*****
*
* MODULE NAME           =   ELEMEXIT
*
* DESCRIPTIVE NAME      =   SAMPLE AUTOMATIC RESTART MANAGER ELEMENT
*                        RESTART EXIT.
*
* FUNCTION              =   THIS EXIT WILL PROHIBIT RESTARTS FOR ELEMENT
*                        TERMINATIONS BUT WILL ALLOW RESTARTS FOR
*                        SYSTEM TERMINATIONS.
*
* OPERATION             =   DETERMINES THE TERMINATION TYPE FROM THE
*                        EVENT CODE IN THE ELEMENT RESTART EXIT
*                        PARAMETER LIST. IF AN ELEMENT TERMINATION IS
*                        INDICATED, THE RESTART TYPE IN THE PARAMETER
*                        LIST WILL BE SET TO RESTART OF NONE AND THE
*                        EXIT'S RETURN CODE WILL BE SET TO FOUR.
*                        IF A SYSTEM TERMINATION IS INDICATED, THE
*                        PARAMETER LIST WILL NOT BE CHANGED AND THE
*                        EXIT'S RETURN CODE WILL BE SET TO ZERO.
*
* ENTRY POINT           =   ELEMEXIT
*
* PURPOSE               =   TO DETERMINE THE WAY IN WHICH AN ELEMENT
*                        WILL BE RESTARTED.
*
* LINKAGE               =   BALR
*
```

```
*
* INPUT DATA           =   REG1  ADDRESS OF THE IXCYERE PARAMETER LIST
*                        REG13  ADDRESS OF STANDARD SAVE AREA
*                        REG14  RETURN ADDRESS
*                        REG15  ENTRY POINT ADDRESS
*
* REGISTERS SAVED       =   REG0 - REG15
*
* REGISTER USAGE        =   REG0  - USED FOR BASING
*                        REG1  - PARAMETER REGISTER
*                        REG2  - NOT USED
*                        REG3  - WORK REGISTER
*                        REG4  - NOT USED
*                        REG5  - POINTER TO IXCYERE
*                        REG6  - NOT USED
*                        REG7  - NOT USED
*                        REG8  - NOT USED
*                        REG9  - NOT USED
*                        REG10 - NOT USED
*                        REG11 - NOT USED
*                        REG12 - MODULE BASE REGISTER
*                        REG13 - POINTER TO A STANDARD SAVE AREA
*                        REG14 - RETURN POINT
*                        REG15 - RETURN CODE
*
* REGISTERS RESTORED    =   REG0 - REG14
*
* CONTROL BLOCKS        =
*   NAME      MAPPING MACRO  REASON USED      USAGE
*   ----      -
*   ERE       IXCYERE       EXIT PARAMETER LIST  R,W
*
* KEY = R-READ, W-WRITE, C-CREATE, D-DELETE
*
* TABLES             =   NONE
*
* MACROS               =   NONE
*
* MESSAGES             =   NONE
*
```

```

*   MODULE TYPE           = CSECT
*
*   ATTRIBUTES            = REENTRANT, REUSABLE, AMODE 31, RMODE ANY
*
*****
EJECT
ELEMEXIT CSECT
ELEMEXIT AMODE 31          31-BIT ADDRESSING MODE
ELEMEXIT RMODE ANY        31-BIT RESIDENCE
SPACE 1

```

```

*****
*
*   REGISTER ASSIGNMENTS
*
*****
REG0 EQU 0          REGISTER 0
REG1 EQU 1          REGISTER 1
REG2 EQU 2          REGISTER 2
REG3 EQU 3          REGISTER 3
REG4 EQU 4          REGISTER 4
EREPTR EQU 5        REGISTER 5 - POINTS TO ERE
REG6 EQU 6          REGISTER 6
REG7 EQU 7          REGISTER 7
REG8 EQU 8          REGISTER 8
REG9 EQU 9          REGISTER 9
REG10 EQU 10        REGISTER 10
REG11 EQU 11        REGISTER 11
REG12 EQU 12        REGISTER 12
BASEREG EQU 12      REGISTER 12 - MODULE BASE
REG13 EQU 13        REGISTER 13
REG14 EQU 14        REGISTER 14
REG15 EQU 15        REGISTER 15
EJECT
*****
*
*   STANDARD ENTRY LINKAGE
*
*****
STM REG14,REG12,12(REG13)  SAVE CALLER'S REGISTERS
BALR BASEREG,REG0          ESTABLISH MODULE BASE
USING *,BASEREG            ESTABLISH ADDRESSABILITY
LR EREPTR,REG1             ESTABLISH ADDRESSABILITY
USING ERE,EREPTR           TO THE ERE
*****
*
*   DETERMINE THE TERMINATION TYPE BASED ON THE INPUT
*   EVENT CODE.
*
*****
SPACE 1
LA REG3,EREELEMTerm
CH REG3,EREEVENTCODE      ELEMENT TERMINATION?
BNE SYSTEM                NO, GO TO SYSTEM TERMINATION
*****
*
*   IF ELEMENT TERMINATION IS INDICATED, THE RESTART TYPE IN
*   THE PARAMETER LIST IS SET TO RESTART OF NONE AND THE
*   EXIT'S RETURN CODE IS SET TO FOUR.
*
*****
MVI ERERESTARTTYPE,ERERESTARTNONE SET RESTART TO NONE
L REG15,FOUR                  SET RETURN CODE TO FOUR
B FINISHED                    GO TO FINISHED

```

```

*****
*
*   IF SYSTEM TERMINATION IS INDICATED, THE PARAMETER LIST
*   IS NOT CHANGED AND THE EXIT'S RETURN CODE IS SET TO ZERO.
*
*****
SYSTEM EQU *
L REG15,ZERO                  SET RETURN CODE TO ZERO
*****
*
*   STANDARD EXIT LINKAGE, AND EXIT FROM THIS MODULE
*
*****
FINISHED EQU *
L 14,12(REG13)              RESTORE CALLER'S

```

IXC_ELEM_RESTART — Element Restart Exit

```

LM      0,12,20(REG13)      REGISTERS
BR      REG14              RETURN TO CALLER
EJECT
*****
*      CONSTANTS      *
*****
DS      0F
ZERO    DC      F'0'      ZERO
FOUR    DC      F'4'      FOUR
EJECT
IXCYERE      ERE
EJECT
END      ELEMEXIT
```


Chapter 45. IXC_WORK_RESTART – Workload Restart Exit

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routine” on page 277](#)
- [“Exit Routine Environment” on page 277](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 278](#)
- [“Programming Considerations” on page 278](#)
- [“Entry Specifications” on page 278](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 278](#)
- [“Coded Example of the Exit Routine” on page 279](#)

Through the IXC_WORK_RESTART exit, your installation can prepare a system to receive additional workload from a failing system in the sysplex. MVS invokes IXC_WORK_RESTART one time on each system that is selected to restart work from a failing system. MVS selects the system most capable of handling the additional work. Because of the system's resources or unusual workload, your installation might want to improve this system's capability. Your installation can do so by coding the workload restart exit to perform tasks such as cancelling lower priority work.

This exit cannot cancel or change the restart of an element. To prevent the restart of an element, or to change how an element will be restarted, see [Chapter 44, “IXC_ELEM_RESTART – Element Restart Exit,” on page 271](#).

Installing the Exit Routine

IXC_WORK_RESTART must be a load module in LPA or in an APF-authorized library in the LNKST concatenation, on all the systems in the sysplex that are, or may be, connected to the automatic restart management (ARM) couple data set. This exit must be linkedited as reentrant.

For general instructions on installing a dynamic exit routine, see [“Link editing a Dynamic Exit Routine into a Library” on page 5](#).

Exit Routine Environment

The workload restart exit receives control on the system where the work is to be restarted, in the following environment:

- Task mode
- Supervisor state with PSW key 0
- 31-bit addressing mode
- Primary ASC mode
- Enabled for interrupts
- No locks held

Exit Recovery: Your installation must provide recovery for this exit, if it is critical for the exit to successfully complete its processing. If you do not provide recovery and the exit ends abnormally, MVS restarts proceed without modification.

Exit Routine Processing

MVS invokes the IXC_WORK_RESTART exit once on each system where elements from a failed system are to be restarted, just prior to any restarts. MVS passes to the exit a parameter list that contains information about the failing system and the elements to be restarted. Design this exit to use the parameter list information, and information about this system and its current workload and resources, to cancel lower priority work or take any other actions necessary to lessen the impact of or prepare for additional work on this system.

You cannot use IXC_WORK_RESTART to cancel or redirect the elements to another system. MVS expects no information on return from this exit, and so will not alter the restarts.

Programming Considerations

- Code IXC_WORK_RESTART to be reentrant.
- Because MVS expects no information on return from the exit, you might want to code the exit to issue a message to indicate successful or unsuccessful processing. You might also code it to issue messages to report whatever actions the exit has taken to prepare the system for the restarts.

Entry Specifications

MVS passes to IXC_WORK_RESTART the address of the parameter list mapped by IXCYWRE.

Registers at Entry: The contents of the registers on entry to the exit are as follows.

Register

Contents

0

Does not contain any information for use by the exit

1

Address of the IXCYWRE parameter list

2-12

Does not contain any information for use by the exit

13

Register save area

14

Return address

15

Entry point address of IXC_WORK_RESTART

Parameter List Contents: Register 1 contains the address of the workload restart exit parameter list, which is mapped by the IXCYWRE mapping macro. The parameter list contains:

- The name of the failing system.
- The number of elements that are to be restarted on this system.
- The names of the elements that are to be restarted on this system.

IXCYWRE is described in *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourceLink/svc00100.nsf/pages/zosInternetLibrary).

Return Specifications

No information is expected on return to MVS.

Registers at Exit: MVS does not use any register contents returned from this exit, so you are not required to place any specific contents in the registers.

Coded Example of the Exit Routine

The following is an example of an IXC_WORK_RESTART exit.

```

TITLE 'WORKLOAD - SAMPLE AUTOMATIC RESTART MANAGER WORKLOAD RESTART EXIT'
***START OF SPECIFICATIONS*****
*
* MODULE NAME           =   WORKLOAD
*
* DESCRIPTIVE NAME      =   SAMPLE AUTOMATIC RESTART MANAGER WORKLOAD
*                          RESTART EXIT.
*
* FUNCTION              =   BASED ON THE NUMBER OF ELEMENTS TO BE
*                          RESTARTED, THIS EXIT WILL CANCEL THE SAME
*                          NUMBER OF JOBS ON THE SYSTEM.
*
* OPERATION             =   DETERMINES THE NUMBER OF ELEMENTS TO BE
*                          RESTARTED FROM THE INPUT PARAMETER LIST. IF
*                          THE NUMBER IS LARGER THAN 10, 10 JOBS WILL BE
*                          CANCELLED. OTHERWISE, THE NUMBER OF JOBS TO
*                          BE CANCELLED WILL BE THE SAME AS THE NUMBER
*                          TO BE RESTARTED.
*
*                          THE JOB NAMES WILL BE OBTAINED FROM AN
*                          INTERNAL LIST AND EACH WILL BE CANCELLED VIA
*                          THE MGCRC MACRO. A WTO WILL BE ISSUED
*                          INDICATING THAT EACH JOB IS BEING CANCELLED.
*
* ENTRY POINT           =   WORKLOAD
*
* PURPOSE               =   TO FREE RESOURCES BY CLEANING UP LOW PRIORITY
*                          WORK ON THE SYSTEM PRIOR TO RESTART.
*
* LINKAGE               =   BALR
*
*
* INPUT DATA           =   REG1  ADDRESS OF THE IXCYWRE PARAMETER LIST
*                          REG13 ADDRESS OF STANDARD SAVE AREA
*                          REG14 RETURN ADDRESS
*                          REG15 ENTRY POINT ADDRESS
*
* REGISTERS SAVED       =   REG0 - REG15
*
* REGISTER USAGE        =   REG0  - PARAMETER REGISTER
*                          REG1  - PARAMETER REGISTER
*                          REG2  - NOT USED
*                          REG3  - WORK REGISTER
*                          REG4  - WORK REGISTER
*                          REG5  - POINTER TO WRE
*                          REG6  - WORK REGISTER
*                          REG7  - WORK REGISTER
*                          REG8  - WORK REGISTER
*                          REG9  - RETURN REGISTER FOR SUBROUTINES
*                          REG10 - NOT USED
*                          REG11 - MODULE DATA REGISTER
*                          REG12 - MODULE BASE REGISTER
*                          REG13 - POINTER TO A STANDARD SAVE AREA
*                          REG14 - RETURN POINT
*                          REG15 - PARAMETER REGISTER
*
* REGISTERS RESTORED    =   REG0 - REG15
*
* CONTROL BLOCKS        =
*   NAME      MAPPING MACRO  REASON USED      USAGE
*   ----      -
*   WRE       IXCYWRE        EXIT PARAMETER LIST  R
*
* KEY = R-READ, W-WRITE, C-CREATE, D-DELETE
*
* TABLES              =   JOB NAME TABLE
*
* MACROS                =   GETMAIN, FREEMAIN, MGCRC, WTO
*
* MESSAGES              =   USER001I

```

IXC_WORK_RESTART — Workload Restart Exit

```

*   MODULE TYPE           = CSECT                                           *
*                                                                    *
*   ATTRIBUTES            = REENTRANT, REUSABLE, AMODE 31, RMODE ANY        *
*                                                                    *
*****
      EJECT
WORKLOAD CSECT
WORKLOAD AMODE 31              31-BIT ADDRESSING MODE
WORKLOAD RMODE ANY            31-BIT RESIDENCE
      SPACE 1

*****
*                                                                    *
*   REGISTER ASSIGNMENTS                                                  *
*                                                                    *
*****
REG0    EQU    0              REGISTER 0
REG1    EQU    1              REGISTER 1
REG2    EQU    2              REGISTER 2
REG3    EQU    3              REGISTER 3
REG4    EQU    4              REGISTER 4
WREPTR  EQU    5              REGISTER 5 - POINTS TO WRE
REG6    EQU    6              REGISTER 6
REG7    EQU    7              REGISTER 7
REG8    EQU    8              REGISTER 8
REG9    EQU    9              REGISTER 9
REG10   EQU    10             REGISTER 10 - CURRENTLY UNUSED
DATAREG EQU    11             REGISTER 11 - DYNAMIC DATA AREA
REG12   EQU    12             REGISTER 12
BASEREG EQU    12             REGISTER 12 - MODULE BASE
REG13   EQU    13             REGISTER 13
REG14   EQU    14             REGISTER 14
REG15   EQU    15             REGISTER 15
      SPACE 1

*****
*                                                                    *
*   EQUATES                                                                *
*                                                                    *
*****
SPINPRVT EQU    230           SUBPOOL VALUE FOR GETMAIN
      EJECT

*****
*                                                                    *
*   STANDARD ENTRY LINKAGE                                                *
*                                                                    *
*****
      STM    REG14,REG12,12(REG13)    SAVE CALLER'S REGISTERS
      BALR   BASEREG,REG0              ESTABLISH MODULE BASE
      USING *,BASEREG                 ESTABLISH ADDRESSABILITY
      LR     WREPTR,REG1              ESTABLISH ADDRESSABILITY
      USING WRE,WREPTR               TO THE WRE

*****
*                                                                    *
*   OBTAIN DYNAMIC STORAGE                                                *
*                                                                    *
*****
      SPACE 1
      LA     REG0,DATAEND              LENGTH OF DATA AREAS
      GETMAIN RU,LV=(REG0),SP=SPINPRVT OBTAIN DYNAMIC STORAGE
      LR     DATAREG,REG1              ADDRESS RETURNED IN REG1
      USING DATAAREA,DATAREG         ADDRESSABILITY TO DYNAMIC      X
      STORAGE

*****
*                                                                    *
*   DETERMINE THE NUMBER OF JOBS TO CANCEL BASED ON THE INPUT          *
*   NUMBER OF ELEMENTS TO BE RESTARTED.  IF THE NUMBER IS              *
*   LARGER THAN 10, 10 WILL BE USED.                                     *
*                                                                    *
*****
      SPACE 1
      LA     REG3,10                  MAX NUMBER OF JOBS TO CANCEL
      L      REG4,WRENUMBEROFELEMENTS NUMBER OF ELEMENTS TO RESTART
      CR     REG4,REG3                IS NUMBER GREATER THAN MAX?
      BL     CANCEL                   NO, GO TO CANCEL
      LR     REG4,REG3                USE THE MAX

*****
*                                                                    *
*   CANCEL THE JOBS SPECIFIED IN THE INTERNAL TABLE VIA THE           *
*   MGCRC MACRO.  ISSUE A WTO INDICATING EACH JOB THAT IS              *

```

```

*          CANCELLED.                                     *
*                                                                 *
*****
CANCEL    EQU    *
          ST      REG4,JOBNUM          SAVE THE NUMBER OF JOBS
          LA      REG3,0              SET COUNTER TO ZERO
LOOP      EQU    *
          LR      REG7,REG3           MANIPULATE COUNTER VALUE TO
          M      REG6,ENTRYLNG        OBTAIN JOBS INDEX VALUE
          LA      REG6,JOBS           GET ADDRESS OF JOBS TABLE
          AR      REG7,REG6           ADD THE DISPLACEMENT
          MVC     JOBNAME(8),0(REG7)  STORE JOB NAME TO BE CANCELLED
          BAL     REG9,ISSMGCRE       ISSUE CANCEL COMMAND
          BAL     REG9,ISSUWTO        ISSUE MESSAGE USER001I
          A      REG3,ONE             INCREMENT COUNTER BY ONE
          C      REG3,JOBNUM          IF COUNTER IS LESS THAN NUMBER
          BL      LOOP               OF ELEMENTS, LOOP
          EJECT ,
*****
*          RETURN THE DYNAMIC STORAGE OBTAINED              *
*****
          LA      REG0,DATAEND        LENGTH OF DATA AREAS
          FREEMAIN RU,LV=(REG0),A=(DATAREG),SP=SPINPRVT      X
          FREE THE DYNAMIC STORAGE AREA
*****
*                                                                 *
*          STANDARD EXIT LINKAGE, AND EXIT FROM THIS MODULE  *
*                                                                 *
*****
FINISHED EQU    *
          LM      REG14,REG12,12(REG13)  RESTORE CALLER'S          X
          BR      REG14                 REGISTERS
          EJECT                        RETURN TO CALLER

```

```

*****
*                                                                 *
*          PROCEDURE - ISSMGCRE                               *
*                                                                 *
*          FUNCTION - ISSUES A CANCEL COMMAND FOR A JOB      *
*                                                                 *
*          INPUT      - REGISTER 11 POINTS TO THE DYNAMIC AREA WHICH CONTAINS *
*                      STORAGE FOR THE MGCRC PARAMETER LIST  *
*                                                                 *
*          OUTPUT     - A CANCEL COMMAND IS ISSUED VIA MGCRC *
*                                                                 *
*          NOTES      - LIST AND EXECUTE FORMS OF MGCRC ARE REQUIRED. *
*                                                                 *
*****
          SPACE 1
ISSMGCRE EQU    *
          LA      REG7,DYNCMDR1        ADDRESS COMMAND REPLY AREA
          MVI     0(REG7),BLANK        BLANK FIRST MESSAGE CHARACTER
          MVC     1(CMDRLNG-1,REG7),0(REG7) BLANK ENTIRE MESSAGE FIELD
          MVC     0(L'CMDLNGTH,REG7),CMDLNGTH INITIALIZE COMMAND LENGTH
          MVC     L'CMDLNGTH(L'TXINSRT1,REG7),TXINSRT1
          *          MOVE CANCEL VERB TO AREA
*****
*          JOBNAME CONTAINS THE JOB NAME VALUE. ENTRYLNG    *
*          CONTAINS THE LENGTH OF THE JOB NAME. USE THESE FIELDS TO *
*          MOVE THE JOB NAME INTO THE TEXT AREA              *
*****
          LH      REG8,ENTRYLNG        JOB NAME LENGTH
          BCTR    REG8,0               DECREMENT BY 1 FOR EXECUTE
          EX      REG8,MOVEJOBN        MOVE JOB NAME VALUE INTO TEXT
          LA      REG4,DYNMGCRC       ADDRESS MGCRC PARAMETER LIST
          MVC     0(REPLEN,REG4),REPAREA COPY MGCRC LIST TO DYNAMIC
          XR      REG6,REG6           CONSOLE ID VALUE OF ZERO
          MGCRC TEXT=(REG7),CONSID=(REG6),MF=(E,(REG4))
          BR      REG9               RETURN TO CALLER
*****
*          OBJECT OF AN EXECUTE                                *
*****
MOVEJOBN MVC TXINSRT2-CMDCANCL(0,REG7),JOBNAME MOVE JOB NAME
          *          INTO CANCEL COMMAND
          EJECT
*****
*                                                                 *
*          PROCEDURE - ISSUWTO                                *
*                                                                 *
*          FUNCTION - ISSUES A MESSAGE INFORMING OPERATOR THAT A JOB IS *

```

IXC_WORK_RESTART — Workload Restart Exit

```

*                BEING CANCELLED                *
*                *                               *
* INPUT      - NONE                            *
*                *                               *
* OUTPUT     - MESSAGE STATING JOB CANCELLED    *
*                *                               *
*****
SPACE 1
ISSUWTO EQU *
```

```

*****
* INITIALIZE MESSAGE TEXT FOR TEXT= PARAMETER ON WTO *
*****
LA REG8,DYNAMTXT          DYNAMIC MESSAGE AREA
MVC 0(USERLENG,REG8),USERMSG1 INITIALIZE MESSAGE TEXT
MVC USERM1VB-USERMSG1(L'USERM1VB,REG8),JOBNAME JOB NAME
MVC DYNUSERS,USERSTAT      MOVE WTO STATIC AREA
SR REG0,REG0              INITIALIZE REGISTER 0 TO ZERO
WTO TEXT=(REG8),ROUTCDE=(11),DESC=(6),MF=(E,DYNUSERS)
*                          ISSUE THE MESSAGE
BR REG9                  RETURN TO CALLER
EJECT

*****
*                *                               *
* JOB NAME TABLE                                *
*                *                               *
*****
JOBS DC CL8'JOB1 '
DC CL8'JOB2 '
DC CL8'JOB3 '
DC CL8'JOB4 '
DC CL8'JOB5 '
DC CL8'JOB6 '
DC CL8'JOB7 '
DC CL8'JOB8 '
DC CL8'JOB9 '
DC CL8'JOB10 '
SPACE 1
*****
* LENGTH AND TEXT OF CANCEL COMMAND *
*****
CMDCANCL EQU *
CMDLNGTH DC XL2'0F'          LENGTH OF CANCEL COMMAND
TXINSRT1 DC CL7'CANCEL '     FIRST STATIC INSERT
TXI1LENG EQU *-CMDCANCL      OFFSET TO TXINSRT1
TXINSRT2 DC CL8'XXXXXXXXX'    PLACE JOB NAME HERE
CMDRLENG EQU *-CMDCANCL      COMMAND LENGTH
EJECT ,
*****
*                *                               *
* LIST FORM OF MGCRE MACRO (STATIC) *
*                *                               *
*****
USERREP DS 0H
REPAREA MGCRE MF=L          LIST FORM OF MACRO
REPLEN EQU *-USERREP        LENGTH OF MGCRE PARAMETER LIST
```

```

*****
*                *                               *
* LIST FORM OF WTO MACRO (STATIC) *
*                *                               *
*****
USERSTAT DS 0H
WTO TEXT=USERMSG1,ROUTCDE=(11),DESC=(6),MF=L
CNCLMSG1 EQU *-USERSTAT      LENGTH OF PARAMETER LIST
SPACE 1
*****
* CONSTANTS *
*****
DS 0F
ENTRYLNG DC F'8'          LENGTH OF JOB NAME TABLE ENTRY
ONE DC F'1'              ONE
BLANK EQU X'40'          BLANK CHARACTER
SPACE 1
*****
* LAYOUT OF MESSAGE TEXT FOR USER001I *
*****
USERMSG1 DS 0H
USERM1LN DC XL2'1C'        LENGTH OF MESSAGE (IN HEX)
USERM1S1 DC C'USER001I CANCELLING ' FIRST STATIC FIELD
```

```

USERM1VB DC      CL8'  '          JOB NAME
USERLENG EQU    *-USERMSG1        LENGTH OF AREA FOR GETMAIN
      EJECT
*****
*                                     *
*      STORAGE DEFINITIONS          *
*                                     *
*****
DATAAREA DSECT
      DS      0F
JOBNUM   DS      F
JOBNAME  DS      CL8
DYNMGCRE DS      CL(REPLEN)        DYNAMIC MGCRC AREA
DYNAMTXT DS      CL(USERLENG)      DYNAMIC MESSAGE TEXT AREA
DYNUSERS DS      CL(CNCLMSG1)      WTO MACRO AREA
DYNMSG1  DS      CL(USERLENG)      DYNAMIC USER001I MESSAGE
DYNCMDR1 DS      CL(CMDRLENG)      DYNAMIC COMMAND REPLY AREA
      DS      0H
      ORG
DATAEND  EQU    *-DATAAREA
      EJECT
      IXCYWRE          WRE
      EJECT
      END      WORKLOAD

```


Chapter 46. Log Stream Subsystem Exit (IXGSEXIT, For Example)

Topics for This Exit Routine Appear as Follows:

- [“Installing the Exit Routine” on page 286](#)
- [“Exit Routine Environment” on page 286](#)
 - Linkage Conventions
 - Exit Recovery
- [“Exit Routine Processing” on page 287](#)
- [“Programming Considerations” on page 290](#)
- [“Entry Specifications” on page 292](#)
 - Registers at Entry
- [“Return Specifications” on page 292](#)
 - Registers at Exit

A specifically-named exit routine is given control for the log stream subsystem exit routine. The exit routine name is provided by the log stream owner, which is identified by the SUBSYS specification on a JCL DD statement or through equivalent dynamic allocation (DYNALLOC) text units, that is, when keys 005F (DALSSNM) and 0060 (DALSSPRM) are provided (see mapping macro IEFZB4D2). If no name is identified on the SUBSYS specification, the logger default exit routine name IXGSEXIT is used.

If the log stream owner has special processing considerations, the log stream subsystem exit routine must be modified. For example, z/OS components logrec and SMF each provide an exit routine for access to log blocks from their respective log streams. The exit routine name for logrec is IFBSEXIT and for SMF is IFASEXIT. Another example is the CICS® exit routine named DFHLGCVN that is used when running the the CICS DFHJUP utility program, which is a batch program used to access CICS log stream data.

Note: The log stream subsystem exit routine can support applications that use QSAM and BSAM (GET and READ) requests in a sequential fashion. The exit routine cannot support applications that attempt to use other access method services when processing the records maintained in a log stream. If other access method services are required by the application or if the application does not intend to obtain records in a sequential fashion, you will need to update the application to make use of the system logger services. QSAM and BSAM support record sizes up to approximately 32 KB. A log stream log block can have record lengths of up to 64K-4. If log blocks (no blocking) or individual records are written with a size greater than what the access methods allow, then applications using the LOGR subsystem will not be able to obtain entire records.

The log stream subsystem exit routine receives control at six different points in the processing of an application's JCL DD statement that has the SUBSYS=(LOGR,exit_routine_name,...) specification. Each point causes the exit routine to be invoked when the DD with the SUBSYS specification is encountered, with the exception of the GET request. The exit routine receives control during GET processing once per GET request from the requesting application. The exit routine can also receive control at five of the six same different points of processing for an application's dynamic allocation request that contains the equivalent text units. The converter exit point call is not made to the exit routine for dynamic allocation requests.

You can use the log stream subsystem exit routine to:

- At the converter exit point:
 - Validate the JCL parameters on the DD's SUBSYS keyword.

- Cause system-type messages to be issued to the job's log.
- Cause the job to end processing because of a JCL error.
- At the allocation exit point:
 - Validate the parameters on the DD's SUBSYS keyword or on the corresponding dynamic allocation text units.
 - Cause system-type messages to be issued to the job's log.
 - Cause the job to end processing because of a JCL error, or, cause a dynamic allocation request to fail because of a text unit error.
 - Establish data areas or obtain resources that will be persistent throughout the other exit points.
- At the open exit point:
 - Connect to the system logger log stream.
 - Start the log stream browse session.
- At the get exit point:
 - Return a record to the requesting application.
- At the close exit point:
 - End the log stream browse session.
 - Disconnect from the system logger log stream.
- At the unallocation exit point:
 - Cause unneeded log blocks to be deleted from the log stream.
 - Disconnect from the system logger log stream.
 - Return data areas or resources that were obtained in prior exit event calls.

Installing the Exit Routine

The log stream subsystem exit routine must be link-edited in its own load module into SYS1.LINKLIB or any APF-authorized library in the LNKLIST concatenation. To activate the exit routine, refresh LLA through the MODIFY LLA,REFRESH command. Do not give the exit routine APF authority. In other words, do not specify the binder option AC(1). That option is only for programs that are designed to run as job step tasks.

To activate the exit routine, refresh LLA through the MODIFY LLA,REFRESH command.

The name of the exit routine is determined by the log stream owner and must match the value in the second positional parameter of the SUBSYS=(LOGR,exit_routine_name,...) DD JCL specification for applications that intend to access records from the owner's log stream. The name of the exit routine must also match its load module and entry point names.

It is the responsibility of the log stream owner to provide the exit routine name to applications that will use the exit routine name to applications that will use the exit. If an exit routine name is not specified on the SUBSYS=(LOGR,exit_routine_name,...) statement, IXGSEXIT is used as a default exit routine name.

Note: To use the log stream subsystem exit routine, the LOGR subsystem must be activated, and the installation must allow authorization for the log stream subsystem exit routine name to be used. For more information, see [Authorization for system logger applications in z/OS MVS Setting Up a Sysplex](#).

Exit Routine Environment

The log stream subsystem exit routine receives control in the following environment:

- Task mode
- Enabled for interrupts and unlocked
- Primary ASC mode

As Table 7 on page 287 shows, other environmental factors for the log stream subsystem exit routine are based on the event that causes the routine to be invoked.

Table 7. Environmental factors for the log stream subsystem exit routine				
Event	Authorization	AMODE	Cross Memory Mode	Considerations
Converter	Supervisor state with PSW key 1	31	PASN = HASN = SASN	The control blocks passed to the exit routine do not reside in the application's address space. The application's address space might even be on a different processor than where converter processing is occurring.
Allocation	Supervisor state with PSW key 1	31	PASN = HASN = SASN	The control blocks passed to the exit routine reside in the application's address space.
Unallocation	Supervisor state with PSW key 1	31	PASN = HASN = SASN	The control blocks passed to the exit routine reside in the application's address space.
Open	Supervisor state with PSW key 1	31	PASN = HASN = SASN	The control blocks passed to the exit routine reside in the application's address space.
Close	Supervisor state with PSW key 1	31	PASN = HASN = SASN	The control blocks passed to the exit routine reside in the application's address space.
Get	State and PSW key of the application, typically problem state and key 8	31	PASN = HASN = SASN	The control blocks passed to the exit routine reside in the application's address space.

Linkage Conventions: The log stream subsystem exit routine is invoked using BALR R14,R15 for each event or purpose.

Exit Recovery: The log stream subsystem exit routine should provide its own recovery. If it does not provide a recovery routine, or if an exit routine error percolates beyond the exit routine's recovery, the system's ESTAEX recovery routine gets control. The ESTAEX records information in the SDWA and requests an SDUMP.

If the exit routine abends, the system does not allow the current point to continue. Based on the specific point, an abend in the exit routine could cause the job or application to end. If the exit routine abends and the log stream owner provides recovery that returns to the normal return point of the invoking routine, the LOGR subsystem does not cause the job or application to end.

Exit Routine Processing

The processing in the exit routine depends on which point caused the exit routine to be invoked.

The exit routine is invoked with register 1 pointing to a word that contains the address of the common parameter list (IXGSXCMP) for the exit routine. Code your exit routine to check IXGSXCMP_EVENT for the type of call for which it was invoked. The IXGSXCMP parameter list contains information that is common to all of the exit calls. In addition, the IXGSXCMP_SPECIFIC_PTR field points to the specific point's parameter list extension.

Converter Call

The log stream subsystem exit routine receives control during JCL converter processing each time a DD statement containing a SUBSYS=(LOGR,exit_routine_name,...) specification is encountered. The purpose of this call is to validate the JCL parameters. It is not meant to build any control blocks based on the JCL parameters; because this processing runs in a different address space, possibly on a different system

from the actual job processing, any control blocks built during this call would not be accessible during later calls.

Before the log stream subsystem exit routine gets control, the LOGR subsystem validates and checks the syntax of the SUBSYS parameters with the exception of *SUBSYS-options2*. If there are any errors, an error return code is returned to the converter. Otherwise, the log stream subsystem exit routine is invoked.

When the log stream subsystem exit routine receives control, it can also validate the input JCL, especially the *SUBSYS-options2* parameters. The *SUBSYS-options2* parameters are unique to each exit routine, so the exit routine must check for syntax errors.

If there are no errors, the job continues processing. If a parsing error occurs, the job ends. If the system provided an error message describing the parsing error, the message is returned so that it can be placed in the job log. If an abend occurs, the job ends.

Allocation Call

The log stream subsystem exit routine receives control during allocation processing each time a DD statement containing a SUBSYS=(LOGR,exit_routine_name,...) specification is encountered. The exit routine can perform similar processing as for the converter call (dynamic allocation does not go through converter processing). You can set the IXGSXCMP_EXIT_TOKEN field to be used as input for the other exit calls.

Before the log stream subsystem exit routine gets control, the LOGR subsystem validates and checks the syntax of the SUBSYS parameters with the exception of the *SUBSYS-options2* parameters. If there are any errors it will return an error return code to allocation. Otherwise it will invoke the log stream subsystem exit routine.

When the log stream subsystem exit routine receives control, it can also validate the input JCL, especially the *SUBSYS-options2* parameters. The *SUBSYS-options2* parameters are unique to each exit routine, so they are the exit routine's responsibility for syntax checking.

If there are no errors, the job continues processing. If a parsing error occurs, the job ends. If the system provided an error message describing the parsing error, the message is returned so that it can be placed in the job log. If an abend occurs, the job ends.

Open Call

The log stream subsystem exit routine receives control during OPEN processing each time a DD statement containing a SUBSYS=(LOGR,exit_routine_name,...) specification is encountered.

When the log stream subsystem exit routine receives control, it might ensure that the log stream can be accessed by the current job or application. When a program issues a log stream connect using the IXGCONN macro, system logger processing will perform the SAF authorization checking. The *xstreamname* to be used on the connect can be obtained from field IXGSXCMP_LOGNAME in data area IXGSXCMP.

After the log stream is connected, the log stream subsystem exit routine can start a browse session. See [z/OS MVS Programming: Assembler Services Guide](#) for more information about a browse session. The SUBSYS parameters have been processed by the LOGR subsystem and the values have been corrected in fields in the IXGSXCMP parameter list. If some of these keywords are not specified, defaults were used. Logger can add new parameters on the SUBSYS-options1 set. New parameters that are added to this set are done in a compatible manner. It is up to the exit routine owner to provide additional support to take advantage of the new options. For example, the VIEW= ACTIVE | ALL | INACTIVE options were newly added as maintenance on HBB6608 and higher releases and on JBB7713.

The exit routine needs to save the log stream connect token and browse token for use on GET exit calls to browse the log stream data. The exit routine needs to save the browse token for use on GET exit calls.

In the IXGSXOCP parameter list, your exit routine can provide the name of the routine to process the GET requests. It might make the exit routine's structure and processing easier to provide a separate routine to handle the GET requests.

When the exit routine returns to the LOGR subsystem, control returns to OPEN processing. If there are no errors, the job continues. If the request was unsuccessful, DFSMS issues an abend for the open failure.

The system can call the subsystem exit routine for open under a task that differs from the task that issued the open. This is due to the principle of concatenation. Consider a case in which a user submits JCL to concatenate (logically join) multiple data sets. Any or all of these could be logger subsystem data sets. Suppose all of them are logger subsystem data sets. Suppose task A opens the concatenation and task B then reads all of the records from the whole concatenation of data sets. As far as task B is concerned, it is reading one large data set. Inside the access method (BSAM or QSAM), when it reaches the end of the first data set, it calls close for that data set and it calls open for the next data set. The system will call the logger subsystem exit routines for close and open under task B, even though task A opened the data sets. Therefore, any code in the close exit that frees storage that was obtained by the open exit must be sharing the subpool between the tasks or the close exit routine must know the address of the TCB that opened the data set so it can direct the FREEMAIN to that task. This works only if the exit is running authorized. The exit can go to the DEB (provided in the open call) to learn the address of the TCB that issued the open from the user.

Get Call

The log stream subsystem exit routine receives control during GET processing each time a GET request from the requesting application containing a SUBSYS=(LOGR,exit_routine_name,...) specification is encountered. The intent of this exit call is to allow a log stream owner the ability to return records from a log stream as if they were being obtained from a conventional data set. This is for QSAM or BSAM requests only.

On GET requests, the LOGR subsystem sets up the input parameter list and passes control to the log stream subsystem exit routine. The log stream subsystem exit routine receives control in the application's state and key (typically problem state, key 8).

The exit routine obtains log stream blocks, deblocks and formats the logical records, if appropriate, and returns them to the application.

After the exit routine returns, the LOGR subsystem returns control to GET processing with a normal or error return code.

Close Call

When the application program issues a CLOSE macro for a log stream data set, the LOGR subsystem calls the log stream subsystem exit routine for the close function. The subsystem also calls the log stream subsystem exit routine for the close function when the application program terminates without closing the DCB. The task termination function of the system will call close on behalf of the application program. Another situation where the subsystem calls the log stream subsystem exit routine for the close function is when the reading program reaches the end of a log stream subsystem data set in a concatenation of data sets and the subject data set is not the last in the concatenation. In this last case, the call might happen under a task that differs from the open function that the application program issued.

When the log stream subsystem exit routine receives control, it might end the log stream browse session established during the Open exit call.

When the exit routine returns to the LOGR subsystem, control returns to CLOSE processing. If there are no errors, the job continues. If the request was unsuccessful, DFSMS issues an abend for the close failure.

Unallocation Call

The log stream subsystem exit routine receives control during Unallocation processing each time a DD statement containing a SUBSYS=(LOGR,exit_routine_name,...) specification is encountered.

The exit routine might need to invoke other system logger functions prior to disconnecting from the log stream. For example, the exit routine can invoke the IXGDELET service to delete log stream blocks from the oldest to the block just before a specified blockid. Optionally, all of the log stream blocks can be deleted on the request.

The exit routine should ensure that all resources that were obtained during the other exit calls are returned to the system. For example,

```
IXGCONN REQUEST=DISCONNECT,STREAMNAME=xstreamname,  
        STREAMTOKEN=xstreamtoken,...
```

The *xstreamname* to be used on the disconnect can be obtained from field IXGSXCMP_LOGNAME in data area IXGSXCMP. The *xstreamtoken* is the value returned on the previous log stream connect request for this DD statement.

If the exit routine used the IXGSXCMP_EXIT_TOKEN field as an anchor for keeping persistent data across the exit calls, the storage should be returned to the system.

If there are no errors, the job continues.

Programming Considerations

If the log stream owner does not have any special processing requirements for handling the SUBSYS parameters and interfacing with the system logger, the system logger default exit routine, IXGSEXIT, might be suitable to satisfy the processing requirements.

You might not want to use IXGSEXIT. You might want to code your own exit routine, for any number of reasons, including:

- Data read from the log stream need to be de-blocked. For example, data might now be written to a log stream in log blocks that contains more than one record of data per block. IXGSEXIT returns only one entire block of data to the caller for each read request.
- Additional processing features are required. IXGSEXIT supports only the FROM, TO, DURATION, and VIEW keywords of the LOGR subsystem. See [z/OS MVS Programming: Assembler Services Guide](#) for more information about the LOGR subsystem keywords.
- IXGSEXIT tries again when a system logger service returns a log stream or a resource-temporarily-unavailable condition.

Consider the following scenario, in which you are given three options. You have an application that writes data to one data set per system in a sysplex. Some users of your application have written tools to read the data using QSAM/BSAM.

Suppose that you change your application to write to a single log stream instead of to system data sets.

You now have three choices:

- Inform your users that they have to write new code and use system logger services to read the data.
- Inform your users that they have to change their JCL and use the LOGR subsystem with the default exit routine, IXGSEXIT.
- Write a log stream subsystem exit routine with more features than IXGSEXIT, and inform your users to change their JCL to use the LOGR subsystem with your exit.

If you decide to write your own log stream subsystem exit routine, code the exit routine to be reentrant. If your exit is in the LNKLIST concatenation, the system loads a new copy of the exit in each address space that invokes it and it does not have to be reentrant. If your exit is in the LPALIST concatenation, the system loads only one copy of the exit.

• Converter Call

The conversion of a job's JCL will take place in a different address space and potentially on a different system image from where the application will run. The exit routine should not attempt to keep persistent data from this invocation of the exit routine to the other invocations of the exit routine.

• Allocation Call

The allocation invocation of the exit routine provides a mechanism for the exit routine to obtain persistent data that can be used in the other invocations of the exit routine.

The IXGSSCMP_EXIT_TOKEN field can be set by the log stream subsystem exit routine during the allocation call and it will then be input to the next exit call for this DD statement.

It is the responsibility of the exit routine to ensure that the resources it obtains are released. If the exit routine obtains any resources that are not explicitly job related, such as common storage, a resource manager routine may need to be established. If an abnormal memory end occurs, close and unallocation processing do not occur, so the exit routine will not receive control through this exit interface.

Note: Log stream data sets can be concatenated. Some special processing by the exit routine is needed to handle this. For example, it must recognize that the DDname (the IXGSXAP_DDNAME field in the IXGSXAP data area) can be blank. The system automatically goes through open and close functions for each data set, although the application does not issue them for each data set.

- Open Call

Field IXGSSCMP_EXIT_TOKEN can be used to pass data from the Allocation call to the Open exit routine. It can also be set as output from the Open exit routine to pass data to the subsequent log stream subsystem exit routine invocations.

It is the responsibility of the log stream subsystem exit routine to establish the correct connection and references to the log stream.

It is possible that Logger will add new parameters on the SUBSYS-options1 set. New parameters that are added to this set are done in a compatible manner. It is up to the exit routine owner to provide additional support to take advantage of the new options. For example, the VIEW= ACTIVE | ALL | INACTIVE options were newly added as maintenance on HBB6608 and higher releases and on JBB7713.

The exit routine needs to save the log stream connect token and browse token for use on GET exit calls to browse the log stream data.

Field IXGSXOCP_IOEXIT_NAME can be updated by the exit routine to identify the name of an exit routine to be invoked on GET requests. This allows a separate exit routine to be invoked and operate in problem program state and key 8 (to aid in protecting system security and integrity).

An end of file condition may be encountered via a specific return/reason code from the IXGBRWSE API or as a result of the exit routine determining that no data meets the input criteria. If the exit routine returns an error condition on the Open call, then DFSMS will fail/ABEND the DD OPEN request. To avoid the OPEN failure condition, the exit routine could indicate the end of file condition in its persistent data area and use that indication on the first GET call. This allows the program that is attempting to read the log stream data to simply receive an end of file (or end of data) condition versus an OPEN failure.

- Get Call

Any special deblocking or formatting of records from a log stream block needs to be performed during this call.

The GET exit routine should recognize any special conditions established during the Open call exit routine processing.

- Close Call

The application program might call the allocation function but not the open or close functions.

The close call frees storage that the open call obtained. The close and open calls to the exit can be made during what the reading program considers a get call. That close call might be made under a task that differs from the task that opened the DCB initially. Therefore, if the exit routine for close wants to free storage that the exit routine obtained for open, the two tasks must share the subpool or the close function must direct the FREEMAIN to the task that handled the first open. The address of the TCB for the task that issued the open for the first data set in the concatenation is in field DEBTCBB in the DEB. See the DEB mapping macro IEZDEB.

- Unallocation Call

When the exit routine is invoked for unallocation, all resources that were obtained by the exit should be returned.

It is the responsibility of the exit routine to ensure that the resources it obtains are released. If the exit routine obtains any resources that are not explicitly job related, such as common storage, a resource manager routine may need to be established. If an abnormal memory end occurs, close and unallocation processing do not occur, so the exit routine will not receive control through this exit interface.

The application program might call the allocation function but not the open or close functions.

Entry Specifications

The LOGR subsystem passes a standard format parameter list and linkage on entry to the log stream subsystem exit routine.

Registers at Entry: The contents of the registers on entry to the exit routine are as follows.

Register

Contents

0

Not applicable

1

Pointer to a full word field containing the address of the common parameter list (IXGSXCMP) of the log stream subsystem exit routine. The high-order bit in the full word field pointed to by register 1 is set on ('1'b) to indicate the end of the input parameter list.

2-12

Not applicable

13

Register save area

14

Return address

15

Entry point address of the exit routine

The contents of the registers on entry to this exit routine are: See *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for the following data areas, which are used as parameter lists: IXGSXCMP, IXGSXCNP, IXGSXAP, IXGSXOCP, IXGSXGP, IXGSXUP, IXGSXMSP, and IXGSXTXT.

Return Specifications

The exit routine can return information in specific output fields in the parameter list and in register 15 to indicate a return code.

Output Parameter Descriptions, Converter are as follows.

IXGSXCNP_ISSUE_MSG

Issue message indicator. The message contained in the area pointed to by IXGSXCNP_MSG_PTR is to be issued as part of the system messages in the job's log. The message area contains a halfword length field followed by the message text. The length of the message text does not include the 2-byte prefix. See *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for data area IXGSXMSP.

Output Parameter Descriptions, Allocation are as follows

IXGSXCMP_EXIT_TOKEN

Exit token. The value returned in this field will be provided as input to the next exit call for this DD.

IXGSXAP_ISSUE_MSG

Issue message indicator. The message contained in the area pointed to by IXGSXAP_MSG_PTR is to be issued as part of the system messages in the job's log (during batch allocation). The message area contains a halfword length field followed by the message text. The length of the message text does

not include the 2-byte prefix. See *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for data area IXGSXMSP.

IXGSXAP_INFO_CODE

DD error information code. Passed back to allocation to identify the reason why the allocation for the DD statement failed.

Output Parameter Descriptions, Open are as follows.

IXGSXCMP_EXIT_TOKEN

Exit token. The value returned in this field will be provided as input to the next exit call for this DD statement.

IXGSXOCP_IOEXIT_NAME

Name of the exit routine to be invoked on GET requests. This exit routine will be loaded into storage and called for the GET exit processing. The field is initialized with the exit name specified as the second positional parameter on the SUBSYS keyword.

Output Parameter Descriptions, GET are as follows.

IXGSXGP_RETURN_CODE

Return code to be passed to the issuer of the GET request. The following values, in decimal, can be set:

IXGSXGP_OK

0 - record is returned in the user's area.

IXGSXGP_PHYSICAL_ERROR

8 - logical error was encountered. The record was not returned in the user's area.

IXGSXGP_SYSTEM_ERROR

24 - the exit routine had an abend or a system error and could not process the request. Do not continue job processing. The record was not returned in the user's area.

IXGSXGP_ERROR_CODE

Error code used to identify the reason for a non-zero value in IXGSXGP_RETURN_CODE. The following values, in decimal, can be set:

IXGSXGP_NO_ERROR

0 - no error was encountered. The field is initialized with a zero.

IXGSXGP_END_OF_DATA

4 - end of data condition was detected. The record was not returned in the user's area.

IXGSXGP_PERM_ERROR

8 - a permanent error condition was detected.

Output Parameter Descriptions, Close are as follows.

IXGSXCMP_EXIT_TOKEN

Exit token. The value returned in this field will be provided as input to the next exit call for this DD statement.

Output Parameter Descriptions, Unallocation are as follows.

IXGSXCMP_EXIT_TOKEN

Exit token. No longer applicable because unallocation is the last in the series of calls.

Registers at Exit: Upon return from the exit processing, the register contents must be as follows.

Register

Contents

0-1

Not relevant

2-14

Restored to contents at entry

15

One of the following return codes:

Return Code	Explanation
-------------	-------------

Value of 0	Job processing is to continue. Refer to specific exit calls for details for these messages.
-------------------	---

Value of 4	Job processing is not to continue. Refer to specific exit calls for details for these messages.
-------------------	---

Value of 20	The exit routine had an abend or logical error and could not process the request. Job processing is not to continue. Refer to specific exit calls for details for these messages.
--------------------	---

Value other than 0 or 4	Treated the same as for return code 20.
--------------------------------	---

Chapter 47. MVS Commands Installation Exit

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routine” on page 295](#)
 - Replacing an MVS Commands Exit Routine Without a ReIPL
 - Deactivating a Command Exit
- [“Exit Routine Environment” on page 296](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 297](#)
 - MVS Commands Exit Routines in a Sysplex Environment
- [“Programming Considerations” on page 298](#)
 - Communication Between the Exits
 - Macro Instructions and Restrictions
 - Security Consideration
- [“Entry Specifications” on page 300](#)
 - Registers at Entry
 - Parameter List Contents
- [“Return Specifications” on page 301](#)
 - Registers at Exit
- [“Coded Example of the Exit Routine” on page 301](#)

The MVS commands installation exit allows you to modify command processing in a system or sysplex. Use one or more MVS commands exit routines to modify command text or modify the MCS authority of consoles that issue commands (for example, to allow a console to issue a command for which it is not authorized).

You can use MVS commands installation exit routines to:

- Change the text of commands
- In a sysplex, change the destination of commands by routing them to a different system for execution
- Modify a console's MCS authority for a particular command. That is, you can use the exit to:
 - Allow the command from a console that normally would not have the MCS authority to issue the command
 - Reject the command from a console that normally would have the MCS authority to issue the command
- Execute commands
- Suppress commands

Installing the Exit Routine

You can insert MVS commands exit routines into the control program by:

- Linkediting the routines into an APF-authorized library as part of the LNKLIST concatenation. Use 31-bit addresses in the routines and assemble them with AMODE 31. RMODE ANY is recommended.
- Specifying the name of each exit routine on the USEREXIT parameter of the .CMD statement of the required MPFLSTxx member of SYS1.PARMLIB. If you specify more than one exit routine, the routines

are called in the order in which they are specified on the .CMD statement. The name of each exit routine can be from 1 to 8 alphanumeric characters.

- Activating the MPFLSTxx member with SET MPF=xx

For more information on how to specify MVS commands exit routines in the MPFLSTxx member of SYS1.PARMLIB, see [z/OS MVS Initialization and Tuning Reference](#).

Replacing an MVS Commands Exit Routine Without a ReIPL: There may be times when you need to replace a commands exit routine, either because you want to add functions to the routine or because the routine abended when it was processing a particular command.

If you want to replace a commands exit routine with a fresh copy, you must do the following:

- Linkedit the new copy of the routine into SYS1.LINKLIB
- Refresh LLA with the MODIFY LLA,REFRESH command
- Reactivate the exit routine using the SET MPF=xx command

Deactivating a Command Exit: There are times when you might want to deactivate a command exit routine, perhaps because its function is not required at particular times or because you want to modify the routine. You can deactivate a command exit routine in one of two ways:

- Specify, on the .CMD statement of the required MPFLSTxx member, the name of a command exit that does not exist in SYS1.LINKLIB, such as 'USEREXIT(NONE)'. Enter the SET MPF=xx command to refresh the MPFLSTxx member.

This action effectively deactivates any command exits that were enabled during the prior MPFLSTxx activation. The system issues an informational message that can be ignored in this case.

- Enter the SET MPF=NO command to disable all active MPFLSTxx members. Remove the exit name from the .CMD statement of the appropriate MPFLSTxx member and enter the SET MPF=xx command to resume MPF processing.



Attention: Entering the SET MPF=NO command deactivates all installation-specified MPF options. IBM-supplied defaults are used until the installation reactivates its MPFLSTxx members.

Exit Routine Environment

MVS commands exit routines receive control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In primary ASC mode.
- With no locks held; they must return control with no locks held.
- In AMODE 31. RMODE ANY is recommended.
- In the address space of the routine that issued the command.

Exit Recovery: The MVS commands exit routines must provide their own level of recovery because, with one exception, the system does not continue to pass control to an exit routine after it abnormally terminates. The exception is when the exit routine is to be deleted and the installation has provided a clean-up routine that will get control for termination calls. When the system calls the exits for deletion, a commands exit routine can invoke the clean-up routine to release any work areas the exits may have created.

See [“Installing the Exit Routine” on page 295](#) for information on how to reactivate the exit routine if it abnormally terminates.

See [“Communication Between the Exits” on page 299](#) for more information on exit routine work areas and clean-up routines.

Exit Routine Processing

The MVS commands exit routines get control whenever a command is issued. Command processing invokes the exit prior to issuing the subsystem interface (SSI) call for command processing.

The MVS commands exit routine parameter list (the CMDX) contains a command buffer (CMDXCLIB). The buffer contains the command text, and the length of the command text, to be processed as it was entered on the console. The exit must place the modified command text and its new length back into this buffer before it returns control to the calling module. The modified command text can be up to 126 bytes long.

Operator commands may contain the following characters:

- A to Z
- 0 to 9
- ' # \$ & () * + , - . / ¢ < | ! ; - % _ > ? : @ " =

The system translates characters that are not valid into null characters (X'00').

If you are modifying the MCS authority of the console for this command in the exit routine, you must place the modified command authority into the CMDXAUTH field in the CMDX. Also you must set the appropriate authority change bits in the CMDXAFLA field in the CMDX.

The CMDX is mapped by the IEZVX101 macro (data area CMDX). See *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for a description of the IEZVX101 mapping.

Changing Command Text with Exit Routines: If a command installation exit changes the text of a command, the system does the following:

- Logs the "new" text of the command (the result of the change by the exit routine)
- Issues message IEE295I to display both the original text and the new text.

If the command installation exit specified system symbols in the new command text, the system *does not* substitute text for those system symbols. The system symbols appear in the new command text in their original format.

To add or change a system symbol in command text and have it processed, the exit can create a copy of the new system symbol text, and then call the ASASYMBM service explicitly to substitute text for the system symbol.

For more information about ASASYMBM, see *z/OS MVS Programming: Assembler Services Reference ABE-HSP*.

See the section on sharing system commands in *z/OS MVS System Commands* for more information about using system symbols in commands.

Considerations for System Symbols: When a command contains system symbols, MVS provides the command text to command installation exits *after* it substitutes text for the system symbols. For example, if the following command is entered to display a console group on system SYS1:

```
DISPLAY CNGRP,G=(CN1GRP&SYSCLONE.)
```

The command installation exit receives the following text (assuming that the default for &SYSCLONE., the last two characters of the system name, is taken):

```
DISPLAY CNGRP,G=(CN1GRPS1)
```

If a command installation exit requires the original command text (the one that existed *before* symbolic substitution), the exit can do the following:

1. Access the CMDXSYMS field in the CMDX to validate that the command was changed by symbolic substitution

2. If the command was changed by symbolic substitution, access the CMDXOLIP field in the CMDX to obtain the address of structure CMDXOLIB, which contains the original command text (before symbolic substitution occurred).

For a description of the IEZVX101 mapping macro, which maps the CMDX, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).

MVS Commands Exit Routines in a Sysplex Environment: In a sysplex, a command can be routed from one system to another. If a .CMD statement specifies MVS commands exit routines in an active MPFLSTxx member for a system, the exit routines on that system are invoked. (For a description of the .CMD statement, see *z/OS MVS Initialization and Tuning Reference*.) Which system executes command exit routines depends on the following:

- If the ROUTE command is used, the MVS commands exit routines, if specified, are invoked on both the system that issued the ROUTE command and the system that received the routed command. However, the exit routines on the target system do not see 'ROUTE'.
- If a command is issued with an L= parameter, and the console addressed is on a different system, only the command exit routines on the system that issued the command are invoked. The exit routines on the system in which the console specified by L= is attached, are not invoked.
- If the MCS command prefix facility (CPF) is used to route a prefix command from one system to another system, only the command exit routines on the receiving system are invoked.
- If commands are directed to a specific system (via the CMDSYS option specified in the CONSOLxx member of SYS1.PARMLIB), only the command exit routines on the receiving system are invoked.

Programming Considerations

When you code an MVS commands exit routine, observe the following conventions:

- The MVS commands exit routines get control **before** the subsystem interface (SSI) passes control to subsystems enabled for function code 10 (command processing SSI call). For information on SSI function code 10, see *z/OS MVS Using the Subsystem Interface*.
- If you specify REMOVE=YES on the CPF macro, the system removes the command's prefix before invoking the MVS commands exit routines. If STRIP is specified for the prefix, the prefix will be stripped before the exit gets control.
- The MVS commands exit routines must be reentrant and serially reusable. Do not use macros with expansions that store information into an inline parameter list.
- Do not code an exit routine that receives control for a command that the routine issues; this causes an endless loop. The exit routine must be coded so that when it receives control for that command, it does not issue the command again.
- If you specify command text, or a text length value, that exceeds the maximum length allowed for that type of command, the system truncates the command.
- The LOGON command has been architected so that all keywords and keyword values appear in the same position when the LOGON command is issued. There are two formats of the command depending on if password phrases are permitted or not.
- A discriminator is provided so you can determine which format is being used. All LOGON commands are issued as if they were issued from a typical console that is 80 columns wide. For the architected LOGON mapping, which is mapped by CNZMYLGN, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).
- When the discriminator value (CNZLGNOPNDPTYPE) is '40'x, use (CNZ_LGNOPNDPW) to map LOGON information when password phrases are not enabled.
- When the discriminator value (CNZLGNOPNDPTYPE) is 'FF'x, use (CNZ_LGNOPNDPP) to map LOGON information when password phrases are enabled.

Note: The system does not substitute text for system symbols specified in the LOGON command.

Communication Between the Exits

Common Data Area: The MVS commands exits receive from the system the address of a 12-byte common data area in the exit routine parameter list. The common data area allows the exit routines to:

- Share data (in common work areas) across invocations.
- Supply the address of an installation-supplied routine that will clean up the common work areas when the exit routines are deleted. Deleted exit routines occur when:
 - MPF terminates (via a SET MPF=NO command) or
 - MPF is refreshed with a new MPFLSTxx that contains a new .CMD userexit name. MPF is then refreshed with that member using the SET MPF=xx command.

Sharing data: To enable your MVS commands exit routines to share data across invocations, code one of the exit routines to:

1. Create work areas in the extended common storage area (ECSA) by issuing a GETMAIN or STORAGE macro.
2. Place the addresses of the work areas in the second and third words of the common data area.

Whenever they are invoked, the MVS commands exit routines can access the common data area to obtain the addresses of the work areas. If the data required by the exits is 8 bytes or less, you can place the data itself within the second and third words of the common data area instead of creating work areas.

Supplying the address of a clean-up routine: You can also use the common data area to hold the address of an installation-supplied clean-up routine that will get control when the exits are to be deleted. The clean-up routine can perform any processing that is usually associated with exit routine work areas (such as releasing storage or clearing a control block). When you want to use a common data area specified clean-up routine, do the following:

1. Code the clean-up routine.
2. Supply the address of the clean-up routine in the first word of the common data area, which is pointed to by CMDXCWKP (the system initializes this field to 0).
3. The clean-up routine will be invoked when:
 - a. MPF terminates or
 - b. MPF is refreshed with a new MPFLSTxx that contains a new .CMD userexit name.
4. The clean-up routine will get control via a BALR 14, 15 instruction with the CMDXCCDA bit set to 1. Register 1 will be a pointer to an address that points to CMDX.

Note: There is a restriction on the data that resides in the first word of a storage pointed to by CMDXCWKP. It MUST be a valid address of your clean-up routine or zero. During command exit termination, the SET MPF processor checks the first word of the storage pointed to by CMDXCWKP, and if it is non-zero BALR 14, 15 is executed, where register 15 contains the first word pointed to by CMDXCWKP. So, if the first word pointed to by CMDXCWKP is not a valid address of a clean-up routine (it contains any non-zero value) an ABEND can be encountered.

Setting up the common data area: Normally, the first exit routine that anchors work areas from the last 8 bytes of the common data area will also initialize the first 4 bytes to the address of the clean-up routine, as shown in Table 8 on page 299.

Table 8. Setting Up the Common Data Area	
Field	Description
Word 1	Address of an installation-supplied clean-up routine that the exit routine calls when it is to be deleted
Word 2	Address of an installation-defined value (such as the address of a work area)
Word 3	Address of an installation-defined value (such as the address of a work area)

The system initializes the common data area to 0; thereafter, the common data area contains whatever values the exit routines place in it.

The exit routines must manage serialization of the common data area.

Individual Data Area

In addition to the common data area, the MVS commands exit routines each receive from the system the address of an individual 8-byte data area (in field CMDXIWKP of the CMDX) whenever they are invoked. Each exit routine can use its individual data area to:

- Pass data to itself (in a work area) across invocations
- Process the data during exit deletion

Passing data to itself: To enable an exit routine to pass data to itself across invocations, code the exit routine to:

1. Create a work area in the ECSA by issuing a GETMAIN or STORAGE macro
2. Place the address of the work area in the individual data area.

To obtain the address of the work area, code the exit routine to access the individual data area. As with the common data area, each individual data area is initialized to zero by the system and subsequently contains whatever values the exit routine places in it.

Processing during exit deletion: A command exit will be invoked once before deletion if its individual work area is non-zero. For this final invocation, the bit CMDXCIDA will be set to 1. The exit should then clean up and free any storage pointed to from the individual work area. Exit deletion occurs when:

1. MPF terminates or
2. MPF is refreshed with a new MPFLSTxx that contains a new .CMD userexit name.

Note: There is NO restriction on the data pointed to by CMDXIWKP. The data can be bits or pointers to other data areas that contain data.

Each exit routine must manage serialization of its individual data area.

Macro Instructions and Restrictions

The MVS commands exit routines can issue system macros, but you should be aware of the following restrictions:

- Do not install an exit routine that issues the WAIT macro or calls a service that issues a WAIT. WAITs and implied WAITs can terminate console communications.
- Do not use macros whose expansions store data into an in-line parameter list.
- Do not issue the GETMAIN or STORAGE macro for subpools that represent space within a region (0 — 127, 240, or 250—252). Because the exit routines execute as part of the control program, they can use subpools 229, 230, and 249.
- Do not issue the DYNALLOC macro. Requesting dynamic allocation functions can cause an abend if your exit is processing a command that originated from a console. To avoid the abend, create a subsystem that runs in its own address space, and request dynamic allocation functions through that subsystem.

Security Consideration

It is the responsibility of your installation to provide any required security for an exit routine that issues system commands. For example, the routine can issue the RACROUTE REQUEST=VERIFYX macro to obtain the user token for a user id that is authorized to the command and then append the security token to the MGCRC macro parameter list. See System Authorization Facility (SAF) in the [z/OS MVS Programming: Authorized Assembler Services Guide](#) for further information on the security interface.

Entry Specifications

On entry, register 1 points to the address of the MVS commands exit parameter list (CMDX).

Registers at Entry: The contents of the registers on entry to the exit are as follows:

**Register
Contents**

- 0** Not applicable
- 1** Address of the pointer to the CMDX
- 2-12** Not applicable
- 13** Register save area
- 14** Return address
- 15** Entry point address of the exit routine

Parameter List Contents: Register 1 contains a pointer to the address of the commands exit parameter list (CMDX). The CMDX is mapped by the IEZVX101 macro (data area CMDX). See *z/OS MVS Data Areas* in the *z/OS Internet* library (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for a description of the IEZVX101 mapping.

Return Specifications

Registers at Exit: Upon return from the exit, the register contents must be:

**Register
Contents**

- 0-14** Restored to contents at entry
- 15** One of the following return codes:

**Return Code
Explanation**

- 0** Indicates that the exit routine requests that the system process the command in the parameter list. The routine takes no action in processing the command itself.
- 2** Indicates that the user is not authorized to issue the command. No more exits are invoked for the command, and the subsystem call is bypassed.
- 4** Indicates that the exit routine (or module called from the routine) has processed the command. On return, the system takes no further action.
- 8** Indicates that the exit (or module called by the exit) should process the command but cannot at this time. The system issues message IEE707I. No more exits are invoked, and the subsystem call is bypassed.

Any value higher than 8 indicates an error condition.

Note: Installation-modified command text is used only when the exit routine returns a 0 return code.

Coded Example of the Exit Routine

The following is a coded example of an MVS commands installation routine that can be used to modify command processing:

```

*****
*
* MODULE NAME      : CMDXIT
*
* DESCRIPTIVE NAME : SAMPLE COMMUNICATIONS TASK INSTALLATION EXIT
*                   MODIFYING DISPLAY COMMANDS.
*
* FUNCTION         : FOR DISPLAY TIME COMMANDS,
*                   THIS EXIT PERMITS THE COMMAND TO BE
*                   ENTERED WITHOUT THE BLANK BETWEEN THE VERB
*                   AND THE PARAMETER. SPECIFICALLY
*                   - DT BECOMES DISPLAY T
*
* OPERATION        : GET THE ADDRESS OF THE COMMAND BUFFER WHICH
*                   IS POINTED TO BY CMDXCLIP.
*                   DETERMINE IF THE COMMAND IS 'DT'. NO
*                   PROCESSING IS DONE IN THIS EXIT FOR ANY
*                   OTHER COMMANDS.
*                   FOR DT CHANGE THE COMMAND TO DISPLAY T.
*
* NOTES            : FIRST 2 BYTES OF THE COMMAND BUFFER
*                   CONTAINS THE LENGTH OF THE COMMAND AND
*                   THE REST OF THE BUFFER CONTAINS THE COMMAND
*                   IMAGE. THE BUFFER IS 128 BYTES LONG.
*
* ENTRY POINT      : CMDXIT
*
* PURPOSE          : ADD A BLANK BETWEEN THE DISPLAY VERB AND
*                   SUBPARAMETER 'T' TO PERMIT A SHORTER FORM
*                   OF THE COMMAND.
*
* LINKAGE          : BALR
*
* INPUT DATA      : REG1 POINTER TO THE ADDRESS OF THE CMDX
*                   : REG13 ADDRESS OF STANDARD SAVE AREA
*                   : REG14 RETURN ADDRESS
*                   : REG15 ENTRY POINT
*
* REGISTERS SAVED  : REG14 - REG12
*
* REGISTER USAGE   : REG0 - PARAMETER REGISTER
*                   REG1 - PARAMETER REGISTER
*                   REG2 - WORK REGISTER
*                   REG3 - WORK REGISTER
*                   REG4 - WORK REGISTER
*                   REG5 - CMDX
*                   REG6 - COMMAND BUFFER
*                   REG7 - UNUSED
*                   REG8 - UNUSED
*
*                   REG9 - UNUSED
*                   REG10 - UNUSED
*                   REG11 - UNUSED
*                   REG12 - MODULE BASE REGISTER
*                   REG13 - STANDARD SAVE AREA
*                   REG14 - RETURN ADDRESS
*                   REG15 - RETURN CODE ON EXIT
*
* REGISTERS RESTORED : REG14 - REG12
*
* CONTROL BLOCKS   :
*
* NAME             MAPPING MACRO      REASON USED          USAGE
* ----             -
* CMDX             IEZVX101            CMD INSTALLATION EXIT  R,W
*                                     PARAMETER LIST
*
* KEY = R-READ, W-WRITE, C-CREATE, D-DELETE
*
* DATA TABLE     : NONE
*
* DATA AREA       : NONE
*
* EXECUTABLE MACROS : WTO
*

```

```

*****
CMDXIT  CSECT
CMDXIT  AMODE 31                31 BIT ADDRESSING MODE
CMDXIT  RMODE ANY              31 BIT RESIDENCE
REG1    EQU 1
REG2    EQU 2
REG4    EQU 4
CMDXPTR EQU 5
BUFFPTR EQU 6
REG12   EQU 12
REG14   EQU 14
REG15   EQU 15
        EJECT ,
        BAKR REG14,0            SAVE CALLER'S REGISTERS
        BALR REG12,0            ESTABLISH MODULE BASE
        USING *,REG12
        L    CMDXPTR,0(REG1)    GET CMDX ADDRESS
        USING CMDX,CMDXPTR      ACCESS THE CMDX
        L    BUFFPTR,CMDXCLIP   GET THE COMMAND BUFFER ADDRESS
        USING CMDXCLIB,BUFFPTR  ACCESS THE BUFFER
        LA   REG2,CMDXCMDI      ACCESS START OF TEXT
        CLC  0(L'DT,REG2),DT    IS THIS DT
        BNE  EXIT              NO, NO PROCESSING FOR COMMAND

```

```

*****
*      PROCESS THE DT COMMAND.      *
*      1. ALTER THE TEXT IN THE COMMAND BUFFER TO D T      *
*      2. INDICATE TEXT CHANGE REQUEST      *
*****
        MVC  CMDXCMDI(L'D_T),D_T    MOVE IN D T
        LA   REG4,L'D_T             GET NEW COMMAND LENGTH
        STH  REG4,CMDXCMDL          STORE NEW COMMAND LENGTH
        OI   CMDXRFL1,CMDXRCMI      REQUEST TEXT CHANGE
EXIT    EQU  *
        XR   REG15,REG15            SYSTEM TO PROCESS COMMAND
        PR
DT      DC   C'DT'                  SHORT FORM OF D T
D_T     DC   C'D T'                REAL D T
        IEZVX101
        END  CMDXIT

```


Chapter 48. MVS Message Service (MMS) Exits

Topics for This Exit Appear as Follows:

- [“Installing the Exit Routines” on page 306](#)
- [“Exit Routine Environment” on page 306](#)
 - Exit Recovery
- [“Exit Routine Processing” on page 306](#)
 - Message Translation
 - Language Query
- [“Programming Considerations” on page 308](#)
 - Macro Instructions and Restrictions
- [“Entry Specifications” on page 308](#)
 - Registers at Entry
 - Parameter Descriptions
- [“Return Specifications” on page 309](#)
 - Registers at Exit
- [“Coded Examples of MMS Exit Routines” on page 310](#)
 - MMSEXIT1: Preventing Translations of a Particular Language
 - MMSEXIT2: Collecting MMS Usage Statistics

The MVS message service (MMS) enables you to translate U.S. English messages into other languages.

If you are routing system messages to a TSO/E extended MCS console, TSO/E will display translated messages in the primary language associated with the TSO/E session. If MMS is active, users of extended MCS consoles on TSO/E can select available languages for message translation and the system can display translated messages on the user's screen. TSO/E terminal users can also receive on their terminals translated TSO/E messages and the translated messages of any application that directs its messages to TSO/E and uses MMS services directly or through TSO/E services. To receive translated messages on TSO/E terminals, you must have TSO/E Version 2.2 installed on your system.

MMS provides two installation exit points that allow you to modify MMS processing. The MMS exits are invoked when application programs issue macros to request the following user functions:

- Message translation
- Language query (to see if a particular language is available).

For information on MMS and MMS user functions, see *z/OS MVS Programming: Assembler Services Guide*.

For information on MMS macros, see *z/OS MVS Programming: Assembler Services Reference ABE-HSP*.

There are two MMS exits: the MMS preprocessing exit and the MMS postprocessing exit. The MMS preprocessing exit is invoked before MMS processes the user function. The MMS postprocessing exit is invoked after MMS processes the user function.

The MMS preprocessing exit can be used to:

- Replace existing translations of selected messages with other installation-defined translations.
- Prevent translation of selected messages.
- Set a local communication word that will be passed to the MMS postprocessing exit. Use this field to pass any information to your postprocessing exit.

The MMS postprocessing exit can be used to:

- Collect MMS usage statistics.

Installing the Exit Routines

The MMS exits must reside in an APF-authorized load library included in the LNKST concatenation.

Statements that identify either an MMS preprocessing exit routine, an MMS postprocessing exit routine, or both, must be specified in the appropriate MMSLSTxx member of SYS1.PARMLIB.

In MMSLSTxx, do the following on an EXIT statement:

- On the NUMBER keyword:
 - To identify an MMS preprocessing exit, specify: (1)
 - To identify an MMS postprocessing exit, specify: (2).
- Specify the module name of the exit routine on the ROUTINE parameter.

For example, to identify both an MMS preprocessing exit (MMSEXIT1) and an MMS postprocessing exit (MMSEXIT2) in an MMSLSTxx parmlib member, specify:

```
EXIT NUMBER(1)  ROUTINE(mmsexit1)
EXIT NUMBER(2)  ROUTINE(mmsexit2)
```

No more than two MMS exit routines can be specified in an MMSLSTxx parmlib member.

For more information on the MMSLSTxx parmlib member, see [z/OS MVS Initialization and Tuning Reference](#).

For general instructions on installing an exit routine, see [“Link editing an Installation Exit Routine into a Library”](#) on page 3.

Replacing the Exit Routines: To replace an MMS exit routine when MMS is active, you must either:

- Modify the MMSLSTxx parmlib member to name a different exit routine on the ROUTINE parameter and issue the SET MMS=xx command to refresh the parmlib member.
- Issue the SET MMS=xx command for the MMSLSTxx parmlib member that names the required MMS exit routine.

For more information on the SET MMS command, see [z/OS MVS System Commands](#).

Exit Routine Environment

The exit routines receive control in the following environment:

- Enabled for interrupts.
- In supervisor state with PSW key 0.
- In AMODE 31 and RMODE ANY.
- In the MMS address space.
- In pageable storage.
- In cross memory mode.

Exit Recovery: MMS provides a functional recovery routine (FRR) to protect the exits.

If the MMS exit routine abends, the system will shut down MMS. The system recovery routine will request an SDUMP that can be used by the installation to debug the exit routine.

Exit Routine Processing

The MMS preprocessing exit routine, if one is defined, is invoked **before** MMS processes the input parameter block (and its related data areas). The MMS postprocessing exit is invoked immediately **after**

MMS processes the input parameter block but before the block has been copied back to the caller's address space.

The system passes the address of the input parameter block to the exits in word 1 of the exit routine parameter list (pointed to by register 1). For message translation, the input parameter block is a message input/output block (MIO), which is mapped by the CNLMMIO macro. For a language query, the input parameter block is a language query block (LQB), which is mapped by the CNLMLQB macro. The exit routines can modify these blocks as needed.

If your installation defines MMS exits, MMS will invoke the exits for both the message translation and language query functions. The system indicates the type of function for which the exit has been invoked in register 0 with one of the following codes:

Code

Meaning

1

Message translation

4

Language query

Message Translation: The MMS exits are invoked each time an application invokes MMS with a request to translate a message (register 0 is set to function code 1). If you code MMS exit routines to modify MMS translation, you will probably modify translations of *selected* messages. For the *majority* of MMS translations, the exit routines will allow the translations to occur without modification (as if the exit routines did not exist).

Allowing MMS Translations to Occur: To allow MMS translation of a message to occur, the exit routines simply return control to the system:

- Without resetting the default of zero that is in the exit processing indicator (pointed to in word 3 of the parameter list)
- With a zero return code in register 15.

The installation application receives the MMS translated message text.

Modifying MMS Translations: When you want to modify MMS translations, use the preprocessing exit routine. The MMS preprocessing exit is invoked **before** MMS translates a message. The exit routine can examine the input message text (pointed to by the MIO control block) and do one of the following:

- Replace the message with installation-preferred message text
- Prevent the message from being translated.

Using the Preprocessing Exit: To replace or prevent MMS translations of selected messages, code the preprocessing exit routine to set the exit processing indicator to a nonzero value and do one of the following:

- Place an installation-defined message in the message output area (also pointed to in the MIO) and return control to the system. The installation-defined message is returned to the application that invoked MMS.
- Return control to the system, thus preventing translation. The original, U.S. English form of the message is returned to the application that invoked MMS.
- Set register 15 to a nonzero value and return control to MMS. The translation request will be terminated.

The exit routine must return a zero return code in register 15. Otherwise, MMS will terminate the translation request.

With one exception, the postprocessing exit routine (if one is defined) will be invoked even when MMS translation is bypassed. The exception is when the preprocessing exit routine indicates an error (by placing a value greater than 8 in a fullword pointed to by word 4 of the exit parameter list). See [“Return Specifications” on page 309](#) (Using Words 4 and 5) for more information.

Using the Postprocessing Exit: The MMS postprocessing exit (if one is defined) is invoked **after** MMS has translated a message, but before the message is returned to the end user.

Like the MMS preprocessing exit routine, the MMS postprocessing exit routine can examine the input message parameters and place installation-preferred message text in the message output area. Because it is invoked after MMS message translation has occurred, the MMS postprocessing exit routine cannot bypass MMS processing. However, the postprocessing exit routine can do one of the following:

- Gather statistics
- Set the exit processing indicator to a nonzero value and return control to MMS. The original, U.S. English form of the message is returned to the application.

Language Query: The MMS exits are invoked when MMS receives a query to determine which languages are available for message translation (register 0 is set to function code 4).

When invoked during a language query, an MMS exit could:

- Collect usage statistics
- Modify the list of languages to be returned to the application (in the LQB).

Programming Considerations

Using Information in the Exit Parameter List:

- The system passes the address of the input parameter block to the exits in word 1 of the exit routine parameter list (pointed to by register 1). For message translation, the input parameter block is a message input/output block (MIO). For a language query, the input parameter block is a language query block (LQB). The exit routines can modify these blocks as needed. For the mappings of the MIO and LQB control blocks, see *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary).
- The system passes to the exit routines the address of a local communication word in word 2 of the exit parameter list. The pre and postprocessing exit routines can use the local communication word to share data (or the address of data) for one user invocation of MMS.
- The system provides the address of the exit processing indicator in word 3 of the exit parameter list. An MMS exit routine can cause MMS processing of a particular message to be bypassed by setting the exit processing indicator to a nonzero value. The exit processing indicator is set to 0 each time MMS invokes the exit.
- The exit routines can indicate processing errors by placing installation-defined return and reason codes in areas pointed to by words 4 and 5, respectively, of the exit routine parameter list. See “[Return Specifications](#)” on page 309 (Using Words 4 and 5) for more information.
- The system passes to the exit routines the address of a 512-byte work area in word 6 of the exit routine parameter list. The exits can use the work area for the current invocation of the service. Additional storage, if required, must be obtained by the exit routines by issuing a STORAGE or branch-entry GETMAIN macro.

Other Considerations:

- Code the exit routines to be reentrant.
- Because the exit routines run in cross memory mode, they cannot issue SVCs.
- The exit routines are invoked each time MMS processes the message translate or language query functions. Therefore, when coding the exit routines, you should be aware that an increased path length will increase processor use and affect performance.
- The exit routines must follow standard linkage conventions.

Macro Instructions and Restrictions: The exit routines can only use services that run in cross-memory mode. See *z/OS MVS Programming: Assembler Services Reference ABE-HSP* for information on services that run in cross-memory mode.

Entry Specifications

MMS passes to the exit the address of the input parameter block (either an MIO or an LQB, depending on the type of request that MMS has been called to process).

Registers at Entry: The contents of the registers on entry to the MMS exit routines are:

**Register
Contents**

0	Type of MMS function the installation application requested (1 for message translation, 4 for language query)
1	Address of the exit parameter list
2-12	Undefined
13	Address of an 18-fullword register save area
14	Return address
15	Entry point address of exit

Parameter Descriptions: Register 1 points to the following list of addresses:

Word 1

The address of an MIO or LQB control block.

- When the exit is invoked for the message translation function, this field will point to the address of an MIO (mapped by macro CNLMMIO).
- When the exit is invoked for the language query function, this field will point to the address of an LQB (mapped by macro CNLMLQB).

Word 2

The address of a local communication word.

Word 3

The address of the exit processing indicator. The indicator is set to 0 by default.

Word 4

The address of an optional, installation-defined return code.

Word 5

The address of an optional, installation-defined reason code.

Word 6

The address of a 512-byte storage area (starting on a double-word boundary) that the exit routines can use for the current invocation of MMS.

Return Specifications

The exit routines return control to the system with:

- A value in the exit processing indicator, pointed to by Word 3 of the exit parameter list.
- Optional, installation-defined return and reason codes, pointed to by words 4 and 5 of the exit parameter list.
- A return code in register 15.

Preprocessing Exit Routine: The exit routine indicates whether to bypass the requested MMS function by setting the exit processing indicator to a nonzero value. If the exit processing indicator is not set, the system will process the function.

Using Words 4 and 5: The preprocessing exit routine can return optional, installation-defined return and reason codes in areas pointed to by words 4 and 5, respectively, of the exit parameter list. When the exit routine sets the exit processing indicator to a nonzero value, the system checks the value in the area pointed to by word 4. The exit routine can indicate that it has encountered a serious error by setting the

field pointed to by word 4 to a value greater than 8. When this happens, MMS terminates the user request. Otherwise, if the field pointed to by word 4 is set to a value of 8 or less, or the exit routine does not set the exit processing indicator, MMS continues processing and the fields pointed to by words 4 and 5 are passed as information to the MMS postprocessing exit routine (if one is defined).

Postprocessing Exit Routine: Like the preprocessing exit routine, the postprocessing exit routine can cause MMS processing to be bypassed by setting the exit processing indicator to a nonzero value and returning control to the system with a zero return code in register 15. However, any values the exit routine places in the fields pointed to by words 4 and 5 of the exit parameter list are not used by the system.

Registers at Exit: Upon return from exit routine processing, the register contents must be:

Register Contents

0,1

Undefined

2-14

Restored to contents at entry

15

One of the following return codes:

Return Code Explanation

0

The exit routine has completed processing.

nonzero

The exit routine has encountered an error. MMS will terminate the user request.

Coded Examples of MMS Exit Routines

This topic contains the following sample MMS exit routines:

- MMSEXIT1. This MMS preprocessing exit routine prevents translation of a particular language.
- MMSEXIT2. This MMS postprocessing exit routine collects MMS usage statistics.

MMSEXIT1 -- Preventing Translations of a Particular Language: In the following example, an installation uses the MMS preprocessing exit routine to prevent MMS from translating messages into Japanese.

The installation places the language code of the language for which translations are to be suppressed (in this case, JPN is the language code) into the CVTUSER field of the CVT so that the exit routine can access it.

When the installation's exit routine is invoked for a translation request, the routine compares the language code in the CVTUSER field with the language code contained in the MIO. When the request is for Japanese translation (MIO contains 'JPN'), the exit routine causes MMS translation to be bypassed by setting the exit processing indicator (pointed to by word 3 of the exit parameter list) to a nonzero value and returning control.

```
MMSEXIT1 CSECT
MMSEXIT1 AMODE 31
MMSEXIT1 RMODE ANY
          STM 14,12,12(13)
          BALR 12,0
          USING *,12

*****
***
***      FOR A TRANSLATION REQUEST, THIS EXIT WILL COMPARE THE
***      LANGUAGE CODE CONTAINED IN THE CVTUSER FIELD OF THE CVT
***      WITH THAT CONTAINED IN THE MIO FOR THIS REQUEST. THIS EXIT
***      ASSUMES THE INSTALLATION HAS UPDATED THE CVTUSER FIELD TO
***      CONTAIN THE DESIRED THREE CHARACTER LANGUAGE CODE. IF THE
***      LANGUAGE CODE CONTAINED IN THE CVTUSER FIELD MATCHES THE
***      CODE IN THE MIO, THE TRANSLATION REQUEST WILL BE
***      TERMINATED BY SETTING THE EXIT PROCESSING INDICATOR
***
```

```

***      TO A NON-ZERO VALUE.
***
***
*****
*
```

```

      C      R0,ONE      TRANSLATION REQUEST?
      BNE    END          NO, END PROCESSING
      L      R3,0(,R1)    OBTAIN MIO ADDRESS
      L      R2,16(0,R0)  OBTAIN CVT ADDRESS
      CLC    CVTUSER-CVT(3,R2),MIOLANG-MIO(R3) COMPARE LANG. CODES
      BNE    END          EXIT IF NOT EQUAL
      L      R3,8(,R1)    OBTAIN PROCESSING
                          INDICATOR ADDRESS C
      MVC    0(4,R3),ONE  SET PROCESS
                          INDICATOR TO C
                          PREVENT TRANSLATION C

END    DS      0H
      LM     14,12,12(13)
      SLR    15,15
      BR     14
*****
ONE    DC      F'1'
R0     EQU     0
R1     EQU     1
R2     EQU     2
R3     EQU     3
*****
      DSECT
      CVT     DSECT=YES
      CNLMMIO
      END     MMSEXIT1
```

MMSEXIT2 -- Collecting MMS Usage Statistics: In the following example, an installation uses the MMS postprocessing exit routine to track the number of successful and unsuccessful (successful=RC0, unsuccessful=nonzero) translations of U.S. English into Japanese.

The installation first creates a work area to contain counters of successful and unsuccessful translations. The routine places the address of the work area in the CVTUSER field of the CVT so that the postprocessing exit routine can find the work area and update the counters.

The installation can use the following MMS postprocessing exit routine to determine whether the translation was successful. Based on the result, the routine updates the appropriate counter in the work area (pointed to in CVTUSER).

```

MMSEXIT2 CSECT
MMSEXIT2 AMODE 31
MMSEXIT2 RMODE ANY
      STM     14,12,12(13)
      BALR    12,0
      USING   *,12
```

```

*****
***      FOR A TRANSLATION REQUEST, THIS EXIT ROUTINE WILL OBTAIN
***      THE ADDRESS OF AN INSTALLATION DEFINED CONTROL BLOCK
***      (POINTED TO BY THE CVTUSER FIELD OF THE CVT CONTROL BLOCK).
***      IF THE INSTALLATION CONTROL BLOCK EXISTS,
***      A CHECK OF THE SUCCESS OR FAILURE OF THE TRANSLATION
***      REQUEST WILL BE MADE AND THE APPROPRIATE SUCCESS/FAILURE
***      COUNTER IN THE INSTALLATION CONTROL BLOCK WILL BE UPDATED.
*****
      C      R0,ONE      TRANSLATION REQUEST?
      BNE    END          NO, END PROCESSING
      L      R2,0(,R1)    OBTAIN MIO ADDRESS
      CLC    MIOLANG-MIO(3,R2),=C'JPN' COMPARE LANGUAGE
                          CODES C
      BNE    END          EXIT IF NOT EQUAL
      L      R2,0(,R0)
      L      R3,CVTUSER-CVT(,R2) OBTAIN INSTALLATION
                          CONTROL BLOCK ANCHOR C
      LTR    R3,R3        INSTALLATION CONTROL BLOCK C
                          PRESENT?
      BZ     END          NO,END
      L      R4,12(,R1)    OBTAIN RETURN CODE ADDRESS
      L      R4,0(,R4)    OBTAIN RETURN CODE
      LTR    R4,R4        TEST RETURN CODE
```

```

      BNZ    FAIL
      L      R5,INSTLSUC-INSTLCB(R3)      OBTAIN SUCCESS COUNTER
      LA     R5,1(,R5)                    BUMP COUNTER
      ST     R5,INSTLSUC-INSTLCB(R3)      SAVE COUNTER
      B      END                          GOTO END
      L      R5,INSTLFAL-INSTLCB(R3)      OBTAIN FAILURE COUNTER
      LA     R5,1(,R5)                    BUMP COUNTER
      ST     R5,INSTLFAL-INSTLCB(R3)      SAVE COUNTER
      DS     0H                          RETURN
      LM     14,12,12(13)
      SLR    15,15
      BR     14
*****
ONE     DC    F'1'
R0      EQU   0
R1      EQU   1
R2      EQU   2
R3      EQU   3
R4      EQU   4
R5      EQU   5
*****
      DSECT
      CVT     DSECT=YES
      CNLMMIO
INSTLCB DSECT
INSTLACR DS    CL4'INST'      INSTALLATION CONTROL BLOCK ACRONYM
INSTLSUC DS    F              LANGUAGE USAGE COUNTER FOR JAPANESE      C
                                SUCCESSFUL TRANSLATIONS
INSTLFAL DS    F              LANGUAGE USAGE COUNTER FOR JAPANESE      C
                                UNSUCCESSFUL TRANSLATIONS
      DS      CL12             RESERVED
INSTLLEN EQU    *-INSTLCB
      END     MMSEXIT2
```

Part 3. Installation Exit Directory

This section contains a list of installation exits that are coded into the various components of MVS and DFP and related program products. Each installation exit has an entry that lists its name and a short description or title that explains its use.

The installation exits listed in this section are described in other publications. The exits are listed by the title and order number of the manual that contains the documentation for the exit.

This directory contains entries for the following components and program products:

- [Chapter 49, “BCP Exits,” on page 315.](#)
- [Chapter 50, “DFSMS Exits,” on page 317.](#)
- [Chapter 51, “IPCS Exits,” on page 319.](#)
- [Chapter 52, “JES2 Exits,” on page 321.](#)
- [Chapter 53, “JES3 Exits,” on page 323.](#)
- [Chapter 54, “RACF Exits,” on page 325.](#)
- [Chapter 55, “RMF Exits,” on page 327.](#)
- [Chapter 56, “TSO/E Exits,” on page 329.](#)
- [Chapter 57, “VTAM Exits,” on page 333.](#)

Chapter 49. BCP Exits

z/OS MVS System Management Facilities (SMF) describes the exits listed in [Table 9](#) on page 315.

Table 9. IFASMF DL and IFASMF DP SMF Log stream and data set dump programs exits (USERx)	
Exit	Description
USER1(name)	Exit routine is given control when the SMF log stream or data set dump programs retrieve an SMF record from the log stream or read a record from the SMF data set. This exit does not receive control for records that contain an extended header.
USER2(name)	Exit routine is given control when the SMF log stream or data set dump programs select a record to be written. This exit does not receive control for records that contain an extended header.
USER3(name)	Exit routine is given control after the output data set is closed by SMF dump program.
USER4(name)	Exit is given control when the SMF log stream or data set dump programs retrieve an SMF record from the log stream or read a record from the SMF data set . This exit receives control for records that contain any standard or extended record header.
USER5(name)	Exit is given control when the SMF log stream or data set dump programs select a record to be written. This exit receives control for records that contain any standard or extended record header.

z/OS MVS Programming: Authorized Assembler Services Guide describes the exit listed in [Table 10](#) on page 315.

Table 10. BCP Exit (authorized assembler)	
Exit	Description
IEAVTRML	Allows installation to supply resource management routines

z/OS MVS Programming: JES Common Coupling Services describes the exits listed in [Table 11](#) on page 315.

Table 11. BCP Exits (JES common coupling services)	
Exit	Description
IXZXIT01	Allows installation to view, modify, or reroute a message or acknowledgement before the message arrives at the receiving member's mailbox.
IXZXIT02	Allows installation to view or modify a message before it is retrieved from a mailbox.
IXZXIT03	Allows installation to attach to or detach from an installation-defined JES XCF group.

Chapter 50. DFSMS Exits

Table 12 on page 317 lists the DFSMS *installation exits*, described in *z/OS DFSMS Installation Exits* and *z/OS DFSMS OAM Planning, Installation, and Storage Administration Guide for Tape Libraries*.

The list in Table 12 on page 317 does not include DFSMS user exits.

Table 12. DFSMS Exits	
Exit	Description
CBRHADUX	Object access method (OAM) auto-delete
CBRUXCUA	Change use attribute installation exit
CBRUXEJC	Cartridge eject installation exit
CBRUXENT	Cartridge entry installation exit
IDAEOVXT	VSAM EOVS installation exit
IEFXVNSL	Automatic volume recognition (AVR) nonstandard label processing
IFG0EX0A	Format-1 DSCB not found during OPEN or EOVS
IFG0EX0B	Take control during OPEN for a DCB
IFG01991	Open, close, end of volume abnormal conditions
IFG0193G	ISO/ANSI/FIPS Version 3 label exits for volume access, file access, label validation, and label validation suppression
IFG_CLOSE_START	Early part of data set close
IFG_OPEN_START	Early part of data set open
IGG_STOW_START	Early part of STOW SVC
IGBDCSX1 IGBDCSX2	DASD precalculation and postcalculation services
IGDACSDC	Automatic class selection (ACS) data class exit
IGDACSSC	Automatic class selection (ACS) storage class exit
IGDACSMC	Automatic class selection (ACS) management class exit
IGG026DU	Catalog pre-initialization
IGG029DM	Process after DADSM SCRATCH failure
IGG029DU	DADSM SCRATCH pre-initialization
IGGDASU3	DADSM SCRATCH postprocessing
IGG030DU	DADSM RENAME pre-initialization
IGGDARU3	DADSM RENAME postprocessing
IGGPREE0 IGGPOST0	System provided DADSM pre-processing and post-processing exit routines, associated with the IGGPRE00_EXIT and IGGPOST0_EXIT dynamic exits, for allocate, extend, scratch, partial release and rename functions.
IGXMSGEX	Customize messages
NSLETRLI	Nonstandard label processing for input trailers
NSLETRL0 NSLCTRLO	Nonstandard label processing for output trailers

<i>Table 12. DFSMS Exits (continued)</i>	
Exit	Description
NSLOHDRI NSLEHDRI	Nonstandard label processing for input headers
NSLOHDRO NSLEHDRO	Nonstandard label processing for output headers
NSLREPOS	Volume verification using the dynamic device reconfiguration (DDR) option for nonstandard label processing
NSLRHDRI	Nonstandard label processing for restarting after a checkpoint
OMODVOL1 EMODVOL1	Volume label editor for open and EOVS

Chapter 51. IPCS Exits

z/OS MVS IPCS Customization describes the exits listed in [Table 13 on page 319](#).

Table 13. IPCS Exits	
Exit	Description
ANALYZE exit	Generate data for contention analysis
ASCB exit	Generate information related to the address space or ASCB being processed
BLSUGWDM validity check routine	Command validation routine for IPCS
Control block formatter exit	Assist in formatting a control block
Control block status (CBSTAT) exit	Perform analysis and generate condensed output describing information relevant to the debugging process
CTRACE buffer find exit	Locate the component trace buffers in a dump for a particular component
CTRACE filter/analysis (CTRF) exit	<ul style="list-style-type: none"> • Perform statistical analysis of the component trace • Provide additional component trace filtering • Limit the number of component trace entries processed
Find exit	Associate a symbol with an AREA or STRUCTURE in a dump
GTFTRACE filter/analysis exit	<ul style="list-style-type: none"> • Do statistical analysis of GTF trace records • Provide additional GTF trace record filtering • Limit the number of GTF trace records processed
GTFTRACE formatting appendage	Format GTF trace records containing a particular FID and EID format in the user range.
Model processor formatting (MPF) exit	Dynamically interact with the formatting service to augment its function
Post-formatting exit	Supply a routine for any type of structure that can be described by a parmlib data statement
Scan exit	Check the validity of an AREA or STRUCTURE in a dump
Task control block (TCB) exit	Generate information related to the task control block (TCB) being processed
Verb exit	Format and print dump data sets created by stand-alone, SVC or SYSMDUMP dumping services

Chapter 52. JES2 Exits

z/OS JES2 Installation Exits describes the exits listed in [Table 14](#) on page 321.

Table 14. JES2 Exits	
Exit	Description
Exit 0	Pre-initialization
Exit 1	Print/Punch Separators
Exit 2	JOB Statement Scan
Exit 3	JOB Statement Accounting Field Scan
Exit 4	JCL and JES2 Control Statement Scan
Exit 5	JES2 Command Preprocessor
Exit 6	Converter/Interpreter Text Scan
Exit 7	JCT Read/Write (JES2)
Exit 8	Control Block Read/Write (USER)
Exit 9	Job Output Overflow
Exit 10	\$WTO Screen
Exit 11	Spool Partitioning Allocation (\$TRACK)
Exit 12	Spool Partitioning Allocation (\$STRAK)
Exit 13	TSO/E Interactive Data Transmission Facility Screening and Notification
Exit 14	Job Queue Work Select — \$QGET
Exit 15	Output Data Set/Copy Select
Exit 16	Notify
Exit 17	BSC RJE SIGNON/SIGNOFF
Exit 18	SNA RJE LOGON/LOGOFF
Exit 19	Initialization Statement
Exit 20	End of Input
Exit 21	SMF Record
Exit 22	Cancel/Status
Exit 23	FSS Job Separator Page (JSPA) Processing
Exit 24	Post-initialization
Exit 25	JCT Read (FSS)
Exit 26	Termination/Resource Release
Exit 27	PCE Attach/Detach
Exit 28	Subsystem Interface (SSI) Job Termination
Exit 29	Subsystem Interface (SSI) End-of-Memory
Exit 30	Subsystem Interface (SSI) Data Set OPEN and RESTART
Exit 31	Subsystem Interface (SSI) Allocation

Table 14. JES2 Exits (continued)	
Exit	Description
Exit 32	Subsystem Interface (SSI) Job Selection
Exit 33	Subsystem Interface (SSI) Data Set CLOSE
Exit 34	Subsystem Interface (SSI) Data Set Unallocation
Exit 35	Subsystem Interface (SSI) End-of-Task
Exit 36	Pre-security Authorization Call
Exit 37	Post-security Authorization Call
Exit 38	TSO/E Receive Data Set Disposition
Exit 39	NJE SYSOUT Reception Data Set Disposition
Exit 40	Modifying SYSOUT Characteristics
Exit 41	Modifying Output Grouping Key Selection
Exit 42	Modifying a Notify User Message
Exit 43	Transaction Program Select/Terminate/Change
Exit 44	JES2 Converter Exit (Main Task)
Exit 45	Pre-SJF Exit Request
Exit 46	Transmitting an NJE Data Area
Exit 47	Receiving an NJE Data Area
Exit 48	Subsystem Interface (SSI) SYSOUT Data Set Unallocation
Exit 49	Job Queue Work Select — QGOT
Exit 50	End of Input
Exit 51	Job Phase Change Exit (\$QMOD)
Exit 52	JOB JCL Statement Scan (JES2 User Environment)
Exit 53	JOB Statement Accounting Field Scan (JES2 User Environment)
Exit 54	JCL and JES2 Control Statement Scan (JES2 User Environment)
Exit 55	NJE SYSOUT Reception Data Set Disposition
Exit 56	Modifying an NJE Data Area before Its Transmission
Exit 57	Modifying an NJE Data Area before Receiving the Rest of the NJE Job

Chapter 53. JES3 Exits

z/OS JES3 Customization describes the exits listed in [Table 15](#) on page 323.

Table 15. JES3 Exits	
Exit	Description
IATUX03	Examine or modify converter/interpreter text created from JCL
IATUX04	Examine the job information from the JCL
IATUX05	Examine the step information from the JCL
IATUX06	Examine DD statement information from the JCL
IATUX07	Examine or substitute unit, type and volume serial information
IATUX08	Examine setup information
IATUX09	Examine final job status, JST and JVT
IATUX10	Generate a message
IATUX11	Inhibit printing of the LOCATE request or response
IATUX14	Job validation/restart LOCATE request or response
IATUX15	Scan an initialization statement
IATUX17	Define set of scheduler elements
IATUX18	Check input authority level for consoles
IATUX19	Examine or modify temporary OSE
IATUX20	Examine or modify data written on job header pages
IATUX21	Create and write data set headers for output data sets
IATUX22	Examine or alter the forms alignment
IATUX23	Examine or modify data written to trailer pages
IATUX24	Examine the Net-id and the devices requested
IATUX25	Examine or modify volume serial number
IATUX26	Examine MVS scheduler control blocks
IATUX27	Examine or alter the JDAB, JCT and JMR
IATUX28	Examine the accounting information as provided by the JOB statement
IATUX29	Examine the accounting information as provided by the JCT, JDAB and JMR
IATUX30	Examine authority level for TSO/E terminal commands
IATUX32	Override the DYNALDSN initialization statement
IATUX33	JES3 control statement and JCL EXEC statement installation exit
IATUX34	JCL DD statement user exit and JCL EXEC statement installation exit
IATUX35	Validity check network commands
IATUX36	Collect accounting information
IATUX37	Modify the JES3 networking data set header
IATUX38	Change SYSOUT class for networking data sets

Table 15. JES3 Exits (continued)	
Exit	Description
IATUX39	Modify the data set header for a SYSOUT data set
IATUX40	Modify job header
IATUX41	Determines the disposition of job over JCL limit
IATUX42	TSO/E interactive data transmission facility screening and notification
IATUX43	Modify job header segments
IATUX44	Examine and modify the JCL
IATUX45	Examine and modify data sent to an output writer FSS
IATUX46	Select processors eligible for C/I processing
IATUX48	Override operator modification of output data sets
IATUX49	Override address space selected for C/I processing
IATUX50	Process user defined BSIDMOD codes for C/I processing
IATUX57	Select a single WTO routing code for JES3 MSGROUTE
IATUX58	Modify security information before JES3 security processing
IATUX59	Modify security information after JES3 security processing
IATUX60	Determine action to take when a TSO/E user is unable to receive a data set
IATUX61	During MDS processing, chooses whether a job should be canceled or sent to the error queue
IATUX62	Overrides the decision to accept a tape or disk mount
IATUX66	Assigns transmission priority to a SNA/NJE data stream
IATUX67	Determines action when remote data set is rejected by RACF
IATUX69	Determines if a message is to be sent to the JES3 global address space
IATUX70	Performs additional message processing

Chapter 54. RACF Exits

z/OS Security Server RACF System Programmer's Guide describes the exits listed in [Table 16](#) on page 325.

Table 16. RACF Exits	
Exit	Description
ICHCCX00	Command exit
ICHCNX00	Command exit
ICHDEX01	RACF password authentication
ICHDEX11	RACF password authentication
ICHPWX01	New password exit
ICHPWX11	New password phrase exit
ICHRCX01	RACROUTE request=AUTH preprocessing
ICHRCX02	RACROUTE request=AUTH postprocessing
ICHRDX01	RACROUTE request=DEFINE preprocessing
ICHRDX02	RACROUTE request=DEFINE postprocessing
ICHRIX01	RACROUTE request=VERIFY preprocessing
ICHRIX02	RACROUTE request=VERIFY postprocessing
ICHLRX01	RACROUTE request=LIST pre/postprocessings
ICHLRX02	RACROUTE request=LIST selection
ICHRSMFE	RACF report writer
IRRACX01	ACEE compression/expansion
IRREVX01	Common command exit
IRRVAF01	Custom Field Validation exit
ICHRFX01	RACROUTE request=FASTAUTH preprocessing
ICHRFX02	RACROUTE request=FASTAUTH postprocessing
ICHRFX03	RACROUTE request=FASTAUTH preprocessing
ICHRFX04	RACROUTE request=FASTAUTH postprocessing

z/OS Security Server RACF Callable Services describes the exit listed in [Table 17](#) on page 325.

Table 17. RACF Exit	
Exit	Description
ICHRTX00	SAF router exit
ICHRTX01	SAF router exit
IRRSXT00	SAF callable services router

Chapter 55. RMF Exits

z/OS Resource Measurement Facility Programmer's Guide describes the exits listed in [Table 18 on page 327](#).

Table 18. RMF Exits	
Exit	Description
ERBMFDUC	Internal processing
ERBMFEVT	User sampler
ERBMFIUC	Monitor I session initialization
ERBMFPUS	Post-processor
ERBMFRUR	Report writer
ERBMFTUR	Termination
ERBTRACE	Field tracing

Chapter 56. TSO/E Exits

z/OS TSO/E Customization describes the exits listed in [Table 19](#) on page 329.

Table 19. TSO/E Exits	
Exit	Description
ADRS exit	Perform additional processing whenever a user selects the ADRS option from the Information Center Facility
REXX attention handling	Perform special attention processing
CHSFEXIT	Change default space parameters that VM/PC servers use to dynamically allocate MVS data sets
Edit exit for RENUM, MOVE, and COPY subcommands	Tailor the way line numbering is done
Edit exit for syntax checkers	Supply syntax checker with data set attributes
REXX exec initialization	Access or update REXX variables
REXX exec processing	Perform special processing before REXX exec executes
REXX exec termination	Access or update REXX variables
ICQAMFX1	Application manager function pre-initialization
ICQAMFX2	Application manager function post-termination
ICQAMPX1	Application manager panel pre-display
ICQAMPX2	Application manager panel post-display
IDYTSINI	TSOLIB initialization
IDYTSTER	TSOLIB termination
IKJADINI	ALTLIB initialization
IKJADTER	ALTLIB termination
IKJCNXCD	CONSPROF pre-display
IKJCNXCI	CONSPROF initialization
IKJCNXCT	CONSPROF termination
IKJCNXAC	CONSOLE activation
IKJCNXDE	CONSOLE deactivation
IKJCNX50	CONSOLE 80% message capacity
IKJCNX60	CONSOLE 100% message capacity
IKJCNXPP	CONSOLE pre-parse
IKJCT43I	EXEC initialization
IKJCT43T	EXEC termination
IKJCT44B	Add installation-written CLIST built-in functions
IKJCT44S	Add installation-written CLIST statements
IKJEESXA	LISTBC failure

Table 19. TSO/E Exits (continued)	
Exit	Description
IKJEESXB	LISTBC termination
IKJEESX0	SEND initialization
IKJEESX1 IEEVSNX1	SEND pre-display
IKJEESX2 IEEVSNX2	SEND pre-save
IKJEESX3 IEEVSNX3	SEND failure
IKJEESX4 IEEVSNX4	SEND termination
IKJEESX5	LISTBC initialization
IKJEESX6	LISTBC pre-display
IKJEESX7	LISTBC pre-list
IKJEESX8	LISTBC pre-read
IKJEESX9	LISTBC pre-allocate
IKJEFD21	FREE initialization
IKJEFD22	FREE termination
IKJEFD47	ALLOCATE command initialization
IKJEFD49	ALLOCATE command termination
IKJEFF10	SUBMIT command
IKJEFF53	OUTPUT, STATUS and CANCEL commands
IKJEFLD	Logon pre-prompt
IKJEFLD1	Logon authorized pre-prompt
IKJEFLD2	Logoff
IKJEFLD3	Logon post-prompt
IKJEFLN1	Logon pre-display
IKJEFLN2	Logon post-display
IKJEFY11	OUTDES initialization
IKJEFY12	OUTDES termination
IKJEFY60	PRINTDS initialization
IKJEFY64	PRINTDS termination
IKJEGASI	TESTAUTH subcommand initialization
IKJEGAST	TESTAUTH subcommand termination
IKJEGAUI	TESTAUTH initialization
IKJEGAUT	TESTAUTH termination
IKJEGCIE	TEST subcommand initialization
IKJEGCTE	TEST subcommand termination
IKJEGMIE	TEST initialization
IKJEGMTE	TEST termination
IKJPRMX1	PARMLIB initialization
IKJPRMX2	PARMLIB termination

Table 19. TSO/E Exits (continued)

Exit	Description
INMCZ21R	TRANSMIT/RECEIVE NAMES data set pre-allocation
INMRZ01 INMRZ01R	RECEIVE initialization
INMRZ02 INMRZ02R	RECEIVE termination
INMRZ04 INMRZ04R	RECEIVE notification
INMRZ05R	RECEIVE acknowledgment notification
INMRZ06R	RECEIVE pre-acknowledgment notification
INMRZ11 INMRZ11R	RECEIVE data set preprocessing
INMRZ12 INMRZ12R	RECEIVE data set postprocessing
INMRZ13 INMRZ13R	RECEIVE data set decryption
INMRZ15R	RECEIVE post-prompt
INMRZ21R	RECEIVE log data set pre-allocation
INMXZ01 INMXZ01R	TRANSMIT startup
INMXZ02 INMXZ02R	TRANSMIT termination
INMXZ03 INMXZ03R	TRANSMIT encryption
INMXZ21R	TRANSMIT log data set pre-allocation
IRXINITX	REXX pre-environment initialization
IRXITTS IRXITMV	REXX post-environment initialization
IRXTERMX	REXX environment termination
Names service exit	Track changes made to Information Center Facility names directories
Session Manager	Initialization/stream monitoring/termination

Chapter 57. VTAM® Exits

VTAM Customization describes the exits listed in [Table 20 on page 333](#).

Table 20. VTAM Exits	
Exit	Description
ISTAUCAG	Calculates and records time during which a terminal user or an application program is logged onto an application program
ISTAUCAT	Validates a logon request to an application program
ISTEXCVR	Provides ACF/VTAM with an ordered list of virtual routes for path selection to transmit data through network
ISTINCDT	User supplies supplementary tables to session-link unformatted system services table which ACF/VTAM uses to handle command input and message output
ISTINCLM	User can change IBM-supplied logon mode table which contains parameters representing protocols for telecommunications session or user can supply supplementary tables
ISTINCNO	User supplies supplementary tables to operation-level unformatted system services tables which handle commands from an ACF/VTAM operator and messages to an ACF/VTAM operator
ISTMGC00	Communication network management (CNM) table routes unsolicited network service requests to application programs to record and report maintenance statistics
ISTPUCWC	Virtual route pacing window size calculator specifies limits to data flow through a network to avoid congestion in nodes along a virtual route
ISTRACON	Module containing constants used to control functions not suitable for modification by operator command or start option

Part 4. MVS Converter / Interpreter Text Processing

Topics for This Section Appear as Follows:

- [Chapter 58, “Issuing Messages through JES Installation Exits,” on page 337](#)
 - Initializing the Converter Message Buffer (CNMB)
- [Chapter 59, “Converter / Interpreter \(C/I\) Text Strings,” on page 339](#)
 - Prefix Information
 - Keyword Information
 - End-of-text Information
- [Chapter 60, “Converter / Interpreter Text String Formats,” on page 341](#)
 - Prefix Format
 - Positional Format
 - Text Format for JDT-defined JCL
 - Extended Statement Type String Positional Parameters
 - Key Entry Format Examples
 - End-of-text Format
- [“Examples of MVS/CI Text Strings” on page 350](#)
- [“User References” on page 350](#)
- [Chapter 61, “Modifying Converter / Interpreter Text,” on page 351](#)
 - Related Documents

The processing of a job control language (JCL) statement includes the stage of converting the JCL statement to C/I text, a form of data that the job entry subsystem (JES) and the job scheduler function of MVS both recognize. The converter takes the job's JCL, merges it with JCL from a procedure library, and converts the composite JCL into C/I text. The converter scans each JCL statement for syntax errors and issues appropriate error messages. The converter also resolves symbolic parameters and assigns default values. The converter / interpreter (C/I) text is further interpreted to build the necessary control blocks needed before the job can be scheduled for execution. See the JES2 exit, Exit 6 (converter/interpreter text scan) in *z/OS JES2 Installation Exits*, and the JES3 exit, IATUX03 (examine/modify converter/interpreter text created for JCL) in *z/OS JES3 Customization* for more information.

Chapter 58. Issuing Messages through JES Installation Exits

After all JCL statements are converted to C/I text, the converter calls a JES installation exit that allows the installation to issue messages to the JCLMSG data set and indicate whether or not the converter should fail the job. The installation must place any desired message in a converter message buffer (CNMB), which is mapped by the IEFCNMB mapping macro. See *z/OS MVS Data Areas* in the *z/OS Internet library* (www.ibm.com/servers/resourcelink/svc00100.nsf/pages/zosInternetLibrary) for more information on the CNMB data area.

The maximum length of a message for a single CNMB is 110 characters. If the CNMBLEN field of a CNMB contains a value greater than 110, the message is truncated at 110 characters. You can chain multiple CNMBs together to pass longer messages. The CNMBNPTR field of the CNMB contains either the address of the next CNMB in the chain or zero if no other CNMBs follow.

Initializing the CNMB:

To initialize the converter message buffer (CNMB):

1. Obtain a buffer from a private area subpool, such as 230, to contain the CNMB. The storage must be obtained in key 1.

You do not need to issue a FREEMAIN in the installation exit since the converter releases the storage for the CNMB after writing the messages to the JCLMSG data set. IBM recommends that you obtain buffer storage

- in multiples of the CNMB mapping size (CNMBSIZE) when NOT issuing messages to the message data set, OR
- in multiples of the CNMB mapping size plus the maximum size of a message text (CNMBSIZE + CNMBMAXL) when issuing messages to the message data set.

This is to ensure that the converter releases the correct amount of storage and that no storage fragmentation occurs.

2. Set the following fields in all cases:

- Set the CNMBID field to CNMBCID (C'CNMB').
- Set the CNMBVER field to CNMBCVER.
- Set the CNMBSUBP field with the subpool number from which the storage was obtained via GETMAIN.

3. Set the following fields if you are issuing a message to the message data set:

- Set the CNMBMSG field with the message text.
- Set the CNMBNPTR field to zeroes or to the address of the next CNMB if you are issuing a message that is longer than 110 characters.
- Set the CNMBMLEN field with the length of the message text. The message text cannot be longer than 110 characters.
- Set the CNMBLEN field based on how much storage was obtained:
 - If the storage is the size of the CNMB mapping plus the size of the message text, set the CNMBLEN field to CNMBSIZE + CNMBMLEN.
 - If the storage is the size of the CNMB mapping plus the **maximum** size of the message text, set the CNMBLEN field to CNMBSIZE + CNMBMAXL.

4. Set the following fields if you are failing the job:

Issuing Messages through JES Installation Exits

- Set the CNMBFJOB bit on in the CNMBOPTS byte to indicate that the converter should fail the job.
Setting the CNMBFJOB bit causes the converter to mark the job as failed when it regains control from the JES installation exit, and the job will not be run.
- Set the CNMBMLEN field to zero if the installation exit is not going to issue a message.

For more information on the JES installation text, see:

- Exit 6 in [*z/OS JES2 Installation Exits*](#).
- IATUX03 in [*z/OS JES3 Initialization and Tuning Guide*](#).

Chapter 59. Converter / Interpreter (C/I) Text Strings

Each C/I text record represents one JCL statement. This record, or text string, is built in an 8192-byte buffer. The length of the used data area of this buffer is specified by a 2-byte field at the beginning of the text string. **If modifications are made, it is the user's responsibility to ensure that the data in this length field is correct.**

The C/I text string for a record contains a hexadecimal value to indicate the statement type, such as JOB statement, EXEC statement, or last DD statement, among others. The text string also contains a specific key value (called the verb key) to identify the type of JCL statement (such as JOB, EXEC, DD).

The information for one type of JCL statement differs from the information for another, depending on the presence of parameters and subparameters. In general, however, the text strings adhere to a common format. Each C/I text record contains prefix information and an end-of-text indicator. In addition, key entries are defined for parameters in the text string. Positional information specified may be represented in the prefix and/or in the key entries.

Prefix Information

The prefix information contains the two-byte field at the beginning that specifies the length of the used data area of this record. The third byte is the statement type. Other prefix information relates specifically to the type of JCL statement (such as, "account number required" on a JOB statement or "SYSOUT data set" on a DD statement). The text string for a JOB statement contains seven bytes of prefix information; all other JCL statements have a prefix section containing five bytes.

Keyword Information

The keyword information defines the associated parameters on a JCL statement. The length of this section of the text string is variable depending on the number of parameters and subparameters. Each keyword (such as DSNAME or UNIT) has a one-byte hexadecimal key associated with it. These key values can be referenced with the mapping macro IEFVKEYS (data area ITK). For **each** of these keywords in the JCL statement, the following information (in this "key entry" format) is included in the text string:

Number of Parameters

1-byte key specifying the number of parameters.

Length

1-byte number specifying the length of the parameter. The high order bit is always off.

Parameter

Variable length string containing the value of the specified parameter.

Number of Subparameters

1-byte number specifying the number of subparameters. The high order bit is always on.

Length

1-byte number specifying the length of the subparameter. The high order bit is always off.

Subparameter

Variable length string containing the value of the specified subparameter.

This key entry format is repeated for each keyword in the JCL statement.

End-of-text Information

The final entry in the text string is the end-of-text key. This entry is required by the MVS interpreter to indicate the end of the text string.

Chapter 60. Converter / Interpreter Text String Formats

The following section describe the formats of converter and interpreter text strings.

Prefix Format

The first three bytes of a text string always contain the string length and the statement type. The string length is a 2-byte length of the entire text string. The statement type is a 1-byte indicator of the type of text string.

The statement type is one of the following values:

- X'01'**
JOB statement text string
- X'02'**
EXEC statement text string
- X'04'**
DD statement text string
- X'08'**
PROC statement text string
- X'10'**
Last statement for this step
- X'20'**
JDT-defined verb string
- X'40'**
JDT-defined JCL appears on this statement
- X'80'**
Extended JCL statement types.

JOB String Prefix

String Length	Statement Type	Job Indicators	BLP Default	Job Verb Key
---------------	----------------	----------------	-------------	--------------

- String Length**
Two-byte length of the entire text string
- Statement Type**
One-byte indicator of the type of text string
- Job Indicators**
Two bytes of job-related information indicators
- BLP Default**
One byte containing the bypass label default
- Job Verb Key**
Verb key for the job text string (X'B4')

- The statement type value for a JOB statement is X'01'.
- Values for the two bytes of job indicators are as follows:
 - Byte 1
 - X'01'**
Account number required

X'02'

Programmer name required

X'04'

Job has been failed

X'08'

Job has a SYSCHK DD statement

X'10'

Flush to restart step name

X'20'

Message header has been written

X'40'

Region value is a default

X'80'

JDT-defined JCL appears in this job's JCL

– Byte 2

X'01'

JDT-defined JCL error in this job's JCL

X'02'

Job is enabled to run with SWA located in virtual storage above 16 megabytes.

- The BLP default is one byte containing the bypass label default.

X'01'

No label

X'10'

Bypass label processing

- The job verb key for the JOB text string is always X'B4'.

EXEC String Prefix

String Length	Statement Type	EXEC Indicators	EXEC Verb Key
---------------	----------------	-----------------	---------------

String Length

Two-byte length of the entire text string

Statement Type

One-byte indicator of the type of text string

EXEC indicators

One byte of EXEC-related information indicators

EXEC Verb Key

Verb key for the EXEC text string (X'94')

- The statement type value for an EXEC statement is X'02'.
- The EXEC indicator field contains one byte of EXEC-related information.

X'01'

Checkpoint restart EXEC statement

X'02'

Step has a STEPCAT DD

X'04'

Step has a STEPLIB DD

X'08'

Statement is from a procedure

X'10'

Step has no DD statements

X'20'

Statement invokes a procedure

- The verb key for the EXEC text string is always X'94'.

DD String Prefix

String Length	Statement Type	DD Indicators	DD Verb Key
---------------	----------------	---------------	-------------

String Length

Two-byte length of the entire text string

Statement Type

One-byte indicator of the type of text string

DD indicators

One byte of DD-related information indicators

DD Verb Key

Verb key for the DD text string (X'6E')

- The DD indicator field contains one byte of DD-related information.

X'01'

DUMMY specified

X'02'

DDNAME= specified

X'04'

DSNAME specified in quotation marks

X'08'

DYNAM specified

X'10'

SYSIN (DD * or DD DATA) data set

X'20'

SYSOUT data set

X'40'

SUBSYS= specified

X'80'

Statement is from a procedure

- The verb key for the DD text string is always X'6E'.

JDT String Prefix

String Length	Statement Type	JDT Indicators	JDT Verb Key
(none)	(none)	(none)	(none)

String Length

Two-byte length of the entire text string

Statement Type

One-byte indicator of the type of text string

JDT indicators

One byte of JDT-related information indicators (all reserved)

JDT Verb Key

Verb key for the JDT text string (X'BE')

- The JDT indicator field contains one byte of JDT-related information and is reserved.

X'20'

The statement is regenerated.

X'40'

Statement is generated.

X'80'

Statement is from a PROC.

- The verb key for the JDT-defined text string is always X'BE'.

Extended Statement Type String Prefix

String Length	Statement Type	Statement Indicators	Verb Key
---------------	----------------	----------------------	----------

String Length

Two-byte length of the entire text string

Statement Type

One-byte indicator of whether this is an extended statement type (always set to X'80')

Statement indicator

Two bytes of extended statement type indicators

Verb Key

Verb key for the extended statement text string

- The statement indicator field contains one byte that indicates one of the following statement type values:

X'80'

IF statement

X'40'

ELSE statement

X'20'

ENDIF statement

- The verb key for the extended statement type text string is equal to the extended statement type value.

Positional Format

Positional parameters specified may be represented in the prefix and/or in the key entries depending on the particular parameter. The following section describes the manner in which each positional parameter is represented.

JOB String Positional Parameters

```
//JOB1 JOB (1234,ABCD), 'John Doe'
```

Key	No.Parms	Length Jobname	Jobname	Sublist/ no. elements	Length Account Par 1	Account Info. Par 1	Length Account Par 2	Account Info. Par 2	Length Name	Programmer Name
B4	03	04	JOB1	82	04	1234	04	ABCD	08	John Doe

- The statement label is the first parameter on the job verb key.
- Accounting information is the second parameter on the job verb key.
- Programmer name is the third parameter on the job verb key.

```
//JOB1 JOB (1234), 'John Doe'
```

Key	No. Parns	Length Jobname	Jobname	Sublist / no. elements	Length Account parm#1	Account Info.	Length Name	Programmer Name
B4	03	04	JOB1	81	04	1234	08	John Doe

- The statement label is the first parameter on the JOB verb key.
- Accounting information is the second parameter on the JOB verb key.

Note: Enclosing the accounting information within parentheses indicates that the information is in the form of a subparameter list. In this case, the subparameter list has one element (1234).

- Programmer name is the third parameter on the JOB verb key.

EXEC String Positional Parameters

The verb key for an EXEC statement is always X'94'. When executing a procedure, the positional parameters associated with the EXEC statement depend on whether the statement has been coded with the PROC= keyword or not.

- When no PROC= keyword is used, the text string for the statement contains two positional parameters on the EXEC verb key.

```
//STEP1 EXEC PROC1
```

1. The statement label (STEP1) is the first parameter on the EXEC verb key.
2. The PROC name (PROC1) is the second parameter on the EXEC verb key.

Verb Key	Number Parameters	Label Length	Label	Proc Length	Proc Name
94	02	05	STEP1	05	PROC1

- When the PROC= keyword is used, the text string contains a verb key for the EXEC statement (X'94') and also a PROC key for the PROC= keyword (X'8B'). The text string for the statement contains one positional parameter on each key.

```
//STEP1 EXEC PROC=PROC1
```

1. The statement label is the first parameter on the EXEC verb key (X'94').
2. The PROC name is the first parameter on the PROC key (X'8B').

Verb Key	Number Parameters	Label Length	Label	Proc Key	Number Parameters	Proc Length	Proc Name
94	01	05	STEP1	8B	01	05	PROC1

DD String Positional Parameters

There are two instances when a positional parameter is represented by key entries in the text string for a DD statement. When a DD statement specifies DD DYNAM, the DD indicator in the prefix is set to X'08'. When it specifies DD DUMMY, the DD indicator is set to X'01'. In both of these cases, a key entry containing the respective key value and one parameter of length zero is added to the text string.

If a DD statement specifies DD * or DD DATA, the DD indicator in the prefix is set to X'10'. No other key entry is defined in the text string for these positional parameters.

Text Format for JDT-defined JCL

- JDT-defined verbs

```
//OUTPUT1 OUTPUT .....
```

Verb Key	Number Parameters	Verb Length	Verb	Label Length	Label
BE	02	06	OUTPUT	07	OUTPUT1

- The JDT-defined verb is the first parameter on the verb key (X'BE').
- The statement label is the second parameter on the verb key (X'BE').
- JDT-defined keywords

```
//DD1      DD  ACCODE=A
```

Long Parameters: The length of some parameters, such as a pathname for an hierarchical file, can be up to 255 bytes. Any parameter with a maximum length that is over 127 bytes is represented in the key entry format as a subparameter list within the key for the parameter. Each subparameter has a maximum length of 127 bytes.

The PATH parameter is used to specify the pathname:

```
//ddname DD PATH=pathname
```

Example 1: In the following example, the PATH parameter has 6 characters:

```
//DD2 DD PATH='/name1'
```

Even though the pathname parameter is only 6 bytes, it must be represented as a subparameter list because the maximum length of the pathname can be 255 bytes.

Table 21. Text Format for Long Parameters: Example 1

Key	Number Parameters	Key Length	JDT-Defined Key for Specified Keyword	Number Sub-parameters	Parameter Length	Parameter Value
1A	02	02	X'8017'	81	6	X'61D5C1D4C5F1'

Example 2: In this example, the PATH parameter has 130 characters:

```
// DD2 DD PATH='/NAME11111/NAME22222/NAME33333/NAME44444/NAME55555/NAME6  
// 6666/NAME77777/NAME88888/NAME99999/NAME00000/NAME11111/N  
// AME22222/NAME33333'
```

It would be represented as shown in Table 22 on page 346.

Table 22. Text Format for Long Parameters: Example 2

Key	Number Parameters	Key Length	JDT-Defined Key for Specified Keyword	Number Subparameters	Parameter Length	Parameter Value
1A	02	02	X'8017'	82	7F	X'61D5C1D4C5F1F1F1F1,,,61D5C1D4C5F3F3'
					03	X'F3F3F3'

Because only 127 characters can fit in a single subparameter field, the parameter must be represented as two subparameters. Therefore, the Num_of_Subparameters field is 82.

- The first subparameter is 'X'7F' (127 decimal) bytes long, and its value in the C/I text is the hex string representing the first 127 characters of the PATH parameter value in the JCL.
- The second subparameter is 3 bytes long, and its value in the text is the hex string representing the last 3 bytes of the PATH parameter value.

Pre-MVS/ESA SP 4.1: For JCL converted on a pre-MVS/ESA SP 4.1 system, the JDT-defined keyword is the first parameter on the JDT key (X'1A').

Key	Number of Parameters	Keyword Length	Keyword	Parameter Length	Parameter
1A	02	06	ACC0DE	01	A

- The parameter on the JDT-defined keyword is the second parameter on the JDT key (X'1A').

MVS/ESA SP 4.1: For JCL converted on an MVS/ESA SP 4.1 system, the JDT-defined key for the specified JDT keyword is the first parameter on the JDT key (X'1A'). For JDT-defined keywords on the DD statement, refer to the macro IEFSJKEY. For JDT-defined keywords on the OUTPUT statement, refer to the macro IEFDOKEY.

Key	Number of Parameters	Key Length	JDT-Defined Key for the Specified Keyword	Parameter Length	Parameter
1A	02	02	X'8001'	01	A

- The parameter on the JDT-defined keyword is the second parameter on the JDT key (X'1A').

Extended Statement Type String Positional Parameters

```
//IFBAD IF (STEP1.RC > 4) THEN
```

Key	BF
Number of Name Parmeters	00 02
Number of Name Qualifiers	01
Length of Qualifier	05
Subject of Test	03
Length Compared Value	04
Compared Value	4
Type of Comparator	0C
Number of Comparators	01
Length	01
Comparator	>

- The qualifier specifies the step and procedure level of the statement.
- The possible values for the "Subject of Test" field are:

X'01'

Job level return code

X'02'

Step level return code (within the procedure)

X'03'

Return code

X'04'

Job abend code

X'05'

Step abend code (within the procedure)

X'06'

User abend code

X'07'

System abend code

X'08'

Job abend code

X'09'

Step abend code

X'0A'

Processed/run

- The "Type of Comparator" field can be set to either of the following values:

X'0B'

Boolean comparator (such as | or &);

X'0C'

Mathematical operator (such as < or >)

Key Entry Format Examples

SPACE=(TRK,(30,10))

Key	Number Parms	Length	Parameter	Number Sub-parm	Length	Parameter	Length	Parameter
47	02	03	TRK	82	02	F3F0	02	F1F0

The key X'47' represents the keyword SPACE=, which has two parameters — TRK and (30,10). The first parameter, TRK, has a length of 3. The second parameter is made up of two subparameters and the high order bit of that field is on (X'82'). The length of each subparameter is 2; the values are given in EBCDIC.

VOL=SER=111111

Key	Number Parms	Key	Number Parms	Length	Parameter
43	00	4F	01	06	F1F1F1F1F1F1

The key X'43' represents the keyword VOL=. The subparameter keyword, SER=, is considered a minor keyword and is assigned a unique key entry. Therefore SER= will not be defined in the key entry for the keyword (VOL=) on which it appears. VOL= (key X'43') then has no parameters. SER= (key X'4F') has one parameter with a length of 6. The value of this parameter (111111) is given in EBCDIC.

Referral Type Data

Referral type data is represented in the key entry format as subparameter fields. The pieces of the parameter are defined as delimited by periods. Each piece of the referred-to data is identified by its length and name in the order in which it appears in the statement. The asterisk is the first subparameter defined.

//DD1 DD DCB=*.STEP1.DD1

Key	Number Parameters	Number Subparms	Length	*	Length Piece 1	Piece 1	Length Piece 2	Piece 2
40	01	83	01	*	05	STEP1	03	DD1

- The asterisk is the first subparameter.
- The remaining subparameters are the pieces of the referred-to data delimited by periods.

Note: In the “number of subparameters” field, the high-order bit is always set on.

Data Set Name with Member Name

A data set name that includes a member is represented in the key entry format as subparameter fields within the key for the parameter. The data set is identified as the first subparameter; the member name is the second subparameter.

//DD1 DD DSN=THIS.DATA1(MEMBER1)

Key	Number Parm	Number Subparms	Length DS Name	Data set Name	Length Member	Member Name
4A	01	82	0A	THIS.DATA1	07	MEMBER1

- The data set name is the first subparameter.
- The member name is the second subparameter.

Overrides of Parameters

Keywords that override EXEC statement keywords within a procedure appear in the text string for the EXEC statement for the procedure. The values specified for the overridden keywords are applied to the EXEC statement during conversion.

```
// EXEC PROC=PROCA,TIME.STEP1=2,PARM.STEP2='ABCD'
```

Proc Key	Number Parameters	Proc Length	Proc Name
8B	01	05	PROCA

Key	Number Parameters	Step Length	Step Name	Parm Length	Parm
8F	02	05	STEP1	01	F2

Key	Number Parameters	Step Length	Step Name	Parm Length	Parm
8E	02	05	STEP2	04	ABCD

DD statements that override DD statements within a procedure are merged with the overridden statement as the statements are converted. The resulting text string contains the result of the merged statements. The merging of the statements keeps all the keywords present on the overridden statement as long as they are not explicitly overridden or are not mutually exclusive with a keyword already specified on the overriding statement.

```
//DD1 DD SYSOUT=A,DCB=(LRECL=133,DSORG=PS)
```

is overridden by

```
//STEP1.DD1 DD DSN=XYZ,DCB=LRECL=80,DISP=SHR
```

The keywords are merged so that overridden parameters are replaced and mutually exclusive parameters are nullified. The resulting text string contains

```
//DD1 DD DSN=XYZ,DCB=(LRECL=80,DSORG=PS),DISP=SHR
```

End-of-text Format

This final entry, after return from the installation's converter / interpreter (C/I) text exit, if any, (that is, Exit 6 in JES2, Exit IATUX03 in JES3), signifies the end of the text string with an end-of-text key. (Prior to and within the C/I text exit, if any, the end-of-text format is just the **FE** key, with nothing following it.)

Key	Number Parm	Length	Proc Level	Length	Statement Number
FE	02	01		04	

The procedure nesting level is a value between 0 and 15 inclusive, and is obtained as follows:

- JOB-level statements (not in a procedure) are level 0.
- Statements within the first procedure level are level 1.

Examples of MVS/CI Text Strings

- The nesting level is incremental for each successive level of procedure nesting.
- The nesting level is not affected by INCLUDE statement nesting.

See [z/OS MVS JCL Reference](#) for more information on procedure nesting.

Note that the system ignores JCL comment statements when computing the statement number.

Examples of MVS/CI Text Strings

```
//SYSUT1 DD DSN=LINKEDIT.WORK,UNIT=3380,SPACE=(TRK,(30,10)),  
//          VOL=SER=111111
```

Prefix and Statement Label (SYSUT1)

String Length	Type	DD Ind.	DD Verb Key	Number Parms	Length	Parameter
003D	04	00	6E	01	06	SYSUT1	

DSNAME=LINKEDIT.WORK,

Key	Number Parms	Length	Parameter
4A	01	0D	LINKEDIT.WORK	

UNIT=3380,

Key	Number Parms	Length	Parameter
41	01	04	F3F3F8F0	

SPACE=(TRK,(30,10)),

Key	Number Parms	Length	Parameter	Number Subparm	Length	Parameter	Length	Parameter
47	02	03	TRK	82	02	F3F0	02	F1F0	

VOL=SER=111111

Key	Number Parms	Key	Number	Length	Parameter
43	00	4F	01	06	F1F1F1F1F1F1	

User References

You can find additional information about C/I text in MVS macros. The C/I text format is mapped in the macro IEFTXTFT. The table of converter/interpreter key definitions is mapped in the macro IEFVKEYS (data area ITK).

Chapter 61. Modifying Converter / Interpreter Text

Both JES2 and JES3 provide installation exit points for scanning the text created by the converter. You can use these exits to decide whether JES should cancel the job or allow it to continue normally. Your routine also can modify the C/I text. You cannot add text for an additional JCL statement, but you can add parameters to an existing JCL statement. You cannot delete the text for an entire JCL statement, but you can delete some of the parameters on that statement.

Use Caution When Modifying C/I Text. At the exit point at which the text is made available to your routine, the data already has been validated for syntax and for the proper keywords. The converter **does not** repeat this validation process after any modifications that you make. Therefore, there is no way to correct any error that a modification to the C/I text causes, and the job might fail at a later point in processing.

MVS creates the C/I text and uses it in its preparation for executing your job. IBM recommends that you do not modify this text. If you decide to do so, use the following guidelines:

The interpreter needs to have all the correct lengths, the number of parameters, and the end-of-text key (X'FE') in order to parse the text string. You must ensure that the length of the entire text string (in the prefix) and the values for the length and number of parameters (in the key entries) are updated to reflect any modifications that you make.

More information about how you can use installation exits to modify C/I text is available in the following documents :

- [*z/OS JES3 Customization*](#)
- [*z/OS JES2 Installation Exits*](#).

Part 5. Testing SMF Exit Routines

Topics for This Section Appear as Follows:

- Chapter 62, “TESTEXIT Exit Routine Requirements,” on page 355
 - Obtaining TESTEXIT from SYS1.SAMPLIB
 - Modifying the TESTEXIT Procedure

This section describes one method of testing user-written SMF exit routines, the TESTEXIT procedure in SYS1.SAMPLIB. This procedure contains an assembler language source program (also named TESTEXIT) which attaches the data generator utility program (IEBDG) to create sample parameter lists for all user-written exit routines except IEFU29. (The TESTEXIT procedure creates the parameter list for the IEFU29 exit routine without using the data generator utility program.) The source program then calls each user-written exit routine being tested, and passes the appropriate parameter list to it.




Figure 26. TESTEXIT Input/Output and Control Flow

Before using the TESTEXIT procedure:

1. Fulfill the following user-written exit routine testing requirements:
 - Specify a user subpool (0-127) in all GETMAIN macro instructions included in the routines.
 - Provide a special SMFWTM macro instruction in all routines that use the macro.
 - Place the routines in a partitioned data set.
2. Obtain the TESTEXIT procedure from SYS1.SAMPLIB.
3. Modify the procedure to meet the installation's testing requirements.

Chapter 62. TESTEXIT Exit Routine Requirements

Before using the TESTEXIT procedure, fulfill the following exit routine requirements:

- Specify a user subpool (0-127) in all GETMAIN macro instructions included in your routines.
- Provide a special SMFWTM macro instruction in all exit routines that use the macro. The special macro definition writes to the TESTEXIT data set defined by the DD statement named MANX. (With the normal SMFWTM macro instruction the data is written to the active SMF data set.) Using this macro definition, then, data is processed without accessing the system data on the active SMF data set. When testing is completed, remove the macro definition.

Figure 27 on page 355 shows the SMFWTM macro instruction that is required for using the TESTEXIT procedure.

```

&NAME      MACRO
SMFWTM      &MSGAD
AIF         ('&MSGAD'EQ');E1
AIF         ('&MSGAD'EQ'(1)');BAL
AIF         ('&MSGAD'(1,1)EQ'(');REGA
AGO         .LODIT
.E1         MNOTE
           '***NO OPERAND SPECIFIED***'
           MEXIT
.BAL        ANOP
           CNOP      0,4
&NAME      BAL      15,*+8
.LIST       DC      V(TSMFWTM)
           L        15,0(15)
           BALR     14,15
           MEXIT
.REGA       ANOP
&NAME      LR        1,&MSGAD(1)
           CNOP     0,4
           BAL      15,*+8
           AGO      .LIST
.LODIT      ANOP
&NAME      LA        1,&MSGAD
           CNOP     0,4
           BAL      15,*+8
           AGO      .LIST
           MEND

```

Figure 27. SMFWTM Macro Definition Required for Using TESTEXIT

- Place the exit routines in a partitioned data set named EXITLIB. Figure 28 on page 356 shows sample JCL for entering the routines into EXITLIB.

```
//UPDTE      JOB      MSGLEVEL=1
//           EXEC      PGM=IEBUPDTE,PARM=NEW
//SYSUT2     DD        DSNAME=EXITLIB,VOLUME=SER=338000,
//           UNIT=3380,SPACE=(TRK,(10,3,1)),DISP=(,KEEP),
//           DCB=(LRECL=80,BLKSIZE=400,RECFM=FB)
//SYSPRINT   DD        SYSOUT=A
//SYSIN      DD        DATA
./ ADD       NAME=IEFUJV

(IEFUJV object deck)
./ ADD       NAME=IEFUJI

(IEFUJI object deck)
./ ADD       NAME=IEFUSI

(IEFUSI object deck)
./ ADD       NAME=IEFUTL

(IEFUTL object deck)
./ ADD       NAME=IEFUSO

(IEDUSO object deck)
./ ADD       NAME=IEFU83

(IEFU83 object deck)
./ ADD       NAME=IEFACTRT

(IEFACTRT object deck)
./ ADD       NAME=IEFUJP

(IEFUJP object deck)
./ ADD       NAME=IEFU29

(IEFU29 object deck)
./ ADD       NAME=IEFU84

(IEFU84 object deck)
./ ENDUP
/*
```

Figure 28. Sample JCL for Entering User-Written Exit Routines into EXITLIB

Obtaining TESTEXIT from SYS1.SAMPLIB

Figure 29 on page 356 shows sample JCL for obtaining a punched deck of TESTEXIT from SYS1.SAMPLIB.

```
//PUNCH      JOB      MSGLEVEL=1
//           EXEC      PGM=IEBTPCH
//SYSPRINT   DD        SYSOUT=A
//SYSUT1     DD        DSNAME=SYS1.SAMPLIB,DISP=(OLD,KEEP),
//           UNIT=xxxx,VOLUME=SER=xxxxxx1
//SYSUT2     DD        UNIT=2540-2
//SYSIN      DD        *
//           PUNCH     TYPORG=PO,MAXNAME=1,MAXFLDS=1
//           MEMBER    NAME=TESTEXIT
//           RECORD    FIELD=(80)
```

¹The volume and unit parameters depend on your installation's request.

Figure 29. Sample JCL for Obtaining a Punched Deck of TESTEXIT

Modifying the TESTEXIT Procedure

“Sample JCL for Executing TESTEXIT” on page 356 shows sample JCL for executing the TESTEXIT procedure.

Sample JCL for Executing TESTEXIT

```
//TESTEXIT   JOB      MSGLEVEL=1
//TEST       EXEC      ASMFCL
//ASM.SYSIN  DD        *
(TESTEXIT Source Module)
/*
```



```

//LKED.SYSLMOD DD DSN=TESTLIB,VOLUME=SER=338000.
//              UNIT=3380,SPACE=(TRK,(5,2,1)),
//              DISP=(NEW,KEEP)
//LKED.EXITSS DD DSN=EXITLIB,VOLUME=SER=338000.
//              UNIT=3380,DISP=OLD
//LKED.SYSIN DD *
INCLUDE EXITS(IEFUJV,IEFUJI,IEFUSI,IEFUTL,IEFUSO,
              IEFU83,IEFACTRT,IEFUJP,IEFU29,IEFU84)
ENTRY TESTEXIT
NAME TESTEXIT
/*
//DATAGEN JOB MSGLEVEL=1
// EXEC PGM=IEBGENER
//SYSUT2 DD DSN=DGINPUT,UNIT=3380,DISP=(,KEEP),
//          VOLUME=SER=338000,SPACE=(TRK,(10,5,1)),
//          DCB=(LRECL=80,BLKSIZE=400,RECFM=FB)
//SYSPRNG DD SYSOUT=A
//SYSIN DD *,DLM=XX
GENERATE MAXNAME=9,MAXGPS=0
MEMBER NAME=UJV
RECORD IDENT=(6,'ENDUJV',1)
MEMBER NAME=UJI
RECORD IDENT=(6,'ENDUJI',1)
MEMBER NAME=USI
RECORD IDENT=(6,'ENDUSI',1)
MEMBER NAME=UTL
RECORD IDENT=(6,'ENDUTL',1)
MEMBER NAME=U83
RECORD IDENT=(6,'ENDU83',1)
MEMBER NAME=ACT
RECORD IDENT=(6,'ENDACT',1)
MEMBER NAME=USO
RECORD IDENT=(6,'ENDUSO',1)
MEMBER NAME=UJP
RECORD IDENT=(6,'ENDUJP',1)
MEMBER NAME=U84
RECORD IDENT=(6,'ENDU84',1)
XX
//SYSUT1 DD DATA,DLM=YY
DSD OUTPUT=(OUTUJV)
(IEBDG Control Statements for IEFUJV)
ENDUJV END
DSD OUTPUT=(OUTUJI)
(IEBDG Control Statements for IEFUJI)
ENDUJI END
DSD OUTPUT=(OUTUSI)
(IEBDG Control Statements for IEFUSI)
ENDUSI END
DSD OUTPUT=(OUTUTL)
(IEBDG Control Statements for IEFUTL)
ENDUTL END
DSD OUTPUT=(OUTU83)
(IEBDG Control Statements for IEFU83)
ENDU83 END
DSD OUTPUT=(OUTACT)
(IEBDG Control Statements for IEFACTRT)
ENDACT END
DSD OUTPUT=(OUTUSO)
(IEBDG Control Statements for IEFUSO)
ENDUSO END
DSD OUTPUT=(OUTUJP)
(IEBDG Control Statements for IEFUJP)
ENDUJP END
DSD OUTPUT=(OUTU84)
(IEBDG Control Statements for IEFU84)
ENDU84 END
YY
//TESTING JOB MSGLEVEL=1
//JOB LIB DD DSN=TESTLIB,VOLUME=SER=338000,
//          UNIT=3380,DISP=(OLD,KEEP)
// EXEC PGM=TESTEXIT,
// PARM='UJV=25,UJI=8,USI=8,USO=5,UTL=5,U83=12,ACT=2,UJP=2,U29=2,U84=12'
//INUJV DD DSN=DGINPUT(UJV),DCB=(LRECL=80,
//          BLKSIZE=400,RECFM=FB),DISP=(OLD,PASS),
//          UNIT=3380,VOLUME=SER=338000
//INUJI DD DSN=DGINPUT(UJI),DCB=(LRECL=80,
//          BLKSIZE=400,RECFM=FB),DISP=(OLD,PASS),
//          UNIT=3380,VOLUME=SER=338000
//INUSI DD DSN=DGINPUT(USI),DCB=(LRECL=80,
//          BLKSIZE=400,RECFM=FB),DISP=(OLD,PASS),
//          UNIT=3380,VOLUME=SER=338000
//INUSO DD DSN=DGINPUT(USO),DCB=(RECL=80,

```

TESTEXIT Exit Routine Requirements

```
//          BLKSIZE=400,RECFM=FB),DISP=(OLD,PASS),
//          UNIT=3380,VOLUME=SER=338000
//INUTL      DD      DSN=DSNAME=DGINPUT(UTL),DCB=(LRECL=80,
//          BLKSIZE=400,RECFM=FB),DISP=(OLD,PASS),
//          UNIT=3380,VOLUME=SER=338000
//INU83      DD      DSN=DSNAME=DGINPUT(U83),DCB=(RECL=80,
//          BLKSIZE=400,RECFM=FB),DISP=(OLD,PASS),
//          UNIT=3380,VOLUME=SER=338000
//INACT      DD      DSN=DSNAME=DGINPUT(ACT),DCB=(RECL=80,
//          BLKSIZE=400,RECFM=FB),DISP=(OLD,PASS),
//          UNIT=3380,VOLUME=SER=338000
//INUJP      DD      DSN=DSNAME=DGINPUT(UJP),DCB=(LRECL=80,
//          BLKSIZE=400,RECFM=FB),DISP=(OLD,PASS),
//          UNIT=3380,VOLUME=SER=338000
//INU84      DD      DSN=DSNAME=DGINPUT(U84),DCB=(RECL=80,
//          BLKSIZE=400,RECFM=FB),DISP=(OLD,PASS),
//          UNIT=3380,VOLUME=SER=338000
//OUTUJV     DD      DSN=DSNAME=UJV(OUT),UNIT=3380,DISP=(,PASS),
//          SPACE=9TRK,(10,5,1),VOLUME=SER=338000,
//          DCB=(LRECL=80,BLKSIZE=400,RECFM=FB)
//OUTUJI     DD      DSN=DSNAME=UJI(OUT),UNIT=3380,DISP=(,PASS),
//          SPACE=(TRK,(10,5,1),VOLUME=SER=338000,
//          DCB=(LRECL=80,BLKSIZE=400,RECFM=FB)
//OUTUSI     DD      DSN=DSNAME=USI(OUT),UNIT=3380,DISP=(,PASS),
//          SPACE=(TRK,(10,5,1),VOLUME=SER=338000,
//          DCB=(LRECL=80,BLKSIZE=400,RECFM=FB)
//OUTUSO     DD      DSN=DSNAME=USO(OUT),UNIT=3380,DISP=(,PASS),
//          SPACE=(TRK,(10,5,1),VOLUME=SER=338000,
//          DCB=(LRECL=80,BLKSIZE=400,RECFM=FB)
//OUTUTL     DD      DSN=DSNAME=UTL(OUT),UNIT=3380,DISP=(,PASS),
//          SPACE=(TRK,(10,51,1),VOLUME=SER=338000,
//          DCB=(LRECL=80,BLKSIZE=400,RECFM=FB)
//OUTU83     DD      DSN=DSNAME=U83(OUT),UNIT=3380,DISP=(,PASS),
//          SPACE=(TRK,(10,5,1),VOLUME=SER=338000,
//          DCB=(LRECL=130,BLKSIZE=130,RECFM=FB)
//OUTACT     DD      DSN=DSNAME=ACT(OUT),UNIT=3380,DISP=(,PASS),
//          SPACE=(TRK,(10,5,1),VOLUME=SER=338000,
//          DCB=(RECL=180,BLKSIZE=180,RECFM=FB)
//OUTUJP     DD      DSN=DSNAME=UJP(OUT),UNIT=3380,DISP=(,PASS),
//          SPACE=(TRK,(10,5,1),VOLUME=SER=338000,
//          DCB=(LRECL=130,BLKSIZE=130,RECFM=FB)
//OUTU84     DD      DSN=DSNAME=U84(OUT),UNIT=3380,DISP=(,PASS),
//          SPACE=(TRK,(10,5,1),VOLUME=SER=338000,
//          DCB=(LRECL=130,BLKSIZE=130,RECFM=FB)
//MANX       DD      UNIT=3380,VOLUME=SER=338000,DSN=MANX,
//          SPACE=(TRK,(3,1),DISP=(NEW,KEEP),
//          DCB=(BLKSIZE=200,LRECL=196)
//SYSPRINT   DD      SYSOUT=a,dcbl=(BLKSIZE=136,LRECL=132)
//DGPRINT    DD      SYSOUT=A
//SYSABEND   DD      SYSOUT=A
/*
```

The following summarizes the operations performed by the procedure shown in [“Sample JCL for Executing TESTEXIT”](#) on page 356:

- The TESTEXIT job assembles the TESTEXIT source program (not illustrated in the figure) and linkedit it with the exit routines being tested. (Note that the exit routines must reside in EXITLIB, a partitioned data set.)
- The DATAGEN job, using the IEBGENER utility program, creates a partitioned data set (DGINPUT) containing control statements for the IEBDG utility program, which will be attached by the TESTEXIT source program.
- The TESTING job includes the execution of the TESTEXIT source program.

Use the TESTEXIT procedure provided in SYS1.SAMPLIB to linkedit the example exit routines in SYS1.SAMPLIB, generate sample parameter lists, and test the sample exit routines. To adapt the TESTEXIT procedure to your installation's testing requirements, however, note the following modifications:

- The TESTEXIT job shown in [“Sample JCL for Executing TESTEXIT”](#) on page 356 linkedit the TESTEXIT source program with the exit routines. The TESTEXIT procedure in SYS1.SAMPLIB contains ten exit names in the INCLUDE statement. However, when you use the TESTEXIT procedure your INCLUDE statement should contain only the names of the exit routines you are testing.
- The DATAGEN job shown in [“Sample JCL for Executing TESTEXIT”](#) on page 356 creates a partitioned data set containing the IEBDG control statements that generate samples of standard parameter lists.

The TESTEXIT procedure contains the control statements for nine exits. Note that control statements are not required for the IEFU29 exit routine because the TESTEXIT procedure creates the parameters needed to test that routine. When using the TESTEXIT procedure you should include only those statements needed for the routine you are testing. When testing for special conditions or required additional test parameters, you must make appropriate modifications and additions to the control statements.

You must supply the control statements in such an order that the records the IEBDG utility program generates later will be grouped as complete parameter lists that conform in length and format to the exit parameters defined earlier in this chapter. (Be sure to include the entry code passed to exits IEFUTL and IEFACTRT in register 0 as a one-byte parameter at the end of the parameter lists for those exits.) For detailed information on using IEBDG control statements, see *z/OS DFSMSdfp Utilities*.

- The TESTING job shown in “Sample JCL for Executing TESTEXIT” on page 356 includes the execution of the TESTEXIT source program. Values for the PARM parameter of the EXEC statement specify which exit routines are to be tested and the number of times each is to be tested. The TESTEXIT procedure in SYS1.SAMPLIB contains the parameters to test ten exits. However, when you use the TESTEXIT procedure you should include only the parameters for the routines you are testing. This parameter has the format:

```
PARM= 'xxx=nnn , . . . ,xxx=nnn '
```

where:

xxx

is an exit routine identifier.

nnn

is the number of times an exit routine is to be tested (the maximum value is 255).

The DD statements to be included depend upon the exit routines being tested. The TESTEXIT procedure contains DD statements for nine exits as shown in the sample (“Sample JCL for Executing TESTEXIT” on page 356). When you use the TESTEXIT procedure you should include only the DD statements for exits you are testing. DD statements are not required for the IEFU29 exit. Table 23 on page 359 shows the exit-routine identifiers, specified on the EXEC statement, and the DD statements that you must include for each exit routine being tested.

Table 23. Parameters and DD Statements for Executing TESTEXIT		
Exit Routine	Identifier	DD Statements
IEFUJV	UJV	INUJV, OUTUJV
IEFUJI	UJI	INUJI, OUTUJI
IEFUSI	USI	INUSI, OUTUSI
IEFUTL	UTL	INUTL, OUTUTL
IEFUSO	USO	INUSO, OUTUSO
IEFU83	U83	INU83, OUTU83
IEFACTRT	ACT	INACT, OUTACT
IEFUJP	UJP	INUJP, OUTUJP
IEFU29	U29	Not required
IEFU84	U84	INU84, OUTU84
Any		MANX,SYSPRINT,DGPRING,SYABEND

You must include (in the JCL for the TESTEXIT procedure) the DD statements for any other data sets the exit routines use.

Part 6. SMF Exit — System Interface Diagrams

This section contains diagrams that show the system interface(s) for the SMF exit routines listed below. Each diagram illustrates the general flow of events that occur before and after the exit routine receives control. Note that the diagrams do not indicate the specific control path between system modules.

The system interfaces for the following SMF exits are illustrated:

- [Figure 30 on page 362](#). IEFUJV — Job Validation Exit (Converter)
- [Figure 31 on page 363](#). IEFUJV — Job Validation Exit (Interpreter)
- [Figure 32 on page 364](#). IEFUJI — Job Initiation Exit and IEFUSI — Step Initiation Exit
- [Figure 33 on page 365](#). IEFUTL — Time Limit Exit
- [Figure 34 on page 366](#). IEFUSO — JES2 SYSOUT Limit Exit
- [Figure 35 on page 367](#). IEFUSO — JES3 SYSOUT Limit Exit
- [Figure 36 on page 368](#). IEFU83 — SMF Record Exit
- [Figure 37 on page 369](#). IEFU84 — SMF Record Exit
- [Figure 38 on page 370](#). IEFU85 — SMF Record Exit
- [Figure 39 on page 371](#). IEFU86 — SMF Record Exit
- [Figure 40 on page 372](#). IEFACTRT — Termination Exit
- [Figure 42 on page 374](#). IEFUJP — JES2 Job Purge Exit
- [Figure 43 on page 375](#). IEFUJP — JES3 Job Purge Exit




Figure 30. IEFUJV – Job Validation Exit (Converter)




Figure 31. IEFUJV – Job Validation Exit (Interpreter)




Figure 32. IEFUJI – Job Initiation Exit and IEFUSI – Step Initiation Exit




Figure 33. IEFUTL – Time Limit Exit




Figure 34. IEFUSO – JES2 SYSOUT Limit Exit




Figure 35. IEFUSO – JES3 SYSOUT Limit Exit




Figure 36. IEFU83 – SMF Record Exit




Figure 37. IEFU84 – SMF Record Exit




Figure 38. IEFU85 — SMF Record Exit




Figure 39. IEFU86 – SMF Record Exit




Figure 40. IEFACTRT – Termination Exit Part 1 of 2




Figure 41. IEFACRT – Termination Exit Part 2 of 2




Figure 42. IEFUJP – JES2 Job Purge Exit




Figure 43. IEFUJP – JES3 Job Purge Exit

Appendix A. Accessibility

Accessible publications for this product are offered through [IBM Documentation \(www.ibm.com/docs/en/zos\)](http://www.ibm.com/docs/en/zos).

If you experience difficulty with the accessibility of any z/OS information, send a detailed message to the [Contact the z/OS team web page \(www.ibm.com/systems/campaignmail/z/zos/contact_z\)](http://www.ibm.com/systems/campaignmail/z/zos/contact_z) or use the following mailing address.

IBM Corporation
Attention: MHVRCFS Reader Comments
Department H6MA, Building 707
2455 South Road
Poughkeepsie, NY 12601-5400
United States

Notices

This information was developed for products and services that are offered in the USA or elsewhere.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
United States of America*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan*

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

This information could include missing, incorrect, or broken hyperlinks. Hyperlinks are maintained in only the HTML plug-in output for IBM Documentation. Use of hyperlinks in other output formats of this information is at your own risk.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Corporation
Site Counsel
2455 South Road*

Poughkeepsie, NY 12601-5400
USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Terms and conditions for product documentation

Permissions for the use of these publications are granted subject to the following terms and conditions.

Applicability

These terms and conditions are in addition to any terms of use for the IBM website.

Personal use

You may reproduce these publications for your personal, noncommercial use provided that all proprietary notices are preserved. You may not distribute, display or make derivative work of these publications, or any portion thereof, without the express consent of IBM.

Commercial use

You may reproduce, distribute and display these publications solely within your enterprise provided that all proprietary notices are preserved. You may not make derivative works of these publications, or

reproduce, distribute or display these publications or any portion thereof outside your enterprise, without the express consent of IBM.

Rights

Except as expressly granted in this permission, no other permissions, licenses or rights are granted, either express or implied, to the publications or any information, data, software or other intellectual property contained therein.

IBM reserves the right to withdraw the permissions granted herein whenever, in its discretion, the use of the publications is detrimental to its interest or, as determined by IBM, the above instructions are not being properly followed.

You may not download, export or re-export this information except in full compliance with all applicable laws and regulations, including all United States export laws and regulations.

IBM MAKES NO GUARANTEE ABOUT THE CONTENT OF THESE PUBLICATIONS. THE PUBLICATIONS ARE PROVIDED "AS-IS" AND WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT, AND FITNESS FOR A PARTICULAR PURPOSE.

IBM Online Privacy Statement

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session cookies that collect each user's name, email address, phone number, or other personally identifiable information for purposes of enhanced user usability and single sign-on configuration. These cookies can be disabled, but disabling them will also eliminate the functionality they enable.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at ibm.com/privacy and IBM's Online Privacy Statement at ibm.com/privacy/details in the section entitled "Cookies, Web Beacons and Other Technologies," and the "IBM Software Products and Software-as-a-Service Privacy Statement" at ibm.com/software/info/product-privacy.

Policy for unsupported hardware

Various z/OS elements, such as DFSMSdfp, JES2, JES3, and MVS, contain code that supports specific hardware servers or devices. In some cases, this device-related element support remains in the product even after the hardware devices pass their announced End of Service date. z/OS may continue to service element code; however, it will not provide service related to unsupported hardware devices. Software problems related to these devices will not be accepted for service, and current service activity will cease if a problem is determined to be associated with out-of-support devices. In such cases, fixes will not be issued.

Minimum supported hardware

The minimum supported hardware for z/OS releases identified in z/OS announcements can subsequently change when service for particular servers or devices is withdrawn. Likewise, the levels of other software products supported on a particular release of z/OS are subject to the service support lifecycle of those

products. Therefore, z/OS and its product publications (for example, panels, samples, messages, and product documentation) can include references to hardware and software that is no longer supported.

- For information about software support lifecycle, see: [IBM Lifecycle Support for z/OS \(www.ibm.com/software/support/systemsz/lifecycle\)](http://www.ibm.com/software/support/systemsz/lifecycle)
- For information about currently-supported IBM hardware, contact your IBM representative.

Programming Interface Information

This manual is intended to help a customer modify the processing of an MVS operating system. This manual also documents intended Programming Interfaces that allow the customer to write programs to obtain the services of z/OS.

Trademarks

IBM, the IBM logo, and [ibm.com](http://www.ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at [Copyright and Trademark information \(www.ibm.com/legal/copytrade.shtml\)](http://www.ibm.com/legal/copytrade.shtml).

Index

A

- accessibility
 - contact IBM [377](#)
- account number processing [167](#), [175](#), [193](#)
- accounting information
 - passed to IEFUJI and IEFUSI [175](#)
- Allocated or Offline Device Installation Exit [97](#)
- allocation input validation routine [147](#)
- allocation WTOR [97](#), [119](#), [125](#), [129](#)
- APPC/MVS user account validation [167](#)
- ASREXIT installation exit [11](#)
- assistive technologies [377](#)

B

- Batch ENQ request
 - exit routine [260](#)
- Batch ISGENQ request
 - exit routine [260](#)

C

- C/I (converter/interpreter)
 - processing
 - IEFUJV exit [185](#)
 - text
 - modifying text [351](#)
 - text processing [335](#)
 - text string
 - example [350](#)
- change options / suppress dump [79](#), [85](#)
- CMDX parameter list [297](#)
- CMDXAFLA field [297](#)
- CMDXAUTH field [297](#)
- CMDXCLIB command buffer [297](#)
- CNZ_MSGTOSYSLOG installation exit [15](#)
- CNZ_MSIEXIT installation exit [21](#)
- CNZ_WTOMDBEXIT installation exit [23](#)
- COFXDLF1 exit routine [39](#)
- command modification [295](#)
- command suppression [295](#)
- commands exit [295](#)
- communications task exit parameter list
 - used by IEAVMXIT [76](#)
- contact
 - z/OS [377](#)
- control block
 - formatting
 - exit routine [62](#), [66](#)
- converter/interpreter [185](#), [335](#)
- CSVLLIX1 installation exit
 - LLA module fetch [29](#)
- CSVLLIX2 installation exit
 - LLA module staging [33](#)
- CTXT parameter list [76](#)

D

- data lookaside facility [39](#)
- data space
 - controlling use [196](#)
 - default size [196](#)
- DFSMS exits [317](#)
- directory of installation exits [313](#)
- Display global resource serialization request
 - exit routine [256](#)
- DLF (data lookaside facility)
 - DLF Connect / Disconnect Installation Exit [39](#)
- DLF Connect / Disconnect Installation Exit [39](#)
- dump formatting
 - exit routine [59](#), [65](#)
- dynamic exit routine
 - linkediting [5](#)
 - replacing [6](#)
- dynamic exits
 - ABDUMP [5](#)
 - providing security [6](#)
 - SDUMP [5](#)
- dynamic exits facility [4](#)
- dynamic output SVC [155](#)

E

- ENQ/DEQ preprocessing
 - exit routine [258](#)
- ENQ/DEQ/RESERVE/ISGENQ request
 - exit routine [250](#)

F

- fast ENQ/DEQ
 - exit routine [247](#)
- fast ISGENQ
 - exit routine [247](#)
- feedback xv
- Filter global resource serialization
 - exit routine [252](#), [254](#)

G

- Global resource serialization
 - contention notification
 - SYSTEM scope [252](#)
 - SYSTEMS scope [254](#)

H

- Hiperbatch [39](#)
- hiperspace
 - controlling use [196](#)
 - default size [196](#)

I

- IARVserv macro
 - sharing page limit [193, 198](#)
- ICHSAFP mapping macro
 - RACROUTE parameter list [52](#)
- IEALIMIT installation exit
 - compared with IEFUSI [55](#)
 - use of REGION parameter [56, 57](#)
- IEAVADFM installation exit
 - compared with IEAVADUS [59](#)
- IEAVADUS installation exit
 - compared with IEAVADFM [65](#)
- IEAVMXIT installation exit
 - common data area [75](#)
 - communication between exit routines [75](#)
 - data shared across invocations [75](#)
 - incompatible request [72](#)
 - individual data area [75](#)
 - message modification [69](#)
 - replacement
 - without a re-IPL [71](#)
- IEAVTABX installation exit
 - using IHAABEPL [82, 86](#)
- IEAVTABX_EXIT installation exit [85](#)
- IEAVTSEL installation exit [89](#)
- IEFACTRT installation exit
 - common exit parameter area [141](#)
 - recovery processing [135](#)
 - SMF termination record [135](#)
- IEFDB401 installation exit
 - coded example [151](#)
- IEFDOIXT installation exit [155](#)
- IEFJFRQ installation exit
 - recovery processing [162](#)
- IEFTB724 module [136](#)
- IEFTXTFT mapping macro [350](#)
- IEFU29 installation exit
 - recovery processing [216](#)
- IEFU29L installation exit
 - recovery processing [220](#)
- IEFU83 installation exit
 - recovery processing [224](#)
- IEFU84 installation exit
 - recovery processing [228](#)
- IEFU85 installation exit
 - recovery processing [234](#)
- IEFU86 installation exit
 - recovery processing [240](#)
- IEFUAV installation exit
 - recovery processing [168](#)
- IEFUJI installation exit
 - compared with IEFUJV [175](#)
 - recovery processing [176](#)
- IEFUJP installation exit
 - recovery processing [182](#)
- IEFUJV installation exit
 - recovery processing [187](#)
- IEFUSI installation exit
 - common exit parameter area [196](#)
 - compared with IEALIMIT [197](#)
 - compared with IEFUJV [194](#)
 - recovery processing [195](#)

- IEFUSI installation exit (*continued*)
 - region limit processing [196](#)
 - shared page limit [198](#)
- IEFUSO installation exit
 - common exit parameter area [207](#)
 - recovery processing [206](#)
- IEFUTL installation exit
 - common exit parameter area [212](#)
 - recovery processing [210](#)
- IEFVKEYS mapping macro [350](#)
- IEFYS module [136](#)
- IEZVX101 mapping macro [297](#)
- IFASMF DL and IFASMF DP SMF Dump Program Exits [245](#)
- installation exit
 - ABDUMP exit [85](#)
 - Allocated or Offline Device installation Exit [97](#)
 - Allocation Event Installation Exit [107](#)
 - Allocation Modify DDname Installation Exit [111](#)
 - Allocation Unload Device Exit [115](#)
 - ASREXIT [11](#)
 - CNZ_MSGTOSYSLOG [15](#)
 - CNZ_MSIXIT [21](#)
 - CNZ_WTOMDBEXIT [23](#)
 - CSVLLIX1 [29](#)
 - CSVLLIX2 [33](#)
 - DLF Connect / Disconnect exit [39](#)
 - HISserv Service Installation Exit [45](#)
 - ICHRTX00 [49](#)
 - IEALIMIT [55](#)
 - IEAVADFM [59](#)
 - IEAVADUS [65](#)
 - IEAVMXIT [69](#)
 - IEAVTABX [79](#)
 - IEAVTABX_EXIT [85](#)
 - IEAVTSEL [89](#)
 - IEFACTRT [133](#)
 - IEFDB401 [147](#)
 - IEFDOIXT [155](#)
 - IEFJFRQ [161](#)
 - IEFU29 [215](#)
 - IEFU29L [219](#)
 - IEFU83 [223](#)
 - IEFU84 [227](#)
 - IEFU85 [233](#)
 - IEFU86 [239](#)
 - IEFUAV [167](#)
 - IEFUJI [175](#)
 - IEFUJP [181](#)
 - IEFUJV [185](#)
 - IEFUSI [193](#)
 - IEFUSO [205](#)
 - IEFUTL [209](#)
 - introduction
 - calling an installation exit routine [3](#)
 - keyword modification [3](#)
 - link editing [3](#)
 - macro use [3](#)
 - programming considerations [3](#)
 - register saving [3](#)
 - replaceable module [3](#)
 - restrictions [3](#)
 - source code [3](#)
 - user modification routine [3](#)
 - ISGCNFXITSYSPLX [254](#)

- installation exit (*continued*)
 - ISGCNFXITSYSTEM [252](#)
 - ISGENDOFLQCB [268](#)
 - ISGNQXIT [250](#)
 - ISGNQXITBATCH [256, 260](#)
 - ISGNQXITQUEUED1 [264](#)
 - IXC_ELEM_RESTART [271](#)
 - IXC_WORK_RESTART [277](#)
 - log stream subsystem exit [285](#)
 - MMS installation exit [305](#)
 - MVS commands installation exit [295](#)
 - specific waits installation exit [119](#)
 - volume ENQ installation exit [125](#)
 - volume mount installation exit [129](#)
- Installation exit
 - ISGNQXITFAST [247](#)
 - ISGNQXITPREBATCH [258](#)
- installation exit directory [313](#)
- installation exit name list
 - IEAVADFM [59](#)
 - using a DSECT [3](#)
- installation exit point
 - instruction [3](#)
 - keyword modification [3](#)
- installation-specified MPF exit [69](#)
- IPCS exits [319](#)
- ISGCNFXITSYSLEX installation exit [254](#)
- ISGCNFXITSYSTEM installation exit [252](#)
- ISGDGRSRES installation exit [256](#)
- ISGENDOFLQCB installation exit [268](#)
- ISGENQ preprocessing
 - exit routine [258](#)
- ISGNQXIT installation exit [250](#)
- ISGNQXITBATCH installation exit [260](#)
- ISGNQXITFAST installation exit [247](#)
- ISGNQXITPREBATCH installation exit [258](#)
- ISGNQXITQUEUED1 installation exit [264](#)
- IXC_ELEM_RESTART installation exit [271](#)
- IXC_WORK_RESTART installation exit [277](#)

J

- JCL
 - JDT-defined
 - long parameters [346](#)
- JES2 exits [321](#)
- JES3 exits [323](#)
- job initiation exit [175](#)
- job purge exit [181](#)
- job validation exit [185](#)

K

- keyboard
 - navigation [377](#)
 - PF keys [377](#)
 - shortcut keys [377](#)
- keyword modification
 - installation exit point [3](#)

L

- library lookaside [29, 33](#)

- limit user region size [55](#)
- LLA (library lookaside)
 - CSVLLIX1 exit routine [29](#)
 - CSVLLIX2 exit routine [33](#)
- LLA module fetch [29](#)
- LLA module staging [33](#)
- log stream subsystem exit [285](#)
- long parameters [346](#)

M

- MCS authority for console
 - modifying
 - exit routine [295](#)
- message automation [69](#)
- message display [69](#)
- message modification [69](#)
- message processing
 - incompatible request [72](#)
 - minor-line processing [72](#)
- message routing [69](#)
- message suppression [69](#)
- MGCRE macro [300](#)
- minor-line [72](#)
- MMS (MVS message service) [305](#)
- MMS installation exit
 - modifying user request [305](#)
- module fetch [29](#)
- module staging [33](#)
- MPF exit [69](#)
- MPFLSTxx member
 - activation [296](#)
 - specifying command exit [295](#)
- multiple console support [295](#)
- MVS command [295](#)
- MVS commands installation exit
 - coded example [301](#)
 - command modification [295](#)
 - common data area [299](#)
 - in a sysplex environment [298](#)
 - individual data area [300](#)
 - replacing
 - without a reIPL [296](#)
 - specified in MPFLSTxx member [295](#)
- MVS message service [305](#)
- MVS router
 - installation exit [49](#)
- MVS router exit [49](#)

N

- navigation
 - keyboard [377](#)
- nonextended region limit
 - set by IEALIMIT [55](#)

O

- OUTADD macro [155](#)
- OUTDEL macro [155](#)

P

PATH parameter
 z/OS UNIX pathname [346](#)
post dump exit name list [89](#)

Q

QCB Destroy Exit request
 exit routine [268](#)
Queued ENQ/DEQ request
 exit routine [264](#)

R

RACF exits [325](#)
RACROUTE macro [49](#)
region limit processing [193](#)
REGION parameter
 used by IEALIMIT [56](#), [57](#)
resource name list [247](#), [250](#), [252](#), [254](#), [256](#), [258](#), [260](#), [264](#), [268](#)
RMF exits [327](#)
RNL (resource name list)
 fast ENQ/DEQ
 exit routine [247](#)
 preprocessing
 exit routine [258](#)
 scanning
 exit routine [250](#), [252](#), [254](#), [256](#), [260](#), [264](#), [268](#)
router exit [49](#)

S

SAF (system authorization facility)
 ICHRTX00 exit routine [49](#)
 router exit [49](#)
sending to IBM
 reader comments [xv](#)
sharing page limit
 IARVserv macro [193](#), [198](#)
shortcut keys [377](#)
SMF data set
 SMF dump exit [217](#)
SMF dump exit [215](#), [219](#)
SMF Dump Program Exits
 IFASMF DL and IFASMF DP [245](#)
SMF exit routines, user-
 written
 testing [353](#)
SMF job and job step termination exits [133](#)
SMF log stream
 SMF dump exit [221](#)
SMF record exit [223](#), [227](#), [233](#), [239](#)
SMF termination record
 description [135](#)
SNAP dump
 formatting
 exit routine [59](#), [65](#)
specific waits installation exit [119](#)
step initiation exit [193](#)
subsystem function request exit [161](#)

summary of changes [xvii](#)
SYSABEND dump
 formatting
 exit routine [59](#), [65](#)
SYSOUT limit exit [205](#)
system authorization facility [49](#)
system command [295](#)
system symbols
 changing in command text [297](#)
 processing, in command text [297](#)
SYSUDUMP dump
 formatting
 exit routine [59](#), [65](#)

T

TESTEXIT assembler program [353](#)
text unit
 modification
 exit routine [155](#)
time limit exit [209](#)
time limit extension [209](#)
TP (transaction program)
 account number processing [167](#)
 user accounting information
 validation [169](#)
TP user accounting validation [167](#)
trademarks [382](#)
transaction program [167](#)
TSO/E exits [329](#)

U

user account validation exit [167](#)
user interface
 ISPF [377](#)
 TSO/E [377](#)
user modification routine
 introduction [3](#)
user's region size [193](#)
USEREXIT parameter
 in MPFLSTxx [295](#)

V

volume ENQ installation exit [125](#)
volume mount installation exit [129](#)
VTAM exits [333](#)

W

WTO modification [69](#)
WTO/WTOR exit [69](#)
WTO/WTOR macro [69](#)

Z

z/OS UNIX
 pathname [346](#)



Product Number: 5650-ZOS

SA23-1381-50

