

# **SOLARWINDS**

## Serv-U File Server Administrator Guide

Copyright © 1995-2014 SolarWinds Worldwide, LLC. All rights reserved worldwide. No part of this document may be reproduced by any means nor modified, decompiled, disassembled, published or distributed, in whole or in part, or translated to any electronic medium or other means without the written consent of SolarWinds. All right, title, and interest in and to the software and documentation are and shall remain the exclusive property of SolarWinds and its respective licensors.

SOLARWINDS DISCLAIMS ALL WARRANTIES, CONDITIONS OR OTHER TERMS, EXPRESS OR IMPLIED, STATUTORY OR OTHERWISE, ON SOFTWARE AND DOCUMENTATION FURNISHED HEREUNDER INCLUDING WITHOUT LIMITATION THE WARRANTIES OF DESIGN, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE, AND NONINFRINGEMENT. IN NO EVENT SHALL SOLARWINDS, ITS SUPPLIERS, NOR ITS LICENSORS BE LIABLE FOR ANY DAMAGES, WHETHER ARISING IN TORT, CONTRACT OR ANY OTHER LEGAL THEORY EVEN IF SOLARWINDS HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

The SolarWinds, the SolarWinds & Design, ipMonitor, LANsurveyor, Orion, and other SolarWinds marks, identified on the SolarWinds website, as updated from SolarWinds from time to time and incorporated herein, are registered with the U.S. Patent and Trademark Office and may be registered or pending registration in other countries. All other SolarWinds trademarks may be common law marks or registered or pending registration in the United States or in other countries. All other trademarks or registered trademarks contained and/or mentioned herein are used for identification purposes only and may be trademarks or registered trademarks of their respective companies. Microsoft®, Windows®, and SQL Server® are registered trademarks of Microsoft Corporation in the United States and/or other countries.

Last revised: 10/24/2014

<b>Serv-U File Server Administrator Guide</b>	<b>15</b>
About SolarWinds	15
Conventions	15
Serv-U documentation library	16
Technical support	16
Free email support	16
Knowledge base	17
Sales support	17
Contacting SolarWinds	17
<b>Chapter 1: Serv-U File Server</b>	<b>18</b>
Serv-U File Server overview	18
Serv-U editions	19
How to purchase Serv-U	20
<b>Chapter 2: Getting started</b>	<b>22</b>
System requirements	22
Hardware requirements	22
Operating system requirements	23
Client requirements	24
Server concepts	26
Glossary	28
Quick start guide	29
Installing the Serv-U file server	29
Creating domains	30
Creating user accounts	33
Sharing files	35
Using URL parameters	35

---

The Serv-U Management Console .....	36
User interface conventions .....	37
Understanding user interface conventions .....	38
<b>Chapter 3: Server .....</b>	<b>39</b>
Server overview .....	39
Server details .....	39
IP access rules .....	39
Specifying IP access masks .....	39
Caveats .....	40
IP access list controls .....	42
Examples .....	43
Serv-U Gateway .....	44
Deploying Serv-U Gateway .....	45
Serv-U Gateway tab .....	45
Gateway Address column .....	46
Public IP Address column .....	46
Description column .....	46
Managing gateways in Serv-U .....	47
Serv-U Gateway Add/Edit dialog .....	47
Serv-U Gateway Properties dialog .....	48
Status area .....	48
Install information area .....	49
Registration ID area .....	49
Database access .....	49
Using SQL templates .....	50
Using user and group table mappings .....	50

Serv-U events .....	53
Server events .....	54
Server and domain events .....	54
Server, domain, user and group events .....	56
Creating common events .....	59
Using event filters .....	62
Using event filters .....	64
License information .....	66
Program Information .....	67
Serv-U SMTP configuration .....	68
Directory access rules .....	69
Directory access rules .....	69
File permissions .....	70
Directory permissions .....	71
Subdirectory permissions .....	72
Advanced: Access as Windows User (Windows Only) .....	72
Quota permissions .....	73
Mandatory access control .....	73
Restricting file types .....	74
Virtual paths .....	77
Physical path .....	77
Virtual path .....	77
Including virtual paths in "Maximum Directory Size" calculations .....	77
Case File: Using virtual paths .....	78
Case File: Creating relative virtual paths .....	78
Automated file management .....	78

---

Server limits and settings .....	80
Connection .....	82
Password .....	84
Directory Listing .....	86
Data Transfer .....	87
HTTP .....	90
Email .....	91
File Sharing .....	92
Advanced .....	94
Server settings .....	96
Connection Settings .....	96
Network Settings .....	97
Other Settings .....	98
FTP settings .....	98
Global Properties .....	98
Editing FTP Commands and Responses .....	100
Case File: Custom FTP command response .....	101
Encryption .....	102
Configuring SSL for FTPS and HTTPS .....	103
Advanced SSL Options .....	104
FIPS Options .....	105
SFTP (Secure File Transfer over SSH2) .....	105
SSH Ciphers and MACs .....	106
Custom HTML .....	106
File sharing .....	108
Server activity .....	110

Disconnecting sessions .....	111
Using the spy & chat function .....	112
Broadcasting messages .....	112
Canceling sessions .....	112
Server and domain statistics .....	113
Session statistics .....	113
Login statistics .....	113
Transfer statistics .....	114
User and group statistics .....	115
Session statistics .....	115
Login statistics .....	115
Transfer statistics .....	116
Server and domain log .....	117
<b>Chapter 4: Domain .....</b>	<b>119</b>
Domain overview .....	119
Managing Domains .....	119
Domain details .....	120
Domain listeners .....	121
Adding a listener .....	122
Pure Virtual Domains .....	124
Virtual hosts .....	124
Server details .....	126
IP access rules .....	126
Specifying IP access masks .....	126
Caveats .....	127
IP access list controls .....	129

---

Examples .....	130
Database access .....	131
Using SQL templates .....	131
Using user and group table mappings .....	132
Serv-U events .....	135
Server events .....	136
Server and domain events .....	136
Server, domain, user and group events .....	138
Creating common events .....	141
Using event filters .....	144
Using event filters .....	146
Serv-U SMTP configuration .....	148
Directory access rules .....	149
Directory access rules .....	149
File permissions .....	151
Directory permissions .....	151
Subdirectory permissions .....	152
Advanced: Access as Windows User (Windows Only) .....	152
Quota permissions .....	153
Mandatory access control .....	153
Restricting file types .....	154
Virtual paths .....	157
Physical path .....	157
Virtual path .....	157
Including virtual paths in "Maximum Directory Size" calculations .....	157
Case File: Using virtual paths .....	158



Case File: Creating relative virtual paths .....	158
Automated file management .....	158
Domain limits and settings .....	160
Connection .....	162
Password .....	164
Directory Listing .....	166
Data Transfer .....	167
HTTP .....	169
Email .....	170
File Sharing .....	171
Advanced .....	173
Domain settings .....	174
Connection settings .....	175
Custom HTTP Settings .....	175
Other Settings .....	177
FTP settings .....	177
Global Properties .....	178
Editing FTP Commands and Responses .....	179
Case File: Custom FTP command response .....	181
Encryption .....	181
Configuring SSL for FTPS and HTTPS .....	182
SFTP (Secure File Transfer over SSH2) .....	184
SSH Ciphers and MACs .....	185
Custom HTML .....	185
File sharing .....	187
Server activity .....	188

Disconnecting sessions .....	189
Using the spy & chat function .....	190
Broadcasting messages .....	190
Canceling sessions .....	190
Server and domain statistics .....	191
Session statistics .....	191
Login statistics .....	191
Transfer statistics .....	192
User and group statistics .....	193
Session statistics .....	193
Login statistics .....	193
Transfer statistics .....	194
Server and domain log .....	195
Configuring domain logs .....	197
Logging to File Settings .....	197
<b>Chapter 5: Users .....</b>	<b>200</b>
About user accounts .....	200
User Information .....	203
Directory access rules .....	210
Directory access rules .....	210
File permissions .....	211
Directory permissions .....	212
Subdirectory permissions .....	212
Advanced: Access as Windows User (Windows Only) .....	212
Quota permissions .....	213
Mandatory access control .....	213

---

Restricting file types .....	214
Virtual paths .....	217
Physical path .....	217
Virtual path .....	217
Including virtual paths in "Maximum Directory Size" calculations .....	217
Case File: Using virtual paths .....	218
Case File: Creating relative virtual paths .....	218
Configuring user and group logs .....	218
Logging to File Settings .....	219
Log file path .....	219
Enable logging to file .....	220
Automatically rotating the log file .....	220
Purging old log files .....	220
Specifying IP addresses exempt from logging .....	221
Group memberships .....	221
Serv-U events .....	223
Server events .....	224
Server and domain events .....	224
Server, domain, user and group events .....	226
Creating common events .....	229
Using event filters .....	232
Using event filters .....	234
Server details .....	236
IP access rules .....	236
Specifying IP access masks .....	236
Caveats .....	237

IP access list controls .....	239
Examples .....	240
Limits and settings .....	241
Connection .....	242
Password .....	244
Directory Listing .....	246
Data Transfer .....	247
HTTP .....	248
Email .....	250
File Sharing .....	250
Advanced .....	252
Transfer ratio and quota management .....	253
Transfer ratio .....	254
Quota .....	254
Ratio free files .....	255
Windows authentication .....	255
Using a Windows user group home directory instead of account home directory .....	256
Configuring Windows user groups .....	256
Using Windows user permissions .....	256
LDAP authentication .....	257
Using the LDAP user group home directory instead of the account home directory .....	257
Specifying the LDAP login ID suffix .....	258
Differences between Windows users and LDAP users .....	258
LDAP user groups .....	258
LDAP group membership .....	259
LDAP server configuration .....	260

List of LDAP servers .....	260
LDAP server configuration .....	261
SFTP (Secure File Transfer over SSH2) for users and groups .....	266
<b>Chapter 6: Groups .....</b>	<b>268</b>
About groups .....	268
Using group templates .....	268
Setting up Windows groups (Windows only) .....	269
Configuring a Windows user group (Windows only) .....	270
LDAP user groups .....	270
Group information .....	272
Directory access rules .....	275
Directory access rules .....	275
File permissions .....	276
Directory permissions .....	277
Subdirectory permissions .....	278
Advanced: Access as Windows User (Windows Only) .....	278
Quota permissions .....	279
Mandatory access control .....	279
Restricting file types .....	280
Virtual paths .....	282
Physical path .....	282
Virtual path .....	282
Including virtual paths in "Maximum Directory Size" calculations .....	282
Case File: Using virtual paths .....	283
Case File: Creating relative virtual paths .....	283
Configuring user and group logs .....	283

Logging to File Settings .....	284
Log file path .....	284
Enable logging to file .....	285
Automatically rotating the log file .....	285
Purging old log files .....	285
Specifying IP addresses exempt from logging .....	286
Group members .....	286
Serv-U events .....	289
Server events .....	290
Server and domain events .....	290
Server, domain, user and group events .....	292
Creating common events .....	295
Using event filters .....	298
Using event filters .....	300
Server details .....	302
IP access rules .....	302
Specifying IP access masks .....	302
Caveats .....	303
IP access list controls .....	305
Examples .....	306
Limits and Settings .....	307
Connection .....	308
Password .....	310
Directory Listing .....	312
Data Transfer .....	313
HTTP .....	314

Email .....	316
File Sharing .....	316
Advanced .....	318
Ratio Free Files .....	320
SFTP (Secure File Transfer over SSH2) for users and groups .....	320
<b>Chapter 7: System variables .....</b>	<b>323</b>
Server information .....	323
Server statistics .....	325
Domain statistics .....	327
User statistics - Applies to all sessions attached to the user account .....	328
Last transfer statistics - Applies to the most recently completed successful data transfer .....	329
Date/Time .....	331
Server settings .....	332
Session information - Applies to the current session .....	332
File information - Applies to the last remotely accessed file, which is not necessarily the last transferred file .....	336
Current activity .....	337

# Serv-U File Server Administrator Guide

## About SolarWinds

SolarWinds, Inc develops and markets an array of IT management, monitoring, and discovery tools to meet the diverse requirements of today's IT management and consulting professionals. SolarWinds products continue to set benchmarks for quality and performance and have positioned the company as the leader in IT management and discovery technology. The SolarWinds customer base includes over 85 percent of the Fortune 500 and customers from over 170 countries. Our global business partner distributor network exceeds 100 distributors and resellers.

## Conventions

The documentation uses consistent conventions to help you identify items throughout the printed and online library.

Convention	Specifying
<b>Bold</b>	Window items, including buttons and fields
<i>Italics</i>	Book and CD titles, variable names, new terms
<code>Fixed font</code>	File and directory names, commands and code examples, text typed by you
Straight brackets, as in [value]	Optional command parameters
Curly braces, as in {value}	Required command parameters



Logical OR, as in value1 value2	Exclusive command parameters where only one of the options can be specified
------------------------------------	--

## Serv-U documentation library

The following documents are included in the Serv-U File Server documentation library:

Document	Purpose
Administrator Guide	Provides detailed setup, configuration, and conceptual information.
Evaluation Guide	Provides an introduction to Serv-U features and instructions for installation and initial configuration.
Page Help	Provides help for every window in the Serv-U user interface.
Release Notes	Provides late-breaking information, known issues, and updates. The latest Release Notes can be found at <a href="http://www.solarwinds.com">http://www.solarwinds.com</a> .

## Technical support

Have a question and need more help? SolarWinds offers a variety of technical support options. For current product support policies, please refer to the [Serv-U Help Desk](#).

Users who purchased their copy of Serv-U from an official reseller are referred back to their reseller for support. Telephone technical support is available.

### Free email support

Free technical support is available through email to users with active maintenance. We ask that all users submit their inquiries to <http://www.Serv-U.com/support/> for technical support requests.

## Knowledge base

Our knowledge base is a dynamic support tool that you can use to research solutions to your questions and problems. Nearly every technical question posed to our technical support team is answered here. The knowledge base can provide immediate, informative, step-by-step answers with screenshots to your questions.

Visit <http://www.Serv-U.com/kb/> to get answers now.

## Sales support

Sales questions relative to the Serv-U File Server software should be directed to: <http://www.Serv-U.com/sales/>. Sales representatives can also be reached by calling SolarWinds at +1 (855) 498-4154.

Technical support options are subject to change without notice at the discretion of SolarWinds.

## Contacting SolarWinds

If you have lost your registration ID, visit the [Online Customer Service Center](#).

You can contact SolarWinds at:

### SolarWinds

**7171 Southwest Parkway**

**Bldg 400**

**Austin, TX 78735**

**Sales: +1 (855) 498-4154**

**FAX: +1 (512) 682-9301**

**Phone: +1 (866) 530-8100**

<http://www.Serv-U.com/>

<http://www.Serv-U.com/sales/>

<http://www.Serv-U.com/support/>

For sales inquiries, visit: <http://www.Serv-U.com/sales/>.

For more information about the Serv-U File Server, visit: <http://www.Serv-U.com/>.

# Chapter 1: Serv-U File Server

## Serv-U File Server overview

The Serv-U File Server is a multi-protocol file server capable of sending and receiving files from other networked computers through various means.

Administrators create accounts for users that allow access to specific files and folders on the server's hard drive or any other available network resource. These access permissions define where and how the users can access the available resources. Serv-U's multi-protocol support means that users can employ whatever access method is available to them when connecting to your server. In addition, Serv-U supports both IPv4 and IPv6 for next-generation networks. The Serv-U File Server supports the following protocols:

- FTP (File Transfer Protocol)
- HTTP (Hyper Text Transfer Protocol)
- FTPS (FTP over SSL)
- HTTPS (HTTP over SSL)\*
- SFTP using SSH2 (File Transfer over Secure Shell)\*

In addition to Serv-U's support for a large collection of the most popular FTP clients, you can use your favorite web browser or SSH client to connect and transfer files to and from Serv-U. Server administrators looking to provide a full-featured FTP client to users who may not have an FTP client license of their own can even license FTP Voyager JV. FTP Voyager JV is a Java-enabled FTP client delivered to the user after logging in to their Serv-U account.

The Serv-U File Server maintains the Serv-U brand's legendary feature set. Using the Serv-U File Server, you can perform the following actions:

- Access files from anywhere
- Share files with friends, family, and clients

- Provide employees in the field with a central location to send and receive data files
- Use full group support that streamlines user creation and maintenance
- View images in thumbnails and slide shows, generated on-the-fly to minimize bandwidth usage
- Administer the server through a custom-built web interface
- Chat with FTP clients and view session logs in real time
- Customize FTP command responses
- Create custom limits and rules at a granular level to control resource usage on the server
- Connect securely using SSL/TLS or SSH2
- Use third party digital certificates to guarantee the identity of the server to clients
- Host multiple domains on the same IP address and port
- Use multiple sources of authentication on the same domain (local user database, NT/SAM, ODBC)
- Automatically build the tables necessary for ODBC authentication

You can test Serv-U MFT Server in a non-production environment for a specific period of time. After the evaluation period expires, a commercial license or maintenance renewal provides you with free software updates and free technical support through email, phone, or both, depending on your edition, for the duration of the associated maintenance plan.

*\* - Requires Serv-U MFT Server*

## Serv-U editions

Serv-U is available in two editions to support the different needs of different organizations.

Serv-U FTP Server is designed for small businesses and project teams requiring FTPS to secure FTP, scripted transfers, and smaller number of users and domains supported on a single server.

Serv-U MFT Server is designed for businesses of all sizes that need to secure data in transit through SFTP, FTPS or HTTPS. It also adds remote administration through web browsers and iPad, authentication through Active Directory or a database, clustering and event-driven automation, and branding. It also includes the FTP Voyager JV module for a rich "sync and side-by-side" web client interface.

Both editions contain FTP, web transfer, and mobile device support. Both editions also support the optional Serv-U Gateway module, which is a reverse proxy component that prevents "data at rest" in a DMZ segment.

For a feature-by-feature comparison of the versions, see the [Serv-U FTP Server Editions Information](#).

## How to purchase Serv-U

Serv-U is available as a fully functional MFT Server trial for 30 days after the date of initial installation. To continue using Serv-U with its full set of features, you must purchase a Serv-U license.

You can purchase a license online at the [Serv-U website](#). Choose which edition of the Serv-U File Server is required and the quantity to purchase. Discount pricing applies for bulk purchasing. You must purchase a Serv-U File Server license before adding an FTP Voyager JV license to your shopping cart.

You can find pricing information at the [Serv-U FTP Server pricing web page](#).

If you have lost your registration ID, visit the [Online Customer Service Center](#) to retrieve it.

When the purchase has been completed, an email containing the registration details is immediately sent. If you do not receive it within an hour, check your spam filter to make sure that the email has not been filtered.

You can send a purchase orders to SolarWinds in one of the following ways:

1. Send an email purchase order, preferably in a PDF, JPG, or GIF format, to a marketing representative at the [Serv-U Sales web page](#).
2. Send a fax purchase order to +1 512 682 9301.
3. Send a mail directly to SolarWinds to the following address:

**SolarWinds**

**7171 Southwest Parkway**

**Bldg 400**

**Austin, TX 78735**

**USA**

# Chapter 2: Getting started

## System requirements

This topic contains detailed information about the minimum hardware, operating system, and browser requirements that you must meet to run Serv-U.

### Hardware requirements

Most modern operating systems require higher hardware specifications. Use minimum operating system requirements instead where applicable.

Hardware	Minimum requirement
CPU	1 GHz+
RAM	256 MB+
Network	10/100 Mbps NIC
Hard drive space	30 MB
Video	128 MB Video RAM

The hardware requirements of Serv-U are modest, but Serv-U can take advantage of multicore processors and multiple processor architectures.

The following table lists the requirements in the case of modest traffic: up to 500 configured users and 25 simultaneous transfers.

Hardware	Minimum requirement for modest traffic
CPU	2 GHz+ multicore

Hardware	Minimum requirement for modest traffic
RAM	2 GB+
Network	10/100/1000 Mbps NIC
Hard drive space	120 GB
Video	128 MB Video RAM

The following table lists the requirements in the case of high traffic: up to 10 000 configured users and 250 simultaneous transfers.

Hardware	Minimum requirement for high traffic
CPU	Multiple 3.2 GHz+ multicore
RAM	4 GB+
Network	10/100/1000 Mbps NIC
Hard drive space	120 GB
Video	128 MB Video RAM

### Operating system requirements

We recommend the use of Microsoft Windows Server 2008 R2 or Red Hat Enterprise Linux v6 with our Serv-U and Serv-U Gateway deployments, but we also support other Windows and Linux operating systems. 64-bit and 32-bit editions are supported unless otherwise noted (or not available).



Operating system	Requirement
Microsoft Windows	<ul style="list-style-type: none"><li>• Windows Server 2012</li><li>• Windows Server 2012 RC2</li><li>• Windows Server 2008, 2008 SP2, 2008 R2, and 2008 R2 SP1</li><li>• Windows Server 2003 SP2 and 2003 R2 SP2</li><li>• Windows XP SP2, Windows Vista, Windows 7, Windows 8, Windows 8.1 for trial purposes</li></ul>
Linux	<ul style="list-style-type: none"><li>• Red Hat Enterprise Linux (RHEL) v.6.4</li><li>• Fedora 19</li><li>• Ubuntu</li><li>• CentOS 6.4</li><li>• OpenSUSE</li></ul>

### Client requirements

The default web browser on many mobile devices can be used to transfer files, work with files and folders, or run the web-based Management Console of Serv-U without any plugins. However, Javascript and cookies must be enabled.

The following functionality is supported on the following devices:

Device	Supported functionality
Apple iPhone 3+	download, manage, and preview files
Apple iPad 1+	download, manage, and preview files, run the Management Console

Device	Supported functionality
Apple iPod	download, manage, and preview files
Google Android 2.2+	upload, download, manage, and preview files
Amazon Kindle Fire	upload, download, manage, and preview files
BlackBerry	upload, download, manage, and preview files
Microsoft Windows Mobile	upload, download, manage, and preview files

The following major browsers are supported with the basic web client, for file management and for web administration purposes:

- Microsoft Internet Explorer 8.0+
- Mozilla Firefox: latest two versions
- Safari 5 and 7
- Google Chrome: latest version
- Mobile browser

The following database management systems are supported:

- MS SQL 2012, 2012 SP1
- MySQL 5.7.3 and 5.7.4
- PostgreSQL: latest version

The following LDAP versions are supported:

- Active Directory 2003, 2008 and 2012
- Open Directory 4
- OpenLDAP 2.4

The following Java versions are supported:

- Java JRE 7 and 8

**Notes:**

- To be able to use Web Client Pro and FTP Voyager JV, Java must be installed and enabled in the browser.
- Web Client Pro does not work on Linux in Google Chrome version later than v35 due to an incompatibility between Chrome and the Java browser plugin.
- Apple Macintosh users must have at least Mac OS X 10.6 installed.

## Server concepts

The Serv-U File Server makes use of several concepts that help you understand how to configure and administer your file server as a single, hierarchical unit. The Serv-U File Server contains four related levels of configuration: the *server*, the *domain*, the *group*, and the *user*. Of all of these, only the group level is optional; all the other levels are mandatory parts of the file server. The following section contains an explanation of each configuration level:

### Server

The server is the basic unit of the Serv-U File Server and the highest level of configuration that is available. It represents the file server as a whole and governs the behavior of all domains, groups, and users. The Serv-U File Server contains a set of default options that can be overridden on a per setting basis. The server is at the top level of the hierarchy of configuring Serv-U. Domains, groups, and users inherit their default settings from the server. Inherited settings can be overridden at each of these lower levels. However, some settings are exclusive to the server, such as the PASV port range.

### Domain

A server can contain one or more domains. Domains are the interface through which users connect to the file server and access a specific user account. The settings of a domain are inherited from the server. A domain

also defines the collection of settings that all of its groups and user accounts inherit. If a server setting is overridden at the domain level, all the groups and user accounts that belong to the domain inherit the domain value as their default value.

### **Group**

The group is an optional level of configuration that can make it easier to manage related user accounts that share many of the same settings. By using a group, you can make changes that propagate to more than one user account instead of having to manually configure each user account separately. A group inherits all of its default settings from the domain it belongs to. A group defines the collection of settings inherited by all users who are members of the group. Virtually every user level setting can be configured at the group level, or can be overridden at the user level.

### **User**

The user is at the bottom of the hierarchy. It can inherit its default settings from multiple groups (if it is a member of more than one group) or from its parent domain (if it is not a member of a group, or the group does not define a default setting). A user account identifies a physical connection to the file server and defines the access rights and limitations of that connection. Settings overridden at the user level cannot be overridden elsewhere and are always applied to connections authenticated with that user account.

### **User collection**

Contrary to groups, a user collection does not offer any level of configuration to the user accounts they contain. Instead, a user collection offers a way to organize users into containers for easy viewing and administration. For example, collections can be created to organize user accounts based on group membership. User collections must be maintained manually when user accounts change group membership.

## Glossary

This topic contains the list and definition of terms that are frequently used in the Serv-U File Server.

### **Listener**

A listening service in Serv-U that is configured in a domain to accept incoming FTP, FTPS, SFTP, HTTP or HTTPS connections.

### **Limit**

A configuration option that can be set at the server, domain, group, or user level. Limits can be set for password complexity requirements, session timeout, Web Client customization, and more.

### **Event**

A Serv-U event primarily consists of an event type (for example, User Login or File Upload Failed), and an action type (for example, Show Balloon Tip or Send Email). Serv-U events are used to automate behavior and to provide greater visibility of important file transfer processes.

### **Anti-hammering**

A Serv-U feature which allows administrators to block IP addresses who attempt to connect repeatedly with incorrect credentials. By handling only IP addresses who repeatedly fail to log on correctly, anti-hammering allows for smart blocking of bots and hackers.

### **IP access rules**

IP access rules are used in Serv-U to determine who can connect to the server. Rules set up at the server and domain levels define who is allowed to make an initial connection to Serv-U. Rules set up at the group and user levels define who can connect using a given user account.

### **Directory access**

Directory access encompasses all of the permissions applied to a server, domain, group and user that grant and deny access to files and folders. Directory access rules are the foundation of file access rights, because they

determine what a user may and may not access, and also how they may access it.

### Quick start guide

Serv-U is simple to configure with the flexibility and control you require to easily share files with others under the best security possible. This quick start guide helps you install the server, create your first domain, and add a user account to the new domain. After you completed the following steps, you will be able to connect to your new file server and start transferring files.

#### Installing the Serv-U file server

If you are installing Serv-U for the first time, follow the instructions on the installation screens to choose the installation directory and to configure desktop shortcuts for quickly accessing the server.

Serv-U supports installation in English, German, Spanish, French, Italian, Serbian, Swedish, Russian, and Simplified and Traditional Chinese. At this point you are selecting only the default language for the Management Console. When users connect to Serv-U, they can select any language they want from the list of supported languages.

You can also choose to install Serv-U as a system service. If Serv-U is installed as a system service, Serv-U is automatically started when the server is started, before any user logs on to the system. This is useful if Serv-U is run on a dedicated server that does not regularly have an interactive user session logged on to it. If Serv-U is not installed as a system service, it has to be manually started after logging on to the server.

If you are installing Serv-U over an existing Serv-U installation, create a backup of the original installation folder first. While Serv-U can be safely installed over any existing installations and performs any necessary upgrades to data files and binaries, it is considered good data management practice to back up critical components before upgrading them.

When the installation is complete, the Serv-U Management Console is started. If you chose not to have the Serv-U Management Console started after installation, you can launch it by double-clicking the Serv-U icon in the system tray, or by right-clicking the Serv-U icon and selecting **Start Management Console**.

### Creating domains

When the Management Console finished loading, you are prompted whether you want to create a new domain if no domains are currently present.

Serv-U domains are collections of users and groups that share common settings, such as transfer rate limitations, service listeners, and directory access rules. In most cases, all of your users and settings will exist in the same domain, with no need to create separate domains.

**Note:** Having users sharing the same domain does not mean that all users have access to the same files. Each user in Serv-U has unique permissions to the directories you define, and does not have access to any files or folders unless you explicitly grant them access.

Click **Yes** to start the domain creation wizard. You can run this wizard at any time by clicking **+ (New Domain)** at the top of the Management Console.

#### To create a new domain:

1. Click **+ (New Domain)** at the top of the Management Console.
2. Type a unique name and an optional description for the new domain.  
**Note:** The domain name is not visible to any of its users, nor does it affect the way the domain is accessed by others. The name serves as an identifier for the domain to make the identification and management of the domain easier for administrators. The name must be unique so that it can be distinguished by Serv-U from the other domains on the server.
3. ***If you want the domain to be temporarily unavailable to users while you are configuring it,*** clear the **Enable domain** check box.
4. Click **Next**.

5. Decide whether you want the domain to be a File Transfer Domain, a File Sharing Domain, or both, and then click **Next**.

- ***If you are setting up a File Transfer Domain only***, perform the following steps:

- a. On the Protocols page, select the protocols and port numbers the domain should use to provide access to its users, and then click **Next**.

**Note:** The standard file sharing protocol is FTP, which operates on the default port of 21. However, you can change any of the available ports to a value you want. If you want to run the server on a non-default port, it is recommended that you use a port above 1024. For more information about the supported protocols in each Serv-U edition, see "Serv-U editions".

- b. On the IP Listeners page, specify the IP address that is used to connect to this domain, and then click **Next**.

**Note:** ***If you do not specify an address***, Serv-U will use any available IP address on the computer.

- c. On the Encryption page, select the encryption mode you want to use when storing passwords on the domain.

**Note:** For more information about password encryption modes, see "Domain limits and settings".

- d. ***If you want to enable users to recover their passwords***, select the appropriate option.

- e. Click **Finish** to create the domain, or click **Back** to modify the settings you specified.

- ***If you are setting up a File Sharing Domain only***, perform the following steps:



- a. On the File Sharing page, specify the domain URL, the file sharing repository, and whether you want to use secure URL.
- b. Click **Configure SMTP** to set up an SMTP server. An SMTP server is necessary for sending email notifications, and for events that use email actions.

**Note:** You can configure the SMTP server at a later time as well. For more information, see "Serv-U SMTP configuration".

- c. Click **Next**.
- d. On the IP Listeners page, specify the IP address that is used to connect to this domain.

**Note:** If you do not specify an address, Serv-U will use any available IP address on the computer.

- e. Click **Finish** to create the domain, or click **Back** to modify the settings you specified.

- ***If you are setting up a File Transer and File Sharing Domain,*** perform the following steps:

- a. On the File Sharing page, specify the domain URL, the file sharing repository, and whether you want to use Secure URL.
- b. Click **Configure SMTP** to set up an SMTP server. An SMTP server is necessary for sending email notifications, and for events that use email actions.

**Note:** You can configure the SMTP server at a later time as well. For more information, see "Serv-U SMTP configuration".

- c. Click **Next**.
- d. On the Protocols page, select the protocols and port numbers the domain should use to provide access to its users, and then

click **Next**.

**Note:** The standard file sharing protocol is FTP, which operates on the default port of 21. However, you can change any of the available ports to a value you want. If you want to run the server on a non-default port, it is recommended that you use a port above 1024. For more information about the supported protocols in each Serv-U edition, see "Serv-U editions".

- e. On the IP Listeners screen, specify the IP address that is used to connect to this domain, and then click **Next**.

**Note:** If you do not specify an address, Serv-U will use any available IP address on the computer.

- f. On the Encryption screen, select the encryption mode you want to use when storing passwords on the domain.

**Note:** For more information about password encryption modes, see Domain limits and settings.

- g. ***If you want to enable users to recover their passwords,*** select the appropriate option.

- h. Click **Finish** to create the domain, or click **Back** to modify the settings you specified.

You can configure additional properties for a domain. For more information about the available configuration options, see Domain settings.

### Creating user accounts

After your first domain is created, you are taken to the user's page of the Management Console and you are asked whether you want to create a new user account with the User Wizard. Click **Yes** to start the User Wizard

You can run this wizard at any time by navigating to the **Users** menu under Global or Domain, and then clicking **Wizard** on the Users page.

First, provide a unique login ID for the account. This login ID is used to begin the authentication process when the user connects to the domain. The login ID must be unique for the particular domain. Other domains on your server can have an account with the same login ID. To create an anonymous account, specify `anonymous` or `ftp` as the login ID.

You can also specify a full name and an email address for the user account. The full name provides a canonical name with which to refer to the user account. The email address is used by Serv-U to send email notifications and recovered passwords to the user account. Click **Next** to continue.

After specifying a unique login ID, you must also specify a password for the account. You can leave this field blank, however, that allows anyone who knows the login ID to access your domain. Click **Next** to continue.

The third step is to specify a home directory for the account. The home directory is the location on the hard drive of the server, or on an accessible network resource that the user account is placed in after a successful login. It is the location you want the user account to use when sending and receiving files on the server. Click **Browse** to browse to a location on your hard drive, or type the location. If users are locked in their home directory, they are not able to access files or folders above the directory structure of their home directory. Additionally, the actual location of their home directory is masked and displayed as "/". Click **Next** to proceed to the last step.

The last step is to grant access rights to the user account. Access rights are granted on a per directory basis. However, access rights can be inherited by all subdirectories contained in an accessible directory. The default access is **Read Only**, which means that the user can list files and folders in their home directory and can download them. However, they cannot upload files, create new directories, delete files or folders, or rename files or folders. If **Full Access** is selected, the user can do all of these things. After the user is created, you can configure the access rights on a more granular basis by editing the user, and

selecting the Directory Access page. After selecting the directory access rights, click **Finish** to create the user account.

The Serv-U File Server is now accessible and ready for sharing. You can create more accounts just like this one to share it with other friends, family, or colleagues. Each user can have a different home directory. This way you can share different files with different people. There are several more configurable options with which you can fine-tune the way a user account can access the server. For more information about these options, see "About user accounts".

### Sharing files

By using the file sharing feature, domain users can send or receive files from guests.

To send file sharing invitation emails, you must configure your SMTP settings. This configuration only needs to be set once for the entire server or a domain.

**Note:** File sharing is disabled by default.

For more information, see "File sharing".

### Using URL parameters

By using URL parameters, you can enhance the login process in various ways. You can create special login links. By using the special login links, users can automatically send their login ID and password, start audio files immediately, and more. To specify URL parameters, use the syntax in the following example:

```
www.example.com/?user=admin&password=test
```

The following parameters are supported in Serv-U:

```
user=username&password=password
```

Allows the Login ID and password to be sent automatically to Serv-U, bypassing the need to log in. This can be convenient for audio or video, but should not be used for confidential or protected information.

```
thumbnail=1
```

Starts the Web Client in thumbnail mode, showing thumbnails of images.

`slideshow=1`

Starts the Web Client in slideshow mode, showing a slideshow of all images.

`playlist=1`

Starts the Web Client in media mode, playing audio or video files in order.

`playmedia=1`

Starts the Web Client in media mode, playing video files only.

`dir=directory_name`

Specifies which directory to browse to immediately after login.

`file=file_name`

Specifies a file to download immediately after login. By default, the Web Client attempts to download the file from the home directory. If the `dir` parameter is used in conjunction with the `file` parameter, the Web Client attempts to download the specified file from the specified folder.

`sortcol=column`

Specifies the column by which to sort the files in the Web Client. The column accepts the integer values 1 - 3, for sorting by name, size, or time, respectively.

## The Serv-U Management Console

The Serv-U Management Console is designed to provide quick and easy access to the configuration options of the file server in a familiar way. When viewing a configuration page, you can return to the main Management Console page at any time by clicking the Serv-U File Server logo in the upper left corner.

### Management Console layout

The Management Console is presented in an accordion style layout, with an accordion list on the left, and the global dashboard on the right. The accordion menu contains the name of the server on top, and then the list of configured domains. The global dashboard contains the session statistics, the server log,

information about the active sessions, and it also provides direct access to the [thwack community](#).

Click the name of the server or a domain to expand the list of configuration options available for the server or for the particular domain, and then select one of the options.

Domain administrators only have access to configuring settings and options for their particular domain, and do not have access to the server-level categories that are displayed to system administrators.

To return to the global dashboard, click the Serv-U Management Console icon in the top left corner.

When opening a category from the Management Console, all related sub-category pages are displayed in tabs on the same page. This allows for quick navigation between related configuration options.

### Launching the Web Client

While configuring the Serv-U File Server, an HTTP session can be launched by clicking **Serv-U Products > Web Client** on the top toolbar. If licensed for use, the Web Client is available and runs from within the browser. If licensed for use, FTP Voyager JV can also be launched by clicking **Serv-U Products > FTP Voyager JV**.

**Note:** To use FTP Voyager JV, you must install the Java Runtime Environment.

## User interface conventions

The Serv-U File Server uses a consistent method of representing configuration options in a manner that conveys the current value of the option, and also indicates whether that value is the default or inherited value.

When an option inherits its value from a parent, the text of the option is displayed in regular font. The value that is displayed (whether it is a text value or a check box) can change to reflect changes made to the parent where the item is currently inheriting its value.

However, if the value is overriding the default, the text of the value is displayed in **bold**. The value that is currently displayed is always the value of that option, regardless of changes to its parent.

### Understanding user interface conventions

To better illustrate the user interface conventions, consider the following use case.

Example Technology Co. is a computer repair company that maintains a Serv-U File Server which provides global access to shared corporate resources to their traveling technicians. Each technician has their own account on the file server. To facilitate easy administration of the user accounts, the file server administrator makes each user account a member of the "Technician" group. The administration privilege level of this group is set to **No Privilege** because none of the technicians have any file server administration duties.



A technician receives a promotion. In addition to his current technician duties, he is also given administration privileges on the file server so he can assist other technicians with their accounts. The file server administrator can edit the technician's user account and change the technician's administration privilege level to **Domain Administrator**. The text of this option turns bold to reflect that it is overriding the default value (No Privilege) that the user account inherits from its membership of the "Technician" group.



At a later date, the administration privilege can be reverted to the default value which is inherited from the "Technician" group by selecting the **Inherit default value** option from the **Administration Privilege** list.

# Chapter 3: Server

## Server overview

On the Serv-U File Server you can configure certain settings at the server level. If you configure a setting at the server level, the setting applies to all users, groups, and domains on the server unless it is overridden at a lower level. Settings you can configure at the server level include directory access rules, IP access rules, bandwidth limitations, global user accounts, and more. The following sections contain detailed information about each setting and how it can be configured.

## Server details

### IP access rules

IP access rules restrict login access to specific IP addresses, ranges of IP addresses, or a domain name. IP access rules can be configured at the server, domain, group, and user levels.

IP access rules are applied in the order they are displayed. In this way, specific rules can be placed at the top to allow or deny access before a more general rule is applied later on in the list. The arrows on the right side of the list can be used to change the position of an individual rule in the list.

### Specifying IP access masks

IP access rules use masks to authorize IP addresses and domain names. The masks can contain specific values, ranges, and wildcards made up of the following elements:

#### **xxx**

Stands for an exact match, such as `192.0.2.0` (IPv4),  
`fe80:0:0:0:a450:9a2e:ff9d:a915` (IPv6, long form) or  
`fe80::a450:9a2e:ff9d:a915` (IPv6, shorthand).



### **xxx-xxx**

Stands for a range of IP addresses, such as `192.0.2.0-19` (IPv4),  
`fe80:0:0:0:a450:9a2e:ff9d:a915-a9aa` (IPv6, long form), or  
`fe80::a450:9a2e:ff9d:a915-a9aa` (IPv6, shorthand).

### **\***

Stands for any valid IP address value, such as `192.0.2.*`, which is  
analogous to `192.0.2.0-255`, or `fe80::a450:9a2e:ff9d:*`, which is  
analogous to `fe80::a450:9a2e:ff9d:0-ffff`.

### **?**

Stands for any valid character when specifying a reverse DNS name, such  
as `server?.example.com`.

### **/**

Specifies the use of CIDR notation to specify which IP addresses should be  
allowed or blocked. Common CIDR blocks are `/8` (for `1.*.*.*`), `/16` (for  
`1.2.*.*`) and `/24` (for `1.2.3.*`). CIDR notation also works with IPv6  
addresses, such as `2001:db8::/32`.

## **Caveats**

Specific IP addresses listed in Allow rules will not be blocked by anti-hammering. These IP addresses are whitelisted. However, addresses matched by a wildcard or a range will be subject to anti-hammering prevention.

## **Implicit deny all**

Until you add the first IP access rule, connections from any IP address are accepted. After you add the first IP access rule, all connections that are not explicitly allowed will be denied. This is also known as an implicit 'Deny All' rule. With this in mind, make sure you add a 'wildcard allow' rule (such as `Allow *.*.*.*`) at the end of your IP access rule list.

## **Matching all addresses**

Use the `*.*.*.*` mask to match any IPv4 address. Use the `::*` mask to match any IPv6 address. If you use both IPv4 and IPv6 listeners, add Allow

ranges for both IPv4 and IPv6 addresses.

### **DNS lookup**

If you use a dynamic DNS service, you can specify a domain name instead of an IP address to allow access to users who do not have a static IP address. You can also specify reverse DNS names. If you create a rule based on a domain name or reverse DNS, Serv-U performs either a reverse DNS lookup or DNS resolution to apply these rules. This can cause a slight delay during login, depending on the speed of the DNS server of the system.

### **Rule use during connection**

The level at which you specify an IP access rule also defines how far a connection is allowed before it is rejected. Server and domain level IP access rules are applied before the welcome message is sent. Domain level IP access rules are also applied when responding to the `HOST` command to connect to a virtual domain. Group and user level IP access rules are applied in response to a `USER` command when the client identifies itself to the server.


### **Anti-hammering**

You can set up an anti-hammering policy that blocks clients who connect and fail to authenticate more than a specified number of times within a specified period of time. You can configure an anti-hammering policy server-wide in **Server Limits and Settings > Settings** and domain-wide in **Domain Limits and Settings > Settings**.

IP addresses blocked by anti-hammering rules appear in the domain IP access rules with a value in the **Expires in** column. If you have multiple domains with different listeners, blocked IP addresses appear in the domain that contains the listener. Blocked IP addresses do not appear in the server IP access list, even if anti-hammering is configured at the server level.

The **Expires in** value of the blocked IP counts down second by second until the entry disappears. You can unblock any blocked IP early by deleting its

entry from the list.



### IP access list controls

The following section contains a description of the options that are available on the IP Access page.

#### Using the sort mode

By using the sort mode, you can sort the IP access list numerically rather than in the processing order. Displaying the IP access list in sort mode does not change the order in which rules are processed. To view rule precedence, disable this option. Viewing the IP access list in numerical order can be a valuable tool when you review long lists of access rules to determine if an entry already exists.

#### Importing and exporting IP access rules

You can export and import Serv-U IP access rules from users, groups, domains, and the server by using a text-based CSV file. To export IP access

rules, view the list of rules to export, click **Export**, and then specify the path and the file name you want to save the list to. To import IP access rules, click **Import** and select the file that contains the rules you want to import. The CSV file must contain the following fields, including the headers:

**IP**

The IP address, IP range, CIDR block, or domain name for which the rule applies.

**Allow**

Set this value to 0 for Deny, or to 1 for Allow.

**Description**

A text description of the rule for reference purposes.

**Examples****Case File: Office-only access**

A contractor has been hired to work in the office, and only in the office. Office workstations have IP addresses in the range of 192.0.2.0 - 192.0.2.24. The related Serv-U access rule should be `Allow 192.0.2.0-24`, and it should be added to either the contractor's user account or a Contractors group that contains multiple contractors. No deny rule is required here because Serv-U provides an implicit deny all rule at the end of the list.

**Case File: Prohibited computers**

Users should normally be able to access Serv-U from anywhere, except from a bank of special internal computers in the IP address range of 192.0.2.0 - 192.0.2.24. The related Serv-U access rules should therefore be `Deny 192.0.2.0-24`, followed by `Allow *.*.*.*`, and these should both be added to either the domain or the server IP access rules.

**Case File: DNS-based access control**


The only users allowed to access a Serv-U domain will be connecting from `*.example.com` or `*.example1.com`. The related Serv-U access rules should

therefore be `Allow *.example.com` and `Allow *.example1.com` in any order, and these should both be added to the domain IP access rules. No deny rule is required here because Serv-U provides an implicit deny all rule at the end of the list.

### Serv-U Gateway

Serv-U Gateway provides defense in depth to Serv-U deployments.

It acts as a reverse proxy in DMZ segments and prevents your Serv-U deployments from storing data in the DMZ, or opening connections from the DMZ to the internal network. This type of architecture is essential to meet PCI DSS, managed file transfer, and other high-security requirements.




### Deploying Serv-U Gateway


The following documents contain detailed information about the deployment of Serv-U Gateway:


- [Serv-U Distributed Architecture Guide](#)
- Serv-U Gateway Installation Instructions
  - [For Windows](#)
  - [For Linux](#)
- [Planning Your Serv-U Gateway Deployment](#)

### Serv-U Gateway tab


 **Server Details** - Displays information pertaining to the entire file server, including server-wide access rules, license, and registration information.

IP Access | **Serv-U Gateway** | Database | Events | License Information | Program Information

 Serv-U Gateway is an optional reverse-proxy component that safely terminates file transfer connections in the DMZ to avoid inbound connections or storing data in the DMZ. See the Serv-U Distributed Architecture Guide for more information. Click "Properties" to apply Serv-U Gateway licenses.

Gateway Address	Status	Enabled	Public IP Address
 192.168.5.62	Disabled	No	67.52.42.101

< | >

Add... Edit... Delete Properties...  More Information





The Serv-U Gateway page in Server Details displays all configured gateways known to the Serv-U deployment. Serv-U periodically checks every configured gateway and displays a brief status message here.

### Gateway Address column

The gateway address is the IP address on the Serv-U Gateway that Serv-U uses to communicate with Serv-U Gateway. This should almost always be a private IP address.

A status icon is displayed on the left of the gateway address. The Status column displays a brief message that indicates the current status of the gateway.

The icon in the Gateway Address column changes to reflect the current gateway status.

-  The gateway is ready for connections. However, the gateway still needs listeners to receive connections.
-  Serv-U is checking the status of the gateway. Another status will appear in a few seconds.
-  The gateway is ready but the Serv-U installation is running close to the end of the trial period, or support period.
-  An error occurred. For more information about why it is not possible connect to the gateway, select the gateway entry, and then select **Properties**.

### Public IP Address column

The Public IP Address column shows the IP address file transfer clients should connect to.

A private IP address is displayed in the Public IP Address column if a private IP address was explicitly configured in the gateway. This will be the case if the gateway has no public IP addresses, which is common during trials and situations in which the gateway is placed behind NAT (network address translation).

### Description column

The Description column displays any note that is added to the gateway

configuration. It does not affect behavior in any way.

### Managing gateways in Serv-U


Click **Add** to add new gateway configurations.

Click **Edit** to edit existing gateway configurations.

Click **Delete** to delete existing gateway configurations.

Click **Properties** to view detailed status about and add licenses to existing gateway configurations. This button only displays complete properties when Serv-U is connected to the gateway.

### Serv-U Gateway Add/Edit dialog



The screenshot shows the 'Serv-U Gateway' dialog box. It has a title bar with the text 'Serv-U Gateway' and a close button (X). The dialog contains the following fields and controls:

- Gateway Address:** A text input field containing '192.168.5.63'.
- Port:** A text input field containing '1180'.
- Public IP Address:** A text input field containing '67.52.42.106'.
- Enable Gateway:** A checkbox that is checked.
- Description:** A text input field that is empty.
- Buttons:** Three buttons are located on the right side: 'Save', 'Cancel', and 'Help'.

The Gateway Address is the IP address on the Serv-U Gateway that Serv-U uses to communicate with Serv-U Gateway. This should almost always be a private IP address.

The Port is the TCP port on the Serv-U Gateway that Serv-U uses to communicate with Serv-U Gateway. The default is TCP port 1180.


The Public IP Address field should contain the IP address file transfer clients should connect to. A private IP address should be entered in the Public IP Address field if the gateway has no public IP addresses. This is common during trials and situations in which the gateway lives behind NAT (network address translation).



The **Enable Gateway** option is used to turn the gateway on and off. The default is selected.

The Description is an optional note that describes the gateway. It has no effect on the behavior.

### Serv-U Gateway Properties dialog



### Status area

The large icon in the **Status** area and a status message indicate if the gateway is running, and whether or not it is running with a trial or commercial license.

The **Available Public IP Addresses** field contains a list of all the public IP addresses automatically detected on Serv-U Gateway. If a private address is configured in the **Public IP Address** field of the gateway, this field displays a message indicating that no public IP addresses are found on the gateway server. This is expected behavior.

### **Install information area**

The **Install Information** area shows the version and build date of the Serv-U Gateway software running on the gateway, the date Serv-U Gateway was installed or last updated, and, if applicable, the number of days left in the evaluation period.

### **Registration ID area**

Copy and paste your Serv-U Gateway Registration ID (not your Serv-U Registration ID) into this field, and then click **Save** to apply a commercial license to your Serv-U Gateway software.

### **Database access**

Serv-U enables the use of an ODBC database to store and maintain group and user accounts at both the domain and server levels. You can configure the ODBC connections in two locations: **Domain > Domain Details > Database** and **Server > Server Details > Database**. Serv-U can automatically create all of the tables and columns that are necessary to begin storing users and groups in the database. Because Serv-U uses one set of table names to store its information, individual ODBC connections must be configured for each item which stores details in the database. In other words, the server as well as each domain must have a unique ODBC connection to ensure they are stored separately.

**To configure a database, perform the following steps:**

1. Create an ODBC connection for Serv-U to use. SolarWinds recommends MySQL, but you can use any database that has an ODBC driver available. Use a System DSN if Serv-U is operating as a system service, or a User DSN if Serv-U is operating as a regular application.

2. Open the Serv-U Management Console and browse to the appropriate domain or server database settings. Enter the Data Source Name (DSN), the login ID, and the password, and then click **Save**.

If you configure the database connection for the first time, leave the **Automatically create** options selected. With these options selected, the Serv-U File Server builds the database tables and columns automatically.

### Using SQL templates

Serv-U uses multiple queries to maintain the databases that contain user and group information. These queries conform to the SQL language standards. However, if your database have problems working with Serv-U, you may need to alter these queries. In the SQL Templates window, you can modify each query used by Serv-U to conform to the standards supported by your database.

**Warning:** Incorrectly editing these SQL queries could cause ODBC support to stop working in Serv-U. Do not edit these queries unless you are comfortable constructing SQL statements and are positive that it is necessary to enable ODBC support with your database software.

### Using user and group table mappings

By default, Serv-U automatically creates and maintains the tables and columns that are necessary to store user and group information in a database. However, if you want to connect Serv-U to an existing database which contains this information, you must customize the table and column names to conform to the existing database structure. Click **User Table Mappings** or **Group Table Mappings** to get started.

Serv-U stores information for a user or group in 10 separate tables. Only the User/Group Info Table and User/Group Dir Access Table are required. You can change the current table in the **Object Table** list. The **Attribute** column lists the attributes that are stored in the current table. The **Mapped Database Value** displays the name of the column that attribute is mapped to in the database. The

first row displays the "TableName" and can be used to change the name of the table.

Certain tables where the order of the entries is important have a **SortColumn** attribute listed. This column is used to store the order in which rules are applied.

Click **Edit** or double-click the column name to edit a value.

When enabled, the table is accessed as needed. In special situations a table that is not being used can be disabled to reduce the number of ODBC (database) calls. For example, if you do not use ratios and quotas, you can disable the User Ratio-Free Files, Per User Files Ratio, Per User Bytes Ratio, Per Session Files Ratio, and Per Session Bytes Ratio tables to prevent unnecessary ODBC calls. Use caution when you disable tables, because the fields will appear in dialogs, but they will not be saved or loaded.

The User Info and Group Info tables cannot be disabled.

### **Case file: ODBC authentication**

Authentication in the Serv-U File Server can be handled through an ODBC database, allowing for scripted account management and maintenance. To use ODBC functionality, migrate to ODBC authentication through a database. By storing credentials in settings in a database, accounts can be managed from outside the Serv-U Management Console through scripted database operations which can be built into many existing account provisioning systems. A DSN must first be created in **Control Panel > Administrative Tools > ODBC Data**

**Sources.** Use a System DSN if Serv-U is running as a service or a User DSN if Serv-U is running as an application. After you created the appropriate DSN, specify the data source name, login ID and password, and then click **Save**. Serv-U creates the tables and columns transparently. You can manage database users and groups in the Database Users and Database Groups pages of Serv-U, located near the normal Users and Groups pages.

### **Creating data source names in Linux**

Database access in Serv-U on Linux follows the same method as Serv-U on Windows, with the one change in how data source names are created. On Linux,

you can create a DSN after installing the following packages:

- `mysql-connector-odbc`
- `postgresql-odbc`
- `unixodbc`

Only the ODBC driver corresponding to the database needs to be installed. If Serv-U is running as a service, the next step is to edit the `/etc/odbc.ini` file, which contains all system-level DSNs. If Serv-U is running as an application, edit the `~/odbc.ini` file instead, and then enter the parameters as follows:

```
[MySQL-test]
Description = MySQL test database
Trace = Off
TraceFile = stderr
Driver = MySQL
SERVER = YOURIPADDRESS
USER = USERNAME
PASSWORD = PASSWORD
PORT = 3306
DATABASE = YOURDATABASE
```

```
[PostgreSQL-test]
Description = Test to Postgres
Driver = PostgreSQL
Trace = Yes
TraceFile = sql.log
Database = YOURDATABASE
Servername = YOURIPADDRESS
Username = USERNAME
Password = PASSWORD
Port = 5432
Protocol = 6.4
ReadOnly = No
RowVersioning = No
ShowSystemTables = No
ShowOidColumn = No
FakeOidIndex = No
ConnSettings =
```

Adjust the names in brackets to the DSN name string you want. Finally, test the DSN by using the `isql %DSN% -c -v` command.

For further customization options, see the [Serv-U Database Integration Guide](#).

## Serv-U events

**Events**

Events Event Filters

**Event Information**

Event Type:  
File Uploaded

Event Name:  
Event 01

☒ Enable event

Description:  
Show balloon tip when users upload a file.

**Event Actions**

Action:  
Show Balloon Tip

Balloon Title:  
"\$name" Has Uploaded A File.

Balloon Information:  
\$LocalPathName  
Size: \$FileSizeFmt bytes (\$FileSize KB KB)  
\$TransferBytes bytes transferred.  
\$TransferKBPerSecond KB/sec.  
Protocol: \$Protocol

Save Cancel Help

In Serv-U, you can use event handling which can perform various actions triggered by a list of selected events. The following list contains the available actions:

### Server events

#### Server Start

Triggered by Serv-U starting up, whether by starting the Serv-U service or starting Serv-U as an application.

#### Server Stop

Triggered by Serv-U shutting down, whether from service or application-level status. This event only triggers for graceful stops.

### Server and domain events

#### Domain Start

Triggered by a Serv-U domain starting, through the **Enable Domain** setting in the **Domain Details > Settings** menu, or as part of normal server startup.

#### Domain Stop

Triggered by a Serv-U domain stopping, through the **Enable Domain** setting in the **Domain Details > Settings** menu, or as part of normal server startup.

#### Session Connection

Triggered by a new TCP session connection.

#### Session Disconnect

Triggered by a TCP session disconnection.

#### Session Connection Failure

Triggered by a failed session connection attempt.

#### Log File Deleted

Triggered by the automatic deletion of a log file, according to logging settings.

#### Log File Rotated

Triggered by the automatic rotation of a log file, according to logging settings.

**Listener Success**

Triggered by a successful listener connection.

**Listener Stop**

Triggered by a stopped listener connection.

**Listener Failure**

Triggered by a failed listener connection.

**Gateway Listener Success**

Triggered by a successful gateway listener connection.

**Gateway Listener Stop**

Triggered by a stopped gateway listener connection.

**Gateway Listener Failure**

Triggered by a failed gateway listener connection.

**Permanent Listener Success**

Triggered by a successful permanent listener connection.

**Permanent Listener Failure**

Triggered by a failed permanent listener connection.

**Permanent Listener Stop**

Triggered by a stopped permanent listener connection.

**Permanent Gateway Listener Success**

Triggered by a successful permanent gateway listener connection.

**Permanent Gateway Listener Stop**

Triggered by a stopped permanent gateway listener connection.

**Permanent Gateway Listener Failure**

Triggered by a failed permanent gateway listener connection.

**File Management Rule Success**

Triggered when a file management rule is applied, and no errors are encountered.



### **File Management Rule Failure**

Triggered when a file management rule is applied, and at least one error is encountered.

### **Server, domain, user and group events**

#### **User Login**

Triggered by the login of a user account.

#### **User Logout**

Triggered by the logout of a user account.

#### **User Login Failure**

Triggered by a failed login. A failed login is any connection attempt to Serv-U that fails, whether due to invalid credentials, or a session disconnect before authentication, either due to an incorrect user name, incorrect password, incorrect SSH key pair (for SFTP public key authentication), or any or all of the above.

#### **User Password Change**

Triggered by the change of a password for a user account by the user (if permitted).

#### **User Password Change Failure**

Triggered by a failed password change attempt.

#### **User Enabled**

Triggered by the enabling of a user account that was previously disabled.

#### **User Disabled**

Triggered by the disabling of a user account that was previously enabled.

#### **User Deleted**

Triggered by the deletion of a user account by a remote administrator, in an ODBC database, or in the local Management Console.

### **User Added**

Triggered by the creation of a user account by a remote administrator, in an ODBC database, or in the local Management Console.

### **Password Recovery Sent**

Triggered by a successful password recovery by an end user.

### **Password Recovery Failed**

Triggered by a failed password recovery attempt, either due to lack of email address in the user account or lack of permissions.

### **Password Stale**

Triggered by a stale password, as configured in **Limits & Settings**, that is going to expire.

### **User Auto Disable**

Triggered by the automatic disabling of a user account, as configured by a user's **Automatically Disable** date.

### **User Auto Deleted**

Triggered by the automatic deletion of a user account, as configured by a user's **Automatically Delete** date.

### **User Pre-disable**

Triggered by the upcoming disabling of a user account, as configured in the user's **Automatically Disable** date and the "Days before automatically disabling account to trigger the pre-disable event" limit.

### **User Pre-delete**

Triggered by the upcoming deletion of a user account, as configured in the user's **Automatically Delete** date and the **Days before automatically deleting account to trigger the pre-delete** event limit.

### **User Email Set**

Triggered by a user setting the email address for a user account.

### **User Email Set Failure**

Triggered by a failed attempt by a user to set the email address for a user account.

### **IP Blocked**

Triggered by a failed login attempt due to an IP access rule.

### **IP Blocked Time**

Triggered by a failed login attempt due to an IP access rule that was automatically added by brute force settings, configured in **Domain Limits & Settings** or **Server Limits & Settings**.

### **Too Many Sessions**

Triggered by more sessions logging on to the server than are permitted, per the **Limits & Settings** for the user account, group, domain, or server.

### **Too Many Session On IP**

Triggered by more sessions logging on to the server from a specific IP address than are permitted, according to the **Limits & Settings** for the user account, group, domain, or server.

### **IP Auto Added To Access Rules**

Triggered by the automatic addition of an IP access rule due to a user triggering the "brute force" settings.

### **Session Idle Timeout**

Triggered by an idle session timeout.

### **Session Timeout**

Triggered by a session timeout.

### **File Uploaded**

Triggered by a file uploaded to Serv-U. This event triggers for partial uploads if the upload session terminated with a successful message and no data corruption.

### **File Upload Failed**

Triggered by a failed file upload to Serv-U.

### **File Download**

Triggered by a file downloaded from Serv-U.

### **File Download Failed**

Triggered by a failed file download from Serv-U.

### **File Deleted**

Triggered by the deletion of a file on the Serv-U server by a user.

### **File Moved**

Triggered by the moving of a file on the Serv-U server by a user.

### **Directory Created**

Triggered by the creation of a directory.

### **Directory Deleted**

Triggered by the deletion of a directory.

### **Directory Changed**

Triggered by changing the current working directory.

### **Directory Moved**

Triggered by moving a directory to a new location.

### **Over Quota**

Triggered by going over disk quota space. The current quota space is shown in the user account, in the **Limits & Settings** menu.

### **Over Disk Space**

Triggered by exceeding the Max Dir Size configured for a directory access rule. The current disk space is shown with the **AVBL FTP** command, or by using the **Directory Properties** option in the HTTP or HTTPS Web Client and FTP Voyager JV.

## **Creating common events**

You can automatically create a list of the most common events. You can choose to create these common events using email or balloon tip actions. Click **Create Common Event** in the Events page. Select either the **Send Email** or **Show**

**balloon tip** option for the action you want to perform on the common events. If you choose to send email, also enter an email address where the events are to be sent.

**Note:** The **Write to Windows Event Log** and **Write to Microsoft Message Queue (MSMQ)** options are available for Windows only.

### Using event actions

You can select from the following actions that will be executed when an event is triggered:

- Send Email
- Show Balloon Tip\*
- Execute Command\*
- Write to Windows Event Log (Windows only)\*
- Write to Microsoft Message Queue (MSMQ) (Windows only)\*

\* Events involving anything other than email can only be configured by Serv-U server administrators.

### Using email actions

You can configure email actions to send emails to multiple recipients and to Serv-U groups when an event is triggered. To add an email address, enter it in the **To** or **Bcc** fields. To send emails to a Serv-U group, use the **Group** icon to add or remove Serv-U groups from the distribution list. Separate email addresses by commas or semicolons. Email actions contain a **To**, **Subject** and **Message** parameter. You can use special variables to send specific data pertaining to the event. For more information about the variables, see "System variables".

To use email actions, you must first configure SMTP in Serv-U. For information about SMTP configuration, see "Serv-U SMTP configuration".

### Using balloon tip actions

You can configure balloon tip actions to show a balloon tip in the system tray when an event is triggered. Balloon tip actions contain a **Balloon Title** and a

**Balloon Message** parameter. You can use special variables to send specific data pertaining to the event. For more information about the variables, see "System variables".

### Using execute command actions

You can configure execute command actions to execute a command on a file when an event is triggered. Execute command actions contain an **Executable Path**, **Command Line Parameters**, and a **Completion Wait Time** parameter. For the **Completion Wait Time** parameter, you can enter the number of seconds to wait after starting the executable path. Enter zero for no waiting.

**Note:** Any amount of time Serv-U spends waiting delays any processing that Serv-U can perform.

A wait value should only be used to give an external program enough time to perform some operation, such as move a log file before it is deleted (for example, `$LogFilePath` for the Log File Deleted event). You can use special variables to send specific data pertaining to the event. For more information about the variables, see "System variables".

### Writing to the Windows Event Log

By writing event messages to a local Windows Event Log, you can monitor and record Serv-U activity by using third-party network management software. All messages appear in the Windows Application Log from a source of "Serv-U".

This event has only one field:

- **Log Information:** The contents of the message to be written into the event log. This is normally either a human-readable message (for example, `filename uploaded by person`) or a machine-readable string (for example, `filename|uploaded|person`), depending on who or what is expected to read these messages. Serv-U system variables are supported in this field. This field can be left blank, but usually is not.

### Writing to Microsoft Queue (MSMQ)

Microsoft Message Queuing (MSMQ) is an enterprise technology that provides a

method for independent applications to communicate quickly and reliably. Serv-U can send messages to new or existing MSMQ queues whenever a Serv-U event is triggered. Corporations can use this feature to tell enterprise applications that files have arrived, files have been picked up, partners have signed on, or many other activities have occurred.

These events have the following two fields:

- **Message Queue Path:** The MSMQ path that addresses the queue. Remote queues can be addressed when a full path (for example, `MessageServer\Serv-U Message Queue`) is specified. Local, public queues on the local machine can be addressed when a full path is not specified (for example, `.\Serv-U Message Queue` or `Serv-U Message Queue`). If the specified queue does not exist, Serv-U attempts to create it. This normally only works on public queues on the local machine. You can also use Serv-U system variables in this field.
- **Message Body:** The contents of the message to be sent into the queue. This is normally a text string with a specific format specified by an enterprise application owner or enterprise architect. Serv-U system variables can also be used in this field. This field may be left blank, but usually is not.

**Note:** Microsoft message queues created in Windows do not grant access to SYSTEM by default, preventing Serv-U from writing events to the queue. To correct this, after creating the queue in MSMQ, right-click it, select **Properties**, and then set the permissions so that SYSTEM (or the network account under which Serv-U runs) has permission to the queue.

### Using event filters

By using Serv-U event filters, you can control to a greater degree when a Serv-U event is triggered. By default, Serv-U events trigger each time the event occurs. The event filter allows events to be triggered only if certain conditions are met. For example, a standard Serv-U event might trigger an email each time a file is uploaded to the server. However, by using an event filter, events can be triggered

on a more targeted basis. For example, you can configure a File Uploaded event to only send an email when the file name contains the string `important`, so an email would be sent when the file `Important Tax Forms.pdf` is uploaded but not when other files are uploaded to the server. Additionally, you can configure a File Upload Failed event to run only when the FTP protocol is used, not triggering for failed HTTP or SFTP uploads. You can do this by controlling the various variables and values related to the event and by evaluating their results when the event is triggered.

### Event filter fields

Each event filter has the following critical values that must be set:

- **Name:** This is the name of the filter, used to identify the filter for the event.
- **Description (Optional):** This is the description of the event, which may be included for reference.
- **Logic:** This determines how the filter interacts with other filters for an event. In most cases, AND is used, and all filters must be satisfied for the event to trigger. The function of AND is to require that all conditions be met. However, the OR operator can be used if there are multiple possible satisfactory responses (for example, abnormal bandwidth usage of less than 20 KB/s OR greater than 2000 KB/s).
- **Filter Comparison:** This is the most critical portion of the filter. The Filter Comparison contains the evaluation that must occur for the event to trigger. For example, a filter can be configured so that only the user "admin" triggers the event. In this case, the comparison will be `If $Name = (is equal to) admin`, and the data type will be `string`. For bandwidth, either an "unsigned integer" or "double precision floating point" value would be used.

Event filters also support wildcards when evaluating text strings. The supported wildcards are the following:

- **\*** - The asterisk wildcard matches any text string of any length. For example:
  - An event filter that compares the `$FileName` variable to the string `data*` matches files named `data`, `data7`, `data77`, `data.txt`, `data7.txt`, and



`data77.txt.`

- **?** - The question mark wildcard matches any one character, but only one character. For example:
  - An event filter that compares the `$FileName` variable to the string `data?` matches a file named `data7` but not `data`, `data77`, `data.txt`, `data7.txt`, or `data77.txt`.
  - An event filter that compares the `$FileName` variable to the string `data?.*` matches files named `data7` and `data7.txt` but not `data`, `data77`, `data.txt`, or `data77.txt`.
  - An event filter that compares the `$Name` variable to the string `A????` matches any five-character user name that starts with `A`.
- **[]** - The bracket wildcard matches a character against the set of characters inside the brackets. For example:
  - An event filter that compares the `$FileName` variable to the string `data[687].txt` matches files named `data6.txt`, `data7.txt` and `data8.txt` but not `data5.txt`.
  - An event filter that compares the `$LocalPathName` variable to the string `[CD]:\*` matches any file or folder on the `C:` or `D:` drives.

You can use multiple wildcards in each filter. For example:

- An event filter that compares the `$FileName` variable to the string `[cC]:\*.???` matches any file on the `C:` drive that ends in a three letter file extension.
- An event filter that compares the `$FileName` variable to the string `?:\*Red[678]\?????.*` matches a file on any Windows drive, contained in any folder whose name contains `Red6`, `Red7` or `Red8`, and that also has a five character file name followed by a file extension of any length.

### Using event filters

Event filters are used by comparing fields to expected values in the Event Filter

menu. The best example is raising an event only when a certain user triggers the action, or when a certain file is uploaded. For example, an administrator may want to raise an email event when the file `HourlyUpdate.csv` is uploaded to the server, but not when other files are uploaded. To do this, create a new event in the **Domain Details > Events** menu. The **Event Type** is File Uploaded, and on the Event Filter tab a new filter must be added. The `$FileName` variable is used and the value is `HourlyUpdate.csv` as shown in the following screen capture:

**Filter Comparison** [X]

Comparisons must be added to the event filter to define the scenario that will allow or disallow the event.

Save Cancel Help

If  = (is equal to)

Data Type:

As another example, it might be necessary to know when a file transfer fails for a specific user account. To perform this task, create a new File Upload Failed event, and then add a new filter. The filter comparison is the `$Name` variable, and the value to compare is the user name, such as `ProductionLineFTP`:

**Filter Comparison** [X]

Comparisons must be added to the event filter to define the scenario that will allow or disallow the event.

Save Cancel Help

If  = (is equal to)

Data Type:

You can also filter for events based on specific folders, using wildcards. In some cases it may be necessary to trigger events for files uploaded only to a specific folder, such as when an accounting department uploads time-sensitive tax files. To filter based on a folder name, create a new File Uploaded event in the **Domain Details > Events** menu, and set it to **Send Email**. After specifying the

email recipients, subject line, and message content, open the Event Filters page. Create a new event filter, and add the filter comparison `If $LocalPathName = (is equal to) C:\ftproot\accounting\*` with the type of `(abcd) string`. This will cause the event to trigger only for files that are located within `C:\ftproot\accounting\.`

### License information

The License Information tab displays the information contained in the current registration ID in use by the Serv-U File Server. If the installation is running in trial mode, information about the number of trial days remaining is also included. Information contained on this page includes the following:

#### **Name**

The name associated with the current license.

#### **Email address**

The email address associated with the current license.

#### **Serv-U edition**

The Serv-U edition that is enabled by the current license. For more information, see Serv-U editions.

#### **Copies**

The number of concurrent installations allowed by the current license.

#### **Purchase date**

The date the current license was purchased.

### **Updates**

The date through which the current license allows free updates to the latest version. If Serv-U is running as a trial version, the number of trial days remaining is displayed.

### **Additional products**

Additional add-ons for Serv-U, and whether or not they are enabled.

### **Edition information**

Displays the enabled functionality and limitations of the licensed Serv-U edition.

### **Registering Serv-U**

To register the Serv-U File Server, click **Enter License ID** on the bottom toolbar, and then enter your alphanumeric registration ID. If you have lost your ID, click **Lost ID** for assistance in retrieving it. If you want to purchase an ID, click **Purchase** to visit the Serv-U website to purchase an ID. To upgrade your Serv-U installation, click **Upgrade License**.

## **Program Information**

The Program Information page displays information about the current version of Serv-U installed on the server including the following details:

### **Serv-U File Server Version Number**

The full version number of the current installation.

### **Build Date**

The date of the software build of the current installation.

### **Install Date**

The original date when Serv-U was first installed on the computer.

### **Operating system**

Information about the operating system on which Serv-U is installed.

### **Development Information**

Information about the development and localization (if applicable) for the

Serv-U File Server.

### Contact Information

The contact information for SolarWinds.

### Legal Disclaimer

The Serv-U legal disclaimer.

## Serv-U SMTP configuration


In Serv-U, you can configure an SMTP connection to send email for events which are configured to use email actions. You can configure SMTP on the server or domain level, or both. SMTP configuration at the domain level can be inherited from the server level. The SMTP configuration dialog is located in the Events tab in the **Domain Details** and **Server Details** pages. Click **Configure SMTP** to launch the dialog, and then specify the following details:

- **SMTP Server:** The name or IP address of the SMTP server.
- **SMTP Server Port:** The port the SMTP server is using.
- **From Email Address:** The email address to use for the outgoing email.
- **From Name (optional):** The name to use for the outgoing email.
- **This server requires a secure connection (SSL):** On some SMTP servers all incoming connections must be encrypted to protect against possible attacks. If your server requires that all incoming connections must be encrypted, enable this option. The default port for encrypted SMTP connections is 465. Serv-U supports Implicit SSL only, and does not support Explicit SSL (port 587).
- **My server requires authentication:** To enable authentication, select this option.

If your SMTP server requires authentication, enter the following information:

- **Account Name:** The account name associated with authentication for the SMTP server.

- **Password:** The password for the account.



The screenshot shows the 'SMTP Configuration' dialog box. It has a title bar with a close button (X). Below the title bar is a message icon and text: 'Configure Serv-U to use a SMTP server to send email for email notifications and events that use email actions. This configuration only needs to be set once for an entire domain.' To the right of this message are three buttons: 'OK', 'Cancel', and 'Help'.

The dialog is divided into two main sections:

- Server Information:**
  - SMTP Server:
  - SMTP Server Port:
  - ☐ This server requires a secure connection (SSL)
  - From Email Address:
  - From Name (optional):
  - ☒ My server requires authentication
- Authentication Information:**
  - Account Name:
  - Password:

## Directory access rules

### Directory access rules

Directory access rules define the areas of the system which are accessible to user accounts. While traditionally restricted to the user and group levels, in Serv-U, the usage of directory access rules is extended to both the domain and the server levels through the creation of global directory access rules. Directory access rules specified at the server level are inherited by all users of the file server. If they are specified at the domain level, they are only inherited by users who belong to the particular domain. The traditional rules of inheritance apply

where rules specified at a lower level (for example, the user level) override conflicting or duplicate rules specified at a higher level (for example, the server level).

When you set the directory access path, you can use the `%USER%`, `%HOME%`, `%USER_FULL_NAME%`, and `%DOMAIN_HOME%` variables to simplify the process. For example, use `%HOME%/ftproot/` to create a directory access rule that specifies the `ftproot` folder in the home directory of the user. Directory access rules specified in this manner are portable if the actual home directory changes while maintaining the same subdirectory structure. This leads to less maintenance for the file server administrator. If you specify the `%USER%` variable in the path, it is replaced with the user's login ID. This variable is useful in specifying a group's home directory to ensure that users inherit a logical and unique home directory. You can use the `%USER_FULL_NAME%` variable to insert the Full Name value into the path (the user must have a Full Name specified for this to function). For example, the user "Tom Smith" could use `D:\ftproot\%USER_FULL_NAME%` for `D:\ftproot\Tom Smith`. You can also use the `%DOMAIN_HOME%` macro to identify the user's home directory. For example, to place a user and their home directory into a common directory, use `%DOMAIN_HOME%\%USER%`.

Directory access rules are applied in the order they are listed. The first rule in the list that matches the path of a client's request is the one that is applied for that rule. In other words, if a rule exists that denies access to a particular subdirectory but is listed *below* the rule that grants access to the parent directory, then a user still has access to the particular subdirectory. Use the arrows on the right of the directory access list to rearrange the order in which the rules are applied.

The following section contains the list and description of the directory access permissions.

### File permissions

#### Read

Allows users to read (that is, download) files. This permission does not allow users to list the contents of a directory, which is granted by the **List**

permission.

### **Write**

Allows users to write (that is, upload) files. This permission does not allow users to modify existing files, which is granted by the **Append** permission.

### **Append**

Allows users to append data to existing files. This permission is typically used to grant users the ability to resume transferring partially uploaded files.

### **Rename**

Allows users to rename existing files.

### **Delete**

Allows users to delete files.

### **Execute**

Allows users to remotely execute files. The execute access is meant for remotely starting programs and usually applies to specific files. This is a very powerful permission and great care should be used in granting it to users. Users with **Write** and **Execute** permissions can install any program they want on the system.

## **Directory permissions**

### **List**

Allows users to list the files and subdirectories contained in the directory. Also allows users to list this folder when listing the contents of a parent directory.

### **Create**

Allows users to create new directories within the directory.

### **Rename**

Allows users to rename existing directories within the directory.



### Remove

Allows users to delete existing directories within the directory.

**Note:** If the directory contains files, the user also needs to have the **Delete** files permission in order to remove the directory.

### Subdirectory permissions

#### Inherit

Allows all subdirectories to inherit the same permissions as the parent directory. The **Inherit** permission is appropriate for most circumstances, but if access must be restricted to subfolders (as is the case when implementing mandatory access control), clear the **Inherit** check box and grant permissions specifically by folder.

### Advanced: Access as Windows User (Windows Only)

For a variety of reasons, files and folders may be kept on external servers in order to centralize file storage or provide additional layers of security. In this environment, files can be accessed by the UNC path (`\\servername\folder\`) instead of the traditional `C:\ftproot\folder` path. However, accessing folders stored across the network poses an additional challenge, because Windows services are run under the Local System account by default, which has no access to network resources.

To mitigate this problem for all of Serv-U, you can configure the Serv-U File Server service to run under a network account. The alternative, preferred when many servers exist, or if the Serv-U File Server service has to run under Local System for security reasons is to configure a directory access rule to use a specific Windows user for file access. By clicking the **Advanced** button, you can specify a specific Windows user for each individual directory access rule. As in Windows authentication, directory access is subject to NTFS permissions, and in this case also to the configured permissions in Serv-U.

**Note:** When you use Windows authentication, the NTFS permissions of the Windows user take priority over the directory access rules. This means that when

a Windows user tries to access a folder, the security permissions of the user are applied instead of the credentials specified in the directory access rule.

### Quota permissions

#### Maximum size of directory contents

Setting the maximum size actively restricts the size of the directory contents to the specified value. Any attempted file transfers that cause the directory contents to exceed this value are rejected. This feature serves as an alternative to the traditional quota feature that relies upon tracking all file transfers (uploads and deletions) to calculate directory sizes and is not able to consider changes made to the directory contents outside of a user's file server activity.

#### Mandatory access control

You can use mandatory access control (MAC) in cases where users need to be granted access to the same home directory but should not necessarily be able to access the subdirectories below it. To implement mandatory access control at a directory level, disable the **Inherit** permission as shown in the following screen capture. In the following example, the rule applies to `D:\ftp\root\`.

The screenshot shows the 'Directory Access Rule' dialog box. At the top, there is a title bar with a lock icon and the text 'Directory Access Rule', and a close button (X). Below the title bar, there is a 'Path:' label followed by a text input field and a folder icon button. To the right of the path field are three buttons: 'Save', 'Cancel', and 'Help'. Below the path field, there are two columns of permissions. The 'Files' column has checkboxes for 'Read' (checked), 'Write' (checked), 'Append' (checked), 'Rename' (checked), 'Delete' (checked), and 'Execute' (unchecked with a warning icon). The 'Directories' column has checkboxes for 'List' (checked), 'Create' (checked), 'Rename' (checked), and 'Remove' (checked). Below these columns is a 'Subdirectories' section with an 'Inherit' checkbox. To the right of the 'Subdirectories' section is a label 'Maximum size of directory contents:' followed by a text input field and the text 'MB (leave blank for no limit)'. At the bottom right, there is an 'Advanced >>' button. On the right side of the dialog, there are two buttons: 'Full Access' and 'Read Only'.

Now, the user has access to the `ftproot` folder but to no folders below it. Permissions must individually be granted to subfolders that the user needs access to, providing the security of mandatory access control in the Serv-U File Server.

### Restricting file types

If users are using storage space on the Serv-U File Server to store non-work-related files, such as MP3 files, you can prevent this by configuring a directory access rule placed *above* the main directory access rule to prevent MP3 files from being transferred as shown below. In the text entry for the rule, type `*.mp3`, and use the permissions shown in the following screen capture:

**Directory Access Rule** [X]

Path:  

**Files**

- ☐ Read
- ☐ Write
- ☐ Append
- ☐ Rename
- ☐ Delete
- ☒ Execute 

**Directories**

- ☐ List
- ☐ Create
- ☐ Rename
- ☐ Remove

**Subdirectories**

- ☒ Inherit

Maximum size of directory contents:  MB (leave blank for no limit)

**Buttons:** Save, Cancel, Help, Full Access, Read Only, Advanced >>

The rule denies permission to any transfer of files with the `.mp3` extension and can be modified to reflect any file extension. Similarly, if accounting employees only need to transfer files with the `.mdb` extension, configure a pair of rules that grants permissions for `.mdb` files but denies access to all other files, as shown in the following screen captures. In the first rule enter the path that should be the user's home directory or directory they need access to, and in the second rule enter the extension of the file that should be accessed (such as `*.mdb`).

## Chapter 3: Server

---

Directory Access Rule

Path:

Save


Cancel

Files

☐ Read

☐ Delete

☐ Write

☐ Execute 

☐ Append

☐ Rename

Directories

☒ List

☐ Create

☐ Rename

☐ Remove

Subdirectories

☒ Inherit

Maximum size of directory contents:  
 MB (leave blank for no limit)

Advanced >>

Help

Full Access

Read Only

Directory Access Rule

Path:

Save


Cancel

Files

☒ Read

☒ Delete

☒ Write

☐ Execute 

☒ Append

☒ Rename

Directories

☒ List

☐ Create

☐ Rename

☐ Remove

Subdirectories

☒ Inherit

Maximum size of directory contents:  
 MB (leave blank for no limit)

Advanced >>

Help

Full Access

Read Only

These rules only allow users to access `.mdb` files within the specified directories. You can adapt these rules to any file extension or set of file extensions.

## Virtual paths

If virtual paths are specified, users can gain access to files and folders outside of their own home directory. A virtual path only defines a method of mapping an existing directory to another location on the system to make it visible within a user's accessible directory structure. In order to actually have access to the mapped location, the user must still have a directory access rule specified for the physical path of a virtual path.

Like directory access rules, virtual paths can be configured at the server, domain, group, and user levels. Virtual paths created at the server level are available for all users of the file server. When virtual paths are created at the domain level, they are only accessible by users belonging to that domain. You can also create virtual paths specifically for individual users or groups.

### Physical path

The physical path is the actual location on the system, or network, that is to be placed in a virtual location accessible by a user. If the physical path is located on the same computer, use a full path, such as `D:\inetpub\ftp\public`. You can also use a UNC path, such as `\\Server\share\public`. To make a virtual path visible to users, users must have a directory access rule specified for the physical path.

### Virtual path

The virtual path is the location that the physical path should appear in for the user. The `%HOME%` macro is commonly used in the virtual path to place the specified physical path in the home directory of the user. When specifying the virtual path, the last specified directory is used as the name displayed in directory listings to the user. For example, a virtual path of `%HOME%/public` places the specified physical path in a folder named `public` within the user's home directory. You can also use a full path without any macros.

### Including virtual paths in "Maximum Directory Size" calculations

When this option is selected, the virtual path is included in Maximum Directory

Size calculations. The Maximum Directory Size limits the size of directories affecting how much data can be uploaded.

### Case File: Using virtual paths

A group of web developers have been granted access to the directory `D:\ftproot\example.com\` for web development purposes. The developers also need access to an image repository located at `D:\corpimages\`. To avoid granting the group access to the root D drive, a virtual path must be configured so that the image repository *appears* to be contained within their home directory. Within the group of web developers, add a virtual path to bring the directory to the users by specifying `D:\corpimages\` as the physical path and `D:\ftproot\example.com\corpimages` as the virtual path. Be sure to add a group level directory access rule for `D:\corpimages\` as well. The developers now have access to the image repository without compromising security or relocating shared resources.

### Case File: Creating relative virtual paths

Continuing with the previous example, if the home directory of the group of web developers is relocated to another drive, both the home directory and the virtual path need to be updated to reflect this change. You can avoid this by using the `%HOME%` macro to create a relative virtual path location that eliminates the need to update the path if the home directory changes. Instead of using `D:\ftproot\example.com\corpimages` as the virtual path, use `%HOME%\corpimages`. This way the `corpimages` virtual path is placed within the home directory of the group, regardless of what the home directory is. If the home directory changes at a later date, the virtual path still appears there.

## Automated file management

Using file management rules, you can automatically remove or archive files from the file server. You can configure automated file management rules at the server and domain level. If they are specified at the server level, the file management

rules are accessible to all users of the file server. If they are specified at the domain level, they are only accessible to users belonging to that domain.

Depending on the file system, Serv-U uses the creation or change date of files to determine the expiration date. On Windows, the creation date of the file is used to determine when a file expires. On Linux, the change date is used to determine the expiration date. The change date is updated whenever the metadata or index node (inode) of the file is modified. If the contents or attributes (such as the permissions) of the file are modified, the change date is also updated.

**Note:** The change date is not modified if the file is read from.

The file management rules apply recursively to all files within the folder for which they are configured, and not only to those that have been uploaded through Serv-U. This way you can manage files which are transferred by clients, or which are copied to the folder outside of Serv-U.

The folder structure is not affected by the file management rules. When expired files are deleted or moved, the folders themselves remain intact.

The file management rules run hourly in the background. For this reason, there can be an hour delay before Serv-U deletes or moves an expired file.

To monitor the status of the file management rules, you can configure a File Management Rule Success and a File Management Rule Error event under **Server/Domain Details > Events**. The file management rules continue to run even if deleting or moving a single file fails. For more information, see Serv-U events.

### To define a new file management rule:

1. Navigate to **Directories > File Management**, and then click **Add**.
2. Type the path to the file or folder in the **Directory Path** field, or click **Browse** to navigate to the file or folder.
3. Select the action you want to perform on the file:
  - a. If you want to delete the file after it expires, select **Delete file(s) after specified time**.



- b. If you want to move the file after it expires, select **Move file(s) after specified time**, and then in the **Destination Directory Path** field, specify the folder where you want to move the file.
4. Specify the number of days after the file creation date when the action should be executed.
5. Click **Save**.

**Note:** Serv-U regularly and individually checks all the files in the directory for their age, and performs the specified action on the files that meet the age criteria you specify.

## Server limits and settings

Serv-U contains options which you can use to customize how Serv-U can be used, and which also provide ways to apply limits and custom settings to users, groups, domains, and the server in its entirety. The limits stack intelligently, with user settings overriding group settings, group settings overriding domain settings, and domain settings overriding server settings. In addition, you can configure limits so that they are only applied during certain days of the week or times of the day. You can also grant exceptions to administrators and restrict specific users more than others, providing total control over the server. The limits and settings in Serv-U consist of the following categories:

- Connection
- Password
- Directory Listing
- Data Transfer
- HTTP
- Email

- File Sharing
- Advanced

To apply a limit, select the appropriate category, click **Add**, select the limit, and then select or enter the value. For example, to disable the **Lock users in home directory** option for a server, perform the following steps:

1. In the Serv-U Management Console, click **Limits & Settings**.
2. From the **Limit Type** list, select the **Directory Listing**.
3. Click **Add**.
4. From the **Limit** list, select **Lock users in home directory**.
5. Deselect the option.
6. Click **Save**.

The limits list displays the current limits applied to the domain. Limits with a light-blue background are default values. Limits with a white background are values that override the defaults. After completing the previous steps, a new "Lock users in home directory" limit appears in the list that displays "No" for the value.

Because of inheritance rules, this option applies to all users in the domain unless overridden at the group or user level. For more information about this method of inheritance, see "User interface conventions".

You can delete limits by selecting them and clicking **Delete**. To edit an overridden value, select the limit, and then click **Edit**. Default rules cannot be edited or deleted. Create a new limit to override a default limit.

To create a limit that is restricted to a specific time of day, or specific days of the week, click **Advanced** in the New Limit or Edit Limit window. Select **Apply limit only at this time of day** to specify a start and stop time for the new limit. To restrict the limit to certain days of the week, deselect the days for which you do not want the limit applied. When a limit is restricted in this way, default values (or the value of other limit overrides) are applied when the time of day or day of the week restrictions are not met for this limit.

The following section contains a reference of all available server limits, organized by category.

### **Connection**

#### **Maximum number of sessions on server**

Specifies the maximum number of concurrent sessions that may be allowed on the entire server.

#### **Maximum sessions per IP address on server**

Specifies the maximum number of concurrent sessions that may be opened to the entire server from a single IP address.

#### **Maximum number of sessions per user account**

Specifies the maximum number of concurrent sessions that may be opened from a single user account.

#### **Maximum sessions per IP address for user account**

Specifies the maximum number of concurrent sessions that a user may open from a single IP address.

#### **Require secure connection before login**

Requires that a connection must be secure (for example, FTPS, SFTP, or HTTPS) before it is accepted.

#### **Automatic idle connection timeout**

Specifies the number of minutes that must pass after the last client data transfer before a session is disconnected for being idle.

**Note:** Setting the Packet time-out is a requirement for this limit to work. The value of Packet time-out must be less than the value of the Automatic idle connection timeout for the Automatic idle connection timeout to work properly. For information about setting the packet time-out, see "Server settings".

#### **Automatic session timeout**

Specifies the number of minutes a session is allowed to last before it is

disconnected by the server.

**Block anti-timeout schemes**

Blocks the use of commands such as `noop`, which is commonly used to keep FTP Command Channel connections open during long file transfers or other periods of inactivity when no information is being transferred on the control channel. When these are blocked, Serv-U disconnects the client when the connection has been idle, that is, not transferring data for a specified period of time.

**Automatically create home directories**

Instructs Serv-U whether or not to automatically create the home directory specified when creating a new user account if the directory does not already exist.

**Block IP address of timed out session**

Specifies the number of minutes for which the IP address of a timed out session is blocked.

**Allow X-Forwarded-For to change HTTP connection IP addresses**

When enabled, the "X-Forwarded-For" HTTP header parameter changes the IP address of the client for Serv-U. This is useful when all HTTP connections are coming from a proxy server or a load balancer. Proxy servers and load balancers typically append this parameter to the HTTP header so that HTTP servers can identify the actual client IP address and apply security rules as necessary.

**Require reverse DNS name**

Requires that users connecting to the server must connect from an IP address that has a valid reverse DNS name, also known as a PTR record. This limit checks for the existence of a valid PTR record but does not check its contents.

**Maximum sessions per IP address on domain**

Specifies the maximum number of concurrent sessions that may be opened to the entire domain from the same IP address.

**Password**

**Check anonymous passwords**

Specifies whether or not Serv-U should validate email addresses supplied as the password to log in anonymously.

**Require complex passwords**

Specifies that all user account passwords must contain at least one uppercase and one non-alphabetic character to be considered valid.

**Minimum password length**

Specifies the minimum number of characters required in a user account's password. Specifying zero characters indicates that there is no minimum requirement.

**Automatically expire passwords**

Specifies the number of days a password is valid before it must be changed. Specifying zero days indicates that passwords never expire.

**Allow users to change password**

Specifies whether or not users are allowed to change their own passwords.

**Mask received passwords in logs**

Masks the passwords received from clients from being shown in log files. Disabling this allows passwords to be displayed in log files, which can be useful for debugging connection problems or auditing user account security.

**Password encryption mode**

Specifies the level of password encryption on user passwords. The following options are available:

- One-way encryption (more secure): This option fully encrypts passwords and cannot be reversed. This is the default setting.

- Simple two-way encryption (less secure): This option encrypts passwords in a reversible format for easy recovery. Use this option when users are expected to take advantage of the password recovery utility in the Web Client. In this case it may be desirable to use two-way encryption so that Serv-U does not need to reset their passwords when password recovery is requested.
- No encryption (not recommended): This option stores passwords in clear text. Using this option may be necessary for integration with legacy systems (especially when using database support).

**Note:** When you change this setting, all user passwords must be reset. Existing passwords are not updated automatically, and must be re-saved to be stored in the new format.

#### **Allow users to recover passwords**

If enabled, allows users to recover passwords using the Web Client password recovery utility at the login page.

#### **SSH authentication type**

Specifies how SSH authentication is to occur. The following options are available:

- Password and Public Key: Requires both a password and a public key (when specified) for login.
- Password or Public Key: Requires either a password or public key for login.
- Public Key Only: Requires that a public key is provided for successful login, a password is not allowed.
- Password Only: Requires that a password is provided for successful login, a public key is not allowed.

**Note:** The Public Key Only authentication type allows users to log in with a password if they have no SSH key configured in Serv-U. This way the administrator cannot deny access to a user account through misconfiguration.

### **FTP password type**

Specifies the type of password to be used for FTP connections. The following options are available: regular password, OTP S/Key MD4, and OTP S/Key MD5.

### **Days before considering password to be stale**

The number of days before expiration that a password is to be considered stale. A stale password is a password that is about to expire. An event can be configured to identify when a password is about to expire. This value is the lead-time, in days, before password expiration.

### **Disable password generators**

If enabled, this limit allows users to generate a random password.

### **Directory Listing**

#### **Hide files marked as hidden from listings**

Hides files and folders from directory listings that have the Windows "hidden" system attribute set on them.

#### **Use lowercase for file names and directories**

Forces Serv-U to display all file names and directories using lowercase characters, regardless of the actual letter case in use by the file or directory.

#### **Interpret Windows shortcuts as links**

Instructs Serv-U to treat all valid .lnk files as the actual destination object. In other words, if a .lnk file points to another file, the destination file is shown in the directory listing instead of the .lnk file itself.

#### **Treat Windows shortcuts as target in links**

Instructs Serv-U to treat all valid .lnk (shortcut) files as a UNIX symbolic link.

#### **Lock users in home directory**

Locks users into their home directory, and does not allow users to browse above their home directory. In addition, their home directory is displayed as "/", masking the actual physical location.

### **Allow root ("/") to list drives for unlocked users (Windows Only)**

Allows users to change directory to the root ("/") of the system and display all drives on the computer. This option only works when users are not locked in their home directory.

### **Hide the compressed state of files and directories**

Hides the compressed state of all compressed files and directories being viewed by the user.

### **Hide the encrypted state of files and directories**

Hides the encrypted state of all encrypted files and directories being viewed by the user.

### **Message file path**

Welcome messages are typically displayed once to a user during login to relay important information to users about the file server site. By using a secondary message file, welcome messages can be provided in specific folders to relay additional information. A non-relative path such as `MessageFile.message` can be used as the path. The welcome message will only be displayed when navigating into folders which contain a file matching the specified file name.

### **Directory listing mask (Windows Only)**

Specifies the text string sent to FTP clients for file permissions. Windows does not support traditional file permissions like Unix, which makes this option largely cosmetic, however some clients require a certain mask to operate correctly.

## **Data Transfer**

### **Maximum upload speed for server**

Limits the maximum bandwidth that can be used server-wide for all uploads. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum download speed for server**

Limits the maximum bandwidth that can be used server-wide for all



downloads. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum upload speed per session**

Limits the maximum upload bandwidth for each individual session. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum download speed per session**

Limits the maximum download bandwidth for each individual session. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum upload speed for user accounts**

Limits the maximum upload bandwidth shared between all sessions associated with an individual user account. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum Upload File Size**

Restricts the maximum single file size a user can upload to Serv-U. File size is measured in kilobytes.

### **Maximum download speed for user accounts**

Limits the maximum download bandwidth shared between all sessions associated with an individual user account. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Delete partially uploaded files**

Instructs Serv-U to delete incomplete file uploads. If this option is enabled, users are not able to restart interrupted uploads by using the `REST` (Restart) FTP command.

### **Interpret line feed byte as a new line when in ASCII mode (Windows Only)**

When uploading and downloading files using ASCII mode, Serv-U will assume `<LF>` characters are the same as `<CR><LF>` end-of-line markers. Most Windows applications expect `<CR><LF>` to represent a new line, as does the FTP protocol. However, because the definition of a new-line sequence is not fully defined in Windows, this option allows Serv-U to assume `<LF>` is the same as `<CR><LF>`. When uploading in ASCII mode

stand-alone <LF> characters are changed to <CR><LF> before writing to the file. When downloading in ASCII mode, standalone <LF> characters are changed to <CR><LF> prior to sending to the client.

### **Automatically check directory sizes during upload**

Instructs Serv-U to occasionally check the size of directories in which a maximum directory size has been specified. This attribute ensures that Serv-U always has updated directory sizes available instead of having to calculate them at transfer time, which can be a time consuming operation.

### **File upload access**

Specifies the method in which uploaded files are opened while they are being received from a client. The default **Allow read access** means that other clients can attempt to download the file even while it is still being received. **Allow full access** means other clients can read from and write to the file while it is being transferred. To prevent any other client from accessing a file while it is still being transferred, select **Allow no access**.

### **File download access**

Specifies the method in which downloaded files are opened while they are being sent to a client. The default **Allow read access** means that other clients can also attempt to concurrently download the same file. **Allow full access** means other clients can read from and write to the file while it is being sent to another client. To prevent any other client from accessing a file while it is still being sent, select **Allow no access**.

### **Maximum simultaneous thumbnails**

Specifies the maximum number of threads that are dedicated towards generating thumbnail images for HTTP clients and in response to the FTP **THUMB** command. Generating thumbnails is a CPU intensive operation. Increasing this value too high may cause thumbnails to take longer to generate, even while Serv-U is able to handle more client thumbnail requests concurrently.

## HTTP

### **Warn end users when using old web browsers**

When enabled (default) users are warned when they are using an outdated browser that they should upgrade the browser to take advantage of performance and feature enhancements to improve their experience.

### **Default language for Web Client**

When the end-user connects with an unsupported language, the HTTP login page is displayed in English. The default language can be set to any language you want. When connecting to Serv-U using a supported localization of Windows, the local language of Windows is used.

### **Allow HTTP media playback**

The Serv-U Web Client supports fully interactive media playback of audio and video files. This function can be disabled during specific business hours or altogether based on business needs.

### **Allow browsers to remember login information**

The HTTP login page supports a **Remember me** option (not enabled by default) that allows user names to be remembered by the login page. This feature can be disabled for security reasons.

### **Allow users to change languages**

The Serv-U Web Client is supported in many languages, but this option can be disabled if users should not be able to select their preferred language.

### **Allow users to use Web Client**

The Serv-U Web Client is enabled by default. Administrators can disallow the use of the Serv-U Web Client by disabling this limit.

### **Allow users to use Web Client Pro**

The Serv-U Web Client Pro is enabled by default. Administrators can disallow the use of the Serv-U Web Client Pro by disabling this limit.

### **Allow users to use FTP Voyager JV**

FTP Voyager JV is enabled by default. Administrators can disallow the use

of FTP Voyager JV by disabling this limit.

**Maintain file dates and times after uploading (FTP Voyager JV and Web Client Pro only)**

When enabled, Serv-U can maintain the last modification date and time of the file when end-users are using FTP Voyager JV or Web Client Pro.

When disabled, Serv-U will not set the last modification date and time of the file; it will remain the date and time the file was uploaded.

**Allow HTTP sessions to change IP address (disabling may cause mobile devices to fail)**

The Serv-U Web Client supports the transfer of HTTP sessions if the IP address changes. This option can be disabled but it may cause mobile devices to be disconnected due to frequent IP address changes by these devices.

**Hide Serv-U version information in HTTP response headers**

When enabled, the version information of Serv-U will be hidden in HTTP and HTTPs response headers. This way a potential security threat arising from the knowledge of the version information can be mitigated.

**Allow autocomplete for HTTP login fields**

With this limit you can configure whether or not password auto-completion is allowed on the Serv-U login screen. This option is enabled by default.

**Email**

**Allow end-user to set account email address**

Specifies whether users are allowed to modify their account email address using the Change Email Address option in the Web Client and File Sharing interfaces.

**Require end-user to set email address at next HTTP login**

Specifies whether users must set their email address when they log in to Serv-U.

### File Sharing

#### Require a password for guest access

Specifies whether it is possible to set up a file share where the guest is required to provide a password. When this limit is set to Always or Never, the creator of the file share will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share whether or not the guest must provide a password.

#### Insert passwords within invitation emails

Specifies whether it is possible to set up a file share where the password for the share is included in the invitation email. When this limit is set to Always or Never, the creator of the file share will not be able to specify this optional setting. When this limit is set to Optional, the **Include the password in the email** option can be selected individually in each file share.

#### Maximum file size guests can upload (per file)

Specifies the file size constraints imposed upon the guest user. If set to zero, there is no file size constraint. In this case, the creator of the file share request can specify the maximum file size in each file share request without an upper limit.

#### Allow user-defined guest link expiration

When enabled, users will be able to specify link expiration dates individually on the Request Files and Send Files wizards. When disabled, the file share links will expire after the number of days specified in the **Duration before guest link expires** limit.

#### Duration before guest link expires

Limits the number of days after which a file share link expires if the Allow user-defined guest link expiration limit is disabled.

#### Notify user after a file is downloaded

Specifies whether the **Notify me when the file(s) have been downloaded** option can be used in the Send Files wizard. When this limit is set to Always

or Never, the creator of the file share will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share whether to receive notification of the file download.

#### **Notify user after a file is uploaded**

Specifies whether the **Notify me when the file(s) have been uploaded** option can be used in the Request Files wizard. When this limit is set to Always or Never, the creator of the file share request will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share request whether to receive notification of the file upload.

#### **Send the guest access link to the recipients**

Specifies whether the **Automatically send the download/upload link to the guest user(s) in email** option can be used in the Send Files and Request Files wizards. When this limit is set to Always or Never, the user will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share or file share request whether to send the access link automatically.

#### **Send the guest access link to the sender**

Specifies whether the **Send me an email copy with the download/upload link** option can be used in the Send Files and Request Files wizards. When this limit is set to Always or Never, the user will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share or file share request whether to receive an email copy with the download or upload link.

#### **Allow user-defined contact information**

When enabled, users can edit their name and email address in the Request Files and Send Files wizards. When disabled, users are not allowed to edit their contact information in the Request Files and Send Files wizards.

### **Maximum number of files for "Sent" shares**

Specifies the maximum number of files users can include in a single file share. If set to zero, the default limit of 20 is used.

### **Maximum number of files for "Requested" shares**

Specifies the maximum number of files users can upload after receiving a file share request. If set to zero, the default limit of 20 is used.

### **Allowed "Sent" file share sources**

Specifies the valid file sharing sources that users can browse to when they create an outgoing file share. By default, users can browse to any file stored on their computer or on Serv-U.

## **Advanced**

### **Convert URL characters in commands to ASCII**

Instructs Serv-U to convert special characters contained in command parameters to plain ASCII text. Certain web browsers can encode special characters contained in file names and directories when using the FTP protocol. This attribute allows Serv-U to decode these special characters.

### **Inline out-of-band data**

Parse out-of-band socket data into the regular TCP data stream, treating it like normal data. This option is useful to counter denial-of-service attacks that send large amounts of out-of-band (OOB) data to socket stacks that cannot handle large amounts of OOB data.

### **Send keep alive packets to detect broken connections**

Periodically sends keepalive packets to determine if the socket is still connected.

### **Disable usage of Nagle algorithm**

Disables waiting for the ACK TCP handshake before sending the next packet. This option is typically only used for connections with very large latencies, such as satellite links.

**Use adaptive time-out on fast file uploads**

Slowly lower packet time-out for consistently fast transfers during file uploads. If the transfer does not complete successfully, adaptive time-outs make it easier to resume the upload since Serv-U recognizes more quickly that the transfer is dead and thus allows access to the file sooner.

**Maximum supported SFTP Version**

Specifies the maximum version of SFTP permitted for SFTP connections. Serv-U supports SFTP versions 3 - 6.

**Allow rename overwrite**

When enabled (default) Serv-U allows files to be renamed to files where the destination already exists. When disabled, users are not allowed to rename a file or directory to a path name that already exists.

**Apply server and domain directory access rules before user and group**

The order in which directory access rules are listed is important in determining the resources that are available to a user or group account. By default, directory access rules specified at the group or user level take precedence over ones specified at the domain and server level. However, there are certain instances where you may want the domain and server level rules to take precedence. Setting this value to "Yes" places the directory access rules of the group and user *below* the server and domain. For more information, see the "Apply group directory access rules first" setting in "Group information".

**Days before automatically disabling account to trigger the pre-disable event**

The number of days prior to automatically disabling the user account that the pre-disable event should be triggered.

**Days before automatically deleting account to trigger the pre-delete event**

The number of days prior to automatically deleting the user account that the pre-delete event should be triggered.

**Reset user stats after restart**

When this limit is enabled, the user statistics are reset after a server restart.



### **Reset group stats after restart**

When this limit is enabled, the group statistics are reset after a server restart.

### **Owner ID (user name) for created files and directories (Linux Only)**

The user name given to set as the owner of a created file or directory.

### **Group ID (group name) for created files and directories (Linux Only)**

The group name given to set as the owner of a created file or directory.

## **Server settings**

On the **Server Limits & Settings > Settings** pages, you can configure basic server settings that affect performance, security, and network connectivity. To configure a setting, type the value you want in the appropriate area, and then click **Save**. This topic contains detailed information about the settings that you can configure.

### **Connection Settings**

#### **Block users who connect more than 'x' times within 'y' seconds for 'z' minutes**

Also known as anti-hammering, enabling this option is a method of preventing brute force password guessing systems from using dictionary style attacks to locate a valid password for a user account. Using strong, complex passwords defeats most dictionary attacks. However, enabling this option ensures that Serv-U does not waste time processing connections from these illegitimate sources. When configuring this option, ensure that there is some room for legitimate users to correct an incorrect password before they are blocked.

When enabled, this option temporarily blocks IP addresses for the specified number of minutes that fail to successfully login after the specified number of attempts within the specified number of seconds. IP addresses blocked in this way can be viewed in the appropriate IP access rules tab. A successful login resets the counter that is tracking login attempts.

### **Hide server information from SSH identity**

After a successful SSH login, the server sends identification information to the client. Normally, this information includes the server name and version number. Enable this option to prevent the information from being given to the client.

### **Default Web Client**

Specifies whether the Web Client or FTP Voyager JV should be used by all HTTP clients by default. The third, default option is to prompt the users for the client they want to use instead. This option is also available at the group and user level.

## **Network Settings**

### **Auto-configure firewall through UPnP (Windows Only)**

When enabled, Serv-U automatically configures the necessary port forwards in your UPnP-enabled network device (usually a router) so that the file server is accessible from outside your network. This is particularly useful in enabling PASV mode FTP data transfers.

### **Packet time-out**

Specifies the timeout, in seconds, for a TCP packet transfer. Only very slow networks experiencing high levels of latency may need to change this value from the default 300 seconds.

### **PASV Port Range**

Specifies the inclusive range of ports that Serv-U should use for PASV mode data transfers. Serv-U normally allows the operating system to assign it a random port number when opening a socket for a PASV mode data transfer. This attribute accommodates routers or firewalls that need to know a specific range of ports in advance by restricting the PASV port range of Serv-U to a known range. A range of 10 ports is sufficient for the busiest of file servers.

**Note:** Some NAT routers work differently and may require a larger port range. If Serv-U and clients have troubles listing directories or transferring files, try increasing the port range here and on your router.

### Other Settings

#### Ratio Free Files

Files listed by opening the **Ratio Free Files** button are exempt from transfer ratio limitations on file transfers. Ratio free files specified at the server or domain level are inherited by all their users accounts. For more information, see "Transfer ratio and quota management".

#### Change Admin Password

The Serv-U Management Console can be password protected when it is launched by double-clicking on the Serv-U system tray icon. When the Management Console is running in this way, the option to change the password becomes available. By default, there is no admin password.

### FTP settings

In the Serv-U File Server, you can customize the FTP commands that Serv-U accepts, and you can also customize the responses of Serv-U to the FTP commands it receives. If you configure these options at the server level, all domains inherit the customizations. To customize the FTP behavior for a specific domain, select the appropriate domain, open the FTP Settings page for the domain, and then click **Use Custom Settings**. At any time, you can click **Use Default Settings** to have the domain revert back to the default settings of the server.

**Warning:** Customizing the FTP behavior in this way is not recommended except for those very familiar with the FTP protocol and its standard and extended command set.

#### Global Properties

When using custom settings, the **Global Properties** button becomes available.

## FTP Responses

Global FTP responses are responses shared amongst most FTP commands, such as the error message sent when a file is not found. Customizing a global FTP response ensures that the response is used by all other FTP commands rather than having to customize it for each individual FTP command. FTP command responses can contain special macros that allow real-time data to be inserted in to the response. For more information, see System variables.

## Message File

The server welcome message is sent in addition to the standard "220 Welcome Message" that identifies the server to clients when they first connect. If the **Include response code in text of message file** option is selected, the 220 response code begins each line of the specified welcome message. To customize the welcome message, enter the path to a text file in the **Message File Path** field. Click **Browse** to select a file on the computer. Serv-U opens this file and sends its contents to connecting clients.

## Advanced Options

- Block "FTP\_bounce" attacks and FXP (server-to-server transfers): Select this option to block all server-to-server file transfers involving this Serv-U File Server by only allowing file transfers to the IP address in use by the command channel. For more information about FTP\_bounce attacks, see [CERT advisory CA-97.27](#).
- Include response code on all lines of multi-line responses: The FTP protocol defines two ways in which a multi-line response can be issued by an FTP server. Some older FTP clients have trouble parsing multi-line responses that do not contain the three-digit response code on each line. Select this option if your clients are using an FTP client experiencing problems with multi-line responses from Serv-U.

- Use UTF-8 encoding for all sent and received paths and file names: By default, Serv-U treats all file names and paths as UTF-8 encoded strings. It also sends all file names and paths as UTF-8 encoded strings, such as when sending a directory listing. Deselecting this option prevents Serv-U from UTF-8 encoding these strings. When this option is deselected, UTF-8 is not included in the FEAT command response to indicate to clients that the server is not using UTF-8 encoding.

### Editing FTP Commands and Responses

To edit FTP Commands, select the FTP command you want to change, and then click **Edit**.

#### Information

On the Information page, basic information about the command is shown along with a link to more information on the Serv-U website. Each FTP command can also be disabled by selecting the **Disable command** option. Disabled commands are treated as unrecognized commands when they are received from a client.

### FTP Responses

On the FTP Responses page, all possible FTP responses to the command as issued by the server can be modified by clicking **Edit** for each response. FTP command responses can contain special macros that allow real-time data to be inserted in to the response. For more information, see System variables.

### Message Files

Certain FTP commands allow a message file to be associated with them. The contents of a message file are sent along with the standard FTP response. In addition, a secondary message file path is available as a default option. This allows for message files to be specified using a path relative to the home directory of the user for the Message File. If the first message file is not found, Serv-U attempts to use the Secondary Message File instead. By specifying an absolute file path in the secondary location,

you can ensure that each user receives a message file.

The following FTP commands can be used for specifying a message file:

- **CDUP**
- **CWD**
- **QUIT**

### Managing Recursive Listings

Serv-U supports recursive listings by default, allowing FTP clients to obtain large directory listings with a single command. In some cases, clients may request excessively large directory listings using the **-R** parameter to the **LIST** and **NLIST** commands. If performance in Serv-U is impacted by users requesting excessively large listings, recursive listings can be disabled by using the **Allow client to specify recursive directory listings with -R parameter** option.

### Advanced Options

Some FTP commands contain advanced configuration options that offer additional ways to configure the behavior of the command. Where available, the configuration option is described in detail in the Management Console.

The following FTP commands contain advanced configuration options:

- **LIST**
- **MDTM**
- **NLIST**

### Case File: Custom FTP command response

Users connecting to the server need to know how much quota space is available in a given folder when they have completed a transfer. To do this, edit the response to the **STOR** command to include a report about available space. By default, the 226 (command successful) response to the **STOR** command (which stores files on the server) is the following:

```
Transfer complete. $TransferBytes bytes transferred.  
$TransferKBPerSecond KB/sec.
```

Modify this to include an extra variable in the following way:

```
Transfer complete. $TransferBytes bytes transferred.  
$TransferKBPerSecond KB/sec. Remaining storage space is $QuotaLeft.
```

The last sentence shows the user how much storage space is left at the end of each file upload. The same can be done for the **DELE** command, so that every time a user deletes a file, their updated quota value, showing an increase in available space, is displayed. This can be done for any FTP command response.

### Encryption

Serv-U supports two methods of encrypted data transfer: Secure Socket Layer (SSL) and Secure Shell 2 (SSH2). SSL is used to secure the File Transfer Protocol (FTP) and Hypertext Transfer Protocol (HTTP). SSH2 is a method of securely interacting with a remote system that supports a method of file transfer commonly referred to as SFTP. Despite its name, SFTP does not have anything in common with the FTP protocol itself.

In order for each method of encryption to work, a certificate, a private key, or both must be supplied. SSL requires the presence of both, while SSH2 only requires a private key. If you do not have either of these required files, you can create them in Serv-U.

Encryption options specified at the server level are automatically inherited by all domains. Any encryption option specified at the domain level automatically overrides the corresponding server-level option. Certain configuration options are only available to the server.

When creating SSL/TLS, SSH, and HTTPS encrypted domains within Serv-U, it is important to know that encrypted domains cannot share listeners. Because SSL/TLS and SSH encryption is based on encrypting traffic sent between IP addresses, each domain must have unique listeners in order to operate properly. In the case that multiple encrypted domains are created that share listeners, the domain that is created first takes precedence, and causes other encrypted

domains to fail to function properly. To operate multiple encrypted domains, modify the listeners of each domain to ensure they listen on unique port numbers.

### Configuring SSL for FTPS and HTTPS

#### To use an existing certificate:

1. Obtain an SSL certificate and private key file from a certificate authority.
2. Place these files in a secured directory in the server.
3. Use the appropriate **Browse** button to select both the certificate and private key files.
4. If a CA (Certificate Authority) PEM file has been issued, enter or browse to the file.
5. Enter the password used to encrypt the private key file.
6. Click **Save**.

If the provided file paths and password are all correct, Serv-U starts to use the certificate immediately to secure FTPS and HTTPS connections using the provided certificate. If the password is incorrect or Serv-U cannot find either of the provided files, an error message is displayed that explains the encountered error.

#### To create a new certificate:

1. Click **Create Certificate**.
2. Specify the **Certificate Set Name** that is used to name each of the files Serv-U creates.
3. Specify the output path where the created files are to be placed. In most cases, the installation directory is a safe location (for example, `C:\ProgramData\RhinoSoft\Serv-U\`).
4. Specify the city or town in which the server or corporation is located.
5. Specify the state (if applicable) in which the server or corporation is located.



6. Specify the two-digit country code for the country in which the server or corporation is located.
7. Specify the password used to secure the private key.
8. Specify the full organization name.
9. Specify the common name of the certificate. The IP address or the Fully Qualified Domain Name (FQDN) that users use to connect must be listed here.

**Note:** If the Common Name is not the IP address or FQDN used by clients to connect, clients may be prompted that the certificate does not match the domain name they are connecting to.

10. Specify the business unit the server is located in.
11. Specify the key length in bits.
12. Click **Create** to complete the certificate creation.

Serv-U creates three files using the provided information: A self-signed certificate (.crt) that can be used immediately on the server but is not authenticated by any known certificate authority, a certificate request (.csr) that can be provided to a certificate authority for authentication, and a private key file (.key) that is used to secure both certificate files. It is extremely important that you keep the private key in a safe and secure location. If your private key is compromised, your certificate can be used by malicious individuals.

### Viewing the certificate

To view the SSL certificate when it is configured, click **View Certificate**. All identifying information about the certificate, including the dates during which the certificate is valid, are displayed in a new window.

### Advanced SSL Options

The advanced SSL options can only be configured at the server level. All domains inherit this behavior, which cannot be individually overridden.

- **Enable low-security SSL ciphers:** Select this option to enable low-security SSL ciphers to be used. Some older or international clients may not support today's best SSL ciphers. Because these ciphers are considered insecure by today's computing standards, Serv-U does not accept these ciphers by default.
- **Disable SSLv2 support:** Serv-U supports several different versions of SSL. An older version, SSLv2, has documented security weaknesses that make it less secure than SSLv3 and TLS. However, it may be necessary to support SSLv2 for compatibility with exported clients or old client software. Select this option to disable support for the older SSLv2 protocol.
- **SSL Ciphers:** By default, the low security SSL ciphers are disabled for use by the server. To enable these ciphers select **Enable low-security SSL ciphers**. These ciphers are listed in the third column under **SSL Ciphers**. All other SSL ciphers are enabled by default. If your specific security needs dictate that only certain ciphers can be used, you can individually disable unwanted ciphers by deselecting the corresponding options.

## FIPS Options

Enable FIPS 140-2 mode: FIPS 140-2 is a set of rigorously tested encryption specifications set by the National Institute of Standards and Technology (NIST). Enabling FIPS 140-2 mode limits Serv-U to encryption algorithms certified to be FIPS 140-2 compliant and ensures the highest level of security for encrypted connections.

## SFTP (Secure File Transfer over SSH2)

### To use an existing private key:

1. Obtain a private key file.
2. Place the private key file in a secured directory in the server. Use **Browse** in Serv-U to select the file.
3. Enter the password for the private key file.

4. Click **Save**. After clicking **Save**, Serv-U displays the SSH key fingerprint associated with the private key.

### To create a private key:

1. Click **Create Private Key**.
2. Enter the name of the private key (for example, `MyDomain Key`), which is also used to name the storage file.
3. Enter the output path of the certificate (for example, `C:\ProgramData\RhinoSoft\Serv-U\`).
4. Select the Key Type (default of DSA is preferred, but RSA is available).
5. Select the Key Length (default of 1024 bits provides best performance, 2048 bits is a good median, and 4096 bits provides best security).
6. Enter the password to use for securing the private key file.
7. After you create a new key, Serv-U displays the SSH key fingerprint associated with the new private key.

### SSH Ciphers and MACs

By default, all supported SSH ciphers and MACs (Message Authentication Codes) are enabled for use by the server. If your specific security needs dictate that only certain ciphers or MACs can be used, you can individually disable unwanted ciphers and MACs by deselecting the appropriate ciphers or MACs.


### Custom HTML

You can use custom HTML for the HTTP and HTTPS login pages of Serv-U. By using this feature, web developers can design their login experience to show off their exclusive brand and design the page to match existing business themes. Basic branding (custom logo and limited text changes) is also available. For more information, see Domain settings.

By using the custom HTML feature, you can provide a custom header and custom footer for the HTTP and HTTPS login page. The main login form is automatically inserted between the content defined in the header file and footer file. The custom HTML interface also uses a CSS file which defines the style used in the login form. This CSS file can also be used to define custom CSS styles, containers, and other CSS formatting as needed.

Several branding samples are automatically unpacked to your installation folder (for example, `C:\Program Files\RhinoSoft\Serv-U\Custom HTML Samples`) when Serv-U is installed. [Serv-U KB #2054](#) has step-by-step instructions to explore the current set of samples and build your own branding.

The following fields are used by the Custom HTML feature:



- Custom HTML Container Directory: This directory contains all of the files used by the custom HTML, including all images, the header file, the footer file, and the CSS file. Subdirectories in this folder are allowed.
- CSS File: This .CSS file contains all the styles, containers, and other formatting that is used throughout the header file and footer file, and also the styles that will be used by the login form.
- Header File: This .HTM file contains the content for the HTML header that is inserted before the login form.

- **Footer File:** This .HTM file contains the content for the HTML footer that is inserted after the login form.
- **Enable Custom HTML:** The custom HTML is not used by Serv-U until this option is enabled.

Most custom HTML interfaces include custom images. To use custom images, the storage location of the images must be specified. To universalize the storage location, use of the `%CUSTOM_HTML_DIR%` tag in paths that refer to images. This has the further benefit of avoiding changes to HTML when the container storing the HTML files and images is changed, because the path only has to be defined once in the **Custom HTML Container Directory** field. The tag is used in the following way:

```

```

### File sharing

By using the file sharing feature, domain users can send or receive files from guests.

**Note:** File sharing is disabled by default. You must select the relevant option to enable it.

To send file sharing invitation emails, you must configure your SMTP settings. This configuration only needs to be set once for the entire server or a domain.


For more information about file sharing, see the [Serv-U Web Client and File Sharing User Guide](#).

#### To enable file sharing:

1. Navigate to **Server Limits and Settings > File Sharing**.
2. Type the address for the domain URL.
3. Type the location of the file sharing repository.
4. Select the number of days until the shares expire.


5. Select whether you want to use the inherited default email invitation subject, or customize your own. If the option is deselected, you can type in a custom email invitation subject.
6. Select whether you want to use the inherited default email notification message, or customize your own. If the option is deselected, you can type in a custom message.
7. Select **Enable File Sharing**.
8. If it is not configured yet, configure your SMTP to be able to send and receive notification emails. For more information about configuring an SMTP server, see "Serv-U SMTP configuration".
9. Click **Save**.


LimitsSettingsFTP SettingsEncryptionCustom HTMLFile Sharing

 The File Sharing feature allows your domain users to send or receive files from guests. Use the options below to configure this feature.

File Sharing Settings

Domain URL (ex. "www.mysite.com" or "127.0.0.1"):

File Sharing Repository:  
 

Remove expired shares after  days 


Invitation Subject Template:

☒ Use inherited default subject

Invitation Email Template:  

You have received access to a Serv-U File Share from \$FullName. The link to transfer your file(s) will expire on \$FileShareExpires.  
  
\$FileShareTokenURL  
  
\$FileShareComments  
  
Need help? See some troubleshooting tips at <http://www.Serv-U.com/sharefiles>.

☒ Use inherited default message  
☐ Use Secure URL (HTTPS)  
☒ Enable File Sharing

 Additional file sharing settings are available under the "Limits" tab.

Save

## Server activity

The **Server Activity > Sessions** and **Domain Activity > Sessions** pages display the current file server session activity. When you view the Sessions page from the server, all connected sessions from all domains are displayed. When you view the Sessions page while you are administering a domain, only the current sessions of the particular domain are displayed. From this page, you can see an overall picture of the current activity on the file server. In addition, you can view individual sessions, including their current status, connection state, and transfer information.

To view detailed information about a specific session, select the session. The **Active Session Information** group is populated with the details of the currently highlighted session. This information is frequently updated to provide an accurate and up-to-date snapshot of the activities of the session.

Depending on the type of connection made by that session (for example, FTP, HTTP, or SFTP), certain additional functions are available.

### Disconnecting sessions

You can disconnect any type of session at any time by clicking **Disconnect**. Click this button to bring up another window with additional options for how the disconnect should be performed. The following disconnect options are available:

- **Disconnect:** Immediately disconnects the session. Another session can be immediately established by the disconnected client. This is also known as "kicking" the user.
- **Disconnect and ban IP for x:** Immediately disconnects the session and bans its IP address for the specified number of minutes, preventing the client from immediately reconnecting.
- **Disconnect and block IP permanently:** Immediately disconnects the session and adds a deny IP access rule for the IP address, preventing the client from ever reconnecting from the same IP address.

When disconnecting a session from the Server Session view, you can also use the **Apply IP rule to** option. By using this option, you can select where you want the temporary or permanent IP ban to be applied: for the entire server, or only the domain the session is connected to.

In addition to disconnecting the session, you can also disable the user account in use by the session by selecting **Disable user account**.

If the current session is using the FTP protocol, you can send a message to the user before disconnecting them by typing it in the **Message to user** field. This option is not available for HTTP or SFTP sessions because neither protocol defines a method for chatting with users.



### Using the spy & chat function

You can spy on any type of session by clicking **Spy & Chat** or by double-clicking a session in the list. Spying on a user displays all the detailed information normally visible by highlighting the session, and also includes a complete copy of the session log since it first connected to the file server. This way you can browse the log and view all actions taken by the user of the session.

If the current session is using the FTP protocol, additional options are available for chatting with the user. The **Chat** group shows all messages sent to and received from the session since beginning to spy on the session. To send a message to the session, type the message text in the **Message Content** field, and then click **Send**. When a message is received from the session, it is automatically displayed here.

**Note:** Not all FTP clients support chatting with system administrators. The command used to send a message to the server is `SITE MSG`. In order for a client to receive messages, the client application must be capable of receiving unsolicited responses from the server instead of discarding them.

### Broadcasting messages

You can send a message to all currently connected FTP sessions by clicking **Broadcast**. Sending a message through broadcast is equivalent to opening the **Spy & Chat** window to each individual FTP session and sending it a chat message.

### Canceling sessions

If a session is performing a file transfer, you can cancel the file transfer without disconnecting the session by clicking **Abort**. After confirming the command, the current file transfer for that session is terminated by the server. Some clients, especially FTP and SFTP clients, may automatically restart the canceled transfer, making it appear that the cancellation failed. If this is the case, try disconnecting the session instead.

## Server and domain statistics

The **Server Activity > Statistics** and **Domain Activity > Statistics** pages show detailed statistics about the use of the server for use in benchmarking and records keeping. Statistics viewed at the server level are an aggregate of those accumulated by all domains on the server. Statistics viewed for an individual domain are for that domain only. The displayed information includes the following details:

### Session statistics

#### Current Sessions

The number of sessions currently connected.

#### Total Sessions

The total number of sessions that have connected since being placed online.

#### 24 Hrs Sessions

The number of sessions that have connected in the past 24 hours.

#### Highest Num Sessions

The highest number of concurrent sessions that has been recorded since being placed online.

#### Average Session Length

The average length of time a session has remained connected.

#### Longest Session

The longest recorded time for a session.

### Login statistics

These statistics can apply to either a domain or the entire server depending on the statistics currently being viewed. Login statistics differ from session statistics because they apply to a login (providing a login ID and password) as opposed to connecting and disconnecting.

### **Logins**

The total number of successful logins.

### **Average Duration Logged In**

The average login time for all sessions.

### **Last Login Time**

The last recorded valid login time. This is not the last time a connection was made.

### **Last Logout Time**

The last recorded valid logout time.

### **Most Logged In**

The highest number of users logged in concurrently.

### **Currently Logged In**

The number of sessions currently logged in.

### **Transfer statistics**

#### **Download Speed**

The cumulative download bandwidth currently being used.

#### **Upload Speed**

The cumulative upload bandwidth currently being used.

#### **Downloaded**

The total amount of data, and number of files, downloaded since being placed online.

#### **Uploaded**

The total amount of data, and number of files, uploaded since being placed online.

#### **Average Download Speed**

The average download bandwidth used since being placed online.

#### **Average Upload Speed**

The average upload bandwidth used since being placed online.

## User and group statistics

The User & Group Statistics pages show detailed statistics based on individual user or group activity. Statistics viewed for a user or group are for that user or group only. The displayed information includes the following details:

### Session statistics

#### Current Sessions

The number of sessions currently connected.

#### 24 Hrs Sessions

The number of sessions that have connected in the past 24 hours.

#### Total Sessions

The total number of sessions that have connected since being placed online.

#### Highest Num Sessions

The highest number of concurrent sessions that has been recorded since being placed online.

#### Avg. Session Length

The average length of time a session has remained connected.

#### Longest Session

The longest recorded time for a session.

### Login statistics

These statistics can apply to either a user or a group of users, depending on the statistics currently being viewed. Login statistics differ from session statistics because they apply to a login (providing a login ID and password) as opposed to connecting and disconnecting.

#### Logins

The total number of successful logins.

**Last Login Time**

The last recorded valid login time (not the last time a connection was made).

**Last Logout Time**

The last recorded valid logout time.

**Logouts**

The total number of logouts.

**Most Logged In**

The highest number of simultaneously logged in sessions.

**Longest Duration Logged In**

The longest amount of time a session was logged in.

**Currently Logged In**

The number of sessions currently logged in.

**Average Duration Logged In**

The average login time for all sessions.

**Shortest Login Duration Seconds**

The shortest amount of time a session was logged in.

**Transfer statistics**

**Download Speed**

The cumulative download bandwidth currently being used.

**Upload Speed**

The cumulative upload bandwidth currently being used.

**Average Download Speed**

The average download bandwidth used since being placed online.

**Average Upload Speed**

The average upload bandwidth used since being placed online.

**Downloaded**

The total amount of data, and number of files, downloaded since being

placed online.

### Uploaded

The total amount of data, and number of files, uploaded since being placed online.

### Save Statistics

User and group statistics can be saved directly to a CSV file for programmatic analysis and review. To save statistics to a file, first select the user or group you want to generate a statistics file for, and then click **Save Statistics** at the bottom of the page.

## Server and domain log

The **Server Activity > Log** and **Domain Activity > Log** pages show logged activity for the server or domain.

The server log shows file server startup, configuration, and shutdown information. It does not show domain activity information. For activity logs, view the log of the appropriate domain instead. In addition to status information about libraries, licensing, and the current build that is logged when the file server first starts, the server log also contains information about all domain listener status, Universal Plug-and-Play (UPnP) status information, and PASV port range status. The information contained in the server log is also saved to a text file located in the installation directory that is named `Serv-U-StartupLog.txt`. This file is replaced each time the Serv-U File Server is started.

The domain log contains information about and activity pertaining to the currently administered domain only. This includes the status of the listeners of the domain, and any configured activity log information. For more information about the types of activity information that can be placed in the domain log, see [Configuring domain logs](#).

You can highlight information contained in the log by clicking and dragging the mouse cursor over the appropriate portion of the log. When it is highlighted, you can copy the selected portion to the clipboard.

### Freeze Log

Select this option to temporarily pause the refreshing of the log. This is useful on busy systems so you can highlight and copy a particular section of the log before it scrolls out of view. When you have finished, deselect the option to resume the automatic updating of the log.

### Select All

Click this button to automatically freeze the log and highlight all currently displayed log information so you can copy it to the clipboard.

### Clear Log

When the log has become too large for you to view at once, click this button to erase the currently displayed log information. Only log information received after clicking the button is displayed.

### Legend

To make viewing the different components of the log easier, each different type of logged message is color-coded for quick identification. Clicking this shows the legend in a draggable dialog. Drag the legend dialog to a convenient location so you can use it for reference while you browse the log.

### Filter Log

To quickly find and read through specific sections of the log, you can filter it based on a search string. Click this button to bring up the Filter Log window. Provide a search string, and then click **Filter** to refresh the log to only display log entries containing the search string. To view the entire contents of the log again, open the Filter Log window, and then click **Reset**.

### Download Log

To download the full log file from Serv-U, click **Download Log**. If you have permission to download the file, your web browser prompts you to choose a location to save the file, or it begins to download the file automatically.

# Chapter 4: Domain

## Domain overview

At the core of the Serv-U File Server is the Serv-U domain. At the most basic level, a Serv-U domain is a set of user accounts and listeners that allow users to connect to the server to access files and folders. Serv-U domains can also be configured further to restrict access based on IP address, limit bandwidth usage, enforce transfer quotas, and more. Virtually every setting available at the server level can be overridden for each individual domain. With careful advanced planning, you can specify an acceptable level of default options at the server level to minimize the amount of configuration required for a domain.

Serv-U supports any number of domains on the file server. Domains can share listeners, or they can each be hosted on a unique IP address if the system has multiple IP addresses. However, the maximum number of domains that can be created on an installation is dictated by the license. For more information about the different editions of Serv-U, see Serv-U editions.

When you run a new installation of the Serv-U File Server for the first time, you are prompted to create your first domain using the New Domain Wizard. Follow the instructions on each page of the wizard to create your first domain. For more information about creating domains, see the Quick start guide.

### Managing Domains

The domain that you currently manage is always displayed in the header of each page next to the **+ (New Domain)** button. To change the active domain, click the domain name in the accordion menu on the left, and then select one of the available options.

If it is supported by your license, you can create new domains at any time by clicking **+ (New Domain)** in the Management Console. After you change the



active domain, the current page is automatically reloaded to reflect the settings of the new active domain.

To delete a domain and all of its users and groups, navigate to **Domain > Domain Details**, and then click **Delete Domain**.

**Warning:** This action cannot be undone.

## Domain details

### Domain name and description

Each domain must be uniquely identified with a domain name. If you provide a name that is not unique, an error message is displayed, indicating that a unique name is required for each domain. The domain name is used purely for administrative purposes and is not visible or accessible to users.

In addition, you can associate additional descriptive information to each domain through the description. Like the domain name, the description text is also only available to users with administrative access. This field is useful for describing the purpose of the domain or summarizing the resources made available by the existence of the domain on the file server.

You can temporarily disable a domain by clearing the **Enable domain** option. While disabled, the domain is inaccessible to all users. The domain still exists on the file server, all settings are preserved, and you can still administer it while it is disabled. To make the domain accessible to users again, select **Enable domain**.

After making changes to any of the previous domain settings, click **Save** to apply the changes.

### Domain home directory

You can limit the disk space available to a domain by configuring a home directory for the domain and specifying a maximum size. The home directory of the domain does not affect user directory access rules, and it does not restrict the paths that are available to a user in any way. However, in order to calculate the amount of disk space in use by a domain, you must specify the root directory

under which Serv-U expects all domain files to be stored.

To specify the domain home directory, enter a path in the **Domain Home Directory** field, or click **Browse** to select a path. When you create a domain administrator account for this domain, it is suggested that their home directory be the same, which ensures that all users of the domain are placed in a subdirectory of the home directory of the domain. Enter the amount of disk space, in megabytes (MB), available to the domain in the **Maximum Size** field. Leaving this field blank or entering "0" does not impose a maximum size on the domain. When a limit is imposed, any upload that would cause this maximum size to be exceeded is rejected by the server.

Click **Save** to apply the changes.

**Note:** Calculating the amount of disk space in use by a domain can be a time consuming operation depending on the directory structure.

## Domain listeners

The Serv-U File Server offers a highly configurable interface for enabling the different file sharing protocols on a domain. You can add, edit, and delete listeners. Each domain can listen on multiple ports and IP addresses by adding a listener bound to the IP address and port you want. In addition to selecting these connection attributes for a listener, you must also select a file sharing protocol. Serv-U supports IPv4 and IPv6 simultaneously; to offer services to both IPv4 and IPv6 users, create a listener both for an IPv4 address and an IPv6 address.

The following section contains the list and short description of the file sharing protocols supported by the Serv-U File Server.

### FTP - File Transfer Protocol

FTP is the traditional protocol for transferring files over the Internet. It normally operates on the default port 21. Traditionally, FTP is handled in plain-text, however, SSL connections are explicitly supported through the use of the **AUTH** command.

### **FTPS - File Transfer Protocol using SSL**

FTPS is identical to FTP, however, connecting to a listener configured for FTPS means that an SSL connection is required before any protocol communication is performed. This is commonly referred to as Implicit FTPS, which normally takes place on the default port 990.

### **SFTP - Secure File Transfer Using SSH2**

SFTP is a secure method of transferring files through a secure shell session. It performs all protocol communications and data transfers over the same port eliminating the need to open multiple ports in firewalls as is commonly required when using FTP. SFTP sessions are always encrypted. SFTP operates on the default port 22.

### **HTTP - Hypertext Transfer Protocol**

HTTP is the protocol used to browse websites. It is also a simple method for downloading and transferring files. One benefit to adding an HTTP listener to a domain is the availability of the Web Client, which allows users to transfer files to and from your file server without the need for a standalone client. HTTP traditionally operates on port 80.

### **HTTPS - Hypertext Transfer Protocol using SSL**

HTTPS is identical to HTTP except all communications are secured using SSL. Like FTPS, a secure connection is implied when connecting to a listener running the HTTPS protocol. The default port for HTTPS is 443.

### **Adding a listener**

After clicking **Add**, the listener configuration window is displayed. After configuring each of the listener options, click **Save** to add the listener to the domain.

The following section contains the list and short description of the options you can configure for a listener.

#### **Type**

Select the file sharing protocol that is to be supported by this listener. Each

listener can only support a single protocol. To add more file sharing protocols to the domain, create new listeners for each protocol. A brief description of the supported file sharing protocols is found in the previous section.

### **IP Address**

You can bound a listener to a single IP address by entering the IP address here. Serv-U supports both IPv4 and IPv6 addresses. If the file server does not have an external IP address (for example, it is behind a router), you can leave this field blank. If you do not specify an IP address, you must select the option to either listen on all available IPv4 addresses or all IPv6 addresses. Unless you are running a purely IPv6 network, it is recommended to use IPv4 addresses and add IPv6 listeners as needed.

### **PASV IP Address or Domain Name (FTP ONLY)**

If the listener supports the FTP protocol, this additional field is available where you can specify a separate IP address to use for PASV mode data transfers. Entering an IP address here ensures that PASV mode works properly on both unsecured and secured connections. If the file server does not have an external IP address, try using a dynamic DNS service and entering your DNS domain name in this field. Serv-U resolves the DNS domain name to ensure it always has the proper external IP address for PASV command responses.

### **Use only with SSL connections**

This option allows the PASV IP address or domain name to only be used for SSL connections where it is always necessary to provide the PASV IP address to connecting clients. When this option is enabled, the IP address specified for PASV mode will not be provided to clients connecting through non-SSL FTP.

### **Use with LAN connections**

Normally, Serv-U does not use the PASV IP address for connections coming from the local area network (computers on the same network as

Serv-U). When this option is enabled, the PASV IP Address is also used for LAN connections.

### **Port**

The default port for the selected protocol is automatically provided. However, you can use any port between 1 and 65535. When using a non-standard port, clients must know the proper port in advance when they attempt to connect to the domain. If you use a non-standard port, it is recommended that you use a value above 1024 to prevent potential conflicts.

### **Enable listener**

You can temporarily disable a listener by deselecting this option. When they are disabled, listeners are displayed with a different icon in the list.

### **Pure Virtual Domains**

Serv-U supports the ability for multiple domains to "share" the same listeners. In other words, one domain can possess the necessary listener configurations while the other domain "piggybacks" on the first one. In this way, the second domain exists in a virtual way. To have a domain "piggyback" on the listener configurations of existing domains, leave the listener list blank for the domain. The "piggybacking" domain needs to have at least one virtual host defined for it. For more information, see Virtual hosts.

This method of "piggybacking" only works with the FTP and HTTP protocols because they are the only two file sharing protocols that specify a method for identifying the specific host after a connection is established. For FTP connections, the client must issue a `HOST` command to identify the specific domain. For HTTP connections, the browser automatically handles providing the necessary host header to Serv-U based on the domain name that is used to establish the HTTP connection.

### **Virtual hosts**

Virtual hosts provide a way for multiple domains to share the same IP and listener

port numbers. Normally, each domain listener must use a unique IP address and port number combination. By using virtual hosts, you can host multiple domains on a system that only has one unique IP address without having to use non-standard port numbers. The domains can share the same listeners by proper implementation of virtual hosts. This feature is only available when the current license supports hosting multiple domains.

To configure virtual hosts for a domain, click **Add** under **Domain Details > Virtual Hosts**, and then type the virtual host name for the domain. The virtual host name is usually the fully qualified domain name used to connect to the domain, such as `ftp.Serv-U.com`.

The method used by a client to connect to a specific virtual host depends on the protocol that is used to connect to Serv-U.

### FTP

FTP users can use one of two methods to connect to a specific virtual host. If it is supported by the FTP client, the `HOST` command can be issued to Serv-U before login to identify the virtual host. Otherwise, the virtual host can be provided with the login ID in the following format: `virtual_host_name|login ID`. The virtual host name is entered first, followed by the vertical bar character ('|'), then the login ID.

### SFTP

SFTP users who want to connect to a specific virtual host must use the specially crafted login ID format as described in the FTP section.

### HTTP

For HTTP users, the browser automatically provides Serv-U with the host name that is used to reach the site, allowing Serv-U to identify the virtual host from the fully qualified domain name entered into the navigation bar of the browser.

### Case File: Using virtual hosts

Multiple domains are being configured on the same server, which has one IP address and two Fully Qualified Domain Names (FQDN) pointing to it. Because users connecting to both domains must use port 21 for connections, configure virtual hosts on each domain so that Serv-U can distinguish between requests for

the two domains. After setting up the same listener properties on each domain, open the Virtual Hosts page, click **Add**, and then type the FQDN that clients should use to connect to the domain (such as `ftp.Serv-U.com`).

After connecting to the server with FTP, users can send a `HOST ftp.Serv-U.com` command to connect to the appropriate domain on the File Server. FTP and SFTP users can also identify the virtual host through their login ID of `ftp.Serv-U.com|login ID`. If connecting through HTTP, users can connect to this domain by visiting `http://ftp.Serv-U.com`.

## Server details

### IP access rules

IP access rules restrict login access to specific IP addresses, ranges of IP addresses, or a domain name. IP access rules can be configured at the server, domain, group, and user levels.

IP access rules are applied in the order they are displayed. In this way, specific rules can be placed at the top to allow or deny access before a more general rule is applied later on in the list. The arrows on the right side of the list can be used to change the position of an individual rule in the list.

### Specifying IP access masks

IP access rules use masks to authorize IP addresses and domain names. The masks can contain specific values, ranges, and wildcards made up of the following elements:

#### **xxx**

Stands for an exact match, such as `192.0.2.0` (IPv4),  
`fe80:0:0:0:a450:9a2e:ff9d:a915` (IPv6, long form) or  
`fe80::a450:9a2e:ff9d:a915` (IPv6, shorthand).

#### **xxx-xxx**

Stands for a range of IP addresses, such as `192.0.2.0-19` (IPv4),  
`fe80:0:0:0:a450:9a2e:ff9d:a915-a9aa` (IPv6, long form), or

`fe80::a450:9a2e:ff9d:a915-a9aa` (IPv6, shorthand).

**\***

Stands for any valid IP address value, such as `192.0.2.*`, which is analogous to `192.0.2.0-255`, or `fe80::a450:9a2e:ff9d:*`, which is analogous to `fe80::a450:9a2e:ff9d:0-ffff`.

**?**

Stands for any valid character when specifying a reverse DNS name, such as `server?.example.com`.

**/**

Specifies the use of CIDR notation to specify which IP addresses should be allowed or blocked. Common CIDR blocks are `/8` (for `1.*.*.*`), `/16` (for `1.2.*.*`) and `/24` (for `1.2.3.*`). CIDR notation also works with IPv6 addresses, such as `2001:db8::/32`.

## Caveats

Specific IP addresses listed in Allow rules will not be blocked by anti-hammering. These IP addresses are whitelisted. However, addresses matched by a wildcard or a range will be subject to anti-hammering prevention.

### Implicit deny all

Until you add the first IP access rule, connections from any IP address are accepted. After you add the first IP access rule, all connections that are not explicitly allowed will be denied. This is also known as an implicit 'Deny All' rule. With this in mind, make sure you add a 'wildcard allow' rule (such as `Allow *.*.*.*)` at the end of your IP access rule list.

### Matching all addresses

Use the `*.*.*.*` mask to match any IPv4 address. Use the `::*` mask to match any IPv6 address. If you use both IPv4 and IPv6 listeners, add Allow ranges for both IPv4 and IPv6 addresses.

### DNS lookup

If you use a dynamic DNS service, you can specify a domain name instead



of an IP address to allow access to users who do not have a static IP address. You can also specify reverse DNS names. If you create a rule based on a domain name or reverse DNS, Serv-U performs either a reverse DNS lookup or DNS resolution to apply these rules. This can cause a slight delay during login, depending on the speed of the DNS server of the system.

### Rule use during connection


The level at which you specify an IP access rule also defines how far a connection is allowed before it is rejected. Server and domain level IP access rules are applied before the welcome message is sent. Domain level IP access rules are also applied when responding to the `HOST` command to connect to a virtual domain. Group and user level IP access rules are applied in response to a `USER` command when the client identifies itself to the server.

### Anti-hammering

You can set up an anti-hammering policy that blocks clients who connect and fail to authenticate more than a specified number of times within a specified period of time. You can configure an anti-hammering policy server-wide in **Server Limits and Settings > Settings** and domain-wide in **Domain Limits and Settings > Settings**.

IP addresses blocked by anti-hammering rules appear in the domain IP access rules with a value in the **Expires in** column. If you have multiple domains with different listeners, blocked IP addresses appear in the domain that contains the listener. Blocked IP addresses do not appear in the server IP access list, even if anti-hammering is configured at the server level.

The **Expires in** value of the blocked IP counts down second by second until the entry disappears. You can unblock any blocked IP early by deleting its entry from the list.



### IP access list controls

The following section contains a description of the options that are available on the IP Access page.

#### Using the sort mode

By using the sort mode, you can sort the IP access list numerically rather than in the processing order. Displaying the IP access list in sort mode does not change the order in which rules are processed. To view rule precedence, disable this option. Viewing the IP access list in numerical order can be a valuable tool when you review long lists of access rules to determine if an entry already exists.

#### Importing and exporting IP access rules

You can export and import Serv-U IP access rules from users, groups, domains, and the server by using a text-based CSV file. To export IP access rules, view the list of rules to export, click **Export**, and then specify the path

and the file name you want to save the list to. To import IP access rules, click **Import** and select the file that contains the rules you want to import. The CSV file must contain the following fields, including the headers:

**IP**

The IP address, IP range, CIDR block, or domain name for which the rule applies.

**Allow**

Set this value to 0 for Deny, or to 1 for Allow.

**Description**

A text description of the rule for reference purposes.

### Examples

#### Case File: Office-only access

A contractor has been hired to work in the office, and only in the office. Office workstations have IP addresses in the range of 192.0.2.0 - 192.0.2.24. The related Serv-U access rule should be `Allow 192.0.2.0-24`, and it should be added to either the contractor's user account or a Contractors group that contains multiple contractors. No deny rule is required here because Serv-U provides an implicit deny all rule at the end of the list.

#### Case File: Prohibited computers

Users should normally be able to access Serv-U from anywhere, except from a bank of special internal computers in the IP address range of 192.0.2.0 - 192.0.2.24. The related Serv-U access rules should therefore be `Deny 192.0.2.0-24`, followed by `Allow *.*.*.*`, and these should both be added to either the domain or the server IP access rules.

#### Case File: DNS-based access control

The only users allowed to access a Serv-U domain will be connecting from `*.example.com` or `*.example1.com`. The related Serv-U access rules should therefore be `Allow *.example.com` and `Allow *.example1.com` in any order, and

these should both be added to the domain IP access rules. No deny rule is required here because Serv-U provides an implicit deny all rule at the end of the list.

## Database access

Serv-U enables the use of an ODBC database to store and maintain group and user accounts at both the domain and server levels. You can configure the ODBC connections in two locations: **Domain > Domain Details > Database** and **Server > Server Details > Database**. Serv-U can automatically create all of the tables and columns that are necessary to begin storing users and groups in the database. Because Serv-U uses one set of table names to store its information, individual ODBC connections must be configured for each item which stores details in the database. In other words, the server as well as each domain must have a unique ODBC connection to ensure they are stored separately.

**To configure a database, perform the following steps:**

1. Create an ODBC connection for Serv-U to use. SolarWinds recommends MySQL, but you can use any database that has an ODBC driver available. Use a System DSN if Serv-U is operating as a system service, or a User DSN if Serv-U is operating as a regular application.
2. Open the Serv-U Management Console and browse to the appropriate domain or server database settings. Enter the Data Source Name (DSN), the login ID, and the password, and then click **Save**.

If you configure the database connection for the first time, leave the **Automatically create** options selected. With these options selected, the Serv-U File Server builds the database tables and columns automatically.

## Using SQL templates

Serv-U uses multiple queries to maintain the databases that contain user and group information. These queries conform to the SQL language standards. However, if your database have problems working with Serv-U, you may need to

alter these queries. In the SQL Templates window, you can modify each query used by Serv-U to conform to the standards supported by your database.

**Warning:** Incorrectly editing these SQL queries could cause ODBC support to stop working in Serv-U. Do not edit these queries unless you are comfortable constructing SQL statements and are positive that it is necessary to enable ODBC support with your database software.

### Using user and group table mappings

By default, Serv-U automatically creates and maintains the tables and columns that are necessary to store user and group information in a database. However, if you want to connect Serv-U to an existing database which contains this information, you must customize the table and column names to conform to the existing database structure. Click **User Table Mappings** or **Group Table Mappings** to get started.

Serv-U stores information for a user or group in 10 separate tables. Only the User/Group Info Table and User/Group Dir Access Table are required. You can change the current table in the **Object Table** list. The **Attribute** column lists the attributes that are stored in the current table. The **Mapped Database Value** displays the name of the column that attribute is mapped to in the database. The first row displays the "TableName" and can be used to change the name of the table.

Certain tables where the order of the entries is important have a **SortColumn** attribute listed. This column is used to store the order in which rules are applied.

Click **Edit** or double-click the column name to edit a value.

When enabled, the table is accessed as needed. In special situations a table that is not being used can be disabled to reduce the number of ODBC (database) calls. For example, if you do not use ratios and quotas, you can disable the User Ratio-Free Files, Per User Files Ratio, Per User Bytes Ratio, Per Session Files Ratio, and Per Session Bytes Ratio tables to prevent unnecessary ODBC calls.

Use caution when you disable tables, because the fields will appear in dialogs, but they will not be saved or loaded.

The User Info and Group Info tables cannot be disabled.

### **Case file: ODBC authentication**

Authentication in the Serv-U File Server can be handled through an ODBC database, allowing for scripted account management and maintenance. To use ODBC functionality, migrate to ODBC authentication through a database. By storing credentials in settings in a database, accounts can be managed from outside the Serv-U Management Console through scripted database operations which can be built into many existing account provisioning systems. A DSN must first be created in **Control Panel > Administrative Tools > ODBC Data**

**Sources.** Use a System DSN if Serv-U is running as a service or a User DSN if Serv-U is running as an application. After you created the appropriate DSN, specify the data source name, login ID and password, and then click **Save**. Serv-U creates the tables and columns transparently. You can manage database users and groups in the Database Users and Database Groups pages of Serv-U, located near the normal Users and Groups pages.

### **Creating data source names in Linux**

Database access in Serv-U on Linux follows the same method as Serv-U on Windows, with the one change in how data source names are created. On Linux, you can create a DSN after installing the following packages:

- mysql-connector-odbc
- postgresql-odbc
- unixodbc

Only the ODBC driver corresponding to the database needs to be installed. If Serv-U is running as a service, the next step is to edit the `/etc/odbc.ini` file, which contains all system-level DSNs. If Serv-U is running as an application, edit the `~/odbc.ini` file instead, and then enter the parameters as follows:

```
[MySQL-test]
Description = MySQL test database
```

## Chapter 4: Domain

---

```
Trace = Off
TraceFile = stderr
Driver = MySQL
SERVER = YOURIPADDRESS
USER = USERNAME
PASSWORD = PASSWORD
PORT = 3306
DATABASE = YOURDATABASE

[PostgreSQL-test]
Description = Test to Postgres
Driver = PostgreSQL
Trace = Yes
TraceFile = sql.log
Database = YOURDATABASE
Servername = YOURIPADDRESS
UserName = USERNAME
Password = PASSWORD
Port = 5432
Protocol = 6.4
ReadOnly = No
RowVersioning = No
ShowSystemTables = No
ShowOidColumn = No
FakeOidIndex = No
ConnSettings =
```

Adjust the names in brackets to the DSN name string you want. Finally, test the DSN by using the `isql %DSN% -c -v` command.

For further customization options, see the [Serv-U Database Integration Guide](#).

## Serv-U events

**Events**

Events Event Filters

**Event Information**

Event Type:  
File Uploaded

Event Name:  
Event 01

☒ Enable event

Description:  
Show balloon tip when users upload a file.

**Event Actions**

Action:  
Show Balloon Tip

Balloon Title:  
"\$name" Has Uploaded A File.

Balloon Information:  
\$LocalPathName  
Size: \$FileSizeFmt bytes (\$FileSize KB KB)  
\$TransferBytes bytes transferred.  
\$TransferKBPerSecond KB/sec.  
Protocol: \$Protocol

Save Cancel Help

In Serv-U, you can use event handling which can perform various actions triggered by a list of selected events. The following list contains the available actions:



### Server events

#### Server Start

Triggered by Serv-U starting up, whether by starting the Serv-U service or starting Serv-U as an application.

#### Server Stop

Triggered by Serv-U shutting down, whether from service or application-level status. This event only triggers for graceful stops.

### Server and domain events

#### Domain Start

Triggered by a Serv-U domain starting, through the **Enable Domain** setting in the **Domain Details > Settings** menu, or as part of normal server startup.

#### Domain Stop

Triggered by a Serv-U domain stopping, through the **Enable Domain** setting in the **Domain Details > Settings** menu, or as part of normal server startup.

#### Session Connection

Triggered by a new TCP session connection.

#### Session Disconnect

Triggered by a TCP session disconnection.

#### Session Connection Failure

Triggered by a failed session connection attempt.

#### Log File Deleted

Triggered by the automatic deletion of a log file, according to logging settings.

#### Log File Rotated

Triggered by the automatic rotation of a log file, according to logging settings.

**Listener Success**

Triggered by a successful listener connection.

**Listener Stop**

Triggered by a stopped listener connection.

**Listener Failure**

Triggered by a failed listener connection.

**Gateway Listener Success**

Triggered by a successful gateway listener connection.

**Gateway Listener Stop**

Triggered by a stopped gateway listener connection.

**Gateway Listener Failure**

Triggered by a failed gateway listener connection.

**Permanent Listener Success**

Triggered by a successful permanent listener connection.

**Permanent Listener Failure**

Triggered by a failed permanent listener connection.

**Permanent Listener Stop**

Triggered by a stopped permanent listener connection.

**Permanent Gateway Listener Success**

Triggered by a successful permanent gateway listener connection.

**Permanent Gateway Listener Stop**

Triggered by a stopped permanent gateway listener connection.

**Permanent Gateway Listener Failure**

Triggered by a failed permanent gateway listener connection.

**File Management Rule Success**

Triggered when a file management rule is applied, and no errors are encountered.

### **File Management Rule Failure**

Triggered when a file management rule is applied, and at least one error is encountered.

### **Server, domain, user and group events**

#### **User Login**

Triggered by the login of a user account.

#### **User Logout**

Triggered by the logout of a user account.

#### **User Login Failure**

Triggered by a failed login. A failed login is any connection attempt to Serv-U that fails, whether due to invalid credentials, or a session disconnect before authentication, either due to an incorrect user name, incorrect password, incorrect SSH key pair (for SFTP public key authentication), or any or all of the above.

#### **User Password Change**

Triggered by the change of a password for a user account by the user (if permitted).

#### **User Password Change Failure**

Triggered by a failed password change attempt.

#### **User Enabled**

Triggered by the enabling of a user account that was previously disabled.

#### **User Disabled**

Triggered by the disabling of a user account that was previously enabled.

#### **User Deleted**

Triggered by the deletion of a user account by a remote administrator, in an ODBC database, or in the local Management Console.

### **User Added**

Triggered by the creation of a user account by a remote administrator, in an ODBC database, or in the local Management Console.

### **Password Recovery Sent**

Triggered by a successful password recovery by an end user.

### **Password Recovery Failed**

Triggered by a failed password recovery attempt, either due to lack of email address in the user account or lack of permissions.

### **Password Stale**

Triggered by a stale password, as configured in **Limits & Settings**, that is going to expire.

### **User Auto Disable**

Triggered by the automatic disabling of a user account, as configured by a user's **Automatically Disable** date.

### **User Auto Deleted**

Triggered by the automatic deletion of a user account, as configured by a user's **Automatically Delete** date.

### **User Pre-disable**

Triggered by the upcoming disabling of a user account, as configured in the user's **Automatically Disable** date and the "Days before automatically disabling account to trigger the pre-disable event" limit.

### **User Pre-delete**

Triggered by the upcoming deletion of a user account, as configured in the user's **Automatically Delete** date and the **Days before automatically deleting account to trigger the pre-delete** event limit.

### **User Email Set**

Triggered by a user setting the email address for a user account.

### **User Email Set Failure**

Triggered by a failed attempt by a user to set the email address for a user account.

### **IP Blocked**

Triggered by a failed login attempt due to an IP access rule.

### **IP Blocked Time**

Triggered by a failed login attempt due to an IP access rule that was automatically added by brute force settings, configured in **Domain Limits & Settings** or **Server Limits & Settings**.

### **Too Many Sessions**

Triggered by more sessions logging on to the server than are permitted, per the **Limits & Settings** for the user account, group, domain, or server.

### **Too Many Session On IP**

Triggered by more sessions logging on to the server from a specific IP address than are permitted, according to the **Limits & Settings** for the user account, group, domain, or server.

### **IP Auto Added To Access Rules**

Triggered by the automatic addition of an IP access rule due to a user triggering the "brute force" settings.

### **Session Idle Timeout**

Triggered by an idle session timeout.

### **Session Timeout**

Triggered by a session timeout.

### **File Uploaded**

Triggered by a file uploaded to Serv-U. This event triggers for partial uploads if the upload session terminated with a successful message and no data corruption.

### **File Upload Failed**

Triggered by a failed file upload to Serv-U.

### **File Download**

Triggered by a file downloaded from Serv-U.

### **File Download Failed**

Triggered by a failed file download from Serv-U.

### **File Deleted**

Triggered by the deletion of a file on the Serv-U server by a user.

### **File Moved**

Triggered by the moving of a file on the Serv-U server by a user.

### **Directory Created**

Triggered by the creation of a directory.

### **Directory Deleted**

Triggered by the deletion of a directory.

### **Directory Changed**

Triggered by changing the current working directory.

### **Directory Moved**

Triggered by moving a directory to a new location.

### **Over Quota**

Triggered by going over disk quota space. The current quota space is shown in the user account, in the **Limits & Settings** menu.

### **Over Disk Space**

Triggered by exceeding the Max Dir Size configured for a directory access rule. The current disk space is shown with the **AVBL FTP** command, or by using the **Directory Properties** option in the HTTP or HTTPS Web Client and FTP Voyager JV.

### **Creating common events**

You can automatically create a list of the most common events. You can choose to create these common events using email or balloon tip actions. Click **Create Common Event** in the Events page. Select either the **Send Email** or **Show**

**balloon tip** option for the action you want to perform on the common events. If you choose to send email, also enter an email address where the events are to be sent.

**Note:** The **Write to Windows Event Log** and **Write to Microsoft Message Queue (MSMQ)** options are available for Windows only.

### Using event actions

You can select from the following actions that will be executed when an event is triggered:

- Send Email
- Show Balloon Tip\*
- Execute Command\*
- Write to Windows Event Log (Windows only)\*
- Write to Microsoft Message Queue (MSMQ) (Windows only)\*

\* Events involving anything other than email can only be configured by Serv-U server administrators.

### Using email actions

You can configure email actions to send emails to multiple recipients and to Serv-U groups when an event is triggered. To add an email address, enter it in the **To** or **Bcc** fields. To send emails to a Serv-U group, use the **Group** icon to add or remove Serv-U groups from the distribution list. Separate email addresses by commas or semicolons. Email actions contain a **To**, **Subject** and **Message** parameter. You can use special variables to send specific data pertaining to the event. For more information about the variables, see "System variables".

To use email actions, you must first configure SMTP in Serv-U. For information about SMTP configuration, see "Serv-U SMTP configuration".

### Using balloon tip actions

You can configure balloon tip actions to show a balloon tip in the system tray when an event is triggered. Balloon tip actions contain a **Balloon Title** and a

**Balloon Message** parameter. You can use special variables to send specific data pertaining to the event. For more information about the variables, see "System variables".

### Using execute command actions

You can configure execute command actions to execute a command on a file when an event is triggered. Execute command actions contain an **Executable Path**, **Command Line Parameters**, and a **Completion Wait Time** parameter. For the **Completion Wait Time** parameter, you can enter the number of seconds to wait after starting the executable path. Enter zero for no waiting.

**Note:** Any amount of time Serv-U spends waiting delays any processing that Serv-U can perform.

A wait value should only be used to give an external program enough time to perform some operation, such as move a log file before it is deleted (for example, `$LogFilePath` for the Log File Deleted event). You can use special variables to send specific data pertaining to the event. For more information about the variables, see "System variables".

### Writing to the Windows Event Log

By writing event messages to a local Windows Event Log, you can monitor and record Serv-U activity by using third-party network management software. All messages appear in the Windows Application Log from a source of "Serv-U".

This event has only one field:

- **Log Information:** The contents of the message to be written into the event log. This is normally either a human-readable message (for example, `filename uploaded by person`) or a machine-readable string (for example, `filename|uploaded|person`), depending on who or what is expected to read these messages. Serv-U system variables are supported in this field. This field can be left blank, but usually is not.

### Writing to Microsoft Queue (MSMQ)

Microsoft Message Queuing (MSMQ) is an enterprise technology that provides a



method for independent applications to communicate quickly and reliably. Serv-U can send messages to new or existing MSMQ queues whenever a Serv-U event is triggered. Corporations can use this feature to tell enterprise applications that files have arrived, files have been picked up, partners have signed on, or many other activities have occurred.

These events have the following two fields:

- **Message Queue Path:** The MSMQ path that addresses the queue. Remote queues can be addressed when a full path (for example, `MessageServer\Serv-U Message Queue`) is specified. Local, public queues on the local machine can be addressed when a full path is not specified (for example, `.\Serv-U Message Queue` or `Serv-U Message Queue`). If the specified queue does not exist, Serv-U attempts to create it. This normally only works on public queues on the local machine. You can also use Serv-U system variables in this field.
- **Message Body:** The contents of the message to be sent into the queue. This is normally a text string with a specific format specified by an enterprise application owner or enterprise architect. Serv-U system variables can also be used in this field. This field may be left blank, but usually is not.

**Note:** Microsoft message queues created in Windows do not grant access to SYSTEM by default, preventing Serv-U from writing events to the queue. To correct this, after creating the queue in MSMQ, right-click it, select **Properties**, and then set the permissions so that SYSTEM (or the network account under which Serv-U runs) has permission to the queue.

### Using event filters

By using Serv-U event filters, you can control to a greater degree when a Serv-U event is triggered. By default, Serv-U events trigger each time the event occurs. The event filter allows events to be triggered only if certain conditions are met. For example, a standard Serv-U event might trigger an email each time a file is uploaded to the server. However, by using an event filter, events can be triggered

on a more targeted basis. For example, you can configure a File Uploaded event to only send an email when the file name contains the string `important`, so an email would be sent when the file `Important Tax Forms.pdf` is uploaded but not when other files are uploaded to the server. Additionally, you can configure a File Upload Failed event to run only when the FTP protocol is used, not triggering for failed HTTP or SFTP uploads. You can do this by controlling the various variables and values related to the event and by evaluating their results when the event is triggered.

### Event filter fields

Each event filter has the following critical values that must be set:

- **Name:** This is the name of the filter, used to identify the filter for the event.
- **Description (Optional):** This is the description of the event, which may be included for reference.
- **Logic:** This determines how the filter interacts with other filters for an event. In most cases, AND is used, and all filters must be satisfied for the event to trigger. The function of AND is to require that all conditions be met. However, the OR operator can be used if there are multiple possible satisfactory responses (for example, abnormal bandwidth usage of less than 20 KB/s OR greater than 2000 KB/s).
- **Filter Comparison:** This is the most critical portion of the filter. The Filter Comparison contains the evaluation that must occur for the event to trigger. For example, a filter can be configured so that only the user "admin" triggers the event. In this case, the comparison will be `If $Name = (is equal to) admin`, and the data type will be `string`. For bandwidth, either an "unsigned integer" or "double precision floating point" value would be used.

Event filters also support wildcards when evaluating text strings. The supported wildcards are the following:

- **\*** - The asterisk wildcard matches any text string of any length. For example:
  - An event filter that compares the `$FileName` variable to the string `data*` matches files named `data`, `data7`, `data77`, `data.txt`, `data7.txt`, and

`data77.txt.`

- **?** - The question mark wildcard matches any one character, but only one character. For example:
  - An event filter that compares the `$FileName` variable to the string `data?` matches a file named `data7` but not `data`, `data77`, `data.txt`, `data7.txt`, or `data77.txt`.
  - An event filter that compares the `$FileName` variable to the string `data?.*` matches files named `data7` and `data7.txt` but not `data`, `data77`, `data.txt`, or `data77.txt`.
  - An event filter that compares the `$Name` variable to the string `A????` matches any five-character user name that starts with `A`.
- **[]** - The bracket wildcard matches a character against the set of characters inside the brackets. For example:
  - An event filter that compares the `$FileName` variable to the string `data[687].txt` matches files named `data6.txt`, `data7.txt` and `data8.txt` but not `data5.txt`.
  - An event filter that compares the `$LocalPathName` variable to the string `[CD]:\*` matches any file or folder on the `C:` or `D:` drives.


You can use multiple wildcards in each filter. For example:

- An event filter that compares the `$FileName` variable to the string `[cC]:\*.???` matches any file on the `C:` drive that ends in a three letter file extension.
- An event filter that compares the `$FileName` variable to the string `?:\*Red[678]\?????.*` matches a file on any Windows drive, contained in any folder whose name contains `Red6`, `Red7` or `Red8`, and that also has a five character file name followed by a file extension of any length.

### Using event filters


Event filters are used by comparing fields to expected values in the Event Filter

menu. The best example is raising an event only when a certain user triggers the action, or when a certain file is uploaded. For example, an administrator may want to raise an email event when the file `HourlyUpdate.csv` is uploaded to the server, but not when other files are uploaded. To do this, create a new event in the **Domain Details > Events** menu. The **Event Type** is File Uploaded, and on the Event Filter tab a new filter must be added. The `$FileName` variable is used and the value is `HourlyUpdate.csv` as shown in the following screen capture:



The screenshot shows a 'Filter Comparison' dialog box. At the top, there is a title bar with a funnel icon and the text 'Filter Comparison', and a close button (X). Below the title bar, there is a message: 'Comparisons must be added to the event filter to define the scenario that will allow or disallow the event.' To the right of this message are three buttons: 'Save', 'Cancel', and 'Help'. The main area of the dialog contains a form with the following fields: 'If' (a dropdown menu), '\$FileName' (a text input field), '= (is equal to)' (a dropdown menu), and 'HourlyUpdate.csv' (a text input field). Below these fields is a 'Data Type:' label and a dropdown menu showing '(abcd) string'.


As another example, it might be necessary to know when a file transfer fails for a specific user account. To perform this task, create a new File Upload Failed event, and then add a new filter. The filter comparison is the `$Name` variable, and the value to compare is the user name, such as `ProductionLineFTP`:



The screenshot shows a 'Filter Comparison' dialog box. At the top, there is a title bar with a funnel icon and the text 'Filter Comparison', and a close button (X). Below the title bar, there is a message: 'Comparisons must be added to the event filter to define the scenario that will allow or disallow the event.' To the right of this message are three buttons: 'Save', 'Cancel', and 'Help'. The main area of the dialog contains a form with the following fields: 'If' (a dropdown menu), '\$Name' (a text input field), '= (is equal to)' (a dropdown menu), and 'ProductionLineFTP' (a text input field). Below these fields is a 'Data Type:' label and a dropdown menu showing '(abcd) string'.

You can also filter for events based on specific folders, using wildcards. In some cases it may be necessary to trigger events for files uploaded only to a specific folder, such as when an accounting department uploads time-sensitive tax files. To filter based on a folder name, create a new File Uploaded event in the **Domain Details > Events** menu, and set it to **Send Email**. After specifying the

email recipients, subject line, and message content, open the Event Filters page. Create a new event filter, and add the filter comparison `If $LocalPathName = (is equal to) C:\ftproot\accounting\*` with the type of `(abcd) string`. This will cause the event to trigger only for files that are located within `C:\ftproot\accounting\.`



**Filter Comparison**

Comparisons must be added to the event filter to define the scenario that will allow or disallow the event.

If `$LocalPathName` = (is equal to) `C:\ftproot\accounting\*`

Data Type:  
(abcd) string

Save Cancel Help

### Serv-U SMTP configuration

In Serv-U, you can configure an SMTP connection to send email for events which are configured to use email actions. You can configure SMTP on the server or domain level, or both. SMTP configuration at the domain level can be inherited from the server level. The SMTP configuration dialog is located in the Events tab in the **Domain Details** and **Server Details** pages. Click **Configure SMTP** to launch the dialog, and then specify the following details:


- **SMTP Server:** The name or IP address of the SMTP server.
- **SMTP Server Port:** The port the SMTP server is using.
- **From Email Address:** The email address to use for the outgoing email.
- **From Name (optional):** The name to use for the outgoing email.
- **This server requires a secure connection (SSL):** On some SMTP servers all incoming connections must be encrypted to protect against possible attacks. If your server requires that all incoming connections must be encrypted, enable this option. The default port for encrypted SMTP connections is 465. Serv-U supports Implicit SSL only, and does not support Explicit SSL (port 587).

- **My server requires authentication:** To enable authentication, select this option.

If your SMTP server requires authentication, enter the following information:

- **Account Name:** The account name associated with authentication for the SMTP server.
- **Password:** The password for the account.

SMTP Configuration



Configure Serv-U to use a SMTP server to send email for email notifications and events that use email actions. This configuration only needs to be set once for an entire domain.

Server Information

SMTP Server:  
mail.emailserver.com

SMTP Server Port:  
465

☐ This server requires a secure connection (SSL)

From Email Address:  
smtp@emailserver.com

From Name (optional):  
SMTP Server

☒ My server requires authentication

Authentication Information

Account Name:  
smtp@emailserver.com

Password:  
••••••••

OK

Cancel

Help

## Directory access rules

### Directory access rules

Directory access rules define the areas of the system which are accessible to

user accounts. While traditionally restricted to the user and group levels, in Serv-U, the usage of directory access rules is extended to both the domain and the server levels through the creation of global directory access rules. Directory access rules specified at the server level are inherited by all users of the file server. If they are specified at the domain level, they are only inherited by users who belong to the particular domain. The traditional rules of inheritance apply where rules specified at a lower level (for example, the user level) override conflicting or duplicate rules specified at a higher level (for example, the server level).

When you set the directory access path, you can use the `%USER%`, `%HOME%`, `%USER_FULL_NAME%`, and `%DOMAIN_HOME%` variables to simplify the process. For example, use `%HOME%/ftproot/` to create a directory access rule that specifies the `ftproot` folder in the home directory of the user. Directory access rules specified in this manner are portable if the actual home directory changes while maintaining the same subdirectory structure. This leads to less maintenance for the file server administrator. If you specify the `%USER%` variable in the path, it is replaced with the user's login ID. This variable is useful in specifying a group's home directory to ensure that users inherit a logical and unique home directory. You can use the `%USER_FULL_NAME%` variable to insert the Full Name value into the path (the user must have a Full Name specified for this to function). For example, the user "Tom Smith" could use `D:\ftproot\%USER_FULL_NAME%` for `D:\ftproot\Tom Smith`. You can also use the `%DOMAIN_HOME%` macro to identify the user's home directory. For example, to place a user and their home directory into a common directory, use `%DOMAIN_HOME%\%USER%`.

Directory access rules are applied in the order they are listed. The first rule in the list that matches the path of a client's request is the one that is applied for that rule. In other words, if a rule exists that denies access to a particular subdirectory but is listed *below* the rule that grants access to the parent directory, then a user still has access to the particular subdirectory. Use the arrows on the right of the directory access list to rearrange the order in which the rules are applied.

The following section contains the list and description of the directory access permissions.

### File permissions

#### Read

Allows users to read (that is, download) files. This permission does not allow users to list the contents of a directory, which is granted by the **List** permission.

#### Write

Allows users to write (that is, upload) files. This permission does not allow users to modify existing files, which is granted by the **Append** permission.

#### Append

Allows users to append data to existing files. This permission is typically used to grant users the ability to resume transferring partially uploaded files.

#### Rename

Allows users to rename existing files.

#### Delete

Allows users to delete files.

#### Execute

Allows users to remotely execute files. The execute access is meant for remotely starting programs and usually applies to specific files. This is a very powerful permission and great care should be used in granting it to users. Users with **Write** and **Execute** permissions can install any program they want on the system.

### Directory permissions

#### List

Allows users to list the files and subdirectories contained in the directory. Also allows users to list this folder when listing the contents of a parent directory.



### Create

Allows users to create new directories within the directory.

### Rename

Allows users to rename existing directories within the directory.

### Remove

Allows users to delete existing directories within the directory.

**Note:** If the directory contains files, the user also needs to have the **Delete** files permission in order to remove the directory.

### Subdirectory permissions

#### Inherit

Allows all subdirectories to inherit the same permissions as the parent directory. The **Inherit** permission is appropriate for most circumstances, but if access must be restricted to subfolders (as is the case when implementing mandatory access control), clear the **Inherit** check box and grant permissions specifically by folder.

### Advanced: Access as Windows User (Windows Only)

For a variety of reasons, files and folders may be kept on external servers in order to centralize file storage or provide additional layers of security. In this environment, files can be accessed by the UNC path (`\\servername\folder\`) instead of the traditional `C:\ftproot\folder` path. However, accessing folders stored across the network poses an additional challenge, because Windows services are run under the Local System account by default, which has no access to network resources.

To mitigate this problem for all of Serv-U, you can configure the Serv-U File Server service to run under a network account. The alternative, preferred when many servers exist, or if the Serv-U File Server service has to run under Local System for security reasons is to configure a directory access rule to use a specific Windows user for file access. By clicking the **Advanced** button, you can specify a specific Windows user for each individual directory access rule. As in

Windows authentication, directory access is subject to NTFS permissions, and in this case also to the configured permissions in Serv-U.

**Note:** When you use Windows authentication, the NTFS permissions of the Windows user take priority over the directory access rules. This means that when a Windows user tries to access a folder, the security permissions of the user are applied instead of the credentials specified in the directory access rule.

### Quota permissions

#### Maximum size of directory contents

Setting the maximum size actively restricts the size of the directory contents to the specified value. Any attempted file transfers that cause the directory contents to exceed this value are rejected. This feature serves as an alternative to the traditional quota feature that relies upon tracking all file transfers (uploads and deletions) to calculate directory sizes and is not able to consider changes made to the directory contents outside of a user's file server activity.

#### Mandatory access control

You can use mandatory access control (MAC) in cases where users need to be granted access to the same home directory but should not necessarily be able to access the subdirectories below it. To implement mandatory access control at a directory level, disable the **Inherit** permission as shown in the following screen capture. In the following example, the rule applies to `D:\ftproot\`.

The screenshot shows the 'Directory Access Rule' dialog box. At the top, there is a title bar with a lock icon and the text 'Directory Access Rule', and a close button (X). Below the title bar, there is a 'Path:' label followed by a text input field and a folder icon button. To the right of the path field are three buttons: 'Save', 'Cancel', and 'Help'. Below the path field, there are two columns of permissions. The 'Files' column has checkboxes for 'Read' (checked), 'Write' (checked), 'Append' (checked), 'Rename' (checked), 'Delete' (checked), and 'Execute' (unchecked with a warning icon). The 'Directories' column has checkboxes for 'List' (checked), 'Create' (checked), 'Rename' (checked), and 'Remove' (checked). Below these columns is a 'Subdirectories' section with an 'Inherit' checkbox. To the right of the 'Subdirectories' section is a label 'Maximum size of directory contents:' followed by a text input field and the text 'MB (leave blank for no limit)'. At the bottom right, there is an 'Advanced >>' button. On the right side of the dialog, there are two buttons: 'Full Access' and 'Read Only'.

Now, the user has access to the `ftproot` folder but to no folders below it. Permissions must individually be granted to subfolders that the user needs access to, providing the security of mandatory access control in the Serv-U File Server.

### Restricting file types

If users are using storage space on the Serv-U File Server to store non-work-related files, such as MP3 files, you can prevent this by configuring a directory access rule placed *above* the main directory access rule to prevent MP3 files from being transferred as shown below. In the text entry for the rule, type `*.mp3`, and use the permissions shown in the following screen capture:

The screenshot shows the 'Directory Access Rule' dialog box. At the top is a title bar with a blue icon and the text 'Directory Access Rule', and a close button (X) on the right. Below the title bar is a 'Path:' label followed by a text input field and a folder icon button. To the right of the path field are three buttons: 'Save', 'Cancel', and 'Help'. Below the path field are two columns of checkboxes. The 'Files' column contains: Read, Write, Append, Rename, Delete, and Execute (with a yellow warning triangle icon). The 'Directories' column contains: List, Create, Rename, and Remove. To the right of these columns are two buttons: 'Full Access' and 'Read Only'. Below the 'Files' and 'Directories' columns is a 'Subdirectories' section with a checked 'Inherit' checkbox. To the right of this is a 'Maximum size of directory contents:' label, a text input field, and the text 'MB (leave blank for no limit)'. At the bottom right is an 'Advanced >>' button.

Path:  

**Files**

- ☐ Read
- ☐ Write
- ☐ Append
- ☐ Rename
- ☐ Delete
- ☐ Execute 

**Directories**

- ☐ List
- ☐ Create
- ☐ Rename
- ☐ Remove

**Subdirectories**

☒ Inherit

Maximum size of directory contents:  MB (leave blank for no limit)

The rule denies permission to any transfer of files with the `.mp3` extension and can be modified to reflect any file extension. Similarly, if accounting employees only need to transfer files with the `.mdb` extension, configure a pair of rules that grants permissions for `.mdb` files but denies access to all other files, as shown in the following screen captures. In the first rule enter the path that should be the user's home directory or directory they need access to, and in the second rule enter the extension of the file that should be accessed (such as `*.mdb`).

## Chapter 4: Domain

---

Directory Access Rule

X

Path:

Save

Cancel

Files

Directories


☐ Read

☐ Write

☐ Append

☐ Rename

☐ Delete

☐ Execute 

☒ List

☐ Create

☐ Rename

☐ Remove

☒ Inherit

Maximum size of directory contents:  
 MB (leave blank for no limit)

Help

Full Access

Read Only

Advanced >>

Directory Access Rule

X

Path:

Save

Cancel

Files

Directories


☒ Read

☒ Write

☒ Append

☒ Rename

☒ Delete

☐ Execute 

☒ List

☐ Create

☐ Rename

☐ Remove

☒ Inherit

Maximum size of directory contents:  
 MB (leave blank for no limit)

Help

Full Access

Read Only

Advanced >>

These rules only allow users to access `.mdb` files within the specified directories. You can adapt these rules to any file extension or set of file extensions.

## Virtual paths

If virtual paths are specified, users can gain access to files and folders outside of their own home directory. A virtual path only defines a method of mapping an existing directory to another location on the system to make it visible within a user's accessible directory structure. In order to actually have access to the mapped location, the user must still have a directory access rule specified for the physical path of a virtual path.

Like directory access rules, virtual paths can be configured at the server, domain, group, and user levels. Virtual paths created at the server level are available for all users of the file server. When virtual paths are created at the domain level, they are only accessible by users belonging to that domain. You can also create virtual paths specifically for individual users or groups.

### Physical path

The physical path is the actual location on the system, or network, that is to be placed in a virtual location accessible by a user. If the physical path is located on the same computer, use a full path, such as `D:\inetpub\ftp\public`. You can also use a UNC path, such as `\\Server\share\public`. To make a virtual path visible to users, users must have a directory access rule specified for the physical path.

### Virtual path

The virtual path is the location that the physical path should appear in for the user. The `%HOME%` macro is commonly used in the virtual path to place the specified physical path in the home directory of the user. When specifying the virtual path, the last specified directory is used as the name displayed in directory listings to the user. For example, a virtual path of `%HOME%/public` places the specified physical path in a folder named `public` within the user's home directory. You can also use a full path without any macros.

### Including virtual paths in "Maximum Directory Size" calculations

When this option is selected, the virtual path is included in Maximum Directory

Size calculations. The Maximum Directory Size limits the size of directories affecting how much data can be uploaded.

### Case File: Using virtual paths

A group of web developers have been granted access to the directory `D:\ftproot\example.com\` for web development purposes. The developers also need access to an image repository located at `D:\corpimages\`. To avoid granting the group access to the root D drive, a virtual path must be configured so that the image repository *appears* to be contained within their home directory. Within the group of web developers, add a virtual path to bring the directory to the users by specifying `D:\corpimages\` as the physical path and `D:\ftproot\example.com\corpimages` as the virtual path. Be sure to add a group level directory access rule for `D:\corpimages\` as well. The developers now have access to the image repository without compromising security or relocating shared resources.

### Case File: Creating relative virtual paths

Continuing with the previous example, if the home directory of the group of web developers is relocated to another drive, both the home directory and the virtual path need to be updated to reflect this change. You can avoid this by using the `%HOME%` macro to create a relative virtual path location that eliminates the need to update the path if the home directory changes. Instead of using `D:\ftproot\example.com\corpimages` as the virtual path, use `%HOME%\corpimages`. This way the `corpimages` virtual path is placed within the home directory of the group, regardless of what the home directory is. If the home directory changes at a later date, the virtual path still appears there.

## Automated file management

Using file management rules, you can automatically remove or archive files from the file server. You can configure automated file management rules at the server and domain level. If they are specified at the server level, the file management

rules are accessible to all users of the file server. If they are specified at the domain level, they are only accessible to users belonging to that domain.

Depending on the file system, Serv-U uses the creation or change date of files to determine the expiration date. On Windows, the creation date of the file is used to determine when a file expires. On Linux, the change date is used to determine the expiration date. The change date is updated whenever the metadata or index node (inode) of the file is modified. If the contents or attributes (such as the permissions) of the file are modified, the change date is also updated.

**Note:** The change date is not modified if the file is read from.

The file management rules apply recursively to all files within the folder for which they are configured, and not only to those that have been uploaded through Serv-U. This way you can manage files which are transferred by clients, or which are copied to the folder outside of Serv-U.

The folder structure is not affected by the file management rules. When expired files are deleted or moved, the folders themselves remain intact.

The file management rules run hourly in the background. For this reason, there can be an hour delay before Serv-U deletes or moves an expired file.

To monitor the status of the file management rules, you can configure a File Management Rule Success and a File Management Rule Error event under **Server/Domain Details > Events**. The file management rules continue to run even if deleting or moving a single file fails. For more information, see Serv-U events.

### To define a new file management rule:

1. Navigate to **Directories > File Management**, and then click **Add**.
2. Type the path to the file or folder in the **Directory Path** field, or click **Browse** to navigate to the file or folder.
3. Select the action you want to perform on the file:
  - a. If you want to delete the file after it expires, select **Delete file(s) after specified time**.



- b. If you want to move the file after it expires, select **Move file(s) after specified time**, and then in the **Destination Directory Path** field, specify the folder where you want to move the file.
4. Specify the number of days after the file creation date when the action should be executed.
5. Click **Save**.

**Note:** Serv-U regularly and individually checks all the files in the directory for their age, and performs the specified action on the files that meet the age criteria you specify.

## Domain limits and settings

Serv-U contains options which you can use to customize how Serv-U can be used, and which also provide ways to apply limits and custom settings to users, groups, domains, and the server in its entirety. The limits stack intelligently, with user settings overriding group settings, group settings overriding domain settings, and domain settings overriding server settings. In addition, limits can be applied only during certain days of the week or times of the day. It is possible to grant exceptions to administrators and restrict specific users more than others, providing total control over the server. The limits and settings in Serv-U consist of the following categories:

- Connection
- Password
- Directory Listing
- Data Transfer
- HTTP
- Email

- File Sharing
- Advanced

To apply a limit, select the appropriate category, click **Add**, select the limit, and then select or enter the value. For example, to disable the **Lock users in home directory** option for a domain, follow these steps:

1. Select Domain Limits & Settings from the Serv-U Management Console.
2. From the **Limit Type** list, select **Directory Listing**.
3. Click **Add**.
4. From the **Limit** list, select **Lock users in home directory**.
5. Deselect the option.
6. Click **Save**.

The limits list displays the current limits applied to the domain. Limits with a light-blue background are default values. Limits with a white background are values that override the defaults. After completing the previous steps, a new **Lock users in home directory** limit appears in the list that displays "No" as the value.

Because of inheritance rules, this option applies to all users in the domain unless overridden at the group or user level. For more information about this method of inheritance, see "User interface conventions".

You can delete limits by selecting them and clicking **Delete**. To edit an overridden value, select the limit, and then click **Edit**. Default rules cannot be edited or deleted. Create a new limit to override a default one.

To create a limit that is restricted to a specific time of day or days of the week, click **Advanced** in the New Limit or Edit Limit window. Select **Apply limit only at this time of day** to specify a start and stop time for the new limit. To restrict the limit to certain days of the week, deselect the days for which you do not want to apply the limit. When a limit is restricted in this way, default values (or the value of other limit overrides) are applied when the time of day or day of the week restrictions are not met for this limit.

The following section contains a reference of all available domain limits, organized by category.

### **Connection**

#### **Maximum number of sessions on domain**

Specifies the maximum number of concurrent sessions that may be allowed on the current domain.

#### **Maximum sessions per IP address on domain**

Specifies the maximum number of concurrent sessions that may be opened to the current domain from a single IP address.

#### **Maximum number of sessions per user account**

Specifies the maximum number of concurrent sessions that may be opened from a single user account.

#### **Maximum sessions per IP address for user account**

Specifies the maximum number of concurrent sessions that a user may open from a single IP address.

#### **Require secure connection before login**

Requires that a connection must be secure (for example, FTPS, SFTP, or HTTPS) before it is accepted.

#### **Automatic idle connection timeout**

Specifies the number of minutes that must pass after the last client data transfer before a session is disconnected for being idle.

**Note:** Setting the Packet time-out is a requirement for this limit to work. The value of Packet time-out must be less than the value of the Automatic idle connection timeout for the Automatic idle connection timeout to work properly. For information about setting the packet time-out, see "Server settings".

#### **Automatic session timeout**

Specifies the number of minutes a session is allowed to last before being

disconnected by the server.

### **Block anti-timeout schemes**

Blocks the use of commands such as `noop`, which is commonly used to keep FTP Command Channel connections open during long file transfers or other periods of inactivity where no information is being transferred on the control channel. When these are blocked, Serv-U disconnects the client when the connection has been idle, that is, not transferring data, for a specified period of time.

### **Automatically create home directories**

Instructs Serv-U on whether or not to automatically create the home directory specified when creating a new user account if the directory does not already exist.

### **Block IP address of timed out session**

Specifies the number of minutes for which the IP address of a timed out session is blocked.

### **Allow X-Forwarded-For to change HTTP connection IP addresses**

When enabled, the "X-Forwarded-For" HTTP header parameter changes the IP address of the client for Serv-U. This is useful when all HTTP connections are coming from a proxy server or a load balancer. Proxy servers and load balancers typically append this parameter to the HTTP header so that HTTP servers can identify the actual client IP address and apply security rules as needed.

### **Require reverse DNS name**

Requires that users connecting to the server must connect from an IP address that has a valid reverse DNS name, also known as a PTR record. Checks for the existence of a valid PTR record but does not check its contents.

## **Password**

### **Check anonymous passwords**

Specifies whether or not Serv-U should validate email addresses supplied as the password to login anonymously.

### **Require complex passwords**

Specifies that all user account passwords must contain at least one uppercase and one non-alphabetic character to be considered valid.

### **Minimum password length**

Specifies the minimum number of characters required in the password of a user account. Specifying zero characters indicates that there is no minimum requirement.

### **Automatically expire passwords**

Specifies the number of days a password is valid before it must be changed. Specifying zero days means that passwords never expire.

### **Allow users to change password**

Specifies whether or not users are allowed to change their own passwords.

### **Mask received passwords in logs**

Masks the passwords received from clients from being shown in log files. Disabling this allows passwords to be displayed in log files, which can be useful for debugging connection problems or auditing user account security.

### **Password encryption mode**

Specifies the level of password encryption on user passwords. The following options are available:

- One-way encryption (more secure): This option fully encrypts passwords and cannot be reversed. This is the default setting.
- Simple two-way encryption (less secure): This option encrypts passwords in a reversible format for easy recovery. Use this option when users are expected to take advantage of the Password Recovery utility in the Web

Client. In this case it may be desirable to use two-way encryption so that Serv-U does not need to reset their passwords when password recovery is requested.

- No encryption (not recommended): This option stores passwords in clear text. Using this option may be necessary for integration with legacy systems (especially when using database support).

**Note:** When you change this setting, all user passwords must be reset. Existing passwords are not updated automatically, and must be re-saved to be stored in the new format.

### **Allow users to recover password**

If enabled, allows users to recover passwords using the Web Client password recovery utility at the login page.

### **SSH authentication type**

Specifies how SSH authentication is to occur. The following options are available:

- Password and Public Key: Requires both a password and a public key (when specified) for login.
- Password or Public Key: Requires either a password or public key for login.
- Public Key Only: Requires that a public key is provided for successful login, a password is not allowed.
- Password Only: Requires that a password is provided for successful login, a public key is not allowed.

**Note:** The Public Key Only authentication type allows users to log in with a password if they have no SSH key configured in Serv-U. This way the administrator cannot deny access to a user account through misconfiguration.

### **FTP password type**

Specifies the type of password to be used for FTP connections. The available options are regular password, OTP S/Key MD4, and OTP S/Key

MD5.

### **Days before considering password to be stale**

The number of days prior to expiration that a password is to be considered stale. A stale password is a password that is about to expire. An event can be configured to identify when a password is about to expire. This value is the lead-time, in days, before password expiration.

### **Disable password generators**

If enabled, this limit allows users to generate a random password.

### **Directory Listing**

#### **Hide files marked as hidden from listings**

Hides files and folders from directory listings that have the Windows "hidden" system attribute set on them.

#### **Use lowercase for file names and directories**

Forces Serv-U to display all file names and directories using lowercase characters, regardless of the actual letter case in use by the file or directory.

#### **Interpret Windows shortcuts as links**

Instructs Serv-U to treat all valid .lnk files as the actual destination object. In other words, if a .lnk file points to another file, the destination file is shown in the directory listing instead of the .lnk file itself.

#### **Treat Windows shortcuts as target in links**

Instructs Serv-U to treat all valid .lnk (shortcut) files as a UNIX symbolic link.

#### **Lock users in home directory**

Locks users into their home directory, and does not allow users to browse above that folder. In addition, their home directory is displayed as "/", masking the actual physical location.

#### **Allow root ("/") to list drives for unlocked users (Windows Only)**

Allows users to change directory to the root ("/") of the system and display all drives on the computer. This option only works when users are not

locked in their home directory.

### **Use natural language sorting for sorted listings**

By default, Serv-U uses natural language sorting for a more intuitive sort order. However, some clients may prefer ASCII sorting. Serv-U supports both sort orders.

### **Hide the compressed state of files and directories**

Hides the compressed state of all compressed files and directories being viewed by the user.

### **Hide the encrypted state of files and directories**

Hides the encrypted state of all encrypted files and directories being viewed by the user.

### **Message file path**

Welcome messages are normally displayed once to a user during login to relay important information to users about the file server site. By using a secondary message file, welcome messages can be provided in specific folders to relay additional information. A non-relative path such as `MessageFile.message` can be used as the path. The welcome message will only be displayed when navigating into folders which contain a file matching the specified file name.

## **Data Transfer**

### **Maximum upload speed for domain**

Limits the maximum bandwidth that can be used domain-wide for all uploads. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum download speed for domain**

Limits the maximum bandwidth that can be used domain-wide for all downloads. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum upload speed per session**

Limits the maximum upload bandwidth for each individual session. Setting a



limit of 0 KB/s means unlimited bandwidth.

### **Maximum download speed per session**

Limits the maximum download bandwidth for each individual session.

Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum upload speed for user accounts**

Limits the maximum upload bandwidth shared between all sessions associated with an individual user account. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum upload file size**

Restricts the maximum single file size a user can upload to Serv-U. The file size is measured in kilobytes.

### **Maximum download speed for user accounts**

Limits the maximum download bandwidth shared between all sessions associated with an individual user account. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Delete partially uploaded files**

Instructs Serv-U to delete incomplete file uploads. If this option is enabled, users are not able to restart interrupted uploads by using the `REST` (Restart) FTP command.

### **Interpret line feed byte as a new line when in ASCII mode (Windows Only)**

When uploading and downloading files using ASCII mode, Serv-U will assume `<LF>` characters are the same as `<CR><LF>` end-of-line markers. Most Windows applications expect `<CR><LF>` to represent a new-line, as does the FTP protocol. However, since the definition of a new-line sequence is not fully defined in Windows, this option allows Serv-U to assume `<LF>` is the same as `<CR><LF>`. When uploading in ASCII mode stand-alone `<LF>` characters are changed to `<CR><LF>` prior to writing to the file. When downloading in ASCII mode, stand-alone `<LF>` characters are changed to `<CR><LF>` prior to sending to the client.

**Automatically check directory sizes during upload**

Instructs Serv-U to occasionally check the size of directories in which a maximum directory size has been specified. This attribute ensures that Serv-U always has updated directory sizes available instead of having to calculate them at transfer time, which can be a time consuming operation.

**HTTP****Warn end users when using old web browsers**

When enabled (default) users are warned when they are using an outdated browser that they should upgrade the browser to take advantage of performance and feature enhancements to improve their experience.

**Default language for Web Client**

When the end-user connects with an unsupported language, the HTTP login page is displayed in English. The default language can be set to any language you want. When connecting to Serv-U using a supported localization of Windows, the local language of Windows is used.

**Allow HTTP media playback**

The Serv-U Web Client supports fully interactive media playback of audio and video files. This function can be disabled during specific business hours or altogether based on business needs.

**Allow browsers to remember login information**

The HTTP login page supports a Remember me option (not enabled by default) that allows user names to be remembered by the login page. This feature can be disabled for security reasons.

**Allow users to change languages**

The Serv-U Web Client is supported in many languages, but this option can be disabled if users should not be able to select their preferred language.

**Allow users to use Web Client**

Serv-U Web Client is enabled by default. Administrators can disallow the use of Serv-U Web Client by disabling this limit.

### **Allow users to use Web Client Pro**

Serv-U Web Client Pro is enabled by default. Administrators can disallow the use of Serv-U Web Client Pro by disabling this limit.

### **Allow users to use FTP Voyager JV**

FTP Voyager JV is enabled by default. Administrators can disallow the use of FTP Voyager JV by disabling this limit.

### **Maintain file dates and times after uploading (FTP Voyager JV and Web Client Pro only)**

When enabled, Serv-U can maintain the last modification date and time of the file when end-users are using FTP Voyager JV or Web Client Pro.

When disabled, Serv-U will not set the last modification date and time of the file; it will remain the date and time the file was uploaded.

### **Allow HTTP sessions to change IP address (disabling may cause mobile devices to fail)**

The Serv-U Web Client supports the transfer of HTTP sessions if the IP address changes. This option can be disabled but it may cause mobile devices to be disconnected due to frequent IP address changes by these devices.

### **Hide Serv-U version information in HTTP response headers**

When enabled, the version information of Serv-U will be hidden in HTTP and HTTPs response headers. This way a potential security threat arising from the knowledge of the version information can be mitigated.

### **Allow autocomplete for HTTP login fields**

With this limit you can configure whether or not password auto-completion is allowed on the Serv-U login screen. This option is enabled by default.

## **Email**

### **Allow end-user to set account email address**

Specifies whether users are allowed to modify their account email address using the Change Email Address option in the Web Client or File Sharing interfaces.

### **Require end-user to set email address at next HTTP login**

Specifies whether users must set their email address when they log in to Serv-U.

## **File Sharing**

### **Require a password for guest access**

Specifies whether it is possible to set up a file share where the guest is required to provide a password. When this limit is set to Always or Never, the creator of the file share will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share whether or not the guest must provide a password.

### **Insert passwords within invitation emails**

Specifies whether it is possible to set up a file share where the password for the share is included in the invitation email. When this limit is set to Always or Never, the creator of the file share will not be able to specify this optional setting. When this limit is set to Optional, the **Include the password in the email** option can be selected individually in each file share.

### **Maximum file size guests can upload (per file)**

Specifies the file size constraints imposed upon the guest user. If set to zero, there is no file size constraint. In this case, the creator of the file share request can specify the maximum file size in each file share request without an upper limit.

### **Allow user-defined guest link expiration**

When enabled, users will be able to specify link expiration dates individually on the Request Files and Send Files wizards. When disabled, the file share links will expire after the number of days specified in the **Duration before guest link expires** limit.

### **Duration before guest link expires**

Limits the number of days after which a file share link expires if the Allow user-defined guest link expiration limit is disabled.

### **Notify user after a file is downloaded**

Specifies whether the **Notify me when the file(s) have been downloaded** option can be used in the Send Files wizard. When this limit is set to Always or Never, the creator of the file share will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share whether to receive notification of the file download.

### **Notify user after a file is uploaded**

Specifies whether the **Notify me when the file(s) have been uploaded** option can be used in the Request Files wizard. When this limit is set to Always or Never, the creator of the file share request will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share request whether to receive notification of the file upload.

### **Send the guest access link to the recipients**

Specifies whether the **Automatically send the download/upload link to the guest user(s) in email** option can be used in the Send Files and Request Files wizards. When this limit is set to Always or Never, the user will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share or file share request whether to send the access link automatically.

### **Send the guest access link to the sender**

Specifies whether the **Send me an email copy with the download/upload link** option can be used in the Send Files and Request Files wizards. When this limit is set to Always or Never, the user will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share or file share request whether to receive an email copy with the download or upload link.

### **Allow user-defined contact information**

When enabled, users will be able to edit their name and email address in the Request Files and Send Files wizards. When disabled, users are not

allowed to edit their contact information in the Request Files and Send Files wizards.

**Maximum number of files for "Sent" shares**

Specifies the maximum number of files users can include in a single file share. If set to zero, the default limit of 20 is used.

**Maximum number of files for "Requested" shares**

Specifies the maximum number of files users can upload after receiving a file share request. If set to zero, the default limit of 20 is used.

**Allowed "Sent" file share sources**

Specifies the valid file sharing sources that users can browse to when they create an outgoing file share. By default, users can browse to any file stored on their computer or on Serv-U.

**Advanced****Convert URL characters in commands to ASCII**

Instructs Serv-U to convert special characters contained in command parameters to plain ASCII text. Certain web browsers can encode special characters contained in file names and directories when using the FTP protocol. This attribute allows Serv-U to decode these special characters.

**Maximum supported SFTP version**

Specifies the maximum version of SFTP permitted for SFTP connections. Serv-U supports SFTP versions 3 - 6.

**Allow rename overwrite**

When enabled (default) Serv-U allows files to be renamed to files where the destination already exists. When disabled, users are not allowed to rename a file or directory to a path name that already exists.

**Apply server and domain directory access rules before user and group**

The order in which directory access rules are listed is important in determining the resources that are available to a user or group account. By

default, directory access rules specified at the group or user level take precedence over ones specified at the domain and server level. However, there are certain instances where you may want the domain and server level rules to take precedence. Setting this value to "Yes" places the directory access rules of the group and user *below* the server and domain. For more information, see the "Apply group directory access rules first" setting in Group information.

### **Days before automatically disabling account to trigger the pre-disable event**

The number of days prior to automatically disabling the user account that the pre-disable event should be triggered.

### **Days before automatically deleting account to trigger the pre-delete event**

The number of days prior to automatically deleting the user account that the pre-delete event should be triggered.

### **Owner ID (user name) for created files and directories (Linux Only)**

The user name given to set as the owner of a created file or directory.

### **Group ID (group name) for created files and directories (Linux Only)**

The group name given to set as the owner of a created file or directory.

### **Reset user stats after restart**

When this limit is enabled the user statistics are reset after a server restart.

### **Reset group stats after restart**

When this limit is enabled the group statistics are reset after a server restart.

## **Domain settings**

On the **Domain Limits and Settings > Settings** pages, you can configure basic domain settings that affect performance, security, and network connectivity. To configure a setting, type the value you want in the appropriate area, and then click **Save**. This topic contains detailed information about the settings that you can configure.

## Connection settings

### **Block users who connect more than 'x' times within 'y' seconds for 'z' minutes**

Also known as anti-hammering, enabling this option is a method of preventing brute force password guessing systems from using dictionary style attacks to locate a valid password for a user account. Using strong, complex passwords defeats most dictionary attacks. However, enabling this option ensures that Serv-U does not waste time processing connections from these illegitimate sources. When configuring this option, ensure that there is some room for legitimate users to correct an incorrect password before they are blocked.

When enabled, this option temporarily blocks IP addresses for the specified number of minutes that fail to successfully login after the specified number of attempts within the specified number of seconds. IP addresses blocked in this way can be viewed in the appropriate IP Access rules tab. A successful login resets the counter that is tracking login attempts.

### **Hide server information from SSH identity**

After a successful SSH login, the server sends identification information to the client. Normally, this information includes the server name and version number. Enable this option to prevent the information from being given to the client.

### **Default Web Client**

Specifies whether the Web Client or FTP Voyager JV should be used by all HTTP clients by default. The third, default option is to prompt the user for the client they want to use instead. This option is also available at the group and user level.

### **Custom HTTP Settings**

Basic branding (custom logo and limited text changes) can be implemented using the Custom HTTP Settings. Advanced branding is also available. For



more information, see Custom HTML.

### **Specify a custom logo to be displayed on the login and Web Client pages**

Dimensions for custom logos must have a width of 400 pixels and a height of 100 pixels. If a logo does not meet this criteria an error message will appear when you attempt to save the logo.

**Note:** JPEG images which use CMYK instead of RGB encoding may not work properly in certain browsers. Test your logo image to make sure it is displayed properly in all browsers.

To add a logo, click **Browse** next to **Custom Logo Path**, and then select the path to your logo. Click **Save** and the logo will appear below the **Custom Logo Path** field. To delete a custom logo, clear the path in the **Custom Logo Path** field, and then click **Save**.

### **HTTP Login Title Text (no HTML)**

Provide text to be used as the title of the HTTP login and Web Client pages.

### **HTTP Login Page Text**

Provide any custom login page text you want in this area. This text can be HTML-formatted, including links, images, and standard formatting like italics, bold, underline, alignment and more.

### **HTTP Client Interface Background (CSS Only)**

Provide a custom CSS background style for the Web Client, File Sharing and FTP Voyager JV landing page. This style follows the CSS background shorthand standard. The "background:" string is assumed so it does not need to be entered here. The format for a CSS background is `color url('/%CUSTOM_HTML_DIR%/images/yourimage.png') repeat-type horizontal-alignment vertical-alignment`.

The `%CUSTOM_HTML_DIR%` must be used in conjunction with the Custom HTML settings. Custom HTML must be enabled and a Custom HTML Container Directory must be specified.

The following examples provide a reference:

- `#0b16f8 url('/%CUSTOM_HTML_DIR%/images/Header01.png') no-repeat right top`
- `#FFFFFF url('/%CUSTOM_HTML_DIR%/images/MyLogoTile.png') repeat-x left top`
- `red` (this example uses no image)
- `url('/%CUSTOM_HTML_DIR%/images/MyHeader.png') no-repeat center top` (this example uses no custom color)

### Password Recovery Email Message

Send email messages to users with their login credentials using this customizable password recovery message.

The password recovery email message has a simple default subject and message with the user's login ID and password. This message will be sent if the user has a valid email address recorded in Serv-U. Users can request this message from the Serv-U login page.

Administrators can also send this message to users using the **Recover Password** button under domain users and global users in the Management Console.

### Integration DLL / Shared Library

For information about writing an Integration DLL or Shared Library, see the Serv-U Integration Sample DLL installed with Serv-U in the `Serv-U Integration Sample DLL` sub-directory. The Integration API is documented in this sample.

## Other Settings

### Ratio Free Files

Files listed by clicking **Ratio Free Files** are exempt from transfer ratio limitations on file transfers. Ratio free files specified at the server or domain level are inherited by all their users accounts. For more information about ratio free files, see Transfer ratio and quota management.

## FTP settings

In the Serv-U File Server, you can customize the FTP commands that Serv-U

accepts, and you can also customize the responses of Serv-U to the FTP commands it receives. If you configure these options at the server level, all domains inherit the customizations. To customize the FTP behavior for a specific domain, select the appropriate domain, open the FTP Settings page for the domain, and then click **Use Custom Settings** . At any time, you can click **Use Default Settings** to have the domain revert back to the default settings of the server.

**Warning:** Customizing the FTP behavior in this way is not recommended except for those very familiar with the FTP protocol and its standard and extended command set.

### Global Properties

When using custom settings, the **Global Properties** button becomes available.

### FTP Responses

Global FTP responses are responses shared amongst most FTP commands, such as the error message sent when a file is not found. Customizing a global FTP response ensures that the response is used by all other FTP commands rather than having to customize it for each individual FTP command. FTP command responses can contain special macros that allow real-time data to be inserted in to the response. For more information, see System variables.

### Message File

The server welcome message is sent in addition to the standard "220 Welcome Message" that identifies the server to clients when they first connect. If the **Include response code in text of message file** option is selected, the 220 response code begins each line of the specified welcome message. To customize the welcome message, enter the path to a text file in the **Message File Path** field. Click **Browse** to select a file on the computer. Serv-U opens this file and sends its contents to connecting clients.

### Advanced Options

- Block "FTP\_bounce" attacks and FXP (server-to-server transfers): Select this option to block all server-to-server file transfers involving this Serv-U File Server by only allowing file transfers to the IP address in use by the command channel. For more information about FTP\_bounce attacks, see [CERT advisory CA-97.27](#).
- Include response code on all lines of multi-line responses: The FTP protocol defines two ways in which a multi-line response can be issued by an FTP server. Some older FTP clients have trouble parsing multi-line responses that do not contain the three-digit response code on each line. Select this option if your clients are using an FTP client experiencing problems with multi-line responses from Serv-U.
- Use UTF-8 encoding for all sent and received paths and file names: By default, Serv-U treats all file names and paths as UTF-8 encoded strings. It also sends all file names and paths as UTF-8 encoded strings, such as when sending a directory listing. Deselecting this option prevents Serv-U from UTF-8 encoding these strings. When this option is deselected, UTF-8 is not included in the FEAT command response to indicate to clients that the server is not using UTF-8 encoding.

### Editing FTP Commands and Responses

To edit FTP Commands, select the FTP command you want to change, and then click **Edit**.

#### Information

On the Information page, basic information about the command is shown along with a link to more information on the Serv-U website. Each FTP command can also be disabled by selecting the **Disable command** option. Disabled commands are treated as unrecognized commands when they are received from a client.

### FTP Responses

On the FTP Responses page, all possible FTP responses to the command

as issued by the server can be modified by clicking **Edit** for each response. FTP command responses can contain special macros that allow real-time data to be inserted in to the response. For more information, see System variables.

### Message Files

Certain FTP commands allow a message file to be associated with them. The contents of a message file are sent along with the standard FTP response. In addition, a secondary message file path is available as a default option. This allows for message files to be specified using a path relative to the home directory of the user for the Message File. If the first message file is not found, Serv-U attempts to use the Secondary Message File instead. By specifying an absolute file path in the secondary location, you can ensure that each user receives a message file.

The following FTP commands can be used for specifying a message file:

- **CDUP**
- **CWD**
- **QUIT**

### Managing Recursive Listings

Serv-U supports recursive listings by default, allowing FTP clients to obtain large directory listings with a single command. In some cases, clients may request excessively large directory listings using the **-R** parameter to the **LIST** and **NLIST** commands. If performance in Serv-U is impacted by users requesting excessively large listings, recursive listings can be disabled by using the **Allow client to specify recursive directory listings with -R parameter** option.

### Advanced Options

Some FTP commands contain advanced configuration options that offer additional ways to configure the behavior of the command. Where available, the configuration option is described in detail in the Management Console.

The following FTP commands contain advanced configuration options:

- **LIST**
- **MDTM**
- **NLST**

### Case File: Custom FTP command response

Users connecting to the server need to know how much quota space is available in a given folder when they have completed a transfer. To do this, edit the response to the **STOR** command to include a report about available space. By default, the 226 (command successful) response to the **STOR** command (which stores files on the server) is the following:

```
Transfer complete. $TransferBytes bytes transferred.  
$TransferKBPerSecond KB/sec.
```

Modify this to include an extra variable in the following way:

```
Transfer complete. $TransferBytes bytes transferred.  
$TransferKBPerSecond KB/sec. Remaining storage space is $QuotaLeft.
```

The last sentence shows the user how much storage space is left at the end of each file upload. The same can be done for the **DELE** command, so that every time a user deletes a file, their updated quota value, showing an increase in available space, is displayed. This can be done for any FTP command response.

## Encryption

Serv-U supports two methods of encrypted data transfer: Secure Socket Layer (SSL) and Secure Shell 2 (SSH2). SSL is used to secure the File Transfer Protocol (FTP) and Hypertext Transfer Protocol (HTTP). SSH2 is a method of securely interacting with a remote system that supports a method of file transfer commonly referred to as SFTP. Despite its name, SFTP does not have anything in common with the FTP protocol itself.

In order for each method of encryption to work, a certificate, a private key, or both must be supplied. SSL requires the presence of both, while SSH2 only requires a

private key. If you do not have either of these required files, you can create them in Serv-U.

Encryption options specified at the server level are automatically inherited by all domains. Any encryption options specified at the domain level automatically overrides the corresponding server-level option. Certain configuration options are only available to the server.

When creating SSL/TLS, SSH, and HTTPS encrypted domains within Serv-U, it is important to know that encrypted domains cannot share listeners. Because SSL/TLS and SSH encryption is based on encrypting traffic sent between IP addresses, each domain must have unique listeners in order to operate properly. In the case that multiple encrypted domains are created that share listeners, the domain that is created first takes precedence, and causes other encrypted domains to fail to function properly. To operate multiple encrypted domains, modify the listeners of each domain to ensure they listen on unique port numbers.

### Configuring SSL for FTPS and HTTPS

#### To use an existing certificate:

1. Obtain an SSL certificate and private key file from a certificate authority.
2. Place these files in a secured directory in the server.
3. Use the appropriate **Browse** button to select both the certificate and private key files.
4. If a CA (Certificate Authority) PEM file has been issued, enter or browse to the file.
5. Enter the password used to encrypt the private key file.
6. Click **Save**.

If the provided file paths and password are all correct, Serv-U starts to use the certificate immediately to secure FTPS and HTTPS connections using the provided certificate. If the password is incorrect or Serv-U cannot find either of the provided files, an error message is displayed that explains the encountered error.

### To create a new certificate:

1. Click **Create Certificate**.
2. Specify the **Certificate Set Name** that is used to name each of the files Serv-U creates.
3. Specify the output path where the created files are to be placed. In most cases, the installation directory is a safe location (for example, `C:\ProgramData\RhinoSoft\Serv-U\`).
4. Specify the city/town in which the server or corporation is located.
5. Specify the state (if applicable) in which the server or corporation is located.
6. Specify the 2-digit country code for the country in which the server or corporation is located.
7. Specify the password used to secure the private key.
8. Specify the full organization name.
9. Specify the common name of the certificate. The IP address or the Fully Qualified Domain Name (FQDN) that users use to connect must be listed here.  
**Note:** If the Common Name is not the IP address or FQDN used by clients to connect, clients may be prompted that the certificate does not match the domain name they are connecting to.
10. Specify the business unit the server is located in.
11. Specify the key length in bits.
12. Click **Create** to complete the certificate creation.

Serv-U creates three files using the provided information: A self-signed certificate (.crt) that can be used immediately on the server but is not authenticated by any known certificate authority, a certificate request (.csr) that can be provided to a certificate authority for authentication, and a private key file (.key) that is used to secure both certificate files. It is extremely important that you keep the private key in a safe and secure location. If your private key is compromised, your certificate



can be used by malicious individuals.

### Viewing the certificate

To view the SSL certificate once it is configured, click **View Certificate**. All identifying information about the certificate, including the dates during which the certificate is valid, are displayed in a new window.

### SFTP (Secure File Transfer over SSH2)

#### To use an existing private key:

1. Obtain a private key file.
2. Place the private key file in a secured directory in the server. Use **Browse** in Serv-U to select the file.
3. Enter the password for the private key file.
4. Click **Save**. After clicking **Save**, Serv-U displays the SSH key fingerprint associated with the private key.

#### To create a private key:

1. Click **Create Private Key**.
2. Enter the name of the private key, (for example, `MyDomain Key`), which is also used to name the storage file.
3. Enter the output path of the certificate, (for example, `C:\ProgramData\RhinoSoft\Serv-U\`).
4. Select the Key Type (default of DSA is preferred, but RSA is also available).
5. Select the Key Length (default of 1024 bits provides best performance, 2048 bits is a good median, and 4096 bits provides best security).
6. Enter the password to use for securing the private key file.
7. After you create a new key, Serv-U displays the SSH key fingerprint associated with the new private key.

### SSH Ciphers and MACs

By default, all supported SSH ciphers and MACs (Message Authentication Codes) are enabled for use by the server. If your specific security needs dictate that only certain ciphers or MACs can be used, you can individually disable unwanted ciphers and MACs by deselecting the appropriate ciphers or MACs.


### Custom HTML

You can use custom HTML for the HTTP and HTTPS login pages of Serv-U. By using this feature, web developers can design their login experience to show off their exclusive brand and design the page to match existing business themes. Basic branding (custom logo and limited text changes) is also available. For more information, see Domain settings.

By using the custom HTML feature, you can provide a custom header and custom footer for the HTTP and HTTPS login page. The main login form is automatically inserted between the content defined in the header file and footer file. The custom HTML interface also uses a CSS file which defines the style used in the login form. This CSS file can also be used to define custom CSS styles, containers, and other CSS formatting as needed.

Several branding samples are automatically unpacked to your installation folder (for example, `C:\Program Files\RhinoSoft\Serv-U\Custom HTML Samples`) when Serv-U is installed. [Serv-U KB #2054](#) has step-by-step instructions to explore the current set of samples and build your own branding.

The following fields are used by the Custom HTML feature:



- Custom HTML Container Directory: This directory contains all of the files used by the custom HTML, including all images, the header file, the footer file, and the CSS file. Subdirectories in this folder are allowed.
- CSS File: This .CSS file contains all the styles, containers, and other formatting that is used throughout the header file and footer file, and also the styles that will be used by the login form.
- Header File: This .HTM file contains the content for the HTML header that is inserted before the login form.
- Footer File: This .HTM file contains the content for the HTML footer that is inserted after the login form.
- Enable Custom HTML: The custom HTML is not used by Serv-U until this option is enabled.

Most custom HTML interfaces include custom images. To use custom images, the storage location of the images must be specified. To universalize the storage location, use of the `%CUSTOM_HTML_DIR%` tag in paths that refer to images. This has the further benefit of avoiding changes to HTML when the container storing the HTML files and images is changed, because the path only has to be defined once in the **Custom HTML Container Directory** field. The tag is used in the following way:

```

```

## File sharing

By using the file sharing feature, domain users can send or receive files from guests.

**Note:** File sharing is disabled by default. You must select the relevant option to enable it.

To send file sharing invitation emails, you must configure your SMTP settings. This configuration only needs to be set once for the entire server or a domain.


For more information about file sharing, see the [Serv-U Web Client and File Sharing User Guide](#).

### To enable file sharing:

1. Navigate to **Server Limits and Settings > File Sharing**.
2. Type the address for the domain URL.
3. Type the location of the file sharing repository.
4. Select the number of days until the shares expire.
5. Select whether you want to use the inherited default email invitation subject, or customize your own. If the option is deselected, you can type in a custom email invitation subject.
6. Select whether you want to use the inherited default email notification message, or customize your own. If the option is deselected, you can type in a custom message.
7. Select **Enable File Sharing**.
8. If it is not configured yet, configure your SMTP to be able to send and receive notification emails. For more information about configuring an SMTP server, see "Serv-U SMTP configuration".
9. Click **Save**.


## Chapter 4: Domain


LimitsSettingsFTP SettingsEncryptionCustom HTMLFile Sharing

 The File Sharing feature allows your domain users to send or receive files from guests. Use the options below to configure this feature.

File Sharing Settings

Domain URL (ex. "www.mysite.com" or "127.0.0.1"):

File Sharing Repository:  
 

Remove expired shares after  days 


Invitation Subject Template:

☒ Use inherited default subject

Invitation Email Template:  

You have received access to a Serv-U File Share from \$FullName. The link to transfer your file(s) will expire on \$FileShareExpires.  
  
\$FileShareTokenURL  
  
\$FileShareComments  
  
Need help? See some troubleshooting tips at <http://www.Serv-U.com/sharefiles>.

☒ Use inherited default message  
☐ Use Secure URL (HTTPS)  
☒ Enable File Sharing

 Additional file sharing settings are available under the "Limits" tab.

Save

## Server activity

The **Server Activity > Sessions** and **Domain Activity > Sessions** pages display the current file server session activity. When you view the Sessions page from the server, all connected sessions from all domains are displayed. When you view the Sessions page while you are administering a domain, only the current sessions of the particular domain are displayed. From this page, you can see an overall picture of the current activity on the file server. In addition, you can view individual sessions, including their current status, connection state, and transfer information.

To view detailed information about a specific session, select the session. The **Active Session Information** group is populated with the details of the currently highlighted session. This information is frequently updated to provide an accurate and up-to-date snapshot of the activities of the session.

Depending on the type of connection made by that session (for example, FTP, HTTP, or SFTP), certain additional functions are available.

### Disconnecting sessions

You can disconnect any type of session at any time by clicking **Disconnect**. Click this button to bring up another window with additional options for how the disconnect should be performed. The following disconnect options are available:

- **Disconnect:** Immediately disconnects the session. Another session can be immediately established by the disconnected client. This is also known as "kicking" the user.
- **Disconnect and ban IP for x:** Immediately disconnects the session and bans its IP address for the specified number of minutes, preventing the client from immediately reconnecting.
- **Disconnect and block IP permanently:** Immediately disconnects the session and adds a deny IP access rule for the IP address, preventing the client from ever reconnecting from the same IP address.

When disconnecting a session from the Server Session view, you can also use the **Apply IP rule to** option. By using this option, you can select where you want the temporary or permanent IP ban to be applied: for the entire server, or only the domain the session is connected to.

In addition to disconnecting the session, you can also disable the user account in use by the session by selecting **Disable user account**.

If the current session is using the FTP protocol, you can send a message to the user before disconnecting them by typing it in the **Message to user** field. This option is not available for HTTP or SFTP sessions because neither protocol defines a method for chatting with users.

### Using the spy & chat function

You can spy on any type of session by clicking **Spy & Chat** or by double-clicking a session in the list. Spying on a user displays all the detailed information normally visible by highlighting the session, and also includes a complete copy of the session log since it first connected to the file server. This way you can browse the log and view all actions taken by the user of the session.

If the current session is using the FTP protocol, additional options are available for chatting with the user. The **Chat** group shows all messages sent to and received from the session since beginning to spy on the session. To send a message to the session, type the message text in the **Message Content** field, and then click **Send**. When a message is received from the session, it is automatically displayed here.

**Note:** Not all FTP clients support chatting with system administrators. The command used to send a message to the server is `SITE MSG`. In order for a client to receive messages, the client application must be capable of receiving unsolicited responses from the server instead of discarding them.

### Broadcasting messages

You can send a message to all currently connected FTP sessions by clicking **Broadcast**. Sending a message through broadcast is equivalent to opening the **Spy & Chat** window to each individual FTP session and sending it a chat message.

### Canceling sessions

If a session is performing a file transfer, you can cancel the file transfer without disconnecting the session by clicking **Abort**. After confirming the command, the current file transfer for that session is terminated by the server. Some clients, especially FTP and SFTP clients, may automatically restart the canceled transfer, making it appear that the cancellation failed. If this is the case, try disconnecting the session instead.

## Server and domain statistics

The **Server Activity > Statistics** and **Domain Activity > Statistics** pages show detailed statistics about the use of the server for use in benchmarking and records keeping. Statistics viewed at the server level are an aggregate of those accumulated by all domains on the server. Statistics viewed for an individual domain are for that domain only. The displayed information includes the following details:

### Session statistics

#### Current Sessions

The number of sessions currently connected.

#### Total Sessions

The total number of sessions that have connected since being placed online.

#### 24 Hrs Sessions

The number of sessions that have connected in the past 24 hours.

#### Highest Num Sessions

The highest number of concurrent sessions that has been recorded since being placed online.

#### Average Session Length

The average length of time a session has remained connected.

#### Longest Session

The longest recorded time for a session.

### Login statistics

These statistics can apply to either a domain or the entire server depending on the statistics currently being viewed. Login statistics differ from session statistics because they apply to a login (providing a login ID and password) as opposed to connecting and disconnecting.



### **Logins**

The total number of successful logins.

### **Average Duration Logged In**

The average login time for all sessions.

### **Last Login Time**

The last recorded valid login time. This is not the last time a connection was made.

### **Last Logout Time**

The last recorded valid logout time.

### **Most Logged In**

The highest number of users logged in concurrently.

### **Currently Logged In**

The number of sessions currently logged in.

### **Transfer statistics**

#### **Download Speed**

The cumulative download bandwidth currently being used.

#### **Upload Speed**

The cumulative upload bandwidth currently being used.

#### **Downloaded**

The total amount of data, and number of files, downloaded since being placed online.

#### **Uploaded**

The total amount of data, and number of files, uploaded since being placed online.

#### **Average Download Speed**

The average download bandwidth used since being placed online.

#### **Average Upload Speed**

The average upload bandwidth used since being placed online.

## User and group statistics

The User & Group Statistics pages show detailed statistics based on individual user or group activity. Statistics viewed for a user or group are for that user or group only. The displayed information includes the following details:

### Session statistics

#### Current Sessions

The number of sessions currently connected.

#### 24 Hrs Sessions

The number of sessions that have connected in the past 24 hours.

#### Total Sessions

The total number of sessions that have connected since being placed online.

#### Highest Num Sessions

The highest number of concurrent sessions that has been recorded since being placed online.

#### Avg. Session Length

The average length of time a session has remained connected.

#### Longest Session

The longest recorded time for a session.

### Login statistics

These statistics can apply to either a user or a group of users, depending on the statistics currently being viewed. Login statistics differ from session statistics because they apply to a login (providing a login ID and password) as opposed to connecting and disconnecting.

#### Logins

The total number of successful logins.

**Last Login Time**

The last recorded valid login time (not the last time a connection was made).

**Last Logout Time**

The last recorded valid logout time.

**Logouts**

The total number of logouts.

**Most Logged In**

The highest number of simultaneously logged in sessions.

**Longest Duration Logged In**

The longest amount of time a session was logged in.

**Currently Logged In**

The number of sessions currently logged in.

**Average Duration Logged In**

The average login time for all sessions.

**Shortest Login Duration Seconds**

The shortest amount of time a session was logged in.

**Transfer statistics**

**Download Speed**

The cumulative download bandwidth currently being used.

**Upload Speed**

The cumulative upload bandwidth currently being used.

**Average Download Speed**

The average download bandwidth used since being placed online.

**Average Upload Speed**

The average upload bandwidth used since being placed online.

**Downloaded**

The total amount of data, and number of files, downloaded since being

placed online.

### Uploaded

The total amount of data, and number of files, uploaded since being placed online.

### Save Statistics

User and group statistics can be saved directly to a CSV file for programmatic analysis and review. To save statistics to a file, first select the user or group you want to generate a statistics file for, and then click **Save Statistics** at the bottom of the page.

## Server and domain log

The **Server Activity > Log** and **Domain Activity > Log** pages show logged activity for the server or domain.

The server log shows file server startup, configuration, and shutdown information. It does not show domain activity information. For activity logs, view the log of the appropriate domain instead. In addition to status information about libraries, licensing, and the current build that is logged when the file server first starts, the server log also contains information about all domain listener status, Universal Plug-and-Play (UPnP) status information, and PASV port range status. The information contained in the server log is also saved to a text file located in the installation directory that is named `Serv-U-StartupLog.txt`. This file is replaced each time the Serv-U File Server is started.

The domain log contains information about and activity pertaining to the currently administered domain only. This includes the status of the listeners of the domain, and any configured activity log information. For more information about the types of activity information that can be placed in the domain log, see [Configuring domain logs](#).

You can highlight information contained in the log by clicking and dragging the mouse cursor over the appropriate portion of the log. When it is highlighted, you can copy the selected portion to the clipboard.

### Freeze Log

Select this option to temporarily pause the refreshing of the log. This is useful on busy systems so you can highlight and copy a particular section of the log before it scrolls out of view. When you have finished, deselect the option to resume the automatic updating of the log.

### Select All

Click this button to automatically freeze the log and highlight all currently displayed log information so you can copy it to the clipboard.

### Clear Log

When the log has become too large for you to view at once, click this button to erase the currently displayed log information. Only log information received after clicking the button is displayed.

### Legend

To make viewing the different components of the log easier, each different type of logged message is color-coded for quick identification. Clicking this shows the legend in a draggable dialog. Drag the legend dialog to a convenient location so you can use it for reference while you browse the log.

### Filter Log

To quickly find and read through specific sections of the log, you can filter it based on a search string. Click this button to bring up the Filter Log window. Provide a search string, and then click **Filter** to refresh the log to only display log entries containing the search string. To view the entire contents of the log again, open the Filter Log window, and then click **Reset**.

### Download Log

To download the full log file from Serv-U, click **Download Log**. If you have permission to download the file, your web browser prompts you to choose a location to save the file, or it begins to download the file automatically.

## Configuring domain logs

In the Serv-U File Server, you can customize the logging of domain events and activity to a great extent. Logging consists of two sections: File and Screen. To enable a logging option, select the appropriate option in the File or Screen column. When an option is selected from the File column, the appropriate logging information is saved to the specified log file if **Enable logging to file** is selected. When an option is selected from the Screen column, the event is displayed in the log when viewed from the Serv-U Management Console. You can configure the log to show as much or as little information as you want. After configuring the logging options you want, click **Save** to save the changes.

### Logging to File Settings

#### Log file path

You must specify the name of the log file before information can be saved to a file. Click **Browse** to select an existing file or directory location for the log file. The log file path supports certain wildcard characters. Wildcard characters which refer to the date apply to the day that the log file is created. When combined with the **Automatically rotate log file** option, wildcards provide an automatic way to archive domain activity for audits. The following list contains the wildcard characters that you can use:

**%H**

The hour of the day (24-hour clock).

**%D**

The current day of the month.

**%M**

The name of the current month.

**%N**

The numeric value of the current month (1-12).

**%Y**

The 4-digit value of the current year, (for example, 2014).

### %X

The 2-digit value of the current year, (for example, 14 for 2014).

### %S

The name of the domain whose activity is being logged.

### Enabling logging to file

Select this option to enable Serv-U to begin saving log information to the file specified in the **Log file path**. If this option is not selected, Serv-U does not log any information to the file, regardless of the individual options selected in the File column.

### Automatically rotating the log file

To ensure that log files remain a manageable size and can be easily referenced during auditing, you can automatically rotate the log file on a regular basis. By specifying a **Log file path** containing wildcards referencing the current date, Serv-U can rotate the log file and create a unique file name every hour, day, week, month, or year.

### Purging old log files

You can automatically purge old log files by setting a maximum number of files to keep, a maximum size limit in megabytes, or both. Setting these options to "0" means that the setting is unlimited, and the limit is not applied.

**Warning:** Log files are purged based only on the current log file path name, and they are purged approximately every 10 minutes. Log file variables are replaced with Windows wildcard values used to search for matching files. For example:

```
C:\Logs\%Y:%N:%D %S Log.txt is searched for C:\Logs\????:??:?? * Log.txt
C:\Logs\%Y:%M:%D %S Log.txt is searched for C:\Logs\????:*:?? * Log.txt
C:\Logs\%S\%Y:%M:%D Log.txt is searched for C:\Logs\--DomainName--
\????:*:?? Log.txt
```

The following wildcards can be used for log variables:

%D --> ??

%N --> ??

%M --> \*

%Y --> ????

%X --> ??

%S --> \*

Anything matching the path name you used wildcards for can be purged. Use caution: it is best practice to place log files into a single directory to avoid unexpected file deletion.

### **Specifying IP addresses exempt from logging**

You can specify IP addresses that are exempt from logging. Activity from these IP addresses is not logged to the location specified by the rule: the Screen, a File, or both. This is useful to exempt IP addresses for administrators that may otherwise generate a significant amount of logging information that can obfuscate domain activity from regular users. It can also be used to save log space and reduce overhead. Click **Do Not Log IPs**, and then add IP addresses as appropriate.



# Chapter 5: Users

## About user accounts

A user account is required in order to provide access to the file server. At its most basic level, a user account defines login credentials (that is, login ID and password), a home directory, and a set of directory access rules that define the areas of the system that are accessible to the user, and the actions the user can perform in those locations. Each active session on the file server has a user account associated with it that identifies the client to the administrator.

User accounts can be defined in various ways on the Serv-U File Server, including the following:

### **Domain Users**

Defined at the domain level, domain users can only log in to the domain under which they are created.

### **Global Users**

Defined at the server level, global users can log in to any domain on the file server.

### **Database Users**

Available at both the server and domain level, database users are stored in an external database accessible through ODBC and supplement the local account database.

### **Windows Users**

Defined at the domain level, Windows users use the credentials and often, the home directories, of Windows accounts from the local machine or Windows domain controller (including Active Directory). Windows users only work on Windows, and require a Serv-U MFT Server license.

### **LDAP Users**

Defined at the domain level, LDAP users use the credentials and often, the email and other attributes, of LDAP accounts from a remote LDAP server. Unlike Windows users, LDAP users work on both Windows and Linux, and may access LDAP servers, including Active Directory and OpenLDAP, in any accessible domain. LDAP users require a Serv-U MFT Server license.

Because user accounts can be assigned at the various levels with the same login ID, a hierarchy is used by Serv-U to determine which account takes precedence. The user account types listed previously are listed in the order of precedence. Where user accounts can be specified at both the domain and server levels, the domain level account always takes precedence over the server one.

When you create users, consider what kind of access they need, and select the appropriate location for the user account accordingly. You can save time and effort by entering such settings at the server level to remove the need for multiple user accounts at the domain level.

In Serv-U MFT Server, you can organize user accounts into collections to make account management more logical and organized. This can be useful when you manage all users from a department or physical location. For example, you can place all users in the accounting department in a collection named `Accounting`, or place all users at an office in Topeka in a collection named `Topeka Users`.

To create a collection, click **Add** in the **Select user collection** area in the users window. In the new window, type the name of your collection, and then click **Save**. You can add users to this new collection by selecting them and clicking **Add** below the user list. To move a user from one collection to another, click **Move** below the user list, and then select the destination collection for the highlighted user accounts. You can also rename or delete collections by using the appropriate button.

**Warning:** When deleting a collection, all user accounts contained in that collection are deleted, too. If you want to keep the user accounts, make sure you move them before deleting the collection.

By default, all users are created in the **General** user collection.

## **New User Wizard**

Click **Wizard** on the Users page to open the New User Wizard. The New User Wizard walks you through the four steps required to create a user account with the minimum number of required attributes. After it is created, you can edit the user account to configure more advanced settings, such as group membership or additional directory access rules. For more information about using the New User Wizard, see the Quick start guide

## **User Template**

While the New User Wizard provides a way to quickly create a user account with the minimum number of required attributes, most File Server administrators have a collection of settings that they want all user accounts to abide by. Groups are the best way to accomplish this task, however, there are times when it may not be the course of action you want.

Serv-U allows an administrator to configure a template for new user accounts by clicking **Template**. Once opened, the template user can be configured just like any other user account, with the exception of a login ID. After these settings are saved to the template, all new user accounts that are manually created are done so with their default settings set to those found within the template.

## **Copying user accounts**

User templates offer a way for large numbers of users to be created with the same settings. In cases where only the settings of a single user must be duplicated or there is a need for multiple user templates, use **Copy** to create a copy of a user account that only lacks the user name and the password. To copy a user, select the user account, and then choose **Copy**.

## **Recovering passwords**

Serv-U supports password recovery both through the Management Console and through the Web Client. For password recovery to be available, you must configure the SMTP options for the server or domain, and the user account must have an email address listed. To use password recovery from the Management Console, select a user account, and then click **Recover Password**. If the

password is stored using one-way encryption, the password will be reset and the new password will be sent to the user's email address. If the password is stored using two-way encryption or no encryption, the original password will be sent by email.

Password Recovery from the Web Client requires that the **Allow users to recover password** limit be enabled for the user account. Once this option is enabled, users can use the Recover Password option in the Web Client. Password Recovery from the Web Client otherwise works the same as from the Management Console.

### Importing and exporting user accounts

User accounts can be imported and exported using the **Import** and **Export** options. Click **Export** to export all users in either the current domain/server or the current Collection to a comma-separated values file (CSV file), which can be viewed in Excel and analyzed by database engines, among other things. Additionally, by creating a CSV file using the same format as the export it is possible to import lists of users from CSV files into Serv-U.

### Filtering user and group ID lists

In larger deployments of Serv-U, the user list can grow very large. In order to easily find a specific user account, you can filter user and group lists by login ID using input from the administrator. The following wildcards are also supported:

- Use the "\*" parameter to filter for Users or Group login IDs when the whole ID is unknown (for example, \*Department, \*Admin\*, Tech\*).
- Use the "?" parameter when a specific character is unknown (for example, ????Lastname, Firstname???).
- Use the "[]" parameter when a specific character is unknown but should contain one of the specified characters in the brackets (for example, [utr]sername, User[fmn]ame).

## User Information

A user account consists of several attributes and settings. The User Information

page contains general information about the user account including login credentials, the home directory, and the type of account. This topic provides detailed information about each attribute.

### Login ID

The login ID is provided by the client as one part of authenticating the session to the file server. In addition to the login ID, clients must provide a password to complete authentication. Login IDs must be unique for each account specified at the particular level. Login IDs cannot contain any of the following special characters:

\\ / < > | : . ? \*

**Note:** Two special login IDs exist: `Anonymous` and `FTP`. These login IDs are synonymous with one another, and they can be used for guests on your file server. These users do not require a password, which should be left blank in this case. Instead, Serv-U requires users who log on with one of these accounts to provide their email address to complete the login process.

### Full name

The full name of the account is available to specify additional identifying information about the account. It is not used by clients when they log in.

### Password

The password is the second item that is required so that a session can be authenticated with the file server. The password should be kept a secret and not shared with anyone other than the person that owns the account. A strong password contains at least six characters including a mix of upper and lowercase letters and at least one number. You can place restrictions on the length and complexity of passwords through limits. For more information about password limits, see "Limits and settings".

You can also generate a new random password for a user by clicking the **Lock** icon next to the **Password**. This new password will follow the defined password length requirements. By default, all passwords are eight characters long and are complex. If the minimum password length is equal to or less than four characters,

the password will be four characters long. Otherwise, generated passwords will follow the specified domain value.

### **Administration privilege**

A user account can be granted one of the following types of administrative privileges:

- No Privilege
- Group Administrator
- Domain Administrator
- System Administrator

The value of this attribute can be inherited through group membership. A user account with No Privilege is a regular user account that can only log in to transfer files to and from the File Server. The Serv-U Management Console is not available to these user accounts.

A Group Administrator can only perform administrative duties relating to their primary group (the group that is listed first in their Groups memberships list). They can add, edit, and delete users which are members of their primary group, and they can also assign permissions at or below the level of the Group Administrator. They may not make any other changes.

A Domain Administrator can only perform administrative duties for the domain to which their account belongs. A Domain Administrator is also restricted from performing domain-related activities that may affect other domains. The domain-related activities that may *not* be performed by Domain Administrators consist of configuring their domain listeners or configuring ODBC database access for the domain.

A System Administrator can perform any file server administration activity including creating and deleting domains, user accounts, or even updating the license of the file server. A user account with System Administrator privileges that

is logged in through HTTP remote administration can administer the server as if they had physical access to the server.

You can also create read-only administrator accounts which can allow administrators to log in and view configuration options at the domain or server level, greatly aiding remote problem diagnosis when working with outside parties. Read-only administrator privileges are identical to their full-access equivalents, except that they cannot change any settings, and cannot create, delete or edit user accounts.

**Note:** When you configure a user account with administrative privileges, take care in specifying their home directory. An administrator with a home directory other than "\\" (root) that is locked in their home directory may not use file paths outside of their home directory when configuring the file server.

### Home directory

The home directory for a user account is where the user is placed immediately after logging in to the file server. Each user must have a home directory assigned to it, although it can be specified at the group level if the user is a member of a group. Home directories must be specified using a full path including the drive letter or the UNC share name. If the home directory is not found, you can configure Serv-U to create it.

When you specify the home directory, you can use the `%USER%` macro to insert the login ID in to the path. This is used mostly to configure a default home directory at the group level or within the new user template to ensure that all new users have a unique home directory. When it is combined with a directory access rule for `%HOME%`, a new user can be configured with a unique home directory and the appropriate access rights to that location with a minimal amount of effort.

You can also use the `%DOMAIN_HOME%` macro to identify the user's home directory. For example, to place a user's home directory into a common location, use

`%DOMAIN_HOME%\%USER%`.

The home directory can be specified as "/" (root) in order to grant system-level access to a user, allowing them the ability to access all system drives. In order for this to work properly, the user must not be locked in their home directory.

### SSH public key path

The SSH public key can be used to authenticate a user when logging in to the the Serv-U File Server. The public key path should point to the key file in a secured directory on the server. This path can include the following macros:

#### %HOME%

The home directory of the user account.

#### %USER%

The login ID, used if the public key will have the login ID as part of the file name.

#### %DOMAIN\_HOME%

The home directory of the domain, set in **Domain Details > Settings**, used if the keys are in a central folder relative to the domain home directory.

Examples:

```
%HOME%\SSHpublic.pub
```

```
%HOME%\%USER%.pub
```

```
%DOMAIN_HOME%\SSHKeys\%USER%.pub
```

For information about creating an SSH key pair, see "SFTP (Secure File Transfer over SSH2) for users and groups".

### Account type

By default, all accounts are permanent and exist on the file server until they are manually deleted or disabled. You can configure an account to be automatically disabled or even deleted on a specified date by configuring the account type. After selecting the appropriate type, the **Account Expiration Date** control is displayed. Click the calendar or expiration date to select when the account should be disabled or deleted.



### **Default Web Client**

If your Serv-U license enables the use of FTP Voyager JV, then users connecting to the file server through HTTP can choose which client they want to use after logging in. Instead of asking users which client they want to use, you can also specify a default client. If you change this option, it overrides the option specified at the server or domain level. It can also be inherited by a user through group membership. Use the **Inherit default value** option to reset it to the appropriate default value.

### **Email address**

Serv-U events can use the **Email Address** field when sending email notifications to groups, and password recovery using the Web Client requires an email address to send a recovered password to a user. Type an email address here to allow email notifications or password recovery for the user account.

### **Lock user in home directory**

Users locked in their home directory may not access paths above their home directory. In addition, the actual physical location of their home directory is masked because Serv-U always reports it as "/" (root). The value of this attribute can be inherited through group membership.

### **Enable account**

Deselect this option to disable the current account. Disabled accounts remain on the file server but cannot be used to log in. To re-enable the account, select the **Enable account** option again.

### **Always allow login**

Enabling this option means that the user account is always permitted to log in, regardless of restrictions placed upon the file server, such as maximum number of sessions. It is useful as a fail-safe in order to ensure that critical system administrator accounts can always remotely access the file server. As with any option that allows bypassing access rules, care should be taken in granting this ability. The value of this attribute can be inherited through group membership.

**Note:** Enabling the Always Allow Login option does not override IP access rules. If both options are defined, the IP access rules prevail.

### Description

The description allows for the entry of additional notes that are only visible to administrators.

### Availability

This feature limits when users can connect to this server. You can place limitations on the time of day, and also on the day of the week. When users attempt to log in outside the specified available times, they are presented with a message that their user account is currently unavailable.

### Welcome message

The welcome message is a message that is traditionally sent to the FTP client during a successful user login. Serv-U extends this ability to HTTP so that users accessing the file server through the Web Client or FTP Voyager JV also receive the welcome message. This feature is not available to users logging in through SFTP over SSH2, because SSH2 does not define a method for sending general text information to users.

The welcome message can contain general information about the status of the server, a special message for the user, disclaimers, or other legal notices. You can configure a welcome message in one of two ways. The first method involves specifying the path to a file containing the welcome message in the **Message File Path** field. Use **Browse** to select an existing file on the system.

As an alternative, the text of the welcome message can be explicitly provided to Serv-U in the appropriate text field. In order to override an explicit welcome message at the user level, select the **Override inherited group welcome message** option first. The provided text is then sent to the user instead of the contents of the file specified in the **Message File Path** field.

These values can be inherited by the user through group membership.

You can also use system variables in the welcome message. For a comprehensive list of system variables, see "System variables".

## Directory access rules

### Directory access rules

Directory access rules define the areas of the system which are accessible to user accounts. While traditionally restricted to the user and group levels, in Serv-U, the usage of directory access rules is extended to both the domain and the server levels through the creation of global directory access rules. Directory access rules specified at the server level are inherited by all users of the file server. If they are specified at the domain level, they are only inherited by users who belong to the particular domain. The traditional rules of inheritance apply where rules specified at a lower level (for example, the user level) override conflicting or duplicate rules specified at a higher level (for example, the server level).

When you set the directory access path, you can use the `%USER%`, `%HOME%`, `%USER_FULL_NAME%`, and `%DOMAIN_HOME%` variables to simplify the process. For example, use `%HOME%/ftproot/` to create a directory access rule that specifies the `ftproot` folder in the home directory of the user. Directory access rules specified in this manner are portable if the actual home directory changes while maintaining the same subdirectory structure. This leads to less maintenance for the file server administrator. If you specify the `%USER%` variable in the path, it is replaced with the user's login ID. This variable is useful in specifying a group's home directory to ensure that users inherit a logical and unique home directory. You can use the `%USER_FULL_NAME%` variable to insert the Full Name value into the path (the user must have a Full Name specified for this to function). For example, the user "Tom Smith" could use `D:\ftproot\%USER_FULL_NAME%` for `D:\ftproot\Tom Smith`. You can also use the `%DOMAIN_HOME%` macro to identify the user's home directory. For example, to place a user and their home directory into a common directory, use `%DOMAIN_HOME%\%USER%`.

Directory access rules are applied in the order they are listed. The first rule in the list that matches the path of a client's request is the one that is applied for that rule. In other words, if a rule exists that denies access to a particular subdirectory but is listed *below* the rule that grants access to the parent directory, then a user still has access to the particular subdirectory. Use the arrows on the right of the directory access list to rearrange the order in which the rules are applied.

The following section contains the list and description of the directory access permissions.

### File permissions

#### Read

Allows users to read (that is, download) files. This permission does not allow users to list the contents of a directory, which is granted by the **List** permission.

#### Write

Allows users to write (that is, upload) files. This permission does not allow users to modify existing files, which is granted by the **Append** permission.

#### Append

Allows users to append data to existing files. This permission is typically used to grant users the ability to resume transferring partially uploaded files.

#### Rename

Allows users to rename existing files.

#### Delete

Allows users to delete files.

#### Execute

Allows users to remotely execute files. The execute access is meant for remotely starting programs and usually applies to specific files. This is a very powerful permission and great care should be used in granting it to users. Users with **Write** and **Execute** permissions can install any program they want on the system.

## Directory permissions

### List

Allows users to list the files and subdirectories contained in the directory. Also allows users to list this folder when listing the contents of a parent directory.

### Create

Allows users to create new directories within the directory.

### Rename

Allows users to rename existing directories within the directory.

### Remove

Allows users to delete existing directories within the directory.

**Note:** If the directory contains files, the user also needs to have the **Delete** files permission in order to remove the directory.

## Subdirectory permissions

### Inherit

Allows all subdirectories to inherit the same permissions as the parent directory. The **Inherit** permission is appropriate for most circumstances, but if access must be restricted to subfolders (as is the case when implementing mandatory access control), clear the **Inherit** check box and grant permissions specifically by folder.

### Advanced: Access as Windows User (Windows Only)

For a variety of reasons, files and folders may be kept on external servers in order to centralize file storage or provide additional layers of security. In this environment, files can be accessed by the UNC path (`\\servername\folder\`) instead of the traditional `C:\ftproot\folder` path. However, accessing folders stored across the network poses an additional challenge, because Windows services are run under the Local System account by default, which has no access to network resources.

To mitigate this problem for all of Serv-U, you can configure the Serv-U File Server service to run under a network account. The alternative, preferred when many servers exist, or if the Serv-U File Server service has to run under Local System for security reasons is to configure a directory access rule to use a specific Windows user for file access. By clicking the **Advanced** button, you can specify a specific Windows user for each individual directory access rule. As in Windows authentication, directory access is subject to NTFS permissions, and in this case also to the configured permissions in Serv-U.

**Note:** When you use Windows authentication, the NTFS permissions of the Windows user take priority over the directory access rules. This means that when a Windows user tries to access a folder, the security permissions of the user are applied instead of the credentials specified in the directory access rule.

### Quota permissions

#### Maximum size of directory contents

Setting the maximum size actively restricts the size of the directory contents to the specified value. Any attempted file transfers that cause the directory contents to exceed this value are rejected. This feature serves as an alternative to the traditional quota feature that relies upon tracking all file transfers (uploads and deletions) to calculate directory sizes and is not able to consider changes made to the directory contents outside of a user's file server activity.

#### Mandatory access control

You can use mandatory access control (MAC) in cases where users need to be granted access to the same home directory but should not necessarily be able to access the subdirectories below it. To implement mandatory access control at a directory level, disable the **Inherit** permission as shown in the following screen capture. In the following example, the rule applies to `D:\ftproot\`.

Directory Access Rule

Path:  

**Files**

- ☒ Read
- ☒ Write
- ☒ Append
- ☒ Rename
- ☒ Delete
- ☐ Execute 

**Directories**

- ☒ List
- ☒ Create
- ☒ Rename
- ☒ Remove

**Subdirectories**

☐ Inherit

Maximum size of directory contents:  MB (leave blank for no limit)

Now, the user has access to the `ftproot` folder but to no folders below it. Permissions must individually be granted to subfolders that the user needs access to, providing the security of mandatory access control in the Serv-U File Server.

### Restricting file types

If users are using storage space on the Serv-U File Server to store non-work-related files, such as MP3 files, you can prevent this by configuring a directory access rule placed *above* the main directory access rule to prevent MP3 files from being transferred as shown below. In the text entry for the rule, type `*.mp3`, and use the permissions shown in the following screen capture:

## Chapter 5: Users

---

The screenshot shows the 'Directory Access Rule' dialog box. At the top is a title bar with a blue icon and the text 'Directory Access Rule', and a close button (X) on the right. Below the title bar is a 'Path:' label followed by a text input field and a folder icon button. To the right of the path field are three buttons: 'Save', 'Cancel', and 'Help'. Below the path field are two columns of permissions. The 'Files' column has checkboxes for 'Read', 'Write', 'Append', 'Rename', 'Delete', and 'Execute' (which has a yellow warning triangle next to it). The 'Directories' column has checkboxes for 'List', 'Create', 'Rename', and 'Remove'. To the right of these columns are two buttons: 'Full Access' and 'Read Only'. Below the permissions columns is a 'Subdirectories' section with a checkbox labeled 'Inherit' that is checked. To the right of this is a label 'Maximum size of directory contents:' followed by a text input field and the text 'MB (leave blank for no limit)'. At the bottom right is an 'Advanced >>' button.

Directory Access Rule

Path:

Save

Cancel

Help

Full Access

Read Only

Files

Read

Write

Append

Rename

Delete

Execute

Directories

List

Create

Rename

Remove

Subdirectories

☒ Inherit

Maximum size of directory contents:

MB (leave blank for no limit)

Advanced >>

The rule denies permission to any transfer of files with the `.mp3` extension and can be modified to reflect any file extension. Similarly, if accounting employees only need to transfer files with the `.mdb` extension, configure a pair of rules that grants permissions for `.mdb` files but denies access to all other files, as shown in the following screen captures. In the first rule enter the path that should be the user's home directory or directory they need access to, and in the second rule enter the extension of the file that should be accessed (such as `*.mdb`).



Directory Access Rule

Path:

Save

Cancel

Files


☐ Read

☐ Write

☐ Append

☐ Rename

☐ Delete

☐ Execute 

Directories

☒ List

☐ Create

☐ Rename

☐ Remove

Subdirectories

☒ Inherit

Maximum size of directory contents:

MB (leave blank for no limit)

Advanced >>

Help

Full Access

Read Only

Directory Access Rule

Path:

Save

Cancel

Files

☒ Read

☒ Write

☒ Append

☒ Rename

☒ Delete

☐ Execute 

Directories

☒ List

☐ Create

☐ Rename

☐ Remove

Subdirectories

☒ Inherit

Maximum size of directory contents:

MB (leave blank for no limit)

Advanced >>

Help

Full Access

Read Only

These rules only allow users to access `.mdb` files within the specified directories. You can adapt these rules to any file extension or set of file extensions.

### Virtual paths

If virtual paths are specified, users can gain access to files and folders outside of their own home directory. A virtual path only defines a method of mapping an existing directory to another location on the system to make it visible within a user's accessible directory structure. In order to actually have access to the mapped location, the user must still have a directory access rule specified for the physical path of a virtual path.

Like directory access rules, virtual paths can be configured at the server, domain, group, and user levels. Virtual paths created at the server level are available for all users of the file server. When virtual paths are created at the domain level, they are only accessible by users belonging to that domain. You can also create virtual paths specifically for individual users or groups.

### Physical path

The physical path is the actual location on the system, or network, that is to be placed in a virtual location accessible by a user. If the physical path is located on the same computer, use a full path, such as `D:\inetpub\ftp\public`. You can also use a UNC path, such as `\\Server\share\public`. To make a virtual path visible to users, users must have a directory access rule specified for the physical path.

### Virtual path

The virtual path is the location that the physical path should appear in for the user. The `%HOME%` macro is commonly used in the virtual path to place the specified physical path in the home directory of the user. When specifying the virtual path, the last specified directory is used as the name displayed in directory listings to the user. For example, a virtual path of `%HOME%/public` places the specified physical path in a folder named `public` within the user's home directory. You can also use a full path without any macros.

### Including virtual paths in "Maximum Directory Size" calculations

When this option is selected, the virtual path is included in Maximum Directory

Size calculations. The Maximum Directory Size limits the size of directories affecting how much data can be uploaded.

### Case File: Using virtual paths

A group of web developers have been granted access to the directory `D:\ftproot\example.com\` for web development purposes. The developers also need access to an image repository located at `D:\corpimages\`. To avoid granting the group access to the root D drive, a virtual path must be configured so that the image repository *appears* to be contained within their home directory. Within the group of web developers, add a virtual path to bring the directory to the users by specifying `D:\corpimages\` as the physical path and `D:\ftproot\example.com\corpimages` as the virtual path. Be sure to add a group level directory access rule for `D:\corpimages\` as well. The developers now have access to the image repository without compromising security or relocating shared resources.

### Case File: Creating relative virtual paths

Continuing with the previous example, if the home directory of the group of web developers is relocated to another drive, both the home directory and the virtual path need to be updated to reflect this change. You can avoid this by using the `%HOME%` macro to create a relative virtual path location that eliminates the need to update the path if the home directory changes. Instead of using `D:\ftproot\example.com\corpimages` as the virtual path, use `%HOME%\corpimages`. This way the `corpimages` virtual path is placed within the home directory of the group, regardless of what the home directory is. If the home directory changes at a later date, the virtual path still appears there.

## Configuring user and group logs

In the Serv-U File Server, you can customize the logging of user and group events and activity to a great extent. To enable a logging option, select the appropriate option in the **Log Message Options** grouping. When an option is selected, the appropriate logging information is saved to the specified log file if

the **Enable logging to file** option is selected. You can configure the log to show as much or as little information as you want. After configuring the logging options you want, click **Save** to save the changes.

### Logging to File Settings

#### Log file path

You must specify the name of the log file before information can be saved to a file. Click **Browse** to select an existing file or directory location for the log file. The log file path supports certain wildcard characters. Wildcard characters which refer to the date apply to the day that the log file is created. When combined with the **Automatically rotate log file** option, wildcards provide an automatic way to archive activity for audits. The following list contains the wildcard characters that you can use:

#### %H

The hour of the day (24-hour clock).

#### %D

The current day of the month.

#### %M

The name of the current month.

#### %N

The numeric value of the current month (1-12).

#### %Y

The 4-digit value of the current year (for example, 2014).

#### %X

The 2-digit value of the current year (for example, 14 for 2014).

#### %S

The name of the domain whose activity is being logged.

#### %G

The name of the group whose activity is being logged.

## %L

The name of the login ID whose activity is being logged.

## %U

The full name of the user whose activity is being logged.

## Enable logging to file

Select this option to enable Serv-U to begin saving log information to the file that you specified in the **Log file path**. If this option is not selected, Serv-U does not log any information to the file, regardless of the individual options selected in the **Log Message Options** area.

## Automatically rotating the log file

To ensure that log files remain a manageable size and can be easily referenced during auditing, you can automatically rotate the log file on a regular basis. By specifying a **Log file path** containing wildcards that reference the current date, Serv-U can rotate the log file and create a unique file name every hour, day, week, month, or year.

## Purging old log files

You can automatically purge old log files by setting a maximum number of files to keep, a maximum size limit in megabytes, or both. Setting these options to "0" means that the setting is unlimited and the limit is not applied.

**Warning:** Log files are purged based only on the current log file path name, and they are purged approximately every 10 minutes. Log file variables are replaced with Windows wildcard values used to search for matching files. For example:

```
C:\Logs\%Y:%N:%D %S Log.txt is searched for C:\Logs\????:??:?? * Log.txt
C:\Logs\%Y:%M:%D %S Log.txt is searched for C:\Logs\????:*:?? * Log.txt
C:\Logs\%S\%Y:%M:%D Log.txt is searched for C:\Logs\--DomainName--
\????:*:?? Log.txt
C:\Logs\%G\%Y:%M:%D Log.txt is searched for C:\Logs\--GroupName--\????:*:??
Log.txt
C:\Logs\%L\%Y:%M:%D Log.txt is searched for C:\Logs\--LoginID--\????:*:??
```

## Chapter 5: Users

---

Log.txt

C:\Logs\%U\%Y:%M:%D Log.txt is searched for C:\Logs\--UserFullName--  
\?????:\*:\*? Log.txt

The following wildcards can be used for log variables:

%H --> ??

%D --> ??

%N --> ??

%M --> \*

%Y --> ????

%X --> ??

%S --> \*

%G --> \*

%L --> \*

%U --> \*

Anything matching the path name you used wildcards for can be purged. Use caution: it is best practice to place log files into a single directory to avoid unexpected file deletion.

### Specifying IP addresses exempt from logging

You can specify IP addresses that are exempt from logging. Activity from these IP addresses is not logged. This is useful to exempt IP addresses for administrators that may otherwise generate a lot of logging information that can obfuscate domain activity from regular users. It can also be used to save log space and reduce overhead. Click **Do Not Log IPs**, and then add IP addresses as appropriate.


## Group memberships

A user can be a member of any number of groups. Groups provide a convenient way of applying a base set of user attributes and settings to multiple users. For more information about configuring groups, see "About groups".

Because a user can be a member of multiple groups, the order in which group memberships are presented is important. The first group membership for a user encountered by Serv-U that provides a value for an attribute is the value that is used. Use the arrows on the right side of the group membership list to arrange the order of group memberships.

Use the left arrow buttons to add additional group memberships to the user, or use the right arrow buttons to remove the user from the selected groups.

## Serv-U events



The screenshot shows the 'Events' configuration window in Serv-U. The window has a title bar with a close button. Inside, there are two tabs: 'Events' and 'Event Filters'. The 'Events' tab is active. It contains two main sections: 'Event Information' and 'Event Actions'. In the 'Event Information' section, 'Event Type' is set to 'File Uploaded', 'Event Name' is 'Event 01', and 'Enable event' is checked. The 'Description' field contains the text 'Show balloon tip when users upload a file.' In the 'Event Actions' section, 'Action' is set to 'Show Balloon Tip', 'Balloon Title' is '"\$name" Has Uploaded A File.', and 'Balloon Information' contains a list of variables: '\$LocalPathName', 'Size: \$FileSizeFmt bytes (\$FileSize KB KB)', '\$TransferBytes bytes transferred.', '\$TransferKBPerSecond KB/sec.', and 'Protocol: \$Protocol'. At the bottom of the window are three buttons: 'Save', 'Cancel', and 'Help'.

Events

Event Information

Event Type:  
File Uploaded

Event Name:  
Event 01

☒ Enable event

Description:  
Show balloon tip when users upload a file.

Event Actions

Action:  
Show Balloon Tip

Balloon Title:  
"\$name" Has Uploaded A File.

Balloon Information:  
\$LocalPathName  
Size: \$FileSizeFmt bytes (\$FileSize KB KB)  
\$TransferBytes bytes transferred.  
\$TransferKBPerSecond KB/sec.  
Protocol: \$Protocol

Save Cancel Help

In Serv-U, you can use event handling which can perform various actions triggered by a list of selected events. The following list contains the available actions:



## **Server events**

### **Server Start**

Triggered by Serv-U starting up, whether by starting the Serv-U service or starting Serv-U as an application.

### **Server Stop**

Triggered by Serv-U shutting down, whether from service or application-level status. This event only triggers for graceful stops.

## **Server and domain events**

### **Domain Start**

Triggered by a Serv-U domain starting, through the **Enable Domain** setting in the **Domain Details > Settings** menu, or as part of normal server startup.

### **Domain Stop**

Triggered by a Serv-U domain stopping, through the **Enable Domain** setting in the **Domain Details > Settings** menu, or as part of normal server startup.

### **Session Connection**

Triggered by a new TCP session connection.

### **Session Disconnect**

Triggered by a TCP session disconnection.

### **Session Connection Failure**

Triggered by a failed session connection attempt.

### **Log File Deleted**

Triggered by the automatic deletion of a log file, according to logging settings.

### **Log File Rotated**

Triggered by the automatic rotation of a log file, according to logging settings.

**Listener Success**

Triggered by a successful listener connection.

**Listener Stop**

Triggered by a stopped listener connection.

**Listener Failure**

Triggered by a failed listener connection.

**Gateway Listener Success**

Triggered by a successful gateway listener connection.

**Gateway Listener Stop**

Triggered by a stopped gateway listener connection.

**Gateway Listener Failure**

Triggered by a failed gateway listener connection.

**Permanent Listener Success**

Triggered by a successful permanent listener connection.

**Permanent Listener Failure**

Triggered by a failed permanent listener connection.

**Permanent Listener Stop**

Triggered by a stopped permanent listener connection.

**Permanent Gateway Listener Success**

Triggered by a successful permanent gateway listener connection.

**Permanent Gateway Listener Stop**

Triggered by a stopped permanent gateway listener connection.

**Permanent Gateway Listener Failure**

Triggered by a failed permanent gateway listener connection.

**File Management Rule Success**

Triggered when a file management rule is applied, and no errors are encountered.

### **File Management Rule Failure**

Triggered when a file management rule is applied, and at least one error is encountered.

### **Server, domain, user and group events**

#### **User Login**

Triggered by the login of a user account.

#### **User Logout**

Triggered by the logout of a user account.

#### **User Login Failure**

Triggered by a failed login. A failed login is any connection attempt to Serv-U that fails, whether due to invalid credentials, or a session disconnect before authentication, either due to an incorrect user name, incorrect password, incorrect SSH key pair (for SFTP public key authentication), or any or all of the above.

#### **User Password Change**

Triggered by the change of a password for a user account by the user (if permitted).

#### **User Password Change Failure**

Triggered by a failed password change attempt.

#### **User Enabled**

Triggered by the enabling of a user account that was previously disabled.

#### **User Disabled**

Triggered by the disabling of a user account that was previously enabled.

#### **User Deleted**

Triggered by the deletion of a user account by a remote administrator, in an ODBC database, or in the local Management Console.

### **User Added**

Triggered by the creation of a user account by a remote administrator, in an ODBC database, or in the local Management Console.

### **Password Recovery Sent**

Triggered by a successful password recovery by an end user.

### **Password Recovery Failed**

Triggered by a failed password recovery attempt, either due to lack of email address in the user account or lack of permissions.

### **Password Stale**

Triggered by a stale password, as configured in **Limits & Settings**, that is going to expire.

### **User Auto Disable**

Triggered by the automatic disabling of a user account, as configured by a user's **Automatically Disable** date.

### **User Auto Deleted**

Triggered by the automatic deletion of a user account, as configured by a user's **Automatically Delete** date.

### **User Pre-disable**

Triggered by the upcoming disabling of a user account, as configured in the user's **Automatically Disable** date and the "Days before automatically disabling account to trigger the pre-disable event" limit.

### **User Pre-delete**

Triggered by the upcoming deletion of a user account, as configured in the user's **Automatically Delete** date and the **Days before automatically deleting account to trigger the pre-delete** event limit.

### **User Email Set**

Triggered by a user setting the email address for a user account.

### **User Email Set Failure**

Triggered by a failed attempt by a user to set the email address for a user account.

### **IP Blocked**

Triggered by a failed login attempt due to an IP access rule.

### **IP Blocked Time**

Triggered by a failed login attempt due to an IP access rule that was automatically added by brute force settings, configured in **Domain Limits & Settings** or **Server Limits & Settings**.

### **Too Many Sessions**

Triggered by more sessions logging on to the server than are permitted, per the **Limits & Settings** for the user account, group, domain, or server.

### **Too Many Session On IP**

Triggered by more sessions logging on to the server from a specific IP address than are permitted, according to the **Limits & Settings** for the user account, group, domain, or server.

### **IP Auto Added To Access Rules**

Triggered by the automatic addition of an IP access rule due to a user triggering the "brute force" settings.

### **Session Idle Timeout**

Triggered by an idle session timeout.

### **Session Timeout**

Triggered by a session timeout.

### **File Uploaded**

Triggered by a file uploaded to Serv-U. This event triggers for partial uploads if the upload session terminated with a successful message and no data corruption.

### **File Upload Failed**

Triggered by a failed file upload to Serv-U.

### **File Download**

Triggered by a file downloaded from Serv-U.

### **File Download Failed**

Triggered by a failed file download from Serv-U.

### **File Deleted**

Triggered by the deletion of a file on the Serv-U server by a user.

### **File Moved**

Triggered by the moving of a file on the Serv-U server by a user.

### **Directory Created**

Triggered by the creation of a directory.

### **Directory Deleted**

Triggered by the deletion of a directory.

### **Directory Changed**

Triggered by changing the current working directory.

### **Directory Moved**

Triggered by moving a directory to a new location.

### **Over Quota**

Triggered by going over disk quota space. The current quota space is shown in the user account, in the **Limits & Settings** menu.

### **Over Disk Space**

Triggered by exceeding the Max Dir Size configured for a directory access rule. The current disk space is shown with the **AVBL FTP** command, or by using the **Directory Properties** option in the HTTP or HTTPS Web Client and FTP Voyager JV.

### **Creating common events**

You can automatically create a list of the most common events. You can choose to create these common events using email or balloon tip actions. Click **Create Common Event** in the Events page. Select either the **Send Email** or **Show**

**balloon tip** option for the action you want to perform on the common events. If you choose to send email, also enter an email address where the events are to be sent.

**Note:** The **Write to Windows Event Log** and **Write to Microsoft Message Queue (MSMQ)** options are available for Windows only.

### Using event actions

You can select from the following actions that will be executed when an event is triggered:

- Send Email
- Show Balloon Tip\*
- Execute Command\*
- Write to Windows Event Log (Windows only)\*
- Write to Microsoft Message Queue (MSMQ) (Windows only)\*

\* Events involving anything other than email can only be configured by Serv-U server administrators.

### Using email actions

You can configure email actions to send emails to multiple recipients and to Serv-U groups when an event is triggered. To add an email address, enter it in the **To** or **Bcc** fields. To send emails to a Serv-U group, use the **Group** icon to add or remove Serv-U groups from the distribution list. Separate email addresses by commas or semicolons. Email actions contain a **To**, **Subject** and **Message** parameter. You can use special variables to send specific data pertaining to the event. For more information about the variables, see "System variables".

To use email actions, you must first configure SMTP in Serv-U. For information about SMTP configuration, see "Serv-U SMTP configuration".

### Using balloon tip actions

You can configure balloon tip actions to show a balloon tip in the system tray when an event is triggered. Balloon tip actions contain a **Balloon Title** and a

**Balloon Message** parameter. You can use special variables to send specific data pertaining to the event. For more information about the variables, see "System variables".

### Using execute command actions

You can configure execute command actions to execute a command on a file when an event is triggered. Execute command actions contain an **Executable Path**, **Command Line Parameters**, and a **Completion Wait Time** parameter. For the **Completion Wait Time** parameter, you can enter the number of seconds to wait after starting the executable path. Enter zero for no waiting.

**Note:** Any amount of time Serv-U spends waiting delays any processing that Serv-U can perform.

A wait value should only be used to give an external program enough time to perform some operation, such as move a log file before it is deleted (for example, `$LogFilePath` for the Log File Deleted event). You can use special variables to send specific data pertaining to the event. For more information about the variables, see "System variables".

### Writing to the Windows Event Log

By writing event messages to a local Windows Event Log, you can monitor and record Serv-U activity by using third-party network management software. All messages appear in the Windows Application Log from a source of "Serv-U".

This event has only one field:

- **Log Information:** The contents of the message to be written into the event log. This is normally either a human-readable message (for example, `filename uploaded by person`) or a machine-readable string (for example, `filename|uploaded|person`), depending on who or what is expected to read these messages. Serv-U system variables are supported in this field. This field can be left blank, but usually is not.

### Writing to Microsoft Queue (MSMQ)

Microsoft Message Queuing (MSMQ) is an enterprise technology that provides a



method for independent applications to communicate quickly and reliably. Serv-U can send messages to new or existing MSMQ queues whenever a Serv-U event is triggered. Corporations can use this feature to tell enterprise applications that files have arrived, files have been picked up, partners have signed on, or many other activities have occurred.

These events have the following two fields:

- **Message Queue Path:** The MSMQ path that addresses the queue. Remote queues can be addressed when a full path (for example, `MessageServer\Serv-U Message Queue`) is specified. Local, public queues on the local machine can be addressed when a full path is not specified (for example, `.\Serv-U Message Queue` or `Serv-U Message Queue`). If the specified queue does not exist, Serv-U attempts to create it. This normally only works on public queues on the local machine. You can also use Serv-U system variables in this field.
- **Message Body:** The contents of the message to be sent into the queue. This is normally a text string with a specific format specified by an enterprise application owner or enterprise architect. Serv-U system variables can also be used in this field. This field may be left blank, but usually is not.

**Note:** Microsoft message queues created in Windows do not grant access to SYSTEM by default, preventing Serv-U from writing events to the queue. To correct this, after creating the queue in MSMQ, right-click it, select **Properties**, and then set the permissions so that SYSTEM (or the network account under which Serv-U runs) has permission to the queue.

### Using event filters

By using Serv-U event filters, you can control to a greater degree when a Serv-U event is triggered. By default, Serv-U events trigger each time the event occurs. The event filter allows events to be triggered only if certain conditions are met. For example, a standard Serv-U event might trigger an email each time a file is uploaded to the server. However, by using an event filter, events can be triggered

on a more targeted basis. For example, you can configure a File Uploaded event to only send an email when the file name contains the string `important`, so an email would be sent when the file `Important Tax Forms.pdf` is uploaded but not when other files are uploaded to the server. Additionally, you can configure a File Upload Failed event to run only when the FTP protocol is used, not triggering for failed HTTP or SFTP uploads. You can do this by controlling the various variables and values related to the event and by evaluating their results when the event is triggered.

### Event filter fields

Each event filter has the following critical values that must be set:

- **Name:** This is the name of the filter, used to identify the filter for the event.
- **Description (Optional):** This is the description of the event, which may be included for reference.
- **Logic:** This determines how the filter interacts with other filters for an event. In most cases, AND is used, and all filters must be satisfied for the event to trigger. The function of AND is to require that all conditions be met. However, the OR operator can be used if there are multiple possible satisfactory responses (for example, abnormal bandwidth usage of less than 20 KB/s OR greater than 2000 KB/s).
- **Filter Comparison:** This is the most critical portion of the filter. The Filter Comparison contains the evaluation that must occur for the event to trigger. For example, a filter can be configured so that only the user "admin" triggers the event. In this case, the comparison will be `If $Name = (is equal to) admin`, and the data type will be `string`. For bandwidth, either an "unsigned integer" or "double precision floating point" value would be used.

Event filters also support wildcards when evaluating text strings. The supported wildcards are the following:

- **\*** - The asterisk wildcard matches any text string of any length. For example:
  - An event filter that compares the `$FileName` variable to the string `data*` matches files named `data`, `data7`, `data77`, `data.txt`, `data7.txt`, and

`data77.txt.`

- **?** - The question mark wildcard matches any one character, but only one character. For example:
  - An event filter that compares the `$FileName` variable to the string `data?` matches a file named `data7` but not `data`, `data77`, `data.txt`, `data7.txt`, or `data77.txt`.
  - An event filter that compares the `$FileName` variable to the string `data?.*` matches files named `data7` and `data7.txt` but not `data`, `data77`, `data.txt`, or `data77.txt`.
  - An event filter that compares the `$Name` variable to the string `A????` matches any five-character user name that starts with `A`.
- **[]** - The bracket wildcard matches a character against the set of characters inside the brackets. For example:
  - An event filter that compares the `$FileName` variable to the string `data[687].txt` matches files named `data6.txt`, `data7.txt` and `data8.txt` but not `data5.txt`.
  - An event filter that compares the `$LocalPathName` variable to the string `[CD]:\*` matches any file or folder on the `C:` or `D:` drives.


You can use multiple wildcards in each filter. For example:

- An event filter that compares the `$FileName` variable to the string `[cC]:\*.???` matches any file on the `C:` drive that ends in a three letter file extension.
- An event filter that compares the `$FileName` variable to the string `?:\*Red[678]\?????.*` matches a file on any Windows drive, contained in any folder whose name contains `Red6`, `Red7` or `Red8`, and that also has a five character file name followed by a file extension of any length.

## Using event filters


Event filters are used by comparing fields to expected values in the Event Filter

menu. The best example is raising an event only when a certain user triggers the action, or when a certain file is uploaded. For example, an administrator may want to raise an email event when the file `HourlyUpdate.csv` is uploaded to the server, but not when other files are uploaded. To do this, create a new event in the **Domain Details > Events** menu. The **Event Type** is File Uploaded, and on the Event Filter tab a new filter must be added. The `$FileName` variable is used and the value is `HourlyUpdate.csv` as shown in the following screen capture:



The screenshot shows a 'Filter Comparison' dialog box. At the top, there is a title bar with a funnel icon and the text 'Filter Comparison', and a close button (X). Below the title bar, there is a message: 'Comparisons must be added to the event filter to define the scenario that will allow or disallow the event.' To the right of this message are three buttons: 'Save', 'Cancel', and 'Help'. Below the message, there is a form with the following fields: 'If' (a dropdown menu), '\$FileName' (a text input), '= (is equal to)' (a dropdown menu), and 'HourlyUpdate.csv' (a text input). Below these fields is a 'Data Type:' section with a dropdown menu showing '(abcd) string'.

As another example, it might be necessary to know when a file transfer fails for a specific user account. To perform this task, create a new File Upload Failed event, and then add a new filter. The filter comparison is the `$Name` variable, and the value to compare is the user name, such as `ProductionLineFTP`:



The screenshot shows a 'Filter Comparison' dialog box. At the top, there is a title bar with a funnel icon and the text 'Filter Comparison', and a close button (X). Below the title bar, there is a message: 'Comparisons must be added to the event filter to define the scenario that will allow or disallow the event.' To the right of this message are three buttons: 'Save', 'Cancel', and 'Help'. Below the message, there is a form with the following fields: 'If' (a dropdown menu), '\$Name' (a text input), '= (is equal to)' (a dropdown menu), and 'ProductionLineFTP' (a text input). Below these fields is a 'Data Type:' section with a dropdown menu showing '(abcd) string'.

You can also filter for events based on specific folders, using wildcards. In some cases it may be necessary to trigger events for files uploaded only to a specific folder, such as when an accounting department uploads time-sensitive tax files. To filter based on a folder name, create a new File Uploaded event in the **Domain Details > Events** menu, and set it to **Send Email**. After specifying the

email recipients, subject line, and message content, open the Event Filters page. Create a new event filter, and add the filter comparison `If $LocalPathName = (is equal to) C:\ftproot\accounting\*` with the type of `(abcd) string`. This will cause the event to trigger only for files that are located within `C:\ftproot\accounting\`.

**Filter Comparison**

Comparisons must be added to the event filter to define the scenario that will allow or disallow the event.

If `$LocalPathName` = (is equal to) `C:\ftproot\accounting\*`

Data Type:  
(abcd) string

Save Cancel Help

## Server details

### IP access rules

IP access rules restrict login access to specific IP addresses, ranges of IP addresses, or a domain name. IP access rules can be configured at the server, domain, group, and user levels.

IP access rules are applied in the order they are displayed. In this way, specific rules can be placed at the top to allow or deny access before a more general rule is applied later on in the list. The arrows on the right side of the list can be used to change the position of an individual rule in the list.

### Specifying IP access masks

IP access rules use masks to authorize IP addresses and domain names. The masks can contain specific values, ranges, and wildcards made up of the following elements:

#### **xxx**

Stands for an exact match, such as `192.0.2.0` (IPv4),  
`fe80:0:0:0:a450:9a2e:ff9d:a915` (IPv6, long form) or

`fe80::a450:9a2e:ff9d:a915` (IPv6, shorthand).

### **xxx-xxx**

Stands for a range of IP addresses, such as `192.0.2.0-19` (IPv4),  
`fe80:0:0:0:a450:9a2e:ff9d:a915-a9aa` (IPv6, long form), or  
`fe80::a450:9a2e:ff9d:a915-a9aa` (IPv6, shorthand).

### **\***

Stands for any valid IP address value, such as `192.0.2.*`, which is  
analogous to `192.0.2.0-255`, or `fe80::a450:9a2e:ff9d:*`, which is  
analogous to `fe80::a450:9a2e:ff9d:0-ffff`.

### **?**

Stands for any valid character when specifying a reverse DNS name, such  
as `server?.example.com`.

### **/**

Specifies the use of CIDR notation to specify which IP addresses should be  
allowed or blocked. Common CIDR blocks are `/8` (for `1.*.*.*`), `/16` (for  
`1.2.*.*`) and `/24` (for `1.2.3.*`). CIDR notation also works with IPv6  
addresses, such as `2001:db8::/32`.

## **Caveats**

Specific IP addresses listed in Allow rules will not be blocked by anti-hammering.  
These IP addresses are whitelisted. However, addresses matched by a wildcard  
or a range will be subject to anti-hammering prevention.

### **Implicit deny all**

Until you add the first IP access rule, connections from any IP address are  
accepted. After you add the first IP access rule, all connections that are not  
explicitly allowed will be denied. This is also known as an implicit 'Deny All'  
rule. With this in mind, make sure you add a 'wildcard allow' rule (such as  
`Allow *.*.*.*`) at the end of your IP access rule list.

### **Matching all addresses**

Use the `*.*.*.*` mask to match any IPv4 address. Use the `::*` mask to

match any IPv6 address. If you use both IPv4 and IPv6 listeners, add Allow ranges for both IPv4 and IPv6 addresses.

### **DNS lookup**

If you use a dynamic DNS service, you can specify a domain name instead of an IP address to allow access to users who do not have a static IP address. You can also specify reverse DNS names. If you create a rule based on a domain name or reverse DNS, Serv-U performs either a reverse DNS lookup or DNS resolution to apply these rules. This can cause a slight delay during login, depending on the speed of the DNS server of the system.

### **Rule use during connection**

The level at which you specify an IP access rule also defines how far a connection is allowed before it is rejected. Server and domain level IP access rules are applied before the welcome message is sent. Domain level IP access rules are also applied when responding to the `HOST` command to connect to a virtual domain. Group and user level IP access rules are applied in response to a `USER` command when the client identifies itself to the server.

### **Anti-hammering**


You can set up an anti-hammering policy that blocks clients who connect and fail to authenticate more than a specified number of times within a specified period of time. You can configure an anti-hammering policy server-wide in **Server Limits and Settings > Settings** and domain-wide in **Domain Limits and Settings > Settings**.

IP addresses blocked by anti-hammering rules appear in the domain IP access rules with a value in the **Expires in** column. If you have multiple domains with different listeners, blocked IP addresses appear in the domain that contains the listener. Blocked IP addresses do not appear in the server IP access list, even if anti-hammering is configured at the server level.

The **Expires in** value of the blocked IP counts down second by second until the entry disappears. You can unblock any blocked IP early by deleting its entry from the list.



**Domain Details** - Defines the basic information about the selected domain, how the domain listens for incoming connections, and the IP access rules that govern who can connect to the domain.



### IP access list controls

The following section contains a description of the options that are available on the IP Access page.

#### Using the sort mode

By using the sort mode, you can sort the IP access list numerically rather than in the processing order. Displaying the IP access list in sort mode does not change the order in which rules are processed. To view rule precedence, disable this option. Viewing the IP access list in numerical order can be a valuable tool when you review long lists of access rules to determine if an entry already exists.



## Importing and exporting IP access rules

You can export and import Serv-U IP access rules from users, groups, domains, and the server by using a text-based CSV file. To export IP access rules, view the list of rules to export, click **Export**, and then specify the path and the file name you want to save the list to. To import IP access rules, click **Import** and select the file that contains the rules you want to import. The CSV file must contain the following fields, including the headers:

### IP

The IP address, IP range, CIDR block, or domain name for which the rule applies.

### Allow

Set this value to 0 for Deny, or to 1 for Allow.

### Description

A text description of the rule for reference purposes.

## Examples

### Case File: Office-only access

A contractor has been hired to work in the office, and only in the office. Office workstations have IP addresses in the range of 192.0.2.0 - 192.0.2.24. The related Serv-U access rule should be `Allow 192.0.2.0-24`, and it should be added to either the contractor's user account or a Contractors group that contains multiple contractors. No deny rule is required here because Serv-U provides an implicit deny all rule at the end of the list.

### Case File: Prohibited computers

Users should normally be able to access Serv-U from anywhere, except from a bank of special internal computers in the IP address range of 192.0.2.0 - 192.0.2.24. The related Serv-U access rules should therefore be `Deny 192.0.2.0-24`, followed by `Allow *.*.*.*`, and these should both be added to either the domain or the server IP access rules.

### Case File: DNS-based access control

The only users allowed to access a Serv-U domain will be connecting from \*.example.com or \*.example1.com. The related Serv-U access rules should therefore be Allow \*.example.com and Allow \*.example1.com in any order, and these should both be added to the domain IP access rules. No deny rule is required here because Serv-U provides an implicit deny all rule at the end of the list.

## Limits and settings

Serv-U contains options which you can use to customize how Serv-U can be used, and which also provide ways to apply limits and custom settings to users, groups, domains, and the server in its entirety. The limits stack intelligently, with user settings overriding group settings, group settings overriding domain settings, and domain settings overriding server settings. In addition, you can configure limits so that they are only applied during certain days of the week, or certain times of the day. You can also grant exceptions to administrators and restrict specific users more than others, providing total control over the server. The limits and settings in Serv-U are divided into the following categories:

- Connection
- Password
- Directory Listing
- Data Transfer
- HTTP
- Email
- File Sharing
- Advanced

To apply a limit, select the appropriate category, click **Add**, select the limit, and then select or enter the value. For example, to disable the **Lock users in home directory** option for a domain, perform the following steps:

- In the Serv-U Management Console, click **Domain > Domain Limits & Settings**.
- From the **Limit Type** list, select **Directory Listing**.
- Click **Add**.
- From the **Limit** list, select **Lock users in home directory**.
- Deselect the option.
- Click **Save**.

The limits list displays the current limits applied to the domain. Limits with a light-blue background are default values. Limits with a white background are values that override the default values. After you complete the previous steps, a new **Lock users in home directory** limit appears in the list that displays "No" as the value. Because of inheritance rules, this option applies to all users in the domain unless it is overridden at the group or user level. For more information about this method of inheritance, see "User interface conventions".

You can delete limits by selecting them and clicking **Delete**. To edit an overridden value, select the limit, and then click **Edit**. Default rules cannot be edited or deleted. Create a new limit to override a default one.

To create a limit that is restricted to a specific time of day or days of the week, click **Advanced** in the New Limit or Edit Limit window. Select **Apply limit only at this time of day** to specify a start and stop time for the new limit. To restrict the limit to certain days of the week, deselect the days for which you do not want to apply the limit. When a limit is restricted in this way, default values (or the value of other limit overrides) are applied when the time of day or day of the week restrictions are not met for this limit.

The following section contains a reference of all available user limits, organized by category.

## Connection

### Maximum number of sessions per user account

Specifies the maximum number of concurrent sessions that may be opened

from a single user account.

### **Maximum sessions per IP address for user account**

Specifies the maximum number of concurrent sessions that a user may open from a single IP address.

### **Require secure connection before login**

Requires that a connection be secure (for example, FTPS, SFTP, or HTTPS) before it is accepted.

### **Automatic idle connection timeout**

Specifies the number of minutes that must pass after the last client data transfer before a session is disconnected for being idle.

**Note:** Setting the Packet time-out is a requirement for this limit to work. The value of Packet time-out must be less than the value of the Automatic idle connection timeout for the Automatic idle connection timeout to work properly. For information about setting the packet time-out, see Server settings.

### **Automatic session timeout**

Specifies the number of minutes a session is allowed to last before being disconnected by the server.

### **Block anti-timeout schemes**

Blocks the use of commands such as `noop`, which is commonly used to keep FTP Command Channel connections open during long file transfers or other periods of inactivity where no information is being transferred on the control channel. When these are blocked, Serv-U disconnects the client when the connection has been idle, that is, not transferring data, for a specified period of time.

### **Block IP address of timed out session**

Specifies the number of minutes for which the IP address of a timed out session is blocked.

### **Allow FTP and FTPS connections**

Allows the user to connect using the FTP and FTPS protocols. Deselect

**Allow FTP and FTPS connections** to disable the FTP and FTPS protocols.

**Allow SFTP connections**

Allows the user to connect using the SFTP protocol. Deselect **Allow SFTP connections** to disable the SFTP protocol.

**Allow HTTP and HTTPS connections**

Allows the user to connect using the HTTP and HTTPS protocols. Deselect **Allow HTTP and HTTPS connections** to disable the HTTP and HTTPS protocols.

**Password**

**Require complex passwords**

Specifies that all user account passwords must contain at least one uppercase and one non-alphabetic character to be considered valid.

**Minimum password length**

Specifies the minimum number of characters required in a user account's password. Specifying zero characters indicates that there is no minimum requirement.

**Automatically expire passwords**

Specifies the number of days a password is valid before it must be changed. Specifying zero days means passwords never expire.

**Allow users to change password**

Specifies whether or not users are allowed to change their own passwords.

**Mask received passwords in logs**

Masks the passwords received from clients from being shown in log files. Disabling this allows passwords to be displayed in log files, which can be useful for debugging connection problems or auditing user account security.

**SSH authentication type**

Specifies how SSH authentication is to occur. The following options are

available:

- One-way encryption (more secure): This option fully encrypts passwords and cannot be reversed. This is the default setting.
- Simple two-way encryption (less secure): This option encrypts passwords in a reversible format for easy recovery. Use this option when users are expected to take advantage of the password recovery utility in the Web Client. In this case it may be desirable to use two-way encryption so that Serv-U does not need to reset their passwords when password recovery is requested.
- No encryption (not recommended): This option stores passwords in clear text. Using this option may be necessary for integration with legacy systems (especially when using database support).

**Note:** When you change this setting, all user passwords must be reset. Existing passwords are not updated automatically, and must be re-saved to be stored in the new format.

### **Allow users to recover password**

If enabled, allows users to recover passwords using the Web Client password recovery utility at the login page.

### **FTP password type**

All passwords are stored in an encrypted, irreversible state in Serv-U's configuration files (unless the file server is configured to not encrypt stored passwords through a password limit). In addition to the **Regular Password** option, two additional types of password storage are available for accounts that use the FTP protocol: **MD4** and **MD5 OTP S/KEY** passwords. This type of password setting allows the user to log in through FTP without sending the password to the file server as plain text. These options only apply to the FTP protocol. Setting this option does not affect a user's ability to log in through other protocols.

### **Days before considering password to be stale**

The number of days prior to expiration that a password is to be considered stale. A stale password is a password that is about to expire. An event can be configured to identify when a password is about to expire. This value is the lead-time, in days, before password expiration.

### **Disable password generators**

If enabled, this limit allows users to generate a random password.

## **Directory Listing**

### **Hide files marked as hidden from listings**

Hides files and folders from directory listings that have the Windows "hidden" system attribute set on them.

### **Use lowercase for file names and directories**

Forces Serv-U to display all file names and directories using lowercase characters, regardless of the actual letter case in use by the file or directory.

### **Interpret Windows shortcuts as links**

Instructs Serv-U to treat all valid .lnk files as the actual destination object. In other words, if a .lnk file points to another file, the destination file is shown in the directory listing instead of the .lnk file itself.

### **Treat Windows shortcuts as target in links**

Instructs Serv-U to treat all valid .lnk (shortcut) files as a UNIX symbolic link.

### **Allow root ("/") to list drives for unlocked users (Windows Only)**

Allows users to change directory to the root ("/") of the system and display all drives on the computer. This option only works when the user is not locked in their home directory.

### **Hide the compressed state of files and directories**

Hides the compressed state of all compressed files and directories being viewed by the user.

### **Hide the encrypted state of files and directories**

Hides the encrypted state of all encrypted files and directories being viewed

by the user.

### **Message file path**

Welcome messages are normally displayed once to a user during login to relay important information to users about the file server site. By using a secondary message file, welcome messages can be provided in specific folders to relay additional information. A non-relative path such as `MessageFile.message` can be used as the path. The welcome message will only be displayed when navigating into folders which contain a file matching the specified file name.

### **Data Transfer**

#### **Maximum upload speed per session**

Limits the maximum upload bandwidth for each individual session. Setting a limit of 0 KB/s means unlimited bandwidth.

#### **Maximum download speed per session**

Limits the maximum download bandwidth for each individual session. Setting a limit of 0 KB/s means unlimited bandwidth.

#### **Maximum upload speed for user accounts**

Limits the maximum upload bandwidth shared between all sessions associated with an individual user account. Setting a limit of 0 KB/s means unlimited bandwidth.

#### **Maximum upload file size**

Restricts the maximum single file size a user can upload to Serv-U. The file size is measured in kilobytes.

#### **Maximum download speed for user accounts**

Limits the maximum download bandwidth shared between all sessions associated with an individual user account. Setting a limit of 0 KB/s means unlimited bandwidth.

#### **Delete partially uploaded files**

Instructs Serv-U to delete incomplete file uploads. If this option is enabled,



users are not able to restart interrupted uploads using the **REST** (Restart) FTP command.

### **Interpret line feed byte as a new line when in ASCII mode (Windows Only)**

When uploading and downloading files using ASCII mode, Serv-U will assume <LF> characters are the same as <CR><LF> end-of-line markers. Most Windows applications expect <CR><LF> to represent a new-line, as does the FTP protocol. However, since the definition of a new-line sequence is not fully defined in Windows, this option allows Serv-U to assume <LF> is the same as <CR><LF>. When uploading in ASCII mode stand-alone <LF> characters are changed to <CR><LF> prior to writing to the file. When downloading in ASCII mode, stand-alone <LF> characters are changed to <CR><LF> prior to sending to the client.

### **Automatically check directory sizes during upload**

Instructs Serv-U to occasionally check the size of directories in which a maximum directory size has been specified. This attribute ensures that Serv-U always has updated directory sizes available instead of having to calculate them at transfer time, which can be a time consuming operation.

## **HTTP**

### **Default language for Web Client**

When the end-user connects with an unsupported language, the HTTP login page is displayed in English. The default language can be set to any language. When connecting to Serv-U using a supported localization of Windows, the local language of Windows is used.

### **Allow HTTP media playback**

The Serv-U Web Client supports fully interactive media playback of audio and video files. This function can be disabled during specific business hours or altogether based on business needs.

### **Allow browsers to remember login information**

The HTTP login page contains a **Remember me** option (not enabled by

default) that allows user names to be remembered by the login page. This feature can be disabled for security reasons.

### **Allow users to change themes**

The Serv-U Web Client supports visual themes to change the look and feel of the Web Client and HTTP login page. This feature is visual only and has no impact on security or functionality. This option can be disabled for business needs.

### **Allow users to change languages**

The Serv-U Web Client is supported in many languages, but if users should not be able to select their preferred language this can be disabled.

### **Allow users to use Web Client Pro**

Serv-U Web Client Pro is enabled by default. Administrators can disallow the use of Serv-U Web Client Pro by disabling this limit.

### **Allow users to use FTP Voyager JV**

FTP Voyager JV is enabled by default. Administrators can disallow the use of FTP Voyager JV by disabling this limit.

### **Maintain file dates and times after uploading (FTP Voyager JV and Web Client Pro only)**

When enabled, Serv-U can maintain the last modification date and time of the file when end-users are using FTP Voyager JV or Web Client Pro.

When disabled, Serv-U will not set the file's last modification date and time, it will remain the date and time the file was uploaded.

### **Allow HTTP sessions to change IP address (disabling may cause mobile devices to fail)**

The Serv-U Web Client supports the transfer of HTTP sessions if the IP address changes. This option can be disabled but it may cause mobile devices to be disconnected due to frequent IP address changes by these devices.

## Email

### **Allow end-user to set account email address**

Specifies whether users are allowed to modify their account email address using the Change Email Address option in the Web Client or File Sharing interfaces.

### **Require end-user to set email address at next HTTP login**

Specifies whether users must set their email address when they log in to Serv-U.

## File Sharing

### **Require a password for guest access**

Specifies whether it is possible to set up a file share where the guest is required to provide a password. When this limit is set to Always or Never, the creator of the file share will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share whether or not the guest must provide a password.

### **Insert passwords within invitation emails**

Specifies whether it is possible to set up a file share where the password for the share is included in the invitation email. When this limit is set to Always or Never, the creator of the file share will not be able to specify this optional setting. When this limit is set to Optional, the **Include the password in the email** option can be selected individually in each file share.

### **Maximum file size guests can upload (per file)**

Specifies the file size constraints imposed upon the guest user. If set to 0, there is no file size constraint. In this case, the creator of the file share request can specify the maximum file size in each file share request without an upper limit.

### **Allow user-defined guest link expiration**

When enabled, users will be able to specify link expiration dates individually in the Request Files and Send Files wizards. When disabled,

the file share links will expire after the number of days specified in the **Duration before guest link expires** limit.

### **Duration before guest link expires**

Limits the number of days after which a file share link expires if the Allow user-defined guest link expiration limit is disabled.

### **Notify user after a file is downloaded**

Specifies whether the **Notify me when the file(s) have been downloaded** option can be used in the Send Files wizard. When this limit is set to Always or Never, the creator of the file share will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share whether to receive notification of the file download.

### **Notify user after a file is uploaded**

Specifies whether the **Notify me when the file(s) have been uploaded** option can be used in the Request Files wizard. When this limit is set to Always or Never, the creator of the file share request will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share request whether to receive notification of the file upload.

### **Send the guest access link to the recipients**

Specifies whether the **Automatically send the download/upload link to the guest user(s) in email** option can be used in the Send Files and Request Files wizards. When this limit is set to Always or Never, the user will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share or file share request whether to send the access link automatically.

### **Send the guest access link to the sender**

Specifies whether the **Send me an email copy with the download/upload link** option can be used in the Send Files and Request Files wizards. When this limit is set to Always or Never, the user will not be able to specify this optional setting. When this limit is set to Optional, the user can individually

specify in each file share or file share request whether to receive an email copy with the download/upload link.

**Allow file sharing**

Specifies whether the user is allowed to use file sharing.

**Allow user-defined contact information**

When enabled, users will be able to edit their name and email address in the Request Files and Send Files wizards. When disabled, users are not allowed to edit their contact information in the Request Files and Send Files wizards.

**Maximum number of files for "Sent" shares**

Specifies the maximum number of files users can include in a single file share. If set to 0, the default limit of 20 is used.

**Maximum number of files for "Requested" shares**

Specifies the maximum number of files users can upload after receiving a file share request. If set to 0, the default limit of 20 is used.

**Allowed "Sent" file share sources**

Specifies the valid file sharing sources that users can browse to when they create an outgoing file share. By default, users can browse to any file stored on their computer or on Serv-U.

**Advanced**

**Convert URL characters in commands to ASCII**

Instructs Serv-U to convert special characters contained in command parameters to plain ASCII text. Certain browsers can encode special characters contained in file names and directories when using the FTP protocol. This attribute allows Serv-U to decode these special characters.

**Maximum Supported SFTP Version**

Specifies the maximum version of SFTP permitted for SFTP connections. Serv-U supports SFTP versions 3 - 6.

### **Allow Rename Overwrite**

When enabled (default) Serv-U allows files to be renamed to files where the destination already exists. When disabled, users are not allowed to rename a file or directory to a path name that already exists.

### **Apply server and domain directory access rules before user and group**

The order in which directory access rules are listed has significance in determining the resources that are available to a user or group account. By default, directory access rules specified at the group or user level take precedence over ones specified at the domain and server level. However, there are certain instances where you may want the domain and server level rules to take precedence. Setting this value to "Yes" places the group's and user's directory access rules *below* the server and domain. For more information, see the "Apply group directory access rules first" setting in "Group information".

### **Days before automatically disabling account to trigger the pre-disable event**

The number of days prior to automatically disabling the user account that the pre-disable event should be triggered.

### **Days before automatically deleting account to trigger the pre-delete event**

The number of days prior to automatically deleting the user account that the pre-delete event should be triggered.

### **Owner ID (user name) for created files and directories (Linux Only)**

The user name given to set as owner of a created file or directory.

### **Group ID (group name) for created files and directories (Linux Only)**

The group name given to set as owner of a created file or directory.

### **Reset user stats after restart**

When this limit is enabled, the user statistics are reset after a server restart.

## **Transfer ratio and quota management**

Transfer ratios and quotas are just one of the many ways in which file transfers

are managed on the Serv-U File Server. The following sections provide information about their usage.

### Transfer ratio

Transfer ratios are a convenient way of encouraging file sharing on your file server. By specifying an appropriate transfer ratio setting, you can grant credits to the user for transferring a specified number of bytes or complete files. This is commonly used to grant a user the ability to download 'x' megabytes of data or files for every 'y' megabytes of data or files that they upload.

To enable transfer ratios for the current user account, click **Ratios & Quotas** on the User Information page of the User Properties window, and then select **Enable transfer ratio**. Select the appropriate type of ratio to impose on the user account. Ratios can be tracked in terms of megabytes or complete files. They can also be tracked per session established or for all sessions established by the user account.

The ratio itself is configured by assigning a numeric value to both the uploads and downloads side of the ratio. For example, a 3:1 ratio that is counting files over all sessions means that the user account must upload three files in order to have the ability to download one file. The current credit for the user account is displayed in the **Credit** field. This value is the current value and can be initialized to a non-zero value to grant the user initial credits.

### Quota

Quotas are another way to limit the amount of data that is transferred by a user account. When a **Maximum** quota value is assigned to the user, they are not able to use more disk space than that value. The **Current** field shows how much disk space is currently being used by the user account. When initially configuring a quota, both fields must be filled in. From that point on, Serv-U tracks the file uploads and deletions made by the user and updates the current value as appropriate.

**Note:** A considerable drawback to using quotas is that in order for the current value to remain accurate, changes must not be made to the contents of the directories that are accessible by the user account outside of Serv-U. Because these changes take place outside of a file server connection, Serv-U cannot track them and update the current quota value. As an alternative to quotas, consider imposing a maximum size on the contents of a directory when specifying the directory access rules for the user account. For more information about this option, see "Directory access rules".

### Ratio free files

Files listed in the ratio free file list are exempt from any imposed transfer ratios. In other words, if a user must upload files in order to earn credits towards downloading a file, a file that matches an entry in this list can always be downloaded by users, even if they have no current credits. This is commonly used to make special files, such as a readme or a directory information file, always accessible to users.

You can use the `*` and `?` wildcard characters when you specify a ratio free file. Using `*` specifies a wildcard of any kind of character and any length. For example, entering `*.txt` makes any file with a `.txt` extension free for download, regardless of the actual filename. You can use a `?` to represent a single character within the file name or directory. You can also specify full paths by using standard directory paths such as `C:\ftproot\common\` (on Windows) or `/var/ftpfiles/shared/` (on Linux).

In addition, you can use full or relative paths when you are specifying an entry. If you use a full path when you specify a file name, only that specific file is exempt from transfer ratios. If you use a relative path, such as when you enter just `readme.txt`, the provided file is exempt from transfer ratios regardless of the directory it is located in.

## Windows authentication

By enabling Windows authentication, users can log in to Serv-U using their



## Using a Windows user group home directory instead of account home directory

---

Windows login credentials as provided by the local Windows account database or a specific Windows domain server (Active Directory). When logging in using their Windows account, users are placed in the home directory for their Windows account eliminating the need to manually specify a home directory.

To enable Windows authentication, select **Enable Windows authentication**. To authenticate to Active Directory or a Windows domain server, enter a specific domain name in this field and ensure your Serv-U computer is a member of that domain. If the system is a member of a Windows domain, the domain name can be entered in this field to have user logins authorized by the domain server. After changing this field, click **Save** to apply the changes.

### Using a Windows user group home directory instead of account home directory

By default, Serv-U uses the Windows account's home directory when a client logs in using a Windows user account. Enabling this option causes Serv-U to use the home directory specified in the Windows user group instead. If no home directory is specified at the group level, then the Windows user account's home directory is still used.

### Configuring Windows user groups

Windows user accounts are not visible, and they cannot be configured on an individual basis in Serv-U. To aid in configuring the many advanced options of a local user account, all Windows user accounts are a member of a special Windows user group. Click **Configure Windows User Group** to configure this group just like a normal group. All settings configured in this group are inherited by Windows user accounts. This feature can be used to add IP access rules, specify bandwidth limitations, or add additional directory access rules.

For more information, see "About groups".

### Using Windows user permissions

By default, Windows and Active Directory user accounts do not require any directory access rules to be configured because Serv-U automatically applies

their NTFS permissions to their login sessions. This way, administrators do not need to configure specific permissions beyond those already defined on the network, saving time and documentation.

**Note:** In some cases Windows may cache directory access rules for a short period of time. If an important NTFS permissions change is made that requires immediate application, restarting the Serv-U service can force Windows to provide the updated permissions to the Serv-U File Server.

## LDAP authentication

By enabling LDAP authentication, users can log in to Serv-U using login credentials as provided by a remote LDAP server, such as Active Directory or OpenLDAP. LDAP users can use a home directory from their LDAP account, eliminating the need to manually specify a home directory.

To enable LDAP authentication, select **Enable LDAP authentication** in **Users > LDAP Authentication**.

LDAP user home folders are normally pulled from the "Home Directory" LDAP attribute that is specified in your LDAP server configuration. The service account Serv-U runs as should have full permission to the root folder of all LDAP User folders. For example, if your LDAP user home folders are similar to `\\usernas\homefolders\username` and Serv-U is running as a service on Windows as `servu`, then the Windows `servu` user should have full permissions to `\\usernas\homefolders`.

### Using the LDAP user group home directory instead of the account home directory

By default, Serv-U uses the LDAP account's home directory (that is, the value of the "Home Folder" attribute) when an LDAP user logs in. Enabling this option causes Serv-U to use the home directory specified in the Default LDAP User Group instead. If no home directory is specified at the group level, then the LDAP account's home directory is still used. However, if no home directory is defined at the user, group, domain, or system level, and none is available from the LDAP

server, the user will not be allowed to sign on.

### Specifying the LDAP login ID suffix

The **LDAP Login ID suffix** field is used to send fully qualified Login IDs to the LDAP server. A typical value in an Active Directory environment might be `@mydomain.com`. After changing this field, click **Save** to apply the change.

### Differences between Windows users and LDAP users

Windows and LDAP Users are similar in many ways but there are a number of important differences that can help you decide which type of user is right for your environment.

Use Windows users if the following conditions apply:

- You only want to access one Windows machine or domain (per Serv-U domain).
- You want each end user to see that user's home folders and enjoy that user's NTFS permissions. Serv-U uses impersonation so that it respects the Windows directory access rules. The Windows directory access rules can be supplemented with directory access rules defined in Serv-U. For more information about directory access rules, see [Directory access rules](#).

Use LDAP users if the following conditions apply:

- You want to deploy Serv-U on Linux.
- You want to be able to access more than one Windows domain.
- You want to be able to access different Windows domains.
- You do not care about natively incorporating NTFS permissions. It is not possible to pull directory access rules from LDAP directly, but you can define Serv-U directory access rules for LDAP users. For more information about directory access rules, see [Directory access rules](#).

### LDAP user groups

LDAP user accounts are not visible or configurable on an individual basis in


## Chapter 5: Users

---

Serv-U, but LDAP group membership can be used to apply common permissions and settings such as IP restrictions and bandwidth throttles.

All LDAP users are members of a special Default LDAP group. Click **Configure Default LDAP Group** under **Users > LDAP Authentication** or under **Groups > LDAP Groups** to configure this group just like a normal Serv-U group. For information about the configuration options available at the group level, see "Groups".

LDAP Users can also be members of individual LDAP Groups. Click **Configure LDAP Groups** under **Users > LDAP Authentication** to configure these groups just like normal Serv-U groups.



### LDAP group membership

In order for Serv-U to match users up to the appropriate user groups, the entire hierarchy, including the Distinguished Name (DN) must be recreated in the user group hierarchy.

LDAP Users are also added to any LDAP Groups whose names appear in "Group Membership" attributes defined on the **LDAP Authentication** page. For example, if the Group Membership field is configured to be `grp` and an LDAP user record has both `grp=Green` and `grp=Red` attributes, Serv-U will associate that LDAP User with both the "Red" and "Green" LDAP Groups.

Membership in one or more LDAP groups is required if the **Require fully-qualified group membership for login** option is selected on the **Groups > LDAP Groups** page. If this option is selected, and LDAP Users cannot be matched up to at least one LDAP Group, they will not be allowed to sign on. In this case it is possible that Serv-U successfully authenticates to the LDAP server, and then rejects the user login because the user is not a member of any group. For more information about group permissions and settings, see [About groups](#).

### LDAP server configuration

Serv-U requires administrators to define one or more LDAP Servers before LDAP authentication will work. LDAP Servers are configured on the **Users > LDAP Authentication** page in the Serv-U Management Console.

#### List of LDAP servers

Administrators can define more than one LDAP Server if they want Serv-U to try a backup server in case the primary LDAP server is down, or if they want to try LDAP credentials against different LDAP servers with different sets of users.

Authentication is attempted against the list of LDAP servers from top to bottom. During login, the first LDAP server that approves a set of credentials will be the server from which the associated LDAP user will draw its full name, email address and other attributes. After attempting a login against the first LDAP server, Serv-U will try each LDAP server in the list until it either encounters a successful login, or it encounters an unsuccessful login paired with an authoritative response from the LDAP server that the attempted LoginID exists on that LDAP server. (In other words, the preceding LDAP servers need to have

## Chapter 5: Users

---

either been unresponsive or report that they had no knowledge of the LDAP User for login attempts to be made to LDAP servers lower on the list.)

Serv-U tries each available LDAP server, even if the login credentials fail. The error log provides detailed information of any possible connection failure.

**Note:** The error log contains information about the last LDAP server Serv-U contacted.

**Users** - Create, modify, and delete user accounts for this domain.

Domain Users | Database Users | Windows Authentication | **LDAP Authentication**

When LDAP Authentication is enabled, a client can login using a valid LDAP account instead of a local account from the Serv-U user database. If an account already exists in the Serv-U user database, it takes precedence over the LDAP account.

☒ Enable LDAP authentication  
☐ Use LDAP Group home directory instead of the account home directory

LDAP Login ID Suffix:  
@myoffice.net Save

**LDAP Servers**

Host	Port	Server Name	Description
local-dc.myoffice.net	389	My Office's Active Directory	This is a typical configuration for an Active Directory server. Note that...
192.168.45.41	389	Local OpenLDAP Server	A different type of LDAP server.
backup-dc.myoffice.net	389	Backup for AD server	Backup server.
192.168.45.41	389	Backup for OpenLDAP	Offline for repairs.


Add... Edit... Delete Copy...

Configure Default LDAP Group... Configure LDAP Groups...

Use the **Add**, **Edit**, **Delete**, and **Copy** buttons to work with individual LDAP server entries. When there are multiple LDAP server entries in the list, selecting any entry will reveal **move up**, **move down**, **move to top**, and **move to bottom** ordering arrows on the right of the window.

### LDAP server configuration

The LDAP Server configuration dialog is displayed when you click **Add**, **Edit**, or **Copy** on the LDAP Servers list.



The image shows a dialog box titled "LDAP Server" with a close button (X) in the top right corner. The dialog contains several input fields and a checkbox. On the right side, there are three buttons: "Save", "Cancel", and "Help".

Host: local-dc.myoffice.net

Port: 389

Server Name: My Office's Active Directory

☒ Enable LDAP Server

Connection Account: Test@myoffice.net

Connection Account Password: .....

Description: This is a typical configuration for an Active Directory server. Note that the "LoginID to LDAP username" attribute map is configured in TWO places: Search Filter and Login ID. All other attributes are only configured in one place.

Base DN: DC=myoffice,DC=net

Search Filter: (&(objectclass=user)(userPrincipalName=\$LoginID))

Attribute Mapping

Home Directory:	Full Name:
homeDirectory	name
Email Address:	Login ID:
mail	userPrincipalName
Group Membership:	
memberOf	

The LDAP Server Configuration dialog contains the following fields:

- **Host:** The host name or IP address of the LDAP server. This may be IPv4 or IPv6, but it is always required.
- **Port:** The TCP port on which the LDAP server is listening. This will often be 389.
- **Server Name:** This required field should contain a short description of this LDAP server. Provide a brief description of the domain and the type of LDAP server (for example, Tampa Office OpenLDAP).

- **Connection Account:** The user name of the account that is used to execute queries against the LDAP server. Provide the account name complete with the UPN suffix. Serv-U does not automatically apply the UPN suffix for the name you provide here.
- **Connection Account Password:** The password belonging to the account that is used to execute queries against the LDAP server.  
**Note:** If the Connection Account credentials are not supplied, then the credentials that are being authenticated are used.
- **Enable LDAP Server:** Select this option to enable the LDAP server. Disabled LDAP servers will be skipped over during LDAP authentication if you have configured multiple LDAP servers. LDAP authentication will stop working if you disable all your configured LDAP servers.
- **Description:** An optional field in which you can write more notes about your LDAP server.
- **Base DN:** Use this required field to provide the Base DN (or search DN) of the main node in your LDAP server. This is usually similar to the domain name over which your LDAP server has authority. For example, if your LDAP server provides information about your `myoffice.net` domain, this value can be `DC=myoffice,DC=net`.
- **Search Filter:** This required field is used to tell Serv-U how to match incoming LoginIDs ("usernames") to specific LDAP Server entries. `$LoginID` must be included somewhere in this field. During authentication Serv-U will replace this variable with the LDAP User's LoginID (and LDAP Login ID suffix, if specified). The value of the search filter varies between different types of LDAP servers, and may even vary between different LDAP servers of the same type (depending on the specific schema your LDAP administrator has implemented). For Active Directory LDAP servers, a value of `(&(objectClass=user)(userPrincipalName=$LoginID))` is recommended. Consult with your local LDAP administrator or use an LDAP client (for example, Softerra LDAP Browser or Apache Directory Studio) to find and test the right value for your LDAP server before deploying into production.



- **Attribute Mapping - Home Directory:** This optional field assigns the value of the named LDAP user entry attribute as your LDAP Users' home directory. A typical value on Active Directory is `homeDirectory`.
- **Attribute Mapping - Full Name:** This optional field assigns the value of the named LDAP user entry attribute as your LDAP Users' full name. A typical value on Active Directory is `name`.
- **Attribute Mapping - Email Address:** This optional field assigns the value of the named LDAP user entry attribute as your LDAP Users' email address. A typical value on Active Directory is `mail`.
- **Attribute Mapping - Login ID:** This optional field assigns the value of the named LDAP user entry attribute as your LDAP Users' login ID (username). A typical value on Active Directory is `userPrincipalName`. This value will almost always match the value paired with `$LoginID` in your Search Filter.
- **Attribute Mapping - Group Membership:** This optional field uses all the values found in the named LDAP attribute as additional LDAP Group membership assignments. For example, if this is configured as `grp` and an LDAP user record has both `grp=Green` and `grp=Red` attributes, Serv-U associates that LDAP User with both the "Red" and "Green" LDAP Groups. A typical value on Active Directory is `memberOf`.

To test the connection to the LDAP server, log in with an LDAP user. If the connection fails, the log files of Serv-U will provide detailed information about the reason for the failure.

**Note:** Active Directory and OpenLDAP users are configured in the same way. In the case of OpenLDAP, the user account must have permission to connect to the OpenLDAP database.

The possible error messages are the following:

- An unknown LDAP authentication error has occurred. Please double-check your LDAP configuration - This message signifies a generic issue when the LDAP server does not return any specific error.

- An unknown LDAP authentication error has occurred. The error code returned by the LDAP server was %d - This message signifies a specific LDAP error. The error code returned by the LDAP server can be used to find the specific LDAP error.
- LDAP server returned zero or multiple user records matching the account credentials - This message either indicates that the provided user name is wrong (if zero accounts are returned), or it indicates a problem with the search filter (if multiple accounts are returned).
- Authenticated external user "%s" rejected because group membership is required and no matching Serv-U group was found. A list of all known groups for this user follows.
- No group memberships found. If group membership is expected, double-check the "Group Membership" attribute map for your LDAP configuration in Serv-U.
- No LDAP servers are defined or enabled.
- Unable to initialize LDAP server.
- The connection credentials in the LDAP server configuration have been rejected by the LDAP server.
- The user credentials were rejected by the LDAP server.
- The LDAP server is unavailable to Serv-U.
- The connection credentials in the LDAP server configuration do not have permission to run queries.
- The search filter string in the LDAP server configuration was rejected by the LDAP server.

The following error messages relate to issues with accessing an account's home directory, and are not LDAP specific:

- Error logging in user "%s", permission denied by Serv-U access rules to access home dir "%s"

- Error logging in user "%s", the device for home dir "%s" is not ready
- Error logging in user "%s", could not access home dir "%s"; the error returned by the operating system was %d
- Error logging in user "%s", permission denied by the operating system to access home dir "%s"

## SFTP (Secure File Transfer over SSH2) for users and groups

### Using an existing public key

1. Obtain a public key file.
2. Place the public key file in a secured directory in the server, and then use **Browse** in Serv-U to select the file.
3. Click **Save**.

### Creating a key pair

1. Click **Manage Keys**.
2. Click **Create Key**.
3. Type the name of the key pair (for example, `MyKey`), which is also used to name the storage file.
4. Type the output directory of the certificate (for example, `C:\ProgramData\RhinoSoft\Serv-U\`).
5. Select the key type (default of DSA is preferred, but RSA is available).
6. Select the key length (default of 1024 bits provides best performance, 2048 bits is a good median, and 4096 bits provides best security).
7. Enter the password to use for securing the key file.
8. Click **Create**.

### Creating multiple keys per user

For the purposes of public key authentication, you can associate multiple public keys with a user account.

#### To create multiple keys for an account:

1. Click **Manage Keys**.
2. Click **Add Key**, and then specify the key name and the key path.

When authenticating a client, Serv-U checks all the keys you provide here. If authenticating against one key fails, Serv-U proceeds to check the next key.

For optimal results, the following best practices are recommended:

- It is recommended that you do not create more than 100 keys per user account.
- If you have a large number of public keys, divide the keys between multiple users, and define the common user properties at group level.
- Avoid storing the public keys in a network path.

# Chapter 6: Groups

## About groups

Groups are a method of sharing common configuration options with multiple user accounts. Configuring a group is similar to configuring a user account. Virtually every configuration option available for a user account can be set at the group level. In order for a user to inherit a group's settings, it must be a member of the group. Permissions and attributes inherited by a user through group membership can still be overridden at the user level. A user can be a member of multiple groups in order to acquire multiple collections of permissions, such as directory or IP access rules.

Like user accounts, groups can be created at multiple different levels, including the following:

- Global Groups
- Domain Groups
- Database Groups (available at both the server and domain levels)
- Windows Groups

However, groups are only available to user accounts that are defined at the same level. In other words, a global user (that is, a user defined at the server level) can only be a member of a global group. Likewise, a user defined for a specific domain can only be a member of a group also created for that domain. This restriction also applies to groups created in a database in that only users created within a database at the same level can be members of those groups.

Use the **Add**, **Edit**, and **Delete** buttons to manage the available groups.

### Using group templates


You can configure a template for creating new groups by clicking **Template**. The template group can be configured just like any other group object, with the

exception of giving it a name. After the settings are saved to the template, all new groups are created with their default settings set to those found within the template. This way you can configure some basic settings that you want all of your groups to use by default.

### Setting up Windows groups (Windows only)

You can use Window groups to apply common permissions and settings such as IP restrictions and bandwidth throttles to Windows users.

All Windows users are members of the default Windows group. You can create additional Windows groups to assign different permissions and settings to different groups of Windows users.



Windows group membership is determined by the hierarchical OU (organizational unit) membership of each Windows user. For example, a user in the **My Business > Accounting > red team** OU tree would be a member of the **My Business > Accounting > red team** Windows group on Serv-U, if that group exists. (Visually, "My Business" would be the top Windows group, "Accounting"

would be an indented child Windows group under that, and "red team" would be an indented child under "Accounting".)

Membership in one or more Windows Groups is required if the **Require fully-qualified group membership for login** option is selected on the Windows Groups page. If this option is selected and Windows users cannot be matched up to at least one Windows group, they are not be allowed to log in.

Windows groups are only available when the following conditions apply:

- Serv-U is running on Windows.
- Serv-U has an MFT Server license.
- Windows Authentication is enabled under **Domain Users > Windows Authentication**.

### Configuring a Windows user group (Windows only)

Administrators can allow clients to log in to the file server using the local Windows user database or one that is made accessible through a domain server. These user accounts do not exist in the local Serv-U user database and cannot be configured on an individual basis. To aid in configuring these accounts, all users logged in through this method belong to the Default Windows User Group. Clicking this button allows this group to be configured like normal. However, changes that are made to this group only apply to Windows user accounts.


### LDAP user groups

LDAP user accounts are not visible or configurable on an individual basis in Serv-U, but LDAP group membership can be used to apply common permissions and settings such as IP restrictions and bandwidth throttles.

All LDAP users are members of a special default LDAP group. Click **Configure Default LDAP Group** in **Users > LDAP Authentication** or in **Groups > LDAP groups** to configure this group just like a normal Serv-U group.

## Chapter 6: Groups

LDAP users can also be members of individual LDAP groups. Click **Configure LDAP Groups** in **Users > LDAP Authentication** to configure these groups just like normal Serv-U groups.



### LDAP group membership

In order for Serv-U to match users up to the appropriate user groups, the entire hierarchy, including the Distinguished Name (DN) must be recreated in the user group hierarchy.

LDAP users are also added to any LDAP Groups whose names appear in Group Membership attributes defined on the **LDAP Authentication** page. For example, if the Group Membership field is configured to be `grp` and an LDAP user record has both `grp=Green` and `grp=Red` attributes, Serv-U will associate that LDAP user with both the "Red" and "Green" LDAP groups.

Membership in one or more LDAP groups is required if the **Require fully-qualified group membership for login** option is selected on the **Groups > LDAP Groups** page. If this option is selected, and LDAP users cannot be



matched up to at least one LDAP Group, they will not be allowed to sign on. In this case it is possible that Serv-U successfully authenticates to the LDAP server, and then rejects the user login because the user is not a member of any group.

For more information about LDAP authentication, see "LDAP authentication".

## Group information

Virtually every attribute available for a user account can be configured at the group level. Group level settings are inherited by the group members and can be overridden at the user level. The Group Information tab contains general information about the group including the name, home directory, and the default administrative privilege for group members. The following sections contain detailed information about each of the available attributes.

### Group name

The group name is a unique identifier that must be unique for each group specified at the particular level (server or domain). Group names may not contain any of the following special characters:

`\ / < > . | : ? *`

### Home directory

The home directory for a user account is where the user is placed immediately after logging in to the file server. Each user must have a home directory assigned to it, although the home directory can be specified at the group level if the user is a member of a group. Home directories must be specified using a full path including the drive letter or the UNC share name. If the home directory is not found, Serv-U can be configured to create it.

When specifying the home directory, you can use the `%USER%` macro to insert the login ID into the path. This is used mostly to configure a default home directory at the group level or within the new user template to ensure that all new users have a unique home directory. When combined with a directory access rule for `%HOME%`, a new user can be configured with a unique home

directory and the proper access rights to that location with a minimal amount of effort.

You can also use the `%DOMAIN_HOME%` macro to identify the user's home directory. For example, to place a user's home directory into a common location, use `%DOMAIN_HOME%\%USER%`.

The home directory can be specified as `"\"` (root) in order to grant system-level access to users, allowing them the ability to access all system drives. In order for this to work properly, the user must not be locked in their home directory.

### **Administration privilege**

A user account can be granted one of the following types of administrative privileges:

- No Privilege
- Group Administrator
- Domain Administrator
- System Administrator

The value of this attribute can be inherited through group membership.

A user account with no privilege is a regular user account that can only log in to transfer files to and from the file server. The Serv-U Management Console is not available to these user accounts.

A group administrator can only perform administrative duties relating to their primary group (the group that is listed first in their group memberships list). They can add, edit, and delete users which are members of their primary group, and they can also assign permissions at or below the level of the group administrator. They may not make any other changes.

A domain administrator can only perform administrative duties for the domain to which their account belongs. A domain administrator is also

restricted from performing domain-related activities that may affect other domains. The domain-related activities that may *not* be performed by domain administrators consist of configuring their domain listeners or configuring ODBC database access for the domain.

A system administrator can perform any file server administration activity including creating and deleting domains, user accounts, or even updating the license of the file server. A user account with system administrator privileges that is logged in through HTTP remote administration can essentially administer the server as if they had physical access to the system.

### **Default web client**

If your Serv-U license enables the use of FTP Voyager JV, then users connecting to the file server through HTTP can choose which client they want to use after logging in. Instead of asking users which client they want to use, you can also specify a default client. If this option is changed, it overrides the option specified at the server or domain level. It can also be inherited by a user through group membership. Use the **Inherit default value** option to reset it to the appropriate default value.

### **Lock user in home directory**

Users who are locked in their home directory cannot access paths above their home directory. In addition, the actual physical location of their home directory is masked because Serv-U always reports it as "/" (root). The value of this attribute can be inherited through group membership.

### **Apply group directory access rules first**

The order in which directory access rules are listed has significance in determining the resources that are available to a user account. By default, directory access rules specified at the group level take precedence over directory access rules specified at the user level. However, there are certain instances where you may want the user level rules to take precedence. Deselect this option to place the directory access rules of the group *below*

the user's.

### **Always allow login**

Enabling this option means that the user account is always permitted to log in, regardless of restrictions placed upon the file server such as maximum number of sessions. It is useful as a fail-safe in order to ensure that critical system administrator accounts can always remotely access the file server. As with any option that allows bypassing access rules, care should be taken in granting this ability. The value of this attribute can be inherited through group membership.

**Note:** Enabling the Always Allow Login option does not override IP access rules. If both options are defined, the IP access rules prevail.

### **Description**

The description allows for the entry of additional notes that are only visible by administrators.

### **Availability**

This feature limits when users can connect to this server. You can place limitations on the time of day and also on the day of the week. When users attempt to log in outside the specified available times, they are presented with a message that their user account is currently unavailable.

## **Directory access rules**

### **Directory access rules**

Directory access rules define the areas of the system which are accessible to user accounts. While traditionally restricted to the user and group levels, in Serv-U, the usage of directory access rules is extended to both the domain and the server levels through the creation of global directory access rules. Directory access rules specified at the server level are inherited by all users of the file server. If they are specified at the domain level, they are only inherited by users who belong to the particular domain. The traditional rules of inheritance apply where rules specified at a lower level (for example, the user level) override

conflicting or duplicate rules specified at a higher level (for example, the server level).

When you set the directory access path, you can use the `%USER%`, `%HOME%`, `%USER_FULL_NAME%`, and `%DOMAIN_HOME%` variables to simplify the process. For example, use `%HOME%/ftproot/` to create a directory access rule that specifies the `ftproot` folder in the home directory of the user. Directory access rules specified in this manner are portable if the actual home directory changes while maintaining the same subdirectory structure. This leads to less maintenance for the file server administrator. If you specify the `%USER%` variable in the path, it is replaced with the user's login ID. This variable is useful in specifying a group's home directory to ensure that users inherit a logical and unique home directory. You can use the `%USER_FULL_NAME%` variable to insert the Full Name value into the path (the user must have a Full Name specified for this to function). For example, the user "Tom Smith" could use `D:\ftproot\%USER_FULL_NAME%` for `D:\ftproot\Tom Smith`. You can also use the `%DOMAIN_HOME%` macro to identify the user's home directory. For example, to place a user and their home directory into a common directory, use `%DOMAIN_HOME%\%USER%`.

Directory access rules are applied in the order they are listed. The first rule in the list that matches the path of a client's request is the one that is applied for that rule. In other words, if a rule exists that denies access to a particular subdirectory but is listed *below* the rule that grants access to the parent directory, then a user still has access to the particular subdirectory. Use the arrows on the right of the directory access list to rearrange the order in which the rules are applied.

The following section contains the list and description of the directory access permissions.

### File permissions

#### Read

Allows users to read (that is, download) files. This permission does not allow users to list the contents of a directory, which is granted by the **List** permission.

### **Write**

Allows users to write (that is, upload) files. This permission does not allow users to modify existing files, which is granted by the **Append** permission.

### **Append**

Allows users to append data to existing files. This permission is typically used to grant users the ability to resume transferring partially uploaded files.

### **Rename**

Allows users to rename existing files.

### **Delete**

Allows users to delete files.

### **Execute**

Allows users to remotely execute files. The execute access is meant for remotely starting programs and usually applies to specific files. This is a very powerful permission and great care should be used in granting it to users. Users with **Write** and **Execute** permissions can install any program they want on the system.

## **Directory permissions**

### **List**

Allows users to list the files and subdirectories contained in the directory. Also allows users to list this folder when listing the contents of a parent directory.

### **Create**

Allows users to create new directories within the directory.

### **Rename**

Allows users to rename existing directories within the directory.

### **Remove**

Allows users to delete existing directories within the directory.

**Note:** If the directory contains files, the user also needs to have the **Delete**

files permission in order to remove the directory.

### Subdirectory permissions

#### Inherit

Allows all subdirectories to inherit the same permissions as the parent directory. The **Inherit** permission is appropriate for most circumstances, but if access must be restricted to subfolders (as is the case when implementing mandatory access control), clear the **Inherit** check box and grant permissions specifically by folder.

#### Advanced: Access as Windows User (Windows Only)

For a variety of reasons, files and folders may be kept on external servers in order to centralize file storage or provide additional layers of security. In this environment, files can be accessed by the UNC path (`\\servername\folder\`) instead of the traditional `C:\ftproot\folder` path. However, accessing folders stored across the network poses an additional challenge, because Windows services are run under the Local System account by default, which has no access to network resources.

To mitigate this problem for all of Serv-U, you can configure the Serv-U File Server service to run under a network account. The alternative, preferred when many servers exist, or if the Serv-U File Server service has to run under Local System for security reasons is to configure a directory access rule to use a specific Windows user for file access. By clicking the **Advanced** button, you can specify a specific Windows user for each individual directory access rule. As in Windows authentication, directory access is subject to NTFS permissions, and in this case also to the configured permissions in Serv-U.

**Note:** When you use Windows authentication, the NTFS permissions of the Windows user take priority over the directory access rules. This means that when a Windows user tries to access a folder, the security permissions of the user are applied instead of the credentials specified in the directory access rule.

### Quota permissions

#### Maximum size of directory contents

Setting the maximum size actively restricts the size of the directory contents to the specified value. Any attempted file transfers that cause the directory contents to exceed this value are rejected. This feature serves as an alternative to the traditional quota feature that relies upon tracking all file transfers (uploads and deletions) to calculate directory sizes and is not able to consider changes made to the directory contents outside of a user's file server activity.

#### Mandatory access control

You can use mandatory access control (MAC) in cases where users need to be granted access to the same home directory but should not necessarily be able to access the subdirectories below it. To implement mandatory access control at a directory level, disable the **Inherit** permission as shown in the following screen capture. In the following example, the rule applies to `D:\ftproot\`.

The screenshot shows the 'Directory Access Rule' dialog box. The 'Path' field is empty. The 'Files' section has checkboxes for Read, Write, Append, Rename, Delete, and Execute (disabled with a warning icon). The 'Directories' section has checkboxes for List, Create, Rename, and Remove. The 'Subdirectories' section has an 'Inherit' checkbox that is unchecked. The 'Maximum size of directory contents' field is empty, with the text 'MB (leave blank for no limit)' below it. On the right, there are buttons for 'Save', 'Cancel', 'Help', 'Full Access', 'Read Only', and 'Advanced >>'.

Now, the user has access to the `ftproot` folder but to no folders below it.




Permissions must individually be granted to subfolders that the user needs access to, providing the security of mandatory access control in the Serv-U File Server.

### Restricting file types


If users are using storage space on the Serv-U File Server to store non-work-related files, such as MP3 files, you can prevent this by configuring a directory access rule placed *above* the main directory access rule to prevent MP3 files from being transferred as shown below. In the text entry for the rule, type `*.mp3`, and use the permissions shown in the following screen capture:

Directory Access Rule

Path:  

**Files**

☐ Read ☐ Delete

☐ Write ☐ Execute 

☐ Append

☐ Rename

**Directories**

☐ List

☐ Create

☐ Rename

☐ Remove

**Subdirectories**

☒ Inherit

Maximum size of directory contents:  MB (leave blank for no limit)

Save Cancel Help Full Access Read Only Advanced >>

The rule denies permission to any transfer of files with the `.mp3` extension and can be modified to reflect any file extension. Similarly, if accounting employees only need to transfer files with the `.mdb` extension, configure a pair of rules that grants permissions for `.mdb` files but denies access to all other files, as shown in the following screen captures. In the first rule enter the path that should be the user's home directory or directory they need access to, and in the second rule enter the extension of the file that should be accessed (such as `*.mdb`).

## Chapter 6: Groups

---

Directory Access Rule

Path:

Save


Cancel

Files

☐ Read

☐ Delete

☐ Write

☐ Execute 

☐ Append

☐ Rename

Directories

☒ List

☐ Create

☐ Rename

☐ Remove

Help

Full Access

Read Only

Subdirectories

☒ Inherit

Maximum size of directory contents:  
 MB (leave blank for no limit)

Advanced &gt;&gt;

Directory Access Rule

Path:

Save


Cancel

Files

☒ Read

☒ Delete

☒ Write

☐ Execute 

☒ Append

☒ Rename

Directories

☒ List

☐ Create

☐ Rename

☐ Remove

Help

Full Access

Read Only

Subdirectories

☒ Inherit

Maximum size of directory contents:  
 MB (leave blank for no limit)

Advanced &gt;&gt;

These rules only allow users to access `.mdb` files within the specified directories. You can adapt these rules to any file extension or set of file extensions.

## Virtual paths

If virtual paths are specified, users can gain access to files and folders outside of their own home directory. A virtual path only defines a method of mapping an existing directory to another location on the system to make it visible within a user's accessible directory structure. In order to actually have access to the mapped location, the user must still have a directory access rule specified for the physical path of a virtual path.

Like directory access rules, virtual paths can be configured at the server, domain, group, and user levels. Virtual paths created at the server level are available for all users of the file server. When virtual paths are created at the domain level, they are only accessible by users belonging to that domain. You can also create virtual paths specifically for individual users or groups.

### Physical path

The physical path is the actual location on the system, or network, that is to be placed in a virtual location accessible by a user. If the physical path is located on the same computer, use a full path, such as `D:\inetpub\ftp\public`. You can also use a UNC path, such as `\\Server\share\public`. To make a virtual path visible to users, users must have a directory access rule specified for the physical path.

### Virtual path

The virtual path is the location that the physical path should appear in for the user. The `%HOME%` macro is commonly used in the virtual path to place the specified physical path in the home directory of the user. When specifying the virtual path, the last specified directory is used as the name displayed in directory listings to the user. For example, a virtual path of `%HOME%/public` places the specified physical path in a folder named `public` within the user's home directory. You can also use a full path without any macros.

### Including virtual paths in "Maximum Directory Size" calculations

When this option is selected, the virtual path is included in Maximum Directory

Size calculations. The Maximum Directory Size limits the size of directories affecting how much data can be uploaded.

### Case File: Using virtual paths

A group of web developers have been granted access to the directory `D:\ftproot\example.com\` for web development purposes. The developers also need access to an image repository located at `D:\corpimages\`. To avoid granting the group access to the root D drive, a virtual path must be configured so that the image repository *appears* to be contained within their home directory. Within the group of web developers, add a virtual path to bring the directory to the users by specifying `D:\corpimages\` as the physical path and `D:\ftproot\example.com\corpimages` as the virtual path. Be sure to add a group level directory access rule for `D:\corpimages\` as well. The developers now have access to the image repository without compromising security or relocating shared resources.

### Case File: Creating relative virtual paths

Continuing with the previous example, if the home directory of the group of web developers is relocated to another drive, both the home directory and the virtual path need to be updated to reflect this change. You can avoid this by using the `%HOME%` macro to create a relative virtual path location that eliminates the need to update the path if the home directory changes. Instead of using `D:\ftproot\example.com\corpimages` as the virtual path, use `%HOME%\corpimages`. This way the `corpimages` virtual path is placed within the home directory of the group, regardless of what the home directory is. If the home directory changes at a later date, the virtual path still appears there.

## Configuring user and group logs

In the Serv-U File Server, you can customize the logging of user and group events and activity to a great extent. To enable a logging option, select the appropriate option in the **Log Message Options** grouping. When an option is selected, the appropriate logging information is saved to the specified log file if

the **Enable logging to file** option is selected. You can configure the log to show as much or as little information as you want. After configuring the logging options you want, click **Save** to save the changes.

### Logging to File Settings

#### Log file path

You must specify the name of the log file before information can be saved to a file. Click **Browse** to select an existing file or directory location for the log file. The log file path supports certain wildcard characters. Wildcard characters which refer to the date apply to the day that the log file is created. When combined with the **Automatically rotate log file** option, wildcards provide an automatic way to archive activity for audits. The following list contains the wildcard characters that you can use:

#### %H

The hour of the day (24-hour clock).

#### %D

The current day of the month.

#### %M

The name of the current month.

#### %N

The numeric value of the current month (1-12).

#### %Y

The 4-digit value of the current year (for example, 2014).

#### %X

The 2-digit value of the current year (for example, 14 for 2014).

#### %S

The name of the domain whose activity is being logged.

#### %G

The name of the group whose activity is being logged.

### %L

The name of the login ID whose activity is being logged.

### %U

The full name of the user whose activity is being logged.

### Enable logging to file

Select this option to enable Serv-U to begin saving log information to the file that you specified in the **Log file path**. If this option is not selected, Serv-U does not log any information to the file, regardless of the individual options selected in the **Log Message Options** area.

### Automatically rotating the log file

To ensure that log files remain a manageable size and can be easily referenced during auditing, you can automatically rotate the log file on a regular basis. By specifying a **Log file path** containing wildcards that reference the current date, Serv-U can rotate the log file and create a unique file name every hour, day, week, month, or year.

### Purging old log files

You can automatically purge old log files by setting a maximum number of files to keep, a maximum size limit in megabytes, or both. Setting these options to "0" means that the setting is unlimited and the limit is not applied.

**Warning:** Log files are purged based only on the current log file path name, and they are purged approximately every 10 minutes. Log file variables are replaced with Windows wildcard values used to search for matching files. For example:

```
C:\Logs\%Y:%N:%D %S Log.txt is searched for C:\Logs\????:??:?? * Log.txt
C:\Logs\%Y:%M:%D %S Log.txt is searched for C:\Logs\????:*:?? * Log.txt
C:\Logs\%S\%Y:%M:%D Log.txt is searched for C:\Logs\--DomainName--
\????:*:?? Log.txt
C:\Logs\%G\%Y:%M:%D Log.txt is searched for C:\Logs\--GroupName--\????:*:??
Log.txt
C:\Logs\%L\%Y:%M:%D Log.txt is searched for C:\Logs\--LoginID--\????:*:??
```

Log.txt

C:\Logs\%U\%Y:%M:%D Log.txt is searched for C:\Logs\--UserFullName--  
\?????:\*:\*? Log.txt

The following wildcards can be used for log variables:

%H --> ??

%D --> ??

%N --> ??

%M --> \*

%Y --> ????

%X --> ??

%S --> \*

%G --> \*

%L --> \*

%U --> \*

Anything matching the path name you used wildcards for can be purged. Use caution: it is best practice to place log files into a single directory to avoid unexpected file deletion.

### Specifying IP addresses exempt from logging

You can specify IP addresses that are exempt from logging. Activity from these IP addresses is not logged. This is useful to exempt IP addresses for administrators that may otherwise generate a lot of logging information that can obfuscate domain activity from regular users. It can also be used to save log space and reduce overhead. Click **Do Not Log IPs**, and then add IP addresses as appropriate.

## Group members

The user accounts that are members of the currently selected group are displayed on this page. It can be used to get a quick overview of what users are currently inheriting the settings of the group at this time. Users cannot be added or removed from the group using this interface. Adding or removing a group membership must

be done from the appropriate user's account properties window.

A user account can be granted one of four types of administrative privileges:

- No Privilege
- Group Administrator
- Domain Administrator
- System Administrator

The value of this attribute can be inherited through group membership. A user account with no privilege is a regular user account that can only log in to transfer files to and from the file server. The Serv-U Management Console is not available to these user accounts.

A group administrator can only perform administrative duties relating to their primary group (the group that is listed first in their groups memberships list). They can add, edit, and delete users which are members of their primary group, and they can also assign permissions at or below the level of the group administrator. They may not make any other changes.

A domain administrator can only perform administrative duties for the domain to which their account belongs. A domain administrator is also restricted from performing domain-related activities that may affect other domains. The domain-related activities that may not be performed by domain administrators consist of configuring their domain listeners or configuring ODBC database access for the domain.

A system administrator can perform any file server administration activity including creating and deleting domains, user accounts, or even updating the license of the file server. A user account with system administrator privileges that is logged in through HTTP remote administration can essentially administer the server as if they had physical access to the system.


Serv-U also supports read-only administrator accounts which can allow administrators to log in and view configuration options at the domain or server level, greatly aiding remote problem diagnosis when working with outside parties.



Read-only administrator privileges are identical to their full-access equivalents, except that they cannot change any settings or create, delete or edit user accounts.

**Note:** When configuring a user account with administrative privileges, take care in specifying their home directory. An administrator account with a home directory other than "\" (root) that is locked in their home directory may not use file paths outside of their home directory when configuring the file server.

## Serv-U events



The screenshot shows the 'Events' configuration window in Serv-U. The window has a title bar with a close button. Inside, there are two tabs: 'Events' and 'Event Filters'. The 'Events' tab is active. It contains two main sections: 'Event Information' and 'Event Actions'. In the 'Event Information' section, 'Event Type' is set to 'File Uploaded', 'Event Name' is 'Event 01', and 'Enable event' is checked. The 'Description' field contains the text 'Show balloon tip when users upload a file.'. In the 'Event Actions' section, 'Action' is set to 'Show Balloon Tip', 'Balloon Title' is '"\$name" Has Uploaded A File.', and 'Balloon Information' contains a list of variables: '\$LocalPathName', 'Size: \$FileSizeFmt bytes (\$FileSize KB KB)', '\$TransferBytes bytes transferred.', '\$TransferKBPerSecond KB/sec.', and 'Protocol: \$Protocol'. At the bottom of the window are three buttons: 'Save', 'Cancel', and 'Help'.

**Events** **Event Filters**

**Event Information**

Event Type:  
File Uploaded

Event Name:  
Event 01

☒ Enable event

Description:  
Show balloon tip when users upload a file.

**Event Actions**

Action:  
Show Balloon Tip

Balloon Title:  
"\$name" Has Uploaded A File.

Balloon Information:  
\$LocalPathName  
Size: \$FileSizeFmt bytes (\$FileSize KB KB)  
\$TransferBytes bytes transferred.  
\$TransferKBPerSecond KB/sec.  
Protocol: \$Protocol

Save Cancel Help

In Serv-U, you can use event handling which can perform various actions triggered by a list of selected events. The following list contains the available actions:

## **Server events**

### **Server Start**

Triggered by Serv-U starting up, whether by starting the Serv-U service or starting Serv-U as an application.

### **Server Stop**

Triggered by Serv-U shutting down, whether from service or application-level status. This event only triggers for graceful stops.

## **Server and domain events**

### **Domain Start**

Triggered by a Serv-U domain starting, through the **Enable Domain** setting in the **Domain Details > Settings** menu, or as part of normal server startup.

### **Domain Stop**

Triggered by a Serv-U domain stopping, through the **Enable Domain** setting in the **Domain Details > Settings** menu, or as part of normal server startup.

### **Session Connection**

Triggered by a new TCP session connection.

### **Session Disconnect**

Triggered by a TCP session disconnection.

### **Session Connection Failure**

Triggered by a failed session connection attempt.

### **Log File Deleted**

Triggered by the automatic deletion of a log file, according to logging settings.

### **Log File Rotated**

Triggered by the automatic rotation of a log file, according to logging settings.

**Listener Success**

Triggered by a successful listener connection.

**Listener Stop**

Triggered by a stopped listener connection.

**Listener Failure**

Triggered by a failed listener connection.

**Gateway Listener Success**

Triggered by a successful gateway listener connection.

**Gateway Listener Stop**

Triggered by a stopped gateway listener connection.

**Gateway Listener Failure**

Triggered by a failed gateway listener connection.

**Permanent Listener Success**

Triggered by a successful permanent listener connection.

**Permanent Listener Failure**

Triggered by a failed permanent listener connection.

**Permanent Listener Stop**

Triggered by a stopped permanent listener connection.

**Permanent Gateway Listener Success**

Triggered by a successful permanent gateway listener connection.

**Permanent Gateway Listener Stop**

Triggered by a stopped permanent gateway listener connection.

**Permanent Gateway Listener Failure**

Triggered by a failed permanent gateway listener connection.

**File Management Rule Success**

Triggered when a file management rule is applied, and no errors are encountered.

### **File Management Rule Failure**

Triggered when a file management rule is applied, and at least one error is encountered.

### **Server, domain, user and group events**

#### **User Login**

Triggered by the login of a user account.

#### **User Logout**

Triggered by the logout of a user account.

#### **User Login Failure**

Triggered by a failed login. A failed login is any connection attempt to Serv-U that fails, whether due to invalid credentials, or a session disconnect before authentication, either due to an incorrect user name, incorrect password, incorrect SSH key pair (for SFTP public key authentication), or any or all of the above.

#### **User Password Change**

Triggered by the change of a password for a user account by the user (if permitted).

#### **User Password Change Failure**

Triggered by a failed password change attempt.

#### **User Enabled**

Triggered by the enabling of a user account that was previously disabled.

#### **User Disabled**

Triggered by the disabling of a user account that was previously enabled.

#### **User Deleted**

Triggered by the deletion of a user account by a remote administrator, in an ODBC database, or in the local Management Console.

### **User Added**

Triggered by the creation of a user account by a remote administrator, in an ODBC database, or in the local Management Console.

### **Password Recovery Sent**

Triggered by a successful password recovery by an end user.

### **Password Recovery Failed**

Triggered by a failed password recovery attempt, either due to lack of email address in the user account or lack of permissions.

### **Password Stale**

Triggered by a stale password, as configured in **Limits & Settings**, that is going to expire.

### **User Auto Disable**

Triggered by the automatic disabling of a user account, as configured by a user's **Automatically Disable** date.

### **User Auto Deleted**

Triggered by the automatic deletion of a user account, as configured by a user's **Automatically Delete** date.

### **User Pre-disable**

Triggered by the upcoming disabling of a user account, as configured in the user's **Automatically Disable** date and the "Days before automatically disabling account to trigger the pre-disable event" limit.

### **User Pre-delete**

Triggered by the upcoming deletion of a user account, as configured in the user's **Automatically Delete** date and the **Days before automatically deleting account to trigger the pre-delete** event limit.

### **User Email Set**

Triggered by a user setting the email address for a user account.

### **User Email Set Failure**

Triggered by a failed attempt by a user to set the email address for a user account.

### **IP Blocked**

Triggered by a failed login attempt due to an IP access rule.

### **IP Blocked Time**

Triggered by a failed login attempt due to an IP access rule that was automatically added by brute force settings, configured in **Domain Limits & Settings** or **Server Limits & Settings**.

### **Too Many Sessions**

Triggered by more sessions logging on to the server than are permitted, per the **Limits & Settings** for the user account, group, domain, or server.

### **Too Many Session On IP**

Triggered by more sessions logging on to the server from a specific IP address than are permitted, according to the **Limits & Settings** for the user account, group, domain, or server.

### **IP Auto Added To Access Rules**

Triggered by the automatic addition of an IP access rule due to a user triggering the "brute force" settings.

### **Session Idle Timeout**

Triggered by an idle session timeout.

### **Session Timeout**

Triggered by a session timeout.

### **File Uploaded**

Triggered by a file uploaded to Serv-U. This event triggers for partial uploads if the upload session terminated with a successful message and no data corruption.

### **File Upload Failed**

Triggered by a failed file upload to Serv-U.

### **File Download**

Triggered by a file downloaded from Serv-U.

### **File Download Failed**

Triggered by a failed file download from Serv-U.

### **File Deleted**

Triggered by the deletion of a file on the Serv-U server by a user.

### **File Moved**

Triggered by the moving of a file on the Serv-U server by a user.

### **Directory Created**

Triggered by the creation of a directory.

### **Directory Deleted**

Triggered by the deletion of a directory.

### **Directory Changed**

Triggered by changing the current working directory.

### **Directory Moved**

Triggered by moving a directory to a new location.

### **Over Quota**

Triggered by going over disk quota space. The current quota space is shown in the user account, in the **Limits & Settings** menu.

### **Over Disk Space**

Triggered by exceeding the Max Dir Size configured for a directory access rule. The current disk space is shown with the **AVBL FTP** command, or by using the **Directory Properties** option in the HTTP or HTTPS Web Client and FTP Voyager JV.

### **Creating common events**

You can automatically create a list of the most common events. You can choose to create these common events using email or balloon tip actions. Click **Create Common Event** in the Events page. Select either the **Send Email** or **Show**



**balloon tip** option for the action you want to perform on the common events. If you choose to send email, also enter an email address where the events are to be sent.

**Note:** The **Write to Windows Event Log** and **Write to Microsoft Message Queue (MSMQ)** options are available for Windows only.

### Using event actions

You can select from the following actions that will be executed when an event is triggered:

- Send Email
- Show Balloon Tip\*
- Execute Command\*
- Write to Windows Event Log (Windows only)\*
- Write to Microsoft Message Queue (MSMQ) (Windows only)\*

\* Events involving anything other than email can only be configured by Serv-U server administrators.

### Using email actions

You can configure email actions to send emails to multiple recipients and to Serv-U groups when an event is triggered. To add an email address, enter it in the **To** or **Bcc** fields. To send emails to a Serv-U group, use the **Group** icon to add or remove Serv-U groups from the distribution list. Separate email addresses by commas or semicolons. Email actions contain a **To**, **Subject** and **Message** parameter. You can use special variables to send specific data pertaining to the event. For more information about the variables, see "System variables".

To use email actions, you must first configure SMTP in Serv-U. For information about SMTP configuration, see "Serv-U SMTP configuration".

### Using balloon tip actions

You can configure balloon tip actions to show a balloon tip in the system tray when an event is triggered. Balloon tip actions contain a **Balloon Title** and a

**Balloon Message** parameter. You can use special variables to send specific data pertaining to the event. For more information about the variables, see "System variables".

### Using execute command actions

You can configure execute command actions to execute a command on a file when an event is triggered. Execute command actions contain an **Executable Path**, **Command Line Parameters**, and a **Completion Wait Time** parameter. For the **Completion Wait Time** parameter, you can enter the number of seconds to wait after starting the executable path. Enter zero for no waiting.

**Note:** Any amount of time Serv-U spends waiting delays any processing that Serv-U can perform.

A wait value should only be used to give an external program enough time to perform some operation, such as move a log file before it is deleted (for example, `$LogFilePath` for the Log File Deleted event). You can use special variables to send specific data pertaining to the event. For more information about the variables, see "System variables".

### Writing to the Windows Event Log

By writing event messages to a local Windows Event Log, you can monitor and record Serv-U activity by using third-party network management software. All messages appear in the Windows Application Log from a source of "Serv-U".

This event has only one field:

- **Log Information:** The contents of the message to be written into the event log. This is normally either a human-readable message (for example, `filename uploaded by person`) or a machine-readable string (for example, `filename|uploaded|person`), depending on who or what is expected to read these messages. Serv-U system variables are supported in this field. This field can be left blank, but usually is not.

### Writing to Microsoft Queue (MSMQ)

Microsoft Message Queuing (MSMQ) is an enterprise technology that provides a

method for independent applications to communicate quickly and reliably. Serv-U can send messages to new or existing MSMQ queues whenever a Serv-U event is triggered. Corporations can use this feature to tell enterprise applications that files have arrived, files have been picked up, partners have signed on, or many other activities have occurred.

These events have the following two fields:

- **Message Queue Path:** The MSMQ path that addresses the queue. Remote queues can be addressed when a full path (for example, `MessageServer\Serv-U Message Queue`) is specified. Local, public queues on the local machine can be addressed when a full path is not specified (for example, `.\Serv-U Message Queue` or `Serv-U Message Queue`). If the specified queue does not exist, Serv-U attempts to create it. This normally only works on public queues on the local machine. You can also use Serv-U system variables in this field.
- **Message Body:** The contents of the message to be sent into the queue. This is normally a text string with a specific format specified by an enterprise application owner or enterprise architect. Serv-U system variables can also be used in this field. This field may be left blank, but usually is not.

**Note:** Microsoft message queues created in Windows do not grant access to SYSTEM by default, preventing Serv-U from writing events to the queue. To correct this, after creating the queue in MSMQ, right-click it, select **Properties**, and then set the permissions so that SYSTEM (or the network account under which Serv-U runs) has permission to the queue.

### Using event filters

By using Serv-U event filters, you can control to a greater degree when a Serv-U event is triggered. By default, Serv-U events trigger each time the event occurs. The event filter allows events to be triggered only if certain conditions are met. For example, a standard Serv-U event might trigger an email each time a file is uploaded to the server. However, by using an event filter, events can be triggered

on a more targeted basis. For example, you can configure a File Uploaded event to only send an email when the file name contains the string `important`, so an email would be sent when the file `Important Tax Forms.pdf` is uploaded but not when other files are uploaded to the server. Additionally, you can configure a File Upload Failed event to run only when the FTP protocol is used, not triggering for failed HTTP or SFTP uploads. You can do this by controlling the various variables and values related to the event and by evaluating their results when the event is triggered.

### Event filter fields

Each event filter has the following critical values that must be set:

- **Name:** This is the name of the filter, used to identify the filter for the event.
- **Description (Optional):** This is the description of the event, which may be included for reference.
- **Logic:** This determines how the filter interacts with other filters for an event. In most cases, AND is used, and all filters must be satisfied for the event to trigger. The function of AND is to require that all conditions be met. However, the OR operator can be used if there are multiple possible satisfactory responses (for example, abnormal bandwidth usage of less than 20 KB/s OR greater than 2000 KB/s).
- **Filter Comparison:** This is the most critical portion of the filter. The Filter Comparison contains the evaluation that must occur for the event to trigger. For example, a filter can be configured so that only the user "admin" triggers the event. In this case, the comparison will be `If $Name = (is equal to) admin`, and the data type will be `string`. For bandwidth, either an "unsigned integer" or "double precision floating point" value would be used.

Event filters also support wildcards when evaluating text strings. The supported wildcards are the following:

- **\*** - The asterisk wildcard matches any text string of any length. For example:
  - An event filter that compares the `$FileName` variable to the string `data*` matches files named `data`, `data7`, `data77`, `data.txt`, `data7.txt`, and

`data77.txt.`

- **?** - The question mark wildcard matches any one character, but only one character. For example:
  - An event filter that compares the `$FileName` variable to the string `data?` matches a file named `data7` but not `data`, `data77`, `data.txt`, `data7.txt`, or `data77.txt`.
  - An event filter that compares the `$FileName` variable to the string `data?.*` matches files named `data7` and `data7.txt` but not `data`, `data77`, `data.txt`, or `data77.txt`.
  - An event filter that compares the `$Name` variable to the string `A????` matches any five-character user name that starts with `A`.
- **[]** - The bracket wildcard matches a character against the set of characters inside the brackets. For example:
  - An event filter that compares the `$FileName` variable to the string `data[687].txt` matches files named `data6.txt`, `data7.txt` and `data8.txt` but not `data5.txt`.
  - An event filter that compares the `$LocalPathName` variable to the string `[CD]:\*` matches any file or folder on the `C:` or `D:` drives.


You can use multiple wildcards in each filter. For example:

- An event filter that compares the `$FileName` variable to the string `[cC]:\*.???` matches any file on the `C:` drive that ends in a three letter file extension.
- An event filter that compares the `$FileName` variable to the string `?:\*Red[678]\?????.*` matches a file on any Windows drive, contained in any folder whose name contains `Red6`, `Red7` or `Red8`, and that also has a five character file name followed by a file extension of any length.

## Using event filters


Event filters are used by comparing fields to expected values in the Event Filter

menu. The best example is raising an event only when a certain user triggers the action, or when a certain file is uploaded. For example, an administrator may want to raise an email event when the file `HourlyUpdate.csv` is uploaded to the server, but not when other files are uploaded. To do this, create a new event in the **Domain Details > Events** menu. The **Event Type** is File Uploaded, and on the Event Filter tab a new filter must be added. The `$FileName` variable is used and the value is `HourlyUpdate.csv` as shown in the following screen capture:



The screenshot shows a 'Filter Comparison' dialog box. At the top, there is a title bar with a funnel icon and the text 'Filter Comparison', and a close button (X). Below the title bar, there is a message: 'Comparisons must be added to the event filter to define the scenario that will allow or disallow the event.' To the right of this message are three buttons: 'Save', 'Cancel', and 'Help'. The main area of the dialog contains a form with the following fields: 'If' (a dropdown menu), '\$FileName' (a text input field), '=' (a dropdown menu), '(is equal to)' (a text input field), and 'HourlyUpdate.csv' (a text input field). Below these fields is a 'Data Type:' label and a dropdown menu showing '(abcd) string'.

As another example, it might be necessary to know when a file transfer fails for a specific user account. To perform this task, create a new File Upload Failed event, and then add a new filter. The filter comparison is the `$Name` variable, and the value to compare is the user name, such as `ProductionLineFTP`:



The screenshot shows a 'Filter Comparison' dialog box. At the top, there is a title bar with a funnel icon and the text 'Filter Comparison', and a close button (X). Below the title bar, there is a message: 'Comparisons must be added to the event filter to define the scenario that will allow or disallow the event.' To the right of this message are three buttons: 'Save', 'Cancel', and 'Help'. The main area of the dialog contains a form with the following fields: 'If' (a dropdown menu), '\$Name' (a text input field), '=' (a dropdown menu), '(is equal to)' (a text input field), and 'ProductionLineFTP' (a text input field). Below these fields is a 'Data Type:' label and a dropdown menu showing '(abcd) string'.

You can also filter for events based on specific folders, using wildcards. In some cases it may be necessary to trigger events for files uploaded only to a specific folder, such as when an accounting department uploads time-sensitive tax files. To filter based on a folder name, create a new File Uploaded event in the **Domain Details > Events** menu, and set it to **Send Email**. After specifying the

email recipients, subject line, and message content, open the Event Filters page. Create a new event filter, and add the filter comparison `If $LocalPathName = (is equal to) C:\ftproot\accounting\*` with the type of `(abcd) string`. This will cause the event to trigger only for files that are located within `C:\ftproot\accounting\`.

## Server details

### IP access rules

IP access rules restrict login access to specific IP addresses, ranges of IP addresses, or a domain name. IP access rules can be configured at the server, domain, group, and user levels.

IP access rules are applied in the order they are displayed. In this way, specific rules can be placed at the top to allow or deny access before a more general rule is applied later on in the list. The arrows on the right side of the list can be used to change the position of an individual rule in the list.

### Specifying IP access masks

IP access rules use masks to authorize IP addresses and domain names. The masks can contain specific values, ranges, and wildcards made up of the following elements:

#### **xxx**

Stands for an exact match, such as `192.0.2.0` (IPv4),  
`fe80:0:0:0:a450:9a2e:ff9d:a915` (IPv6, long form) or

## Chapter 6: Groups

---

`fe80::a450:9a2e:ff9d:a915` (IPv6, shorthand).

### **xxx-xxx**

Stands for a range of IP addresses, such as `192.0.2.0-19` (IPv4),

`fe80:0:0:0:a450:9a2e:ff9d:a915-a9aa` (IPv6, long form), or

`fe80::a450:9a2e:ff9d:a915-a9aa` (IPv6, shorthand).

### **\***

Stands for any valid IP address value, such as `192.0.2.*`, which is analogous to `192.0.2.0-255`, or `fe80::a450:9a2e:ff9d:*`, which is analogous to `fe80::a450:9a2e:ff9d:0-ffff`.

### **?**

Stands for any valid character when specifying a reverse DNS name, such as `server?.example.com`.

### **/**

Specifies the use of CIDR notation to specify which IP addresses should be allowed or blocked. Common CIDR blocks are `/8` (for `1.*.*.*`), `/16` (for `1.2.*.*`) and `/24` (for `1.2.3.*`). CIDR notation also works with IPv6 addresses, such as `2001:db8::/32`.

## **Caveats**

Specific IP addresses listed in Allow rules will not be blocked by anti-hammering. These IP addresses are whitelisted. However, addresses matched by a wildcard or a range will be subject to anti-hammering prevention.

### **Implicit deny all**

Until you add the first IP access rule, connections from any IP address are accepted. After you add the first IP access rule, all connections that are not explicitly allowed will be denied. This is also known as an implicit 'Deny All' rule. With this in mind, make sure you add a 'wildcard allow' rule (such as `Allow *.*.*.*`) at the end of your IP access rule list.

### **Matching all addresses**

Use the `*.*.*.*` mask to match any IPv4 address. Use the `::*` mask to



match any IPv6 address. If you use both IPv4 and IPv6 listeners, add Allow ranges for both IPv4 and IPv6 addresses.

### **DNS lookup**

If you use a dynamic DNS service, you can specify a domain name instead of an IP address to allow access to users who do not have a static IP address. You can also specify reverse DNS names. If you create a rule based on a domain name or reverse DNS, Serv-U performs either a reverse DNS lookup or DNS resolution to apply these rules. This can cause a slight delay during login, depending on the speed of the DNS server of the system.

### **Rule use during connection**

The level at which you specify an IP access rule also defines how far a connection is allowed before it is rejected. Server and domain level IP access rules are applied before the welcome message is sent. Domain level IP access rules are also applied when responding to the `HOST` command to connect to a virtual domain. Group and user level IP access rules are applied in response to a `USER` command when the client identifies itself to the server.

### **Anti-hammering**


You can set up an anti-hammering policy that blocks clients who connect and fail to authenticate more than a specified number of times within a specified period of time. You can configure an anti-hammering policy server-wide in **Server Limits and Settings > Settings** and domain-wide in **Domain Limits and Settings > Settings**.

IP addresses blocked by anti-hammering rules appear in the domain IP access rules with a value in the **Expires in** column. If you have multiple domains with different listeners, blocked IP addresses appear in the domain that contains the listener. Blocked IP addresses do not appear in the server IP access list, even if anti-hammering is configured at the server level.

The **Expires in** value of the blocked IP counts down second by second until the entry disappears. You can unblock any blocked IP early by deleting its entry from the list.



**Domain Details** - Defines the basic information about the selected domain, how the domain listens for incoming connections, and the IP access rules that govern who can connect to the domain.



### IP access list controls

The following section contains a description of the options that are available on the IP Access page.

#### Using the sort mode

By using the sort mode, you can sort the IP access list numerically rather than in the processing order. Displaying the IP access list in sort mode does not change the order in which rules are processed. To view rule precedence, disable this option. Viewing the IP access list in numerical order can be a valuable tool when you review long lists of access rules to determine if an entry already exists.

## Importing and exporting IP access rules

You can export and import Serv-U IP access rules from users, groups, domains, and the server by using a text-based CSV file. To export IP access rules, view the list of rules to export, click **Export**, and then specify the path and the file name you want to save the list to. To import IP access rules, click **Import** and select the file that contains the rules you want to import. The CSV file must contain the following fields, including the headers:

### IP

The IP address, IP range, CIDR block, or domain name for which the rule applies.

### Allow

Set this value to 0 for Deny, or to 1 for Allow.

### Description

A text description of the rule for reference purposes.

## Examples

### Case File: Office-only access

A contractor has been hired to work in the office, and only in the office. Office workstations have IP addresses in the range of 192.0.2.0 - 192.0.2.24. The related Serv-U access rule should be `Allow 192.0.2.0-24`, and it should be added to either the contractor's user account or a Contractors group that contains multiple contractors. No deny rule is required here because Serv-U provides an implicit deny all rule at the end of the list.

### Case File: Prohibited computers

Users should normally be able to access Serv-U from anywhere, except from a bank of special internal computers in the IP address range of 192.0.2.0 - 192.0.2.24. The related Serv-U access rules should therefore be `Deny 192.0.2.0-24`, followed by `Allow *.*.*.*`, and these should both be added to either the domain or the server IP access rules.

### Case File: DNS-based access control

The only users allowed to access a Serv-U domain will be connecting from \*.example.com or \*.example1.com. The related Serv-U access rules should therefore be Allow \*.example.com and Allow \*.example1.com in any order, and these should both be added to the domain IP access rules. No deny rule is required here because Serv-U provides an implicit deny all rule at the end of the list.

## Limits and Settings

Serv-U contains options which you can use to customize how Serv-U can be used, and which also provide ways to apply limits and custom settings to users, groups, domains, and the server in its entirety. The limits stack intelligently, with user settings overriding group settings, group settings overriding domain settings, and domain settings overriding server settings. In addition, you can configure limits so that they are only applied during certain days of the week, or certain times of the day. You can also grant exceptions to administrators and restrict specific users more than others, providing total control over the server. The Limits and Settings in Serv-U are divided into the following categories:

- Connection
- Password
- Directory Listing
- Data Transfer
- HTTP
- Email
- File Sharing
- Advanced

To apply a limit, select the appropriate category, click **Add**, select the limit, and then select or enter the value. For example, to disable the **Lock users in home directory** option for a domain, perform the following steps:

- Select **Domain > Domain Limits & Settings** from the Serv-U Management Console.
- Select **Directory Listing** from the **Limit Type** list.
- Click **Add**.
- Select **Lock users in home directory** from the **Limit** list.
- Deselect the option.
- Click **Save**.

The limits list displays the current limits applied to the domain. Limits with a light-blue background are default values. Limits with a white background are values that override the defaults. After you complete the previous steps, a new **Lock users in home directory** limit appears in the list that displays "No" as the value. Because of inheritance rules, this option applies to all users in the domain unless it is overridden at the group or user level. For more information about this method of inheritance, see "User interface conventions".

You can delete limits by selecting them and clicking **Delete**. To edit an overridden value, select the limit, and then click **Edit**. Default rules cannot be edited or deleted. Create a new limit to override a default one.

To create a limit that is restricted to a specific time of day or days of the week, click **Advanced** in the New Limit or Edit Limit window. Select **Apply limit only at this time of day** to specify a start and stop time for the new limit. To restrict the limit to certain days of the week, deselect the days for which you do not want to apply the limit. When a limit is restricted in this way, default values (or the value of other limit overrides) are applied when the time of day or day of the week restrictions are not met for this limit.

The following section contains a reference of all available group limits, organized by category.

## Connection

### Maximum number of sessions for group

Specifies the maximum number of concurrent sessions that may be allowed

for all users that are a member of the group.

### **Maximum sessions per IP address for group**

Specifies the maximum number of concurrent sessions that may be opened from a single IP address for all users of the group.

### **Maximum number of sessions per user account**

Specifies the maximum number of concurrent sessions that may be opened from a single user account.

### **Maximum sessions per IP address for user account**

Specifies the maximum number of concurrent sessions that a user may open from a single IP address.

### **Require secure connection before login**

Requires that a connection be secure (for example, FTPS, SFTP, or HTTPS) before it is accepted.

### **Automatic idle connection timeout**

Specifies the number of minutes that must pass after the last client data transfer before a session is disconnected for being idle.

**Note:** Setting the Packet time-out is a requirement for this limit to work. The value of Packet time-out must be less than the value of the Automatic idle connection timeout for the Automatic idle connection timeout to work properly. For information about setting the packet time-out, see "Server settings".

### **Automatic session timeout**

Specifies the number of minutes a session is allowed to last before being disconnected by the server.

### **Block anti-timeout schemes**

Blocks the use of commands such as `noop`, which is commonly used to keep FTP Command Channel connections open during long file transfers or other periods of inactivity where no information is being transferred on the control channel. When these are blocked, Serv-U disconnects the client when the

connection has been idle, that is, not transferring data, for a specified period of time.

**Block IP address of timed out session**

Specifies the number of minutes for which the IP address of a timed out session is blocked.

**Allow FTP and FTPS connections**

Allows the user to connect using the FTP and FTPS protocols. Deselect **Allow FTP and FTPS connections** to disable the FTP and FTPS protocols.

**Allow SFTP connections**

Allows the user to connect using the SFTP protocol. Deselect **Allow SFTP connections** to disable the SFTP protocol.

**Allow HTTP and HTTPS connections**

Allows the user to connect using the HTTP and HTTPS protocols. Deselect **Allow HTTP and HTTPS connections** to disable the HTTP and HTTPS protocols.

**Password**

**Require complex passwords**

Specifies that all user account passwords must contain at least one uppercase and one non-alphabetic character to be considered valid.

**Minimum password length**

Specifies the minimum number of characters required in the password of a user account. Specifying zero characters indicates that there is no minimum requirement.

**Automatically expire passwords**

Specifies the number of days a password is valid before it must be changed. Specifying zero days means passwords never expire.

**Allow users to change password**

Specifies whether or not users are allowed to change their own passwords.

### **Mask received passwords in logs**

Masks the passwords received from clients from being shown in log files. Disabling this allows passwords to be displayed in log files, which can be useful for debugging connection problems or auditing User account security.

### **SSH authentication type**

Specifies how SSH authentication is to occur. The following options are available:

- One-way encryption (more secure): This option fully encrypts passwords and cannot be reversed. This is the default setting.
- Simple two-way encryption (less secure): This option encrypts passwords in a reversible format for easy recovery. Use this option when users are expected to take advantage of the password recovery utility in the Web Client. In this case it may be desirable to use two-way encryption so that Serv-U does not need to reset their passwords when password recovery is requested.
- No encryption (not recommended): This option stores passwords in clear text. Using this option may be necessary for integration with legacy systems (especially when using database support).

**Note:** When you change this setting, all user passwords must be reset. Existing passwords are not updated automatically, and must be re-saved to be stored in the new format.

### **Allow users to recover password**

If enabled, this limit allows users to recover passwords using the Web Client password recovery utility at the login page.

### **FTP Password Type**

All passwords are stored in an encrypted, irreversible state in the configuration files of Serv-U (unless the file server is configured to not encrypt stored passwords through a password limit). In addition to the



**Regular Password** option, two additional types of password storage are available for accounts that use the FTP protocol: **MD4** and **MD5 OTP S/KEY** passwords. This type of password setting allows the user to log in through FTP without sending the password to the file server as plain text. These options only apply to the FTP protocol. Setting this option does not affect a user's ability to login through other protocols.

**Days before considering password to be stale**

The number of days prior to expiration that a password is to be considered "stale". A stale password is a password that is about to expire. An event can be configured to identify when a password is about to expire. This value is the lead-time, in days, before password expiration.

**Disable password generators**

If enabled, this limit allows users to generate a random password.

**Directory Listing**

**Hide files marked as hidden from listings**

Hides files and folders from directory listings that have the Windows "hidden" system attribute set on them.

**Use lowercase for file names and directories**

Forces Serv-U to display all file names and directories using lowercase characters, regardless of the actual letter case in use by the file or directory.

**Interpret Windows shortcuts as links**

Instructs Serv-U to treat all valid .lnk files as the actual destination object. In other words, if a .lnk file points to another file, the destination file is shown in the directory listing instead of the .lnk file itself.

**Treat Windows shortcuts as target in links**

Instructs Serv-U to treat all valid .lnk (shortcut) files as a UNIX symbolic link.

**Allow root ("/") to list drives for unlocked users (Windows Only)**

Allows users to change directory to the root ("/") of the system and display

all drives on the computer. This option only works when users are not locked in their home directory.

### **Hide the compressed state of files and directories**

Hides the compressed state of all compressed files and directories being viewed by the user.

### **Hide the encrypted state of files and directories**

Hides the encrypted state of all encrypted files and directories being viewed by the user.

## **Data Transfer**

### **Maximum upload speed for all group members**

Limits the maximum total bandwidth that can be used by all members of the group for all uploads. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum download speed for all group members**

Limits the maximum total bandwidth that can be used by all members of the group for all downloads. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum upload speed per session**

Limits the maximum upload bandwidth for each individual session. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum download speed per session**

Limits the maximum download bandwidth for each individual session. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum upload speed for user accounts**

Limits the maximum upload bandwidth shared between all sessions associated with an individual user account. Setting a limit of 0 KB/s means unlimited bandwidth.

### **Maximum upload file size**

Restricts the maximum single file size a user can upload to Serv-U. The file

size is measured in kilobytes.

**Maximum download speed for user accounts**

Limits the maximum download bandwidth shared between all sessions associated with an individual user account. Setting a limit of 0 KB/s means unlimited bandwidth.

**Delete partially uploaded files**

Instructs Serv-U to delete incomplete file uploads. If this option is enabled, users are not able to restart interrupted uploads using the `REST` (Restart) FTP command.

**Interpret line feed byte as a new line when in ASCII mode (Windows Only)**

When uploading and downloading files using ASCII mode, Serv-U treats <LF> characters the same as <CR><LF> end-of-line markers. Most Windows applications expect <CR><LF> to represent a new-line, as does the FTP protocol. However, since the definition of a new-line sequence is not fully defined in Windows, this option allows Serv-U to treat <LF> the same as <CR><LF>. When uploading in ASCII mode stand-alone <LF> characters are changed to <CR><LF> prior to writing to the file. When downloading in ASCII mode, stand-alone <LF> characters are changed to <CR><LF> prior to sending to the client.

**HTTP****Allow HTTP media playback**

The Serv-U Web Client supports fully interactive media playback of audio and video files. This function can be disabled during specific business hours or altogether based on business needs.

**Allow users to use Web Client**

Serv-U Web Client is enabled by default. Administrators can disallow the use of Serv-U Web Client by disabling this limit.

**Allow users to use Web Client Pro**

Serv-U Web Client Pro is enabled by default. Administrators can disallow

the use of Serv-U Web Client Pro by disabling this limit.

### **Allow users to use FTP Voyager JV**

FTP Voyager JV is enabled by default. Administrators can disallow the use of FTP Voyager JV by disabling this limit.

### **Default language for Web Client**

When the end-user connects with an unsupported language, the HTTP login page is displayed in English. The default language can be set to any language you want. When connecting to Serv-U using a supported localization of Windows, the local language of Windows is used.

### **Allow browsers to remember login information**

The HTTP login page contains a "Remember me" option (not enabled by default) that allows user names to be remembered by the login page. This feature can be disabled for security reasons.

### **Allow users to change languages**

The Serv-U Web Client is supported in many languages, but if users should not be able to select their preferred language this can be disabled.

### **Maintain file dates and times after uploading (FTP Voyager JV and Web Client Pro only)**

When enabled, Serv-U can maintain the last modification date and time of the file when end-users are using FTP Voyager JV or Web Client Pro.

When disabled, Serv-U does not set the last modification date and time of the file, it remains the date and time when the file was uploaded.

### **Allow HTTP sessions to change IP address (disabling may cause mobile devices to fail)**

The Serv-U Web Client supports the transfer of HTTP sessions if the IP address changes. This option can be disabled but it may cause mobile devices to be disconnected due to frequent IP address changes by these devices.

## Email

### **Allow end-user to set account email address**

Specifies whether users are allowed to modify their account email address using the Change Email Address option in the Web Client or File Sharing interfaces.

### **Require end-user to set email address at next HTTP login**

Specifies whether users must set their email address when they log in to Serv-U.

## File Sharing

### **Require a password for guest access**

Specifies whether it is possible to set up a file share where the guest is required to provide a password. When this limit is set to Always or Never, the creator of the file share will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share whether or not the guest must provide a password.

### **Insert passwords within invitation emails**

Specifies whether it is possible to set up a file share where the password for the share is included in the invitation email. When this limit is set to Always or Never, the creator of the file share will not be able to specify this optional setting. When this limit is set to Optional, the **Include the password in the email** option can be selected individually in each file share.

### **Maximum file size guests can upload (per file)**

Specifies the file size constraints imposed upon the guest user. If set to zero, there is no file size constraint. In this case, the creator of the file share request can specify the maximum file size in each file share request without an upper limit.

### **Allow user-defined guest link expiration**

When enabled, users will be able to specify link expiration dates individually in the Request Files and Send Files wizards. When disabled,

the file share links will expire after the number of days specified in the **Duration before guest link expires** limit.

### **Duration before guest link expires**

Limits the number of days after which a file share link expires if the Allow user-defined guest link expiration limit is disabled.

### **Notify user after a file is downloaded**

Specifies whether the **Notify me when the file(s) have been downloaded** option can be used in the Send Files wizard. When this limit is set to Always or Never, the creator of the file share will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share whether to receive notification of the file download.

### **Notify user after a file is uploaded**

Specifies whether the **Notify me when the file(s) have been uploaded** option can be used in the Request Files wizard. When this limit is set to Always or Never, the creator of the file share request will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share request whether to receive notification of the file upload.

### **Send the guest access link to the recipients**

Specifies whether the **Automatically send the download/upload link to the guest user(s) in email** option can be used in the Send Files and Request Files wizards. When this limit is set to Always or Never, the user will not be able to specify this optional setting. When this limit is set to Optional, the user can individually specify in each file share or file share request whether to send the access link automatically.

### **Send the guest access link to the sender**

Specifies whether the **Send me an email copy with the download/upload link** option can be used in the Send Files and Request Files wizards. When this limit is set to Always or Never, the user will not be able to specify this optional setting. When this limit is set to Optional, the user can individually

specify in each file share or file share request whether to receive an email copy with the download/upload link.

**Allow file sharing**

Specifies whether the user is allowed to use file sharing.

**Allow user-defined contact information**

When enabled, users will be able to edit their name and email address in the Request Files and Send Files wizards. When disabled, users are not allowed to edit their contact information in the Request Files and Send Files wizards.

**Maximum number of files for "Sent" shares**

Specifies the maximum number of files users can include in a single file share. If set to 0, the default limit of 20 is used.

**Maximum number of files for "Requested" shares**

Specifies the maximum number of files users can upload after receiving a file share request. If set to 0, the default limit of 20 is used.

**Allowed "Sent" file share sources**

Specifies the valid file sharing sources that users can browse to when they create an outgoing file share. By default, users can browse to any file stored on their computer or on Serv-U.

**Advanced**

**Convert URL characters in commands to ASCII**

Instructs Serv-U to convert special characters contained in command parameters to plain ASCII text. Certain web browsers can encode special characters contained in file names and directories when using the FTP protocol. This attribute allows Serv-U to decode these special characters.

**Maximum Supported SFTP Version**

Specifies the maximum version of SFTP permitted for SFTP connections. Serv-U supports SFTP versions 3 - 6.

### **Automatically check directory sizes during upload**

Instructs Serv-U to occasionally check the size of directories in which a maximum directory size has been specified. This attribute ensures that Serv-U always has updated directory sizes available instead of having to calculate them at transfer time, which can be a time consuming operation.

### **Allow Rename Overwrite**

When enabled (default) Serv-U allows files to be renamed to files where the destination already exists. When disabled users are not allowed to rename a file or directory to a path name that already exists.

### **Apply server and domain directory access rules before user and group**

The order in which directory access rules are listed has significance in determining the resources that are available to a user or group account. By default, directory access rules specified at the group or user level take precedence over ones specified at the domain and server level. However, there are certain instances where you may want the domain and server level rules to take precedence. Setting this value to "Yes" places the group's and user's directory access rules *below* the server and domain. For more information, see the "Apply group directory access rules first" setting in "Group information".

### **Days before automatically disabling account to trigger the pre-disable event**

The number of days prior to automatically disabling the user account that the pre-disable event should be triggered.

### **Days before automatically deleting account to trigger the pre-delete event**

The number of days prior to automatically deleting the user account that the pre-delete event should be triggered.

### **Reset user stats after restart**

When this limit is enabled, the user statistics are reset after a server restart.

### **Reset group stats after restart**

When this limit is enabled, the group statistics are reset after a server restart.



**Owner ID (user name) for created files and directories (Linux Only)**

The user name given to set as owner of a created file or directory.

**Group ID (group name) for created files and directories (Linux Only)**

The group name given to set as owner of a created file or directory.

## Ratio Free Files

Files listed in the ratio free file list are exempt from any imposed transfer ratios. In other words, if a user must upload files in order to earn credits towards downloading a file, a file that matches an entry in this list can always be downloaded by users, even if they have no current credits. This is commonly used to make special files, such as a readme or a directory information file, always accessible to users.

You can use the '\*' and '?' wildcard characters when specifying a ratio free file. Using '\*' specifies a wildcard of any kind of character and any length. For example, entering \*.txt makes any file with a .txt extension free for download, regardless of the actual file name. A '?' can be used to represent a single character within the file name or directory. Finally, full paths can be specified by using standard directory paths such as C:\ftproot\common\ (on Windows) or /var/ftpfiles/shared/ (on Linux).

In addition, full or relative paths can be used when making an entry. If a full path is used when specifying a file name, only that specific file is exempt from transfer ratios. If a relative path is used, such as entering only readme.txt, the provided file is exempt from transfer ratios regardless of the directory it is located in.

## SFTP (Secure File Transfer over SSH2) for users and groups

**Using an existing public key**

1. Obtain a public key file.
2. Place the public key file in a secured directory in the server, and then use

**Browse** in Serv-U to select the file.

3. Click **Save**.

### Creating a key pair

1. Click **Manage Keys**.
2. Click **Create Key**.
3. Type the name of the key pair (for example, `MyKey`), which is also used to name the storage file.
4. Type the output directory of the certificate (for example, `C:\ProgramData\RhinoSoft\Serv-U\`).
5. Select the key type (default of DSA is preferred, but RSA is available).
6. Select the key length (default of 1024 bits provides best performance, 2048 bits is a good median, and 4096 bits provides best security).
7. Enter the password to use for securing the key file.
8. Click **Create**.

### Creating multiple keys per user

For the purposes of public key authentication, you can associate multiple public keys with a user account.

#### To create multiple keys for an account:

1. Click **Manage Keys**.
2. Click **Add Key**, and then specify the key name and the key path.

When authenticating a client, Serv-U checks all the keys you provide here. If authenticating against one key fails, Serv-U proceeds to check the next key.

For optimal results, the following best practices are recommended:

- It is recommended that you do not create more than 100 keys per user account.

## SFTP (Secure File Transfer over SSH2) for users and groups

---

- If you have a large number of public keys, divide the keys between multiple users, and define the common user properties at group level.
- Avoid storing the public keys in a network path.

## Chapter 7: System variables

You can customize certain configurable messages in Serv-U to include a wide range of variables as outlined in the following list. These variables are replaced at run time with the appropriate value allowing up-to-date statistics and feedback to be provided to logged in users. Some of the places where you can use these variables include event messages, customized FTP command responses, or a welcome message.

Furthermore, you can also use the `%USER%`, `%HOME%`, `%USER_FULL_NAME%`, and `%DOMAIN_HOME%` variables. For more information about these variables, see "Directory access rules".

All variables are case sensitive. Statistical information, unless otherwise specified, is calculated since the Serv-U File Server was last started.

### Server information

#### **\$ServerName**

Displays the full name of the server (that is, Serv-U).

#### **\$ServerVersionShort**

Displays the first two digits of the current version of the Serv-U File Server (for example, 15.1).

#### **\$ServerVersionLong**

Displays the full version number of the Serv-U File Server (for example, 15.1.0.480).

#### **\$OS**

Displays the name of the operating system (for example, Windows Server 2008 R2).

#### **\$OSVer**

Displays the full version number of the operating system (for example, 6.1.7601).

**\$OSAndPlatform**

Displays the name of the operating system (for example, Windows Server 2008 R2) and platform (for example, 32-bit or 64-bit).

**\$OSCaseSensitive**

States if the operating system is case sensitive.

**\$ComputerName**

Displays the name of the computer retrieved from the operating system, normally the same as the UNC name on a Windows network (for example, WEB-SERVER-01).

**\$EventName**

Contains the configured name of the event.

**\$EventType**

Contains the type of the event that was triggered.

**\$EventDescription**

Contains the configured description of the event.

**\$LogFilePath**

Retrieves the path to the log file (Log File Deleted and Log File Rotated Events only).

**\$OldLogFilePath**

Retrieves the old path to the log file (Log File Rotated Events only).

**\$GatewayIPAddress**

Retrieves the Gateway IP address (Gateway Listener Success, Gateway Listener Failure, Permanent Gateway Listener Success, Permanent Gateway Listener Failure Events only)

**\$GatewayPort**

Retrieves the Gateway port (Gateway Listener Success, Gateway Listener Failure, Permanent Gateway Listener Success, Permanent Gateway Listener Failure Events only).

**\$ListenerIPAddress**

Retrieves the listener IP address (Listener Success, Listener Failure, Permanent Listener Success, Permanent Listener Failure Events only).

**\$ListenerPort**

Retrieves the listener port (Listener Success, Listener Failure, Permanent Listener Success, Permanent Listener Failure Events only).

**\$ListenerType**

Retrieves the listener type (Listener Success, Listener Failure, Permanent Listener Success, Permanent Listener Failure Events only).

**\$ListenResult**

Retrieves the listener result (Listener Success, Listener Failure, Permanent Listener Success, Permanent Listener Failure Events only).

**Server statistics**

**\$ServerDays**

Displays the total number of days the server has been online continuously.

**\$ServerHours**

Displays the number of hours from 0 to 24 the server has been online, carries over to \$ServerDays.

**\$ServerMins**

Displays the number of minutes from 0 to 60 the server has been online, carries over to \$ServerHours.

**\$ServerSecs**

Displays the number of seconds from 0 to 60 the server has been online, carries over to \$ServerMins.

**\$ServerKUp**

Displays the total number of kilobytes uploaded.

**\$ServerKDown**

Displays the total number of kilobytes downloaded.

**\$ServerFilesUp**

Displays the total number of files uploaded.

**\$ServerFilesDown**

Displays the total number of files downloaded.

**\$ServerFilesTot**

Displays the total number of files transferred, essentially (\$ServerFilesUp + \$ServerFilesDown).

**\$LoggedInAll**

Displays the total number of established sessions.

**\$ServerUploadAvgKBps**

Displays the average upload rate in KB/s.

**\$ServerDownloadAvgKBps**

Displays the average download rate in KB/s.

**\$ServerAvg**

Displays the average data transfer rate (uploads and downloads) in KB/s.

**\$ServerUploadKBps**

Displays the current upload transfer rate in KB/s.

**\$ServerDownloadKBps**

Displays the current download transfer rate in KB/s.

**\$ServerKBps**

Displays the current aggregate data transfer rate in KB/s.

**\$ServerSessions24HPlusOne**

Displays the total number of sessions in the past 24 hours plus one additional session.

**\$ServerSessions24H**

Displays the total number of sessions in the past 24 hours.

## **Domain statistics**

### **\$DomainKBup**

Displays the total number of kilobytes uploaded.

### **\$DomainKBdown**

Displays the total number of kilobytes downloaded.

### **\$DomainFilesUp**

Displays the total number of files uploaded.

### **\$DomainFilesDown**

Displays the total number of files downloaded.

### **\$DomainFilesTot**

Displays the total number of files transferred, essentially (\$DomainFilesUp + \$DomainFilesDown).

### **\$DomainLoggedIn**

Displays the total number of sessions currently connected.

### **\$DomainUploadAvgKBps**

Displays the average upload rate in KB/s.

### **\$DomainDownloadAvgKBps**

Displays the average download rate in KB/s.

### **\$DomainAvg**

Displays the average aggregate data transfer rate (uploads and downloads) in KB/s.

### **\$DomainUploadKBps**

Displays the current upload transfer rate in KB/s.

### **\$DomainDownloadKBps**

Displays the current download transfer rate in KB/s.

### **\$DomainKBps**

Displays the current aggregate data transfer rate in KB/s.



**\$DomainSessions24HPlusOne**

Displays the total number of sessions in the past 24 hours plus one additional session.

**\$DomainSessions24H**

Displays the total number of sessions in the past 24 hours.

**User statistics - Applies to all sessions attached to the user account**

**\$UserKBUp**

Displays the total number of kilobytes uploaded.

**\$UserKBDown**

Displays the total number of kilobytes downloaded.

**\$UserKBTot**

Displays the total amount of kilobytes transferred.

**\$UserLoggedIn**

Displays the total number of sessions.

**\$UserUploadAvgKBps**

Displays the average upload rate in KB/s.

**\$UserDownloadAvgKBps**

Displays the average download rate in KB/s.

**\$UserAvg**

Displays the average aggregate data transfer rate (uploads and downloads) in KB/s.

**\$UserUploadKBps**

Displays the current upload transfer rate in KB/s.

**\$UserDownloadKBps**

Displays the current download transfer rate in KB/s.

**\$UserKBps**

Displays the current aggregate data transfer rate in KB/s.

Last transfer statistics - Applies to the most recently completed successful data

---

**\$UserSessions24HPlusOne**

Displays the total number of sessions in the past 24 hours plus one additional session.

**\$UserSessions24H**

Displays the total number of sessions in the past 24 hours.

**Last transfer statistics - Applies to the most recently completed successful data transfer**

**\$TransferBytesPerSecond**

Displays the effective (compressed) transfer rate in bytes/s.

**\$TransferKBPerSecond**

Displays the effective (compressed) transfer rate in KB/s.

**\$TransferBytes**

Displays the effective (compressed) number of bytes transferred, formatted for display, for example, 32,164.

**\$NoFormatTransferBytes**

Displays the effective (compressed) number of bytes transferred, unformatted, for example, 32164.

**\$TransferKB**

Displays the effective (compressed) number of kilobytes transferred, formatted for display.

**\$ActualTransferBytesPerSecond**

Displays the actual (uncompressed) transfer rate in bytes/s.

**\$ActualTransferKBPerSecond**

Displays the actual (uncompressed) transfer rate in KB/s.

**\$ActualTransferBytes**

Displays the actual (uncompressed) number of bytes transferred, formatted for display, for example, 32,164.

### **\$NoFormatActualTransferBytes**

Displays the actual (uncompressed) number of bytes transferred, unformatted, for example, 32164.

### **\$ActualTransferKB**

Displays the actual (uncompressed) number of kilobytes transferred, formatted for display.

### **\$CompressionRatio**

Displays the ratio of compression for the transfer expressed as a percentage of the expected amount of data transferred. For example, a value of 100.00 means the data could not be compressed. A value of 200.00 means the data compressed to half its original size.

### **\$CommandResult**

Displays the command result in the return response of any command, providing information such as compression level, and so on. (FTP only)

### **\$Command**

Displays the FTP command name, such as RETR, MODE, or SIZE. (FTP only)

### **\$Parameters**

Displays the parameters used for the command, such as "Z" for the MODE command indicating the compression type, a file name for the STOR command, and so on. (FTP only)

### **\$DataMode**

Displays the data transfer mode for an FTP data transfer, which may be either BINARY for binary mode transfers or ASCII for ASCII mode data transfers. (FTP only)

### **\$CurrentCompressedTransferBytes**

Displays the current effective (compressed) number of bytes transferred so far, unformatted, for example, 32164. (FTP only)

**\$CurrentUncompressedTransferBytes**

Displays the current actual (uncompressed) number of bytes transferred so far, unformatted, for example, 32164. (FTP only)

**Date/Time**

**\$Date**

Displays the current date according to the Serv-U File Server, in the local date format of the system.

**\$Time**

Displays the current time according to the Serv-U File Server, in the local time format of the system.

**\$Day**

Displays the day of the month.

**\$Month**

Displays the two-digit numeric month.

**\$TextMonth**

Displays the text version of the month.

**\$Year**

Displays the four-digit year.

**\$2DigitYear**

Displays the two-digit year.

**\$Hour**

Displays the hour (24-hour clock).

**\$Minute**

Displays the minute.

**\$Second**

Displays the second.

## **Server settings**

### **\$MaxUsers**

Displays the maximum number of sessions allowed to log in, which could be limited by the license.

### **\$MaxAnonymous**

Displays the maximum number of anonymous users allowed to log in.

## **Session information - Applies to the current session**

### **\$Name**

Displays the login ID of the attached user account.

### **\$LoginID**

Displays the session's login ID, operates like \$Name. \$Name can refer to the login ID for target user accounts but \$LoginID refers only to the login ID of the session.

### **\$IP**

Displays the client IP address.

### **\$IPName**

Displays the reverse DNS name as obtained by performing a reverse DNS lookup on \$IP.

### **\$Dir**

Displays the session's current directory.

### **\$Disk**

The local drive letter being accessed.

### **\$DFree**

Displays the amount of free space on \$Disk in MB

### **\$FUp**

Displays the total number of files uploaded.

**\$FDown**

Displays the total number of files downloaded.

**\$FTot**

Displays the total number of files transferred, essentially (\$FUp + \$FDown).

**\$BUp**

Displays the total number of kilobytes uploaded .

**\$Bdown**

Displays the total number of kilobytes downloaded.

**\$BTot**

Displays the total number of kilobytes transferred.

**\$TConM**

Displays the total number of minutes the session has been connected.

**\$TConS**

Displays the number of seconds from 0 to 60 that the session has been connected, carries over to \$TconM.

**\$RatioUp**

Displays the 'upload' portion of the applied ratio, "N/A" if not in use.

**\$RatioDown**

Displays the 'download' portion of the applied ratio, "N/A" if not in use.

**\$RatioType**

Displays the type of ratio being applied, either per session or per user.

**\$RatioCreditType**

Displays the type of ratio credit granted for transfers, either per bytes or per complete file.

**\$RatioCredit**

Displays the current transfer credit for the applied ratio, either megabytes or complete files.

### **\$QuotaUsed**

Displays how much disk quota is currently being used in MB, "Unlimited" if no quota is in use.

### **\$QuotaLeft**

Displays how much disk quota is available in MB, "Unlimited" if no quota is in use.

### **\$QuotaMax**

Displays the maximum amount of disk space that can be used in MB, "Unlimited" if no quota is in use.

### **\$CurrentDirMaxSize**

Displays the maximum size of the current directory in MB. If the directory has no size limit, the variable will return "unlimited". If permission is denied in the directory, or any other error occurs, the value "N/A" will be returned.

### **\$SessionID**

Displays the unique session ID of the current session. Session IDs are counted from 000001, and the counter is reset each time Serv-U is started.

### **\$Protocol**

Displays the current protocol being used (FTP, FTPS, HTTP, HTTPS, or SFTP (SSH2)).

### **\$UserDomainName**

Uses either the logged in domain name or the user's parent domain name. A blank name is returned if the user is a global server user that is not logging in.

### **\$DomainName**

Displays the current domain that the session is logged into.

### **\$DomainDescription**

Displays the description of the current domain that the session is logged into.

**\$TimeRemaining**

Displays the time remaining when blocking an IP address for an amount of time (available only in Event notifications).

**\$LocalHomeDirectory**

Displays the local home directory. It should only be used for events that need this specific information such as user creation.

**\$Password**

Displays the password associated with the user account. It is intended only for events. It should NOT be used for welcome messages.

**\$UserEmailAddress**

Displays the user's email address.

**\$FullName**

Displays the user's full name as entered into the "Full Name" field for a user account.

**\$SpaceFullName**

The same as "\$FullName" with the addition of a space before the user's full name. Blank (no space or name) when the user's full name is empty.

**\$FullNameSpace**

The same as "\$FullName" with the addition of a space after the user's full name. Blank (no space or name) when the user's full name is empty.

**\$Port**

Displays the port number of the client.

**\$ServerIP**

Displays the IP address of the server.

**\$ServerPort**

Displays the port number of the server.

**Note:** Using the \$IPName variable inside of an event or sign-on message can cause a slight delay while the reverse DNS information for \$IP is retrieved.



**File information - Applies to the last remotely accessed file, which is not necessarily the last transferred file**

**\$PathName**

Retrieves the full remote path.

**\$FileName**

Retrieves only the file name from \$PathName.

**\$FileSize**

Retrieves the size, in bytes, of the file from \$FileName.

**\$FileSizeFmt**

Displays a formatted version of the file size, containing the thousands separator (comma or period depending on the computer's regional settings).

**\$FileSizeKB**

Displays a formatted floating point value representing the file size in KB.

**\$LocalPathName**

Retrieves the fully qualified local path name for an operation, as it relates to Windows. For example `C:\Temp\File.fid` instead of `/Temp/file.fid`.

**\$LocalFileName**

Retrieves the name of the file as it is stored on the local computer. See \$LocalPathName for details.

**\$OldLocalPathName**

Same as \$LocalPathName, but contains the path prior to renaming.

**\$OldLocalFileName**

Same as \$LocalFileName, but contains the file name prior to renaming.

**\$OldPathName**

Retrieves the remote path name prior to renaming.

**\$OldFileName**

Retrieves the remote file name prior to renaming.

## **Current activity**

### **\$UNow**

Displays the current number of sessions on the Serv-U File Server.

### **\$UAll**

Displays the total number of sessions that have connected to the Serv-U File Server since it was last started.

### **\$U24h**

Displays the total number of sessions that have connected to the Serv-U File Server in the last 24 hours.

### **\$UAnonAll**

Displays the current number of sessions attributed to the anonymous user on the Serv-U File Server.

### **\$UAnonThisDomain**

Displays the current number of sessions attributed to the anonymous user on the connected domain.

### **\$UNonAnonAll**

Displays the current number of sessions not attributed to the anonymous user on the Serv-U File Server.

### **\$UNonAnonThisDomain**

Displays the current number of sessions not attributed to the anonymous user on the connected domain.

### **\$UThisName**

Displays the current number of sessions attributed to the connected user account.