

Dynamic Host Configuration Protocol (DHCP)

CCNA Routing and Switching

Routing and Switching Essentials v6.0

Chapter 8: DHCP



Sections & Objectives

▪ DHCPv4

- Implement DHCPv4 to operate across multiple LANs in a small to medium-sized business network.
- Explain how DHCPv4 operates in a small- to medium-sized business network.
- Configure a router as a DHCPv4 server.
- Configure a router as a DHCPv4 client.
- Troubleshoot a DHCP configuration for IPv4 in a switched network.

▪ DHCPv6

- Implement DHCPv6 to operate across multiple LANs in a small to medium-sized business network.
- Explain the operation of DHCPv6.
- Configure stateless DHCPv6 for a small to medium-sized business.
- Configure stateful DHCPv6 for a small to medium-sized business.


Troubleshoot a DHCP configuration for IPv6 in a switched network.

DHCPv4

DHCPv4 Operation

Introducing DHCPv4


- DHCPv4 assigns IPv4 addresses and other network configuration information dynamically.
 - A dedicated DHCPv4 server is scalable and relatively easy to manage.
 - A Cisco router can be configured to provide DHCPv4 services in a small network.



Introducing DHCPv4


DHCPv4 uses three different address allocation methods:

- **Manual Allocation** – The administrator assigns a pre-allocated IPv4 address to the client, and DHCPv4 communicates only the IPv4 address to the device.
- **Automatic Allocation** – DHCPv4 automatically assigns a static IPv4 address permanently to a device, selecting it from a pool of available addresses.
- **Dynamic Allocation** – DHCPv4 dynamically assigns, or leases, an IPv4 address from a pool of addresses for a limited period of time chosen by the server, or until the client no longer needs the address. This method is the most commonly used.



DHCPv4 Operation

DHCPv4 Operation




- Four step process for a client to obtain a lease:

- DHCP Discover (DHCPDISCOVER)** - client uses Layer 2 and Layer 3 broadcast addresses to find a DHCP server.
- DHCP Offer (DHCPOFFER)** - DHCPv4 server sends the binding DHCPOFFER message to the requesting client as a unicast.
- DHCP Request (DHCPREQUEST)** – the client sends back a broadcast DHCPREQUEST in response to the servers offer.
- DHCP Acknowledgment (DHCPACK)** – the server replies with a unicast DHCPACK message.


DHCPv4 Operation

DHCPv4 Operation – Lease renewal





Message Format & Fields

- DHCPv4 messages:
 - If sent from the client, use UDP source port 68 and destination port 67.
 - If sent from the server, use UDP source port 67 and destination port 68.



DHCPv4 Operation

DHCPv4 Discover and Offer Messages



Configuring a Basic DHCPv4 Server

- Configuring a Cisco router as a DHCPv4 server:
 - Excluding IPv4 Addresses – **ip dhcp excluded-address** can exclude a single address or a range of addresses from being assigned.
 - Configuring a DHCPv4 Pool - **ip dhcp pool pool-name** command creates a pool with the specified name and puts the router in DHCPv4 configuration mode.
 - Address pool assigned using **network** command.
 - Default gateway assigned using **default-router** command.
 - Other commands are optional.

```
R1(config)# ip dhcp excluded-address 192.168.10.1 192.168.10.9
R1(config)# ip dhcp excluded-address 192.168.10.254
R1(config)# ip dhcp pool LAN-POOL-1
R1(dhcp-config)# network 192.168.10.0 255.255.255.0
R1(dhcp-config)# default-router 192.168.10.1
R1(dhcp-config)# dns-server 192.168.11.5
R1(dhcp-config)# domain-name example.com
R1(dhcp-config)# end
R1#
```

Configuring a Basic DHCPv4 Server

Verifying DHCPv4

```
R1# show running-config | section dhcp
ip dhcp excluded-address 192.168.10.1 192.168.10.9
ip dhcp excluded-address 192.168.10.254
ip dhcp excluded-address 192.168.11.1 192.168.11.9
ip dhcp excluded-address 192.168.11.254
ip dhcp pool LAN-POOL-1
 network 192.168.10.0 255.255.255.0
 default-router 192.168.10.1
 dns-server 192.168.11.5
 domain-name example.com
ip dhcp pool LAN-POOL-2
 network 192.168.11.0 255.255.255.0
 default-router 192.168.11.1
 dns-server 192.168.11.5
 domain-name example.com
R1#
```

```
R1# show ip dhcp binding
Bindings from all pools not associated with VRF:
IP address      Client-ID/      Lease expiration    Type
                Hardware address/
                User name
192.168.10.10    0100.e018.5bdd.35  May 28 2013 01:06 PM Automatic
192.168.11.10    0100.b0d0.d817.e6  May 28 2013 01:10 PM Automatic
```


```
R1# show ip dhcp server statistics
Memory usage      25307
Address pools     2
Database agents   0
Automatic bindings 2
Manual bindings   0
Expired bindings  0
Malformed messages 0
Secure arp entries 0

Message           Received
BOOTREQUEST       0
DHCPDISCOVER      8
DHCPREQUEST       3
DHCPDECLINE       0
DHCPRELEASE       0
DHCPINFORM        0
```

- Verify DHCPv4 configuration using the **show running-config |section dhcp** command.
- Verify the operation of DHCPv4 using the **show ip dhcp binding** command.
- Verify that messages are being received or sent by the router using the **show ip dhcp server statistics** command.

Verifying a DHCPv4 Client

- Commands to verify DHCP:
- On the PC, issue the `ipconfig /all` command.



```
C:\WINDOWS\system32\cmd.exe

WINS Proxy Enabled .....: No

Ethernet Adapter Local Area Connection

Connection-specific DNS Suffix.: example.com
Description .....: SiS 900 PCI Fast Ethernet Adapter

Physical Address.....: 00-E0-18-5B-DD-35
Dhcp Enabled .....: Yes
Autoconfiguration Enabled.....: Yes
IP Address .....: 192.168.10.10
Subnet Mask.....: 255.255.255.0
Default Gateway.....: 192.168.10.1
DHCP Server .....: 192.168.10.1
Lease Obtained.....: Monday, May 27, 2013 1:06:22PM


Lease Expires .....: Tuesday, May 28, 2013 1:06:22PM

DNS Servers . . . . .: 192.168.11.5

C:\Documents and settings\SpanPC>
```

Configuring a Basic DHCPv4 Server

DHCPv4 Relay




```
R1(config)# interface g0/0
R1(config-if)# ip helper-address 192.168.11.6
R1(config-if)# end
R1# show ip interface g0/0
GigabitEthernet0/0 is up, line protocol is up
Internet address is 192.168.10.1/24
Broadcast address is 255.255.255.255
Address determined by setup command
MTU is 1500 bytes
Helper address is 192.168.11.6
<output omitted>
```

- DHCPDISCOVER messages are sent as broadcast messages.
- Routers do not forward broadcasts.
- A Cisco IOS helper address is configured so that the router acts as a relay agent forwarding the message to the DHCPv4 server.

Configuring DHCPv4 Client

Configuring a Router as DHCPv4 Client

- Small office/home office (SOHO) and branch sites often have to be configured as DHCPv4 clients.
- Use the **ip address dhcp** interface configuration mode command.



Configuring a Wireless Router as a DHCPv4 Client

The screenshot shows the configuration interface of a Wireless-N Broadband Router (WRT300N) with firmware version v0.93.3. The 'Setup' tab is selected, and the 'Internet Setup' section is active. The 'Internet Connection type' is set to 'Automatic Configuration - DHCP'. Under 'Optional Settings (required by some internet service providers)', the 'Host Name' and 'Domain Name' fields are empty, and the 'MTU' is set to 1500. A 'Help...' link is visible on the right side of the configuration area.

Wireless-N Broadband Router
Firmware Version: v0.93.3

Setup | Wireless Security | Access Restrictions | Applications & Gaming | Administration | Status

Basic Setup | DDNS | MAC Address Clone | Advanced Routing

Internet Setup

Internet Connection type: Automatic Configuration - DHCP

Optional Settings (required by some internet service providers)

Host Name:

Domain Name:

MTU: Size: 1500

Help...

- Wireless routers are set to receive IPv4 addressing information automatically from the ISP.

Troubleshooting Tasks

Troubleshooting Task 1:	Resolve address conflicts.
Troubleshooting Task 2:	Verify physical connectivity.
Troubleshooting Task 3:	Test with a static IPv4 address.
Troubleshooting Task 4:	Verify switch port configuration.
Troubleshooting Task 5:	Test from the same subnet or VLAN.

```
R1# show ip dhcp conflict
IP address Detection Method Detection time
192.168.10.32 Ping Feb 16 2013 12:28 PM
192.168.10.64 Gratuitous ARP Feb 23 2013 08:12 AM
```


Verify Router DHCPv4 Configuration

```
R1# show running-config | section interface GigabitEthernet0/0
interface GigabitEthernet0/0
  ip address 192.168.10.1 255.255.255.0
  ip helper-address 192.168.11.6
  duplex auto
  speed auto
R1#

R1# show running-config | include no service dhcp
R1#
```

- Verify DHCPv4 Relay - use **show running-config** command to verify that the ip helper address is configured.
- Verify DHCPv4 configuration - use the **show running-config | include no service dhcp** command to verify dhcp is enabled because there is no match for the **no service dhcp**.

Debugging DHCPv4


- The extended ACL is used with the **debug ip packet** command to display only DHCPv4 messages.
- Another troubleshooting command is the **debug ip dhcp server events**.

```
R1(config)# access-list 100 permit udp any any eq 67
R1(config)# access-list 100 permit udp any any eq 68
R1(config)# end
R1# debug ip packet 100
IP packet debugging is on for access list 100
*IP: s=0.0.0.0 (GigabitEthernet0/1), d=255.255.255.255,
len 333, rcvd 2
*IP: s=0.0.0.0 (GigabitEthernet0/1), d=255.255.255.255,
len 333, stop process pak for forus packet
*IP: s=192.168.11.1 (local), d=255.255.255.255
(GigabitEthernet0/1), len 328, sending broad/multicast
<output omitted>

R1# debug ip dhcp server events
DHCPD: returned 192.168.10.11 to address pool LAN-POOL-1
DHCPD: assigned IP address 192.168.10.12 to client
0100.0103.85e9.87.
DHCPD: checking for expired leases.
DHCPD: the lease for address 192.168.10.10 has expired.
DHCPD: returned 192.168.10.10 to address pool LAN-POOL-1
```

DHCPv6

Stateless Address Autoconfiguration (SLAAC)




- Two methods to dynamically assign IPv6 global unicast addresses:
 - Stateless Address Autoconfiguration (SLAAC).
 - Dynamic Host Configuration Protocol for IPv6 (Stateful DHCPv6).
- SLAAC uses ICMPv6 Router Solicitation and Router Advertisement messages to provide addressing and other configuration information.


SLAAC and DHCPv6

SLAAC Operation

- The router must have IPv6 routing enabled–**ipv6 unicast-routing**
- PC1 sends an RS message to the all-routers multicast address (FF02::02) that it needs an RA.
- R1 responds with an RA message that has the prefix and prefix length of the network (FF02::01)
- PC1 uses this information to create its IPv6 global unicast address. It creates its interface id using EUI-64 or randomly generates it.
- PC1 must verify that the address is unique by sending an ICMPv6 Neighbor Solicitation message.



SLAAC and DHCPv6




- Different combinations of the Managed Address Configuration flag (M flag) and the Other Configuration flag (O flag) in the RA determine how the IPv6 address is assigned:
 - SLAAC (Router Advertisement only)
 - Stateless DHCPv6 (Router Advertisement and DHCPv6)
 - Stateful DHCPv6 (DHCPv6 only)

SLAAC and DHCPv6

SLAAC Option


- SLAAC is the default on Cisco routers. Both the M flag and the O flag are set to 0 in the RA.
- This option instructs the client to use the information in the RA message only.



SLAAC and DHCPv6

Stateless DHCPv6 Option


- DHCPv6 is defined in RFC 3315.
- Stateless DHCPv6 option - client uses the RA message for addressing, additional parameters are obtained from DHCPv6 server.
- O flag is set to 1 and the M flag is left at the default setting of 0. Use command **ipv6 nd other-config-flag**.



SLAAC and DHCPv6


Stateful DHCPv6 Option

- RA message informs the client not to use the information in the RA message.
- All addressing and configuration information must be obtained from a stateful DHCPv6 server.
- M flag is set to 1. Use the command **ipv6 nd managed-config-flag**.



SLAAC and DHCPv6

DHCPv6 Operations



- DHCPv6 messages from server to client use UDP port 546. Client to server use UDP port 547.
- Client sends a DHCPv6 SOLICIT message using FF02::1:2.
- DHCPv6 server responds with a DHCPv6 ADVERTISE unicast message.
- Stateless DHCPv6 client - Generates its own address. Sends a DHCPv6 INFORMATION-REQUEST to the DHCPv6 server requesting only configuration parameters.
- Stateful DHCPv6 client - Sends a DHCPv6 REQUEST message to server for an IPv6 address and all other configuration parameters.


Configuring a Router as a Stateless DHCPv6 Server

- **Step 1** – Enable IPv6 routing. **ipv6 unicast-routing**
- **Step 2** – Configure a DHCPv6 pool. **ipv6 dhcp pool** *pool-name*
- **Step 3** – Configure pool parameters. **dns-server** *server-address*
- **Step 4** – Configure the DHCPv6 interface **ipv6 dhcp server** *pool-name*

```
R1(config)# ipv6 unicast-routing
R1(config)# ipv6 dhcp pool IPV6-STATELESS
R1(config-dhcpv6)# dns-server 2001:db8:cafe:aaaa::5
R1(config-dhcpv6)# domain-name example.com
R1(config-dhcpv6)# exit
R1(config)# interface g0/1
R1(config-if)# ipv6 address 2001:db8:cafe:1::1/64
R1(config-if)# ipv6 dhcp server IPV6-STATELESS
R1(config-if)# ipv6 nd other-config-flag
```

Configuring a Router as a Stateless DHCPv6 Client

- **Step 1** – IPv6 enabled on interface **ipv6 enable**
- **Step 2** – enable automatic configuration of IPv6 addressing **ipv6 address autoconfig**



Verifying Stateless DHCPv6

■ Commands to verify Stateless DHCPv6:

- **show ipv6 dhcp pool**
- **show running-config**
- **show ipv6 interface**
- **debug ipv6 dhcp detail**

```
R1# show ipv6 dhcp pool
DHCPv6 pool: IPV6-STATELESS
  DNS server: 2001:DB8:CAFE:AAAA::5
  Domain name: example.com
  Active clients: 0
R1#
```


```
R3# show ipv6 interface g0/1
GigabitEthernet0/1 is up, line protocol is up
IPv6 is enabled, link-local address is FE80::32F7:DFF:FE25:2DE1
No Virtual link-local address(es):
Stateless address autoconfig enabled
Global unicast address(es):
  2001:DB8:CAFE:1:32F7:DFF:FE25:2DE1, subnet is 2001:DB8:CAFE:1::/64 [EUI/CAL/PRE]
    valid lifetime 2591935 preferred lifetime 604735
Joined group address(es):
  FF02::1
  FF02::1:FF25:2DE1
MTU is 1500 bytes
ICMP error messages limited to one every 100 milliseconds
ICMP redirects are enabled
ICMP unreachable are sent
ND DAD is enabled, number of DAD attempts: 1
ND reachable time is 30000 milliseconds (using 30000)
ND NS retransmit interval is 1000 milliseconds
Default router is FE80::D68C:B5FF:FECE:A0C1 on
  GigabitEthernet0/1
R3#
```

Configuring a Router as a Stateful DHCPv6 Server

- **Step 1** – Enable IPv6 Routing.
 - **ipv6 unicast routing**
- **Step 2** – Configure a DHCPv6 pool.
 - **ipv6 dhcp pool** *pool-name*
- **Step 3** – Configure pool parameters:
 - **address prefix** *prefix/length*
 - **dns-server** *dns-server-address*
 - **domain-name** *domain-name*
- **Step 4** - Configure DHCPv6 interface:
 - **ipv6 dhcp server** *pool-name*
 - **ipv6 nd managed-config-flag**

```
R1(config)# ipv6 unicast-routing
R1(config)# ipv6 dhcp pool IPV6-STATEFUL
R1(config-dhcpv6)# address prefix 2001:DB8:CAFE:1::/64 lifetime infinite
R1(config-dhcpv6)# dns-server 2001:db8:cafe:aaaa::5
R1(config-dhcpv6)# domain-name example.com
R1(config-dhcpv6)# exit
R1(config)# interface g0/1
R1(config-if)# ipv6 address 2001:db8:cafe:1::1/64
R1(config-if)# ipv6 dhcp server IPV6-STATEFUL
R1(config-if)# ipv6 nd managed-config-flag
```

Configuring a Router as a Stateful DHCPv6 Client



- **Step 1** – Allow the router to send RS messages and participate in DHCPv6.
 - **ipv6 enable**
- **Step 2** – Make the router a DHCPv6 client.
 - **ipv6 address dhcp**


Verifying Stateful DHCPv6

- Use the following commands to verify Stateful DHCPv6:
 - **show ipv6 dhcp pool**
 - **show ipv6 dhcp binding**
 - **show ipv6 interface**

```
R1# show ipv6 dhcp binding
Client: FE80::32F7:DFF:FE25:2DE1
DUID: 0003000130F70D252DE0
Username : unassigned
IA NA: IA ID 0x00040001, T1 43200, T2 69120
Address: 2001:DB8:CAFE:1:5844:47B2:2603:C171
        preferred lifetime INFINITY, , valid lifetime INFINITY,
R1#
```

```
R3# show ipv6 interface g0/1
GigabitEthernet0/1 is up, line protocol is up
IPv6 is enabled, link-local address is
FE80::32F7:DFF:FE25:2DE1
No Virtual link-local address(es):
Global unicast address(es):
  2001:DB8:CAFE:1:5844:47B2:2603:C171, subnet is
2001:DB8:CAFE:1:5844:47B2:2603:C171/128
Joined group address(es):
  FE02::1
  FE02::1:FF03:C171
  FE02::1:FF25:2DE1
MTU is 1500 bytes
ICMP error messages limited to one every 100 milliseconds
ICMP redirects are enabled
ICMP unreachable are sent
ND DAD is enabled, number of DAD attempts: 1
ND reachable time is 30000 milliseconds (using 30000)
ND NS retransmit interval is 1000 milliseconds
Default router is FE80::D68C:B5FF:FECE:A0C1 on
GigabitEthernet0/1
R3#
```


Configuring a Router as a DHCPv6 Relay Agent



- If the DHCPv6 server is located on a different network than the client, the router can be configured as a DHCPv6 relay agent.

- **ipv6 dhcp relay destination**
destination-address

```
R1(config)# interface g0/0
R1(config-if)# ipv6 dhcp relay destination 2001:db8:cafe:1::6
R1(config-if)# end
R1# show ipv6 dhcp interface g0/0
GigabitEthernet0/0 is in relay mode
  Relay destinations:
    2001:DB8:CAFE:1::6
R1#
```

Troubleshooting Tasks

Troubleshooting Task 1	Resolve address conflicts.
Troubleshooting Task 2	Verify allocation method.
Troubleshooting Task 3	Test with a static IPv6 address.
Troubleshooting Task 4	Verify switch port configuration.
Troubleshooting Task 5	Test from the same subnet or VLAN.

Verify Router DHCPv6 Configuration

- Use the **show ipv6 interface** command to verify DHCPv6 configuration.

SLAAC

```
R1# show ipv6 interface g0/1
GigabitEthernet0/1 is up, line protocol is up
  IPv6 is enabled, link-local address is
FE80::D68C:B5FF:FECE:A0C1
<output omitted>

Hosts use stateless autoconfig for addresses.
```

Stateless DHCPv6

```
R1# show ipv6 interface g0/1
GigabitEthernet0/1 is up, line protocol is up
  IPv6 is enabled, link-local address is FE80::D68C:B5FF:FECE:A0C1
<output omitted>

Hosts use DHCP to obtain other configuration.
```

Stateful DHCPv6

```
R1# show ipv6 interface g0/1
GigabitEthernet0/1 is up, line protocol is up
  IPv6 is enabled, link-local address is FE80::D68C:B5FF:FECE:A0C1
<output omitted>

Hosts use DHCP to obtain routable addresses.
```

Troubleshoot DHCPv6

Debugging DHCPv6

```
R1# debug ipv6 dhcp detail
IPv6 DHCP debugging is on (detailed)
R1#
*Feb  3 21:27:41.123: IPv6 DHCP: Received SOLICIT from FE80::32F7:DFF:FE25:2DE1 on
GigabitEthernet0/1
*Feb  3 21:27:41.123: IPv6 DHCP: detailed packet contents
*Feb  3 21:27:41.123:   src FE80::32F7:DFF:FE25:2DE1 (GigabitEthernet0/1)
*Feb  3 21:27:41.127:   dst FF02::1:2
*Feb  3 21:27:41.127:   type SOLICIT(1), xid 13190645
*Feb  3 21:27:41.127:   option ELAPSED-TIME(8), len 2
*Feb  3 21:27:41.127:     elapsed-time 0
*Feb  3 21:27:41.127:   option CLIENTID(1), len 10
*Feb  3 21:27:41.127:     000
*Feb  3 21:27:41.127: IPv6 DHCP: Using interface pool IPV6-STATEFUL
*Feb  3 21:27:41.127: IPv6 DHCP: Creating binding for FE80::32F7:DFF:FE25:2DE1
in pool IPV6-STATEFUL
<output omitted>
```

- To verify the receipt and transmission of DHCPv6 messages:
 - **debug ipv6 dhcp detail**

Chapter Summary

DHCP

- Implement DHCPv4 to operate across multiple LANs in a small to medium-sized business network.
- Implement DHCPv6 to operate across multiple LANs in a small to medium-sized business network.

