

Managing Host and Cluster Lifecycle

Update 1

VMware vSphere 7.0

VMware ESXi 7.0

You can find the most up-to-date technical documentation on the VMware website at:

<https://docs.vmware.com/>

VMware, Inc.
3401 Hillview Ave.
Palo Alto, CA 94304
www.vmware.com

Copyright © 2020 VMware, Inc. All rights reserved. [Copyright and trademark information.](#)

Contents

About Managing Host and Cluster Lifecycle	7
1 About vSphere Lifecycle Manager	8
The vSphere Lifecycle Manager User Interface in the vSphere Client	9
vSphere Lifecycle Manager Operations	12
2 Software Updates and Related Terminology	13
VIBs, Bulletins, Components	13
ESXi Base Images and Vendor Add-Ons	15
3 vSphere Lifecycle Manager Baselines and Images	17
vSphere Lifecycle Manager Baselines and Baseline Groups	18
vSphere Lifecycle Manager Images	19
4 vSphere Lifecycle Manager Images and Other VMware Products and Solutions	21
vSphere Lifecycle Manager and vSphere with Tanzu with vSphere Networking	22
5 vSphere Lifecycle Manager Requirements and Specifics	24
6 vSphere Lifecycle Manager Privileges	27
vSphere Lifecycle Manager Privileges For Using Images	27
vSphere Lifecycle Manager Privileges For Using Baselines	29
7 Working with the vSphere Lifecycle Manager Depot	30
Online and Offline Depots	31
vSphere Lifecycle Manager Download Sources	33
Browsing the vSphere Lifecycle Manager Depot	34
Import Updates to the vSphere Lifecycle Manager Depot	36
Import an ISO Image to the vSphere Lifecycle Manager Depot	37
Delete an ISO Image from the vSphere Lifecycle Manager Depot	38
Synchronize the vSphere Lifecycle Manager Depot	39
Configuring the vSphere Lifecycle Manager Download Sources	39
Configure vSphere Lifecycle Manager to Use a Shared Repository as a Download Source	41
Configure vSphere Lifecycle Manager to Use the Internet as a Download Source	43
Add a New Download Source	44
Modify a Download Source	45

Configure the vSphere Lifecycle Manager Automatic Download Task	46
Run the VMware vSphere vSphere Lifecycle Manager Update Download Task	47
8 Configuring the vSphere Lifecycle Manager Remediation Settings	48
Cluster Settings and Host Remediation	49
Configure Remediation Settings for vSphere Lifecycle Manager Images	51
Configure Remediation Settings for vSphere Lifecycle Manager Baselines	53
9 Cluster Operations and vSphere Lifecycle Manager	56
10 Using Baselines and Baseline Groups	58
Creating and Working with Baselines and Baseline Groups	59
Baseline Types by Content	61
Create a Fixed Patch Baseline	62
Create a Dynamic Patch Baseline	63
Create a Host Extension Baseline	65
Create a Host Upgrade Baseline	66
Create a Host Baseline Group	67
Edit a Patch Baseline	68
Edit a Host Extension Baseline	69
Edit a Host Upgrade Baseline	70
Edit a Baseline Group	70
Add or Remove a Single Update from a Custom Baseline	71
Duplicate Baselines and Baseline Groups	72
Delete Baselines and Baseline Groups	73
Attaching Baselines and Baseline Groups to vSphere Objects	73
Attach Baselines and Baseline Groups to Objects	73
Detach Baselines and Baseline Groups from Objects	74
Checking Compliance Against vSphere Lifecycle Manager Baselines and Baseline Groups	75
Initiate a Compliance Check for ESXi Hosts Manually	76
Schedule Regular Compliance Checks for ESXi Hosts	76
Host Upgrade Compliance Messages	77
Host Upgrade Compliance Messages When Cisco Nexus 1000V Is Present	79
Viewing Compliance Information About ESXi Hosts and Updates	80
Staging Patches and Extensions to ESXi Hosts	90
Stage Patches and Extensions to ESXi Hosts	91
Remediating ESXi Hosts Against vSphere Lifecycle Manager Baselines and Baseline Groups	92
Understanding the Remediation Operation	93
Types of Host Remediation	94
Remediating Hosts in a Cluster	95
Remediating Hosts That Contain Third-Party Software	97

Remediating ESXi 6.5 or ESXi 6.7 Hosts Against an ESXi 7.0 Image	97
Remediation Pre-Check Report	98
Generate a Pre-Remediation Check Report	100
Remediate ESXi Hosts Against a Single Baseline or Multiple Baselines	101

11 Using Images 105

Working with Images	106
Setting Up an Image	107
Viewing Image Details	107
Editing Images	108
Reusing Existing Images	110
Checking Compliance Against a Single Image	113
Compliance States	114
Check Cluster Compliance Against an Image	115
View Host Compliance Information	116
Run a Remediation Pre-Check for a Cluster	116
Run a Remediation Pre-Check for a Single Host	117
Remediating a Cluster Against a Single Image	118
Edit the Remediation Settings for a Cluster	119
Remediate a Cluster Against a Single Image	121
Remediate a Single Host Against an Image	122
View Last Remediation or Remediation Pre-Check Results for a Cluster that Uses a Single Image	123
Manage Depot Overrides for a Cluster	123

12 Switching from Baselines to Images 125

Cluster Eligibility to Use vSphere Lifecycle Manager Images	127
Set Up a New Image	129
Import an Existing Image	131

13 Recommended Images 133

Check for Recommended Images	134
Use a Recommended Image	135

14 Firmware Updates 137

Deploying Hardware Support Managers	138
Use an Image for Firmware Updates	139

15 Hardware Compatibility Checks 142

Automatically Triggered Hardware Compatibility Checks for vSAN Clusters	144
Check the Hardware Compatibility of a Cluster	145
Check the Hardware Compatibility of a Host	146

	Sync Hardware Compatibility Data	147
	Hardware Compatibility Report for a Host	148
16	vSAN Clusters and vSphere Lifecycle Manager	150
	Remediation Specifics of vSAN Clusters	151
	Remediating vSAN Stretched Clusters and Clusters with Configured Fault Domains	153
	Recommendation Baseline Groups	154
	Configure Remediation Settings for a vSAN Cluster	155
	Updating Firmware in vSAN Clusters	156
17	Backup and Restore Scenarios When Using vSphere Lifecycle Manager	158
18	Upgrading Virtual Machines with vSphere Lifecycle Manager	160
	Configure Virtual Machine Rollback Settings	160
	Checking the Status of Virtual Machines	162
	Check the Status of an Individual Virtual Machine	162
	Check the Status of the Virtual Machines in a Container Object	163
	The VMware Tools Status	163
	Upgrading Virtual Machines	164
	Upgrade the VM Hardware Compatibility of Virtual Machines	165
	Upgrade the VMware Tools Version of Virtual Machines	166
	Automatically Upgrade VMware Tools on Reboot	168
19	Installing, Setting Up, and Using Update Manager Download Service	169
	Compatibility Between UMDS and vSphere Lifecycle Manager	170
	Installing UMDS	170
	Supported Linux-Based Operating Systems for Installing UMDS	170
	Install UMDS on a Linux OS	171
	Uninstall UMDS from a Linux OS	171
	Setting Up and Using UMDS	172
	Set Up the Data to Download with UMDS	173
	Change the UMDS Patch Repository Location	173
	Configure URL Addresses for Hosts	174
	Download the Specified Data Using UMDS	174
	Export the Downloaded Data	175

About Managing Host and Cluster Lifecycle

Managing Host and Cluster Lifecycle provides information about configuring and using VMware® vSphere Lifecycle Manager to manage the ESXi hosts and clusters in your environment.

Managing Host and Cluster Lifecycle provides instructions for configuring vSphere Lifecycle Manager, working with the vSphere Lifecycle Manager depot, and using baselines and images to install, update, or upgrade the software and firmware running on your ESXi hosts.

Managing Host and Cluster Lifecycle also provides detailed guidelines about using vSphere Lifecycle Manager recommended images and performing hardware compatibility checks on single hosts or clusters. It also describes how you can configure and use the Update Manager Download Service (UMDS) to download software updates in deployments with no access to the Internet.

At VMware, we value inclusion. To foster this principle within our customer, partner, and internal community, we have updated this guide to remove instances of non-inclusive language.

Intended Audience

This information is intended for experienced system administrators who are familiar with data center operations and virtual machine technology.

Client Interface

The instructions in this guide reflect the HTML5-based vSphere Client.

About vSphere Lifecycle Manager

1

VMware vSphere® vSphere Lifecycle Manager enables centralized and simplified lifecycle management for VMware ESXi hosts through the use of images and baselines.

What Is Lifecycle Management?

Lifecycle management refers to the process of installing software, maintaining it through updates and upgrades, and decommissioning it.

In the context of maintaining a vSphere environment, your clusters and hosts in particular, lifecycle management refers to tasks such as installing ESXi and firmware on new hosts, and updating or upgrading the ESXi version and firmware when required.

vSphere Lifecycle Manager General Overview

vSphere Lifecycle Manager is a service that runs in vCenter Server and uses the embedded vCenter Server PostgreSQL database. No additional installation is required to start using that feature. Upon deploying the vCenter Server appliance, the vSphere Lifecycle Manager user interface becomes automatically enabled in the HTML5-based vSphere Client.

vSphere Lifecycle Manager encompasses the functionality that Update Manager provides in earlier vSphere releases and enhances it by adding new features and options for ESXi lifecycle management at a cluster level.

In vSphere releases earlier than 7.0, Update Manager provides you with the ability to use baselines and baseline groups for host patching and host upgrade operations. Starting with vSphere 7.0, vSphere Lifecycle Manager introduces the option of using vSphere Lifecycle Manager images as an alternative way to manage the lifecycle of the hosts and clusters in your environment. You can also use vSphere Lifecycle Manager to upgrade the virtual machine hardware and VMware Tools versions of the virtual machines in your environment.

vSphere Lifecycle Manager can work in an environment that has access to the Internet, directly or through a proxy server. It can also work in a secured network without access to the Internet. In such cases, you use the Update Manager Download Service (UMDS) to download updates to the vSphere Lifecycle Manager depot, or you import them manually.

The vSphere Lifecycle Manager Depot

Several components make up vSphere Lifecycle Manager and work together to deliver the vSphere Lifecycle Manager functionality and coordinate the major lifecycle management operations that it provides for. The vSphere Lifecycle Manager depot is an important component in the vSphere Lifecycle Manager architecture, because it contains all software updates that you use to create vSphere Lifecycle Manager baselines and images. You can use vSphere Lifecycle Manager only if the vSphere Lifecycle Manager depot is populated with components, add-ons, base images, and legacy bulletins and patches.

For more information about software updates, see [VIBs, Bulletins, Components](#).

For more information about the vSphere Lifecycle Manager depot, see [Chapter 7 Working with the vSphere Lifecycle Manager Depot](#).

vSphere Lifecycle Manager Scalability

For information about the scalability that vSphere Lifecycle Manager supports, visit the VMware Configuration Maximums Matrix at <https://configmax.vmware.com/>.

This chapter includes the following topics:

- [The vSphere Lifecycle Manager User Interface in the vSphere Client](#)
- [vSphere Lifecycle Manager Operations](#)

The vSphere Lifecycle Manager User Interface in the vSphere Client

After you deploy the vCenter Server appliance, vSphere Lifecycle Manager becomes immediately visible in the vSphere Client.

The vSphere Lifecycle Manager user interface has two main views, which for convenience this guide calls the home view and the compliance view.

vSphere Lifecycle Manager Home View

The vSphere Lifecycle Manager home view is where you configure and administer the vSphere Lifecycle Manager instance that runs on your vCenter Server system. You go to the vSphere Lifecycle Manager home view to configure how vSphere Lifecycle Manager baselines and images work.

You do not need any special privilege to access the vSphere Lifecycle Manager home view.

To access the vSphere Lifecycle Manager home view in the vSphere Client, select **Menu > Lifecycle Manager**.

In the vSphere Lifecycle Manager home view, you specify the vSphere Lifecycle Manager instance that you want to administer by selecting a vCenter Server system from the drop-down menu at the top of the **Lifecycle Manager** pane.

In the **Lifecycle Manager** pane, you have the following top-level tabs: **Image Depot**, **Updates**, **Imported ISOs**, **Baselines**, and **Settings**.

You use the **Image Depot** tab when you work vSphere Lifecycle Manager images. You use the **Updates**, **Imported ISOs**, and **Baselines** tabs when you work with vSphere Lifecycle Manager baselines. For more information about the **Image Depot**, **Updates**, and **Imported ISOs** tabs, see [Browsing the vSphere Lifecycle Manager Depot](#).

The **Settings** tab is where you configure all vSphere Lifecycle Manager remediation settings and download sources. You use the **Settings** with both vSphere Lifecycle Manager images and baselines. For more information about configure the vSphere Lifecycle Manager settings, see [Chapter 8 Configuring the vSphere Lifecycle Manager Remediation Settings](#).

In the vSphere Lifecycle Manager home view, you can perform the following tasks:

- Browse the vSphere Lifecycle Manager depot.
- Trigger the synchronization of updates with the configured online depots.
- Trigger the synchronization of hardware compatibility data.
- Import offline depots manually.
- Import ISO images to use for the creation of upgrade baselines.
- Create and manage baselines and baseline groups.
- Configure the default vSphere Lifecycle Manager download source.
- Add a URL to an online depot to the list of download sources.
- Enable or disable downloading from a download source.
- Configure host remediation settings.
- Configure virtual machine rollback settings.

vSphere Lifecycle Manager Compliance View

The vSphere Lifecycle Manager compliance view is where you perform the major vSphere Lifecycle Manager operations - checking the compliance of ESXi hosts against a baseline or an image, staging, remediation pre-checks, remediation, and so on.

You go to the vSphere Lifecycle Manager compliance view to actually use the vSphere Lifecycle Manager baselines and images on your clusters and hosts.

To access the vSphere Lifecycle Manager compliance view in the vSphere Client, you must have the **View Compliance Status** privilege.

Generally, the vSphere Lifecycle Manager compliance view is on the **Updates** tab for a selected object.

Depending on the selected object and whether you use baselines or images to manage the object, you access the vSphere Lifecycle Manager compliance view in two different ways.

- To access the vSphere Lifecycle Manager compliance view for a host or a cluster that you manage with baselines, go to the **Updates** tab for the object and select **Baselines**.

In the **Baselines** pane of the vSphere Lifecycle Manager compliance view, you can perform the following tasks:

- Check the compliance status of ESXi hosts and clusters against baselines or baseline groups.
- Attach and detach baselines and baseline groups to hosts and clusters.
- Generate a remediation pre-check report that lists recommended actions to ensure successful remediation.
- Stage patches or extensions to hosts.
- Check the compliance status of ESXi hosts against an image.
- Remediate hosts against baselines and baseline groups.
- Remediate hosts that are part of a vSAN cluster against system-managed baselines.
- To access the vSphere Lifecycle Manager compliance view for a cluster that you manage with a single image, go to the **Updates** tab for the cluster and select **Image**.

In the **Image** pane of the vSphere Lifecycle Manager compliance view, you can perform the following tasks:

- Export, import, and edit the image that the cluster uses.
- Upgrade the firmware of the ESXi hosts in the cluster.
- Check for and view recommended images for the cluster.
- Check the hardware compatibility for a selected ESXi version against vSAN HCL .
- Check the compliance status of the ESXi hosts against the image.
- Run a remediation pre-check to ensure successful remediation.
- Remediate the ESXi hosts against the image that the cluster uses.

On the the **Updates** tab, you can also perform other tasks.

- Under **Hosts**, select **Hardware Compatibility** to check the hardware compatibility of a host against the VMware Compatibility Guide.
- Under **Hosts**, select **VMware Tools** or **VM Hardware** to check the status of virtual machines and upgrade the VMware Tools version or the virtual hardware version of the virtual machines.

vSphere Lifecycle Manager and vCenter Server Single Sign-On Domain

If your vCenter Server system is connected to other vCenter Server systems by a common vCenter Single Sign-On domain, you can configure the settings for each vSphere Lifecycle Manager instance. The modifications to the settings are applied only to the vSphere Lifecycle Manager instance that you specify and are not propagated to the other instances in the group. Similarly, you can use vSphere Lifecycle Manager to perform compliance and status checks, and remediate only those inventory objects that are managed by the vCenter Server system where the respective vSphere Lifecycle Manager instance runs.

vSphere Lifecycle Manager Operations

The main vSphere Lifecycle Manager operations are related to checking whether the objects in your environment are up to date with a vSphere Lifecycle Manager baseline or an image and updating or upgrading ESXi hosts.

Compliance check

An operation of scanning ESXi hosts to determine their level of compliance with a baseline attached to the cluster or with the image that the cluster uses. The compliance check does not alter the object.

Remediation

An operation of applying software updates to the ESXi hosts in a cluster. During remediation, you install software on the hosts. Remediation makes a non-compliant host compliant with the baselines attached to the cluster or with the image for cluster.

Remediation Pre-Check

You perform a pre-check before remediation to ensure that the health of the cluster is good and that no issues occur during the remediation process.

Staging

When you stage patches or extensions to an ESXi host, you download patch and extension VIBs to the host without applying them immediately. Staging makes the patches and extensions available locally on the hosts. This action is available only for clusters managed by baselines or baseline groups.

Software Updates and Related Terminology

2

To use vSphere Lifecycle Manager effectively, you must understand the basic concepts related to the way software is created, packaged, and distributed.

A software update provides software fixes and enhancements. An update release is a release that makes small changes to the current version of the software. Update releases are marked in the following manner: 7.0 U1, 7.0 U2, and so on.

A software upgrade introduces major changes to the software. Upgrade releases change the major version of the software product. For example, the transitions from vSphere 6.0 to vSphere 6.7 or vSphere 7.0 are both upgrades.

A patch is a small software update that provides bug fixes or enhancements to the current version of the software. patch releases are marked by adding a letter to the version: 7.0a, 7.0 U1a, and so on.

Both patching and upgrade are types of software update operations.

This chapter includes the following topics:

- [VIBs, Bulletins, Components](#)
- [ESXi Base Images and Vendor Add-Ons](#)

VIBs, Bulletins, Components

To understand the difference between vSphere Lifecycle Manager images and vSphere Lifecycle Manager baselines, you must understand the relation between the basic software packaging types that software vendors use to create and ship software updates.

vSphere Lifecycle Manager uses software from VMware, OEMs, and third-party software providers.

- OEMs are VMware partners, for example, Dell, HPE, VMware Cloud on AWS.
- Third-party software providers are providers of I/O filters, device drivers, CIM modules, and so on.

vSphere Installation Bundles (VIBs)

The VIB is the basic building block for the creation of installation packages for ESXi hosts. A VIB is a software package that contains metadata and a binary payload, which represents the actual piece of software to be installed on ESXi. The VIB does not represent an entire feature, but just a single module of the feature. So, the VIB is the smallest installable software unit that VMware and other software vendors ship.

vSphere Lifecycle Manager does not consume and work with individual VIBs. VIBs must be further packaged into a higher-level construct.

VIB Metadata

An XML file (`descriptor.xml`) that describes the contents of the VIB. It also contains dependency information, textual descriptions, system requirements, and information about bulletins.

Standalone VIB

A VIB that is not included in a component.

Bulletins

The bulletin is a grouping of one or more VIBs. Bulletins are defined within the metadata of the VIB. You use bulletins, and not individual VIBs, to create vSphere Lifecycle Manager baselines, which you attach to inventory objects and use to update and upgrade ESXi hosts.

Patch

A small software update that provides bug fixes or enhancements to the current version of the software. A patch groups one or more VIBs together to address a particular issue or to provide enhancements to the current version of the software.

Roll-up Bulletin

A collection of patches that is grouped to facilitate downloads and deployment.

Extension

A bulletin that defines a group of VIBs for adding an optional component to an ESXi host. An extension is usually provided by a third party. The third-party provider is also responsible for providing patches, or updates, for the extension.

Components

The component is a bulletin with additional metadata specifying the name and the version of the component. Unlike the bulletin, the component is a logical grouping of VIBs, which provides you with a complete and visible feature upon installation. Starting with vSphere 7.0, the component becomes the basic packaging construct for VIBs. VMware, OEMs, and third-party software providers now deliver software in the form of components.

However, VMware and OEMs do not deliver components independently. VMware bundles components together into fully functional ESXi base images. OEMs bundle components together into vendor add-ons.

Third-party software vendors create and ship software, for example drivers or adapters, as independent components.

Bulletins or Components?

vSphere Lifecycle Manager can consume both bulletins and components.

If you use baselines and baseline groups to manage hosts and clusters, vSphere Lifecycle Manager reads and lists the software updates that are available in the vSphere Lifecycle Manager depot as bulletins. You can find the list of available bulletins on the **Updates** tab in the vSphere Lifecycle Manager home view.

If you use vSphere Lifecycle Manager images to manage hosts and clusters, you can only work with components and the related notions of add-ons and base image. You can find the list of the components, add-ons, and ESXi base images on the **Image Depot** tab in the vSphere Lifecycle Manager home view.

ESXi Base Images and Vendor Add-Ons

VMware combines multiple components into a complete, bootable ESXi image. OEMs pack one or multiple components into a unit called an add-on. You use vendor add-ons to customize an ESXi release for a family of servers.

Base Images

The base image is an ESXi image that VMware provides with every release of ESXi. The base image is a collection of components that is complete and can boot up a server. Base images have a user-readable name and a unique version that is updated with every major or minor release of ESXi.

The version of a base image corresponds to an ESXi release and uses the following naming format:

- General Availability: 7.0
- Update: 7.0 U1, 7.0 U2
- Patch: 7.0 a / 7.0 b
- Security patch: 7.0 sa, 7.0 sb
- Patch after update: 7.0 U1 a, 7.0 U1 sa, 7.0 b, 7.0 sb

Base images are hosted and available in the VMware online depot. Additionally, you can download an ESXi installer ISO file and an offline bundle (ZIP file) that contains the ESXi version from my.vmware.com.

Vendor Add-Ons

You use vendor add-ons to customize an ESXi image with OEM content and drivers.

The add-on is a collection of components that does not represent a complete, bootable image. You cannot use vendor add-ons on their own. To customize an ESXi release, you must add the vendor add-on to an ESXi base image. The combination of a vendor add-on and an ESXi base image is practically identical to an OEM-provided custom image.

When combined with an ESXi base image, the add-on can add, update, or remove components that are part of the ESXi base image. In the vSphere Client, for each add-on available in the depot, you can view the list of components that it adds to an ESXi base image. Similarly, you can find information about the components that it removes from a base image.

Starting with vSphere 7.0, in addition to custom ISO images and offline bundles, OEMs can release ZIP files that contain only the vendor add-on, that is, the delta between the custom image and the ESXi base image. OEMs can release such add-on ZIP files at their discretion. The introduction of the concept of add-ons decouples the release cycle of OEMs from the release cycle of VMware. As a result, you can update vendor add-ons independently of updating the ESXi version of your hosts. Also, the vendor add-on decouples the OEM customization from the VMware stock image, thus letting you combine software components more freely.

vSphere Lifecycle Manager Baselines and Images

3

vSphere Lifecycle Manager enables you to manage ESXi hosts and clusters with images or baselines. vSphere Lifecycle Manager baselines and vSphere Lifecycle Manager images are different in their essence, the way they work, and the features they support.

You use vSphere Lifecycle Manager baselines and baseline groups to perform the following tasks.

- Upgrade and patch ESXi hosts.
- Install and update third-party software on ESXi hosts.

You use vSphere Lifecycle Manager images to perform the following tasks.

- Install a desired ESXi version on all hosts in a cluster.
- Install and update third-party software on all ESXi hosts in a cluster.
- Update and upgrade the ESXi version on all hosts in a cluster.
- Update the firmware of all ESXi hosts in a cluster.
- Generate recommendations and use a recommended image for your cluster.
- Check the hardware compatibility of hosts and clusters against the VMware Compatibility Guide and the vSAN Hardware Compatibility List.

To start managing a cluster with a single image, you have two options.

- Set up an image for the cluster during the creation of the cluster

For more information about creating a cluster that uses a single image, see the *vCenter Server and Host Management* documentation.

- Skip setting up an image for the cluster and switch from using baselines to using images at a later time.

Note If you switch to using images, you cannot revert to using baselines for that cluster. You can only move the hosts to a cluster that uses baselines.

To start managing a cluster with baselines and baseline groups, you must skip setting up an image during the creation of the cluster. For more information about managing hosts and clusters with baselines and baseline groups, see [Chapter 10 Using Baselines and Baseline Groups](#).

Table 3-1. Comparison Between vSphere Lifecycle Manager Baselines and Images

Criterion	Baselines	Images
Software packaging	A vSphere Lifecycle Manager baseline is a collection of bulletins.	A vSphere Lifecycle Manager image is a collection of components.
Consumable formats	vSphere Lifecycle Manager baselines are distributed through online depots, as offline bundles, or as ISO images.	vSphere Lifecycle Manager images are distributed through online depots, as offline bundles, or as JSON files.
Remediation result	vSphere Lifecycle Manager baselines list the updates to be applied to hosts, but the ESXi image on the hosts might change after remediation.	vSphere Lifecycle Manager images define the precise image to be applied to the hosts after remediation. No deviation from the defined image is possible after remediation. vSphere Lifecycle Manager does not allow solutions to push VIBs to the hosts.
Software recommendations	Limited support. Software recommendations are only available for vSAN clusters in the form of recommendation baselines.	Supported. Based on the hardware of the hosts in the cluster, you get recommendations about available and applicable ESXi updates or upgrades.
Portability	You can create a custom baseline and attach it to different objects in the same vCenter Server instance. You cannot export baselines and distribute them across vCenter Server instances.	You can export an image and use it to manage other clusters in the same or in a different vCenter Server instance. Images are portable across vCenter Server instances.
Remote Office/Branch Office (ROBO) support	Not provided. Although no specific optimization exists for ROBO deployments, you can still use baselines and baseline groups with ROBO clusters.	Provided. With vSphere Lifecycle Manager images, you can set up a local depot and use it in ROBO environments.
REST APIs	Not available.	Available.

This chapter includes the following topics:

- [vSphere Lifecycle Manager Baselines and Baseline Groups](#)
- [vSphere Lifecycle Manager Images](#)

vSphere Lifecycle Manager Baselines and Baseline Groups

You use baselines and baseline groups to update and upgrade the ESXi hosts in your environment.

Baselines

A baseline is a grouping of multiple bulletins. You can attach a baseline to an ESXi host and check the compliance of the host against the associated baseline.

Baselines can be classified according to different criteria.

- Depending on the type of content, baselines are patch baselines, extension baselines, and upgrade baselines.

Patch and extension baselines contain bulletins of the respective kind. Upgrade baselines contain ESXi images.

- Depending on how the update content is selected, baselines are fixed and dynamic.
- Depending on how they are created and managed, baselines are predefined, recommendation, or custom baselines.

Baseline Groups

A baseline group is a collection of non-conflicting baselines. You can attach the entire baseline group to an inventory object to check the compliance status of the object against all the baselines in the group as a whole.

You can combine custom baselines with any of the predefined baselines to create baseline groups.

Host baseline groups can contain a single upgrade baseline, and various patch and extension baselines.

To update or upgrade ESXi hosts by using baselines or baseline groups, you must first attach the baselines or baselines group to an inventory object.

Although you can attach baselines and baseline groups to individual objects, a more efficient method is to attach them to container objects, such as folders, vApps, clusters, and data centers. Individual vSphere objects inherit baselines attached to the parent container object. Removing an object from a container removes the inherited baselines from the object.

For more information about creating and managing baselines and baseline groups, see [Creating and Working with Baselines and Baseline Groups](#).

vSphere Lifecycle Manager Images

You can use a single vSphere Lifecycle Manager image to manage all ESXi hosts in a cluster. You use vSphere Lifecycle Manager images to apply software and firmware updates to the ESXi hosts.

Today, you can use various methods and tools to deploy ESXi hosts and maintain their software lifecycle. For example, you can upgrade hosts by using VMware vSphere® ESXi™ Image Builder CLI, esxcli, vSphere Auto Deploy. The different deployment and upgrade choices involve different workflows and require you to use different ESXi image formats.

When you use vSphere Lifecycle Manager images, you follow one workflow and use the same ESXi image format for all software lifecycle-related operations: install, upgrade, update, and patching, which significantly simplifies the lifecycle management process.

What Is an Image?

A vSphere Lifecycle Manager image represents a desired software specification to be applied to all hosts in a cluster. When you set up a vSphere Lifecycle Manager image, you define the full software stack that you want to run on the hosts in a cluster: the ESXi version, additional VMware software, vendor and third-party software, for example firmware and drivers. Using a single image to manage all hosts in a cluster ensures cluster-wide host image homogeneity.

The Desired State Model

The concept of images that vSphere Lifecycle Manager introduces is based on the Desired State model for managing ESXi hosts and clusters.

The desired state of an ESXi host represents both the target software and target configuration for the host as opposed to the software and configuration that it currently runs. The Desired State model is the idea of managing hosts and clusters by defining and applying a desired state instead of listing and following steps to change the current state.

What Is in an Image?

A vSphere Lifecycle Manager image can contain four elements.

- ESXi base image

The base image is an ESXi image that VMware provides with every release of ESXi. The base image contains an image of VMware ESXi Server and additional components, such as drivers and adapters that are necessary to boot a server. Base images have a user-readable name and a unique version that is updated with every major or minor release of ESXi.

- Vendor add-on

The vendor add-on is a collection of software components that OEMs create and distribute. The vendor add-on can contain drivers, patches, and solutions.

- Firmware and drivers add-on

The firmware and drivers add-on is a special type of vendor add-on designed to assist in the firmware update process. The firmware and drivers add-on contains firmware for a specific server type and corresponding drivers. To add a firmware and drivers add-on to your image, you must install the hardware support manager plug-in provided by the hardware vendor for the hosts in the respective cluster.

- Independent components

The component is the smallest discrete unit in an image. The independent components that you add to an image contain third-party software, for example drivers or adapters.

The ESXi base image is a mandatory element. You cannot set up a vSphere Lifecycle Manager image without selecting a base image. All other elements are optional.

vSphere Lifecycle Manager Images and Other VMware Products and Solutions

4

You can use a vSphere Lifecycle Manager image to manage a cluster only if the cluster is not enabled for a solution that is not integrated to work with vSphere Lifecycle Manager.

A solution is a VMware product that integrates with vCenter Server and adds some new functionality to the ESXi hosts in the inventory.

When you enable a solution for a cluster that uses a vSphere Lifecycle Manager image, the solution automatically uploads an offline bundle with components into the vSphere Lifecycle Manager depot and adds its component to all hosts in the cluster. You cannot control the lifecycle of solution components. For example, if you export the image, solution components are not part of the exported image.

Integrated Solutions

You can manage a cluster with a single image if the cluster has any of the following solutions enabled.

- vSphere High Availability
- vSAN

For more information about the integration between vSAN and vSphere Lifecycle Manager, see [Chapter 16 vSAN Clusters and vSphere Lifecycle Manager](#) and the *Administering VMware vSAN* documentation.

- vSAN File Services
- vSphere with Tanzu

For detailed information about the integration between vSphere with Tanzu and vSphere Lifecycle Manager, see the *vSphere with Tanzu* documentation.

You can also use baselines for clusters that have those solutions enabled.

Unintegrated Solutions

You cannot manage a cluster with a single image if the cluster has any of the following solutions enabled.

- VMware NSX-T™ Data Center

- VMware NSX ® for vSphere ®
- VMware vSphere Replication
- Dell EMC VxRail

You can use baselines and baseline groups to manage clusters that have those solutions enabled.

This chapter includes the following topics:

- [vSphere Lifecycle Manager and vSphere with Tanzu with vSphere Networking](#)

vSphere Lifecycle Manager and vSphere with Tanzu with vSphere Networking

Starting with vSphere 7.0 Update 1, you can enable vSphere with Tanzu on a cluster that uses a single vSphere Lifecycle Manager image.

Requirements

- All ESXi hosts in the cluster must be of version 7.0 Update 1 and later.
- All ESXi hosts in the Supervisor Cluster are assigned the VMware vSphere 7 Enterprise Plus with Add-on for Kubernetes license.
- vCenter Server 7.0 Update 1 and later.
- For the specific vSphere with Tanzu configuration requirements, see the *vSphere with Tanzu* documentation.

Supported Workflows

The following workflows are supported for clusters that are enabled for both vSphere Lifecycle Manager images and vSphere with Tanzu.

- You can enable vSphere with Tanzu on a cluster that you manage with a single vSphere Lifecycle Manager image.

You enable vSphere with Tanzu from the **Workload Management** user interface in the vSphere Client.
- You can upgrade a Supervisor Cluster to the latest version of vSphere with Tanzu. You can also upgrade the ESXi version of the hosts in the Supervisor Cluster.

You perform the upgrade of the Supervisor Cluster from the **Workload Management** user interface in the vSphere Client.

You upgrade the ESXi version of the hosts in the Supervisor Cluster by remediating the cluster from the vSphere Lifecycle Manager user interface in the vSphere Client.

Note You cannot perform a simultaneous upgrade of both vSphere with Tanzu and ESXi.

- You disable vSphere with Tanzu from the **Workload Management** user interface in the vSphere Client. You can disable vSphere with Tanzu on a cluster that uses a single vSphere Lifecycle Manager image.

When you disable vSphere with Tanzu, you can use the cluster for traditional virtual machine workloads.

- You can add and remove hosts to and from a cluster that has both vSphere with Tanzu and vSphere Lifecycle Manager enabled.

For more information about adding and removing hosts to and from a cluster, see the *vCenter Server and Host Management* documentation.

For detailed information about working with a Supervisor Cluster that uses a single image, see the "Managing a Supervisor Cluster Using vSphere Lifecycle Manager" section in the *vSphere with Tanzu* documentation.

Scalability

For information about the scalability that vSphere Lifecycle Manager supports, visit the VMware Configuration Maximums Matrix at <https://configmax.vmware.com/>.

vSphere Lifecycle Manager Requirements and Specifics

5

Depending on whether you want to use baselines or images for software lifecycle management, you must comply with a different set of requirements. To achieve your goals, you must also know the specifics in behavior and limitations that vSphere Lifecycle Manager has.

Table 5-1. Requirements for Using vSphere Lifecycle Manager

Scenario	Requirements
Using a single image to manage a cluster.	<ul style="list-style-type: none"> ■ All ESXi hosts in the cluster must be of version 7.0 and later. ■ All ESXi hosts in the cluster must be stateful. A stateful install is one in which the the host boots from a disk. ■ All ESXi hosts in the cluster must be from the same vendor and with identical hardware. Different generations and models of servers need different software drivers, which implies that you must set up different vSphere Lifecycle Manager images to manage each generation or model. However, with vSphere Lifecycle Manager, you use one single image for the entire cluster. Also, vSphere Lifecycle Manager does not detect and handle the hardware differences between the hosts in the cluster. You can use a vSphere Lifecycle Manager image to manage a heterogeneous cluster only if the vSphere Lifecycle Manager image for the cluster includes vendor customization, for example a vendor or firmware add-on, that can address and handle the hardware differences across the hosts in the cluster, which is a rare scenario. ■ The cluster must include only integrated solutions. For example: <ul style="list-style-type: none"> ■ VMware vSAN™ ■ VMware vSphere® High Availability (HA) ■ vSphere with Tanzu
Using baselines and baseline groups to manage a cluster.	<ul style="list-style-type: none"> ■ To use baselines for ESXi host patching operations, vSphere Lifecycle Manager works with ESXi 6.5, ESXi 6.7, and ESXi 7.0. ■ To use baselines for ESXi host upgrade operations, vSphere Lifecycle Manager works with ESXi 6.5, ESXi 6.7, and their respective Update releases.
Switching from using baselines to using a single image to manage a cluster.	<ul style="list-style-type: none"> ■ The cluster must meet the requirements for using an image. ■ The cluster must be eligible for the transition. For more information about the Check cluster's eligibility to be managed with a single image task, see Cluster Eligibility to Use vSphere Lifecycle Manager Images.
Upgrading virtual machine hardware and VMware Tools	For VMware Tools and virtual machine hardware upgrade operations, vSphere Lifecycle Manager works with ESXi 6.5, ESXi 6.7, and ESXi 7.0.

Table 5-2. vSphere Lifecycle Manager Behavior Specifics

Scenario	vSphere Lifecycle Manager Behavior
Using a single image to manage a cluster.	<ul style="list-style-type: none"> ■ When you set up and save an image for a cluster, the image is not applied to the hosts in the cluster unless you remediate the hosts. The mere action of changing the management method does not alter the hosts in the cluster. ■ After you set up an image for the cluster and remediate the hosts in the cluster against the image, standalone VIBs are deleted from the hosts. ■ After you set up an image for the cluster and remediate the hosts in the cluster against the image, non-integrated solution agents are deleted from the hosts.
Switching from using baselines to using a single image to manage a cluster.	<ul style="list-style-type: none"> ■ If you switch to using images, you cannot revert to using baselines for the cluster. You can move the hosts to a cluster that uses baselines, but you cannot change a cluster that already uses a single image for management purposes. ■ If you enable a solution that cannot work with vSphere Lifecycle Manager, for example Dell EMC VxRail, on an empty cluster and attempt to switch to using an image for that cluster, the transition operation succeeds. However, the result is an unsupported cluster configuration, because both vSphere Lifecycle Manager and the non-integrated solution are enabled on the cluster.

vSphere Lifecycle Manager Privileges

6

To configure vSphere Lifecycle Manager settings and to use successfully vSphere Lifecycle Manager baselines and images, you must have the proper privileges.

You can assign vSphere Lifecycle Manager privileges to different roles from the vSphere Lifecycle Manager client interface in the vSphere Client.

This chapter includes the following topics:

- [vSphere Lifecycle Manager Privileges For Using Images](#)
- [vSphere Lifecycle Manager Privileges For Using Baselines](#)

vSphere Lifecycle Manager Privileges For Using Images

When you use vSphere Lifecycle Manager images, you need a different set of privileges for each task.

Table 6-1. VMware vSphere vSphere Lifecycle Manager Privileges For Using Images

Task	Required Privileges
Set Up Image	<ul style="list-style-type: none">■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Privileges.Read■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Privileges.Write■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Settings Privileges.Read
Import Image	<ul style="list-style-type: none">■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Privileges.Read■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Privileges.Write■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Settings Privileges.Read■ Upload File.Upload File
Export Image	VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Privileges.Read

Table 6-1. VMware vSphere vSphere Lifecycle Manager Privileges For Using Images (continued)

Task	Required Privileges
Edit Image	<ul style="list-style-type: none"> ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Privileges.Read ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Privileges.Write ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Settings Privileges.Read
Work with Recommendations	<ul style="list-style-type: none"> ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Privileges.Read ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Privileges.Write ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Settings Privileges.Read
Work with Depot	<ul style="list-style-type: none"> ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Settings Privileges.Read ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Settings Privileges.Write
Manage Depot Overrides	<ul style="list-style-type: none"> ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Settings Privileges.Read ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Settings Privileges.Write
Check Compliance	VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Privileges.Read
Run Remediation Pre-Check	<ul style="list-style-type: none"> ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: General Privileges.Read ■ VMware vSphere Lifecycle Manager.ESXi Health Perspectives.Read ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Remediation Privileges.Read
Remediate Against an Image	<ul style="list-style-type: none"> ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: General Privileges.Read ■ VMware vSphere Lifecycle Manager.ESXi Health Perspectives.Read ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Remediation Privileges.Read ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Remediation Privileges.Write ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Settings Privileges.Read
Edit Remediation Settings	<ul style="list-style-type: none"> ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Settings Privileges.Read ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Settings Privileges.Write

Table 6-1. VMware vSphere vSphere Lifecycle Manager Privileges For Using Images (continued)

Task	Required Privileges
Update Firmware	<ul style="list-style-type: none"> ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Privileges.Read ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Image Privileges.Write ■ VMware vSphere Lifecycle Manager.Lifecycle Manager: Settings Privileges.Read
View Hardware Compatibility	VMware vSphere Lifecycle Manager.Lifecycle Manager: Hardware Compatibility Privileges.Access Hardware Compatibility

For more information about managing users, groups, roles, and permissions, see the *vSphere Security* documentation.

vSphere Lifecycle Manager Privileges For Using Baselines

Each of the vSphere Lifecycle Manager privileges that you need to use baselines and baseline groups covers a distinct functionality.

Table 6-2. VMware vSphere Lifecycle Manager Privileges For Using Baselines

Task	Privilege	Description
Configure	Configure.Configure Service	Configure the vSphere Lifecycle Manager service and the scheduled patch download task.
Manage Baseline	Manage Baselines.Attach Baseline	Attach baselines and baseline groups to objects in the vSphere inventory.
	Manage Baselines.Manage Baselines	Create, edit, or delete baselines and baseline groups.
Manage Patches and Upgrades	Manage Patches and Upgrades.Remediate to Apply Patches, Extensions, and Upgrades	Remediate virtual machines and hosts to apply patches, extensions, or upgrades. In addition, this privilege allows you to view the compliance status of objects.
	Manage Patches and Upgrades .Scan for Applicable Patches, Extensions, and Upgrades	Scan virtual machines and hosts to search for applicable patches, extensions, or upgrades.
	Manage Patches and Upgrades .Stage Patches and Extensions	Stage patches or extensions to hosts. In addition, this privilege allows you to view the compliance status of hosts.
	Manage Patches and Upgrades .View Compliance Status	View baseline compliance information for an object in the vSphere inventory.
Upload File	Upload File.Upload File	Upload upgrade images and offline patch bundles.

For more information about managing users, groups, roles, and permissions, see the *vSphere Security* documentation.

Working with the vSphere Lifecycle Manager Depot

7

The vSphere Lifecycle Manager depot is the source of software updates for vSphere Lifecycle Manager. Conceptually, the vSphere Lifecycle Manager depot represents all software available for consumption to vSphere Lifecycle Manager.

The vSphere Lifecycle Manager depot is a local depot on the vCenter Server machine. It contains all the content from the online and offline depots that you use with vSphere Lifecycle Manager.

You can work with vSphere Lifecycle Manager only if the vSphere Lifecycle Manager depot contains software packages. For example, ESXi base images, vendor add-ons, third-party components, and legacy patches and updates. For more information about ESXi base images, vendor add-ons, components, and patches, see [Chapter 2 Software Updates and Related Terminology](#).

You control how the vSphere Lifecycle Manager depot gets populated with software. You can configure vSphere Lifecycle Manager to download updates from online depots, or a UMDS-created shared repository. Alternatively, you can use offline depots to import updates into the vSphere Lifecycle Manager depot. For more information about the different types of depots that vSphere Lifecycle Manager can use, see [vSphere Lifecycle Manager Download Sources](#).

Synchronization is the process through which the contents of the online depots that you configure vSphere Lifecycle Manager to use get into the vSphere Lifecycle Manager depot. During synchronization, only the software metadata is downloaded. The actual payloads are downloaded when they are needed, for example during staging or remediation. When you deploy vCenter Server, vSphere Lifecycle Manager synchronizes with the official VMware online depot automatically. After the initial synchronization, you can schedule a download task to run at regular intervals or you can initiate a download task manually.

Import is the operation through which the contents of an offline bundle get into the vSphere Lifecycle Manager depot. During an import operation, both the software metadata and the actual payloads are downloaded into the vSphere Lifecycle Manager depot.

By default, vSphere Lifecycle Manager is configured to use the official VMware online depot as a download source for software updates. The official VMware online depot contains ESXi images, OEM add-ons, drivers, and async VMware Tools releases. You can configure ESXi to use additional online depots for components. You can also change the default download source and use a UMDS-created shared repository.

All software updates hosted in the official VMware online depot are also available as offline bundles, which you can download from my.vmware.com and import manually to the vSphere Lifecycle Manager depot.

This chapter includes the following topics:

- [Online and Offline Depots](#)
- [vSphere Lifecycle Manager Download Sources](#)
- [Browsing the vSphere Lifecycle Manager Depot](#)
- [Import Updates to the vSphere Lifecycle Manager Depot](#)
- [Import an ISO Image to the vSphere Lifecycle Manager Depot](#)
- [Delete an ISO Image from the vSphere Lifecycle Manager Depot](#)
- [Synchronize the vSphere Lifecycle Manager Depot](#)
- [Configuring the vSphere Lifecycle Manager Download Sources](#)
- [Configure the vSphere Lifecycle Manager Automatic Download Task](#)

Online and Offline Depots

vSphere Lifecycle Manager can consume software updates only if they are delivered in one of the following ways - in an online depot, as an offline depot, or as an installable ISO image. So, VMware, OEMs, and third-party software vendors must ship their software updates in any of these three formats.


Online Depots

An online depot is the hosted version of the software updates that VMware, OEMs, and third-party software providers ship. You access an online depot through a URL. vSphere Lifecycle Manager downloads to the vSphere Lifecycle Manager depot the content from the online depots that you configure it to use. vSphere Lifecycle Manager is preconfigured to download updates from the default VMware online depot. You can use the vSphere Client to access third-party online depots that contain additional components.

The Default VMware Online Depot

The default online depot that VMware provides hosts ESXi base images, vendor add-ons, and ESXi-compatible I/O device drivers certified by VMware.

Unlike earlier vSphere releases, all software that you need to install, update, or customize the ESXi version of your hosts is available in the official VMware online depot.



Firmware updates are not hosted in the VMware depot. To perform firmware updates, you must install the hardware support manager plug-in that your hardware vendor provides. The plug-in gives you access to depots that contain the necessary firmware and related drivers updates.

In the vSphere Client, you can list additional online depots for vSphere Lifecycle Manager to download additional third-party components from, for example CIM modules. However, working with additional third-party depots and independent components is rarely necessary. In most cases, the vendor add-ons that are available in the official VMware depot provide full OEM customization for ESXi.

Offline Depots

An offline depot, also called an offline bundle, is a ZIP file that you download from the Internet or copy from a media drive and you save on a local or a shared network drive. You then can import the offline bundle to the vSphere Lifecycle Manager depot. You can also download offline bundles from the VMware website or from the websites of third-party vendors.

Starting with vSphere 7.0, in addition to distributing an `offline.zip` file, or offline bundle, and a custom ISO image, OEMs distribute an `Add-on.zip` file that contains the delta between the OEM custom image and the base image that VMware provides. For more information about OEM add-ons, see [ESXi Base Images and Vendor Add-Ons](#).

Table 7-1. Software Deliverables and Corresponding Distribution Formats

Software Vendor	Software Deliverable	Software Distribution Format
VMware	Base images	<ul style="list-style-type: none"> ■ The default VMware online depot ■ Offline bundle ■ ISO image
OEMs	Add-ons	<ul style="list-style-type: none"> ■ The default VMware online depot ■ Offline bundle ■ Add-on ZIP file ■ ISO image
Third-party software providers	Components	<p>For device drivers that are certified by VMware:</p> <ul style="list-style-type: none"> ■ The default VMware online depot ■ Offline bundle <p>For other third-party software that is verified and certified by OEMs, for example I/O filters, CIM module:</p> <ul style="list-style-type: none"> ■ An online depot ■ Offline bundle

vSphere Lifecycle Manager Download Sources

You can configure vSphere Lifecycle Manager to download software from the Internet or, in air-gap scenarios, from a UMDS-created shared repository.

Download Updates from the Internet

If you configure vSphere Lifecycle Manager to use the Internet, then the download sources are practically all online depots that you use for downloading software.

vSphere Lifecycle Manager is preconfigured to use the official VMware online depot. In the vSphere Client, you can list additional online depots for vSphere Lifecycle Manager to download additional third-party components from, for example CIM modules.

When vSphere Lifecycle Manager synchronizes to online depots, it downloads only the metadata of the updates. The actual payload is downloaded during staging or remediation.

Download Updates from a UMDS Depot

In vCenter Server deployments without access to the Internet, instead of synchronizing to online depots, you can configure vSphere Lifecycle Manager to download updates from an UMDS-created shared repository. When you configure vSphere Lifecycle Manager to use a UMDS repository, synchronization of the updates metadata is not triggered immediately. The metadata is downloaded according to the configured download schedule or when you initiate the download. When the default download source for vSphere Lifecycle Manager is a UMDS repository, only the metadata is stored and displayed in the vSphere Client. The actual payload is downloaded during staging or remediation.

Depot Overrides

In ROBO scenarios, you can configure vSphere Lifecycle Manager to use a local depot with updates for a particular cluster instead of the depots that all clusters in that vCenter Server instance use by default.

For more information, see [Manage Depot Overrides for a Cluster](#).

Browsing the vSphere Lifecycle Manager Depot

You can use the vSphere Client to view and browse the contents of the vSphere Lifecycle Manager depot.

You can view the vSphere Lifecycle Manager depot in the vSphere Lifecycle Manager home view. The contents of the vSphere Lifecycle Manager depot are displayed on three different tabs:

Image Depot, **Updates**, and **Imported ISOs**.

Image Depot

On the **Image Depot** tab, you can view all VMware base images, vendor add-ons, and components that are available in the vSphere Lifecycle Manager depot.

You can use the **ESXi Versions**, **Vendor Addons**, and **Component** links at the top of the pane for easier navigation through the lists.

The **ESXi Versions** list contains all base images available in the depot together with information about the version, release date, and category for each image. When you select an image from the list, an information panel appears on the right. The panel displays a list of all components that the base image applies to a host upon remediation.

The **Vendor Addons** list contains all vendor addons available in the depot together with information about the version, release date, and category for each addon. When you select an add-on from the list, an information panel appears on the right. The panel displays information about the components that the add-on applies to the host and the components that the add-on removes from a host upon remediation.

The **Component** list contains all components that are available in the depot together with information about the version, release date, and category for each component. When you select a component from the list, an information panel appears on the right. The panel displays information about the VIBs that the component contains.

You can filter the **Component** list so that it displays only independent components or all components available in the vSphere Lifecycle Manager depot. Independent components are components that are not part of a vendor add-on.

You use the ESXi images, vendor add-ons, and components visible on the **Image Depot** tab to set up images that you can use to manage hosts in clusters collectively.

Updates

On the **Updates** tab, you can see all components available in the vSphere Lifecycle Manager depot as bulletins. You can use the **Filter by Baseline** drop-down menu to view only the bulletins that are part of a particular baseline.

When you select a bulletin from the list, additional information appears below the bulletins list. In the bottom pane, you see information about the baselines that include the selected bulletin.

You use the bulletins visible on the **Updates** tab to create baselines and baseline groups.

Because in vSphere 7.0 the official VMware depot hosts certified partner content in addition to VMware content, the **Updates** tab displays a broader set of OEM bulletins, for example vendor add-ons and VMware-certified device drivers. Some of these bulletins might have dependencies that must be pulled into the baselines that you create, so that the remediation against those baselines is successful. As a best practice, always consult the KB article for an individual bulletin to find information about its deployment specifics and required dependencies before including the bulletin in your baselines. For more information about the official VMware depot and other types of depots, see [vSphere Lifecycle Manager Download Sources](#).

Starting with vSphere 7.0, some changes are also introduced in the way VMware content is packaged. As a result, you might see additional bulletins on the **Updates** tab at patch and update releases. Those bulletins are usually of the Enhancement or BugFix category. When you include those bulletins in a baseline, you might need to also include a base ESXi bulletins in that baseline. As a best practice, to ensure successful application of patches and updates, always include the appropriate rollup bulletin into your baselines. You can use the **Show only rollup updates** toggle switch that is on the **Updates** tab to filter the list of bulletins.

Imported ISOs

On the **Imported ISOs** tab, you can see the ISO images that you import and make available to vSphere Lifecycle Manager.

You use the ISO images visible on the **Imported ISOs** tab to create upgrade baselines. You cannot use an ISO image for clusters configured to use a single vSphere Lifecycle Manager image.

Note ISO images are not distributed through any online or offline depot, they are a separate software distribution format. As a result, they cannot become available in the vSphere Lifecycle Manager depot through synchronization or the regular import operation that you perform to import offline bundles (ZIP files) to the depot. To make an ISO image available to vSphere Lifecycle Manager, you must trigger the **Import ISO** operation. For more information, see [Import an ISO Image to the vSphere Lifecycle Manager Depot](#)

Import Updates to the vSphere Lifecycle Manager Depot

You can use an offline bundle in ZIP format and import updates to the vSphere Lifecycle Manager depot manually. When you import offline bundles, you add both the update metadata and actual payload to the vSphere Lifecycle Manager depot.

You use the import option to populate the vSphere Lifecycle Manager depot with updates from an offline bundle.

If you want to use vSphere Lifecycle Manager baselines, you can import offline bundles that contain patches and extensions for hosts that run ESXi 6.5 and later. In that case, you can use the contents of the offline bundle only for host patching operations. If you import an OEM offline bundle that contains an ESXi image of a version earlier than 7.0, you cannot use the image for upgrade operations. To create upgrade baselines, you need an ISO image. For more information, see [Import an ISO Image to the vSphere Lifecycle Manager Depot](#).

If you want to use vSphere Lifecycle Manager images, you can import offline bundles that contain software for hosts that run ESXi 7.0 and later. In that case, you can use the contents of the offline bundle to set up vSphere Lifecycle Manager images, which you can use to upgrade ESXi hosts collectively.

As in previous releases, offline bundles can contain patches and extensions. Starting with vSphere 7.0, an offline bundle can also contain an ESXi base image, a vendor add-on, or third-party software, for example, asynchronous drivers specific to the OEM hardware requirements. For more information about base images, vendor add-ons, and components, see [VIBs, Bulletins, Components](#).

Prerequisites

- Verify that the updates that you import are in ZIP format.
- Required privileges: **VMware vSphere Lifecycle Manager.Upload File.Upload File**.

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 Select **Actions > Import Updates** at the top of the vSphere Lifecycle Manager home view.

The **Import Updates** dialog box opens.
- 3 Enter a URL or browse to an offline bundle in ZIP format on your local machine.

If the upload fails, check whether the structure of the ZIP file is correct and whether the vSphere Lifecycle Manager network settings are set up correctly.

4 Click **Import**.

The Import updates task appears in the **Recent Tasks** pane.

Results

You imported updates to the vSphere Lifecycle Manager depot.

You can view the imported patches and extension on the **Updates** tab in the vSphere Lifecycle Manager home view.

You can view the imported ESXi images, vendor add-ons, and additional components on the **Image Depot** tab in the vSphere Lifecycle Manager home view.

Import an ISO Image to the vSphere Lifecycle Manager Depot

You import ESXi images in ISO format to the vSphere Lifecycle Manager local depot, so that you can create upgrade baselines, which you use for host upgrade operations.

You can use ESXi .iso images to upgrade ESXi 6.5.x hosts and ESXi 6.7.x hosts to ESXi 7.0.

ISO images can only be used with vSphere Lifecycle Manager baselines. You cannot use an ISO image to upgrade the hosts in a cluster that uses a single image.

To upgrade hosts, use the ESXi installer image distributed by VMware with the name format `VMware-VMvisor-Installer-7.0.0-build_number.x86_64.iso` or a custom image created by using vSphere ESXi Image Builder. You can also use ISO images created and distributed by OEMs.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Upload File**

Procedure

1 Navigate to the vSphere Lifecycle Manager home view.

a In the vSphere Client, select **Menu > Lifecycle Manager**.

b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.

2 On the **Imported ISOs** tab, click **Import ISO**

3 In the **Import ISO** dialog box, select an image.

■ Click the **Browse** button to import an ESXi image from your local system.

■ Enter an URL address to import an ESXi image that is not on your local system.

Local images are imported immediately, whereas importing images from a URL takes some time.

4 Click **Import**.

Results

The ISO image that you uploaded appears in the list of images. You can view information about the ESXi image, such as product, version, and build details, vendor, acceptance level, and creation date.

What to do next

Create a host upgrade baseline.

Delete an ISO Image from the vSphere Lifecycle Manager Depot

If you do not need an ESXi image, you can delete it from the vSphere Lifecycle Manager depot.

Unlike components and bulletins, which you cannot delete from the vSphere Lifecycle Manager depot, the ISO images that you import in the depot can be deleted when you no longer need them .

Prerequisites

- Verify that the ISO image that you want to delete is not part of any baseline. You cannot delete images that are included in a baseline.
- Delete any baseline that contains the ISO image that you want to delete.

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 On the **Imported ISOs** tab, select an image from the list and click **Delete**.

Note If you try to delete an ESXi image that is used in a baseline, the operation fails with an error message.

- 3 Click **Yes** to confirm the deletion.

Results

The ISO image is deleted and no longer available.

Synchronize the vSphere Lifecycle Manager Depot

Instead of waiting for the predefined download task to run as scheduled, you can update your local vSphere Lifecycle Manager depot immediately.

At regular configurable intervals, vSphere Lifecycle Manager downloads updates from the configured download sources. The download sources can be online depots or a UMDS-created shared repository.

Regardless of the download schedule, you can initiate synchronization between the vSphere Lifecycle Manager depot and the configured download sources. Similar to scheduled synchronization, when you initiate synchronization manually, vSphere Lifecycle Manager downloads software from all online depots that you configured it to use. For more information about configuring the vSphere Lifecycle Manager download sources, see [Configuring the vSphere Lifecycle Manager Download Sources](#).

During synchronization, vSphere Lifecycle Manager downloads only the update metadata, the actual payloads are downloaded during staging or remediation.

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 Select **Actions > Sync Updates** at the top of the vSphere Lifecycle Manager home view.

The Sync updates task appears in the **Recent Tasks** pane.

Results

You downloaded updates to the vSphere Lifecycle Manager depot.

You can view the downloaded patches and extension on the **Updates** tab in the vSphere Lifecycle Manager home view.

You can view the downloaded ESXi images, vendor add-ons, and components on the **Image Depot** tab in the vSphere Lifecycle Manager home view.

Configuring the vSphere Lifecycle Manager Download Sources

You can configure vSphere Lifecycle Manager to download software updates for ESXi hosts either from the Internet or from a shared repository of UMDS data.

vSphere Lifecycle Manager downloads only the metadata and not the actual binary payload of the updates. Downloading the metadata saves disk space and network bandwidth. The availability of regularly updated metadata in the vSphere Lifecycle Manager depot lets you perform compliance checks on hosts at any time.

Whatever the download source, vSphere Lifecycle Manager downloads the following types of information:

- Metadata about all ESXi 6.x updates regardless of whether you have hosts of such versions in your environment.
- Metadata about all ESXi 7.x updates regardless of whether you have hosts of such versions in your environment.
- Patch recalls for ESXi 6.x hosts.

vSphere Lifecycle Manager supports the recall of patches for hosts that are running ESXi 6.5 or later. A patch is recalled when it has problems or potential issues. After you scan the hosts in your environment, vSphere Lifecycle Manager alerts you if the recalled patch has been installed on any host. Recalled patches cannot be installed on hosts with vSphere Lifecycle Manager. vSphere Lifecycle Manager deletes all the recalled patches from the vSphere Lifecycle Manager depot. After a patch that fixes the problem is released, vSphere Lifecycle Manager downloads the new patch to its depot. If you have already installed the problematic patch, vSphere Lifecycle Manager notifies you that a fix is available and prompts you to apply the new patch.

Downloading host patches from the VMware website is a secure process.

- Patches are cryptographically signed with the VMware private keys. Before you try to install a patch on a host, the host verifies the signature. This signature enforces the end-to-end protection of the patch itself and can also address any concerns about downloading the patch.
- vSphere Lifecycle Manager downloads the patch metadata and patch binaries over SSL connections. vSphere Lifecycle Manager verifies both the validity of the SSL certificates and the common name in the certificates. The common name in the certificates must match the names of the servers from which vSphere Lifecycle Manager downloads the patches. vSphere Lifecycle Manager downloads the patch metadata and binaries only after successful verification of the SSL certificates.

Download Sources

If your deployment system is connected to the Internet, you can use the default settings and links for downloading updates to the vSphere Lifecycle Manager depot. You can also add URL addresses to download third-party software, for example drivers.

If your deployment system is not connected to the Internet, you can use a shared repository after downloading the upgrades, patches, and extensions by using Update Manager Download Service (UMDS).

For more information about UMDS, see [Chapter 19 Installing, Setting Up, and Using Update Manager Download Service](#).

The default configuration is for the vSphere Lifecycle Manager to download information directly from the Internet. However, you can change the download source at any time. Changing the download source from a shared repository to the Internet and the reverse is a change in the vSphere Lifecycle Manager configuration. The two options are mutually exclusive. You cannot download updates from the Internet and a shared repository at the same time.

By default, vSphere Lifecycle Manager is configured to use the official VMware online depot as a download source. When you deploy vCenter Server, synchronization to the official VMware depot is triggered automatically. When you change the default download source, synchronization to the new download source is not triggered automatically. The synchronization task runs as per its schedule. To download new data, you must run the VMware vSphere Update Manager Download task or trigger synchronization manually.

The VMware vSphere Update Manager Download task is a scheduled task that runs at regular intervals. You can change the schedule, and you can also trigger the VMware vSphere Update Manager Download task independently of its schedule.

If the VMware vSphere Update Manager Download task is running when you apply the new configuration settings, the task continues to use the old settings until it finishes. The next time the download task starts, vSphere Lifecycle Manager uses the new settings.

Using a Proxy Server

Starting with vSphere 7.0, you cannot configure vSphere Lifecycle Manager to use a proxy server on its own. vSphere Lifecycle Manager uses the proxy settings of the vCenter Server instance where it runs.

In vSphere 6.7 and earlier, you can configure the proxy settings for Update Manager and use a proxy server to download updates metadata from the Internet.

Configure vSphere Lifecycle Manager to Use a Shared Repository as a Download Source

You can configure vSphere Lifecycle Manager to use a shared repository as a source for downloading ESXi images, vendor add-ons, and additional components.

You cannot use folders on a network drive as a shared repository. vSphere Lifecycle Manager does not download updates from folders on a network share in the Microsoft Windows Uniform Naming Convention form (such as \\Computer_Name_or_Computer_IP\Shared), or on a mapped network drive (for example, Z:\).

The downloading of updates takes place at configurable regular intervals. To initiate downloading of updates regardless of the download schedule, see [Synchronize the vSphere Lifecycle Manager Depot](#).

Prerequisites

- Create a shared repository by using UMDS and host the repository on a Web server or a local disk. For detailed information about exporting the upgrades, update binaries, and update metadata in [Export the Downloaded Data](#).
- Verify that UMDS is of version compatible with the version of vSphere Lifecycle Manager that you are using. For more information about compatibility, see [Compatibility Between UMDS and vSphere Lifecycle Manager](#).
- Required privileges: **VMware vSphere Lifecycle Manager.Configure**.

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.

- a In the vSphere Client, select **Menu > Lifecycle Manager**.

- b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.

- 2 On the **Settings** tab, select **Administration > Patch Setup**.

- 3 Click the **Change Download Source** button.

The **Change Download Source Type** dialog box opens.

- 4 Select the **Download patches from a UMDS shared repository** option and enter a path or URL address to the shared repository.

For example, `C:\repository_path\`, `https://repository_path/` or `http://repository_path/`.

In these examples, *repository_path* is the path to the folder with the exported downloaded upgrades, patches, extensions, and notifications. In an environment where vSphere Lifecycle Manager does not have direct access to the Internet, but is connected to a physical machine that has access to the Internet, the folder can be on a Web server.

You can specify an HTTP or HTTPS address, or a location on the disk where vSphere Lifecycle Manager runs. HTTPS addresses are supported without any authentication.

- 5 Click **Save**.

vCenter Server validates the URL. You can use the path to the shared repository only when the validation is successful. If the validation fails, vSphere Lifecycle Manager reports a reason for the failure.

Important If the updates in the folder that you specify are downloaded with a UMDS version that is not compatible with the vCenter Server version that you use, the validation fails and you receive an error message.

Results

The shared repository is used as the main source for downloading software updates. Downloading from the repository is enabled by default.

Example: Using a Folder or a Web Server as a Shared Repository

You can use a folder or a Web server as a shared repository.

- When you use a folder as a shared repository, *repository_path* is the path to the top-level directory that stores the patches and notifications exported from UMDS.

For example, use UMDS to export the patches and notifications to the F:\ drive, which is a drive mapped to a plugged-in USB device on the physical machine where UMDS is installed. Then, plug in the USB device to the physical machine where vSphere Lifecycle Manager runs. The device is mapped as E:\ and the folder to configure as a shared repository for vSphere Lifecycle Manager is E:\.

- When you use a Web server as a shared repository, *repository_path* is the path to the top-level directory on the Web server that stores the patches exported from UMDS.

For example, export the patches and notifications from UMDS to C:\docroot\exportdata. If the folder is configured on a Web server and is accessible from other physical machines at the URL https://umds_host_name/exportdata, the URL to configure as a shared repository in vSphere Lifecycle Manager is https://umds_host_name/exportdata.

Configure vSphere Lifecycle Manager to Use the Internet as a Download Source

If your deployment system is connected to the Internet, you can configure vSphere Lifecycle Manager to directly download ESXi images, vendor add-ons, and other components from the configured online depots to the local vSphere Lifecycle Manager depot.

The Internet is the default download source for vSphere Lifecycle Manager. Downloading takes place at configurable regular intervals. To initiate downloading of updates regardless of the download schedule, see [Synchronize the vSphere Lifecycle Manager Depot](#).

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Configure**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.

2 On the **Settings** tab, select **Administration > Patch Setup**.

3 Click the **Change Download Source** button.

The **Change Download Source Type** dialog box opens.

4 Select the **Download patches directly from the Internet** option and click **Save**.

Add a New Download Source

If you use the Internet as a download source for updates, you can add URL addresses to third-party online depots. vSphere Lifecycle Manager downloads software updates from all the online depots that you configured it to use. Update metadata are downloaded from the online depots to the local vSphere Lifecycle Manager depot.

The default download source for vSphere Lifecycle Manager is the official VMware depot.

Starting with vSphere 7.0, the official VMware online depot also hosts vendor add-ons and VMware-certified device drivers. Unlike previous releases, all software that you need to install, update, or customize the ESXi version of your hosts is available in the official VMware online depot.

Downloading updates takes place at configurable regular intervals. To initiate the downloading of updates regardless of the download schedule, see [Synchronize the vSphere Lifecycle Manager Depot](#).

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Configure**

Procedure

1 Navigate to the vSphere Lifecycle Manager home view.

a In the vSphere Client, select **Menu > Lifecycle Manager**.

b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.

2 On the **Settings** tab, select **Administration > Patch Setup**.

3 In the **Patches downloaded from the Internet** pane, click **New**.

The **New Download Source** dialog box opens.

- 4 Enter a URL address to a new download source.

vSphere Lifecycle Manager supports both HTTP and HTTPS URL addresses. Use HTTPS URL addresses to download data securely. The URL addresses that you add must be complete and contain an `index.xml` file, which lists the vendor and the vendor index.

Note The proxy settings that vSphere Lifecycle Manager uses are also applicable to third-party URL addresses.

- 5 (Optional) Enter a short description for the download source.

- 6 Click **Save**.

Results

The new location is added to the list of download sources and downloading from it is enabled by default.

Modify a Download Source

You can enable, disable, edit, or delete a download source from the list of vSphere Lifecycle Manager download sources.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Configure**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 On the **Settings** tab, select **Administration > Patch Setup**.
- 3 In the **Patches downloaded from the Internet** pane, select a URL address from the list of download sources and select your task.
 - Click **Edit** to edit the source URL or the description for the selected download source.
 - Click **Enable** or **Disable** to enable or disable downloading from the selected download source.
 - Click **Delete** to delete the selected download source.

Note You cannot edit or delete the default VMware download source for ESXi updates. You can only enable or disable downloading update metadata from it.

Configure the vSphere Lifecycle Manager Automatic Download Task

Downloading host updates and related metadata is a predefined automatic process that you can modify. The automatic download task is enabled by default and starts immediately after you deploy vCenter Server. After the initial download, the task runs according to its schedule.

The default schedule settings ensure frequent checks, but you can change the schedule if your environment requires you to adjust the frequency of the checks.

If you need the latest software updates, you might want to reduce the time interval between the checks for updates. By contrast, if you are not concerned about the latest updates, if you want to reduce the network traffic, or if you cannot access the update servers, you might want to increase the time interval between the checks for updates.

The automatic download of update metadata is enabled by default and the default task name is VMware vSphere vSphere Lifecycle Manager Update Download. You can change the configuration of the task.

Prerequisites

- Verify that the machine on which vSphere Lifecycle Manager runs has access to the Internet.
- Required privileges: **VMware vSphere Lifecycle Manager.Configure**.

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 On the **Settings** tab, select **Administration > Patch Downloads**.
- 3 In the **Automatic Download Settings** pane, click the **Edit** button.

The **Edit Settings for Automatic Patch Downloads** dialog box opens.
- 4 Select the **Download patches** check box and configure the schedule and settings for the download.

To receive notification emails after the download task finishes, you must configure mail settings for the vSphere Client. For more information, see the *vCenter Server and Host Management* documentation.
- 5 Click **Save** to save your changes and close the dialog box.

Results

The automatic download task runs according to the schedule you configured.

Run the VMware vSphere vSphere Lifecycle Manager Update Download Task

If you change the download source, you must run the VMware vSphere vSphere Lifecycle Manager Update Download task to download any new updates.

Procedure

- 1 In the vSphere Client, navigate to a vCenter Server instance.
- 2 On the **Configure** tab, select **Scheduled Tasks**.
- 3 In the **Scheduled Tasks** pane, select the **VMware vSphere Lifecycle Manager Update Download** task and click **Run**.

Results

You can see the running task listed in the **Recent Tasks** pane.

Configuring the vSphere Lifecycle Manager Remediation Settings

8

Whether you manage the ESXi hosts in your environment with baselines or with images, you can configure the behavior of vSphere Lifecycle Manager during host update and upgrade operations.

You can configure and modify the vSphere Lifecycle Manager settings only if you have the privileges to configure the vSphere Lifecycle Manager settings and service. The permission must be assigned to the vCenter Server where vSphere Lifecycle Manager runs. For more information about managing users, groups, roles, and permissions, see the *vSphere Security* documentation. For a list of the vSphere Lifecycle Manager privileges and their descriptions, see [Chapter 6 vSphere Lifecycle Manager Privileges](#).

If your vCenter Server system is connected to other vCenter Server systems by a common vCenter Single Sign-On domain, you can configure the settings for each vSphere Lifecycle Manager instance. The configuration properties that you modify are applied only to the vSphere Lifecycle Manager instance that you specify, and are not propagated to the other instances in the domain.

You can change any of the vSphere Lifecycle Manager settings on the **Settings** tab in the vSphere Lifecycle Manager home view.

Host Remediation Settings

You can use baselines or images to remediate individual hosts or all hosts in a cluster collectively. Some remediation settings are applicable regardless of whether you use baselines or images to initiate host remediation. For example, you can configure virtual machine migration settings, maintenance mode settings, and quick boot for hosts that are managed by either cluster images or baselines.

Other settings are applicable only to hosts that you manage by using baselines and baselines groups. Such settings are allowing the installation of software on PXE booted hosts and the removal of media devices before maintenance mode.

For information about how to configure host remediation settings, see [Configure Remediation Settings for vSphere Lifecycle Manager Baselines](#) and [Configure Remediation Settings for vSphere Lifecycle Manager Images](#).

You can also configure certain cluster settings to ensure successful remediation. For more information about the cluster settings that affect host remediation, see [Cluster Settings and Host Remediation](#).

Quick Boot

Quick Boot is a setting that you can use with clusters that you manage with vSphere Lifecycle Manager images and vSphere Lifecycle Manager baselines. Using Quick Boot optimizes the host patching and upgrade operations. Quick Boot lets vSphere Lifecycle Manager reduce the remediation time for hosts that undergo patch and upgrade operations. Patch and upgrade operations do not affect the hardware of a host. If the Quick Boot feature is enabled, vSphere Lifecycle Manager skips the hardware reboot (the BIOS or UEFI firmware reboot). As a result, the time an ESXi host spends in maintenance mode is reduced and the risk of failures during remediation is minimized.

Quick Boot is supported on a limited set of hardware platforms and drivers. Quick Boot is not supported on ESXi hosts that use TPM or passthrough devices. For more information about a host's compatibility with the Quick Boot setting, see the following KB article: <https://kb.vmware.com/s/article/52477>.

This chapter includes the following topics:

- [Cluster Settings and Host Remediation](#)
- [Configure Remediation Settings for vSphere Lifecycle Manager Images](#)
- [Configure Remediation Settings for vSphere Lifecycle Manager Baselines](#)

Cluster Settings and Host Remediation

When you remediate ESXi hosts that are in a cluster, certain cluster settings might cause remediation failure. You must configure the cluster settings in such a way as to ensure successful remediation.

When you update the ESXi hosts in a cluster that has vSphere Distributed Resource Scheduler (DRS), vSphere High Availability (HA), and vSphere Fault Tolerance (FT) enabled, you can temporarily disable vSphere Distributed Power Management (DPM), HA admission control, and FT for the entire cluster. When the update finishes, vSphere Lifecycle Manager restarts these features.

DRS

Updates might require a host to enter maintenance mode during remediation. Virtual machines cannot run when a host is in maintenance mode. To ensure availability, you can enable DRS for the cluster and you can configure it for vSphere vMotion. In this case, before the host is put in maintenance mode, vCenter Server migrates the virtual machines to another ESXi host within the cluster.

To help ensure vSphere vMotion compatibility between the hosts in the cluster, you can enable Enhanced vMotion Compatibility (EVC). EVC ensures that all hosts in the cluster present the same CPU feature set to virtual machines, even if the actual CPUs on the hosts differ. EVC prevents migration failures due to incompatible CPUs. You can enable EVC only in a cluster where the host CPUs meet the compatibility requirements. For more information about EVC and the requirements that the hosts in an EVC cluster must meet, see the *vCenter Server and Host Management* documentation.

DPM

If a host has no running virtual machines, DPM might put the host in standby mode, which might interrupt a vSphere Lifecycle Manager operation. So, to make sure that all vSphere Lifecycle Manager operations finish successfully, you can configure vSphere Lifecycle Manager to disable DPM during these operations. For successful remediation, you must have vSphere Lifecycle Manager disable DPM. After the remediation task finishes, vSphere Lifecycle Manager restores DPM.

If DPM has already put a host in standby mode, vSphere Lifecycle Manager powers on the host before compliance checks and remediation. Additionally, for clusters that you manage with baselines, vSphere Lifecycle Manager powers on the host before staging, too. After the respective task finishes, vSphere Lifecycle Manager turns on DPM and HA admission control and lets DPM put the host into standby mode, if needed. vSphere Lifecycle Manager does not remediate powered off hosts.

If a host is put in standby mode and DPM is manually disabled for a reason, vSphere Lifecycle Manager does not remediate or power on the host.

HA Admission Control

Within a cluster, you must disable HA admission control temporarily to let vSphere vMotion proceed. This action prevents downtime for the machines on the hosts that you remediate. You can configure vSphere Lifecycle Manager to disable HA admission control during remediation. After the remediation of the entire cluster is complete, vSphere Lifecycle Manager restores the HA admission control settings. vSphere Lifecycle Manager disables HA admission control before remediation, but not before compliance checks. Additionally, for clusters that you manage with baselines, vSphere Lifecycle Manager disables HA admission control before staging.

Fault Tolerance

If FT is turned on for any of the virtual machines on a host within a cluster, you must temporarily turn off FT before performing any vSphere Lifecycle Manager operation on the cluster. If FT is turned on for any of the virtual machines on a host, vSphere Lifecycle Manager does not remediate that host. You must remediate all hosts in a cluster with the same updates, so that FT can be reenabled after remediation. A primary virtual machine and a secondary virtual machine cannot reside on hosts of different ESXi versions and patch levels.

Configure Remediation Settings for vSphere Lifecycle Manager Images

You can configure how ESXi hosts and VMs behave before and during the remediation of a cluster that you managed with a single image.

When you edit images remediation settings, you set the global remediation setting for all clusters that you manage with images. However, you can override the global remediation settings and use specific remediation settings for a cluster. For more information, see [Edit the Remediation Settings for a Cluster](#).

Hosts that are in a vSAN cluster can enter maintenance mode only one at a time. This behavior is a peculiarity of the vSAN cluster. For more information about the vSphere Lifecycle Manager behavior during the remediation of hosts in a vSAN cluster, see [Remediation Specifics of vSAN Clusters](#).

For information about automatically triggered hardware compatibility checks, which is a functionality that is also applicable only to vSAN clusters, see [Automatically Triggered Hardware Compatibility Checks for vSAN Clusters](#).

Prerequisites

Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.

- 2 On the **Settings** tab, select **Host Remediation > Images**.

- 3 Click the **Edit** button.

The **Edit Cluster Settings** dialog box opens.

4 Configure the images remediation settings and click **Save**.

Option	Description
Quick Boot	<p>Quick Boot reduces the host reboot time during remediation. Before you enable Quick Boot, you must ensure that the ESXi host is compatible with the feature.</p> <p>By default, Quick Boot is disabled.</p>
VM power state	<p>The VM power state option lets you control the behavior of the virtual machines that run on the ESXi host.</p> <p>You can select from the following options.</p> <ul style="list-style-type: none"> ■ Do not change power state ■ Suspend to disk ■ Power off <p>The default selection is Do not change power state.</p>
VM migration	<p>You can configure vSphere Lifecycle Manager to migrate the suspended and powered off virtual machines from the hosts that must enter maintenance mode to other hosts in the cluster.</p> <p>The default configuration is set to Do not migrate powered off and suspended VMs to other hosts in the cluster.</p>
Maintenance mode failures	<p>You can configure how vSphere Lifecycle Manager behaves if a host fails to enter maintenance mode before remediation. You can configure vSphere Lifecycle Manager to wait for a specified retry delay period and to retry to put the host into maintenance mode as many times as you indicate in the Number of retries text box.</p>
HA admission control	<p>Admission control is a policy that vSphere HA uses to ensure failover capacity within a cluster. If vSphere HA admission control is enabled during remediation, vMotion might be unable to migrate the virtual machines within the cluster.</p> <p>Disabling admission control allows a virtual machine to be powered on even if it causes insufficient failover capacity. When this happens, no warnings are presented, and the cluster does not turn red. If a cluster has insufficient failover capacity, vSphere HA can still perform failovers, and uses the VM Restart Priority setting to determine which virtual machines to power on first.</p> <ul style="list-style-type: none"> ■ If you select the Disable HA admission control on the cluster option, vSphere Lifecycle Manager remediates the hosts in the cluster and re-enables HA admission control after remediation is complete. ■ If you deselect the Disable HA admission control on the cluster option, vSphere Lifecycle Manager skips remediating the clusters on which HA admission control is enabled. <p>By default, the Disable HA admission control on the cluster option is deselected.</p>

Option	Description
DPM	<p>VMware Distributed Power Management (DPM) monitors the resources consumed by the running virtual machines in the cluster. If sufficient excess capacity exists, VMware DPM recommends moving virtual machines to other hosts in the cluster and placing the original host into standby mode to conserve power. If the capacity is insufficient, VMware DPM might recommend returning standby hosts to a powered-on state.</p> <ul style="list-style-type: none"> ■ If you select the Disable DPM on the cluster option, vSphere Lifecycle Manager remediates the hosts in the cluster and re-enables DPM after remediation is complete. ■ If you deselect the Disable DPM on the cluster option, vSphere Lifecycle Manager skips remediating the clusters on which DPM is enabled. <p>By default, the Disable DPM on the cluster option is enabled.</p>
Hardware compatibility issues	<p>vSphere Lifecycle Manager performs a hardware compatibility check as part of the remediation pre-check and the remediation tasks for vSAN clusters. You can configure vSphere Lifecycle Manager to prevent remediation when hardware compatibility issues exist for the cluster.</p> <ul style="list-style-type: none"> ■ If you select the Prevent remediation if hardware compatibility issues are found option, vSphere Lifecycle Manager reports hardware compatibility issues as an error, which prevents remediation. ■ If you deselect the Prevent remediation if hardware compatibility issues are found option, vSphere Lifecycle Manager reports hardware compatibility issues as a warning, which does not prevent remediation. <p>If the cluster is not vSAN-enabled, vSphere Lifecycle Manager does not perform a hardware compatibility check as part of the remediation pre-check or the remediation tasks.</p>

Results

These settings become the default failure response settings with vSphere Lifecycle Manager images. You can specify different settings when you configure individual remediation tasks.

Configure Remediation Settings for vSphere Lifecycle Manager Baselines

You can configure how vSphere Lifecycle Manager behaves before and during remediation against a baseline or a baseline group. The remediation settings help ensure that vSphere Lifecycle Manager puts ESXi hosts in maintenance mode before remediation.

vSphere Lifecycle Manager might behave differently during remediation against an image and against a baseline.

You cannot use vMotion to migrate virtual machines that run on individual hosts. If vCenter Server cannot migrate the virtual machines to another host, you can configure how vSphere Lifecycle Manager responds. You can also configure how vSphere Lifecycle Manager responds when a host fails to enter maintenance mode.

Hosts that are in a vSAN cluster can enter maintenance mode only one at a time. This behavior is a peculiarity of the vSAN cluster. For more information about the vSphere Lifecycle Manager behavior during the remediation of hosts in a vSAN cluster, see [Chapter 16 vSAN Clusters and vSphere Lifecycle Manager](#).

When you use vSphere Lifecycle Manager baselines, you can configure vSphere Lifecycle Manager to let other software initiate the remediation of PXE booted ESXi hosts. The remediation installs software modules on the hosts, but typically those host updates are lost after a reboot. To retain updates on stateless hosts after a reboot, use a PXE boot image that contains the updates. You can update the PXE boot image before applying the updates with vSphere Lifecycle Manager, so that the updates are not lost because of a reboot. vSphere Lifecycle Manager itself does not reboot the hosts, because it does not install updates requiring a reboot on PXE booted ESXi hosts.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Configure**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 On the **Settings** tab, select **Host Remediation > Baselines**.
- 3 Click the **Edit** button.

The **Edit Settings for Host Remediation** dialog box opens.
- 4 Configure the baselines remediation settings and click **Save**.

Option	Description
VM power State	You can determine the behavior of the virtual machines that run on the host. You can configure vSphere Lifecycle Manager to power off or suspend all running virtual machines before host remediation. Alternatively, you can choose not to change the power state of the virtual machines.
Maintenance mode failures	If a host fails to enter maintenance mode before remediation, vSphere Lifecycle Manager waits for the specified retry delay period and retries putting the host into maintenance mode as many times as you indicate in the Number of retries text box.
PXE booted hosts	You can allow the installation of software for solutions on the PXE booted ESXi hosts in the vSphere inventory that you manage with vSphere Lifecycle Manager baselines.

Option	Description
VM migration	vSphere Lifecycle Manager migrates the suspended and powered off virtual machines from the hosts that must enter maintenance mode to other hosts in the cluster.
Removable media devices	vSphere Lifecycle Manager does not remediate hosts on which virtual machines have connected CD/DVD or floppy drives. All removable media drives that are connected to the virtual machines on a host might prevent the host from entering maintenance mode and interrupt remediation. So, you can disconnect all removable media devices to ensure that the respective host enters maintenance mode successfully. After remediation, vSphere Lifecycle Manager reconnects the removable media devices if they are still available.
Quick Boot	Quick Boot reduces the host reboot time during remediation. Before you enable Quick Boot, you must make sure that the ESXi host is compatible with the feature. For more information, see Quick Boot .

Results

These settings become the default failure response settings with vSphere Lifecycle Manager baselines. You can specify different settings when you configure individual remediation tasks.

Cluster Operations and vSphere Lifecycle Manager

9

Whether you manage the hosts and clusters in your environment with vSphere Lifecycle Manager baselines or vSphere Lifecycle Manager images has an impact on the basic cluster operations.

All cluster-related operations are described in full detail in the *vCenter Server and Host Management* documentation.

For information about using Auto Deploy to deploy and provision ESXi hosts, see *VMware ESXi Installation and Setup*.

Creating a Cluster

When you create a new cluster, you can specify an image to be applied to all hosts in the cluster. If you do not specify an image during the creation of the cluster, you must use baselines for host patching and upgrade operations. You can switch from using baselines to using images at a later time. For more information about switching from baselines to images, see [Chapter 12 Switching from Baselines to Images](#).

Before you create a cluster that uses a single image or switch to using images, verify that the cluster meets all requirements for using images. See [Chapter 5 vSphere Lifecycle Manager Requirements and Specifics](#).

Extending a Cluster

You can extend a cluster by adding hosts to the cluster.

You can add hosts of any version to a cluster that you manage with baselines.

You can add hosts to a cluster that you manage with a single image only if the hosts are of ESXi version 7.0 and meet all other requirements. See [Chapter 5 vSphere Lifecycle Manager Requirements and Specifics](#). The image that the cluster uses is applied to the newly added host upon remediation.

Note When you add a host to a vSAN cluster that you manage with a single image, vSphere Lifecycle Manager invalidates the results from the last hardware compatibility check for the cluster. To obtain valid hardware compatibility information about the cluster, re-run a hardware compatibility check. For instructions how to check the hardware compatibility for a cluster, see [Check the Hardware Compatibility of a Cluster](#) .

Removing Hosts from a Cluster

Removing a host from a cluster is a straightforward procedure. If you remove a host from a cluster that uses a single image, the host retains the software and firmware installed during the last remediation against the image for the cluster.

Note When you remove a host from a vSAN cluster that you manage with a single image, vSphere Lifecycle Manager invalidates the results from the last hardware compatibility check for the cluster. To obtain valid hardware compatibility information about the cluster, re-run a hardware compatibility check. For instructions how to check the hardware compatibility for a cluster, see [Check the Hardware Compatibility of a Cluster](#) .

Using Baselines and Baseline Groups

10

vSphere Lifecycle Manager baselines and baseline groups were already available in previous vSphere releases. You use baselines and baseline groups for host patching and upgrade operations.

Using baselines and baseline groups to manage the updates and upgrades of ESXi hosts is a multi-stage process.

- 1 You populate the vSphere Lifecycle Manager repository with patches, extensions, and updates.

The vSphere Lifecycle Manager repository contains software updates that you can use with both vSphere Lifecycle Manager baselines and vSphere Lifecycle Manager images. On the

Updates tab of the vSphere Lifecycle Manager home view, you see all software updates available in the vSphere Lifecycle Manager depot as bulletins.

Updates get into the vSphere Lifecycle Manager local depot through synchronization with configurable download sources. By default, vSphere Lifecycle Manager is configured to synchronize updates from the official VMware depot.

You can also import updates into the depot manually.

For host upgrade operations through baselines, you use ESXi ISO images, which you must also import to the vSphere Lifecycle Manager depot manually.

For more information about working with the vSphere Lifecycle Manager depot, see [Chapter 7 Working with the vSphere Lifecycle Manager Depot](#).

- 2 You create baselines by combining bulletins from the depot and using manually uploaded ESXi ISO images.

You can also combine several non-conflicting baselines to create a baseline group. Baseline groups can contain different types of baselines. If a baseline group contains both upgrade and patch or extension baselines, the upgrade runs first.

For more information about creating baselines and baseline groups, see [Creating and Working with Baselines and Baseline Groups](#).

- 3 You attach the baselines to individual ESXi hosts or container objects for ESXi hosts.

For more information, see [Attach Baselines and Baseline Groups to Objects](#).

- 4 You check the compliance of ESXi hosts against a selected baseline or baseline group.

You can run a compliance check on an individual ESXi host or a container object.

For more information about compliance checks against baselines and baseline groups, see [Checking Compliance Against vSphere Lifecycle Manager Baselines and Baseline Groups](#).

- 5 You review the compliance status of the scanned object.

For more information about compliance states, see [Viewing Compliance Information About ESXi Hosts and Updates](#).

- 6 You stage the patches and extensions to ESXi hosts before remediation. Staging is not a mandatory step, it is a step that you can skip.

For more information about staging updates before remediation, see [Staging Patches and Extensions to ESXi Hosts](#).

- 7 You remediate the non-compliant objects. After remediation, you can review the compliance status again to make sure that the updates are installed.

For more information about remediating objects against baselines and baseline groups, see [Remediating ESXi Hosts Against vSphere Lifecycle Manager Baselines and Baseline Groups](#).

This chapter includes the following topics:

- [Creating and Working with Baselines and Baseline Groups](#)
- [Attaching Baselines and Baseline Groups to vSphere Objects](#)
- [Checking Compliance Against vSphere Lifecycle Manager Baselines and Baseline Groups](#)
- [Staging Patches and Extensions to ESXi Hosts](#)
- [Remediating ESXi Hosts Against vSphere Lifecycle Manager Baselines and Baseline Groups](#)

Creating and Working with Baselines and Baseline Groups

You use baselines and baseline groups to update the ESXi hosts in your vSphere inventory. The vSphere Lifecycle Manager baselines are three types: predefined baselines, recommendation baselines, or custom baselines, which you create. Depending on their content, baselines can be patch, extension, or upgrade baselines.

When you initiate a compliance check for an ESXi host, you evaluate it against baselines and baseline groups to determine its level of compliance to those baselines or baseline groups.

If your vCenter Server system is connected to other vCenter Server systems by a common vCenter Single Sign-On domain, the baselines and baseline groups that you create and manage are applicable only to the inventory objects managed by the vCenter Server system where the selected vSphere Lifecycle Manager instance runs.

In the vSphere Client, the baselines and baseline groups are displayed on the **Baselines** tab of the vSphere Lifecycle Manager home view.

Predefined, Recommendation, and Custom Baselines

Predefined baselines

Predefined baselines cannot be edited or deleted, you can only attach or detach them to inventory objects.

On the **Baselines** tab in the vSphere Lifecycle Manager home view, you can see the following predefined baselines.

- Host Security Patches

The Host Security Patches baseline checks ESXi hosts for compliance with all security patches.

- Critical Host Patches

The Critical Host Patches baseline checks ESXi hosts for compliance with all critical patches.

- Non-Critical Host Patches

The Non-Critical Host Patches baseline checks ESXi hosts for compliance with all optional patches.

The Host Security Patches, and Critical Host Patches predefined baselines are attached by default to the vCenter Server instance where vSphere Lifecycle Manager runs.

Recommendation Baselines

Recommendation baselines are predefined baselines that vSAN generates.

You use recommendation baselines to update your vSAN clusters with recommended critical patches, drivers, updates, or the latest supported ESXi host version for vSAN.

These baselines appear by default when you use vSAN clusters with ESXi hosts of version 6.0 Update 2 and later in your vSphere inventory. If your vSphere environment does not contain any vSAN clusters, no recommendation baselines are created.

Recommendation baselines update their content periodically, which requires vSphere Lifecycle Manager to have constant access to the Internet. The vSAN recommendation baselines are typically refreshed every 24 hours.

Recommendation baselines cannot be edited or deleted. You do not attach recommendation baselines to inventory objects in your vSphere environment. You can create a baseline group by combining multiple recommendation baselines, but you cannot add any other type of baseline to that group. Similarly, you cannot add a recommendation baseline to a baseline group that contains upgrade, patch, and extension baselines.

Custom Baselines

Custom baselines are the baselines that you create. You can create custom patch, extension, and upgrade baselines to meet the needs of your specific deployment.

Baseline Groups

You create a baseline group by assembling existing and non-conflicting baselines. Baseline groups allow you to scan and remediate objects against multiple baselines at the same time.

The following are valid combinations of baselines that can make up a baseline group:

- Multiple host patch and extension baselines.
- One upgrade baseline, multiple patch, and extension baselines.

To create, edit, or delete baselines and baseline groups, you must have the **Manage Baseline** privilege. To attach baselines and baseline groups to target inventory objects, you must have the **Attach Baseline** privilege. The privileges must be assigned on the vCenter Server system where vSphere Lifecycle Manager runs.

For more information about managing users, groups, roles, and permissions, see the *vSphere Security* [vSphere Security](#) documentation.

For a list of all vSphere Lifecycle Manager privileges and their descriptions, see [vSphere Lifecycle Manager Privileges For Using Baselines](#).

Creating Baselines in vSphere 7.0

Because in vSphere 7.0 the official VMware online depot hosts certified partner content in addition to VMware content, a broader set of OEM bulletins are available in the vSphere Lifecycle Manager depot. As a result, in the **Create Baseline** and **Edit Baseline** wizards, you also see a broader set of OEM bulletins. Some of these bulletins might have dependencies that must be pulled into the baselines that you create, so that the remediation against those baselines is successful. As a best practice, always consult the KB article for an individual bulletin before you include it in a baseline. The KB article contains information about the bulletin deployment specifics and required dependencies.

Starting with vSphere 7.0, some changes are also introduced in the way VMware content is packaged. As a result, at patch and update releases, you might see additional bulletins on the patch selection page of the **Create Baseline** and **Edit Baseline** wizards. Those bulletins are usually of the Enhancement or BugFix category. When you include those bulletins in a baseline, you might need to also include a base ESXi bulletins in that baseline. As a best practice, to ensure successful application of VMware patches and updates, always include the appropriate rollup bulletin into your baselines.

Baseline Types by Content

Depending on their content, vSphere Lifecycle Manager baselines can be upgrade, patch, and extension baselines. You use those types of baselines to check the compliance state of target inventory objects and to remediate the non-compliant objects.

Upgrade Baselines

Host upgrade baselines define the version to which you upgrade the hosts in your environment. With vSphere Lifecycle Manager 7.0, you can upgrade ESXi hosts from version 6.5 and 6.7 to ESXi 7.0. Host upgrades to ESXi 5.x, ESXi 6.5, or ESXi 6.7 are not supported.

To create an upgrade baseline, you must first import an ESXi ISO image to the vCenter Server inventory.

Patch Baselines

Patch baselines define a number of patches that must be applied to a given host. Patch baselines can be either dynamic or fixed.

Baseline	Description
Dynamic Patch Baseline	You specify the criteria for patch inclusion in the baseline. Only the patches that meet the criteria are included in the baseline. As the set of available patches in the vSphere Lifecycle Manager depot changes, dynamic baselines are updated as well. You can manually include or exclude patches from the baseline.
Fixed Patch Baseline	You manually select the patches from the total set of patches available in the vSphere Lifecycle Manager depot.

Extension Baselines

Extensions baselines contain additional software modules for ESXi hosts, for example device drivers. This additional software might be VMware software or third-party software. You can install additional modules by using extension baselines, and update the installed modules by using patch baselines.

Extensions are installed on the hosts that do not yet have such software, and patched on the hosts that already have the software installed. All third-party software for ESXi hosts is classified as host extension, although extensions are not restricted to just third-party software.

Create a Fixed Patch Baseline

A fixed baseline is a set of patches that does not change as patch availability in the depot changes.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.

- a In the vSphere Client, select **Menu > Lifecycle Manager**.
- b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.

- 2 On the **Baselines** tab, select **New > Baseline**.

The **Create Baseline** wizard opens.

- 3 On the **Name and Description** page, enter information about the baseline and click **Next**.

- a Enter a name and, optionally, a description for the baseline.
- b Select the **Upgrade**, **Patch**, or **Extension** radio button.

- 4 On the **Select Patches Automatically** page, disable the automatic updates by deselecting the respective check box and click **Next**.

- 5 On the **Select Patches Manually** page, select the patches that you want to include in the baseline and click **Next**.

- To view only the rollup bulletins in the list, turn on the **Show only rollup updates** toggle switch.
- To filter the patches that are available in the vSphere Lifecycle Manager depot and find specific patches to include in the baseline, use the filter icon next to each column header. If you use several criteria to filter the patches, the relationship between those filter criteria is defined by the Boolean operator AND.

- 6 On the **Summary** page, review your selections and click **Finish**.

Results

The new baseline appears in the baselines list on the **Baselines** tab. You can attach the baseline to a data center, a cluster, or a host.

Create a Dynamic Patch Baseline

A dynamic baseline is a set of patches that meet certain criteria. The content of a dynamic baseline changes as the available patches change. You can manually exclude or add specific patches to the baseline.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 On the **Baselines** tab, select **New > Baseline**.

The **Create Baseline** wizard appears.
- 3 On the **Name and Description** page, enter information about the baseline and click **Next**.
 - a Enter a name and, optionally, a description for the baseline.
 - b Select the **Upgrade**, **Patch**, or **Extension** radio button.
- 4 On the **Select Patches Automatically** page, set the criteria for adding patches to the baseline.
 - a Enable the automatic update of the baseline by selecting the respective check box.
 - b On the **Criteria** tab, specify the criteria that a patch must meet to be added to the baseline and click **Next**.

Option	Description
Patch Vendor	Specifies which patch vendor to use. <div> Note In vSphere 7.0, the vendor name of VMware for inbox components has changed from VMware, Inc to VMware. As a result, if you use the filter to see only components by VMware, the filtered list contains both VMware, Inc for 6.x patches and VMware for 7.0 patches. </div>
Product	Restricts the set of patches to the selected products or operating systems. <p>The asterisk at the end of a product name is a wildcard character for any version number.</p>
Severity	Specifies the severity of patches to include.
Category	Specifies the category of patches to include.
Release Date	Specifies the range for the release dates of the patches.

The relationship between these fields is defined by the Boolean operator AND.

For example, when you select a product and severity option, the patches are restricted to the ones that are applicable for the selected product and are of the specified severity level.

- c (Optional) On the **Matched** tab, deselect patches from the ones that matched your criteria to exclude them permanently from the baseline.
- d (Optional) On the **Excluded** and **Selected** tabs, view the patches that are excluded from the baseline and the ones that are included in the baseline.

You can use the filter icon next to each column header on the **Matched**, **Excluded**, and **Selected** tabs to filter the patches that are available in the vSphere Lifecycle Manager depot. This way, you can easily find specific patches to exclude from or include in the baseline. If you use several criteria to filter the patches, the relationship between those filter criteria is defined by the Boolean operator AND.

- 5 On the **Select Patches Manually** page, select individual patches to include in the baseline and click **Next**.

The patches that are displayed on this page are patches that do not meet the criteria you set on the **Select Patches Automatically** page. You can use the filter icon next to each column header to filter the patches that are available in the vSphere Lifecycle Manager depot and find specific patches to include in the baseline. If you use several criteria to filter the patches, the relationship between those filter criteria is defined by the Boolean operator AND.

The patches that you add manually to the dynamic baseline stay in the baseline regardless of the automatically downloaded patches.

- 6 On the **Summary** page, review your selections and click **Finish**.

Results

The new baseline appears in the baselines list on the **Baselines** tab. You can attach the baseline to a data center, a cluster, or a host.

Create a Host Extension Baseline

Extension baselines contain additional software for ESXi hosts. This additional software might be VMware software or third-party software.

Extensions deliver additional host features, updated drivers for hardware, Common Information Model (CIM) providers for managing third-party modules on the host, improvements to the performance or usability of the existing host features, and so on.

The host extension baselines that you create are always fixed. You must carefully select the appropriate extensions for the ESXi hosts in your environment.

You use extension baselines to install extensions on the ESXi hosts in your environment. After an extension is installed on a host, you can update the extension module through either patch, or extension baselines.

Note When you use extension baselines, you must be aware of the functional implications that the installation of new modules on the host might have. Extension modules might alter the behavior of ESXi hosts. During the installation of extensions, vSphere Lifecycle Manager only performs the checks and verifications expressed at the package level.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 On the **Baselines** tab, select **New > Baseline**.

The **Create Baseline** wizard appears.
- 3 On the **Name and Description** page, enter information about the baseline and click **Next**.
 - a Enter a name and, optionally, a description for the baseline.
 - b Select the **Extension** radio button.
- 4 On the **Select Extensions** page, select individual extensions to include in the baseline and click **Next**.

You can use the filter icon next to each column header to filter the extensions that are available in the vSphere Lifecycle Manager depot and find specific extensions to include in the baseline. If you use several criteria to filter the patches, the relationship between those filter criteria is defined by the Boolean operator AND.
- 5 On the **Select Extensions** page, select individual extensions to include in the baseline and click **Next**.
- 6 On the **Summary** page, review your selections and click **Finish**.

Results

The new baseline appears in the baselines list on the **Baselines** tab. You can attach the baseline to a data center, a cluster, or a host.

Create a Host Upgrade Baseline

You can create upgrade baselines for ESXi hosts with ESXi 7.0 images, which you must first import to the vSphere Lifecycle Manager depot.

You can use ESXi .iso images to upgrade ESXi 6.5.x hosts and ESXi 6.7.x hosts to ESXi 7.0.

To upgrade hosts, use the ESXi installer image distributed by VMware with the name format `VMware-VMvisor-Installer-7.0.0-build_number.x86_64.iso` or a custom image created by using vSphere ESXi Image Builder. You can also use ISO images created and distributed by OEMs.

Note In case of an unsuccessful upgrade from ESXi 6.5 or ESXi 6.7 to ESXi 7.0, you cannot roll back to your previous ESXi 6.5 or ESXi 6.7 instance.

Prerequisites

- Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines**.
- Verify that you have an ESXi 7.0 image available in inventory. For more information, see [Import an ISO Image to the vSphere Lifecycle Manager Depot](#).

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 Start the **Create Baseline** wizard.
 - On the **Imported ISOs** tab, select an ESXi image from the list and click **New Baseline**.
 - On the **Baselines** tab, select **New > Baseline**.
- 3 On the **Name and Description** page, enter information about the baseline and click **Next**.
 - a Enter a name and, optionally, a description for the baseline.
 - b Select the **Upgrade** radio button.
- 4 On the **Select ISO** page, select an ESXi image from the list and click **Next**.
- 5 On the **Summary** page, review your selections and click **Finish**.

Results

The new baseline appears in the baselines list on the **Baselines** tab. You can attach the baseline to a data center, a cluster, or a host.

Create a Host Baseline Group

You can combine multiple baselines of different types into a baseline group. For example, you can combine one host upgrade baseline with multiple patch or extension baselines, or you can combine multiple patch and extension baselines.

A baseline group might contain a single host upgrade baseline and multiple patch or extension baselines, or a combination of host patch and host extension baselines.

You can create a baseline group and add baselines to it later.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines**

Procedure

- 1** Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2** On the **Baselines** tab, select **New > Baseline Group**.

The **Create Baseline Group** wizard opens.
- 3** On the **Name and Description** page, enter a unique name and, optionally, a description for the baseline group, and click **Next**.
- 4** (Optional) On the **Upgrade Baseline** page, select an upgrade baseline to include in the baseline group and click **Next**.
 - a Select the **Add the following Upgrade Baseline to the Group** check box.
 - b Select an upgrade baseline from the list.
- 5** (Optional) On the **Patch Baselines** page, select patch baselines to include in the baseline group and click **Next**.
- 6** (Optional) On the **Extension Baselines** page, select extension baselines to include in the baseline group and click **Next**.
- 7** On the **Summary** page, review your selections and click **Finish**.

Results

The new host baseline group appears in the baselines list on the **Baselines** tab. You can attach the baseline group to a data center, a cluster, or a host.

Edit a Patch Baseline

You can edit existing patch baselines.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 On the **Baselines** tab, select a patch baseline from the list and click **Edit**.

The **Edit Baseline** wizard appears.
- 3 (Optional) On the **Name and Description** page, edit the name and, optionally, the description of the baseline.
- 4 (Optional) On the **Select Patches Automatically** page, change the criteria for a patch selection and click **Next**.
- 5 (Optional) On the **Select Patches Manually** page, change the selected patches and click **Next**.

You can deselect patches, or select new ones to include in the patch baseline.
- 6 On the **Summary** page, review your selections and click **Finish**.

What to do next

Attach the baseline to a data center, a cluster, or a host.

Edit a Host Extension Baseline

You can change the name, description, and composition of an existing extension baseline.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 On the **Baselines** tab, select an extension baseline from the list and click **Edit**.

The **Edit Baseline** wizard appears.
- 3 (Optional) On the **Name and Description** page, edit the name and, optionally, the description of the baseline.

- 4 (Optional) On the **Select Extensions** page, change the included extensions and click **Next**.
- 5 On the **Summary** page, review your selections and click **Finish**.

What to do next

Attach the baseline to a data center, a cluster, or a host.

Edit a Host Upgrade Baseline

You can change the name of an existing upgrade baseline. You can also select a different ESXi image for the baseline.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 On the **Baselines** tab, select an upgrade baseline from the list and click **Edit**.

The **Edit Baseline** wizard appears.
- 3 (Optional) On the **Name and Description** page, edit the name and, optionally, the description of the baseline.
- 4 (Optional) On the **Select ISO** page, change the included ESXi image and click **Next**.
- 5 On the **Summary** page, review your selections and click **Finish**.

Edit a Baseline Group

You can change the name and type of an existing baseline group. You also use the **Edit Baseline Group** wizard to add or remove baselines to an existing baseline group.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.

- a In the vSphere Client, select **Menu > Lifecycle Manager**.
- b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.

- 2 On the **Baselines** tab, select a baseline group from the list and click **Edit**.

The **Edit Baseline Group** wizard opens.

- 3 (Optional) On the **Name and Description** page, edit the name, description, or the ESXi version for the baseline group.

- 4 (Optional) On the **Upgrade Baseline** page, select an upgrade baseline and select your task, and click **Next**.

- To add the selected upgrade baseline to the baseline group, select the **Add the following Upgrade Baseline to the Group** check box.
- To remove the selected upgrade baseline from the baseline group, deselect the **Add the following Upgrade Baseline to the Group** check box.

- 5 (Optional) On the **Patch Baselines** page, specify which patch baselines are included in the baseline group and click **Next**.

- To add patch baselines to the baseline group, select the respective patch baselines.
- To remove patch baselines from the baseline group, deselect the respective patch baselines.

- 6 (Optional) On the **Extension Baselines** page, specify which extension baselines are included in the baseline group and click **Next**.

- To add extension baselines to the baseline group, select the respective extension baselines.
- To remove extension baselines from the baseline group, deselect the respective extension baselines.

- 7 On the **Summary** page, review your selections and click **Finish**.

What to do next

Attach the baseline group to a data center, a cluster, or a host.

Add or Remove a Single Update from a Custom Baseline

You can edit the content of a custom baseline by adding or removing individual patches or extension from the baseline.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 Click the **Updates** tab.

You see a list of all updates in the vSphere Lifecycle Manager depot.
- 3 Select a patch or extension from the list, and click **Add/Remove Baselines**.

The **Add/Remove baselines** dialog box opens.
- 4 Select your task.
 - To add the patch to a baseline, select that baseline in the **Custom Patch Baselines** list.
 - To remove the patch from a baseline, deselect that baseline in the **Custom Patch Baselines** list.
- 5 Click **OK**.

Duplicate Baselines and Baseline Groups

You can duplicate baselines and baseline groups and edit the copies without the risk of compromising the original baseline.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 On the **Baselines** tab, select a baseline or a baseline group from the list and click **Duplicate**.

The **Duplicate Baseline** dialog box opens.

- 3 Enter a name for the new baseline or baseline group or use the suggested one.
- 4 Click **Duplicate** to confirm the creation of a duplicate copy of the selected baseline or baseline group.

Results

The duplicated baseline or baseline group appears in the **Baselines** list on the **Baselines** tab.

Delete Baselines and Baseline Groups

You can delete the baselines and baseline groups that you no longer need. Deleting a baseline detaches it from all the objects to which it is attached. You cannot delete predefined and system-managed baselines.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 On the **Baselines** tab, select a baseline or a baseline group from the list and click **Delete**.

The **Delete Baseline** dialog box opens.
- 3 Click **Yes** to confirm the deletion of the selected baseline or baseline group.

Attaching Baselines and Baseline Groups to vSphere Objects

To update ESXi hosts by using vSphere Lifecycle Manager baselines and baseline groups, you must first attach the baselines and baseline groups to individual hosts, clusters, or container objects.

When you no longer need baselines or baseline groups, you can detach them from the objects.

Attach Baselines and Baseline Groups to Objects

To check the compliance status of the objects in your inventory against selected baselines and baseline groups, you must first attach the respective baselines and baseline groups to the objects.

You attach baselines and baseline groups to individual hosts or objects that contain hosts, such as clusters, data centers, and vCenter Server instances. In the vSphere infrastructure hierarchy, the baseline and baseline groups that you attach to container objects are also attached to the child objects. For example, if you attach a baseline or baseline group to a folder, the baseline or the baseline groups is inherited by all the objects in the folder, including subfolders.

You cannot use vSphere Lifecycle Manager to update the hosts in a cluster that uses a single vSphere Lifecycle Manager image. For more information about using vSphere Lifecycle Manager images to manage hosts in clusters collectively, see [Chapter 11 Using Images](#).

Prerequisites

- If you want to attach a baseline or a baseline group to a cluster, verify that the cluster is not configured to use a single image.
- Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines.Attach Baseline**.

Procedure

- 1 In the vSphere Client, navigate to the vSphere Lifecycle Manager compliance view for an individual host or a container object.
 - a Navigate to a host, cluster, or a container object.
 - b Click the **Updates** tab.

- 2 Select **Hosts > Baselines**.

- 3 In the **Attached Baselines** pane, click **Attach > Attach Baseline or Baseline Group**.

The **Attach** dialog box opens.

- 4 Select one or more baselines or baseline groups and click **Attach**.

If you select a baseline group, all the baselines in it are attached to the object.

The selected baselines or baseline groups are attached to the object. They appear on the list in the **Attached Baselines** pane. If the selected object is a container object, the selected baselines or baseline groups are attached to all the child objects.

What to do next

Scan the selected object against the attached baselines.

Detach Baselines and Baseline Groups from Objects

You can detach baselines and baseline groups from the objects to which the baselines or baseline groups are directly attached.

vSphere inventory objects might have inherited properties, so instead of detaching baselines and baseline groups directly from an object, you might need to select its container object and detach the baselines or baseline groups from the container object. For example, if you want to detach a baseline or a baseline group from a host that is a part of a cluster, you must select the cluster and not the host.

Prerequisites

- Verify that the cluster is not configured to manage all its hosts collectively.
- Required privileges: **VMware vSphere Lifecycle Manager.Manage Baselines.Attach Baseline**.

Procedure

- 1 In the vSphere Client, navigate to the vSphere Lifecycle Manager compliance view for an individual host or a container object.
 - a Navigate to a host, cluster, or a container object.
 - b Click the **Updates** tab.

- 2 Select **Hosts > Baselines**.

- 3 In the **Attached Baselines** pane, select one or more baselines or baseline groups and click **Detach**.

The **Detach** dialog box opens.

- 4 Select the object to detach the baseline or baseline group from and click **Detach**.

The baseline is removed from the **Attached Baselines** list.

Checking Compliance Against vSphere Lifecycle Manager Baselines and Baseline Groups

Before you update or upgrade an ESXi host or a container object with vSphere Lifecycle Manager baselines, you must first check its compliance status.

You use vSphere Lifecycle Manager to check the compliance status of ESXi hosts against the baselines and baseline groups that you attach to the hosts or to a parent container object. You do a compliance check on hosts to determine whether they have the latest patches or extensions. During the compliance check, attributes of the host are evaluated against all patches, extensions, and upgrades from an attached baseline or baseline group.

You can check the compliance status of a single ESXi host or a valid container object. Supported groups of ESXi hosts include virtual infrastructure container objects such as folders, clusters, and data centers. When you initiate a compliance check for a container object, vSphere Lifecycle Manager scans all the ESXi hosts in that container object.

Note If you initiate a compliance check for an inventory object, for example data center, that contains clusters that use vSphere Lifecycle Manager images, the compliance check is not performed for those clusters. Operations

To generate compliance information, you can initiate compliance checks manually or you can schedule the compliance checks to run at regular periods. Schedule compliance checks at a data center or vCenter Server system level to make sure that the objects in your inventory are up-to-date.

You check the compliance status of vSphere objects from the vSphere Lifecycle Manager compliance view.

To initiate or schedule compliance checks, you must have the **Scan for Applicable Patches, Extensions, and Upgrades** privilege.

For more information about managing users, groups, roles, and permissions, see the *vSphere Security* documentation.

For a list of all vSphere Lifecycle Manager privileges and their descriptions, see [vSphere Lifecycle Manager Privileges For Using Baselines](#).

Initiate a Compliance Check for ESXi Hosts Manually

Before remediation, you must check the compliance of the vSphere objects against the attached baselines and baseline groups. To check the compliance status of hosts in the vSphere inventory immediately, initiate a compliance check manually.

Prerequisites

If you want to check the compliance status of a cluster, verify that the cluster is not configured to use a single image.

Procedure

- 1 In the vSphere Client, navigate to the vSphere Lifecycle Manager compliance view for an individual host or a container object.

- a Navigate to a host, cluster, or a container object.
- b Click the **Updates** tab.

- 2 Select **Hosts > Baselines**.

The **Baselines** pane shows three panels. In those panels, you obtain host information about the selected object, host compliance information, and remediation information.

- 3 In the compliance information panel, click **Check Compliance**.

Results

The selected inventory object and all child objects are scanned against all attached patch, extension, and upgrade baselines. The larger the virtual infrastructure and the higher up in the object hierarchy that you initiate the scan, the longer the scan takes.

Schedule Regular Compliance Checks for ESXi Hosts

You can configure vSphere Lifecycle Manager to check the compliance status of ESXi hosts at specific times or at intervals that are convenient for you.

Prerequisites

If you want to check the compliance status of a cluster, verify that the cluster is not configured to use a single image.

Procedure

- 1 In the vSphere Client, navigate to the vSphere Lifecycle Manager compliance view for an individual host or a container object.

- a Navigate to a host, cluster, or a container object.
- b Click the **Updates** tab.

- 2 Select **Hosts > Baselines**.

The **Baselines** pane shows three panels. In those panels, you obtain host information about the selected object, host compliance information, and remediation information.

- 3 In the compliance information panel, click **Schedule**.

The **Automatic compliance check** dialog box opens.

- 4 Configure the compliance check schedule.

- a Set the frequency and the starting point of the compliance check.
- b Enter a unique name, and optionally, a description for the scan task.
- c (Optional) Specify one or more email addresses to receive notification after the scan task is complete.

You must configure mail settings for the vCenter Server system to enable this option.

- 5 Click **Save** to exit the **Automatic compliance check** dialog box.

Host Upgrade Compliance Messages

When you check the compliance of ESXi hosts against an upgrade baseline, vSphere Lifecycle Manager runs a precheck script and provides informative messages in the in the bottom pane of the vSphere Lifecycle Manager compliance view. The messages notify you about potential problems with hardware or third-party software on the host, and configuration issues, which might prevent a successful upgrade to ESXi 7.0.

The messages that vSphere Lifecycle Manager provides correspond to error or warning codes from running the host upgrade precheck script.

For interactive installations and upgrades performed by using the ESXi installer, the errors or warnings from the precheck script are displayed on the final panel of the installer, where you are asked to confirm or cancel the installation or upgrade. For scripted installations and upgrades, the errors or warnings are written to the installation log.

vSphere Lifecycle Manager displays scan result information in the bottom pane of the vSphere Lifecycle Manager compliance view. To see the original errors and warnings returned by the precheck script during an vSphere Lifecycle Manager host upgrade scan operation, review the vSphere Lifecycle Manager log file.

Table 10-1. Scan Result Messages and Corresponding Error and Warning Codes

Scan Result Message invSphere Lifecycle Manager	Description
Host CPU is unsupported. New ESXi version requires a 64-bit CPU with support for LAHF/SAHF instructions in long mode.	This message appears if the host processor is 32-bit and does not support required features. The corresponding error code is 64BIT_LONGMODESTATUS.
Trusted boot is enabled on the host but the upgrade does not contain the software package esx-tboot. Upgrading the host will remove the trusted boot feature.	This message indicates that the host upgrade scan did not locate the esx-tboot VIB on the upgrade ISO. The corresponding error code is TBOOT_REQUIRED
VMkernel and Service Console network interfaces are sharing the same subnet <i>subnet_name</i> . This configuration is not supported after upgrade. Only one interface should connect to subnet <i>subnet_name</i> .	Warning. An IPv4 address was found on an enabled Service Console virtual NIC for which there is no corresponding address in the same subnet in the vmkernel. A separate warning appears for each such occurrence. The corresponding error code is COS_NETWORKING.
New ESXi version requires a minimum of <i>core_count</i> processor cores.	The host must have at least two cores. The corresponding error code is CPU_CORES.
Processor does not support hardware virtualization or it is disabled in BIOS. Virtual machine performance may be slow.	Host performance might be impaired if the host processor does not support hardware virtualization or if hardware virtualization is not turned on in the host BIOS. Enable hardware virtualization in the host machine boot options. See your hardware vendor's documentation. The corresponding error code is HARDWARE_VIRTUALIZATION.
Insufficient memory, minimum <i>size_in_MB</i> required for upgrade.	The host requires the specified amount of memory to upgrade. The corresponding error code is MEMORY_SIZE.
Host upgrade validity checks for <i>file_name</i> are not successful.	This test checks whether the precheck script itself can be run. The corresponding error code is PRECHECK_INITIALIZE.
The host partition layout is not suitable for upgrade.	Upgrade is possible only if there is at most one VMFS partition on the disk that is being upgraded and the VMFS partition starts after sector 1843200. The corresponding error code is PARTITION_LAYOUT.
Unsupported configuration.	The file /etc/vmware/esx.conf must exist on the host. This message indicates that the file /etc/vmware/esx.conf is either missing, or the file data cannot be retrieved or read correctly. The corresponding error code is SANE_ESX_CONF.
The host does not have sufficient free space on a local VMFS datastore to back up current host configuration. A minimum of <i>size_in_MB</i> is required.	The host disk must have enough free space to store the ESXi 5.x configuration between reboots. The corresponding error code is SPACE_AVAIL_CONFIG.
The upgrade is not supported for current host version.	Upgrading to ESXi 7.0 is possible only from ESXi 6.5 and ESXi 6.7 hosts. The corresponding error code is SUPPORTED_ESX_VERSION.

Table 10-1. Scan Result Messages and Corresponding Error and Warning Codes (continued)

Scan Result Message <i>invSphere Lifecycle Manager</i>	Description
Unsupported devices <i>device_name</i> found on the host.	The script checks for unsupported devices. Some PCI devices are not supported with ESXi 7.0. The corresponding error code is UNSUPPORTED_DEVICES.
Host software configuration requires a reboot. Reboot the host and try upgrade again.	To ensure a good bootbank for the upgrade, you must reboot the hosts before remediation. The corresponding error code is UPDATE_PENDING.
In an environment with Cisco Nexus 1000V Distributed Virtual Switch, vSphere Lifecycle Manager displays different messages in different situations. For details, see Host Upgrade Compliance Messages When Cisco Nexus 1000V Is Present .	If Cisco's Virtual Ethernet Module (VEM) software is found on the host, the precheck script checks if the software is part of the upgrade as well, and that the VEM supports the same version of the Virtual Supervisor Module (VSM) as the existing version on the host. If the software is missing or is compatible with a different version of the VSM, the script returns a warning and the scan result indicates the version of the VEM software that was expected on the upgrade ISO, and the version, if any, that was found on the ISO. The corresponding error code is DISTRIBUTED_VIRTUAL_SWITCH.
The host uses an EMC PowerPath multipathing module <i>file_name</i> to access storage. The host will not be able to access such storage after upgrade.	The script checks for installation of EMC PowerPath software, consisting of a CIM module and a kernel module. If either of these components is found on the host, the script verifies that matching components (CIM, VMkernel module) also exist in the upgrade. If they do not, the script returns a warning that indicates which PowerPath components were expected on the upgrade ISO and which, if any, were found. The corresponding error code is POWERPATH.

Host Upgrade Compliance Messages When Cisco Nexus 1000V Is Present

When a host is managed by the Cisco Nexus 1000V virtual switch and you check the compliance of the host against an upgrade baseline, the scan messages provide information about problems with compliance between the VEM modules installed on the host and the modules available on the ESXi 7.0 image.

vSphere Lifecycle Manager supports Cisco Nexus 1000V, a virtual access software switch that works with VMware vSphere and consists of two components.

Virtual Supervisor Module (VSM)

The control plane of the switch and a virtual machine that runs NX-OS.

Virtual Ethernet Module (VEM)

A virtual line card embedded in ESXi hosts.

vSphere Lifecycle Manager determines whether a host is managed by Cisco Nexus 1000V. vSphere Lifecycle Manager verifies whether the Cisco Nexus 1000V VEM VIBs in the ESXi upgrade image are compatible with the Cisco Nexus 1000V VSM that manages the host.

By using vSphere ESXi Image Builder, you can create custom ESXi images, which contain third-party VIBs that are required for a successful remediation operation.

Table 10-2. Compliance Check Results for the Cisco Nexus 1000V Network Switch

Compliance Check Message	Description
The upgrade does not contain any Cisco Nexus 1000V software package that is compatible with the Cisco Nexus 1000V software package on the host. Upgrading the host will remove the feature from the host.	A VEM VIB is not available on the ESXi 7.0 upgrade image.
The host is currently added to a Cisco Nexus 1000V virtual network switch. The upgrade contains a Cisco Nexus 1000V software package <i>VIB_name</i> that is incompatible with the Cisco Nexus 1000V VSM. Upgrading the host will remove the feature from the host.	The VEM VIB on the ESXi 7.0 upgrade image is not compatible with the version of the VSM.
The host is currently added to a Cisco Nexus 1000V virtual network switch. The upgrade does not contain any Cisco Nexus 1000V software package that is compatible with the Cisco Nexus 1000V VSM. Upgrading the host will remove the feature from the host.	The host and the image do not contain VEM VIBs, but the host is still listed in vCenter Server as managed by Cisco Nexus 1000V.
Cannot determine whether the upgrade breaks Cisco Nexus 1000V virtual network switch feature on the host. If the host does not have the feature, you can ignore this warning.	There was a problem with determining compatibility between the VEM VIB on the ESXi 7.0 upgrade image and the VSM. Check whether the version of the VSM managing the host is certified as being compatible with vCenter Server 7.0 and ESXi 7.0.

Viewing Compliance Information About ESXi Hosts and Updates

vSphere Lifecycle Manager scans objects to determine how they comply with the baselines and baseline groups that you attach to those objects. You can view compliance information about a single ESXi host or a group of hosts in a container object.

Supported groups of ESXi hosts include virtual infrastructure container objects such as folders, clusters, and data centers.

The host or the container object must have an attached baseline or baseline group to be examined for compliance information. Compliance with baselines and baseline groups is assessed at the time of viewing.

The overall compliance status of an ESXi hosts depends on the compliance statuses of all baselines and baseline groups that are attached to the object. For information about the different compliance statuses that an object, a baseline or a baseline group might have, see [Compliance Statuses of ESXi Hosts, Baselines, and Baseline Groups](#) .

The compliance status of a baseline depends on the compliance statuses of all updates in the baseline. For information about the compliance statuses that updates might have, see [Compliance Statuses of Updates](#).

The ability to view the compliance status of vSphere objects depends on the privileges that you have. To view the compliance status of an inventory object, you must have the **View Compliance Status** privilege. Users that have privileges to remediate against patches, extensions, and upgrades and to stage patches and extensions on a particular inventory object, can view the compliance status of the same object even if they do not have the **View Compliance Status** privilege.

- Users with the privilege to view a container, but not all the contents of the container, can view the aggregate compliance status of all objects in the container.
- If a user does not have the permission to view an object, its contents, or a particular virtual machine, the results of those scans are not displayed.

For more information about managing users, groups, roles, and permissions, see the *vSphere Security* documentation.

For a list of all vSphere Lifecycle Manager privileges and their descriptions, see [vSphere Lifecycle Manager Privileges For Using Baselines](#).

For information about checking the compliance of hosts against an image, see [Check Cluster Compliance Against an Image](#).

The vSphere Lifecycle Manager Compliance View

Compliance information about inventory objects is displayed on the **Updates** tab for the object, in the so-called vSphere Lifecycle Manager compliance view.

The vSphere Lifecycle Manager compliance view for objects that you manage with baselines and baseline groups consists of three panes.

Table 10-3. vSphere Lifecycle Manager Compliance View

Pane	Description
Baselines	<p>The Baselines pane has three information panels.</p> <ul style="list-style-type: none"> ■ Host Information panel <p>For individual ESXi hosts, this panel shows information about the ESXi version installed on the host. You can also view all updates that are installed on the host.</p> <p>For container objects, this panel shows information about the ESXi versions of all hosts in the container object.</p> ■ Compliance Information panel <p>For individual ESXi hosts, this panel shows the overall compliance status of the host against all attached baselines and baseline groups. You can also view compliance information about the baselines and baseline groups attached to the host.</p> <p>For container objects, this panel shows the overall number of compliant and non-compliant hosts.</p> <p>This panel also shows the last time a compliance check was completed.</p> ■ Remediation Information panel <p>This panel shows the result of the remediation pre-check and indicates whether the selected object is ready for remediation. The panel also contains information about the issues that require user attention or action.</p> <p>This panel also shows the last time a remediation pre-check was completed.</p> <p>The information in the Baselines pane changes dynamically depending on the inventory object, baselines, and baseline groups that you select.</p>
Attached Baselines and Baseline Groups	Displays the baselines and baseline groups attached to the selected object.
Bottom pane	<p>The bottom pane appears when you select a baseline or a baseline group from the Attached Baselines and Baseline Groups pane. The information in this pane depends on the type of inventory object that you select.</p> <p>For individual hosts, the bottom pane shows information about all updates in the baseline or baseline group that you select from the Attached Baselines and Baseline Groups pane.</p> <ul style="list-style-type: none"> ■ If you select a patch baseline or extension baseline, the bottom pane shows a list of all updates that the selected baseline contains. ■ If you select an upgrade baseline, the bottom pane shows information about the ESXi image that the upgrade baseline contains. ■ If you select a baseline group, the bottom pane shows all baselines included in the group along with their compliance statuses. You can also view all the updates that the baseline group contains. If the baseline group contains an ESXi image, information about it is also displayed in the bottom pane.

Table 10-3. vSphere Lifecycle Manager Compliance View (continued)

Pane	Description
	For container objects, the bottom pane displays compliance information about the ESXi hosts that have the selected baseline or baseline group. When you select a baseline or a baseline group from the Attached Baselines and Baseline Groups pane, the bottom pane appears and displays all the hosts to which the selected baseline or baseline group is attached along with the individual compliance statuses of those hosts.

Compliance Statuses of Updates

When you work with vSphere Lifecycle Manager baselines, an update stands for all patches, extensions, and upgrades that you can apply with vSphere Lifecycle Manager baselines. The compliance status of the updates in the baselines and baseline groups that you attach to objects in your inventory is calculated after you check the compliance of the target object.

The compliance statuses of the updates in a baseline define the overall compliance status of that baseline. For more information about baseline compliance statuses, see [Compliance Statuses of ESXi Hosts, Baselines, and Baseline Groups](#).

Conflict

The update conflicts with either an existing update on the host or another update in the vSphere Lifecycle Manager depot. vSphere Lifecycle Manager reports the type of conflict. A conflict does not indicate any problem on the target object. It just means that the current baseline selection is in conflict. You can perform compliance checks, remediation, and staging operations. In most cases, you must resolve the conflict.

Conflicting New Module

The host update is a new module that provides software for the first time, but it is in conflict with either an existing update on the host or another update in the vSphere Lifecycle Manager depot. vSphere Lifecycle Manager reports the type of conflict. A conflict does not indicate any problem on the target object. It just means that the current baseline selection is in conflict. You can perform scan, remediation, and staging operations. In most cases, you must resolve the conflict.

Incompatible Hardware

The hardware of the selected object is incompatible or has insufficient resources to support the update. For example, when you perform a host upgrade scan against a 32-bit host or if a host has insufficient RAM.

Installed

The update is installed on the target object and no further user action is required.

Missing

The update is applicable to the target object, but it is not yet installed. You must perform a remediation on the target object with this update, so that the update becomes compliant.

Missing Package

The metadata for the update is in the depot, but the corresponding binary payload is missing. The reasons can be that the product might not have an update for a given locale; the vSphere Lifecycle Manager depot is corrupt, and vSphere Lifecycle Manager no longer has Internet access to download updates; or you have manually deleted an upgrade package from the vSphere Lifecycle Manager depot.

New Module

The update is a new module. An update with this compliance status cannot be installed when it is part of a host patch baseline. When it is part of a host extension baseline, the new module status indicates that the module is missing on the host and can be provisioned by remediation. The compliance status of the baseline depends on the type of baseline containing the update with the New Module status. If the baseline is a host patch baseline, the overall status of the baseline is compliant. If the baseline is a host extension baseline, the overall status of the baseline is non-compliant.

Not Applicable

The update is not applicable to the target object. A patch might have the not applicable compliance status for one of the following reasons:

- There are other patches in the vSphere Lifecycle Manager depot that obsolete this patch.
- The update does not apply to the target object.

Not Installable

The update cannot be installed. The compliance check might succeed, but the remediation of the target object cannot be performed.

Obsoleted By Host

This compliance status is mainly applicable to patches. The target object has a newer version of the patch. For example, if a patch has multiple versions, after you apply the latest version to the host, the earlier versions of the patch have the Obsoleted By Host compliance status.

Staged

This compliance status applies to host patches and host extensions. It indicates that the update is copied from the vSphere Lifecycle Manager depot to the host, but it is not yet installed. Staged compliance status might occur only when you check the compliance status of hosts running ESXi 6.5 and later.

Unknown

A patch is in the unknown state for a target object until vSphere Lifecycle Manager successfully scans the object. A scan might not succeed if the target object is of an

unsupported version, if vSphere Lifecycle Manager lacks metadata, or if the patch metadata is corrupt.

Unsupported Upgrade

The upgrade path is not supported. For example, the current hardware version of the virtual machine is later than the latest version supported by the host.

Compliance Statuses of ESXi Hosts, Baselines, and Baseline Groups

Compliance statuses are computed after you initiate a compliance check for an inventory object against the attached baselines or baseline groups. The compliance statuses that baselines and baseline groups might have depend on the applicability of the patches, extensions, and upgrades contained in the baseline or baseline group attached to an object. The compliance status of a single host depends on the compliance statuses of all baselines and baseline groups attached to the host.

Compliant

The compliant status indicates that a vSphere object is compliant with all baselines in an attached baseline group or with all patches, extensions, and upgrades in an attached baseline. The compliant state requires no further action. If a baseline contains patches or upgrades that are not relevant to the target object, the individual updates, and baselines or baseline groups that contain them, are treated as not applicable, and represented as compliant. Compliant are also hosts with attached patch baselines containing extensions or patches with the obsoleted by host status.

The compliant status occurs under the following conditions:

- Target objects are compliant with the baselines and baseline groups when all updates in the baseline or baseline group are either installed on the target object, obsoleted by host, or are not applicable to the target object.
- The updates in a baseline are compliant when they are installed on the target object, or are not applicable to the object.

Non-Compliant

The non-compliant status indicates that one or more baselines in a baseline group, or one or more patches, extensions, or upgrades in a baseline are applicable to the target object, but are not installed (missing) on the target. You must remediate the target object to make it compliant.

When a baseline contains a non-compliant update, the overall status of the baseline is non-compliant. When a baseline group contains a non-compliant baseline, the overall status of the baseline group is non-compliant. The non-compliant status takes precedence over the incompatible, unknown, and compliant states.

Unknown

When you attach a baseline or a baseline group to a vSphere object and you do not initiate a compliance check for the object, the status of the vSphere object against the baseline or baseline group is unknown. This status indicates that a compliance check is required, that the compliance check has failed, or that you initiated a compliance check on an unsupported platform.

When a baseline contains updates in the compliant and unknown states, the overall status of the baseline is unknown. When a baseline group contains unknown baselines and compliant baselines, the overall status of the baseline group is unknown. The unknown compliance status takes precedence over the compliant status.

Incompatible

The incompatible status requires attention and further action. You must determine the reason for incompatibility by probing further. You can remediate the objects that have this status, but the operation might not be successful. In most cases, vSphere Lifecycle Manager provides sufficient details for the incompatibility.

When a baseline contains updates in the incompatible, compliant, and unknown states, the overall status of the baseline is incompatible. When a baseline group contains incompatible, unknown, and compliant baselines, the overall status of the baseline group is incompatible. The incompatible compliance status takes precedence over the compliant and unknown compliance statuses.

View Compliance Information About ESXi Hosts

You can check how the ESXi hosts in your environment comply with the baselines and baseline groups that you attach to those hosts. You can check and view the compliance status of an individual host or a container object.

Compliance checks provide information about the degree of compliance of an object with the attached baselines and baseline groups.

In the compliance view for an object, you can view information about the compliance of the object with the attached baselines and baseline groups. You can also view the individual compliance statuses of the attached baselines and baseline groups. The compliance view changes dynamically and depends on the object that you want to view compliance information about. For a full description of the compliance information that you can obtain about an object, see [The vSphere Lifecycle Manager Compliance View](#).

For information about the different compliance statuses that an object might have, see [Compliance Statuses of ESXi Hosts, Baselines, and Baseline Groups](#).

Prerequisites

- Verify that the host for which you want to view compliance information uses baselines and is not managed with a single vSphere Lifecycle Manager image.
- Review the [The vSphere Lifecycle Manager Compliance View](#) topic.

Procedure

- 1 In the vSphere Client, navigate to the vSphere Lifecycle Manager compliance view for an individual host or a container object.
 - a Navigate to a host, cluster, or a container object.
 - b Click the **Updates** tab.
- 2 Select **Hosts > Baselines** and review the compliance information in the compliance view.

Results

You see complete compliance information about the selected object.

View Information About the Patches, Extensions, and ISO Images in a Baseline

You can view information about the patches, extensions, and upgrades included in a baseline or a baseline group.

For information about the different compliance statuses that an update might have, see [Compliance Statuses of Updates](#).

Prerequisites

- Verify that the host for which you want to view compliance information uses baselines and is not managed with a single vSphere Lifecycle Manager image.
- Review the [The vSphere Lifecycle Manager Compliance View](#) topic.

Procedure

- 1 In the vSphere Client, navigate to a single ESXi host, cluster, or a valid container object.
- 2 On the **Updates** tab, select **Hosts > Baselines**.
- 3 In the **Attached Baselines and Baseline Groups** pane, select a baseline.

A new pane appears below the **Attached Baselines and Baseline Groups** pane. Depending on the selected object, the bottom pane might contain information about the updates and ESXi images in the baseline that you select. If the selected object is a container for ESXi hosts, the bottom pane shows the compliance of each ESXi in the container object against the selected baseline.

Baseline Type	Available Information
Patch	<p>The bottom pane contains a table that lists all patches in the baseline. For each update, you can see the following information.</p> <ul style="list-style-type: none"> ■ Update Name ■ Update ID <p>The update ID is a vendor-assigned identification code of the patch.</p> <ul style="list-style-type: none"> ■ Status <p>The Status column shows the compliance status of the update.</p> <ul style="list-style-type: none"> ■ Severity ■ Category ■ Impact <p>The Impact column displays the actions that you must take to install the update. For example, rebooting the system or putting the host in maintenance mode.</p> <ul style="list-style-type: none"> ■ ESXi Version
Upgrade	<p>The bottom pane displays the following information.</p> <ul style="list-style-type: none"> ■ ESXi Version ■ Build ■ Status <p>The Status column shows the compliance status of the update.</p> <ul style="list-style-type: none"> ■ Release Date ■ Vendor ■ Details ■ Release Notes ■ Acceptance Level <p>ESXi images can be either Signed or Unsigned, which indicates their level of acceptance by VMware.</p> <p>The software packages included in ESXi images might have any of the following acceptance levels.</p> <p>VMware Certified</p> <p>The package has gone through a rigorous certification program that verifies the functionality of the feature, and is signed by VMware with a private key. VMware provides customer support for these packages.</p> <p>VMware Accepted</p>

Baseline Type	Available Information
	<p>The package has gone through a less rigorous acceptance test program that only verifies that the package does not destabilize the system, and is signed by VMware with a private key. The test regimen does not validate the proper functioning of the feature. VMware support hands off support calls directly to the partner.</p> <p>Partner Supported</p> <p>The partner has signed an agreement with VMware and has demonstrated a sound test methodology. VMware provides a signed private/public key pair to the partner to use for self-signing their packages. The VMware support team redirects support calls directly to the partner.</p> <p>Community Supported</p> <p>The package is either unsigned or signed by a key that is not cross-signed by VMware. VMware does not provide support for the package. For support, customers must either use the community or contact the author of the package.</p>
Extension	<ul style="list-style-type: none"> ■ Update Name ■ Update ID <p>The update ID is a vendor-assigned identification code of the extension.</p> <ul style="list-style-type: none"> ■ Status <p>The Status column shows the compliance status of the update.</p> <ul style="list-style-type: none"> ■ Severity ■ Category ■ Impact <p>The Impact column displays the actions that you must take to install the update. For example, rebooting the system or putting the host in maintenance mode.</p> <ul style="list-style-type: none"> ■ ESXi Version
Baseline Group	<p>To view information about the patches, extension, and ISO images in a baseline group, select the respective tab in the bottom pane.</p> <ul style="list-style-type: none"> ■ Click Baselines for information about the baselines that a baseline group contains. ■ Click ISO for information about the ESXi image that a baseline group contains. ■ Click Updates for information about the patches and extensions that the baseline group contains.

Staging Patches and Extensions to ESXi Hosts

Staging lets you download the patches and extensions from the vSphere Lifecycle Manager repository to ESXi hosts, without applying the patches and extensions immediately. Staging patches and extensions speeds up the remediation process, because the patches and extensions are already available locally on the hosts.

To stage patches or extensions to hosts, first attach a patch or extension baseline or a baseline group containing patches and extensions to the host. Staging patches and extensions does not require that hosts enter maintenance mode.

With the vSphere Client, you can stage a single baseline, multiple baselines, or baseline groups to a single host or a group of hosts in a container object.

Some limitations exist depending on the compliance status of the patches or extensions that you want to stage.

Patches cannot be staged if they are obsoleted by other patches in the baselines or baseline groups for the same stage operation. vSphere Lifecycle Manager stages only the patches that it can install in a subsequent remediation process, based on the current compliance status of the host. If a patch is obsoleted by patches in the same selected patch set, the obsoleted patch is not staged.

If a patch is in conflict with the patches in the vSphere Lifecycle Manager depot and is not in conflict with a host, after a compliance check, vSphere Lifecycle Manager reports this patch as a conflicting one. You can still stage the patch to the host and after the stage operation, vSphere Lifecycle Manager reports this patch as staged.

During the stage operation, vSphere Lifecycle Manager performs prescan and postscan operations and updates the compliance status of the baseline.

For more information about the different compliance statuses that an update might have, see [Compliance Statuses of Updates](#).

After you stage patches or extensions to hosts, you must remediate the hosts against all staged patches or extensions.

After remediation finishes, the host deletes all staged patches or extensions from its cache regardless of whether they were applied during the remediation. The compliance status of the patches or extensions that were staged but not applied to the hosts reverts from Staged to its previous value.

Important Staging patches and extensions is supported for hosts that are running ESXi 6.5 and later. You can stage patches to PXE booted ESXi hosts, but if the host is restarted before remediation, the staged patches are lost and you must stage them again.

Stage Patches and Extensions to ESXi Hosts

Staging is the process during which vSphere Lifecycle Manager downloads patches and extensions on the ESXi hosts. During staging, the patches and extensions are not installed on the host. Staging reduces the time that the host spends in maintenance mode during remediation.

Prerequisites

- Attach a patch or extension baseline or a baseline group containing patches and extensions to the host.
- Required privileges: **VMware vSphere Lifecycle Manager.Manage Patches and Upgrades.Stage Patches and Extensions**.

Procedure

- 1 In the vSphere Client, navigate to the vSphere Lifecycle Manager compliance view for an individual host or a container object.
 - a Navigate to a host, cluster, or a container object.
 - b Click the **Updates** tab.
- 2 Select **Hosts > Baselines**.
- 3 In the **Attached Baselines** pane, select one or more baselines.
- 4 Click **Stage**.

The **Stage Patches** dialog box opens.
- 5 Select hosts on which to stage patches and extensions.

The number of selected hosts is on the top of the list.
- 6 To view the patches or extensions that will download to the selected hosts, expand the **Stage** list.
- 7 Click **Stage**.

Results

The staging operation starts. You can monitor the progress of the task in the **Recent Tasks** pane.

What to do next

Remediate the host or hosts.

After remediation, all staged patches and extensions, whether installed or not during the remediation, are deleted from the host.

Remediating ESXi Hosts Against vSphere Lifecycle Manager Baselines and Baseline Groups

Remediation is the process during which vSphere Lifecycle Manager applies patches, extensions, and upgrades to ESXi hosts. Remediation makes the selected vSphere objects compliant with the attached baselines and baseline groups.

vSphere Lifecycle Manager supports the remediation of ESXi hosts against patch, extension, and upgrade baselines.

You can initiate remediation manually or schedule a regular remediation task to run at a time that is convenient for you.

You can remediate a single ESXi host or a container object. You can initiate remediation at a folder, a cluster, or a data center level.

Note If you initiate remediation for an object that contains clusters that use a single vSphere Lifecycle Manager image, remediation is not performed on those clusters.

If a vCenter Server instance is connected to other vCenter Server systems by a common vCenter Single Sign-On domain, you can remediate only the inventory objects managed by the vCenter Server system where the vSphere Lifecycle Manager instance that you use runs.

Orchestrated Upgrades of ESXi Hosts

You can use baseline groups to perform an orchestrated upgrade of the ESXi hosts in your environment. The baseline group might contain a single host upgrade baseline and multiple patch or extension baselines, or multiple patch and extension baselines. vSphere Lifecycle Manager first upgrades the hosts and then applies the patch or extension baselines. Because the upgrade runs first and patches are applicable to a specific host version, the orchestrated workflow ensures that no patches are lost during the upgrade.

Orchestrated upgrades can be performed at a host, cluster, folder, or a data center level.

Starting with vCenter Server 6.7 Update 2, you can select and work with multiple baselines instead of grouping them into a baseline group first.

Maintenance Mode

If the update requires it, hosts are put into maintenance mode before remediation. Virtual machines cannot run when a host is in maintenance mode. To ensure a consistent user experience, vCenter Server migrates the virtual machines to other hosts within the cluster before the host is put in maintenance mode. vCenter Server can migrate the virtual machines if the cluster is configured for vMotion and if VMware Distributed Resource Scheduler (DRS) and VMware Enhanced vMotion Compatibility (EVC) are enabled. However, EVC is not a prerequisite for vMotion. EVC guarantees that the CPUs of the hosts are compatible. For container objects or individual hosts that are not in a cluster, migration with vMotion cannot be performed.

To remediate vSphere objects, you must have the **Remediate to Apply Patches, Extensions, and Upgrades** privilege. For more information about managing users, groups, roles, and permissions, see the *vSphere Security* documentation.

For a list of all vSphere Lifecycle Manager privileges and their descriptions, see [vSphere Lifecycle Manager Privileges For Using Baselines](#).

Remediation Pre-Check

Before you remediate an object, you can perform a remediation pre-check on the object. During that check, vSphere Lifecycle Manager identifies possible issues that might prevent successful remediation and suggests actions to fix the issues.

For more information about the possible issues that might prevent successful remediation, see [Remediation Pre-Check Report](#).

Remediation of PXE Booted ESXi Hosts

vSphere Lifecycle Manager lets you remediate PXE booted ESXi hosts. vSphere Lifecycle Manager does not apply the patches that require a reboot to PXE booted ESXi hosts.

If there is any additional software installed on the PXE booted ESXi host, the software might be lost if the host restarts. Update your image profile with the additional software so that it will be present after the reboot.

To patch PXE booted ESXi hosts, you must enable the respective setting in the **Edit Settings for Host Remediation** dialog box, which you open from the **Settings** tab in the vSphere Lifecycle Manager home view.

Understanding the Remediation Operation

For ESXi hosts, updates are all-inclusive. The most recent update contains the patches from all previous releases.

The ESXi image on the host maintains two copies. The first copy is in the active boot and the second one is in the standby boot. When you patch an ESXi host, vSphere Lifecycle Manager creates an image based on the content of the active boot and the content of the patch. The new ESXi image is then located in the standby boot and vSphere Lifecycle Manager designates the active boot as the standby boot and reboots the host. When the ESXi host reboots, the active boot contains the patched image and the standby boot contains the previous version of the ESXi host image.

When you upgrade an ESXi host, vSphere Lifecycle Manager replaces the backup image of the host with the new image and replaces the active boot and the standby boot. During the upgrade, the layout of the disk that hosts the boots changes. The total disk space for an ESXi host remains 1GB, but the disk partition layout within that 1GB disk space changes to accommodate the new size of the boots where the ESXi 7.0 image is stored.

For rollback purposes, the term update refers to all ESXi patches, updates, and upgrades. Each time you update an ESXi host, a copy of the previous ESXi build is saved on your host.

If an update fails and the ESXi 7.0 host cannot boot from the new build, the host reverts to booting from the original boot build. ESXi permits only one level of rollback. Only one previous build can be saved at a time. In effect, each ESXi 7.0 host stores up to two builds, one boot build and one standby build.

The remediation of ESXi 6.5 and 6.7 hosts to their respective ESXi update releases is a patching process, while the remediation of ESXi hosts from version 6.5 or 6.7 to 7.0 is an upgrade process.

From the vSphere Lifecycle Manager settings, you can configure the host remediation process to skip a host reboot during host patch and host upgrade operations. This configuration setting is called Quick Boot. For more information about configuring the vSphere Lifecycle Manager remediation settings, see [Chapter 8 Configuring the vSphere Lifecycle Manager Remediation Settings](#).

Types of Host Remediation

Host remediation runs in different ways depending on the types of baselines that you attach to an object and whether the remediated host is in a cluster or not.

Host Upgrade Remediation

When you upgrade an ESXi 6.5 or ESXi 6.7 host to ESXi 7.0, all supported custom VIBs remain intact on the host after the upgrade, regardless of whether the VIBs are included in the installer ISO.

You can upgrade hosts by using custom ESXi images that contain third-party modules for ESXi 7.0. In such a case, third-party modules that are compatible with ESXi 7.0 stay available on the upgraded host.

Host upgrade in a high-latency network in which vSphere Lifecycle Manager and the hosts are at different locations might take a few hours because the upgrade file is copied from the vSphere Lifecycle Manager depot to the host before the upgrade. During this time, the host stays in maintenance mode.

vSphere Lifecycle Manager 7.0 supports upgrade from ESXi 6.5 and ESXi 6.7 to ESXi 7.0.

Upgrading to ESXi 7.0 requires a boot device that is a minimum of 4 GB. When booting from a local disk, SAN or iSCSI LUN, up to 128 GB of disk space is used to create ESXi system partitions. You can create a VMFS datastore on a boot disk larger than 128 GB.

Note After you upgrade your host to ESXi 7.0, you cannot roll back to the previous ESXi versions, ESXi 6.5, ESXi 6.7. So, back up your host configuration before performing an upgrade. If the upgrade fails, you can reinstall the ESXi 6.5 or ESXi 6.7 software that you upgraded from and restore your host configuration. For more information about backing up and restoring your ESXi configuration, see the *VMware ESXi Upgrade* documentation. To upgrade ESXi hosts, you must first import ESXi ISO images to the vSphere Lifecycle Manager depot. You then create baselines and baseline groups to manage the upgrades for the ESXi hosts.

Host Patch Remediation

Patching is the process of remediating ESXi hosts against patch baselines.

The remediation of ESXi 6.5 and 6.7 hosts to their respective ESXi update releases is a patching process, while the remediation of ESXi hosts from version 6.5 or 6.7 to 7.0 is an upgrade process.

vSphere Lifecycle Manager handles host patches in the following ways:

- If a patch in a patch baseline requires the installation of another patch, vSphere Lifecycle Manager detects the prerequisite in the depot and installs it together with the selected patch.
- If a patch is in a conflict with other patches that are installed on the host, the conflicting patch might not be staged or installed. However, if another patch in the baseline resolves the conflicts, the conflicting patch is installed. For example, consider a baseline that contains patch A and patch C, and patch A conflicts with patch B, which is already installed on the host. If patch C obsoletes patch B, and patch C is not in a conflict with patch A, the remediation process installs patches A and C.
- If a patch is in a conflict with the patches in the vSphere Lifecycle Manager depot and is not in a conflict with the host, after a compliance check, vSphere Lifecycle Manager reports this patch as a conflicting one. You can stage and apply the patch to the host.
- When multiple versions of the same patch are selected, vSphere Lifecycle Manager installs the latest version and skips installing the earlier versions.

During patch remediation, vSphere Lifecycle Manager automatically installs the prerequisites of the patches.

With vSphere Lifecycle Manager 7.0, you can remediate hosts of version ESXi 6.5 and ESXi 6.7 against patches from offline bundles, which you import to the vSphere Lifecycle Manager depot manually.

You can stage patches before remediation to reduce host downtime.

Host Extension Remediation

During extension remediation, vSphere Lifecycle Manager does not automatically install the prerequisites of the extension. Missing extension prerequisites cause some remediation operations to fail. If the missing prerequisite is a patch, you can add it to a patch baseline. If the missing prerequisite is an extension, you can add it to the same or another extension baseline. You can then remediate the host against the baseline or baselines that contain the prerequisite and the original extension baseline.

Remediating Hosts in a Cluster

For ESXi hosts in a cluster, the remediation process is sequential by default.

When you remediate a cluster of hosts sequentially and one of the hosts fails to enter maintenance mode, vSphere Lifecycle Manager reports an error and the remediation process stops and fails. The hosts in the cluster that are remediated stay at the updated level. The ones that are not remediated after one host fails remain unupdated.

The host upgrade remediation of ESXi hosts in a cluster proceeds only if all hosts in the cluster can be upgraded.

If you initiate remediation at a data center level, the remediation processes for the clusters run in parallel. Clusters that you manage with a single vSphere Lifecycle Manager image are not remediated against the attached baselines or baseline groups. If the remediation process fails for one of the clusters within a data center, the remaining clusters are still remediated.

Before you start remediation, you can generate a report that shows which cluster, host, or virtual machine has the cluster features enabled. For more information, see [Remediation Pre-Check Report](#).

Remediation and Cluster Settings

If a host in a DRS-enabled cluster runs a virtual machine on which vCenter Server is installed, DRS first attempts to migrate the virtual machine running vCenter Server to another host, so that the remediation succeeds. If the virtual machine cannot be migrated to another host, the remediation fails for the host, but the remediation process for the cluster does not stop. vSphere Lifecycle Manager proceeds to remediate the next host in the cluster.

Remediation of hosts in a cluster requires that you temporarily disable cluster features such as VMware DPM and HA admission control. Also, you must turn off Fault Tolerance if it is enabled on any of the virtual machines on a host, and disconnect the removable devices connected to the virtual machines on a host, so that they can be migrated with vMotion. For more information about configuring the vSphere Lifecycle Manager remediation settings, see [Chapter 8 Configuring the vSphere Lifecycle Manager Remediation Settings](#).

If a vCenter HA failover is initiated during the remediation of a cluster, the remediation task is canceled. After the failover finishes, you must restart the remediation task on the new node.

When you perform remediation on a cluster that consists of not more than two hosts, disabling HA admission control might not be enough to ensure successful remediation. You might need to disable vSphere High Availability (HA) for the cluster. If you keep HA enabled, the remediation attempts on hosts in the cluster fail, because HA cannot provide recommendation to vSphere Lifecycle Manager to place any of the hosts into maintenance mode. The reason is that if one of the two hosts is placed into maintenance mode there is no failover host left available in the cluster. To ensure successful remediation on a two-node cluster, you must disable HA for the cluster or place the hosts in maintenance mode manually and then remediate the two hosts in the cluster.

vSAN Clusters

vSphere Lifecycle Manager remediates hosts that are part of a vSAN cluster sequentially. The reason is that by design only one host from a vSAN cluster can be in a maintenance mode at any time. For more information about using vSphere Lifecycle Manager with vSAN clusters, see [Chapter 16 vSAN Clusters and vSphere Lifecycle Manager](#).

Remediating Hosts That Contain Third-Party Software

Hosts might contain third-party software, such as Cisco Nexus 1000V VEMs or EMC PowerPath modules. When you upgrade an ESXi 6.5 or ESXi 6.7 host to ESXi 7.0, all supported custom VIBs are migrated and remain intact, regardless of whether the VIBs are included in the installer ISO.

If the host or the installer ISO image contains a VIB that creates a conflict and prevents the upgrade, an error message identifies the VIB that creates the conflict.

To discover potential problems with third-party software before an upgrade operation, scan the hosts against an upgrade baseline and review the scan messages in the vSphere Lifecycle Manager compliance view. See [Host Upgrade Compliance Messages](#) and [Host Upgrade Compliance Messages When Cisco Nexus 1000V Is Present](#).

For information about upgrading with third-party customization, see the *VMware ESXi Upgrade* documentation.

For information about using vSphere ESXi Image Builder to make a custom ISO, see the *VMware ESXi Installation and Setup* documentation.

Remediating ESXi 6.5 or ESXi 6.7 Hosts Against an ESXi 7.0 Image

When you upgrade an ESXi 6.5 or ESXi 6.7 host to ESXi 7.0, all supported custom VIBs remain intact on the host after the upgrade, regardless of whether the VIBs are included in the installer ISO.

When you perform a compliance check, the target host is scanned against a set of VIBs from the upgrade image. If you check the compliance of a host against an upgrade baseline that contains an ISO image of the same version as the target host, vSphere Lifecycle Manager displays Compliant or Non-compliant compliance status. If the upgrade image is the basic one distributed by VMware, or is a custom ISO image that contains the same set of VIBs as the ones already installed on the target host, the scan result is Compliant. If the upgrade ISO contains VIBs that are of different kind or version than the VIBs that are already on the target host, the scan result is Non-compliant.

The remediation process of an ESXi 6.5 or ESXi 6.7 host against an ESXi 7.0 image is an upgrade process.

Note Upgrading to ESXi 7.0 requires a boot device that is a minimum of 4 GB. When booting from a local disk, SAN or iSCSI LUN, up to 128 GB of disk space is used to create ESXi system partitions. You can create a VMFS datastore on a boot disk larger than 128 GB.

You can use an ISO 7.0 image in an upgrade operation of an ESXi 7.0 host. The remediation process of ESXi 7.0 host by using ESXi 7.0 image with additional VIBs is equivalent to a patching process. Because the upgrade image is of the same version as the target host, upon completing the upgrade operation, the additional VIBs are added to the target host.

Table 10-4. Scan and Remediation Situations for ESXi 6.5 and ESXi 6.7 Hosts Against ESXi 7.0 Images

Action	Description
Compliance check and remediation of ESXi 6.5 or ESXi 6.7 hosts against an ESXi 7.0 image that contains additional non-conflicting and non-obsoleting VIBs with the target host.	vSphere Lifecycle Manager displays a Non-Compliant compliance status for the host. Remediation succeeds. All VIBs on the target host before remediation remain on the host. All VIBs from the upgrade image that are not present on the target host before remediation are added to the host.
Compliance check and remediation of ESXi 6.5 or ESXi 6.7 hosts against an ESXi 7.0 image that contains VIBs of a version later than the version of the same VIBs on the target host.	vSphere Lifecycle Manager displays a Non-Compliant compliance status for the host. Remediation succeeds. VIBs on the target host are updated to the later version.
Compliance check and remediation of ESXi 6.5 or ESXi 6.7 hosts against an ESXi 7.0 image that contains conflicting VIBs with the target host.	vSphere Lifecycle Manager displays an Incompatible compliance status for the host. Remediation fails. The host remains intact.
Scan and remediation of ESXi 6.5 or ESXi 6.7 hosts against an ESXi 7.0 image that contains vendor-tagged VIBs.	<ul style="list-style-type: none"> ■ If the vendor-tagged VIBs do not match the host hardware, vSphere Lifecycle Manager displays an Incompatible compliance status for the host. Remediation fails. ■ If the vendor-tagged VIBs match the host hardware, vSphere Lifecycle Manager displays a Non-Compliant compliance status for the host and remediation succeeds.
Scan and remediation of ESXi 6.5 or ESXi 6.7 hosts against an ESXi 7.0 image that contains VIBs that obsolete the VIBs installed on the host.	Remediation succeeds. All VIBs that have been installed on the target host before remediation are replaced by the newer VIBs from the ESXi image.

Remediation Pre-Check Report

The remediation pre-check report shows the results of a check that is performed on a cluster or a host before remediation. During that check, vSphere Lifecycle Manager identifies possible issues that might prevent successful remediation. Depending on the type of issue, vSphere Lifecycle Manager suggests actions that you must take to fix the issue or resolves the issue automatically.

You can generate a pre-check remediation report in the vSphere Lifecycle Manager compliance view for an object.

Table 10-5. Cluster Issues

Current Configuration/ Issue	Recommended Action	Details
DRS is disabled on the cluster.	Enable DRS on the cluster.	DRS enables vCenter Server to place and migrate virtual machines automatically on hosts to attain the best use of cluster resources.
vSAN health check fails during the pre-check.	Navigate to the vSAN Health page and address any health issues before proceeding with remediation.	The vSAN health check performs a series of tests on the hosts in the vSAN cluster. The vSAN health check must succeed to ensure the hosts are successfully remediated. If you start a remediation task in a vSAN cluster that failed the vSAN health check during the remediation pre-check, the hosts enter maintenance mode, get upgraded, but might fail to exit maintenance mode. The remediation eventually fails.
Insufficient licenses for one or multiple ESXi hosts in the cluster.	Ensure that you have multiple licenses for the ESXi hosts that have more than 32 cores per CPU.	Starting with vSphere 7.0, one CPU license covers up to 32 physical cores. If a CPU has more than 32 cores, you must assign additional CPU licenses to the respective ESXi host. For more information, see https://www.vmware.com/company/news/updates/cpu-pricing-model-update-feb-2020.html .
DPM is enabled on the cluster.	None. vSphere Lifecycle Manager disables DPM automatically.	If a host has no running virtual machines, DPM might put the host in standby mode before or during remediation and vSphere Lifecycle Manager cannot remediate them.
HA admission control is enabled on the cluster.	None. vSphere Lifecycle Manager disables HA admission control automatically.	HA admission control prevents the migration of virtual machines with vSphere vMotion and the hosts cannot enter maintenance mode.

Table 10-6. Host Issues

Current Configuration/Issue	Recommended Action	Details
A CD/DVD drive is attached to a virtual machine on the ESXi host.	Disconnect the CD/DVD drive.	Any CD/DVD drives or removable devices connected to the virtual machines on a host might prevent the host from entering maintenance mode. When you start a remediation operation, the hosts with virtual machines to which removable devices are connected are not remediated.
A floppy drive is attached to a virtual machine on the ESXi host.	Disconnect the floppy drive.	Any floppy drives or removable devices connected to the virtual machines on a host might prevent the host from entering maintenance mode. When you start a remediation operation, the hosts with virtual machines to which removable devices are connected are not remediated.
Fault Tolerance (FT) is enabled for a virtual machine on the ESXi host.	Disable FT for the virtual machine.	If FT is enabled for any of the virtual machines on a host, vSphere Lifecycle Manager cannot remediate that host.

Table 10-6. Host Issues (continued)

Current Configuration/Issue	Recommended Action	Details
A powered on virtual machine is configured to use Virtual Flash Read Cache.	"Disable Virtual Flash Read Cache before proceeding with the upgrade.	Starting with vSphere 7.0, Virtual Flash Read Cache is not supported. During an upgrade operation, vSphere Lifecycle Manager removes Virtual Flash Read Cache for all virtual machines on the host. Before remediation, consult https://kb.vmware.com/s/article/2057840 .
VMware vCenter Server is installed on a virtual machine on the ESXi host and DRS is disabled on the cluster.	Enable DRS on the cluster and ensure that virtual machines can be migrated with vSphere vMotion.	One of the virtual machines in the cluster runs the vCenter Server instance that you currently use. If you enable DRS on the cluster, vSphere vMotion can migrate the virtual machine where vCenter Server runs to ensure that the remediation of the hosts is successful.
An ESXi host in the cluster has a CPU with more than 32 cores and requires multiple licenses.	Assign as many licenses as the host needs.	Starting with vSphere 7.0, one CPU license covers up to 32 physical cores. If a CPU has more than 32 cores, you must obtain additional CPU licenses. For more information, see https://www.vmware.com/company/news/updates/cpu-pricing-model-update-feb-2020.html .

Generate a Pre-Remediation Check Report

When you generate a pre-remediation check report, vSphere Lifecycle Manager generates a list with actions that you must perform to ensure successful remediation of the hosts in your cluster.

The remediation pre-check report contains information about issues at the cluster, host, and VM level that might prevent the completion of remediation.

For information about the possible issues that might prevent successful remediation, see [Remediation Pre-Check Report](#).

Procedure

- 1 In the vSphere Client, navigate to the vSphere Lifecycle Manager compliance view for an individual host or a container object.
 - a Navigate to a host, cluster, or a container object.
 - b Click the **Updates** tab.

- 2 Select **Host > Baselines**.

- 3 In the **Baselines** pane, click **Pre-Check Remediation**.

The **Remediation Pre-check** dialog box opens.

- 4 Review the results from the pre-check and click **Done**.

In the bottom pane of the **Remediation Pre-check** dialog box, you see a list of issues at the host and virtual machine level.

Results

The **Remediation Pre-check** dialog box lists the issues with cluster, hosts, and virtual machines that might prevent successful remediation of the selected object.

In the upper pane of the **Remediation Pre-check** dialog box, you see a list of issues at a cluster level.

In the bottom pane of the **Remediation Pre-check** dialog box, you see a list of issues at the host and virtual machine level.

What to do next

Fix all issues that vSphere Lifecycle Manager identifies during the pre-remediation check and remediate the selected object.

Remediate ESXi Hosts Against a Single Baseline or Multiple Baselines

You can remediate hosts against attached patch, upgrade, and extension baselines or baseline groups.

You can remediate a host against a single baseline, multiple baselines of the same type, or against a baseline group. To remediate against baselines of different types, you must create a baseline group. Baseline groups might contain multiple patch and extension baselines, or an upgrade baseline combined with multiple patch and extension baselines.

Note Because in vSphere 7.0 the official VMware online depot hosts certified partner content in addition to VMware content, a broader set of OEM bulletins are available in the vSphere Lifecycle Manager depot. As a result, a broader set of OEM bulletins are included in the vSphere Lifecycle Manager predefined bulletins. During remediation, always inspect the contents of those baselines to exclude the bulletins that you do not need in the baseline. For the bulletins that you do need, consult the corresponding KB articles for information about deployment specifics and dependencies. Verify that dependent bulletins are also included in the baselines that you use for remediation.

You can remediate ESXi hosts against a single attached upgrade baseline at a time. You can upgrade all hosts in your vSphere inventory by using a single upgrade baseline that contains an ESXi 7.0 image.

You can remediate a single ESXi host or a group of ESXi hosts in a container object, such as a folder, a cluster, or a data center. You can also initiate remediation at a vCenter Server level.

Note If a vCenter HA failover is initiated during the remediation of a cluster, the remediation task is canceled. After the failover finishes, you must restart the remediation task on the new node.

Prerequisites

- Required privileges: **VMware vSphere Lifecycle Manager.Manage Patches and Upgrades.Remediate to Apply Patches, Extensions, and Upgrades.**
- Attach a patch, upgrade, or extension baseline or a baseline group containing patches, upgrades, and extensions to the host.
- Resolve any issues that occur during Remediation Pre-check.

- In upgrade scenarios, verify that the ESXi hosts to upgrade have a boot disk of at least 4 GB. When booting from a local disk, SAN or iSCSI LUN, up to 128 GB of disk space is used to create ESXi system partitions. You can create a VMFS datastore on a boot disk larger than 128 GB.

Procedure

- 1 In the vSphere Client, navigate to the vSphere Lifecycle Manager compliance view for an individual host or a container object.
 - a Navigate to a host, cluster, or a container object.
 - b Click the **Updates** tab.

- 2 Select **Hosts > Baselines**.

- 3 In the **Attached Baselines and Baseline Groups** pane, select the baselines and baseline groups to use for remediation.

You can select a single baseline or baseline group. You can also select multiple baselines and baseline groups. Your selection of baselines and baseline groups must contain only one upgrade baseline.

- 4 Click **Remediate**.

If the selected baselines and baseline groups do not contain an upgrade image, the **Remediate** dialog box opens.

If the selected baselines and baseline groups contain an upgrade image, the **End User License Agreement** dialog box opens.

- 5 If the selection of baselines and baseline groups contains an upgrade baseline, accept the terms and the license agreement in the **End User License Agreement** dialog box.

After you accept the agreement and click **OK** to close the dialog box, the **Remediate** dialog box opens.

- 6 In the **Remediate** dialog box, review the remediation settings and make any necessary changes.

- a Review the list of actions that vSphere Lifecycle Manager must perform to ensure successful remediation.
- b (Optional) To generate a full pre-remediation check report, click **Show Full Remediation Pre-Check Report**.

If you select this option, the **Remediate** dialog box closes and vSphere Lifecycle Manager does not proceed with the remediation process. Instead, the **Remediation Pre-Check** dialog box opens. After you review the results from the pre-remediation check, you must initiate remediation again.

- c Review the list of hosts to be remediated and deselect any host that you do not want to remediate.

The list contains all the hosts to which the selected baselines and baseline groups are attached. Even if you navigated to a single host before initiating remediation, the list might display multiple hosts to be remediated. All hosts in the list are selected by default. Deselecting hosts from the list changes the overall number of hosts to be remediated.

- 7 (Optional) To view information about the updates that will be installed during the remediation, expand the **Install** list.

If the selection of baselines and baseline groups contains an upgrade baseline, information about the ESXi image is also displayed.

- 8 (Optional) To schedule the remediation task for a later time, expand **Scheduling Options** and configure the scheduled task.

By default, the remediation task starts immediately after closing the **Remediate** dialog box.

- 9 Expand **Remediation settings** and review the remediation settings.

- To disable Quick Boot, deselect the respective check box in the table.
- To disable health checks after remediation, disable the respective check box in the table.
- To ignore warnings about unsupported hardware devices, select the respective check box in the table.
- To change any other of the remediation settings, click the **Close Dialog And Go To Settings** link above the table.

If you select this option, the **Remediate** dialog box closes and vSphere Lifecycle Manager does not proceed with the remediation process. Instead, you are redirected to the **Baselines Remediation Settings** pane on the **Settings** tab of the vSphere Lifecycle Manager home view. To change any of the remediation settings, click the **Edit** button. Remediation does not resume automatically. After you make the desired changes, you must initiate remediation again.

- 10 Click **Remediate**.

Results

Depending on the remediation schedule, the remediation task starts immediately or runs later.

Starting with vSphere 7.0, you can manage the software and firmware lifecycle of the ESXi hosts in a cluster with a single image. vSphere Lifecycle Manager images are a new functionality that provides a simplified and unified workflow for patching and upgrade of ESXi hosts. You can also use vSphere Lifecycle Manager images for bootstrapping purposes and firmware updates.

An image defines the exact software stack to run on all ESXi hosts in a cluster.

Using images to apply software and firmware updates to ESXi hosts is a multi-stage process.

- 1 Software updates must become available in the vSphere Lifecycle Manager depot.

To set up and use an image, you use the software updates that are available in the vSphere Lifecycle Manager depot. The depot contains base images, vendor add-ons, and additional components.

Updates get into the vSphere Lifecycle Manager local depot through synchronization with configurable download sources. By default, vSphere Lifecycle Manager is configured to synchronize with the official VMware depot. You can also import updates into the depot manually.

You can see the contents of the vSphere Lifecycle Manager depot in the vSphere Lifecycle Manager home view.

For more information, see [Chapter 7 Working with the vSphere Lifecycle Manager Depot](#).

- 2 You start using vSphere Lifecycle Manager images.

vSphere Lifecycle Manager provides you with the option to start using images with the very creation of a cluster. If you do not set up an image during the creation of a cluster, you can switch from using vSphere Lifecycle Manager baselines to using vSphere Lifecycle Manager images at a later time.

Even when you save the image, no software is installed on the ESXi hosts during image setup.

For more information, see [Chapter 9 Cluster Operations and vSphere Lifecycle Manager](#) and [Chapter 12 Switching from Baselines to Images](#).

- 3 You check the compliance of the ESXi hosts in the cluster against the image specification.

The compliance check compares the current image on the ESXi hosts in the cluster against the desired image that you specified during the setup process, and defines compatibility status of the hosts.

For more information, see [Check Cluster Compliance Against an Image](#).

- 4 You review the compliance statuses of the hosts in the cluster.
- 5 You can run a remediation pre-check on an ESXi host to ensure software and hardware compatibility with the image.

Running a remediation pre-check is optional. The remediation pre-check ensures that all requirements for successful remediation are met. For more information, see [Run a Remediation Pre-Check for a Cluster](#).

- 6 You remediate the non-compliant ESXi hosts in the cluster.

Remediation is the process through which the software specification defined by the vSphere Lifecycle Manager image that you use for a cluster is actually applied to the hosts in the cluster.

For more information about remediating hosts against an image, see [Remediate a Cluster Against a Single Image](#).

This chapter includes the following topics:

- [Working with Images](#)
- [Checking Compliance Against a Single Image](#)
- [Run a Remediation Pre-Check for a Cluster](#)
- [Run a Remediation Pre-Check for a Single Host](#)
- [Remediating a Cluster Against a Single Image](#)
- [Manage Depot Overrides for a Cluster](#)

Working with Images

When you manage a cluster with a single image, you can change the image at any time. You can edit the image by changing the software that it includes, for example, you can add or remove components, and you can also change the version of the included components.

Using vSphere Lifecycle Manager images starts with setting up an image for a cluster. You can set up an image during the creation of the cluster or later.

After you start managing a cluster with a single image, you can edit the image at any time. You can validate the image before saving it to verify that it includes no conflicting components or missing dependencies.

You can export and import images. For example, you can export an image as an installable ISO file, which you can use for bootstrapping purposes. You can also export the image as a JSON file and reuse it for another cluster that uses images.

Setting Up an Image

To take advantage of all new functionalities that vSphere Lifecycle Manager provides in vSphere 7.0, for example, software recommendations and firmware updates, you must start using images for the clusters in your environment. You can set up an image during the creation of a cluster or later.

During the creation of a cluster, you can only define the ESXi version and, optionally, a vendor add-on to be included in the image for the cluster. You can later edit the image to include additional components or a firmware add-on. For detailed information about creating a cluster and adding hosts to it, see the *vCenter Server and Host Management* documentation.

Note When you set up an image, you select an ESXi version and a vendor add-on from the vSphere Lifecycle Manager depot. If no ESXi base images and vendor add-ons are available in the vSphere Lifecycle Manager depot, you must populate the depot with software updates by synchronizing the depot or uploading updates to the depot manually. For detail information about the corresponding procedures, see [Synchronize the vSphere Lifecycle Manager Depot](#) and [Import Updates to the vSphere Lifecycle Manager Depot](#).

If you do not set up an image during the creation of the cluster, it uses baselines, but you can switch to images at any time. When you set up an image during the transition workflow, you can define the full stack of software to run on the hosts in the cluster. For more information about switching from baselines to images, see [Chapter 12 Switching from Baselines to Images](#).

Whereas switching from baselines to images is possible, the reverse operation is not. If a cluster uses a single image, regardless of whether you set up the image during the cluster creation or transition, you cannot switch to using baselines for that cluster.

Viewing Image Details

You can view details about the image that a cluster uses as well as compliance information for that cluster in the vSphere Lifecycle Manager compliance view.

You access the vSphere Lifecycle Manager compliance view from the **Updates** tab for a cluster.

The **Image** pane consists of two cards.

The **Image** card contains information about the image that the cluster uses. In that card, you perform all image-related operations. You edit the image, you export the image, you validate your selections, and so on. You can also check and view the recommendations that VMware provides.

The **Image Compliance** card contains compliance information about the hosts in the cluster. In that card, you perform host-related operations. You check the compliance of the hosts in the cluster, you run remediation pre-checks, you remediate the hosts, and so on.

In the **Image Compliance** card, you edit remediation settings for that cluster and manage depot overrides.

Editing Images

For a cluster that you manage with a single image, you can edit the image at any time to add, remove, or update an image element. For example, you can edit the image to update the vendor add-on version that it includes, to add or remove a driver, to upgrade the ESXi version in the image, and so on.

Working with Drafts

When you edit an image, vSphere Lifecycle Manager saves the working copy of the image as a draft. The draft is an edited but unsaved version of an image. If you edit an image but for some reason you do not save the new image set-up, when you restart editing the image, you can use the saved draft version as a starting point or you can altogether discard the changes that you previously made.

Validation

You can validate an image draft before you save it. Validation checks whether the image is correct and complete. During validation, vSphere Lifecycle Manager checks for missing dependencies and conflicting components. In case of issues, vSphere Lifecycle Manager returns messages with information about the existing issues. You must resolve all issues before you can save the image.

Edit an Image

If a cluster uses a single image, you can edit that image at any time. You can add, remove, or modify the elements included in the image.

Prerequisites

Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image** card, click the **Edit** button.

4 In the **Edit Image** card, modify the image set-up.

Image Element	Possible Modifications
ESXi Version	From the ESXi Version drop-down menu, select a new ESXi base image.
Vendor Add-On	<ul style="list-style-type: none"> ■ To add a vendor add-on to the image, click Select and select a vendor add-on. ■ To change the version of the vendor add-on in the image or to select a new vendor add-on, click the pencil icon and make your changes . ■ To remove the vendor add-on from the image altogether, click the trash icon .
Firmware and Drivers Add-On	<ul style="list-style-type: none"> ■ To add a firmware add-on to the image, click Select. In the Select Firmware and Drivers Addon dialog box, specify a hardware support manager and select a firmware add-on to add to the image. ■ To select a new firmware add-on, click the pencil icon and make your changes. ■ To remove the firmware add-on element from the image altogether, click the trash icon. <p>Selecting a firmware add-on for a family of vendor servers is possible only if the respective vendor-provided hardware support manager is registered as an extension to the vCenter Server where vSphere Lifecycle Manager runs.</p>
Components	<p>Click Show details and view the list of additional components in the image.</p> <ul style="list-style-type: none"> ■ To add components to the image, click Add Components and select the components and their corresponding versions to add to the image. ■ To delete a component from the image, click the trash icon in the table with components. ■ To delete a manually added component that overrides a component in the selected vendor add-on or base image, click the undo icon in the table with components. <p>This action reverts the override.</p>

5 (Optional) To validate the image, click the **Validate** button.

You validate an image to check for missing dependencies and component conflicts.

6 Click **Save**.

The save operation triggers validation. If the image is valid, vSphere Lifecycle Manager saves it and runs a compliance check against the new image. You can view compliance information in the **Image Compliance** card.

If the image is invalid, saving the image fails and vSphere Lifecycle Manager returns an error.

Results

The new image is validated and displayed in the **Image** card. vSphere Lifecycle Manager performs an automatic hardware compatibility check against the new image.

If there are recommended images generated for the cluster, those recommendations become invalidated. To get recommendations based on the new image, you must initiate the Check for recommended images task manually. For more information, see [Check for Recommended Images](#).

Reusing Existing Images

A vSphere Lifecycle Manager image can be distributed within the same vCenter Server instance where vSphere Lifecycle Manager runs or across vCenter Server instances. You can reuse an image that you already set up by exporting it from its cluster and importing it to the target cluster.

To reuse an existing image for a cluster in the same vCenter Server system, you must export the image as a JSON file and then import the JSON file to the target cluster.

However, when you want to use an existing image for a cluster in another vCenter Server instance, exporting the image as a JSON file might not be enough. You might also need to export the image as a ZIP file. At the target location, you must import the JSON file as an image to the target cluster. You might also need to import the ZIP file to the target vSphere Lifecycle Manager depot to make sure that all components included in the image are available to the target vSphere Lifecycle Manager instance.

Distribution Formats for vSphere Lifecycle Manager Images

You can use vSphere Lifecycle Manager to customize an ESXi base image by adding vendor add-ons and additional components. Depending on your goal, a vSphere Lifecycle Manager image can be distributed and consumed in three different formats.

ISO Image

Distributing an image created with vSphere Lifecycle Manager in an ISO format is useful when you need the image to perform clean installs of ESXi and for bootstrapping purposes, for example the kickstart workflow.

You cannot use an image exported as an ISO file with another cluster that uses vSphere Lifecycle Manager images.

You can import the ISO image into the local depot of the target vSphere Lifecycle Manager instance, but you can only use the ISO file to create upgrade baselines. You cannot use ISO files with vSphere Lifecycle Manager images.

ZIP File

Distributing an image created with vSphere Lifecycle Manager as an offline bundle is useful when you want to import the components that the image contains into the depot of the target vSphere Lifecycle Manager instance.

Unlike the ISO image, you cannot use a ZIP file to create upgrade baselines.

JSON File

Distributing an image created with vSphere Lifecycle Manager as a JSON file is useful when you want to reuse the same image for other clusters that use images for host management.

When you distribute the JSON file to clusters in a different vCenter Server instance, you must make sure that the depot of the target vSphere Lifecycle Manager instance contains all components that the JSON file contains.

The JSON file contains only metadata and not the actual software payloads.

Export an Image

You export an image when you want to use the same image for another cluster in the same or in a different vCenter Server instance.

Depending on your goals, you can export an image in three different formats. You can export the image as a JSON file, as an installable ISO image, or as an offline bundle that contains all software packages included in the image. For more information about the different distribution formats, see [Distribution Formats for vSphere Lifecycle Manager Images](#).

Prerequisites

Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 Click the horizontal ellipsis icon and select **Export**.
- 4 In the **Export Image** dialog box, select a file format, and click **Export**.

You can export the image in one file format at a time. The export format depends on your needs and goals.

If you intend to use the image for a cluster in another vCenter Server, you must export it as a JSON file and as a ZIP file. Afterwards, you must import both the JSON file and the ZIP file to the target vCenter Server system.

Results

The exported file is saved on your local machine.

What to do next

Import the image to a target cluster in the same or in a different vCenter Server instance. For more information, see [Import an Image](#).

For information about importing updates to the vSphere Lifecycle Manager depot, see [Import Updates to the vSphere Lifecycle Manager Depot](#).

Import an Image

Instead of setting up a new image manually, you can reuse an existing image by importing it to a cluster. Upon remediation, the imported image is applied to all hosts in the cluster.

You can import an image only if it is in a JSON format. The JSON file contains only the image metadata, but not the actual software payloads. To successfully import an image to a cluster and apply the software specification to the hosts in the cluster, all the components must specified in the image be available in the vSphere Lifecycle Manager depot.

So, if you want to distribute and reuse an image across vCenter Server instances, importing the JSON file might not be enough if the components from the image are not available in the target vSphere Lifecycle Manager depot. In such cases, before you import the JSON file to the target cluster, you must first import to the target vSphere Lifecycle Manager depot an offline bundle that contains all components included in the image. If you try to import a JSON file to a cluster but the target vSphere Lifecycle Manager depot does not contain the corresponding components, the import operation fails due to validation errors.

For information about importing updates to the vSphere Lifecycle Manager depot, see [Import Updates to the vSphere Lifecycle Manager Depot](#).

Prerequisites

- Verify that the vSphere Lifecycle Manager depot contains all components included in the image that you import.
- Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 Click the horizontal ellipsis icon and select **Import**.
- 4 In the **Import Image** dialog box, select a JSON file and click **Next**.
 - Enter a URL address to the JSON file that you want to import.
 - Browse to a JSON on your local machine.
- 5 (Optional) In the **Edit Image** card, modify the image set-up.

Image Element	Possible Modifications
ESXi Version	From the ESXi Version drop-down menu, select a new ESXi base image.
Vendor Add-On	<ul style="list-style-type: none"> ■ To add a vendor add-on to the image, click Select. ■ To change the version of the vendor add-on in the image or to select a new vendor add-on, click the pencil icon. ■ To remove the vendor add-on element from the image altogether, click the trash icon .

Image Element	Possible Modifications
Firmware and Drivers Add-On	<ul style="list-style-type: none"> ■ To add a firmware add-on to the image, click Select. ■ To select a new firmware add-on, click the pencil icon. ■ To remove the firmware add-on element from the image altogether, click the trash icon. <p>Selecting a firmware add-on for a family of vendor servers is possible only if the respective vendor-provided hardware support manager is registered as an extension to the vCenter Server where vSphere Lifecycle Manager runs.</p>
Components	<p>Click Show details and view the list of additional components in the image.</p> <ul style="list-style-type: none"> ■ To add components to the image, click Add Components and select components to add to the image. ■ To delete a component from the image, click the trash icon in the table with components. ■ To delete a manually added component that overrides a component in the selected vendor add-on, click the undo icon in the table with components. <p>This action reverts the override.</p>

- 6 If the image contains conflicting components or unresolved dependencies, resolve the issues and retry the procedure.

- 7 (Optional) To validate the image, click the **Validate** button.

You validate an image to check for missing dependencies and component conflicts.

- 8 Click **Save**.

A compliance check task is automatically triggered. You can view compliance information in the **Image Compliance** card.

Results

The imported JSON file is imported and set as your new image for the target cluster. At that stage, nothing is installed on the hosts in the cluster. The installation of software on the hosts happens during remediation.

What to do next

Remediate the hosts in the cluster against the new image. See [Run a Remediation Pre-Check for a Cluster](#) and [Remediate a Cluster Against a Single Image](#).

Checking Compliance Against a Single Image

When you check the compliance of a cluster against an image, vSphere Lifecycle Manager compares the software on each host in the cluster with the software specified in the image. If the image contains a firmware and drivers add-on, the compliance check also calculates the firmware compliance of the hosts with the image.

For example, vSphere Lifecycle Manager compares the ESXi version on each host to the ESXi version in the image for the cluster.

In addition to the calculating the compliance state for each host, the compliance check gives you information about the impact that the remediate operation will have on the host, for example if remediation will cause host reboot or if maintenance mode is needed for the host.

Compliance information about the hosts in a cluster is displayed on the **Updates** tab for that cluster, in the **Image Compliance** card. The **Image Compliance** card displays a list of all hosts in the cluster. When you select a host, the compliance information about the host appears on the right.

Compliance States

During a compliance check, the software on each of the hosts in a cluster is compared to the software specification in the image that you set up for the entire cluster. The compliance check defines the compliance of each host with the image for the cluster.

A host can have any of the four compliance states: compliant, non-compliant, incompatible, and unknown.

Compliant

A host is compliant if the image on the host matches the image that you set for the cluster.

Non-Compliant

A host is non-compliant if the image on the host does not match the image that you set for the cluster. A compliant host becomes non-compliant when you set a new image for the cluster or manually add or remove components on the host. You remediate non-compliant hosts to make them compliant.

For example, a host is non-compliant in the following cases.

- The ESXi version on the host is earlier than the ESXi version included in the image for the cluster.
- The firmware on the host is different from the firmware add-on in the image for the cluster.
- The host has a component that is not included in the image for the cluster.
- The host contains a standalone VIB.

Incompatible

A host is incompatible when the image for the cluster cannot be applied to the host.

For example, a host is incompatible in the following cases.

- The ESXi version on the host is later than the ESXi version included in the image for the cluster.
- The host does not have sufficient resources, for example RAM.

- The hardware of the host is incompatible with the vSphere Lifecycle Manager image for the cluster.

Unknown

The unknown compliance state indicates that there is no compliance information about the host.

For example, the compliance state of a host is unknown in the following cases.

- You add a new host to the cluster. The compliance state of the newly added hosts is unknown until you perform a compliance check operation on the cluster.
- You edit the image for the cluster and save the modifications. The compliance state of all hosts in the cluster is unknown until you check the compliance of the cluster against the new image.

Check Cluster Compliance Against an Image

You check the cluster compliance against an image to understand how each of the hosts in the cluster compares to the specified image.

When you perform the check compliance operation on an object that contains multiple clusters that you manage with a single image, for example a data center or vCenter Server instance, vSphere Lifecycle Manager performs compliance checks on all those clusters.

Prerequisites

Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image Compliance** card, click the **Check Compliance** button.

Results

The **Image Compliance** card displays information about the overall number of non-compliant and incompatible hosts in the cluster. For details about a particular host and its compliance state, you must click the host. The information panel appears on the right.

What to do next

Remediate the cluster to make the non-compliant hosts compliant. See [Run a Remediation Pre-Check for a Cluster](#) and [Remediate a Cluster Against a Single Image](#).

View Host Compliance Information

You can view compliance information for each host in a cluster that you manage with a single image. The compliance state of the host indicates whether the software that runs on the selected host matches the software specification expressed in the image.

In the vSphere Lifecycle Manager compliance view, you can see how all elements of the vSphere Lifecycle Manager image for the cluster compare to the software installed on the host. Alternatively, for non-compliant hosts, you can check exactly what causes the image drift.

For hosts that have the incompatible compliance state, vSphere Lifecycle Manager shows in a signpost information about what causes the compatibility issues.

Prerequisites

Verify that the host is not added to the cluster after your last compliance check.

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image Compliance** card, select a host from the list.

An information panel appears on the right. In the **Software compliance** table, you can see what software runs on the selected host and what is the software specification in the image for the cluster.
- 4 To view the full comparison between the image on the host and the image for the cluster, select **Full image comparison** from the drop-down menu for the **Software compliance** table.
- 5 To view only the image elements that make the host non-compliant with the image for the cluster, select **Only drift comparison** from the drop-down menu for the **Software compliance** table.

Run a Remediation Pre-Check for a Cluster

To ensure that cluster health is optimal and that no problems occur during the remediation of the cluster against a single image, you can perform a remediation pre-check.

The remediation pre-check operation includes a series of checks for the cluster and for each host in the cluster. These checks include extensive health checks to determine whether the cluster is in a stable state and to ensure successful remediation. Also, the remediation pre-check triggers a compliance check for the cluster. As a result, after the remediation pre-check, you can view compliance information for each host and whether host reboot or maintenance mode are necessary for successful remediation.

For vSAN clusters, the remediation pre-check operation includes a hardware compatibility check. Depending on how you configure the vSphere Lifecycle Manager remediation settings, vSphere Lifecycle Manager might prevent remediation if hardware compatibility issues exist.

For information about configuring the global vSphere Lifecycle Manager remediation settings, see [Configure Remediation Settings for vSphere Lifecycle Manager Images](#) . For information about configuring the remediation settings for a particular cluster, see [Edit the Remediation Settings for a Cluster](#).

Prerequisites

Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image Compliance** card, click the **Run pre-check** button.

You can observe the progress of the pre-check task. When the task finishes, vSphere Lifecycle Manager displays information about the issues found during the pre-check.

What to do next

If vSphere Lifecycle Manager reports no issues, remediate the cluster. See [Remediate a Cluster Against a Single Image](#).

If issues are reported, resolve the issues before you remediate the cluster.

Run a Remediation Pre-Check for a Single Host

Instead of generating a remediation pre-check report for the entire cluster, you can run a remediation pre-check task for a single host in the cluster.

The remediation pre-check task ensures that the host can be successfully remediated.

Prerequisites

Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image Compliance** card, click the vertical ellipsis icon for a host and select **Run pre-check**.

The **Running pre-check** card appears. You can observe the progress of the task.

Results

When the pre-check finishes, vSphere Lifecycle Manager displays information about the issues found during the pre-check.

What to do next

If vSphere Lifecycle Manager reports no issues, you can remediate the host. See [Remediate a Single Host Against an Image](#).

If vSphere Lifecycle Manager reports any issues, resolve the issues before you remediate the host.

Remediating a Cluster Against a Single Image

When you set up or import a vSphere Lifecycle Manager image to use with a cluster, the software specified in the image is not immediately installed on the hosts in that cluster. To apply the software specification from the image to the hosts, you must remediate the cluster against that image.

To initiate remediation of a cluster, you must have the required privileges. For a list of all vSphere Lifecycle Manager privileges and their descriptions, see [vSphere Lifecycle Manager Privileges For Using Images](#). For more information about managing users, groups, roles, and permissions, see the *vSphere Security* documentation.

In vSphere 7.0, the hosts in a cluster are remediated sequentially. Parallel remediation is not supported. So, if the remediation for a single host in the cluster fails, the remediation of the entire cluster stops.

During remediation, the image that you set up for the cluster is installed on all ESXi hosts in the cluster.

When you remediate a cluster that contains a single ESXi host or that has vSphere Storage DRS disabled or in manual mode, the remediation process cannot put that host into maintenance mode. So, to proceed with the remediation, you must power off the virtual machines that are running on the host, move them to another host, or select a user policy that allows the remediation process to power off the virtual machines. You can also set a user policy to power on the virtual machines after the host is remediated.

For vSAN clusters, the remediation operation includes a hardware compatibility check. Depending on how you configure the vSphere Lifecycle Manager remediation settings, vSphere Lifecycle Manager might not proceed with the remediation task if hardware compatibility issues exist. For information about configuring the global vSphere Lifecycle Manager remediation settings, see [Configure Remediation Settings for vSphere Lifecycle Manager Images](#). For information about configuring the remediation settings for a particular cluster, see [Edit the Remediation Settings for a Cluster](#).

Maintenance Mode

If the update requires, hosts are put into maintenance mode before remediation. Virtual machines cannot run when a host is in maintenance mode. To ensure a consistent user experience, vCenter Server migrates the virtual machines to other hosts within the cluster before a host is put into maintenance mode. vCenter Server can migrate the virtual machines if the cluster is configured for vMotion and if DRS and VMware Enhanced vMotion Compatibility (EVC) are enabled. EVC guarantees that the CPUs of the hosts are compatible, but it is not a prerequisite for vMotion.

Edit the Remediation Settings for a Cluster

You can customize the remediation settings for a particular cluster while the global remediation settings remain intact and applicable to all other clusters that you manage with vSphere Lifecycle Manager images.

The vSphere Lifecycle Manager remediation settings define how ESXi hosts and virtual machines behave before and during a remediation of a cluster. You configure the vSphere Lifecycle Manager remediation settings in the vSphere Lifecycle Manager home view. The remediation settings are valid for all clusters in the vCenter Server instance where vSphere Lifecycle Manager runs. For more information about how to configure the vSphere Lifecycle Manager remediation settings, see [Configure Remediation Settings for vSphere Lifecycle Manager Images](#).

Additionally, you can modify and override the global remediation settings for a single cluster. The overrides are used during the remediation of that specific cluster. For all other clusters, the global remediation settings apply.

For information about automatically triggered hardware compatibility checks, which is a functionality that is applicable only to vSAN clusters, see [Automatically Triggered Hardware Compatibility Checks for vSAN Clusters](#).

Prerequisites

Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image Compliance** card, click the horizontal ellipsis icon and select **Edit remediation settings**.

- 4 In the **Edit Remediation Settings** dialog box, configure the remediation settings of the target cluster and click **Save**.

Option	Description
Quick Boot	Quick Boot reduces the host reboot time during remediation. Before you enable Quick Boot, you must make sure that the ESXi host is compatible with the feature.
VM power state	<p>The VM power state option lets you control the behavior of the virtual machines that run on the ESXi host.</p> <p>You can select from the following options.</p> <ul style="list-style-type: none"> ■ Do not change power state ■ Suspend to disk ■ Power off
VM migration	You can configure vSphere Lifecycle Manager to migrate the suspended and powered off virtual machines from the hosts that must enter maintenance mode to other hosts in the cluster.
Maintenance mode failures	You can configure how vSphere Lifecycle Manager behaves if a host fails to enter maintenance mode before remediation. You can configure vSphere Lifecycle Manager to wait for a specified retry delay period and to retry to put the host into maintenance mode as many times as you indicate in the Number of retries text box.
HA admission control	<p>Admission control is a policy that vSphere HA uses to ensure failover capacity within a cluster. If vSphere HA admission control is enabled during remediation, vMotion might be unable to migrate the virtual machines within the cluster.</p> <p>Disabling admission control allows a virtual machine to be powered on even if it causes insufficient failover capacity. When this happens, no warnings are presented, and the cluster does not turn red. If a cluster has insufficient failover capacity, vSphere HA can still perform failovers, and uses the VM Restart Priority setting to determine which virtual machines to power on first.</p> <ul style="list-style-type: none"> ■ If you select the Disable HA admission control on the cluster option, vSphere Lifecycle Manager remediates the hosts in the cluster and re-enables HA admission control after remediation is complete. ■ If you deselect the Disable HA admission control on the cluster option, vSphere Lifecycle Manager skips remediating the clusters on which HA admission control is enabled.

Option	Description
DPM	<p>VMware Distributed Power Management (DPM) monitors the resources consumed by the running virtual machines in the cluster. If sufficient excess capacity exists, VMware DPM recommends moving virtual machines to other hosts in the cluster and placing the original host into standby mode to conserve power. If the capacity is insufficient, VMware DPM might recommend returning standby hosts to a powered-on state.</p> <ul style="list-style-type: none"> ■ If you select the Disable DPM on the cluster option, vSphere Lifecycle Manager remediates the hosts in the cluster and re-enables DPM after remediation is complete. ■ If you deselect the Disable DPM on the cluster option, vSphere Lifecycle Manager skips remediating the clusters on which DPM is enabled.
Hardware compatibility issues	<p>vSphere Lifecycle Manager performs a hardware compatibility check as part of the remediation pre-check and the remediation tasks for vSAN clusters. You can configure vSphere Lifecycle Manager to prevent remediation when hardware compatibility issues exist for the cluster.</p> <ul style="list-style-type: none"> ■ If you select the Prevent remediation if hardware compatibility issues are found option, vSphere Lifecycle Manager reports hardware compatibility issues as an error, which prevents remediation. ■ If you deselect the Prevent remediation if hardware compatibility issues are found option, vSphere Lifecycle Manager reports hardware compatibility issues as a warning, which does not prevent remediation. <p>If the cluster is not vSAN-enabled, vSphere Lifecycle Manager does not perform a hardware compatibility check as part of the remediation pre-check or the remediation tasks.</p>

Results

These settings become the remediation settings for the selected cluster. vSphere Lifecycle Manager uses those settings for that cluster for all future remediation tasks. The global remediation settings remain unchanged and are applied to all other clusters.

In the **Image Compliance** card, vSphere Lifecycle Manager displays a message that the global remediation settings are overridden. Also, an option to reset the values appears in the card.

Remediate a Cluster Against a Single Image

By remediating a cluster against an image, you apply the software specified in the image to all the hosts in the cluster. So, by remediating a cluster, you make the non-compliant hosts compliant with the image that you set for the cluster.

During remediation, the hosts in the cluster are remediated in sequence. The hosts that have the incompatible compliance state are not remediated.

If a vCenter HA failover is initiated during the remediation of a cluster, the remediation task is canceled. After the failover finishes, you must restart the remediation task on the new node.

Prerequisites

Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image Compliance** card, click the **Remediate All** button.

The **Review Remediation Impact** dialog box appears. The dialog box contains detailed information about all changes that remediation will enforce on the hosts in the cluster.

- 4 In the **Review Remediation Impact** dialog box, review the impact summary, the applicable remediation settings, and the EULA.

- 5 To save and review the impact details later, click **Export Impact Details**

- 6 Accept the EULA by selecting respective check box.

The check box is selected by default.

- 7 Click the **Start remediation** button.

The Remediate Cluster task appears in the **Recent Tasks** pane. You can also observe the progress of the remediation task in the **Image Compliance** card. If remediation fails, vSphere Lifecycle Manager gives information about the reasons for the failure.

Remediate a Single Host Against an Image

When you remediate a single host against the image for the cluster, vSphere Lifecycle Manager applies the image to that host only. Remediation is the operation that makes a non-compliant host in the cluster compliant with the image that you use for that cluster.

Prerequisites

Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image Compliance** card, click the vertical ellipsis icon for a host and select **Remediate**.

The **Review Remediation Impact** dialog box appears. The dialog box contains detailed information about all changes that remediation will enforce on the host.

- 4 Review the impact summary, the applicable remediation settings, and the EULA.

- 5 To save and review the impact details later, click **Export Impact Details**

- 6 Accept the EULA by selecting respective check box.

The check box is selected by default.

- 7 Click the **Start remediation** button.

The Remediate Cluster task appears in the **Recent Tasks** pane. You can also observe the progress of the remediation task in the **Image Compliance** card. If remediation fails, vSphere Lifecycle Manager gives information about the reasons for the failure.

View Last Remediation or Remediation Pre-Check Results for a Cluster that Uses a Single Image

You can view the remediation results from the last remediation or remediation pre-check that vSphere Lifecycle Manager performed.

Prerequisites

Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image Compliance** card, click the horizontal ellipsis icon and select your task.
 - To view the results from the last remediation pre-check performed on the cluster, select **Last pre-check results**.
 - To view the results from the last remediation of the cluster, select **Last remediation results**.

Results

The **Image Compliance** displays detailed information about the last remediation or remediation pre-check task that ran on the cluster.

Manage Depot Overrides for a Cluster

Instead of accessing the vSphere Lifecycle Manager depot in vCenter Server, clusters in Remote Office and Branch Office (ROBO) deployments can download data from a depot that is local for them. You can configure vSphere Lifecycle Manager to use local depots for any cluster that uses images.

A ROBO cluster is a cluster that has limited or no access to the Internet or limited connectivity to vCenter Server. As a result, clusters in ROBO deployments might have limited access to the vSphere Lifecycle Manager depot during the compliance check, remediation pre-check, and remediation operations.

With vSphere Lifecycle Manager images, you can use a local depot for ROBO clusters and configure vSphere Lifecycle Manager to use the local depot during the compliance check, remediation pre-check, and the remediation tasks. The local depot overrides the vSphere Lifecycle Manager depot. Using local depots with ROBO clusters saves time and network bandwidth.

For each cluster that you manage with a single image, you can add and use multiple local depots instead of the default vSphere Lifecycle Manager depot. You can also delete the depot overrides that you configure. If depot overrides are not active for a cluster, the cluster uses the general vSphere Lifecycle Manager depot in vCenter Server.

Prerequisites

- Set up an online depot to which the cluster can connect.
- Export an offline bundle with components from a vSphere Lifecycle Manager image and import the offline bundle to the target local depot.
- Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image Compliance** card, click the horizontal ellipsis icon and select **Manage depot overrides**.

The **Manage depot overrides** dialog box appears.

- 4 Select your task.

Option	Description
Add depot overrides	Enter a URL or a file path to a local depot and click Add . The depot is added to the Depot override URL list.
Delete a depot override	Click the horizontal ellipsis icon for a depot override from the list and click Delete . The depot is removed from the Depot override URL list.

- 5 Click **Close**.

Results

In the **Image Compliance** pane, you see a notification if depot overrides are active for the cluster.

Switching from Baselines to Images

12

In vSphere 7.0, you can manage a cluster with either baselines or images. You cannot use both at the same time for a single cluster. Even if you did not set up an image for the cluster during the cluster creation, you can at any time switch from using baselines to switching images for the cluster.

To switch to vSphere Lifecycle Manager images, you must set up a new image or import an existing one. Before you proceed with setting up or importing an image, vCenter Server checks and reports if the cluster is eligible for using images. For more information about cluster eligibility, see [Cluster Eligibility to Use vSphere Lifecycle Manager Images](#).

With standalone hosts, you can only use baselines. For more information about the difference between baselines and images, see [Chapter 3 vSphere Lifecycle Manager Baselines and Images](#).

Requirements

To switch to using images, the cluster must meet multiple requirements.

- All ESXi hosts in the cluster must be of version 7.0 and later.
- All ESXi hosts in the cluster must be stateful.

A stateful install is one in which the the host boots from a disk.

- No host in the cluster can contain any unknown components.

If a host is of version earlier than 7.0, you must first use an upgrade baseline to upgrade the host and then you can successfully switch to using images. For more information about using baselines for host patching and upgrade operations, see [Chapter 10 Using Baselines and Baseline Groups](#).

For more information about converting a stateless host into a stateful host, find information about Auto Deploy in the *VMware ESXi Installation and Setup* documentation.

Specifics

Several behavioral specifics exist when you switch to using vSphere Lifecycle Manager images.

- If you switch to using images, you cannot revert to using baselines for the cluster. You can move the hosts to a cluster that uses baselines, but you cannot change a cluster that already uses a single image for management purposes.
- When you set up and save an image for a cluster, the image is not applied to the hosts in the cluster unless you remediate the hosts. The mere action of changing the management method does not alter the hosts in the cluster.
- After you set up an image for the cluster and remediate the hosts in the cluster against the image, standalone VIBs are deleted from the hosts.
- After you set up an image for the cluster and remediate the hosts in the cluster against the image, non-integrated solution agents are deleted from the hosts.

Before you switch to using vSphere Lifecycle Manager images, learn what the new functionality lets you do and what the differences between using baselines and using images are.

	Using Baselines	Using Images
Validation	Not supported. You do not validate a baseline before applying the updates to the hosts. You can only perform a remediation pre-check.	Supported. You can validate a vSphere Lifecycle Manager image to check if it is applicable to all hosts in the cluster. You can also perform a remediation pre-check.
Compliance checks	With baselines, you can check the compliance of an object against a single or against multiple baselines.	With vSphere Lifecycle Manager images, you can check the compliance of the hosts against a single image. To check the compliance against another image, you must first set up the new image.
Staging	You can stage updates to the hosts before actually installing them.	Not supported.
Remediation	With vSphere Lifecycle Manager baselines, you can remediate an object against a single baseline or against multiple baselines. So, with a single operation, you can patch and upgrade a host.	With vSphere Lifecycle Manager images, you can add, remove, or modify the components in the image that you use for a cluster. When you remediate the hosts against the new image, all modified components are applied to the host. So, you can upgrade and patch a host with a single remediation operation.

	Using Baselines	Using Images
Firmware updates	Not supported.	With vSphere Lifecycle Manager images, firmware updates are carried out through firmware and drivers add-ons, which you add to the image that you use to manage a cluster. Updating firmware with images requires an OEM-provided hardware support manager plug-in, which integrates with vSphere Lifecycle Manager.
Hardware compatibility checks	Not supported.	You can check the hardware compatibility of the hosts in a cluster against the VMware Compatibility Guide (VCG). You can also check the compatibility of all hosts in a vSAN-enabled cluster against the vSAN Hardware Compatibility List (vSAN HCL).
Software recommendations	Not supported.	Supported. Based on the hardware of the hosts in the cluster, you get recommendations about available and applicable ESXi updates or upgrades.
vCenter Server /Datacenter-level operations	With vSphere Lifecycle Manager baselines, you can trigger any of the main operations at the vCenter Server or data center level.	With vSphere Lifecycle Manager images, you cannot operate at a vSphere Lifecycle Manager or data center level.
Virtual machine management	You can upgrade the VMware Tools and virtual hardware versions of the virtual machines in a cluster that you manage with vSphere Lifecycle Manager baselines.	You can upgrade the VMware Tools and virtual hardware versions of the virtual machines in a cluster that you manage with vSphere Lifecycle Manager images.
Update Manager Download Service (UMDS)	Supported.	Supported.

This chapter includes the following topics:

- [Cluster Eligibility to Use vSphere Lifecycle Manager Images](#)
- [Set Up a New Image](#)
- [Import an Existing Image](#)

Cluster Eligibility to Use vSphere Lifecycle Manager Images

Switching from baselines to images requires that you set up or import a vSphere Lifecycle Manager image to manage the cluster with. As part of the transition, before you set up the image, vCenter Server triggers an automatic task that checks whether the cluster is eligible to use vSphere Lifecycle Manager images.

The **Check cluster's eligibility to be managed with a single image** task ensures that the cluster is not undergoing remediation against a baseline and checks whether all requirements for using vSphere Lifecycle Manager images are met.

Also, the task checks for standalone VIBs and ensures that no unintegrated solutions are enabled for the cluster. You might not be able to switch to using vSphere Lifecycle Manager images if unintegrated solutions are enabled on the cluster.

Note If you use any third-party products or solutions, you must confirm with your third-party software vendor whether the respective solution works with vSphere Lifecycle Manager.

The task returns three types of notifications: error, warning, and info.

Errors

The **Check cluster's eligibility to be managed with a single image** task reports an error if the cluster contains at least one host that is not stateful or that is not of a compatible ESXi version, that is 7.0 and later.

Also, the **Check cluster's eligibility to be managed with a single image** returns an error if the cluster contains VIBs of [Chapter 4 vSphere Lifecycle Manager Images and Other VMware Products and Solutions](#). In that case, you must disable the unintegrated solution and retry the transition.

Warnings

The **Check cluster's eligibility to be managed with a single image** task issues a warning if the cluster contains at least one host with a standalone VIB or an unknown VIB. Warnings do not block the transition to using vSphere Lifecycle Manager images, but they require special attention or a user action.

For example, you see a warning notification if a host in the cluster contains a standalone VIB, for example a driver, for which a component is available in the vSphere Lifecycle Manager depot. If you want to keep the VIB, you must add the respective component to the vSphere Lifecycle Manager image. Otherwise, the standalone VIB is deleted upon remediation.

You also get a warning if a host in the cluster contains an unknown VIB. Unknown VIBs are standalone VIBs for which no component is available in the vSphere Lifecycle Manager depot. If vSphere Lifecycle Manager detects an unknown VIB, you must import a component that contains the VIB into the vSphere Lifecycle Manager depot and restart the transition. Otherwise, the unknown VIB is deleted upon remediation.

Info

The **Check cluster's eligibility to be managed with a single image** task gives an info notification if the cluster contains at least one host with a standalone VIB, but you can still proceed to setting up a vSphere Lifecycle Manager image for the cluster without any additional actions.

For example, you see an info notification if the cluster is enabled for an integrated solution, for example vSphere HA or vSAN.

Set Up a New Image

To take advantage of all new functionalities that vSphere Lifecycle Manager introduces in vSphere 7.0, you must switch to using vSphere Lifecycle Manager images instead of baselines.

If you switch to using images, you cannot revert to using baselines for the cluster. You can move the hosts to another cluster, which uses baselines, but you cannot change the cluster that already uses a single image.

For conceptual information about vSphere Lifecycle Manager images, see [vSphere Lifecycle Manager Images](#).

For information about how to use vSphere Lifecycle Manager images to manage hosts and cluster, see [Chapter 11 Using Images](#).

Prerequisites

- Verify that all ESXi hosts in the cluster are of version 7.0 and later.
- Verify that all ESXi hosts in the cluster are stateful. A stateful install is one in which the host boots from a disk.
- Verify that all ESXi hosts in the cluster are from the same hardware vendor.
- Verify that no unintegrated solution is enabled for the cluster.
- Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with baselines and baseline groups.
- 2 On the **Updates** tab, click **Image**.
- 3 Click the **Set up image** button.

vSphere Lifecycle Manager starts checking if the cluster is eligible for using images. If no problems are reported, the **Convert to an Image** pane appears.
- 4 If the **Check cluster's eligibility to be managed with a single image** task reports an error or a warning that requires an action, resolve the issue and restart the procedure.
- 5 From the **ESXi Version** drop-down menu, select an ESXi image.

6 (Optional) Add a vendor add-on to the image.

- a Click **Select**.

The **Select Vendor Addon** appears.

- b Select an add-on from the list.

An information panel appears on the right. The information panel shows information about the components that the add-on adds to the ESXi image and the components that it removes from the image.

- c From the **Version** drop-down menu for the selected add-on, select the add-on version.
- d Click **Select**.

7 (Optional) Add a firmware and drivers add-on to the image.

- a Click **Select**.

The **Select Firmware and Drivers Addon** appears.

- b Select a hardware support manager from the respective drop-down menu.

A list of firmware and drivers add-ons appears.

- c Select an add-on from the list.

An information panel appears on the right. The information panel shows information about the supported ESXi versions and whether the add-on contains a driver or not.

- d From the **Version** drop-down menu for the selected add-on, select the add-on version.
- e Click **Select**.

8 (Optional) Add additional components to the image.

- a Click **Show details**.

- b Click **Add components**.

The **Add Components** dialog box appears.

- c (Optional) Use the **Show** drop-down menu to sift out the components that are not part of the selected vendor add-on.

- d Select one or multiple components from the list.

An information panel appears on the right. The information panel shows information about the component that you selected first.

- e From the **Version** drop-down menu for the selected component, select the component version.

- f Click **Select**.

The selected components appear in the list of components that the image contains. You can use the **Show** drop-down menu to sift out the additional components.

- g (Optional) Click **Hide details** to hide the list of components.

- 9 (Optional) To validate the image, click the **Validate** button.

You validate an image to check for missing dependencies and component conflicts.

- 10 Click **Save**.

Saving the image triggers an automatic compliance check. All hosts in the cluster are checked against the image.

- 11 In the **Convert to an Image** pane, finish the image setup.

- a Click the **Finish image setup** button.
- b In the **Finish image setup** dialog box, click **Yes, finish image setup**.

Results

You set up an image for the cluster. You now manage all hosts in the cluster collectively with a single image for the cluster. Upon remediation, the image is installed on all hosts in the cluster.

What to do next

To apply the image to all hosts in the cluster, remediate the cluster against the image.

Import an Existing Image

To take advantage of all new functionalities that vSphere Lifecycle Manager introduces in vSphere 7.0, you must switch to using vSphere Lifecycle Manager images instead of baselines.

If you switch to using images, you cannot revert to using baselines for the cluster. You can move the hosts to another cluster, which uses baselines, but you cannot change the cluster that already uses a single image.

For conceptual information about vSphere Lifecycle Manager images, see [vSphere Lifecycle Manager Images](#).

For information about how to use vSphere Lifecycle Manager images to manage hosts and clusters, see [Chapter 11 Using Images](#).

Prerequisites

- Verify that all ESXi hosts in the cluster are of version 7.0 and later.
- Verify that all ESXi hosts in the cluster are stateful. A stateful install is one in which the host boots from a disk.
- Verify that all ESXi hosts in the cluster are from the same hardware vendor.
- Verify that no unintegrated solution is enabled for the cluster.
- Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with baselines and baseline groups.
- 2 On the **Updates** tab, click **Image**.
- 3 Click the **Import Image** button.

The **Import Image** dialog box appears.

- 4 Select a JSON file to import and click **Next**.
 - Click the **Browse** button and select a JSON file on your local machine.
 - Enter a valid URL to a JSON file on a remote web server.

vSphere Lifecycle Manager starts checking if the cluster is eligible for using images. If no problems are reported, the **Convert to an Image** pane appears. The elements of the imported image appear in the **Define Image** card.

- 5 (Optional) Customize the imported image by changing any of its elements.
- 6 (Optional) To validate the image, click the **Validate** button.

You validate an image to check for missing dependencies and component conflicts.

- 7 Click **Save**.

Saving the image triggers an automatic compliance check. All hosts in the cluster are checked against the image.

- 8 In the **Convert to an Image** pane, finish the image setup.
 - a Click the **Finish image setup** button.
 - b In the **Finish image setup** dialog box, click **Yes, finish image setup**.

Results

You now manage all hosts in the cluster collectively with a single image for the cluster. Upon remediation, the image is installed on all hosts in the cluster.

What to do next

To apply the image to all hosts in the cluster, remediate the cluster against the image.

Recommended Images

13

For the clusters that you manage with images, vSphere Lifecycle Manager can generate and provide you with software recommendations in the form of pre-validated images that are compatible with the hardware of the hosts in a cluster. Recommended images are valid images that are based on the latest ESXi major or minor release.

When you set up or edit an image, you manually combine the image elements (ESXi version, vendor add-on, firmware add-on, and additional components) in such a way as to define the full software stack to run on all hosts in the cluster. You must manually check whether a particular image set-up is complete and valid, and suitable to your environment. The vSphere Lifecycle Manager recommendations save you the effort of exploring the possible and applicable combinations of image elements.

Recommended images are validated through a series of checks that ensure that a recommended image has no missing dependencies or conflicting components. For vSAN clusters, the validation also runs a hardware compatibility check against the vSAN Hardware Compatibility List (vSAN HCL). The extensive validation checks ensure that if you decide to use a recommended image for a cluster, the remediation against the recommended image is successful.

To generate recommendations, vSphere Lifecycle Manager checks what software is available in the vSphere Lifecycle Manager depot and what firmware is available in the depot that the selected hardware support manager makes available. Based on the available software, firmware, and, for vSAN clusters, the hardware compatibility checks, for each cluster that you manage with a single image, vSphere Lifecycle Manager provides you with up to two recommended images.

- Latest image

The latest image contains the latest major ESXi version. For example, if the current image for a cluster contains a base image of version ESXi 7.0 and base images of version 7.5 and 8.0 are available in the vSphere Lifecycle Manager depot, the latest image recommendation contains ESXi version 8.0.

- Latest image in the current series

The latest image in a series contains the latest minor ESXi. For example, if the current image for a cluster contains a base image of version ESXi 7.0 and base images of version 7.0a, 7.0 U1, 7.5, and 8.0 are available in the vSphere Lifecycle Manager depot, the latest image in the current series recommendation contains ESXi version 7.0 U1.

The ESXi version in a recommended image might be the same as the ESXi version in the current image for a cluster. But the recommended image might contain a later version of the vendor add-on, component, or firmware add-on.

Sometimes, the latest ESXi version available in the depot might not be recommended, because it causes hardware compatibility issues. In that cases, vSphere Lifecycle Manager reports that no recommended images are available for the cluster.

You can replace the current image of a cluster with one of the recommended images for that cluster.

The recommendation generation task is cancelable.

This chapter includes the following topics:

- [Check for Recommended Images](#)
- [Use a Recommended Image](#)

Check for Recommended Images

By using recommended images for your clusters, you ensure that your environment runs the latest verified software. Because the recommendations that vSphere Lifecycle Manager generates for a cluster are not automatically updated when the cluster changes or when new software is available in the vSphere Lifecycle Manager depot, you must periodically perform the check for recommendations task.

A recommended image contains updates for your cluster. Recommendations are based on the ESXi versions available in the vSphere Lifecycle Manager depot. When you trigger the check for recommendations task, vSphere Lifecycle Manager first determines the recommended ESXi versions for the cluster. After that, vSphere Lifecycle Manager checks sequentially for newer versions of the vendor add-on, additional components, and firmware add-on that are compatible with the recommended ESXi version and the hardware of the hosts in the cluster. So, sometimes, a recommended image might contain the same ESXi version as the ESXi version in the current image for the cluster but combined with an updated vendor add-on, component, or firmware add-on.

The check for recommendation task is non-cancellable. You must rerun the task periodically to ensure that the recommendations are valid and still suitable to the cluster.

Before you check for recommended images, you must ensure that the cluster is not being remediated. Recommendations generation and remediation are mutually exclusive operations. They cannot run simultaneously.

Prerequisites

- Verify that remediation is not running for the cluster.
- Verify that you have connection to the Internet.

- Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image** card, click the horizontal ellipsis icon and select **Check for recommended images**.

When the task finishes, a blue badge appears in the **Image** card.

- 4 To view the recommended images, click the horizontal ellipsis icon and select **View recommended images**.

Results

vSphere Lifecycle Manager generates recommendations. vSphere Lifecycle Manager might list up to two recommended images applicable to the cluster. Sometimes, no recommended images are available. In such cases, vSphere Lifecycle Manager displays detailed information about why no recommendations are available.

What to do next

View the recommendations. You can import a recommended image to the cluster and replace the current image that the cluster uses. See [Use a Recommended Image](#).

Use a Recommended Image

For any cluster that you manage with a single image, you can view the images that vSphere Lifecycle Manager recommends and you can replace the current image for the cluster with a recommended image. Using recommended images saves you the time and effort of identifying valid images that are applicable to all hosts in a cluster.

Prerequisites

- Check for recommended images for a cluster. See [Check for Recommended Images](#).
- Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image** card, click the horizontal ellipsis icon and select **View recommended images**.

If the **View recommended images** option is dimmed, no recommended images are available for this cluster.

Sometimes, even if newer versions of ESXi are available in the vSphere Lifecycle Manager depot, they are not included in a recommended image because of hardware compatibility issues.

The **Recommended Images** dialog box appears.

- 4 In the **Recommended Images** dialog box, select a recommended image by clicking the respective radio button and click **Continue**.

Option	Description
Latest in current series	The recommended image is based on the latest ESXi version in the current series of releases. For example, if the ESXi version in your current image is 7.0, this option might include ESXi version 7.0 Update 1 and a related vendor add-on.
Latest and greatest	The recommended image is based on the latest major ESXi version. For example, if the ESXi version in your current image is 7.0, this option might include ESXi version 8.0 and a related vendor add-on.

The selected image is imported to the cluster as a draft. The **Edit Image** card appears.

- 5 (Optional) Edit the image and validate the new image set-up.
- 6 Click **Save**.

If you do not save the image, it is saved as a draft. The next time you start editing the image for that cluster, you can use the draft as a starting point.

Results

The recommended image is saved for that cluster. If a draft exists for the cluster, the draft is overridden by the recommended image. No software is installed on the hosts in the cluster at this stage.

What to do next

To apply the software specification that the image defines, remediate the cluster against the new image. See [Run a Remediation Pre-Check for a Cluster](#) and [Remediate a Cluster Against a Single Image](#).

Firmware Updates

14

You can use vSphere Lifecycle Manager images to perform firmware updates on the ESXi hosts in a cluster. Using vSphere Lifecycle Manager images simplifies the host update operation. With a single operation, you update both the software and the firmware on the host.

In earlier vSphere releases, you could perform firmware updates on vSAN clusters by using system-managed baselines. For non-vSAN clusters, firmware updates had to be manual.

Starting with vSphere 7.0, you can easily update the firmware in any cluster that you manage with a single image. Firmware updates are not available for clusters that you manage with baselines.

To apply firmware updates to the hosts in a cluster that you manage with a single image, you must include a special type of add-on, the firmware and drivers add-on, in the image and remediate the cluster to apply the image to all hosts. The firmware and drivers add-on is a vendor-provided add-on that contains the components that encapsulate firmware update packages. The firmware and drivers add-on might also contain the necessary drivers.

Unlike vendor add-ons, firmware and drivers add-ons are not distributed through the official VMware online depot or as offline bundles available at my.vmware.com. For a given hardware vendor, firmware updates are available in a special vendor depot, whose content you access through a software module called a hardware support manager. The hardware support manager is a plug-in that registers itself as a vCenter Server extension. Each hardware vendor provides and manages a separate hardware support manager that integrates with vSphere. For each cluster that you manage with a single image, you select the hardware support manager that provides the firmware updates for the cluster. After you determine the hardware support manager that you want to use for a cluster, the hardware support manager provides you with a list of the available firmware updates. When you select and include a firmware add-on to an image, that add-on might modify the specified image by adding or removing components. The firmware add-on also defines the firmware versions to be installed on the hosts. During remediation, vSphere Lifecycle Manager applies the image to the hosts and requests the selected hardware support manager to update the firmware on the hosts in accordance with the firmware add-on specified in the image.

Selecting a hardware support manager and including a firmware add-on in your image guarantees that during a compliance check, vSphere Lifecycle Manager also determines the firmware compliance for the cluster. So, you can easily detect and remediate any unwanted drifts. The hardware support manager is also responsible for retrieving the firmware versions on the host hardware, and, in some cases, determining the appropriate drivers for the updated firmware version.

For vSAN clusters, the hardware support manager inspects the hosts in the cluster to determine their current I/O device controllers and firmware. During a hardware compatibility check for the cluster, vSphere Lifecycle Manager checks whether the firmware in the image is compatible with the hardware in the cluster as per vSAN Hardware Compatibility List (vSAN HCL). The hardware compatibility check ensures that when vSphere Lifecycle Manager remediates the cluster and applies the image to all hosts, the firmware and drivers on the hosts are certified for use with vSAN.

This chapter includes the following topics:

- [Deploying Hardware Support Managers](#)
- [Use an Image for Firmware Updates](#)

Deploying Hardware Support Managers

The deployment method and the management of a hardware support manager plug-in is determined by the respective OEM.

You can deploy and use hardware support managers from the following vendors.

- **Dell**
The hardware support manager that Dell provides is part of their host management solution, OpenManage Integration for VMware vCenter (OMIVV), which you deploy as an appliance.
- **HPE**
The hardware support manager that HPE provides is part of their management tool, iLO Amplifier, which you deploy as an appliance.
- **Lenovo**
The hardware support manager that Lenovo provides is part of their server management solution, Lenovo xClarity Integrator for VMware vCenter, which you deploy as an appliance.

Deploying and Configuring Hardware Support Managers

Regardless of the hardware vendor, you must deploy the hardware support manager appliance on a host with sufficient memory, storage, and processing resources. Typically, hardware support manager appliances are distributed as OVF or OVA templates. You might deploy them on any host in any vCenter Server server.

After you deploy the appliance, you must power on the appliance virtual machine and register the appliance as a vCenter Server extension. You might need to log in to the appliance as an administrator. Each hardware support manager might register with only one or multiple vCenter Server systems.

A vCenter Server plug-in user interface might become available in the vSphere Client after you deploy a hardware support manager appliance, but the hardware support manager might also have a separate user interface of its own. For example, OMIVV, iLO Amplifier, and Lenovo xClarity Integrator for VMware vCenter all have a vCenter Server plug-in user interface, which helps you configure and work with the respective hardware support manager.

Each hardware support manager has its own mechanism of managing the actual firmware packages and making firmware add-ons available for you to choose.

The successful integration between the hardware support manager and vSphere Lifecycle Manager might require a specific configuration of the hardware support manager. For example, with OMIVV, you must first create a connection profile. Then, you must create a cluster profile and associate it with a cluster before you can add a firmware add-on from Dell to the image for that cluster.

For detailed information about deploying, configuring, and managing hardware support managers, refer to the respective OEM-provided documentation.

Use an Image for Firmware Updates

vSphere Lifecycle Manager allows you to manage the firmware lifecycle on ESXi hosts that are part of a cluster that you manage with a single image.

Prerequisites

- Deploy the vendor-provided hardware support manager and register it as a vCenter Server extension. For more information about deploying and managing a hardware support manager, see the respective OEM documentation.
- If you use the hardware support manager provided by Dell, create a cluster profile and associate it with the cluster. For more information, review the OpenManage Integration for VMware vCenter (OMIVV) documentation.
- Verify that all hosts in the cluster are from the same vendor.
- Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Image**.
- 3 In the **Image** card, click the **Edit** button.

- 4 In the **Edit Image** card, for the **Firmware and Drivers Addon**, click **Select**.

The **Firmware and Drivers Addon** dialog box appears.

- 5 In the **Firmware and Drivers Addon** dialog box, select a hardware support manager from the drop-down menu.

The selected hardware support manager must be from the same hardware vendor as the hosts in the cluster. Otherwise, during a compliance check, the hardware support manager reports the selected firmware and drivers add-on to be incompatible with the host or hosts that are from a different vendor. Firmware remediation fails.

A list of all available firmware add-ons appears.

- 6 Select a firmware add-on from the list.

An information panel appears on the right. The panel contains information about the supported ESXi versions and whether the selected add-on contains the necessary drivers.

- 7 Click **Select**.

The selected firmware and drivers add-on is included in the image.

- 8 In the **Image** card, validate and save the image.

After the image is saved, a compliance check against the new image is triggered for the cluster.

- 9 In the **Image Compliance** card, review the compliance check results for the cluster and for each host.

- 10 If any host in the cluster has firmware that is non-compliant with the new image firmware, remediate the respective host or the cluster.

- a (Optional) In the **Image Compliance** card, run a remediation pre-check to ensure that remediation finishes successfully.

- To run a pre-check for all hosts in the cluster, click the **Run Pre-check** button.
- To run a pre-check for a single host, click the vertical ellipsis icon for the host and select **Run Pre-check**.

- b In the **Image Compliance** card, initiate remediation.

- To remediate all hosts in the cluster, click the **Remediate All** button.

During cluster remediation, if the remediation of a single host fails, the remediation for the cluster ends prematurely.

- To remediate a single host, click the vertical ellipsis icon for the host and select **Remediate**.

You are not obliged to start remediation immediately after setting up an image for a cluster. However, nothing is installed on the hosts unless you remediate them against the image for the cluster. The firmware on the hosts is actually updated only after successful remediation. You can remediate the objects in your environment at any time that is convenient for you.

Results

The firmware on the hosts in the cluster is updated to the firmware version specified in the firmware add-on for the image.

Hardware Compatibility Checks

15

vSphere Lifecycle Manager automates the process of validating the hardware compliance of hosts and clusters against a selected ESXi version. Hardware compatibility checks ensure that the host or cluster hardware is compliant with the VMware Compatibility Guide (VCG) and vSAN Hardware Compatibility List (vSAN HCL).

Hardware Compatibility Checks Against VCG and vSAN HCL

Hardware compatibility lists are lists of hardware certified for use with various vSphere releases. VCG contains information about server models and I/O devices that are certified for use with particular vSphere releases. Besides VCG, vSAN maintains a separate hardware compatibility list that lists all I/O device controller hardware and the respective firmware versions certified for use with vSAN.

Note vSphere Lifecycle Manager performs the full driver and firmware verification only if you configure vSphere Lifecycle Manager with a hardware support manager and add a firmware add-on to the vSphere Lifecycle Manager image. Without using a hardware support manager, vSphere Lifecycle Manager only validates PCI device and driver versions.

With vSphere Lifecycle Manager, you can perform the following tasks.

- Check the hardware compatibility of a single host.

The hardware compatibility check for a host validates the server model and the host I/O devices against the current or future ESXi version. The check is performed against the VCG or the vSAN HCL.

- Check the hardware compatibility of a vSAN cluster.

The hardware compatibility check for a cluster validates only the I/O devices against the software specification in the image for the cluster. Unless all hosts are remediated against that image, the hardware compatibility check might not reflect accurately their current status. The hardware compatibility check for a cluster is performed against the vSAN HCL only.

In general, hardware incompatibility does not prevent remediation and is not resolved upon remediation. However, you can configure vSphere Lifecycle Manager to prevent remediation when hardware compatibility issues exist for a cluster. For information about configuring the global vSphere Lifecycle Manager remediation settings, see [Configure Remediation Settings for vSphere Lifecycle Manager Images](#) . For information about configuring the remediation settings for a particular cluster, see [Edit the Remediation Settings for a Cluster](#).

Hardware Compatibility Checks for Clusters

Checking the hardware compatibility of your clusters before remediating them helps you avoid unsupported and unwanted configurations. When you run a hardware compatibility check at the cluster level, vSphere Lifecycle Manager checks for potential hardware compatibility issues between the storage controllers of the hosts in the cluster and the software specification defined in the image for that cluster. The compatibility check is performed against the vSAN HCL. Hardware compatibility checks are available only for vSAN clusters that you manage with a single image.

For vSAN clusters that you manage with a single image, you can manually trigger a hardware compatibility check. Alternatively, vSphere Lifecycle Manager runs regular hardware compatibility checks in accordance with a configurable schedule. A hardware compatibility check starts automatically with certain vSphere Lifecycle Manager operations. For more information about the automatic hardware compatibility checks that vSphere Lifecycle Manager performs, see [Automatically Triggered Hardware Compatibility Checks for vSAN Clusters](#).

If a vSAN cluster uses baselines, hardware compatibility checks are not available. Also, if a cluster uses a single vSphere Lifecycle Manager image but vSAN is not enabled for that cluster, hardware compatibility checks for that cluster are also not available.

Hardware Compatibility Checks for Hosts

With vSphere Lifecycle Manager, you can perform a hardware compatibility check for a single host. The hardware compatibility check ensures that the host hardware, that is server model and I/O devices, is certified for use with a selected ESXi version. The hardware compatibility check for a host is performed against the VCG, unless the host is in a vSAN cluster.

Note If the host is in a vSAN cluster, the hardware compatibility of the I/O devices that are used by vSAN is checked against the vSAN HCL. All other I/O devices are checked against the VCG.

You can check the hardware compatibility of any host, whether it is in a cluster that uses a single image or baselines. You can also check the hardware compatibility of a standalone host.

This chapter includes the following topics:

- [Automatically Triggered Hardware Compatibility Checks for vSAN Clusters](#)
- [Check the Hardware Compatibility of a Cluster](#)
- [Check the Hardware Compatibility of a Host](#)

Automatically Triggered Hardware Compatibility Checks for vSAN Clusters

Starting with vSphere 7.0 Update 1, vSphere Lifecycle Manager performs regular hardware compatibility checks for the vSAN clusters that you manage with a single image. In addition, certain vSphere Lifecycle Manager operations also trigger an automatic hardware compatibility check. Automated hardware compatibility checks are available for vSAN clusters that use a single image.

For information about hardware compatibility checks and instructions how to manually perform a hardware compatibility check for a cluster or for a single host, see [Chapter 15 Hardware Compatibility Checks](#).

vSphere Lifecycle Manager Operations That Trigger a Hardware Compatibility Check

vSphere Lifecycle Manager performs an automatic hardware compatibility check for any vSAN cluster that you manage with a single image in the following cases.

- You edit the image for the cluster and save the image.

When you edit and save an image, vSphere Lifecycle Manager starts the Check hardware compatibility of cluster's host with image task even for clusters without vSAN. In such case, vSphere Lifecycle Manager only returns a warning that image hardware compatibility is not verified in non- vSAN clusters.

If the automatically triggered hardware compatibility task fails, you can still save the new image for the cluster.

- You initiate a remediation pre-check or remediation.

The hardware compatibility check is a part of the remediation pre-check and remediation task for vSAN clusters. If a cluster is not vSAN-enabled, vSphere Lifecycle Manager does not perform a hardware compatibility check when you initiate a remediation pre-check or remediation.

You can configure how vSphere Lifecycle Manager behaves in case of hardware compatibility issues.

- You add or remove a host to and from the cluster.

When you add or remove a host to and from the cluster, vSphere Lifecycle Manager invalidates the hardware compatibility check results for the cluster and issues a warning. You must rerun a hardware compatibility check to obtain valid information about potential hardware compatibility issues. Alternatively, you can remediate the cluster or run a remediation pre-check, which both automatically trigger a hardware compatibility check.

Regular Hardware Compatibility Checks

The vSAN Hardware Compatibility List (vSAN HCL) database changes regularly. For example, when VMware certifies new OEM devices, drivers, or firmware, those become part of the vSAN HCL database. Similarly, devices, drivers, or firmware that are not supported anymore are removed from the vSAN HCL database.

Changes in the vSAN HCL database might make your hardware compatibility results invalid and outdated. To provide you with valid hardware compatibility information, vSphere Lifecycle Manager runs a periodic hardware compatibility check against the latest vSAN HCL data.

The periodic hardware compatibility check is a preconfigured scheduled task that you can edit and force to run at any time. By default, the task runs every 24 hours. The scheduled task is configured at a vCenter Server level. If a vCenter Server system contains no vSAN clusters that you manage with a single image, vSphere Lifecycle Manager skips the scheduled hardware compatibility check. This periodic task runs only for vSAN clusters that you manage with a single image.

Check the Hardware Compatibility of a Cluster

For a vSAN cluster that you manage with a single image, you can check the compliance of the image components with the hardware in the cluster. The check is performed against the vSAN Hardware Compatibility List (vSAN HCL) and ensures that if the image is applied to the hosts, the result after remediation is in accordance with vSAN HCL.

When you initiate a hardware compatibility check for a cluster, vSphere Lifecycle Manager verifies that the components in the image are compatible with all storage controllers on the hosts in the cluster as per vSAN HCL. vSphere Lifecycle Manager scans the image and checks whether the physical I/O device controllers are compatible with the ESXi version specified in the image. The task also checks whether the driver and firmware versions that are specified in the image are compatible with the cluster hardware as per vSAN HCL.

Hardware compatibility issues are reported as warnings, but they do not prevent you from remediating the hosts in the cluster against the image.

During a hardware compatibility check for a cluster, vSphere Lifecycle Manager checks performs the following tasks.

- Verifies that all storage device drivers are certified for the ESXi version specified in the image.
- Verifies that the image contains the correct driver and firmware versions as per vSAN HCL.
- Suggests a compatible driver version for the cluster as per vSAN HCL.

To perform a hardware compatibility check for a vSAN cluster, the HCL data that is available vSphere Lifecycle Manager must be up to date. For more information about updating the vSAN HCL data, see the vSAN documentation.

Prerequisites

- Verify that vSAN is enabled for the cluster.

- Verify that the cluster uses a single image.
- Verify that all hosts in the cluster are from the same vendor.
- To validate the compatibility between the I/O device hardware and the firmware version, verify that the image for the cluster includes a firmware add-on.
- Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a cluster that you manage with a single image.
- 2 On the **Updates** tab, select **Hosts > Hardware Compatibility**.
In the **Hardware Compatibility** pane, you see the results from the previous compatibility check.
- 3 In the **Hardware Compatibility** pane, click **Run Checks**.

Results

vSphere Lifecycle Manager displays all compatibility information and issues in the **Hardware Compatibility** pane. You can see detailed compatibility information for each device by clicking it. The information panel appears on the right.

What to do next

Review the result from the hardware compatibility check.

Resolve any issues before you remediate the cluster.

Check the Hardware Compatibility of a Host

You can check the hardware compatibility of a host to determine whether the host hardware is certified for use with a selected ESXi version. The hardware compatibility check is performed against the VMware Compatibility Guide (VCG) or, if the host is in a vSAN cluster, against the vSAN Hardware Compatibility List (HCL).

The hardware compatibility check that you initiate for a single host checks whether the server and the physical devices on the host are Certified for use with a selected ESXi version. The check is performed against the VCG.

Note If the host is in a vSAN cluster, the hardware compatibility of the I/O devices that are used by vSAN is checked against the vSAN Hardware Compatibility List (HCL). All other I/O devices are checked against the VCG.

After the check, vSphere Lifecycle Manager shows the status for the server and hardware devices. The server and devices might have one of the three different states: compatible, incompatible, and unknown. For more information about compatibility statuses, see [Hardware Compatibility Report for a Host](#).

If the server status is incompatible, vSphere Lifecycle Manager does not proceed with checking the compatibility for the hardware devices.

Prerequisites

- If needed, synchronize hardware compatibility data. See [Sync Hardware Compatibility Data](#).
- Verify that the Customer Experience Improvement Program is enabled.
- Verify that vCenter Server is connected to the Internet.
- Verify that the host is not part of an VxRail environment.
- Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a standalone host or a host in a cluster.
- 2 On the **Updates** tab, select **Hosts > Hardware Compatibility**.
- 3 In the **Hardware Compatibility** pane, select your task.
 - To run a hardware compatibility check for the host for the first time, select a target ESXi from the drop-down menu and click **Apply**.
 - To check the hardware compatibility between the host and the already selected target ESXi version, click **Re-run Checks**.
 - To choose a new target ESXi version for the hardware compatibility check, click **Edit** and select a new target ESXi version.
 - To export the hardware compatibility report in a CSV format, click the **Export** button.

Results

vSphere Lifecycle Manager displays the result from the compatibility check. You can see a list of the compatible, incompatible, and unknown devices. For each device, you can see full details by clicking the expand button.

Sync Hardware Compatibility Data

To initiate a hardware compatibility check for a host, the hardware compatibility data from VMware Compatibility Guide (VCG) must become available to vSphere Lifecycle Manager.

Synchronizing compatibility ensures that the compatibility information from VCG becomes available to vSphere Lifecycle Manager. The synchronization task is not automated. When no compatibility data is available for use to vSphere Lifecycle Manager, you must trigger the compatibility data synchronization manually.

vSAN HCL data is not updated through synchronization. If you want to check the hardware compatibility of a host that is in a vSAN cluster, you must first verify that vSAN HCL data is up to date. For more information about updating vSAN HCL data, see the vSAN documentation.

Procedure

- 1 In the vSphere Client, navigate to a standalone host or a host in a cluster.
- 2 On the **Updates** tab, select **Hosts > Hardware Compatibility**.
- 3 In the **Hardware Compatibility** pane, click **Sync compatibility data**.
- 4 In the **Sync hardware compatibility data** dialog box, click **Go to Lifecycle Manager**.

You are redirected to the vSphere Lifecycle Manager home view.

- 5 Select **Actions > Sync HCL**.

The Update HCL data task appears in the **Recent Tasks** pane.

Results

After the Update HCL data task finishes, the compatibility data from the VCG becomes available to vSphere Lifecycle Manager.

What to do next

Check the hardware compatibility of your hosts against VCG before you update or upgrade them to a later ESXi version.

Hardware Compatibility Report for a Host

The hardware compatibility report gives you information whether for a selected server model and hardware devices, vSphere Lifecycle Manager finds records for a target ESXi version in the VMware Compatibility Guide (VCG).

Server Hardware Compatibility

Host Model is Not Compatible

This compatibility status indicates that there are no records for the selected ESXi version in the VCG. If the host is not compatible with the selected ESXi version, vSphere Lifecycle Manager does not proceed to checking the compatibility of the devices.

In the **Host Model Compatibility** card, you can see details about the host: server model name, CPU model, and the BIOS version running on the host. At the bottom of the card, you see a list of all certified CPU series for the target ESXi version.

Host Model is Compatible

This compatibility status indicates that the host is certified for use with the selected ESXi version as per VCG. When the host is compatible, vSphere Lifecycle Manager proceeds with the device validation.

In the **Host Model Compatibility** card, you can see details about the host: server model name, CPU model, and the BIOS version running on the host. Because in VCG the information about CPUs is based on CPU series, and not specific models, you might need to manually check if the CPU of the host is part of the supported CPU series. You might also need to manually check if the BIOS version on the host matches any of the compatible BIOS versions for the CPU series as per VCG.

Hardware Compatibility Checks Not Supported for the Host Vendor Model

When the server model is not part of the list of certified OEMs, vSphere Lifecycle Manager does not perform a hardware compatibility check and you do not see a hardware compatibility report for the selected host.

Device Hardware Compatibility

The compatibility statuses for devices are: compatible, incompatible, and unknown.

Unknown

Unknown devices are devices for which no records exist in VCG. When you click the expand button for the device, you see the following device information: device IDs, driver and firmware currently running on the device. No compatibility data is generated and displayed.

The unknown status might also indicate that multiple matches exist in the VCG for the respective device. In such cases, use the device ID to manually check if the hardware device matches any of the supported devices for the target ESXi version in the VCG.

Incompatible

The incompatible status indicates that no records exist in the VCG for the selected ESXi version. When you click the expand button for the device, you see information about the ESXi versions that are compatible with the device as per VCG.

Compatible

The compatible status indicates that the device is compatible with the selected ESXi version as per VCG. When you click the expand button for the device, you see the following device information: device IDs, driver and firmware currently running on the device. For compatible devices, you might need to manually confirm that the driver-firmware combination running on the device is supported as per VCG.

vSAN Clusters and vSphere Lifecycle Manager

16

You can manage a vSAN cluster by using baselines and baseline groups or by using a single image for that cluster. Working with vSAN clusters has its specifics regardless of whether you manage the cluster with a single image or with baselines.

What's New in vSphere 7.0 Update 1

- During the [Remediating vSAN Stretched Clusters and Clusters with Configured Fault Domains](#), vSphere Lifecycle Manager upgrades all hosts from one fault domain first and then proceeds with the hosts from the next fault domain. Similarly, in a [Remediating vSAN Stretched Clusters and Clusters with Configured Fault Domains](#), vSphere Lifecycle Manager remediates all the hosts from the preferred site first and then proceeds with the hosts from the secondary site.
- If you manage a vSAN cluster with a single image, hardware compatibility checks for that cluster are automatically triggered with certain vSphere Lifecycle Manager operations. For more information, see [Automatically Triggered Hardware Compatibility Checks for vSAN Clusters](#).
- Reduced host reboot time during remediation.

Managing a vSAN cluster by Using Recommendation Baseline Groups

In earlier vSphere releases, you can update and upgrade the hosts in a vSAN cluster by using automatically generated system-managed baseline groups. You can use system-managed baseline groups to also perform firmware and driver updates on the hosts in the cluster.

Starting with vSphere 7.0, system-managed baseline groups are called recommendation baseline groups. Recommendation baseline groups no longer contain firmware and driver updates, but only a patch baseline. So, you cannot perform firmware updates by using a vendor-specific firmware tool and remediating a cluster against the recommendation baselines that vSAN generates.

To update the firmware of a vSAN cluster, you must switch to using a single image instead of baselines for that cluster. You must set up or import an image that contains a firmware add-on and remediate the cluster against that image.

If an existing cluster contains ESXi hosts of versions earlier than 7.0, you must use an upgrade baseline to upgrade the hosts before you can switch to using a vSphere Lifecycle Manager image for the cluster.

For more information about using baselines to manage hosts and clusters, see [Chapter 10 Using Baselines and Baseline Groups](#).

Managing a vSAN Cluster with a Single Image

The image that you use for a cluster defines the full software stack to run on the hosts in that cluster: ESXi version, vendor customization, drivers, and firmware. When you manage a vSAN cluster with a single image, you can take advantage of the functionalities that vSphere Lifecycle Manager images provide.

- You can update the firmware on all hosts in the vSAN cluster.

You perform firmware update by setting up an image that contains a firmware add-on and remediating the vSAN cluster against that image. For more information about performing firmware updates by using vSphere Lifecycle Manager images, see [Chapter 14 Firmware Updates](#).

- You can manually trigger a hardware compatibility check for the cluster.

The hardware compatibility check task verifies that the image for the cluster can be successfully applied to all hosts and that it is compliant with the vSAN Hardware Compatibility List (HCL). For more information about hardware compatibility checks, see [Chapter 15 Hardware Compatibility Checks](#).

- When you perform a compliance check against the image for a cluster, firmware compliance is also checked. As a result, you can easily notice if a driver or firmware in your cluster becomes non-compliant. For more information about checking the compliance of a cluster against an image, see [Checking Compliance Against a Single Image](#).
- The recommendations that vSphere Lifecycle Manager generates in the form of pre-validated images include a recommended firmware version for the hosts in your cluster. For more information about vSphere Lifecycle Manager recommended images, see [Chapter 13 Recommended Images](#).

This chapter includes the following topics:

- [Remediation Specifics of vSAN Clusters](#)
- [Recommendation Baseline Groups](#)
- [Updating Firmware in vSAN Clusters](#)

Remediation Specifics of vSAN Clusters

Whether you manage a vSAN cluster with baselines or with a single image, remediating the hosts that are part of a vSAN cluster has its specifics.

When you remediate hosts that are part of a vSAN cluster, you must be aware of the following behavior:

- By design, in a vSAN cluster, only one host at a time can be in maintenance mode.
- vSphere Lifecycle Manager remediates hosts that are part of a vSAN cluster sequentially.
- Because vSphere Lifecycle Manager handles the remediation of the hosts sequentially, the host remediation process might take an extensive amount of time to finish.
- vSphere Lifecycle Manager remediates vSAN clusters with configured fault domains by upgrading all hosts from one fault domain first and then upgrading the hosts in the next fault domain.
- For a vSAN stretched cluster, vSphere Lifecycle Manager first remediates the hosts from the preferred site and then proceeds with remediating the hosts in the secondary site.

Host Maintenance Mode and vSAN Clusters

You can remediate a host that is in a vSAN cluster in two ways, depending on how you want to handle the virtual machines on the host:

- You can put the host in maintenance mode manually and remediate the host by using vSphere Lifecycle Manager.
- You can have the host enter maintenance mode during the vSphere Lifecycle Manager remediation process.

In the vSphere Client, when you put a host from a vSAN cluster into maintenance mode, you can choose between multiple options: Ensure accessibility, Full data evacuation, and No data evacuation. The Ensure accessibility option is the default option, and means that when you put a host in maintenance mode, vSAN ensures that all accessible virtual machines on the host remain accessible. To learn more about each of the options, see the "Place a Member of a vSAN Cluster in Maintenance Mode" topic in the *vSphere Storage* documentation.

During remediation, vSphere Lifecycle Manager, puts the hosts from the vSAN cluster in maintenance mode and handles the virtual machines on the host in the manner of the default Ensure accessibility option.

If a host is a part of a vSAN cluster, and any virtual machine on the host uses a VM storage policy with the setting for "Number of failures to tolerate=0", the host might experience unusual delays when it enters maintenance mode. The delay occurs because vSAN has to migrate the virtual machine data from one disk on the vSAN datastore cluster to another. Delays might take up to hours. You can work around this by setting the "Number of failures to tolerate=1" for the VM storage policy, which results in creating two copies of the virtual machine files on the vSAN datastore.

vSAN Health Check

vSphere Lifecycle Manager performs a remediation pre-check of vSAN clusters to ensure successful remediation. The vSAN health check is part of the remediation pre-check.

The vSAN health check gives you information about the cluster state and whether you must take extra actions to ensure successful remediation. Even if you do not take the recommended actions, you can still remediate the vSAN cluster or a host from the cluster. vSphere Lifecycle Manager successfully puts the host in maintenance mode and applies software updates on the host successfully. However, the host might fail to exit maintenance mode, and the remediation process might fail. As a result, the host from the vSAN cluster is upgraded, but you must take manual steps to take the host out of maintenance mode.

Remediating vSAN Stretched Clusters and Clusters with Configured Fault Domains

In vSAN clusters with configured fault domains, vSphere Lifecycle Manager remediates the hosts in an order that vSphere Lifecycle Manager calculates by factoring in the defined fault domains. For vSAN stretched clusters, vSphere Lifecycle Manager factors in the defined preferred and secondary site.

Fault Domains and vSAN Stretched Clusters

A fault domain consists of one or more vSAN hosts grouped according to their physical location in the data center. When configured, fault domains enable vSAN to tolerate failures of entire physical racks as well as failures of a single host, capacity device, network link, or a network switch dedicated to a fault domain.

You can configure fault domains for non-stretched and stretched vSAN clusters. A stretched cluster is a deployment model in which two or more hosts are part of the same logical cluster but are located in separate geographical locations. For more information about stretched clusters and configuring fault domains, see the *Administering VMware vSAN* documentation.

Upgrading vSAN Clusters Configured with Multiple Fault Domains

In earlier releases, vSphere Lifecycle Manager remediates the hosts in any cluster sequentially. To define which host to remediate, vSphere Lifecycle Manager only uses DRS recommendations. This behavior imposes some limitations. For example, if you want to upgrade all hosts from a configured fault domain first, you must check which hosts the fault domain includes and then manually select and remediate those hosts. Also, because vSphere Lifecycle Manager remediates the hosts sequentially, in case of failure, the cluster might be in a state where all fault domains are only partially upgraded.

Starting with vSphere 7.0 Update 1, vSphere Lifecycle Manager remediates vSAN clusters with configured fault domains by remediating all hosts in one fault domain at a time. To define the order of fault domains, vSphere Lifecycle Manager calculates and assigns priority to each fault domain for the vSAN cluster.

Remediation starts with the fault domain that has the highest priority. The priority of a fault domain is determined by the number of non-compliant hosts in that fault domain. The fewer non-compliant hosts in a fault domain, the higher the priority of that fault domain. However, if multiple fault domains have the same priority, vSphere Lifecycle Manager selects the first fault domain from the list of fault domains.

After vSphere Lifecycle Manager selects a fault domain, vSphere Lifecycle Manager uses DRS recommendations to select the optimal host within that domain to be remediated.

Upgrading vSAN Stretched Clusters

For stretched vSAN clusters, vSphere Lifecycle Manager first finishes upgrading all the hosts from the preferred site and then proceeds to upgrading the hosts from the secondary site.

If all the hosts in the preferred site are in a compliant state, then vSphere Lifecycle Manager skips the preferred site and starts remediating the hosts from the secondary site.

If any host in the entire cluster is in an incompatible state, remediation stops.

Requirements

- vCenter Server version 7.0 Update 1.
- ESXi version 7.0 and later.

Recommendation Baseline Groups

vSAN creates system-managed baseline groups, called recommendation baseline groups. You use recommendation baseline groups to upgrade the hosts in a vSAN cluster to the latest supported ESXi version, to patch the hosts with critical patches, or to update drivers on the host.

vSAN generates recommendation baseline groups automatically. If your vSphere environment does not contain any vSAN clusters, no recommendation baseline groups are generated.

vSphere Lifecycle Manager automatically attaches the recommendation baseline group to the vSAN clusters in your environment. For each vSAN cluster in the vSphere inventory, vSphere Lifecycle Manager displays a single recommendation baseline group. You cannot edit or delete a recommendation baseline group and you cannot add it to custom baseline groups.

Recommendation baseline group can contain any of the following updates:

- Upgrade baseline that contains an ESXi upgrade image by a certified vendor with the latest tested and recommended version for the vSAN cluster.
- Patch baseline that contains recommended critical patches for the ESXi version of the hosts in the vSAN cluster.
- Recommended drivers for the ESXi hosts in the vSAN cluster.

Starting with vSphere 7.0, recommendation baseline groups no longer contain firmware updates. To update the firmware on your hosts, you must convert to using a single image for the vSAN cluster.

A vSAN recommendation engine regularly checks the current state of the software installed on the hosts in the vSAN cluster against the vSAN Hardware Compatibility List (HCL). If update recommendations are detected, the engine downloads all new critical patches and upgrade images and generates a vSAN cluster-level baseline. All available baselines are packed together in a recommendation baseline group and made available for use by vSphere Lifecycle Manager.

Every 24 hours, vSphere Lifecycle Manager runs an automatic check for a recommendation baseline group with build recommendations coming from vSAN. If a new system baseline group is detected, vSphere Lifecycle Manager automatically attaches the vSAN system baseline group to the vSAN cluster.

After refreshing the vSAN recommendation baseline group, vSphere Lifecycle Manager automatically performs a compliance check operation on the vSAN clusters against the updated recommendation baseline group. Operations such as adding and removing hosts from an existing vSAN cluster also trigger refresh of the attached recommendation baseline group, followed by a compliance check.

System Requirements for Using vSAN Recommendation Baseline Groups

- vCenter Server 7.0.
 - vSphere Lifecycle Manager runs as a service in vCenter Server.
- vSAN cluster that contains hosts of ESXi version 6.0 Update 2 and later.
- Constant access of the vSphere Lifecycle Manager host machine to the Internet.

Configure Remediation Settings for a vSAN Cluster

You can configure what type of baseline to include in the recommendation baseline group that vSphere Lifecycle Manager generates for a vSAN cluster.

A recommendation baseline group can contain upgrades or only host patches and updates. By default, vSphere Lifecycle Manager is set to generate recommendation baselines that contain upgrades, not only patches and updates. But you can change the default configuration at any time. For any vSAN cluster that you manage with baselines, you can also configure vSphere Lifecycle Manager to generate no recommendation baseline group at all. In such cases, you can still manually create baselines and perform host upgrades.

Prerequisites

- Verify that you manage the vSAN cluster with vSphere Lifecycle Manager baselines and not a single vSphere Lifecycle Manager image.
- Verify that you have the proper privileges. See [vSphere Lifecycle Manager Privileges For Using Images](#).

Procedure

- 1 In the vSphere Client, navigate to a vSAN cluster that you manage with baselines.
- 2 On the **Updates** tab, select **Hosts > Cluster Settings**.
- 3 In the **Remediation Settings for this Cluster** pane, click the **Edit** button.

The **Edit Cluster Remediation Settings** dialog box appears.

- 4 Select what type of baseline to include in the recommendation baseline group that vSphere Lifecycle Manager generates for the selected vSAN cluster.

- To include upgrade baselines into the recommendation baseline group for that cluster, select the **Include upgrades to new ESXi versions** radio button.

The **Include upgrades to new ESXi versions** options is the default selection for any newly created vSAN cluster.

- To include only patches and updates in the recommendation baseline group for that cluster, select the **Include patches and updates for current ESXi version** radio button.
- To disable the generation of the recommendation baseline group for that cluster, select the **No recommendation** baseline group.

- 5 Click the **Done** button to save your selection and exit the dialog box.

Results

The option that you select becomes the default configuration for the vSAN cluster.

Updating Firmware in vSAN Clusters

Starting with vSphere 7.0, you can use vSphere vSphere Lifecycle Manager images to upgrade the firmware of the servers that run in your vSAN clusters.

In a vSAN cluster, the SCSI controller firmware and the physical drive firmware are handling most of the data communication. To ensure your vSAN cluster health, you must perform controller firmware updates, when necessary.

Because firmware updates affect the hardware layer in your vSphere environment, they usually are rare events. Firmware updates occur during initial ESXi host setup or during major updates of vSphere or vSAN.

In earlier vSphere releases, firmware updates are delivered as baselines in the vSAN-managed baseline group. You must use a special vendor-provided tool that vSAN uses to detect, download, and install firmware updates.

Starting with vSphere 7.0, the recommendation baseline group contains only patch updates and driver updates. It no longer contains firmware updates. As a result, you cannot use baselines to update the firmware in your vSAN clusters if the ESXi hosts are of version 7.0 or later. You can still use baselines to perform firmware updates on hosts of earlier versions, for example 6.7. But to perform firmware updates on hosts that are of version 7.0 and later and that are in a vSAN cluster, you must manage that cluster with a single image. You must also [Deploying Hardware Support Managers](#) and register it as a vCenter Server extension. The hardware support manager inspects the hardware of the hosts in the cluster and lists available and compatible firmware versions, which you can add to the image for the cluster. The actual firmware update happens upon remediating the cluster against an image that contains a firmware add-on.

For more information about the requirements for using images, see [Chapter 5 vSphere Lifecycle Manager Requirements and Specifics](#).

For more information about performing firmware updates by using images, see [Chapter 14 Firmware Updates](#).

Backup and Restore Scenarios When Using vSphere Lifecycle Manager

17

Restoring a vCenter Server instance from a backup might impact the clusters in your environment in a seemingly unexpected way. Whether you use images or baselines to manage your clusters, vSphere Lifecycle Manager behaves in a specific manner during backup and restore operations.

When you back up a vCenter Server instance, you create a backup copy of all clusters in that vCenter Server instance.

Restoring vCenter Server After Switching from Baselines to Images for Cluster Lifecycle Management

Cluster A is a cluster that you manage by using baselines. You back up the vCenter Server instance where the cluster is. After the backup, you switch from using baselines to using images to manage cluster A and you remediate the cluster to apply the image to the hosts in the cluster. You now manage the lifecycle of cluster A by using a single cluster image.

If for some reason you must restore the vCenter Server instance from the backup copy you created, the restored vCenter Server instance contains cluster A. Because cluster A was managed through baselines at the time when you backed up the vCenter Server system, the restored vCenter Server instance contains cluster A, but you must again use baselines to manage it.

Restoring vCenter Server After Remediating a Cluster Managed by an Image

After remediation, cluster A uses image X with components Y to manage all hosts in the cluster collectively. At a point in time T, you back up the vCenter Server system. Later, you remediate the cluster against a new image X+1 with new components Y+1. Now all hosts in the cluster use image X+1 with components Y+1.

If for some reason you must restore the vCenter Server system from the backup copy that you created at time T, the restored vCenter Server instance contains cluster A, but the compliance check lists the hosts in the cluster as incompatible with the image that cluster A uses. The reason for the incompatibility is that after the restore operation, cluster A reverts back to using image X with components Y, while the hosts in the cluster still run image X+1 with components Y+1. Because you cannot downgrade ESXi, to make the hosts compliant with the cluster image, you must upgrade the cluster to image X+1 with components Y+1.

Upgrading Virtual Machines with vSphere Lifecycle Manager

18

You can use vSphere Lifecycle Manager to upgrade virtual machine hardware and the VMware Tools version of a virtual machine.

Whether you perform an upgrade of the virtual machine hardware version or the VMware Tools version, the upgrade is a multi-stage process.

- 1 You check the status of individual virtual machines or a container object.

vSphere Lifecycle Manager checks the status of a virtual machine against the latest virtual machine hardware version supported by the host on which the virtual machine runs. Similarly, vSphere Lifecycle Manager checks the status of the virtual machine against the latest VMware Tools version supported by the host on which the virtual machine runs.

For more information about checking virtual machine status, see [Checking the Status of Virtual Machines](#).

- 2 You review the status of the scanned virtual machines.

- 3 You upgrade the virtual machine to match the host where it resides.

With vSphere Lifecycle Manager, you can upgrade the virtual machine hardware version and the VMware Tools version that a virtual machine has. With vSphere Lifecycle Manager 7.0 you can upgrade to hardware version vmx-17 and to the latest VMware Tools version on hosts that are running ESXi 7.0.

For more information about upgrading virtual machines, see [Upgrading Virtual Machines](#).

This chapter includes the following topics:

- [Configure Virtual Machine Rollback Settings](#)
- [Checking the Status of Virtual Machines](#)
- [Upgrading Virtual Machines](#)

Configure Virtual Machine Rollback Settings

By default, vSphere Lifecycle Manager takes snapshots of virtual machines before upgrading them. If the upgrade fails, you can use the snapshot to return a virtual machine to its state before the upgrade.

You can configure vSphere Lifecycle Manager to keep snapshots for an indefinite or fixed period of time. Use the following guidelines when managing snapshots.

- Keeping snapshots indefinitely might consume a large amount of disk space and degrade virtual machine performance.
- Keeping no snapshots saves space, ensures best virtual machine performance, and might reduce the remediation time. However, keeping no snapshots limits the availability of a rollback.
- Keeping snapshots for a fixed period of time uses less disk space and offers a backup for a short time.

vSphere Lifecycle Manager does not take snapshots of fault tolerant virtual machines and virtual machines of virtual machine hardware version 3. If you decide to take snapshots of such virtual machines, the upgrade might fail.

If you configure vSphere Lifecycle Manager to automatically upgrade VMware Tools on power cycle for selected virtual machines, vSphere Lifecycle Manager does not take snapshots of the virtual machines before upgrading them and you cannot roll back.

Prerequisites

Required privileges: **VMware vSphere Lifecycle Manager. Configure**

Procedure

- 1 Navigate to the vSphere Lifecycle Manager home view.
 - a In the vSphere Client, select **Menu > Lifecycle Manager**.
 - b Select a vCenter Server system from the **Lifecycle Manager** drop-down menu.

The drop-down menu is available only when multiple vCenter Server systems are connected by a common vCenter Single Sign-On domain. By selecting a vCenter Server system, you specify which vSphere Lifecycle Manager instance you want to administer.
- 2 On the **Settings** tab, select **Host Remediation > VMs**.
- 3 Click the **Edit** button.

The **Edit Default Settings for VM Rollback** dialog box opens.
- 4 Select the **Take snapshot of VMs** check box.
- 5 Select the time period for keeping the snapshots.
 - Do not delete snapshots
 - Keep snapshots for a configurable, fixed period of time
- 6 Click **Save** to save your changes and close the **Edit Default Settings for VM Rollback** dialog box.

Results

These settings become the default rollback option settings for virtual machines. You can specify different settings when you configure individual remediation tasks.

Checking the Status of Virtual Machines

You use vSphere Lifecycle Manager to check the status of virtual machines before you upgrade them. The status check shows if the virtual machine is up-to-date or can be upgraded.

With vSphere Lifecycle Manager, you can check the status of a single virtual machine or a group of virtual machines in a parent container object.

Supported groups of virtual machines or ESXi hosts include virtual infrastructure container objects such as folders, vApps, clusters, and data centers.

vSphere Lifecycle Manager checks the status of virtual machines in two aspects.

- You can use vSphere Lifecycle Manager to check the status of the virtual machines in respect with the VMware Tools version that they have installed.

The status check is performed against the latest VMware Tools version that the parent host supports.

- vSphere Lifecycle Manager checks the status of the virtual machines in respect with their VM hardware compatibility.

vSphere Lifecycle Manager compares the hardware compatibility of the virtual machines with the default VM hardware compatibility configured for the host.

Check the Status of an Individual Virtual Machine

You check the status of virtual machines to see whether the VMware Tools version they have is up to date and whether their hardware compatibility matches the default VM hardware compatibility for the host.

Procedure

1 In the vSphere Client, navigate to a virtual machine.

2 On the **Updates** tab, click **Check Status**.

The **Scan entity** task appears in the **Recent Tasks** pane. After the task finishes, status information appears in the **VMware Tools** and **VM Hardware Compatibility** panels.

Results

The virtual machines are scanned for VMware Tools and VM hardware compliance.

Check the Status of the Virtual Machines in a Container Object

You check the status of virtual machines to see whether the VMware Tools version they have is up-to-date and whether their hardware compatibility matches the default VM hardware compatibility for the host where they reside.

When you perform a status check for a container object, vSphere Lifecycle Manager checks the VMware Tools and VM Hardware Compatibility statuses for all child virtual machines. The larger the virtual infrastructure and the higher up in the object hierarchy you initiate the status check, the longer the task takes.

Procedure

- 1 In the vSphere Client, navigate to a virtual machine container object, such as a virtual machine folder, host, cluster, and so on.
- 2 Click the **Updates** tab.
- 3 Select your task.

Option	Action
Check the VMware Tools status of the virtual machines in the container object.	<ol style="list-style-type: none"> a Select Hosts > VMware Tools > . b Click Check Status. <p>The information about the VMware Tools status appears in the Tools Status column in the table that lists all virtual machines in the selected container object. If the container object is a data center or a vCenter Server instance, you must first specify the cluster that you want to see results for.</p>
Check the VM Hardware compatibility status of the virtual machines in the container object.	<ol style="list-style-type: none"> a Select Hosts > VM Hardware. b Click Check Status. <p>The information about the VM Hardware Compatibility status appears in the Status column in the table that lists all virtual machines in the selected container object. For each virtual machine in the object, you can also see the VM hardware compatibility and the host compatibility. If the container object is a data center or a vCenter Server instance, you must first specify the cluster that you want to see results for.</p>

The VMware Tools Status

Check the VMware Tools status for information whether the current version of VMware Tools is installed, supported, or whether upgrades are available.

Table 18-1. VMware Tools Status

VMware Tools Status	Description
Up to Date	VMware Tools is installed, supported, and the version is compliant.
	VMware Tools is installed, supported, and the version is newer than the version available on the ESXi host.

Table 18-1. VMware Tools Status (continued)

VMware Tools	
Status	Description
Upgrade Available	VMware Tools is installed, but the version is old.
	VMware Tools is installed and supported, but a newer version is available on the ESXi host.
Version Unsupported	VMware Tools is installed, but the version is old.
	VMware Tools is installed, but the version has a known issue and must be immediately upgraded.
	VMware Tools is installed, but the version is too new to work correctly with this virtual machine.
Not Installed	VMware Tools is not installed on this virtual machine.
Guest Managed	vSphere does not manage VMware Tools.
Unknown	The status of the virtual machine is not checked.

Upgrading Virtual Machines

With vSphere Lifecycle Manager, you can upgrade the VMware Tools version and the hardware version of a virtual machine. You can also upgrade multiple virtual machines simultaneously if the virtual machines are in a container object, such as a folder or vApp. You can also upgrade simultaneously all virtual machines that run on a host, in a cluster, or in a data center.

vSphere Lifecycle Manager supports upgrading powered on, suspended, and powered off virtual machines.

During the upgrade of VMware Tools, the virtual machines must be powered on. If a virtual machine is in the powered off or suspended state before remediation, vSphere Lifecycle Manager powers it on. After the upgrade completes, vSphere Lifecycle Manager restarts the machine and restores the original power state of the virtual machine.

During the virtual hardware upgrade, the virtual machines must be powered off. If a virtual machine is powered on, vSphere Lifecycle Manager powers the machine off, upgrades the virtual hardware, and then powers the virtual machine on.

You can also upgrade VMware Tools and the hardware version of a virtual machine template. A template is a copy of a virtual machine that you can use to create and provision new virtual machines.

You can set up automatic upgrades of VMware Tools on power cycle. For more information, see [Automatically Upgrade VMware Tools on Reboot](#).

You can configure vSphere Lifecycle Manager to take snapshots of virtual machines and to keep the snapshots indefinitely or for a specific period of time. By using snapshots, you can roll back a virtual machine to its previous state if upgrading the virtual machine with vSphere Lifecycle Manager fails. After the upgrade finishes, you can delete the snapshots if you do not need them. For more information about configuring virtual machine rollback settings, see [Configure Virtual Machine Rollback Settings](#).

You can upgrade virtual machines immediately or schedule an upgrade operation to run at a convenient time.

If a host is connected to vCenter Server by using an IPv6 address, you cannot scan and remediate virtual machines that run on the host.

Upgrade the VM Hardware Compatibility of Virtual Machines

You can upgrade the hardware of virtual machines to the latest hardware version that the host supports. You can upgrade immediately or schedule an upgrade at a time that is convenient for you.

With vSphere Lifecycle Manager, you can upgrade the hardware compatibility version of a single virtual machine or multiple virtual machines simultaneously. Supported container objects for virtual machines in the vSphere inventory are folders, vApps, data centers.

Procedure

- 1 In the vSphere Client, navigate to a single virtual machine or a container object.

You can also initiate upgrade at the level of any inventory object where virtual machines run. For example, you can start the upgrade operation at a host or cluster level.

- 2 Open the **Upgrade VM Hardware to Match Host** dialog box.

Inventory Object	Steps
Virtual Machine	<ol style="list-style-type: none"> a Click the Updates tab. b In the VM Hardware Compatibility panel, click Upgrade to Match Host.
Container Object, Host, Cluster, Data Center, or vCenter Server Instance	<ol style="list-style-type: none"> a Click the Updates tab. b Select Hosts > VM Hardware. c If the selected inventory object is a data center or a vCenter Server instance, select a cluster from the list. A list of all virtual machines in the cluster appears in the bottom pane. d Select the virtual machines to upgrade. e Click Upgrade to Match Host.

A list of the virtual machines selected for upgrading is visible in the **Upgrade VM Hardware to Match Host** dialog box.

- 3 (Optional) To change the selection of the virtual machines to upgrade, select or deselect virtual machines from the list.
- 4 (Optional) To schedule the upgrade for a specific date and time, expand **Scheduling Options** and configure the scheduled task.
 - a Enter a name and, optionally, a description for the scheduled upgrade task.
 - b Use the **Powered On VMs**, **Powered Off VMs**, and **Suspended VMs** drop-down menus to configure the upgrade to run immediately or at a specific date and time.

- 5 (Optional) To configure the use of snapshots, expand **Rollback Options** and change the default settings.
 - a To enable or disable taking of snapshots of virtual machines before upgrading them, select or deselect the **Take snapshot of VMs** check box.

The option to take snapshots is selected by default.
 - b Select a period for keeping the snapshots.
 - Keep the snapshots indefinitely.
 - Keep the snapshots for a fixed period.
 - c Enter a snapshot name and, optionally, a description for the snapshot.
 - d Include the virtual machine memory in the snapshot by selecting the respective check box.
- 6 Review your selections and click the **Upgrade to Match Host** button.

Results

The hardware versions of the selected virtual machines are upgraded and the virtual machine status changes to Up to Date.

Upgrade the VMware Tools Version of Virtual Machines

You can upgrade the VMware Tools version of virtual machines to the latest version that the host supports. You can upgrade immediately or schedule an upgrade at a time that is convenient for you.

With vSphere Lifecycle Manager, you can upgrade the VMware Tools version of a single virtual machine or multiple virtual machines simultaneously. Supported container objects for virtual machines in the vSphere inventory are folders, vApps, data centers.

Procedure

- 1 In the vSphere Client, navigate to a single virtual machine or a container object.

You can initiate the upgrade at the level of any inventory object where virtual machines run. For example, you can start the upgrade operation at a host or cluster level.

2 Open the **Upgrade VMware Tools to Match Host** dialog box.

Inventory Object	Steps
Virtual Machine	a Click the Updates tab. b In the VMware Tools panel, click Upgrade to Match Host .
Container Object, Host, Cluster, Data Center, or vCenter Server Instance	a Click the Updates tab. b Select Hosts > VMware Tools . c If the selected inventory object is a data center or a vCenter Server instance, select a cluster from the list. A list of all virtual machines in the cluster appears in the bottom pane. d In the VMs in Cluster pane, select the virtual machines to upgrade. e Click Upgrade to Match Host .

A list of the virtual machines selected for upgrading is visible in the **Upgrade VMware Tools to Match Host** dialog box.

- 3 (Optional) To change the selection of the virtual machines to upgrade, select or deselect virtual machines from the list.
- 4 (Optional) To schedule the upgrade for a specific date and time, expand **Scheduling Options** and configure the scheduled task.
 - a Enter a name and, optionally, a description for the scheduled upgrade task.
 - b Use the **Powered On VMs**, **Powered Off VMs**, and **Suspended VMs** drop-down menus to configure the upgrade to run immediately or at a specific date and time.
- 5 (Optional) To configure the use of snapshots, expand **Rollback Options** and change the default settings.
 - a To enable or disable taking of snapshots of virtual machines before upgrading them, select or deselect the **Take snapshot of VMs** check box.
 The option to take snapshots is selected by default.
 - b Select a period for keeping the snapshots.
 - Keep the snapshots indefinitely.
 - Keep the snapshots for a fixed period.
 - c Enter a snapshot name and, optionally, a description for the snapshot.
 - d Include the virtual machine memory in the snapshot by selecting the respective check box.
- 6 Review your selections and click the **Upgrade to Match Host** button.

Results

The VMware Tools version that runs on the selected virtual machines is upgraded and the VMware Tools status changes to Up to Date.

Automatically Upgrade VMware Tools on Reboot

You can automate the process of upgrading VMware Tools for the virtual machines in your inventory.

You can set up vSphere Lifecycle Manager to check the VMware Tools version of a virtual machine when the virtual machine is rebooted. If necessary, vSphere Lifecycle Manager upgrades VMware Tools to the latest version supported by the host on which the virtual machine runs.

Note When you perform a VMware Tools upgrade on power cycle, vSphere Lifecycle Manager does not take a snapshot of the virtual machine and you cannot roll back to the previous version of the virtual machine.

Procedure

- 1 In the vSphere Client, navigate to a single virtual machine or an inventory object that contains virtual machines.
- 2 Configure vSphere Lifecycle Manager to automatically upgrade VMware Tools on reboot.

Inventory Object	Steps
Virtual Machine	<ol style="list-style-type: none"> a Click the Updates tab. b In the VMware Tools panel, click Turn On.
Container Object, Host, Cluster, Data Center, or vCenter Server Instance	<ol style="list-style-type: none"> a Click the Updates tab. b Select Hosts > VMware Tools. c If the selected inventory object is a data center or a vCenter Server instance, select a cluster from the list. A list of all virtual machines in the cluster appears in the bottom pane. d In the VMs in Cluster pane, select the virtual machines for which you want to enable the automatic upgrade of VMware Tools. e Click Set Auto Update and select On. The new status is visible in the Auto Update column.

Results

The next time you power on or restart a virtual machine, vSphere Lifecycle Manager checks the version of VMware Tools installed on the virtual machines and performs an upgrade, if necessary.

Installing, Setting Up, and Using Update Manager Download Service

19

VMware vSphere Update Manager Download Service (UMDS) is an optional module of vSphere Lifecycle Manager. UMDS downloads patch metadata, patch binaries, and notifications that might not otherwise be available to vSphere Lifecycle Manager.

For security reasons and deployment restrictions, vSphere, including vSphere Lifecycle Manager, might be installed in a secured network that is disconnected from other local networks and the Internet. vSphere Lifecycle Manager requires access to patch information to function properly. If you are using such an environment, you can install UMDS on a computer that has Internet access to download upgrades, patch binaries, and patch metadata, and then export the downloads to a portable media drive so that they become accessible to the vSphere Lifecycle Manager.

If the server on which vCenter Server is installed has no Internet access, but is connected to a server that has Internet access, you can automate the export process and transfer files from UMDS to the vSphere Lifecycle Manager depot by using a Web server on the machine on which UMDS is installed.

UMDS 7.0 supports patch recalls and notifications. A patch is recalled if the released patch has problems or potential issues. After you download patch data and notifications with UMDS, and export the downloads so that they become available to vSphere Lifecycle Manager, vSphere Lifecycle Manager deletes the recalled patches.

Starting with vSphere 7.0, the UMDS is available for installation only on Linux-based operating systems. Installing UMDS on a Windows machine is no longer supported. Administrator access is not a requirement for downloading patches with UMDS that runs on Linux. The machine on which you install UMDS must have Internet access.

vSphere Lifecycle Manager supports using UMDS for both images and baselines. That is, UMDS downloads updates that are packaged and distributed as bulletins, but it also works with components, which are the main software update package in vSphere 7.0

This chapter includes the following topics:

- [Compatibility Between UMDS and vSphere Lifecycle Manager](#)
- [Installing UMDS](#)
- [Setting Up and Using UMDS](#)

Compatibility Between UMDS and vSphere Lifecycle Manager

UMDS must be of the same version as vSphere Lifecycle Manager.

For example, vSphere Lifecycle Manager 7.0 is compatible and can work only with UMDS 7.0. If you are using vSphere Lifecycle Manager of an Update release version, UMDS must be of the same Update release version.

Installing UMDS

In vSphere 7.0 release, the UMDS 7.0 is bundled with the vCenter Server appliance 7.0. You can use the UMDS bundle from the vCenter Server appliance to install UMDS 7.0 on a separate Linux-based system.

UMDS is a 64-bit application and requires a 64-bit Linux-based system.

Note You cannot upgrade UMDS that runs on a Linux-based operating system. You can uninstall the current version of UMDS, perform a fresh installation of UMDS according to all system requirements, and use the existing patch store from the UMDS that you uninstalled.

Supported Linux-Based Operating Systems for Installing UMDS

The Update Manager Download Service (UMDS) can run on a limited number of Linux-based operating systems.

- Ubuntu 14.0.4
- Ubuntu 18.04
- Ubuntu 18.04 LTS
- Ubuntu 20.04 LTS
- Red Hat Enterprise Linux 7.4
- Red Hat Enterprise Linux 7.5
- Red Hat Enterprise Linux 7.7
- Red Hat Enterprise Linux 8.1

Note When you use Red Hat Enterprise Linux 8.1, you must install the `libnsl` package version 2.28 or later on the system where UMDS is deployed. If the package is not present on the system, UMDS operations might fail with the following error:

```
Error while loading shared libraries: libnsl.so.1: cannot open shared object file: No such file or directory.
```

Install UMDS on a Linux OS

If the vCenter Server appliance 7.0 where vSphere Lifecycle Manager runs does not have access to the Internet, you can install UMDS on a Linux-based operating system to download update binaries and metadata.

Prerequisites

- Verify you have administrative privileges on the Linux machine where you install the UMDS.
- Mount the ISO file of the vCenter Server appliance 7.0 to the Linux machine.

Procedure

- 1 In the Linux machine, open the Command Shell.
- 2 From the vCenter Server ISO that you mounted to the Linux machine, copy the `VMware-UMDS-7.0.0-build_number.tar.gz` file to the Linux machine.
- 3 Unarchive the `VMware-UMDS-7.0.0-build_number.tar.gz` file, and navigate to the newly extracted directory `/vmware-umds-distrib`.

For example, if you unarchived the `VMware-UMDS-7.0.0-build_number.tar.gz` file, to a directory you created with the name `umds`, your navigation path is `/umds/vmware-umds-distrib`.

- 4 Run the file UMDS installation script.

The script has the following filename: `vmware-install.pl`.

- 5 Read and accept the EULA.
- 6 Select a directory where to install the UMDS.
- 7 Enter the UMDS proxy settings.

You can also change proxy configuration after you install UMDS by using the following command:

```
vmware-umds -S --proxy <proxyAddress:port>
```

- 8 Select a directory where to store the patches.

Important The patch store directory must be different from the UMDS installation directory.

Results

UMDS is installed.

Uninstall UMDS from a Linux OS

To use the latest UMDS version on your Linux-based system, you must first uninstall the current version of UMDS. No direct upgrade path is available to a later version of UMDS.

Prerequisites

- Verify you have administrative privileges on the Linux machine where UMDS runs.

Procedure

- 1 In the Linux machine, open the Command Shell.
- 2 Navigate to the UMDS installation directory, and locate the file `vmware-uninstall-ums.pl`.
- 3 Run the following command:

```
./vmware-uninstall-ums.pl
```

- 4 To confirm that you want to uninstall UMDS from the system, enter **Yes**.

The UMDS uninstallation procedure starts.

- 5 (Optional) Remove PostgreSQL Database from you Linux machine.

For information about uninstalling PostgreSQL Database, go to the official PostgreSQL documentation.

Results

UMDS is uninstalled from the Linux system.

What to do next

You can upgrade your Linux OS, and install a later compatible version of UMDS.

Setting Up and Using UMDS

You can set up UMDS to download patches for ESXi hosts. You can also set up UMDS to download ESXi 6.5, ESXi 6.7, and ESXi 7.0 patch binaries, patch metadata, and notifications from third-party portals.

Administrator access is not a requirement for downloading patches if UMDS runs on Linux.

After you download the upgrades, patch binaries, patch metadata, you can export the data to a Web server or a portable media drive and set up vSphere Lifecycle Manager to use a folder on the Web server or the media drive (mounted as a local disk) as a shared repository.

You can also set up UMDS to download ESXi 6.5, ESXi 6.7, and ESXi 7.0 patches from third-party portals.

To use UMDS, the machine on which you install it must have Internet access. After you download the data you want, you can copy it to a local Web server or a portable storage device, such as a CD or USB flash drive.

The best practice is to create a script to download the patches manually and set it up as a Windows Scheduled Task that downloads the upgrades and patches automatically.

Set Up the Data to Download with UMDS

By default, UMDS downloads patch binaries, patch metadata, and notifications for hosts. You can specify which patch binaries and patch metadata to download with UMDS.

Procedure

1 Log in to the machine where UMDS is installed, and open a **Command Prompt** window.

2 Navigate to the directory where UMDS is installed.

The default location in 64-bit Linux is `/usr/local/vmware-umds`.

3 Specify the updates to download.

- To set up a download of all ESXi host updates run the following command:

```
vmware-umds -S --enable-host
```

- To disable the download of host updates, run the following command:

```
vmware-umds -S --disable-host
```

What to do next

Download the selected data.

Change the UMDS Patch Repository Location

UMDS downloads upgrades, patch binaries, patch metadata, and notifications to a folder that you can specify during the UMDS installation.

The default folder to which UMDS downloads patch binaries and patch metadata on a Linux machine is `/var/lib/vmware-umds`.

You can change the folder in which UMDS downloads data after you install UMDS.

If you have already downloaded host updates, copy all the files and folders from the old location to the new patch store location. The folder in which UMDS downloads patch binaries and patch metadata must be located on the machine on which UMDS is installed.

Procedure

1 Log in as an administrator to the machine where UMDS is installed, and open a **Command Prompt** window.

2 Navigate to the directory where UMDS is installed.

The default location in 64-bit Linux is `/usr/local/vmware-umds`.

3 Change the patch repository directory by running the command:

```
vmware-umds -S --patch-store your_new_patchstore_folder
```

In this example, *your_new_patchstore_folder* is the path to the new folder in which you want to download the patch binaries and patch metadata.

Results

You successfully changed the directory in which UMDS stores patch data.

What to do next

Download data using UMDS.

Configure URL Addresses for Hosts

You can configure UMDS to connect to the websites of third-party vendors to download ESXi 6.5, ESXi 6.7, and ESXi 7.0 host patches and notifications.

Procedure

- 1 Log in to the machine where UMDS runs, and open a **Command Prompt** window.
- 2 Navigate to the directory where UMDS is installed.
The default location in 64-bit Linux is `/usr/local/vmware-umds`.
- 3 Configure UMDS to download data from the new URL address.
 - ◆ To add a new URL address for downloading patches and notifications for ESXi 6.5, ESXi 6.7, or ESXi 7.0 hosts, run the following command:

```
vmware-umds -S --add-url https://host_URL/index.xml --url-type HOST
```

- 4 (Optional) Remove a URL address, so that UMDS does not download data from it anymore.
Downloaded data is retained and can be exported. Use the following command:

```
vmware-umds -S --remove-url https://URL_to_remove/index.xml
```

Results

You configured UMDS to download host patches and notifications from specific URL addresses.

What to do next

Download the patches and notifications by using UMDS.

Download the Specified Data Using UMDS

After you set up UMDS, you can download upgrades, patches and notifications to the machine on which UMDS is installed.

Administrator level access is not a requirement for downloading data with UMDS that runs on Linux.

Procedure

- 1 Log in to the machine where UMDS is installed, and open a **Command Prompt** window.
- 2 Navigate to the directory where UMDS is installed.

The default location in 64-bit Linux is `/usr/local/vmware-umds`.

- 3 Download the selected updates.

```
vmware-umds -D
```

This command downloads all the upgrades, patches and notifications from the configured sources for the first time. Subsequently, it downloads all new patches and notifications released after the previous UMDS download.

- 4 (Optional) If you have already downloaded upgrades, patches, and notifications and want to download them again, you can include the start and end times to restrict the data to download.

The command to re-download patches and notifications deletes the existing data from the patch store (if present) and re-downloads it.

To re-download the upgrades, patches and notifications that were downloaded in November 2010, for example, run the following command:

```
vmware-umds -R --start-time 2010-11-01T00:00:00 --end-time 2010-11-30T23:59:59
```

The data previously downloaded for the specified period is deleted and downloaded again.

What to do next

Export the downloaded upgrades, patches, and notifications.

Export the Downloaded Data

You can export downloaded upgrades, patches, and notifications to a specific location that serves as a shared repository for vSphere Lifecycle Manager. You can configure vSphere Lifecycle Manager to use the shared repository as a patch download source. The shared repository can also be hosted on a Web server.

Administrator level access is not a requirement for exporting the downloaded data with UMDS that runs on Linux.

Prerequisites

If you installed UMDS with an existing download directory, verify that you perform at least one download by using UMDS 7.0 before you export updates.

Procedure

- 1 Log in to the machine where UMDS is installed and open a **Command Prompt** window.

- 2 Navigate to the directory where UMDS is installed.

The default location in 64-bit Linux is `/usr/local/vmware-umds`.

- 3 Specify the export parameters and export the data.

```
vmware-umds -E --export-store repository_path
```

In the command, you must specify the full path of the export directory.

If you are working in a deployment in which the vCenter Server is installed on a machine connected to the machine on which UMDS is installed, *repository_path* can be the path to the folder on the Web server that serves as a shared repository.

If the vCenter Server is installed on a machine in an isolated and secure environment, *repository_path* can be the path to a portable media drive. Export the downloads to the portable media drive to physically transfer the patches to the machine on which vCenter Server is installed and vSphere Lifecycle Manager runs.

The data you downloaded by using UMDS is exported to the path you specify. Make sure that all files are exported. You can periodically export from UMDS and populate the shared repository so that vSphere Lifecycle Manager can use the new patch binaries and patch metadata.

- 4 (Optional) You can export the ESXi patches that you downloaded during a specified time window.

For example, to export the patches downloaded in November 2010, run the following command:

```
vmware-umds -E --export-store repository_path --start-time 2010-11-01T00:00:00 --end-time 2010-11-30T23:59:59
```

What to do next

Configure vSphere Lifecycle Manager to use a shared repository as a patch download source. For more information, see [Configure vSphere Lifecycle Manager to Use a Shared Repository as a Download Source](#).